# Euler Simulation, Python

## Contents

1	Intr	oducti	on	1
<b>2</b>	Coc	le Doc	umentation	2
	2.1	simula	tor.py	2
		2.1.1		2
		2.1.2		3
		2.1.3	Simulator1D: calculate_time_derivatives()	3
		2.1.4	Simulator1D: volume()	4
		2.1.5	Simulator1D: energy()	4
		2.1.6	Simulator1D: peak_location()	4
		2.1.7	Simulator1D: zeta_at()	$\overline{4}$
		2.1.8	Simulator1D: run_simulation()	$\overline{4}$
		2.1.9	Simulator1D: data_save_params()	7
		2.1.10	Simulator1D: $init_netcdf()$	7
			Simulator1D: soliton()	8
			Simulator1D: KY_bathym()	8
			Simulator1D: KY_sim()	8
			Simulator1D: fields	9
	2.2		ator.py	11
	2.2	2.2.1	Integrator1D: euler	11
		2.2.2	Integrator1D: RK4	11
		2.2.2	Integrator1D: implicit_midpoint	11
		2.2.4	Integrator1D: AM1	12
		2.2.4 $2.2.5$	Integrator1D: DIRK3	12
		2.2.0	integratorib. Diffito	12
3	Exa	mples		13
		KY nv		13

## 1 Introduction

The Euler Simulation project applies the methods used in Knowles and Yeh (2018) to simulate, in one dimension, the shoaling process of a shallow-water wave. The original paper uses such a simulation to predict the wave amplification process, that is, how a, the amplitude of the wave, relates to h, the local water depth.

This project uses the same algorithm, in python, to handle other cases, e.g. the wind's effect on a shoaling solitary wave.

## 2 Code Documentation

Simulation involves two python files.

### 2.1 simulator.py

simulator.py contains one relevant class: Simulator1D, which wraps necessary functionality to run a simulation.

#### 2.1.1 Simulator1D: Constructor

sim = Simulator1D(bathymetry, dt, dx, eta0, phiS0)

Initializes a Simulator instance with the given parameters:

argument	description		
bathymetry	numpy array of the bathymetry, must have an even number of nodes. 0 is		
	expected to be water level.		
dt	time resolution of the simulation		
dx	spatial resolution of the simulation (distance between points of bathymetry)		
eta0	initial free surface heights (with spatial resolution dx, 0 is expected for still		
	water) expected to be a numpy array		
phiS0	velocity potential at the free surface, expected to be a numpy array.		

Simulator1D has the following keyword arguments:

argument	description	default
zeta_x	First derivative (gradient) of the bathymetry, if a higher order	(see description)
	approximation of gradient is desired. If no argument for zeta_x is	
	passed, it is instead calculated from the finite difference	
	$f'(x) = \frac{f(x+h) - f(x-h)}{2h} + O(h^2)$	
	where the edges are assumed to have a gradient of 0	
M	Terms in the pertubation expansion (higher number is more ac-	5
	curate, but requires more computation)	
v	lowpass threshold. If v is a number, any wavenumber greater than	0.7
	the largest wavenumber times v is clipped off each timestep. v can	
	also be a function that takes a wavenumber magnitude and the	
	peak wavenumber, and returns how it should be scaled	
g	acceleration due to gravity.	9.81
h0	base still water depth	bathymetry[0]

In the case that v is a function, the wave number is the first argument and the peak wavenumber is the second argument, so the following will result in the same low-pass filter v = 0.7:

```
def v(k, peak):
    if k/peak <= 0.7:
        return 1
    else:
        return 0</pre>
```

#### 2.1.2 Simulator1D: step()

```
sim.step("RK4")
```

Steps the simulation forward using the given method. Any arguments for the method can be specified as optional arguments or keyword arguments.

argument	description
method	The method to use. This can be a string or a function. When a string is passed
	the method in integrator.py of the same name is used. See section (2.2) for
	such methods.

Optional arguments specific to a method (e.g. tolerance for implicit methods) can be passed into step(), which will be transferred to the method when called. In particular, P\_atmos is common to all integration methods, and is shown below.

argument	description	default
P_atmos	Atmospheric pressure at the surface. This can be either a function	array of zeros
	with arguments eta, phiS, eta_x, phiS_x, w or a numpy array of	
	length Nx. See the beginning of section (2.2) for more specifics on	
	the function.	

#### 2.1.3 Simulator1D: calculate\_time\_derivatives()

sim.calculate\_time\_derivatives(eta, phiS, zeta, zeta\_x, zeta\_t, P\_a)

Returns the tuple (eta\_t, phiS\_t) of time derivatives of  $\eta$  and  $\Phi^S$  respectively. Takes the following arguments:

argument	description		
eta	free surface height at the given time step; pass simulator.eta if you want the		
	current time derivative.		
phiS	free surface velocity potential at the given time step; pass simulator.phiS if you		
	want the current time derivative		
zeta	bathymetry $(\zeta)$ , with 0 corresponding with a depth of -h0		
zeta_x	spatial derivative of $\zeta$		
zeta_t	time derivative of $\zeta$		
P_a	atmospheric pressure at every point, should have the same samples as		
	bathymetry. Expected to be a numpy array or a function. See the beginning		
	of section (2.2) for more specifics on the function.		

#### 2.1.4 Simulator1D: volume()

sim.volume()

Returns the integral

$$\int \eta \ dt$$

over the bounds of the simulation, which represents the volume of water in the simulation, offset by a constant that depends only on the bathymetry. This value should be invariant in the simulation, and can give a means of measuring the accuracy of the simulation.

#### 2.1.5 Simulator1D: energy()

sim.energy()

Calculates the total energy in the system using the formula

$$\int \eta_t \Phi^S + g\eta^2 dt$$

This value should be invariant in the simulation, and can give a means of measuring the accuracy of the simulation.

#### 2.1.6 Simulator1D: peak\_location()

sim.peak\_location()

Returns

$$\arg\max_{x}\eta(x),$$

the value of x that corresponds with the heighest point of the surface. This value is equivalent to the index of the highest eta, times dx, and provides a means of finding the approximate position of a solitary wave.

#### 2.1.7 Simulator1D: zeta\_at()

sim.zeta\_at(x)

Returns  $\zeta(x)$ , using a linear interpolation scheme for non-discrete points. calling  $zeta_at(i*dx)$  is equivalent to evaluating zeta[i].

#### 2.1.8 Simulator1D: run\_simulation()

sim.run\_simulation(plot\_dt, data\_dt, directory)

Runs a simulation, time-stepping until a stop-condition is met, and saving plots and/or data at given intervals of time.

argument	description
saveplot_dt	the timestep between saved plots. This number is rounded to the nearest
	multiple of the simulation dt. If this value does not round to a positive number,
	plots are not saved. Plots are saved as PNG files with a name corresponding
	to the order it is saved in. A plot with number 'i' represents the data at time
	'i*saveplot_dt'
savedata_dt	the timestep between saved data. This number is rounded to the nearest mul-
tiple of the simulation dt. If this value does not round to a posit	
	data is not saved. Data is saved as a json file with name 'dat.json' which is
	created regardless if data should be saved or not. In the case that data is not
	saved, only the metadata of the simulation is stored.
directory	the directory to save the files to. This can also include a prefix to the file. If
	directory="~/sim/", then plots are saved as "[number].png" in the ~/sim/
	directory. If directory="~/sim", then plots are saved as "sim[number].png"
	in the home directory. If directory=None, no files are saved.

 ${\tt run\_simulation}$  has the following optional arguments:

argument	description	default
should_continue	function that determines if a simulation should stop or not. This takes the simulation as an argument and returns a boolean. The simulation is run until should_continue returns false. By default, this is the lambda function sim: sim.t < 500, which stops the simulation when a time of 500 is reached	(see description)
integrator	function or string that timesteps the simulation. functions should	"RK4"
integrator	only take the simulation as an argument and return nothing, modifying the passed simulation. Strings should be the name of a method in Integrator1D, which will be called by the simulation.	Terri
save_eta	Parameters for how eta should be saved when data is saved to json. This should be generated using Simulator1D.data_save_params(). If None, then eta is not saved.	None
save_phi	Parameters for how phiS should be saved when data is saved to json. This should be generated using Simulator1D.data_save_params(). If None, then phiS is not saved.	None
loop_callback	this function is called after every simulation step. It should be a void function that takes the arguments sim, step, plot, data, where sim is the simulator at the step step is the integer multiple of dt that the simulation has run plot is a boolean representing if the plot was saved this step data is a boolean representing if the data was saved this step By default, loop_callback makes a print statement after every 100 time steps.	(see description)
plot_func	A function that is dedicated to plotting and saving the figure. The function is expected to be void and take the arguments (sim, filename).	(see below)
save_json	Whether or not to save the file to json. The metadata of the simulation is saved even if savedata_dt is not positive. Setting save_json to false prevents this.	False
save_netcdf	Whether or not to save the file to netcdf. The netCDF file ignores data truncation specifications of save_eta and save_phi.	True
save_buffer	number of datapoints to buffer in between file-writes. If 0 or 1, then every savedata_dt, the json/netCDF file is opened and written to.	10
cdf_h_invariant	Whether or not h is treated as invariant. If false, then the bathymetry is saved every frame, alongside $\eta$ and $\phi^S$ .	True
cdf_Pderiv	The string that should populate the P_deriv field in the netcdf file.	"zero"
cdf_timeunits	The string that specifies the units of time for the simulation.	"seconds"
cdf_spaceunits	The string that specifies the units of x for the simulation.	"meters"

By default, plot\_func is defined as the function

```
def plot_func(sim, filename):
    plt.plot(sim.x, sim.eta, "b")
    plt.plot(sim.x, sim.zeta - sim.h0, "k")
    plt.ylabel("z")
    plt.xlabel("x")
```

```
plt.title(f"dx={sim.dx},dt={sim.dt},t={round(sim.t,3)}")
plt.savefig(filename)
plt.clf()
```

where plt is matplotlib.pyplot.

#### 2.1.9 Simulator1D: data\_save\_params()

Simulator1D.data\_save\_params()

Returns a dictionary of parameters for how to save data from a simulation. The output of data\_save\_params() should be used for aguments save\_eta and save\_phi in run\_simulation().

argument	description	default
dx	The spatial resolution to save with. If None, then the resolution	None
	is the same as the simulation. This value will always be rounded	
	to a whole number multiple of the simulation dx.	
point_conversion	A boolean that represents if data should be coded as a vector	False
	(array), or if the vector should be converted into a list of (x,y)	
	points. If true, then the conversion is made.	
eps	The tolerance of the save data. The data is rounded to the nearest	0
	multiple of eps. That is, with eps=0.001, the data is saved up to	
	the 3rd decimal place. 0 corresponds with no rounding.	
lin_tol	Only used when point_conversion is true. Specifies a toler-	-1
	ance for which points should not be saved when they are close	
	enough to a linear interpolation of the data. If the points	
	are $\{(0,0),(0.5,0.5),(1,1)\}$ , any nonnegative tolerance will discard	
	(0.5,0.5). If no points should be discarded, a negative value should	
	be given.	
zero_trunc	If a value is less than this distance from 0, the value is truncated	0
	to 0 before saving.	

#### 2.1.10 Simulator1D: init\_netcdf()

Simulator1D.init\_netcdf(''unforced.nc", True, ''zero")

Generates a netCDF file of the given filename and populates it with one point in time representing the simulation's current state. If the file already exists, then it is overwritten with a new file.

Returns the netCDF\_File object.

$\operatorname{argument}$	description
filename	The name of the file to be saved. Overwrites existing files
h_invariant	Whether the simulation should be treated as if h does not vary with time
P_deriv	Information on how pressure is obtained. Expects "zero", "wind" or "custom".

argument	description	default
timeunits	A string representing the units for time.	"seconds"
spaceunits	A string representing the units for spatial coordinates.	"meters"
P	If P_deriv is "zero" then this does nothing.	0
	If it is "wind", then the P attribute is set to this value.	
	If it is "custom", then P is the P <sub>a</sub> variable at time index 0.	
close	Whether or not this method should close the netcdf file resource	True
	after initialization.	

#### 2.1.11 Simulator1D: soliton()

Simulator1D.soliton(x0,a0,h0,Nx,dx)

Returns a tuple (eta,phiS) corresponding to the intial conditions of  $\eta$  and  $\Phi^S$  of a soliton at a given point in space.

argument	description		
x0	The x coordinate of the soliton, where x=0 corresponds with an index of 0 in		
	the vectorization of $\eta$ and $\Phi^S$		
a0	The amplitude of the soliton		
h0	The water deph beneath the soliton		
Nx	The number of points in the vectorization of $\eta$ and $\Phi^S$		
dx	The spatial resolution (distance between points)		
argument	description	default	
g	acceleration due to gravity	9.81	

This can be used in the constructor of Simulator1D through unpacking:

sim = Simulator1D(bathymetry, dt, dx, \*Simulator1D.soliton(x0,a0,h0,Nx,dx))

#### 2.1.12 Simulator1D: KY\_bathym()

Simulator1D.KY\_bathym()

Produces a bathymetry profile similar to Knowles and Yeh's paper. Expects h0 = 1, but the result can be multiplied by the desired h0 if not 1.

argument	description	default
Nx	number of points	$2^{14}$
dx	spatial resolution (distance between each point)	0.04
s0	nominal slope of the bathymetry	0.002
d0	height of the beach plateau	0.9
gamma	smoothing parameter	0.1
X1	position where the bathymetry should start sloping up	4

#### 2.1.13 Simulator1D: KY\_sim()

sim = Simulator1D.KY\_sim()

Returns a new simulator similar to Knowles and Yeh's initial conditions. The bathymetry is produced by KY\_bathym() and the initial  $\eta$  and  $\Phi^S$  values are

produced by soliton().

argument	description	default
Nx	Number of points (nodes) in the discreteized simulation	$2^{14}$
dx	Spatial resolution	0.04
$\overline{\mathrm{dt}}$	Temporal resolution (time step)	0.01
s0	Slope of the bathymetry	1/500
x0	location of the center of the starting soliton	30
a0	amplitude of the soliton	0.1
h0	depth of the water	1

## 2.1.14 Simulator1D: fields

In an instance of Simulator1D, the following fields may be of importance:

Temporal resolution (time step) of the simulation. This variable is used by an integrator when stepping the simulation. Most methods will use this time
step, but an adaptive method may use a timestep that is smaller. This can be modified externally.
Spatial resolution. This is the distance between two points of a vectorized function of $x$ . This should not be modified externally.
Vectorized $\eta$ with a spatial resolution $dx$ at the current time step. This can be modified externally, but must have the same length $(Nx)$ .
Vectorized $\Phi^S$ with a spatial resolution $dx$ at the current time step. This can be modified externally, but must have the same length (Nx).
Terms in the pertubation expansion of $\Phi$ . Calculating the vertical velocity $\Phi_x$ scales approximately $O(M^2)$ . This can be modified externally.
The acceleration due to gravity in this simulation. This can be modified externally.
base still water depth. We approximate the bathymetry as h0 in many calculations. This can be modified externally.
Vectorized bathymetry ( $\zeta$ ), offset so $\zeta = 0$ corresponds with $z = -h0$ . This can be modified externally, but must have the same length (Nx). Additionally, zeta_x should also be changed to the gradient of the new bathymetry.
Vectorized bathymetry gradient $(\nabla \zeta)$ . This can be modified externally, but must have the same length (Nx). Additionally, zeta should also be changed to match the new bathymetry.
Number of points used in the discretization (vectorization) of the simulation along the x-axis. This should not be modified.
distance in $x$ that the simulation uses. The vectorizations of $\eta$ , $\Phi^S$ , and $\zeta$ have the domain $[0, \text{sim\_length})$ . This should not be modified.
Vectorized domain. It holds that x[i] = dx*i. This should not be modified.
The double-domain of wave number. When performing an FFT on a function $f$ with spacing $dx$ , the values of the output correspond to the wavenumber by index. If $V$ is such a vectorization of the function $f$ , then
$ig(\mathcal{F}(f)ig)(\mathtt{kxdb[i]})pprox \mathtt{FFT}(V)\mathtt{[i]}$
where $\mathcal{F}$ is the continuous fourier transform. This should not be modified.
Normalized wavenumber of kxdb. This is equivalent to abs(kxdb). This should not be modified
Vectorized low-pass filter. Any function in the wavenumber domain can apply the filter by pointwise multiplication. This can be modified externally, but kxdb-im must also be modified accordingly.
The precomputed value $ik\chi(k)$ , which is computed from complex(0,1) * kxdb * chi. This should only be modified when chi is modified.
The time the simulation has run. This is only ever incremented by an integration method inside a step() call, and can be freely modified and accessed externally.

#### 2.2 integrator.py

This python file has the class Integrator1D which contains only static members. Each of which is a function that takes a Simulator1D instance, an atmospheric pressure argument P\_atmos, and potential optional arguments.

P\_atmos can either be a numpy array or a function that takes in the arguments eta,phiS,eta\_x,phiS\_x,w and returns a numpy array. The array should have a length equal to the number of nodes Nx used in the simulator, which matches the length of the bathymetry array passed into the constructor. For example, when measuring the wind effect, one may consider

$$P_a = P \frac{d\eta}{dx}$$

for some constant P. Such a function can be expressed as

#### 2.2.1 Integrator1D: euler

Referenced by string "euler". Makes one derivative calculation per step, using the method:

$$y_{n+1} = y_n + hf'(y_n)$$

#### 2.2.2 Integrator1D: RK4

Referenced by string "RK4". Makes 4 derivative calculation per step, using the classic 4 step, 4th order, Runge-Kutta method with the Butcher tableau:

#### 2.2.3 Integrator1D: implicit\_midpoint

Referenced by string "implicit\_midpoint". Uses the implicit midpoint rule:

$$y_{n+1} = y_n + hf\left(\frac{y_n + y_{n+1}}{2}\right)$$

This equation is solved using fixed point iteration after an initial guess from euler's method.

Takes additional arguments:

argument	description	default
max_iters	The most iterations used to achieve the desired tolerance, after	100
	which, RK4 is defaulted to.	
tol	The tolerance allowed for the iteration to stop.	$10^{-10}$

#### 2.2.4 Integrator1D: AM1

Referenced by string "AM1". Uses the one step Adams-Moulton method, the implicit trapezoidal rule:

$$y_{n+1} = y_n + h \frac{f(y_n) + f(y_{n+1})}{2}$$

This equation is solved using fixed point iteration after an initial guess from euler's method.

Takes additional arguments:

argument	description	default
max_iters	The most iterations used to achieve the desired tolerance, after	100
	which, RK4 is defaulted to.	
tol	The tolerance allowed for the iteration to stop.	$10^{-10}$

#### 2.2.5 Integrator1D: DIRK3

Referenced by string "DIRK3". Uses Nørsett's 3 stage, 4th order diagonally implicit Runge-Kutta method withe the Butcher tableau:

$$\begin{array}{c|ccccc}
x & x & 0 & 0 \\
\frac{1}{2} & \frac{1}{2} - x & x & 0 \\
\hline
1 - x & 2x & 1 - 4x & x \\
\hline
& \frac{1}{6(1 - 2x)^2} & \frac{3(1 - 2x)^2 - 1}{3(1 - 2x)^2} & \frac{1}{6(1 - 2x)^2}
\end{array}$$

where x = 1.06858. This equation is solved using fixed point iteration for each stage, where each stage has an initial guess of the former stage, with the first stage's initial guess as the derivative at  $y_n$ . For example, if  $k_1$  and  $k_2$  are the results of the first and second stage respectively, the second stage solves

$$k_2 = f\left(y_n + \left(\frac{1}{2} - x\right)hk_1 + xhk_2\right)$$

with an initial guess  $k_2 = k_1$ .

Takes additional arguments:

argument	description	default
max_iters	The most iterations used to achieve the desired tolerance, after	100
	which, RK4 is defaulted to.	
tol	The tolerance allowed for the iteration to stop.	$10^{-10}$

## 3 Examples

## 3.1 KY.py

This file defines one function, sim\_KY, which runs a simulation very similar to that of the Knowles and Yeh (2018) simulation. Run using python KY.py. When run in this manner, sim\_KY is called with the default arguments. When imported in python using import KY, the function is not called, but can freely be called by the user. sim\_KY has the following optional arguments:

argument	description	default
Nx	number of points (nodes) in the simulation.	$2^{14}$
a0	amplitude of the soliton initial condition	0.1
h0	base water depth. (depth at zeta $= 0$ )	1.0
X0	position (not vector index) of the soliton relative to the center of	-280
	the simulation space. Negative values correspond to the left half	
	of the simulation space.	
d0	height of the beach plateau (on the right side)	0.9
s0	nominal slope of the bathymetry.	$\frac{1}{500}$
dx	spatial resolution (distance between points/nodes in simulation	0.04
	space)	
dt	Time step of the simulation	0.01
Xt	Distance from the soliton wave crest to the beach toe. Positive	50
	values mean that the beach toe is in front of the wave	
mass_err_crit	Largest deviation in mass (calculated from volume()) allowed be-	0.5
	fore the simulation is terminated	
energy_err_crit	Largest deviation in energy (calculated from energy()) allowed	0.5
	before the simulation is terminated	
tmax	Largest time in simulation allowed before termination.	500
v	The low-pass filter. Takes a number to cut off all wavenum-	0.7
	bers greater than v*max(k), or takes a function that maps k	
	and max(k) to how much the corresponding amplitude should be	
	scaled. See the constructor of Simulator1D.	
M	The number of terms in the pertubation expansion to simulate	5
g	Acceleration due to gravity	9.81
tsave	time in between plot saves. Zero or negative corresponds to no	1
	saving. This value is rounded to a multiple of dt.	
save_dir	the directory/file prefix for the saved plots. By default, this is	(see description)
	"./KY_dx[dx]_dt[dt]_s[s0]_a[a0]_plot", where each bracketed value	
	is replaced by the relevant quantity.	
gui	Whether or not to run this program with matplotlib's plotting	True
	features. Use gui=False when running with no GUI access.	