04-10-24	Implementing Topology using CISCO Packet Tracer

Ex No: 5

AIM:

To configure a basic Network Topology using Cisco Packet Tracer.

PROCEDURE:

1. Place the devices:

- From the **Devices menu**, select **Routers** and choose the **1841 Router**. Place it in the centre.
- Go to **Switches**, select two **2960 switches**, and place them on the left and right of the router.
- From **End Devices**, select **PC** and place three PCs connected to the left switch and three PCs connected to the right switch.

2. Configure Connections:

- Router to Switches:
 - Use the Copper Straight-Through Cable tool to connect:
 - Router FastEthernet0/0 to Switch0
 FastEthernet0/1 (left switch).
 - Router FastEthernet0/1 to Switch1
 FastEthernet0/1 (right switch).

Switches to PCs:

- For Switch0, connect each of its FastEthernet ports (e.g., FastEthernet0/2, FastEthernet0/3, and FastEthernet0/4) to PC0, PC1, and PC2.
- For Switch1, connect its FastEthernet ports (e.g., FastEthernet0/2, FastEthernet0/3, and FastEthernet0/4) to PC3, PC4, and PC5.

3. Configure IP Addresses:

- Router Interfaces:
 - Click on Router0, go to Config > FastEthernet0/0, and set:

• **IP Address:** 192.168.10.1

- **Subnet Mask:** 255.255.255.0

• Turn on the interface by clicking on Port Status.

Go to FastEthernet0/1 and set:

• **IP Address:** 192.168.11.1

- **Subnet Mask:** 255.255.255.0

• Turn on the interface by clicking on Port Status.


• PCs:

- o For **PC0**, **PC1**, and **PC2** (connected to the left switch):
 - Set IP addresses within the 192.168.10.0 network (e.g., 192.168.10.2, 192.168.10.3, 192.168.10.4) with a Subnet Mask of 255.255.255.0.
 - Set the **Default Gateway** to 192.168.10.1.
- For PC3, PC4, and PC5 (connected to the right switch):
 - Set IP addresses within the 192.168.11.0 network (e.g., 192.168.11.2, 192.168.11.3, 192.168.11.4) with a Subnet Mask of 255.255.255.0.
 - Set the **Default Gateway** to 192.168.11.1.

4. Test Connectivity:

• Use the **Ping Tool** from **PC0** to **PC3** (or any PC on a different subnet) to verify connectivity.

DIAGRAM:



RESULT:

Thus, the configuration of the basic Network Topology is successfully pings indicate proper configuration and connectivity between the subnets.

Basic VLAN configuration

Ex No: 6

AIM:

To configure VLANs on a switch and router in Cisco Packet Tracer to enable communication between devices in different VLANs through inter-VLAN routing.

PROCEDURE:

Step 1: Set Up the Devices

- Place the **Router**, **Switch**, and **PCs** in the workspace.
- Connect the **Router to the Switch** using a cross-over cable from **Router FastEthernet0/0** to **Switch FastEthernet0/20**.
- Connect each **PC** to the Switch:
 - PC1 and PC2 will be in VLAN 10 (connect to any ports like Fa0/1 and Fa0/2).
 - PC3 and PC4 will be in VLAN 20 (connect to any ports like Fa0/3 and Fa0/4).

Step 2: Configure VLANs on the Switch

1. Access the Switch CLI:

Click on the switch, go to the CLI tab.

2. Enter Configuration Mode:

config# enable config# configure terminal

3. Create VLANs:

∘ VLAN 10:

config# vlan 10

config# name VLAN10 config# exit

o VLAN 20:

config# vlan 20 config# name VLAN20 config# exit

4. Assign Ports to VLANs:

For VLAN 10 (PC1 and PC2):

config# interface FastEthernet0/1
config# switchport mode access
config# switchport access vlan 10
config# exit
config# interface FastEthernet0/2
config# switchport mode access
config# switchport access vlan 10
config# exit

For VLAN 20 (PC3 and PC4):

config# interface FastEthernet0/3
config# switchport mode access
config# switchport access vlan 20
config# exit
config# interface FastEthernet0/4
config# switchport mode access
config# switchport access vlan 20
config# exit

5. Configure the Trunk Port:

 Set the port connected to the router as a trunk port (e.g., FastEthernet0/20).

config# interface FastEthernet0/20 config# switchport mode trunk config# exit

Step 3: Configure the Router for Inter-VLAN Routing

1. Access the Router CLI:

Click on the router, go to the CLI tab.

2. Enter Configuration Mode:

config# enable
config# configure terminal

3. Configure Subinterfaces for Each VLAN:

Subinterface for VLAN 10:

config# interface FastEthernet0/0.10
config# encapsulation dot1Q 10
config# ip address 192.168.1.100 255.255.255.0
config# exit

Subinterface for VLAN 20:

config# interface FastEthernet0/0.20 config# encapsulation dot1Q 20 config# ip address 192.168.2.100 255.255.255.0 config# exit

4. Enable the Main Interface:

• Make sure the main interface **FastEthernet0/0** is up.

config# interface FastEthernet0/0 config# no shutdown config# exit


Step 4: Configure IP Addresses on PCs

- For **PC1** (**VLAN 10**):
 - IP Address: 192.168.1.1
 - Subnet Mask: 255.255.255.0
 - Default Gateway: 192.168.1.100
- For **PC2** (**VLAN 10**):
 - o IP Address: 192.168.1.2
 - Subnet Mask: 255.255.255.0
 - o Default Gateway: 192.168.1.100
- For **PC3** (**VLAN 20**):
 - IP Address: 192.168.2.1
 - Subnet Mask: 255.255.255.0
 - Default Gateway: 192.168.2.100
- For **PC4** (**VLAN 20**):
 - IP Address: 192.168.2.2
 - Subnet Mask: 255.255.255.0
 - Default Gateway: 192.168.2.100

Step 5: Test Connectivity

- **Ping** from PC1 to PC2 within VLAN 10 (should succeed).
- **Ping** from PC3 to PC4 within VLAN 20 (should succeed).
- **Ping** between PCs in different VLANs (e.g., PC1 to PC3) to verify inter-VLAN routing (should also succeed).

DIAGRAM:



RESULT:

Thus, the configuration of VLAN is successfully done and the ping from one PC to other PCs is verified.

25	1	Λ	2/	1
25-	1	U	-24	ŀ

Setting up Firewall using CISCO Packet Tracer

Ex No: 7

AIM:

To setup a network-based firewall using Cisco Packet Tracer.

PROCEDURE:

Step 1: Replace Router_A with Firewall_1

- **a.** Remove **Router_A** and replace it with **Firewall_1**.
- b. Connect the FastEthernet 0/0 interface on Firewall 1 to the **FastEthernet 0/1** interface on **Switch** A. Connect the **FastEthernet 0/1** interface on **Firewall 1** to the **Ethernet 6** interface of the **ISP cloud**. (*Use straight-through cables for both connections.*)
- c. Confirm that the host name of Firewall 1 is Firewall 1.
- **d.** On **Firewall_1**, configure the WAN IP address and subnet mask for the **FastEthernet 0/1** interface as **209.165.200.225** and 255.255.255.224.
- e. Configure the LAN IP address and subnet mask for the FastEthernet 0/0 interface on Firewall_1 as 192.168.1.1 and 255.255.255.0.

Step 2: Verify the Firewall 1 Configuration

• a. Use the **show run** command to verify your configuration. This is a partial example of the output:

```
Firewall_1#show run
Building configuration...
hostname Firewall 1
```

```
interface FastEthernet0/0
 ip address 192.168.1.1 255.255.255.0
 ip nat inside
 duplex auto
 speed auto
interface FastEthernet0/1
 ip address 209.165.200.225 255.255.255.224
 ip access-group 100 in
 ip nat outside
 duplex auto
 speed auto
interface Vlan1
 no ip address
 shutdown
ip nat inside source list 1 interface FastEthernet0/0
overload
ip classless
ip route 192.168.2.0 255.255.255.0 192.168.1.2
ip route 192.168.3.0 255.255.255.0 192.168.1.3
access-list 1 permit 192.168.0.0 0.0.255.255
access-list 100 deny ip any host 209.165.200.225
```

```
<output omitted>
!
end
```

• **b.** From **PC_B**, ping **209.165.200.225** to verify that the internal computer can access the Internet.

PC>ping 209.165.200.225

Pinging 209.165.200.225 with 32 bytes of data:

Reply from 209.165.200.225: bytes=32 time=107ms TTL=120

Reply from 209.165.200.225: bytes=32 time=98ms TTL=120

Reply from 209.165.200.225: bytes=32 time=104ms TTL=120

Reply from 209.165.200.225: bytes=32 time=95ms TTL=120

Ping statistics for 209.165.200.225:


Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 95ms, Maximum = 107ms, Average = 101ms

• **c.** From privileged EXEC mode on **Firewall_1**, save the running configuration to the startup configuration using the **copy run start** command.

DIAGRAM:



RESULT:

Hence, the firewall setup is configured within the network interface.

01-11-24	Router Configuration
Ex No: 8	

AIM:

Basic configuration of Router using Cisco Packet Tracer.

PROCEDURE:

1. Place the Router:

• From the **Devices menu**, go to **Routers** and select a router model (e.g., **1841 Router**). Place it on the workspace.

2. Add Network Devices (Optional):

• Add switches and PCs if you want to connect multiple devices to the router, creating different networks or subnets.

3. Connect Devices:

- Use **Copper Straight-Through Cable** to connect the router to other devices.
- Connect **Router's FastEthernet or GigabitEthernet ports** to the switches or directly to PCs, depending on the setup.

4. Enter Router Configuration Mode:

- Click on the router, then go to the CLI (Command Line Interface) tab.
- When prompted, type no if it asks if you want to enter the initial configuration dialog.

5. Access the Router's Global Configuration Mode:

- Type enable to enter **privileged EXEC mode**.
- Type configure terminal to enter **global configuration mode**.

6. Configure Router Interfaces:

• Enter interface configuration mode for each interface you want to configure:

For FastEthernet0/0:

config# interface FastEthernet0/0

Set the IP address and subnet mask:

config# ip address 192.168.10.1 255.255.255.0

Turn on the interface:

config# no shutdown

Exit the interface configuration:

config# exit

• Repeat the process for **FastEthernet0/1** (or any other interface):

config# interface FastEthernet0/1
config# ip address 192.168.11.1 255.255.255.0
config# no shutdown

7. Configure Routing (Optional, if using multiple networks):

• For **static routing**, type:

config# exit

config# ip route 192.168.11.0 255.255.255.0 192.168.10.2

• This step is optional if you only need basic routing between directly connected networks.

8. Save the Configuration:

- To save the configuration, exit global configuration mode by typing exit until you return to the privileged EXEC mode.
- Type:


config# write memory

• Alternatively, use copy running-config startup-config to save the configuration to non-volatile memory.

9. Test Connectivity:

- Connect PCs to the router via switches or directly.
- Assign IP addresses and default gateways to each PC in their respective network.
- Use the **Ping Tool** to test communication between devices in different networks.

DIAGRAM:



RESULT:

The basic router configuration is made using PCs, Switches and Router which connects all seamlessly.