# When the OS gets in the way

(and what you can do about it)

Mark Price LMAX Exchange

# When the OS gets in the way

(and what you can do about it)

Mark Price LMAX Exchange

#### It's not the OS's fault

- Linux is an excellent general-purpose OS
- Many target platforms
- Low-latency is a special use-case
- We need to provide some hints

# Why should I care?

#### Useful in some scenarios

- Low latency applications
- Response times < 1ms</li>
- Compute-intensive workloads
- Long-running jobs

#### **Jitter**

- "slight irregular movement, variation, or unsteadiness, especially in an electrical signal or electronic device"
- Variation in response time latency
- Long-tail in response time

#### **Dealing with it**

- First take care of the low-hanging fruit
  - e.g. Garbage collection (gc-free / Zing)
  - e.g. Slow I/O
- Once response times are < 10ms the fun begins</li>
- Make sure your code is running!

#### **Measure first**

- Need to validate changes are good
- End-to-end tests
- Using realistic load
- Change one thing and observe
- A refresher...


#### Modern hardware layout

HyperThread

Core

Socket / NUMA node

Chassis




#### Multi-tasking

- num(tasks) > num(HyperThreads)
- OS must share out hardware resources
- Clever? Dumb? Fast? Slow?
- Fair...


#### Linux CFS

- Completely Fair Scheduler
- Maintains a task 'queue' per HT
- Runs the task with the lowest runtime
- Updates task runtime after execution
- Higher priority implies longer execution time
- Tasks are load-balanced across HTs


#### An example application ...



#### ... running on a language runtime



#### ... running on an operating system




#### **Optimise for locality - PCI/memory**

HyperThread


Core

Socket / NUMA node

Chassis



#### **Target deployment**



# How do I start?


#### Start with the metal


- BIOS settings for maximum performance
- That's a whole other talk...

#### Discover what's available

- Istopo is a useful tool for looking at hardware
- Provided by the hwloc package
- Displays:
  - HyperThreads
  - Physical cores
  - NUMA nodes
  - PCI locality

## Istopo





#### NUMA-local RAM

Caches


Core

HyperThread


#### Reserve & use specific resource

- Use isolcpus to reserve cpu resource
- kernel boot parameter
- isolcpus=0-5,10-13
- Use taskset to pin your application to cpus:
- taskset -c 10-13 java ...
- Set affinity of hot threads:
- sched\_setaffinity(...)

#### Deploy the application



#### You have no load-balancer



#### A solution: cpusets

- Create hierarchical sets of reserved resource
- CPU, memory
- Userland tools: cset (SUSE)


#### Isolate OS processes

- cset set --set=/system --cpu=6-9
  - create a cpuset with cpus 6-9
  - create it at the path /system
- cset proc --move --from-set=/ --to-set=/system
  - move all processes from / to /system
  - -k => move unbound kernel threads
  - --threads => move child threads
  - --force => erm... force

#### Run the application

- cset set --cpu=0-5,10-13 --set=/app
- cset proc --exec /app taskset -cp 10-13 java ...
  - start a process in the /app cpuset
  - run the program on cpus 10-13
- sched\_setaffinity() to pin the hot threads to cpus 1,3,5

#### **Isolated threads**



# No more jitter?

#### perf\_events

- Sampling tracer
- Static/dynamic trace points
- Very low overhead
- A good starting point for digging deeper
- perf list to view available trace points
- network, file-system, scheduler, etc

#### What's happening CPU?

- perf record -e "sched:sched\_switch" -C 3
  - Sample task switches on CPU 3
- perf report (best for multiple events)
- perf script (best for single events)

#### Rogue process

```
java 36049 [003] 3011858.780856 sched:sched_switch: java: 36049 [110] R ==> kworker/3:1:13991 [120]
```

```
kworker/3:1
13991 [003] 3011858.780861: sched:sched_switch:
kworker/3:1:13991 [120] S ==> java:36049 [110]
```

#### ftrace

- Function tracer
- Static/dynamic trace points
- Higher overhead
- But captures everything
- Can provide function graphs
- trace-cmd is the usable front-end

#### So what is that kernel thread doing?

- trace-cmd record -P <pid> -p function\_graph
  - Trace functions called by process <pid>
- trace-cmd report
  - Display captured trace data

#### Some things can't be deferred

```
kworker/3:1-13991 [003] 3013287.180771: funcgraph entry:
                                                                    process_one_work() {
kworker/3:1-13991 [003] 3013287.180772: funcgraph entry:
                                                                      cache_reap() {
kworker/3:1-13991 [003] 3013287.180772: funcgraph entry: 0.137 us
                                                                       mutex_trylock();
kworker/3:1-13991 [003] 3013287.180772: funcgraph entry: 0.289 us
                                                                       drain array();
kworker/3:1-13991 [003] 3013287.180773: funcgraph entry: 0.040 us
                                                                       _cond_resched();
kworker/3:1-13991 [003] 3013287.180859: funcgraph_exit: +86.735 us
                                              +86.735 us
```

#### Things to look out for

- cache\_reap() SLAB allocator
- vmstat\_update() kernel stats
- other workqueue events
  - o perf record -e "workqueue:\*" -C 3
- Interrupts set affinity in /proc/irq
- Timer ticks tickless mode
- CPU governor set to performance
  - /sys/devices/system/cpu/cpuN/cpufreq/scaling\_governor


#### Some numbers

- Inter-thread latency is a good proxy
- 2 busy-spinning threads passing a message
- Time taken between producer & consumer
- Record times over several seconds
- Compare tuned/untuned


#### Results

== Latency (ns) ==	untuned	tuned
mean	466	216
min	200	128
50.00%	464	208
90.00%	608	288
99.00%	768	336
99.90%	992	544
99.99%	2432	1664
max	69632	69632

#### tuned vs untuned




### tuned vs untuned (log scale)



#### Results (loaded system)

== Latency (ns) ==	untuned	tuned
mean	545	332
min	144	216
50.00%	464	336
90.00%	544	352
99.00%	736	448
99.90%	2944	544
99.99%	294913	704
max	884739	36864

#### tuned vs untuned (loaded system)



#### Summary

- Select threads that need access to CPU
- Isolate CPUs from the OS
- Pin important threads to isolated CPUs
- Don't forget interrupts
- There will be more things...
- Always test assumptions!

#### Thank you

- Imax.com/blog/staff-blogs
- github.com/epickrram/perf-workshop
- @epickrram