
Single Plot Geometry



ViewObject points outside the plot rect are placed relative to the Outer Box.

Font sizes and line widths are caculated based on the width and height of the Plot Region, not the Outer Box. The sizes are calculated in double precision, allowing for the desired sizes to be determined without regenerating the labels.

All dimensions saved in a plot are unitless and double precision. No reference may be made to the number of pixels.

Multiple Plots can share the same Outer Box.


- -The PlotRects must all adjust to be the same size.
- -The first plot in the list that has use for it gets the Left and Bottom label regions.
- -The second gets the right and top label regions.
- -All subsequent plots don't get Label regions.
- -All plots may put axis lines and labels inside the Plot Region.
- -The axis lines and labels for all plots get printed on the bottom layer; the lines and matrixes get plotted above them (in order) and the child ViewObjects get plotted on top.
- -normally, zoom rects get interpreted by each plot separately. However, a UI must be provided to allow zooming of only one of the plots.

Potential Simplification:

Allow at most 2 plots to share the same outer box:

- -Would this be easier (including UI)?
- -Is there a use case to argue against it?


Plot Geometry and Alignment



Tolerance: 1% of the (Width + Height)/2

of the Top Level View

Plot Geometry with shared Axis.



When the following conditions are true, plots will share their X axis as shown to the left.

- A) Tied Zoom condition:
- -The plot zooms are tied
- -The plots are aligned in a column
- -The X axis range is the same
- B) Parent option Condition:
 -The parent of the plots (eg, a group) has
 - 'Share axis when possible' set -The plots are aligned in a column -The X axis range is the same

- When plots are sharing their X axis:
 __-the top and bottom label regions of the intermediate
- plots are suppressed.

 -The intermediate plots share axis lines
 -Tick marks are still present
 -The outer boxes of the plots are adjusted within the column to maintain a constant Plot Region size. This is dynamic on resize.

If the conditions are only met for part of the column, then the only plots which meet the condition still have their zooms tied.

If the shared axis conditions cease to be met, the plots return to their original size and condition.

Analogous behaviour applies for Y axis sharing.

Tolerances: Alignment needs to be within 1% of the size of the Top Level View to be considered aligned.