# DISCUS Package

Reference Guide

Version 5.99

developed by

Reinhard Neder

Email: reinhard.neder@fau.de

**Thomas Proffen** 

Email: tproffen@ornl.gov

http://tproffen.github.io/DiffuseCode/

Document created: October 17, 2019

# **Contents**

1	Wel	come	3
	1.1	Getting started	4
		1.1.1 Windows	4
		1.1.2 Linux	4
	1.2	Command language overview	4
		1	5
		1.2.2 Main commands	6
		1.2.3 Interrupt	8
2	FOF	RTRAN style interpreter	ç
	2.1	Variables	9
	2.2	Arithmetic expressions	12
	2.3	Logical expressions	12
	2.4		12
	2.5	Intrinsic functions	13
	2.6	Intrinsic commands	13
	2.7	Loops	14
	2.8		16
	2.9	Filenames	17
	2.10		18
		1	2(
			2(
	2.12	Remote control	21
3	Inst		22
	3.1	Windows	22
		3.1.1 DISCUS and CYGWIN	22
	3.2	Mac OSX	23
	3.3	Unix / Linux	23
4	COI	MMON commands	<b>2</b> 4
	4.1	News	24
	4.2	Options	
	4.3	#	
	4.4	@	26

DIFFEV 5.99 Page 1

CONTENTS Reference Guide

4.5	=	27
4.6	input	28
4.7	break	28
4.8	cd	28
4.9	continue	29
4.10	do	29
	echo	
	eval	
4.13	exit	30
4.14	expressions	30
4.15	filenames	32
4.16	fclose	33
	fend	
4.18	fexist	33
4.19	fformat	33
4.20	fget	34
4.21	fopen	34
4.22	fput	35
4.23	fsub	35
4.24	functions	35
4.25	help	37
4.26	if	38
4.27	learn	39
4.28	lend	39
4.29	manual	39
4.30	seed	39
4.31	matrix	40
4.32	set	41
4.33	show	42
4.34	sleep	43
4.35	socket	43
4.36	stop	44
4.37	system	44
4.38	wait	45
	variable	45
	errors	47

# Chapter 1

# Welcome

Congratulations for downloading the DISCUS package. The DISCUS package consists of the following programs:

- **DISCUS SUITE**: The DISCUS SUITE is a common program that includes DISCUS DIFFEV and KUPLOT. It allows to switch seamlessly between the individual sections and will eventually replace the individual parts. It also offers an optimization for large scale computing facilities. For all practical reasons, the **DISCUS SUITE** should be used and the use of the individual programs DISCUS, DIFFEV and KUPLOT is discouraged.
- **DISCUS**: This is the main diffuse scattering and defect structure simulation program. This is the program that gave the package its name.
- **DIFFEV**: This is a more recent addition. This program allows the refinement of a set of high level parameters (*e.g.* input parameters of a DISCUS macro) based on a differential evolutionary algorithm.
- MIXSCAT: This is newest addition to the DISCUS package. This program allows on to extract differential PDFs from neutron- and x-ray data.
- **KUPLOT**: This is plotting program of the package. It is nearly as old as DISCUS itself.

Each of the program(sections) has its own users guide which include disclaimers and the appropriate references to cite in case you are publishing work derived from using these programs. This manual contains a description of the command language common to all programs as well as detailed installation instructions. DISCUS itself has been developing over the last nearly 30 years and the command language was developed before anyone knew about things like python. The commands are loosely related to FORTRAN77 syntax, so the older generation should have no trouble with it.

Please visit the DISCUS homepage frequently at http://tproffen.github.io/DiffuseCode/and also consider subscribing to the DISCUS mailing lists.

DIFFEV 5.99 Page 3

# 1.1 Getting started

#### 1.1.1 Windows

Once the programs have been installed you should see an icon for each of the programs on your personal desktop. Double click the icon to start the program of your choice. At program start, each of the programs sets its starting folder to

```
C:\Users\your_name
```

where your\_name will be your user name. The string Users may be slightly different depending on the language settings. To work with data and macros that are stored in a separate folder, you need to change to this folder.

Within the DIFFUSE program window, type the command cd including a blank space after the cd. At this point do not hit the enter key. Open the desired folder with the Windows-Explorer. Left click on the small folder symbol in the top line that indicates the path to your folder. This should highlight the full path to the folder.

For DISCUS, DIFFEV, and MIXSCAT you can drag this folder symbol into the DIFFUSE program window. The command line should now read something like

```
cd C:\Users\Neder\Documents\DISCUS_examples
```

For KUPLOT and DISCUS SUITE, select the highlighted path to the folder with CTRL-c. Activate the KUPLOT or DISCUS SUITE window and press the middle button on the mouse. This should place the full path into the program window.

Once you activate the window and hit the ENTER key the program will work in this folder.

#### 1.1.2 Linux

Once you have installed the Diffuse program package, the binaries will usually reside in the directory: /usr/local/bin/. To use any of the programs, open a terminal window, switch to the desired directory and type the program name.

Several command line options are available for the Linux version. The most important one is to start the execution of a macro:

```
discus_suite -macro useful.mac
discus_suite -macro useful_with_params.mac par1 par2 par3
```

The first line would start DISCUS SUITE and begin the automatic execution of macro useful.mac. Likewise in the second line, the macro useful\_with\_params.mac is started, which takes three parameters. The actual strings that you provide for <parl>, <par2>, <par2>, <para> are handed down as parameters to this macro. Note that there are no comma between the parameters. For info on further command line options the the on-line help for the Command language.

# 1.2 Command language overview

All sections of the DISCUS SUITE are controlled by a command language. The basic command style is a command verb that may be accompanied by one or several parameters. You must type

at least one empty space between the command and the list of parameters. The parameters are all separated from each other by a comma as in the following short example:

```
discus
! a comment
# another comment
read
cell example.cell, 2,3, 4
show atom, all ! In line comment after exclamation mark
exit
```

Anything to the right of an exclamation mark! or a hash tag # is considered a comment and is not interpreted.

Most commands can be abbreviated, as long as the short form is still unique. Thus these commands are all valid forms to step into the DISCUS fourier menu:

```
fourier
fourie
fouri
four
```

Several command throughout the DISCUS SUITE take optional parameters. Sometimes these are the last parameter(s) that you can simply omit. See the on-line help for the individual commands for full information.

More and more though the optional parameters are specified with the syntax: Name of the optional parameter, a colon ":" and the actual value you want to provide:

```
run plot:inter, kill:yes
```

If an optional parameter is omitted, its value goes back to the default value. This is a bit different compared to the non-optional parameters. These parameters retain their value until you change the value explicitly.

As the named optional parameters are identified by their name, they may be given in arbitrary order.

## 1.2.1 Help

The DISCUS SUITE offers the manuals, and on-line help. To access any of the manuals from the DISCUS SUITE, type:

```
manual ! Opens the manual for your current section manual section:suite ! Opens the SUITE manual manual section:discus ! Opens the DIFFEV manual manual section:diffev ! Opens the DISCUS manual manual section:kuplot ! Opens the KUPLOT manual manual section:package ! Opens this PACKAGE manual
```

The DISCUS SUITE will open the manual with a standard PDF viewer. Alternatively you can open the manual with your favorite viewer with the second optional parameter viewer\_name, where viewer\_name shall be replaced by your favorite.

At a Linux system the manual files are usually installed into /usr/local/share.

At a Windows system the manual files are in the share folder within the Discus installation, commonly at c:Program Files (x86) \Discus\share.

On-line help is available for each command through the help command. A straight help will open the on-line help at the current section respectively menu within a section. Alternatively you can migrate immediately to the on-line help for a specific command by adding the command name after the help command. If the command is within a menu of your current section you can access the help by providing the menu as first parameter, followed by the command name.

```
help ! Opens the help at the current section / menu help fourier ! Opens the help for the fourier command help fourier, lots ! Opens the help for the fourier> lots command
```

To leave the on-line help simply hit the ENTER key. At each help level the on-line help gives a list of further topics, type any of these names to get help on one of these topics.

The help is organized hierarchically for the menus. At the DISCUS section for example the top level provides help to all DISCUS commands. If you step into the help of (for example) the fourier menu you can access the fourier commands.

To go back to an upper help level type . . at the on-line help prompt.

As most help entries are lengthy, the list of help options at the current level will have moved out of your view. Just type ? to refresh this list.

#### 1.2.2 Main commands

The main DISCUS SUITE commands are summarized in table 1.1 followed by a list of common Unix commands.

The DISCUS SUITE can react in different ways to an erroneous calculation or erroneous input. The default "continue" is to display an error message and to stop the execution of a macro/calculation. Thereafter the program continues with the regular interactive prompt. Sometimes one may want to live on after a fault. This may for example occur if you test for the existence of a file or directory/folder, or if you encounter the end of file upon a read. A macro can live on if the error status is set to "live". The most stringent reaction to an error is to terminate the DISCUS SUITE with the error status "exit". Keep in mind that no data are saved! During a regular interactive session the program displays a prompt like

```
suite> ! Prompt within the top level suite
discus/four> ! Prompt within a sub menu of a section, here DISCUS
```

If a macro is executed, the lines that the DISCUS SUITE reads from the macro file are also echoed to the screen. This may produce lengthy output. The choices offered are to set the prompt "on" or "off". An optional parameter allows to save the current prompt status so that the "old" status can be restored at a later stage.

Most of the Unix commands offer many more options. Just try it out, in many cases a parameter like "-help" or "-help" will give a short summary of the available options. Examples:

ls -a List all files, that includes hidden files ls -l List a long listing that includes many details ls -R List recursively into sub directories as well

Unix offers many possibilities to work in a flexible manner with file names. You can place into the filename different *wild* characters:

Name	Description
liscus	Go from the main DISCUS SUITElevel to the DISCUS section.
1.66	Leave this section with an "exit" command.
diffev	Go from the main DISCUS SUITElevel to the DIFFEV section.
	Leave this section with an "exit" command.
kuplot	Go from the main DISCUS SUITElevel to the KUPLOT section.
	Leave this section with an "exit" command.
oranch <name></name>	Step sideway from your current section into the section
	<name>. Leave this section with an "exit" command.</name>
exit	Leave a menu, a section or the program. If you are within
	a menu of any of the three sections, you will get back to the
	main level of this section. If you are at the top level of any
	of the three sections, you will get back to the main DISCUS
	SUITE level. If you are at the mainDISCUS SUITE level, the
	program will terminate without further confirmation.
nelp	Enter the help menu
<sup>®</sup> macro.mac	Run the commands in file "macro.mac" as if they were typed
	interactively. See section 2.10 for full details.
earn macro.mac	Start to learn everything to type and log these command
	into the file "macro.mac". This log will include everything
	you type, including errors
end	Finish the learn sequence. The macro "macro.mac is now
	available to be run as @macro.mac
ed <folder></folder>	Change the directory / folder to the new directory /
	folder <folder>. The path can be a relative path as in cd</folder>
	/new_folder or an absolute path.
system <command/>	Instruct your operating system to execute the command
	<command/> . As the DISCUS SUITE is really a Unix driven
	program, even on a Windows computer these are predomi-
	nantly Unix commands. Some commonly used commands
	are listed in Table 1.2
set error, <status></status>	The <status> may be "continue", "exit" "live".</status>
show	Most sections and menus offer a "show" command to dis-
	play the local settings. Check the on-line help at the respec-
	tive menu for details.
run	Most of the menus expect several commands that define the
	simulation / calculation prior to the calculation. The actual
	calculation is carried out with the "run" command at the re-
	spective menu.
	The <status> may be "on", "off".</status>

 Table 1.1: Main DISCUS SUITE commands

\* character string of any length

? exactly one character

[a-z,A-Z] a character from interval a-z or A-Z.

Name	Description
pwd	Inquire the current directory/folder, the present working
	directory.
ls	List the content of the current directory/folder
mkdir <folder></folder>	Make the new directory/folder <folder></folder>
mkdir -p <folder></folder>	Make the new directory/folder <folder>, including any in-</folder>
	termediate parent folders. This command version will not
	flag an error, if the folder does already exist.
rm <filename></filename>	Remove the file <filename>.</filename>
	Careful, this command does not ask for a confirmation!
	If the file does not exist or if it is a protected file you will get
	an error message.
rm -f <filename></filename>	Forced remove the file <filename>.</filename>
	Careful, this version does not ask for a confirmation!
	This command version will not flag an error, if the file does
	not exist.
cp <from> <to></to></from>	Copies the old file <from> to a new name and or direc-</from>
	tory/folder <to>.</to>

Table 1.2: Common Unix commands

You may provide a single interval as well, and also a range of numbers. Examples:

ls \*.mac List all files that end in ".mac"

ls data.0[0-9]1 List all files called data.001, data.011, to data.091 files called data.002 etc.

are omitted

#### 1.2.3 Interrupt

If a lengthy calculation or macro appears to be faulty you can interrupt the calculation with a CTRL-c. The DISCUS SUITE will offer a selection how to proceed after this interrupt. You can:

CTRL-c. The Dis	SCUS SUTTE WILL offer a selection now to proceed after this interrupt. You can:
resume	the calculation. The program will (hopefully) resume the calculation as if
	nothing had happened.
continue	with the normal interactive prompt. At this point you will be at the top
	level of the DISCUS SUITE . Be aware that a macro may have changed
	the folder/directory. You are well advised to check this with a command
	system pwd
save	The program will write the current crystal to a file EMERGENCY.STRU to
	give you a chance to recover (most) of your work. It then continues in the
	same fashion as with the continue command.
exit	the DISCUS SUITE.

# Chapter 2

# FORTRAN style interpreter

The programs include a FORTRAN style interpreter that allows the user to program complex modifications. The interpreter provides variables, linked to data sets and free variables, loops, logical construction, basic arithmetic and built in functions. Commands related to the FORTRAN interpreter are =, break, do, else, elseif, enddo, endif, eval, if and variable. The command eval allows to examine the contents of a variable or to evaluate an expression, e.g. eval r[1]\*0.5.

#### 2.1 Variables

The programs in the *DISCUS* suite use variables to store data. The programs distinguish three types of variables:

- Variables with fixed name for general use
- Variables with user defined names for general use
- Variables with fixed name that carry program information

#### Variables with fixed name for general use

There are two types of variables: variables of type integer or real, denoted by their fixed names "i" and "r", immediately followed by a left square bracket [, one or more indices (separated by a comma), and finally a right square bracket ].

Examples for build in variables are given next.

Example : i[1], r[0], i[i[1]], x[2]

The build-in variables i[n] and r[n] are general purpose variables. The index n can take integer values from zero to a maximum value defined at program compilation, usually 500. In addition, each of the program has a number of build-in variables related to its function. DISCUS for example has a number of variables related to the structure that the user is using, like unit cell dimensions, atom positions etc. For a list of these variables, please refer to the respective program users guides.

#### Variables with user defined names for general use

The second set of variables are single valued variables with user defined names. These allow

DIFFEV 5.99 Page 9

the user to use more obvious variable names. The programs allow to define real valued, integer valued and character variables. With almost identical syntax, the user can provide 1-D and 2-D integer and real valued arrays. Currently no Character arrays are provided.

An example of the use of defined variables is shown here:

```
variable real,alpha,90.0
variable real,beta
variable real,diff
beta = 94.0
diff = alpha - beta
eval diff
```

In line one we define a real variable alpha with an initial value of 90. Next, two more variables are defined and the difference between alpha and beta is calculated (line 5) and the result displayed on the screen (line 6).

Recently another type of variables was added to the command language: character variables. These can be used in conjunction with format statements (see command reference under *expressions*). An example setting the plot title in KUPLOT to the current date is listed below.

```
1 variable character,datum
2 #
3 datum="%c",fdate(0)
4 tit2 "Plotted on %c",datum
```

Note the slightly different way character intrinsic functions are used. A complete list of character functions can be found in Table 2.3.

To define 1-D or 2-d arrays, simply add the optional parameter "dim" to the variable definition.

```
1 variable real, mat_a, dim:[3:3]
2 variable real, vec_a, dim:[3]
```

To work on user supplied matrices, the DISCUS SUITE provides several commands:

- matmul: Multiply matrices
- matadd: Add matrices
- detmat: Calculate the determinant
- mattrans: Calculate the transposed matrix

#### Variables with predefined name

Starting with version 5.7.0 system wide variables with fixed name were introduced. Currently these are mostly related to the refinement, see the DIFFEV manual for details.

The general predefined variables are explained in the following list:

- UNDEF = -1 A status is undefined
- TRUE = 1 A status is true
- FALSE = 0 A status is false

- IS\_TOP = 0 Possible value for STATE, if you are currently at the top program level. This will be the case within the suite. If the individual programs DISCUS, KUPLOT or DIFFEV are used as stand alone programs you will be in a STATE=IS\_TOP in their main menu.
- IS\_SECTION = 1 Possible value for STATE, if you are currently at one of the three sections DISCUS, DIFFEV, KUPLOT within the suite.
- IS\_BRANCH = 2 Possible value for STATE, if you are currently in a section after a "branch" command.
- SUITE = 0 Possible value for PROGRAM, if you are within the suite.
- DISCUS = 1 Possible value for PROGRAM, if you are within discus.
- DIFFEV = 2 Possible value for PROGRAM, if you are within diffev.
- KUPLOT = 3 Possible value for PROGRAM, if you are within kuplot.
- MPI\_OFF = 0 Possible value for MPI, if the program was not started with mpi.
- MPI\_ON = 1 Possible value for MPI, if the program was started with mpi.
- PROGRAM Receives a value of (SUITE, DISCUS, DIFFEV, KUPLOT) depending on which part you are currently within.
- STATE Receives a value (IS\_TOP, IS\_SECTION, IS\_BRANCH), depending on the way this section was entered.
- MPI\_FIRST Relevant to DIFFEV only. The value will be UNDEFined in the other sections. Within DIFFEV it tells a slave program if the slave was invoked as the first 'run\_mpi' command within the current refinement generation.
- MPI Receives a value of MPI\_OFF or MPI\_ON.
- PI Pi = 3.1415...

One further system variable is PI. The capitalization is mandatory.

#### Variables with fixed name that carry program information

These variables, which are common to the whole program suite are used by the programs to return information to the user.

Currently just one such variable res[n] exists. It is used in a wide variety of commands and functions to return a successful operation or to contain result values.

As an example see:

```
1 fexist dummy.file
2 eval res[0]
2 eval res[1]
```

Here the res variable is used to flag the existence of the file called "dummy.file". res[0] usually carries the number of results returned, in this special case one. Here res[1] would be equal to one if the file exists and zero if it does not exist.

## 2.2 Arithmetic expressions

The language allows the use of arithmetic expressions using the same notation as in FORTRAN. Valid operators are +, -,  $\star$ , / and for the exponentiation  $\star\star$ . Expressions can be grouped by round brackets ( and ). The usual hierarchy for the operators holds. Values of expressions can be assigned to any modifiable variable. If you know FORTRAN (or another programming language) you will have no problems with these examples.

```
i[0] = 1

r[3] = 3.1415

r[i[1]] = 2.0*(i[5]-5.0/6.5)
```

# 2.3 Logical expressions

Logical expressions are formed similar to FORTRAN. They may contain numerical comparisons using the syntax: *<arithmetic expression><arithmetic expression>*. The allowed operators are

```
<, <=, >, >=, ==, /=
or in the older Fortran77 style:
.lt., .le., .gt., .ge., .eq., .ne.
```

for operations less than, less equal, greater than, greater equal, equal and not equal, respectively. Logical expressions can be combined by the logical operators:

```
.not., .and., .or., .xor., .eqv..
```

The following example shows an expression that is true for values of i[1] within the interval of 3 and 11, false otherwise.

```
i[1] >= 3 .and. i[1] <= 11 i[1].ge.3 .and. i[1].le.11
```

Logical operations may be nested and grouped using round brackets ( and ). For more examples see section 2.8.

# 2.4 Character expressions

Character expressions allow you to write annotations in KUPLOT, nicely formatted comments in the output of any section or complex filenames.

The first use might be that of character variables within the sections of the DISCUS suite. The simplest assignment of values to a character variable takes the form:

```
character variable, string
string = 'This is a string'
```

In order to concatenate strings, or to place numerical values into a string three format specifiers are provided:

```
"%c" or "%10c"
"%d" or "%10d"
"%f" or "%10.4f"
```

All specifiers require the leading % as control character. The %c specifier allows to place the value of a character value or a character string into the expression. A number between the % and the c signifies the width of the string that will be placed. If the incoming string is too long it will be truncated as in the following examples:

```
character variable, string
character variable, line
string = 'abcdefghij'
line = "%c", string ! place at variable length
echo "%c",line
abcdefghij ! This will be shown on screen
line = "%c5", string ! place as 5 character long string
echo "%c",line
abcde ! This will be shown on screen
line = "%5c", string(4:8) ! take a sub string
echo "%c",line
defgh ! This will be shown on screen
```

The %d specifier allows to write the value of an integer expression into a character string. The optional number between the % and the d specifies the number of digits that will be printed. If a capital D is used in combination with the the width defining number, any leading digits are printed as zeros.

```
echo "%d more %d", 1, 2

1 more 2 ! This will be shown on screen
echo "%4D more %4d", 1, 2

0001 more 2 ! This will be shown on screen
```

The %f specifier allows to write the value of a real valued expression into a character string. The optional number between the % and the f specifies the width of the field printed and the number of digits that follow the decimal point. If a capital F is used in combination with the the width defining number, any leading digits are printed as zeros.

```
echo "%f more %d", 1.1, 20.2
1.000000 more 20.0000000 ! This will be shown on screen
echo "%4.1F more %6.2f", 1.1, 20.2
01.0 more 20.20 ! This will be shown on screen
```

#### 2.5 Intrinsic functions

Several intrinsic functions are defined. Each function is referenced, as in FORTRAN, by its name followed by a pair of parentheses ( and ) that include the list of arguments. The ( does not have to immediately follow the function name. Trigonometric and arithmetic functions are listed in table 2.1. Table 2.2 contains various random number generating functions. Some programs such as DISCUS have a set of specific intrinsic functions allowing one to for example calculate bond length. Again each individual users guide will contain a table of these specific functions.

Finally the available functions returning a character string are listed in Table 2.3.

#### 2.6 Intrinsic commands

To operate on user variables that are 1-D or 2-D matrices, the DISCUS SUITE provides a couple of standard operations. These are listed in Table 2.4:

Type	Name	Description
real	sin(r) cos(r) tan(r)	Sine, cosine and tangent of <r> in radian</r>
real	sind(r) cosd(r) tand(r)	Sine, cosine and tangent of <r> in degrees</r>
real	asin(r) acos(r) atan(r)	Arc sin, cosine, tangent of <r>, result in radian</r>
real	asind(r) acosd(r) atand(r)	Arc sin, cosine, tangent of <r>, result in degrees</r>
real	sqrt(r)	Square root of <r></r>
real	exp(r)	Exponential of <r>, base e</r>
real	ln(r)	Logarithm of <r></r>
real	sinh(r) cosh(r) tanh(r)	Hyperbolic sine, cosine and tangent of <r></r>
real	abs(r)	Absolute value of <r></r>
integer	mod(r1, r2)	Modulo <r1> of <r2></r2></r1>
integer	int(r)	Convert <r> to integer</r>
integer	nint(r)	Convert <r> to nearest integer</r>
real	frac(r)	Returns fractional part of <r></r>
real	min(r1, r2)	Smaller number of <r1> and <r2></r2></r1>
real	max(r1, r2)	Larger number of <r1> and <r2></r2></r1>

Table 2.1: Trigonometric and arithmetic functions

Type	Name	Description	
real	ran(r)	Uniformly distributed pseudo random number between 0.0	
		inclusively and 1.0 exclusively. Argument <r> is a dummy</r>	
real	gran(r1, typ)	Gaussian distributed random number with mean 0 and a	
		width given by $<$ r1 $>$ . If $<$ typ $>$ is "s" $<$ r1 $>$ is taken as sigma,	
		if <typ> is "f" <r1> is taken as FWHM.</r1></typ>	
real	gbox(r1, r2, r3)	Returns pseudo random number with distribution given by a	
		box centered at 0 with a width of <r2> and two half Gaussian</r2>	
		distributions with individual sigmas of <r1> and <r3> to the</r3></r1>	
		left and right, respectively.	
real	gskew(r1,typ)	Skewed Gaussian distributed random number with mean	
real	logn(r1,r2)	Returns a lognormal distributed number with mean <r1> and</r1>	
		sigma <r2> of the underlying Gaussian distribution.</r2>	
integer	pois(r1)	Returns a Poisson distributed random number with mean	
		<r1>.</r1>	

Table 2.2: Random number functions

# 2.7 Loops

Loops can be programmed using the do command. Three different types of loops are implemented. The first type executes a predefined number of times. The syntax for this type of loop is

```
do <variable> = <start>,<end> [,<increment>]
...commands to be executed ...
enddo
```

Name	Description
date(0)	Returns current date as CCYYMMDDhhmmss.sss.
fdate(0)	Returns current date as character string Day Mon dd hh:mm.ss
	уууу.
fmodt(0)	Returns modification date of the last file opened as character string Day
	Mon dd hh:mm.ss yyyy.
cdate(0)	Returns current date as Day Mon DD hh:mm:ss CCYY.
getcwd(0)	Returns the current working directory.
getenv('VAR')	Returns the value of the environment variable VAR.

**Table 2.3:** String functions

Name	Description
matmul	multiplies two matrices or a matrix by a scalar
matadd	Adds two matrices. The second matrix can be multiplied by a scalar.
detmat	Calculates the determinant of the input matrix and stores this in the
	output matrix.
mattrans	Calculates the transpose of the input matrix and stores this in the output
	matrix.

Table 2.4: Matrix commands

Following modern Fortran, the word "enddo" may also be spelled as "end do" with arbitrary blanks between the words.

Loops may contain constants or arithmetic expressions for <start>, <end>, and <increment>. <increment> defaults to 1. The internal type of the variables is real. The loop counter is evaluated from (<end> - <start>)/<increment> + 1. If this is negative, the loop is not executed at all. The parameters for the counter variable, start end and increment variables are evaluated only at the beginning of the do - loop and stored in internal variables. It is possible to change the values of <variable>, <start> and/or <end> within the loop without any effect on the performance of the loop. This practice is not encouraged, could, however, be an unexpected source of errors.

The second type of loop is executed while <logical expression> is true. Thus it might not be executed at all. The syntax for this type of loop is

```
do while <logical expression> ... commands to be executed ... enddo
```

The last type of loop is executed until <logical expression> is true. This loop, however, is always executed once and has the following syntax

```
do
... commands to be executed ...
enddo until <logical expression>
```

In the body of commands any valid program commands can be used. This includes calls to the sub levels, further do loops or macros, even if these macros contain do loops themselves. The maximum level of nesting is limited by the parameter *MAXLEV* in the file *doloop\_mod.f90*. If necessary adjust this parameter to allow for deeper nesting. All commands from the first do command to the corresponding 'enddo' are read and stored in an internal array. This array can take at most *MAXCOM* (defined in file *doloop\_mod.f90* as well) commands at every level of nesting. If lengthy macro files are included in the do loop, this parameter might have to be adjusted.

If a do loop (or an if block) needs to be terminated, the break command will perform this function. The parameter on the break' command line gives the number of nested levels of do and if blocks to be terminated. The interpreter will continue execution with the first command following the corresponding enddo or endif command. An example is given below, note, that the line numbers are only given for better orientation and are no actual part of the listed commands.

```
1 do i[2]=1,5
2     do i[1]=1,5
3         if ((i[1]+i[2]) .eq 6) then
4         break 2
5         endif
6     enddo
7 enddo
```

In this example, the execution of the inner do-loop will stop as soon as the sum of the two increment variables i[1] and i[2] is equal to 6. The program continues with the enddo line of the outer do - loop. Notice that two levels need to be interrupted, the if block and the innermost do loop. If the parameter had been equal to one, only the if block would have been interrupted, while the innermost do loop would have continued without break.

#### 2.8 Conditional statements

Commands can be executed conditionally by using the if command. Analogous to FORTRAN, the if-control structure takes the following form:

```
if ( <logical expression> ) then
...commands to be executed ...
elseif ( <logical expression> ) then
...commands to be executed ...
else
...commands to be executed ...
endif
```

Following modern Fortran, the words "elseif" and "endif" may also be spelled as "else if" and "end if" with arbitrary blanks between the words.

The logical expressions are explained in section 2.3. Enclosed within an if block any valid program command can be used. This includes calls to the sub levels further if blocks, do loops or macros, even if these macros contain if blocks or do loops themselves. The elseif and

else section is optional. The maximum level of nesting is limited by the parameter *MAXLEV* in the file *doloop\_mod.f90*. If necessary adjust this parameter to allow for deeper nesting. All commands from the first if command to the corresponding endif are read and stored in an internal array. This array can take at most *MAXCOM* (defined in file *doloop\_mod.f90* as well) commands at every level of nesting. If lengthy macro files are included in the do loop, this parameter might have to be adjusted.

If an if block (or a do loop) needs to be terminated, the break command will perform this function. The parameter on the break command line gives the number of nested levels of do and if blocks to be terminated. The interpreter will continue execution with the first command following the corresponding enddo or endif command. See the example in section 2.7 for further explanations.

```
1  #
2  # Read crystal file
3  #
4  read
5  cell cell.cll,10,10,10
6  #
7  # Remove atoms with probability 0.3
8  #
9  do i[0]=1,n[1]
10    if(ran(0).lt.0.3) then
11    remove i[0]
12  endif
13  enddo
```

The example listed above illustrates the use of loops and conditional statements within *DIS-CUS*. Again, the line number are given for easy reference and not part of the actual input. The first three lines are just comments. In lines 4 and 5 an asymmetric unit is read from the file *cell.cll* and expanded to a crystal size of 10x10x10 unit cells. In line 9 starts a do-loop over all atoms within the crystal. The variable n[1] contains this information (see DISCUS users guide). Since the function ran produces a uniformly distributed pseudo random number in the range 0.0 to 1.0, the if statement in line 10 is true in about 30% of its calls, at least for sufficiently large crystal sizes. Thus approximately 30% of the atoms are removed (line 11), and the corresponding amount of vacancies (VOID) created within the crystal.

#### 2.9 Filenames

Usually, file names are understood as typed, including capital letters. Unix operating systems distinguish between upper and lower case typing! However, sometimes it is required to be able to alter a file name e.g. within a loop. Thus, the command language allows the user to construct file names by writing additional (integer) numerical input into the filename. The syntax for this is:

```
"string%dstring",<integer expression>
```

The file format MUST be enclosed in quotation marks. The position of each integer must be characterized by a %d. The sequence of strings and '%d's can be mixed at will. The corresponding integer expressions must follow after the closing quotation mark. If the command line

requires further parameters (like addfile for example) they must be given after the formatparameters. The interpretation of the '%d's follows the C syntax. Up to 10 numbers can be written into a filename. All of the following examples will result in the file name *a1.1*:

```
i[5]=1
outfile a1.1
outfile "a%1d.%1d",1,1
outfile "a%1d.%1d",4-3,i[5]
```

The second example shows how filenames are changed within a loop. Here the output (e.g. Fourier transform) will be written to the files *data1.calc* to *data11.calc*.

```
do i[1]=1,11
    ..
    outfile "data%d.calc",i[1]
    ..
enddo
```

As personal style you might find it best to label the files *data01.calc* to *data11.calc* i.e. with leading zeros and a fixed number of digits that are used for the number. This is readily achieved with the %D format specifier.

```
do i[1]=1,11
    ..
    outfile "data%2D.calc",i[1]
    ..
enddo
```

#### 2.10 Macros

Any list of valid program commands can be written to an ASCII file and executed indirectly by the command <code>@<filename></code>. The commands are executed as typed. Macro files can be written by any editor on your system or be generated by the 'learn' command. 'learn' starts to remember all the commands that follow and saves them into the file given on the <code>learn</code> command. The learn sequence is terminated by the <code>lend</code> command. The default extension of the macro file is <code>.mac</code>. Macro files can be nested and even reference themselves directly or indirectly. This referencing of macro files is, however, just a nesting of the corresponding text of each macro, not a call to a function. All variable retain their values. If an error occurs while executing a macro, the program immediately stops execution of all macros and returns to the interactive prompt. If the macro switched to a sub level, and the error occurred inside of this sub level, the program will remain within this sub level the interactive prompt corresponding to this sub level is returned. The command <code>stop</code> allows the user to interrupt the execution of a macro, enter commands and continue the macro using the command <code>cont</code>. Note, that the macro needs to continued in the same sub level it was interrupted.

On the command line of the macro command @, optional parameters can be supplied. Within the macro these have to be referenced as \$1, \$2 etc. Upon execution of the macro the formal parameters \$n are replaced by the character string of the actual parameters as they are typed on the command line. Even if the actual parameters on the macro command line consist of

expressions or variables, initially the string as typed on the command line is pasted into the macro. If necessary, these strings are evaluated as the macro executes a specific line.

Parameter \$0 contains the number of parameters specified on the command line. As any other command parameters, these parameters must be separated by comma. If a formal parameter is referenced inside a macro without a corresponding parameter on the command line, an error message is given. An example is given below:

```
# Adds two numbers supplied as command line parameters.
# The value is stored in variable defined by parameter three
#
$3 = $1 + $2
eval $3
```

If this macro is called with the following line, @add 1, 2, i[4], the result is stored in variable i[4] which now has the integer value 3. The commands are initially replaced by the macro parameters to yield:

```
# Adds two numbers supplied as command line parameters.
# The value is stored in variable defined by parameter three
#
i[4] = 1 + 2
eval i[4]
```

If macros are nested, the lines of an inner macro are executed at the point where the outer macro encounters the inner macro calling line. The text of the inner macro is effectivley pasted into the main macro. Keep in mind that this is just a pasting of macro lines into a single strem of lines. In contrast to programming languages, a macro does not provide its own reserved name space. All variables have the same value throughout the program.

Besides the plain string substitution the DISCUS SUITE offers a second transfer mechanism, that will transfer the value of an expression or variable to the macro instead of the string that is placed onto the macro line. To achieve this, enclose the macro parameter with the string value(...).

```
variable integer, number
number = 2
@test.mac number, value(number), i[4]
```

The effect of this is that the macro listed previously will execute the line:

```
i[4] = number + 2
eval i[4]
```

In this simple example, no difference results to the standard transfer mode. The main application of the value(...) transfer mode is the possibility to place the result of an expression (character, numeric) at a place, where DISCUS SUITE does not offer the evaluation of such an expression. With a macro call in the form:

```
variable integer, number
number = 2
@subsitute.mac value("base_%4D",number)
```

The corresponding parameter \$1 in macro substitute.mac

```
# macro substitute.mac
echo $1
variable integer, $1
```

would take the form:

```
echo base_0002
variable integer, base_0002
```

#### 2.10.1 Command line options

If the program is started with command line parameters, e.g. discus 1.mac 2.mac, the program will execute the given macros in the specified order, in our example first 1.mac then 2.mac. You cannot, however, provide parameters to these macros.

Alternatively a single macro can be executed by starting the program with the command line option -macro macro\_file\_name parameter(s)

If a macro is not found in the current working directory, a system macro director is searched. This system macro directory is located at path\_to\_binary/sysmac/discus/. Commonly used macro files might be installed in this directory. If a macro file is not found, an error message is displayed.

# 2.11 Working with files

The command language offers the user several commands to write variables to a file or read values from a file. First a file needs to be opened using the command fopen. An optional parameter append allows one to append data to an existing file. Once the task is finished, the file must be closed via fclose. In the standard configuration, the program can open five files at the same time. The first parameter of all file input/output related commands is the unit number which can range from 1 to 5. The commands fget and fput are used to read and write data, respectively. The following example illustrates the usage of these commands:

```
1 fopen 1,sin.dat
2 fput 1,'Cool sinus function'
3 #
4 do i[1]=1,50
5    r[1]=i[1]*0.1
6    r[2]=sin(r[1])
7    fput 1,r[1],r[2]
8 enddo
9 #
10 fclose 1
```

In line 1 we open the file sin.dat and write a title (line 2). If the file already exists it will be overwritten. Note that the text must be given in single quotes. Text and variables may be mixed in a single line. Next we have a loop calculating  $y = \sin(x)$  and writing the resulting x and y values to the open file (line 7). Finally the file is closed (line 10). To read values from a file use simply the command fget and the read numbers will be stored in the specified variables. In contrast to writing to a file, mixing of text and number is not allowed when reading data. However, complete lines will be skipped when the command fget is entered without any parameters.

#### 2.12 Remote control

It is possible to remote control the programs in the DISCUS package using so called sockets. One program acts as server and receives and executes commands. In order to enable the server feature, the program needs to be started using the <code>-remote</code> command line switch as in the example below:

dhcp165057:prog> ./discus -remote

Note that the host IP address and port number are given at the end of the startup output. This information is needed to connect to this running version of in our case DISCUS. To allow connections from computers other than 127.0.0.1 (localhost) or using a different port, use the command line options -access and -port.

In order to connect to the DISCUS server, we use the command socket as in this example:

```
discus > socket open,127.0.0.1,3330
Connecting to 127.0.0.1:3330 ...
Server : ready
Connected ..
discus > socket send,echo This is cool
Server : This is cool
Server : ready
discus >
```

Of course any program or script that can use sockets is able to connect to the DISCUS package programs in this way. For more details refer to the socket command reference later in this guide.

# Chapter 3

# Installation

In this section we will describe the installation process for the DISCUS program package. The current version of the software can be downloaded from the DISCUS homepage at https://github.com/tproffen/DiffuseCode/.

Refer to the section corresponding to your operating system for installation information. At the github release site you will find installation guides for DISCUS for Unix, MacOS and Cygwin. The Windows installation is performed via a self extracting installer.

#### 3.1 Windows

The Windows version of the DISCUS package is distributed as a self-extracting installer. This makes the installation very easy. Simply download the file *Diffuse-X.X.X-win64-YYMMDD.exe* or if necessary *Diffuse-X.X.X-win32-YYMMDD.exe*. Here YYMMDD specifies the date of the distribution and. X.X.X stands for the version number. Make sure you download the most recent one. Run the installer by double clicking on the corresponding file icon. You will first receive a Windows security alert, because the installer is not digitally signed by us. Once we get around to figure out how, this warning will go away. For now, just click on *Run*. This will start the installation process itself and the installation dialog will show up. Follow the instructions on the screen and that is all, you are ready to use any of the programs that are part of the DISCUS package. Look in the *START - Programs* menu for links to the programs as well as the documentation.

As you may noticed, we have changed the way the installer is build. For that reason, you need to **uninstall any DISCUS version prior to 2010 before proceeding with the installation.** The current installer works fine on *Windows XP*, *Windows Vista Windows7* and *Windows 10*.

#### 3.1.1 DISCUS and CYGWIN

The DISCUS package for Windows is developed using the CYGWIN package

http://www.cygwin.com

which provides a UNIX like environment for Windows. We recommend installing the *CYGWIN* 32bit or 64 bit package to be used with the DISCUS package, although this is not required. One side effect of the use of *CYGWIN* is that one needs to specify UNIX style paths. Also you might see that for example drive C: is referred to as /cygdrive/c/.

DIFFEV 5.99 Page 22

Another side effect is the file format for all ASCII or text files like macros, cell files, diffraction pattern output etc. Unfortunately UNIX and Windows use a different encoding to signal the end of a line for such file types. Since we use *cygwin*, the file format is UNIX style. As a consequence, the Windows *Editor* usually found under *All programs* in the *Accessories* section cannot handle such file types. Please use a more advanced text editor like *Notepad+* or *WordPad* instead to edit these files. If you installed *CYGWIN*, you can use the programs *unix2dos* and *dos2unix* to convert file formats.

#### 3.2 Mac OSX

The Mac OSX version of the DISCUS package is distributed as a binary installer as well. Simply download the the file *Diffuse-mac-YYMMDD.exe*. Again YYMMDD specifies the date of the distribution. Make sure you download the most recent one. Once the download is finished, run the installer by double clicking on the corresponding file icon. You will see an installation screen. Follow the instructions. The programs will be installed in /Applications/discus.

#### 3.3 Unix / Linux

For Unix or Linux operating systems, the DISCUS package is distributed as source code and needs to be compiled before the programs can be used. You might also check the DISCUS homepage for available binary distributions for Linux which might be available in the near future. Refer to the separate file INSTALL\_DISCUS.pdf or AAA\_INSTALL\_DISCUS.pdf for details.

To build the programs from the source, you will need a FORTRAN and a C compiler. We use gcc and gfortran which are freely available at

http://directory.fsf.org/project/gcc/.

While gcc is installed on most Linux systems, gfortran might need to be installed separately. First copy or download the file *DIFFUSE\_CODE\_YYYY\_MMDD.tar.gz* or from the github release pages the link to *vX.X.X.tar.gz*. Next unpack the archive using the command

```
tar -xvf DIFFUSE_CODE_YYYY_MMDD.tar.gz
```

This will create a directory *DiffuseCode*, containing the distribution. Within this directory there are separate directories for each of the different programs as well as a directory *lib\_f90* which contains command language related routines common to all programs. Build a a new Directory called *DiffuseBuild* next to the source code directory. Go to this build directory and run ccmake to install the program:

Finally some environment variables need to be defined. Each program looks for a variable corresponding to its name. For example DISCUS will use a variable DISCUS and so on. The definition of the variables can be done e.g. in the <code>.login</code> or <code>.cshrc</code> file using the command <code>setenv DISCUS /path/to/discus</code> for the <code>csh</code> of <code>set DISCUS=/path/to/discus</code>; <code>export DISCUS</code> if you are using the Bourne shell. If this path is also included in your search path you can start the program simply by entering <code>discus</code>. Similarly, the other programs are started by entering their respective names.

# Chapter 4

# **COMMON** commands

#### 4.1 News

Here you find a list of recent changes, additions, bug corrections

### 2019\_June

Modified the test for valid user defined variable names to include a test on all sections.

## 2019\_May

Added a possibility to stop a macro at a 'wait return'

#### 2019\_March

Added two more system variables, LOOP and SLOW that can be used as counters in loops.

#### 2018\_November

Added a new transfer mode value() to macro parameters. See the help entry '@' for further details.

#### 2018\_September

Modified the do and if constructions to be valid as well for "end do" "end if" and "else if" with arbitrary blanks.

#### 2018\_July

Modified the ==> 'fput' and 'fget' commands to take an optional format string

Modified the ==> 'system' command to be a bit more flexible

Modified the ==> function "fmodt" to take a file name as well.

DIFFEV 5.99 Page 24

#### 2018\_June

Revised the reaction to a CTRL-C Added a ==> 'set wait {"on"|"off"} option Added a ==> 'set error, ... , "save" option

#### 2018\_May

The variables ==> 'variable' were augmented by 1-D and 2-D arrays. New commands ==> 'matmul', 'matadd', 'invmat', 'mattrans', 'detmat' provide the usual arithmetics

#### 2018\_Feb

New read-only ==> variables "PROGRAM", "STATE", "MPI", "MPI\_FIRST" were introduced that can be querried to learn in which program section and at what state you are.

As a patch to overcome internal precision, the ==> 'seed' command can take an alternative form.

#### 2018\_Jan

The logical comparisons may now take the operators: <, <=, ==, /=, >=, >/ The classical fortran77 operators are still valid

New logical functions "isvar" and "isexp" can be used within an "if" construction. See help entry ==>'function'

New parameters "reset" and "delete" have been added to the ==> 'variable' command

#### 2017 November

A 'manual' command has been added that reads the manual files

#### 2017\_Sep

Throughout the program the internal calculation of random numbers was changed to the FOR-TRAN 90 intrinsic function.

#### 2017\_July

Predefined variables REF\_\* are now read/write. See ==> variable

Introduced new intrinsic character functions: index and length See help under functions for details.

#### 2016\_October

New system variables have been introduced. They can be used like any other user defined variable. System variables are in capital letters.

#### 2014November

A new random number "gskew" has been added, which returns a Gaussian distributed random number. The underlying distribution can be set to be is left or right skewed.

# 4.2 Options

```
program [-debug] [-remote] [-port=p] [-access=ip] [macro.mac] program -macro <macro.mac>[ <par1> [ <par2> ...]]
```

All programs allow the following command line parameters. The flag "-debug" starts the program in debug mode. This is the same as using the command "set debug,on". The switch "-remote" starts the program in remote control mode. In this case the commands are send to the program through a socket. In this case the switch "-port' allows one to specify the port, the program will be listening on. Port numbers should be larger than 1024. The switch "-access' allows one to specify from which host connections will be accepted. The default is 'localhost'. See file "remote.f" for an example how to remote control the applications from another program. Note that the program will not accept input from the keyboard when in remote control mode. All other command line arguments are interpreted as macro files and will be executed at startup. These macros may not rely on parameters to be given on the command line. If a macro is to be executed that takes 1 or more parameters, use the "-macro" option. Note that this option is mutually exclusive to all other options. The first command line argument after the '-macro' option it the macro name, all further optional command line arguments are taken as macro parameters. These have to be seperated by one or more spaces. Parameters that need to contain spaces must be enclosed in single or double quotation marks. -macro test.mac 1 2 3

-macro test1.mac '1 + 2 + 3' This is the same as @test1.mac 1 + 2 + 3

#### 4.3 #

#### #<comment>

Any line beginning with a "#" is regarded as comment.

#### 4.4 @

#### @<filename> [<argument> ...]

This is the same as @test.mac 1,2,3

Any list of valid commands can be written to an ASCII file and and indirectly by the command:

```
prompt > @<name>
```

The commands that are listed within the macro file may start with leading blanks to help readability of the macro file. The commands are executed as typed. Macro files may call other macro files. This is not a call in the sense of calling a function. All variables are identical at all levels of macro file nesting.

Macro files can be written by any editor on your system or be generated by the ==> 'learn' command. 'learn' starts to remember all the commands that follow and saves them into the file given on the 'learn' command. The learn sequence is terminated by the 'lend' command. The default extension is ".mac"

Optionally arguments can be listed on the command line. These arguments will replace the formal parameters inside the macro. The formal parameters must be given as "\$1", "\$2" ... The string <argument> will replace the string "\$1". "\$1" is the first argument on the command line, "\$2" the second and so on. If there are not enough command line arguments, an error message is displayed. The parameter "\$0" contains the number of parameters listed on the line that called the macro. If no parameters were given this value will be zero.

Starting with version 5.29.0 the parameters on the macro command line may also be written as "value(<expression>)". In this case the corresponding formal parameter in the macro is replaces by the string that corresponds to the value of the expression.

The prompt setting ==> 'set prompt,"redirect"' has an important side effect on macro treatment. With the "redirect" setting, macros are stored internally, once they have been read from disk, and will be reused from memory. This helps to reduce unnecessary I/O, especially when you have nested macros inside loops. As a side effect, if a macro is modified on the disk, a further "@macro.mac" will not read the modified version but will continue to use the internaly stored version.

For all other settings, the internal macro storage is cleared when you get back to the normal interactive mode. This allows you to run a macro, then modify the version stored on the disk and execute the modified/corrected version.

Example assume that a macro file example.mac contains the lines: echo \$1 echo \$2

If this macro is started with: @example.mac 123.+456., abcd the lines that DISCUS\_SUITE will actually execute are: echo 123.+456. echo abcd

If this macro is started with: @example.mac value(123+456), abcd the lines that DISCUS\_SUITE will actually execute are: echo 579.0000000 echo abcd

In this second example "\$1" has been replaced by the value of the expression "123.+456.", while "\$2", has been replaced by the string "abcd".

The expression within the "value()" function may be any arithemtic or character expression as for example: value(sin(PI/2)) value("base\_%4D", i[0])

This last line is very helpful, if you want to replace a string at a position, where DISCUS\_SUITE does not perform a string manipulation operation. If the macro contains a line like "variable integer, \$1" a call to this macro in the form '@macro.mac value("base\_%4D", 1234)' would actually execute the command variable integer, base\_1234 Most DISCUS\_SUITE commands that expect a file name will allow you to replace a constant file name with a character expression. There are, certainly many parts of the program where this character substitution is not implemented. Masking it through a macro parameter value(expression) gives you full control.

#### 4.5 =

#### <variable> = <expression>

The expression on the right of the equal sign is evaluated and its result stored in variable <variable>.

## 4.6 input

#### Input editing functions

If the program was compiled with -DREADLINE, the following basic editing functions are available at the program prompt:

```
: moves to the beginning of the line
^B
                 : moves back a single character
^E
                : moves to the end of the line
^F
                : moves forward a single character
                : kills from current position to the end of line
: moves back through history
^K
^P or arrow up
'N or arrow down : moves forward through history
^H and DEL : delete the previous character
^D
                : deletes the current character
                : redraw line in case it gets trashed
^L/^R
^U
                 : kills the entire line
^W
                 : kills last word
```

Furthermore you can move within the line using the arrow keys.

#### NOTE:

If you redirect the input for executed PROG using 'prog < infile' you MUST use the command 'set prompt,off' or 'set prompt,redirect' in the first line to avoid that the program 'hangs' at the end of the file. (-> set prompt)

#### 4.7 break

#### break < levels>

The 'break' command stops the execution of the current block structure and advances to the next command following the block structure. With <levels> equal to 1 only the current block structure is interrupted, with any higher number the <levels> innermost block structures are interrupted. The 'break' command can be used only inside a block structure.

#### 4.8 cd

#### cd [<directory>]

This command allows one to change the current working directory (may not be available everywhere). If the command is called with no parameters, the current working directory is shown.

For the Windows versions, two different styles help to copy the folder name into the program window.

For KUPLOT and the DISCUS\_SUITE type cd and a space. Do not hit the enter/return key at this moment. Within a Windos Explorer click on the folder icon and copy the string CTRL-c. Activate the KUPLOT or DISCUS\_SUITE program and click the middle mouse button. This should paste the full path to the folder into the KUPLOT or DISCUS\_SUITE window.

For DISCUS, DIFFEV, and MIXSCAT type "cd" with the space as well. Now left click and drag the selected folder icon into the program window. This should copy the full pathinto the program window. Activate the window and hit the ENTER key.

#### 4.9 continue

#### continue [ "prog" ]

This command is effective only while PROG is in the interrupted macro mode or inside interrupted do-loop or if-statements, which serves as a debug mode for lengthy macros or block structures Make sure you have returned to the same sub menu before you continue!

Without parameters PROG resumes the execution of a macro or block structure in the line following the 'stop' command. If you had started another macro while debugging a macro, and this new macro contained a 'stop' command as well, the 'continue' command will run the remaining lines in the new macro and then stop again at the position of the 'stop' command in the outer macro.

By providing the 'prog' parameter, PROG immediately interrupts all macros and returns to the normal prompt. If you are in one of the sub sections "discus", "diffev", "kuplot", you can continue either with this subsection or go back to the main suite if you enter the program name as "suite".

#### 4.10 do

Loops can be programmed with the 'do' command. The command may take the following forms:

Here loops may contain constants or arithmetic expressions for <start>, <end>, and <increment>. The internal type of the variables is real. The loop counter is evaluated from (<end> - <start>) / <increment> =1 . If this is negative, the loop is not executed at all.

```
do while (<logical expression>)
  <commands to be repeated>
enddo
```

These loops are executed while <logical expression> is true. Thus, they may not be executed at all.

```
do
    <commands to be repeated>
enddo until (<logical expression>)
```

These loops, however, are always executed once, and repeated until <logical expression> is true. If an error occurs during execution of the loop, the loop is interrupted.

As of version 5.25.1 and later, the word "enddo" may also be spelled "end do", where the number of blanks that follow the "end" is not significant.

#### 4.11 echo

```
echo [<string>]
echo ["string%dstring",<integer expression>]
```

```
echo ["string%Dstring", <integer expression>]
echo ["string%fstring", <float expression>]
echo ["string%Fstring", <float expression>]
echo ["string%cstring", <character expression>]
```

The string <string> is echoed to the default output device as typed. This command serves as a marker inside long macro files. It gives the user a chance to include easy to find messages in order to follow lengthy or nested structures.

The alternative command format allows to echo formatted strings to the screen. Each "%d" is replaced by the value of the corresponding parameter. The sequence of "%d" corresponds to the sequence of the integer parameters, "%f" stands for parameters of the type real.

The value of a numerical expression between the "%" and the "d" determines the width of the integer field that is printed. In the case of a floating variable two expressions separated by a decimal point specify the width and the number of decimal digits that are printed.

The capital forms "%D" and "%F" will fill leading spaces with zeros.

A character format descriptor "%c" or "%Nc", with N an integer number, describes a string of characters.

```
Examples
echo ">%3d<",44 produces : > 44<
echo ">%1+2d<",44 produces : > 044<
echo ">%3D<",44 produces : > 044<
echo ">%5.1f<",44.1 produces : > 44.1<
echo ">%2**2+1.1f<",44.1 produces : > 44.1<
echo ">%c<",'bla' produces : > bla<
echo ">%5c<",'bla' produces : > bla <
```

#### 4.12 eval

```
eval <expr> [, <expr> ...]
```

Evaluates the expression(s) and displays the result(s). The result is not stored, this command is for interactive display only.

#### 4.13 exit

#### exit

Terminates the program and gets you back to your shell.

# 4.14 expressions

Arithmetic expressions can be evaluated in a FORTRAN style. Character expressions are used to assign a string of characters to a variable or filename.

#### **Arithmetic expressions:**

Five basic operators are defined:

```
"+" Addition
"-" Subtraction
"*" Multiplication
"/" Division
"**" Exponentiation
```

The usual hierarchy of operators holds. The parts of the expression can be grouped with parentheses "(",")" in order to circumvent the standard hierarchy Several intrinsic functions have been defined, see "functions" for a full listing.

Examples of valid expressions are:

```
1
1+3*(sin(3.14*r[1]))
x[1]*0.155
asind(0.5)
```

## Character expressions

A character expression is signaled by a pair of " ". The content may be a just a simple string of characters or additional format specifiers that are replaced by the value of a variable.

! character functions Within an ==> 'if' construction you may also specify a character expression in the form:

```
if( '"%2c", string(3:4)' .eq. 'cd' ) then
```

An expression (M:N) refers to the substring from the M's to the N's character.

#### Format specifiers

In filenames ==>"filename" or character expressions format specifiers are used to write the value of numerical or character variables into the corresponding string. These format specifiers may be:

```
%d writes a decimal/integer number, the number of digits
depends on the numerical value of the number
%D writes a decimal/integer number, the number of digits
depends on the numerical value of the number
%3d writes a decimal/integer number that fills 3 digits
```

```
%3D
       writes a decimal/integer number that fills 3 digits,
       leading blanks are filled with zeros
       Any width larger than the number of digits required is allowed
%Md
       writes a string M digits wide. M may be omitted.
       M may be an integer expression.
       d or D are allowed, D give leading zeros
% f
       A floating/real number is written flushed left into a
       character string of 8 digits
ջㅠ
       A floating/real number is written flushed left into a
       character string of 8 digits
%12.3f A floating/real number is written flushed right into a
       character string of 12 digits. 3 digits are used for the
       fractional part.
%12.3F A floating/real number is written flushed right into a
       character string of 12 digits. 3 digits are used for the
       fractional part. Leading blanks are filled by zeros.
%M.Nf writes a string M digits wide. N may be omitted.
       M and N may be integer expressions.
       f or F are allowed, F give leading zeros
       A character string is written, the width depends on the input
%C
       variable
      A character string of 5 characters is written.
%5c
```

#### Examples

```
variable character, string
variable character, line
string = "abcdefgh"
line = "%c", string ==> "abcdefgh"
line = "%4c", string(1:4) ==> "abcd"
line = "Hallo %c", string(2:4) ==> "Hallo bcd"
line = "Number %5d",1234 ==> "Number 1234"
line = "Number %5D",1234
line = "Float %8.3f",3.1415
                                     ==> "Number 01234"
                                     ==> "Float 3.141"
line = "Float %8.3F",3.1415 ==> "Float 0003.141"
```

#### filenames 4.15

Usually, file names are understood as typed, including capital letters. Unix operating systems distinguish between upper and lower case typing!

Additionally (integer) numerical input can be written into the filename. The syntax for this is:

```
"string%dstring", <integer expression>
"string%fstring", <real expression>
"string%cstring", <character expression>
```

The file format MUST be enclosed in quotation marks. The position of each integer must be characterized by a "%d". The sequence of strings and "%d"'s can be mixed at will. The corresponding integer expressions must follow after the closing quotation mark. If the command line requires further parameters (like "addfile" for example) they must be given after the formatparameters. The interpretation of the "%d"'s follows the C syntax. Up to 10 numbers can be written into a filename.

Refer to the help entry "expressions" for further help. Examples:

```
1)
i[5]=1
outfile a1.1
outfile "a%d.%d",1,1
outfile "a%d.%d",4-3,i[5]
outfile "a%1.1f",1.1
```

All the above examples will result in the file name "a1.1".

```
2)
do i[1]=1,11
...
outfile "data%d.calc",i[1]
...
enddo
```

The output is written to the files "data1.calc" through "data11.calc"

#### 4.16 fclose

```
fclose {<number>|"all"}
```

This command closes a file that was opened with 'fopen <number>' or closes all open files. If this command is not used before exiting the program, data might be lost!

#### 4.17 fend

```
fend <number>,{'continue'|'error'}
```

This command determines the reaction to an unexpected end of file while reading data from input file <number>. If the parameter is set to "continue", the program will set the variable res[0] to -1 and continue the macro. If you repeat the ==> 'fget' command, the program will again set res[0] to -1 and will not result in an error. In order to catch and EOF, you have to evaluate the value of res[0] each time the 'fget' command is executed.

If the parameter is set to "error", the program will stop reading data from the input file and terminate the macro with an error message. The value of res[0] remains undefined.

The default condition at program start is "error"

#### 4.18 fexist

```
fexist <file>
```

This command checks the existence of the specified file <file>. The result is written on the screen and returned via the res[] variables. If the file exists, res[1] is 1, otherwise it is 0. The variable res[0] returns the number of parameters, here 1.

#### 4.19 fformat

fformat <nc>,<format>

This command allows one to specify a FORTRAN style format string <format> to be used for column <nc>. The default is free format, which can be selected using the character \* as format string. If the command is called with no parameters, the current settings are displayed on the screen. Note that an unsuitable format might result in a conversion error and \*\*\* being written to the file!

Example: fform 1,F7.3

# 4.20 fget

fget <number>,<p1>,<p2>,...
[, form:'<string>']

This command allows the user to read data from a file that had been opened with 'fopen <number>. If no parameters are given, a line is read, yet its content is ignored and the line gets skipped. Otherwise the read numbers will overwrite the contents of the specified variables. The values in the input file must be separated by a blank or a comma. This means that to read a set of words in "This is a sentence", you will have to read this into 4 character variables. Note that a 'fget' command that does not run into an unexpected end of file sets the value of res[0] to zero!

The optional format string allows to specify an input format. The format string has to specify the format for each input parameter. It thus takes a comma delimited list of Fortran style descriptors: i<length> Integer = Whole number As in "i4" or "i17" f<length>.<dec> Floating point number: As in "f8.3". Only the overall length <length> is relevant, the length of the digits after a decimal point is ignored. Thus, other than in Fortran you can write: f<length> As in "f8" or "f12" a<length> Character = alphanumeric string As in "a20"

Example: Assume a file "example.text" with the following content:

3.1415 123456 2.7182817 Hello 654321 This is a sentence

This can be read with the following instructions

fopen 1, example.text variable character, str\_a variable character, str\_b! formats are optional for line 1, and 2 fget 1, r[2],i[2], form:'f6,i8' fget 1, r[2],str\_a,i[2], form:'f9.7,a5,i7' fget 1, str\_b, form:'a18'! whole string is read fclose 1

# 4.21 fopen

# fopen <number>,<file>[,{"append" | "overwrite"}]

This command allows the user to open a file for reading and writing using the commands 'fget' and 'fput'. The first argument is the number of the io\_stream. You can open several files at once, the exact value depends on the value of the variable MAC\_MAX\_IO in file "macro.inc". The second argument is the file name. The default is that existing files will be overwritten if 'fput' is used. Alternatively one can append data to a file by specifying the optional parameter "append".

# 4.22 fput

```
fput <number>,<p1>,<p2>, ...
[, form:'<string>']
```

This command allows one to write data to the file that had been opened by 'fopen <number>'. The parameters <pi> can either be variables and expressions or simple text enclosed in single quotes. If no parameters are given, an empty line is written. In order to mix character variables or character functions and numbers, the first parameter must be a format descriptor in double ""

The optional format string allows to specify an output format. The format string has to specify the format for each input parameter. It thus takes a comma delimited list of Fortran style descriptors: i<length> Integer = Whole number As in "i4" or "i17" f<length>.<dec> Floating point number: As in "f8.3". Total width is 8 digits with 3 digits after a decimal point. a<length> Character = alphanumeric string As in "a20"

The optional format string effectively replaces the ==> 'fformat' command.

#### 4.23 fsub

```
fsub <number>,[<left>,<right>]
```

The command allows you to limit the string from which 'fget' reads the data from file <number>. Data will only be read columns <left> to <right>. If both parameters are missing, the full input string is read. If the parameter <right> is set to "-1", the string is read from <left> all the way to the end of the input string, independent of its length.

The default values at program start are 1,-1 for all input channels.

```
Examples:
  Input line: "A text string 20.0 30.0"
  fsub 14,24
  fget r[1],r[2]
```

#### 4.24 functions

The following intrinsic numerical functions exist:

```
atand(<arg1>, <arg2>)
                                 ! Arguments are sine and cosine of angle
sin(<arg>)
cos(<arg>)
tan(<arg>)
sind(<arg>)
                                ! Argument in degrees
cosd(<arg>)
                                ! Argument in degrees
tand(<arg>)
                                ! Argument in degrees
sinh(<arg>)
                                ! Hyperbolic functions
cosh (<arg>)
tanh (<arg>)
                                ! Square root of <arg>
sqrt (<arg>)
                                ! exponential (base e)
exp(<arg>)
ln(<arg>)
                                ! natural logarithm of <arg>
                               ! Absolute value of <arg>
abs(<arg>)
                               ! Modulo <arg1> of <arg2>, real arguments
mod(<arg1>, <arg2>)
max(<arg1>, <arg2>)
                                ! Maximum of <arg1> and <arg2>
min(<arg1>,<arg2>)
                                ! Minimum of <arg1> and <arg2>
                                ! Convert argument to integer
int(<arg>)
                                ! Convert argument to nearest integer
nint (<arg>)
frac(<arg>)
                                 ! Returns fractional part of <arg>
ran(<arg>)
                                 ! Returns uniformly distributed pseudo
                                  random value 0 \le r \le 1.
gran(<arg>{, "s"|"f"})
                                 ! Returns gaussian distributed pseudo
                                  random value with mean 0.0 and
                                   sigma <arg> or FWHM <arg> if the
                                   second argument is equal to "f".
gskew(<arg>, <skew>{, "s" | "f"})
                                 ! Returns gaussian distributed pseudo
                                   random value with mean 0.0 and
                                   sigma <arg> or FWHM <arg> if the
                                   second argument is equal to "f".
                                   If skew is 0 the distribution is symmetric
                                   For skew <= 1.0 it is right skewed
                                   For skew >= -1.0 it is left skewed
logn(<arg1>, <arg2>{, "s"|"f"})
                                 ! Returns lognormal distributed pseudo
                                   random value. <arg1> is the location
                                   of the most likely value.
                                   <arg2> is the width of the distribution.
                                   More accurately, <arg2> is the width of
                                   the underlying distribution ln(logn).
                                   It is either sigma <arg2> or FWHM <arg2>
                                   if the third argument is equal to "f".
pois(<arg>)
                                 ! Returns Poisson distributed pseudo
                                   random value with mean <arg>.
```

The arguments to any of these functions are any arithmetic expression. System functions:

```
date(0)
                                ! Returns the current date as character
                                  string in the format:
                                  CCYYMMDDhhmmss.sss
                                                 (century, year)
                                  CCYY : year
                                        : month
                                                  (1, 2, \ldots 12)
                                  MM
                                                  (1, 2, \ldots 31)
                                  DD
                                       : day
                                                (1,2,... 24)
                                      : hour
                                       : minute (1,2,... 60)
                                  mm
                                  ss.sss: second.milliseconds
                                  (g77: milliseconds are 000)
fdate(0)
                                ! Returns the current date as character
                                  string in the format:
                                  Day Mon DD hh:mm:ss CCYY
                                      : weekday (Mon, Tue,... Sun)
                                  Dav
                                  Mon
                                        : month (Jan, Mar, ... Dec)
                                        : day
                                  DD
                                                  (1, 2, \ldots 31)
```

```
: hour (1,2,... 24)
                                        : minute (1,2,... 60)
                                        : second (1,2,... 60)
                                  SS
                                  CCYY : year (century, year)
fmodt (0)
                                ! Returns modification date and time
                                ! of the last file that was opened by
                                ! the Discus_suite.
fmodt('name')
                                ! Date for file "name"
fmodt(<line>)
                                ! Date for file in variable <line>
                                ! The format ! is the same as for fdate(0)
getcwd(0)
                                ! Returns the current directory as
                                  character string.
getenv('name')
                                ! Returns the value of the environment
                                  variable "name".
getenv(<line>)
                                ! Returns the value of the environment
                                  variable that is stored in variable <line>.
index(<line>, <substring> [,"BACK"]) ! Returns the location of the
                                  substring within the line.
                                  If the optional keyword "BACK" is present,
                                  index returns the last occurence.
                                  Both, the line and the substrings may be
                                  given as simple strings in single quotations
                                  or as a variable with with a preceeding
                                  format specifier, Examples:
                                  line ='Discus'
                                  index('Discus','s')
                                  index('Discus','s', BACK)
                                  index("%",'Discus',"%",'s')
                                  index("%",line
                                                  ,"%",'s')
                                  index("%c",getcwd(0), '/')
length(<line>)
                                  !Returns the length of string <line>
                                  The line may be
                                  given as simple strings in single quotations
                                  or as a variable with with a preceeding
                                  format specifier, Examples:
                                  length('Discus')
                                  length("%c",line)
                                  index("%c",getcwd(0), '/')
isvar('string')
                                  Returns TRUE if the string is a used
                                  defined variable. Can only be used inside
                                  an if construction:
                                  Examples:
                                  if(isvar('name')) then
                                  if(isvar('$1')) then
isexp('string')
                                  Returns TRUE if the string is a valid
                                  expression. Can only be used inside
                                  an if construction:
                                  Examples:
                                  if (isexp('3+5.')) then
                                  if(isexp('$1')) then
```

# 4.25 help

# help [<command>[, <subcommand>]]

The 'help' command is used to display on-line help messages. They are short notes on the command <command>. The command may be abbreviated. If the abbreviation is not unique, only the first help topic that matches the command is listed.

The first line of the help text gives the syntax of the command that is explained in the following lines. For a few commands the syntax line is repeated for different set of possible parameters.

After the text is displayed, you are in the HELP sublevel of PROG and there are the following commands possible:

```
<command> : Display help for <command> of current help level.
".." : Go up one help level.
"?" : Prints list of help entries of the current level.
<RETURN> : Exit help sublevel.
```

# 4.26 if

The if-control structure takes the following form:

The logical expressions may contain numerical comparisons with syntax:

As of version 5.25.1 and later, the words "elseif" and "endif" may also be spelled "else if" or "end if", where the number of blanks that follow the "end" is not significant.

<arithmetic expression> <operator> <arithmetic comparison>

The following operators are allowed:

```
< ! less than
<= ! less or equal
> ! greater than
>= ! greater or equal
== ! equal
/= ! not equal
```

The older forms are still valid:

```
.lt. ! less than
.le. ! less or equal
.gt. ! greater than
.ge. ! greater or equal
.eq. ! equal
.ne. ! not equal
```

The logical expressions may also contain string comparisons with syntax:

```
'<string1>' <operator> '<string2>'
```

Both strings MUST be enclosed by single apostrophes '. The operators are the same as those for the numeric expressions, lexical comparisons are used to evaluate the comparisons "less" and "greater". Within the single apostrophes you can place a character replacement operation. Thus a valid example would be: variable character, line line='text' if( '"%c",line' .eq. 'text' ) then Logical expressions can be combined by logical operators:

```
.not. ! negation of the following expression
.and. ! logical and
.eqv. ! logical equivalent
.xor. ! logical exclusive or
.or. ! logical or
```

Logical operations may be nested and grouped by brackets "(" and ")".

# 4.27 learn

#### learn [<name>]

Starts a learn sequence. All following commands are saved as typed in file <name>. defaults to " to " lend finishes the learn sequence.

# 4.28 lend

#### lend

Finishes the learn sequence started by ==> learn.

#### 4.29 manual

```
manual ["section:"{"suite" | "discus" | "diffev" | "kuplot" | "package" | "mixscat"} 
[,"viewer:"<name>]
```

Opens a PDF viewer for one of the Manuals

The section defaults to the current program section that you are working with. On Linux systems, the viewer defaults to "qpdfview", on Windows system it defaults to "firefox". If DISCUS does not find the default or the user provided viewer, DISCUS will search a list of common PDF viewers. If none is found an error message points to the folder that contains the manuals.

#### 4.30 seed

```
seed [ <value> ]
seed [ <value_a>, <value_b> ] , group:<no>
```

Reinitializes the pseudo random generator. The seed passed to the random generator is -abs(nint(value)). If the <value> is omitted, the random generator will be passed the number of hundredth of seconds passed since midnight, essentially initializing the sequence at a unknown fairly random point.

The seed may take more than one parameter, usually the compiler takes 12 different seeds.

To overcome limited internal precision, a patch has been introduced in version 5.17.0. As the random number generator takes seeds in the range from 1 to 999999999 the internal precision that calculates the value on the command line via the detour of a real valued number turned out to be insufficient. To ensure that an eight digit seed number is properly transfered to the seed initialization routine, split the number into two groups of four digit integers as in: 12345678 => 1234, 5678, group:2 The optional parameter "group" tells the SUITE to group these two numbers together to the original intended eith digit no.

# 4.31 matrix

For the user defined 1-D and 2-D matrices several command are available for the usual matrix arithmetics. These are:

#### detmat

#### detmat < matrix>

Calculates the determinant of a  $[n \times n]$  matrix. Currently limited to dimensions 1 to 4. The result is stored in res[1]

#### invmat

# invmat <result>, <input>

Calculates the inverse matrix for <input> and stores the result in <result>. Both matrices must be square with identical dimensions 1 to 4.

#### matmul

# matmul < result >, <a>[, <b>]

A generic name for several calculations. Mainly, of course, the standard matrix multiplications of user defined variables <a> with <b>. Either or both of <a> and <b> may be arbitrary scalar expressions. The result and the input matrices may be 1-D and or 2-D according to the standard rules for matrix multiplications

Thus the command essentially provides the operations:

- 1) Result\_matrix = Scalar 2) Result\_matrix = Scalar \* Scalar 3) Result\_matrix = Scalar \* Matrix = Matrix \* Scalar 4) Result\_matrix = Matrix 5) Result\_matrix = Matrix \* Matrix
- 1) and 2): Each matrix element is set to the scalar value Result[i,j] = scalar 3): Each input matrix element is multiplied by the scalar and each result element corresponds to the input matrix element Result[i,j] = scalar \* Input[i,j] 4): The result matrix is identical to the input matrix Result[i,j] = Input[i,j] 5): Standard matrix multiplication Result[i,j] = A[i,k] \* B[k,j]

For operations 3 and 4, both matrices must be of identical shape and dimension. For operation 5 the standard rule on shape and dimensions holds with Result[i,j] = A[i,k] \* B[k,j]

#### matadd

# matadd <result>, <a>[, <scalar>], <b>

Adds two user supplied matrix variables. Result[i,j] = A[i,j] + Scalar \* B[i,j]

The three matrices have to be of identical shape and dimensions, The scalar is optional and defaults to +1. The result matrix may be the same variable as any of the two input matrices.

#### mattrans

#### mattrans <resul<, <input>

Calculates the transposed matrix for <input> and stores this in <result>

# 4.32 set

#### set <command>,...

This command allows to alter various program independent setting. Allowed values for <command> are:

# prompt

```
set prompt, {"on"|"off"|"redirect"},[{"on"|"off"|"file"}, ["save"]] set prompt, "old"
```

First parameter sets the status of the PROG prompt. The default is "on", i.e. PROG prompts for the next command by writing "discus > " (in case you run DISCUS ..). You can turn this prompt off. This is useful, if you are running a long macro and do not want to get all the prompts written into the output. By using this option you can considerably shorten the output written by PROG into a redirected log file. If you are using PROG on a UNIX platform, you can start the program with redirected input by the command:

```
"prog < inputfile"
```

By default, PROG will write the prompt "discus >" into the output file, expecting a RETURN from the keyboard. Very long lines in the output file will result. To avoid this situation insert the line "set output,redirect" as first line in the inputfile to force discus to echo the lines from file inputfile.

The prompt setting "redirect" has an important side effect on macro treatment. With the "redirect" setting, macros are stored internally, once they have been read from disk, and will be reused from memory. This helps to reduce unnecessary I/O, especially when you have nested macros inside loops. For all other settings, the internal macro storage is cleared when you get back to the normal interactive mode. This allows you to run a macro, then modify the version stored on the disk and execute the modified/corrected version.

This second parameter allows the user to assign where the text output of the program should go: "on" prints on the screen, "off" will result in no output and "file" will save the output to a file progname.log (e.g. discus.log in DISCUS). Note that the output of the commands 'echo' and 'eval' will always appear on the screen. The last parameter allows on to save the current prompt and output settings.

The parameter "old" allows the user to restore the setting of the prompt and output. This can e.g. be used to turn the prompt off in a macro and then restore the original setting after the macro is executed. Make sure that you saveed the desired prompt by setting the last parameter to "save".

#### error

```
set error, {"cont" | "exit" | "live" | "old"} [, "save"]
Sets the error status.
"cont" PROG returns the normal prompt after the display of the error message. You can continue the input of commands.
```

```
The execution of a macro file is stopped, the program continues
       with the regular prompt of the menu/submenu where the error occurred.
"exit" PROG terminates after the display of the error message.
       This option is useful if you run PROG in the batch mode of your
       operating system. Instead of continuing with a faulty calculation
       PROG stops and you can immediately check the error.
"live" PROG remains alive after an error is encountered. The variable
       "res[0]" is set to -1. The error number is written into "res[1]",
       the error type to "res[2]". Further error codes are written into
       "res[31".
       With this error status, the program remains alive within a loop
       as well, which it does not do with the error status "cont".
       The program also continue to execute a macro!
       It is most helpful to catch errors from the 'system' command
       and to allow a flexible response.
"old"
       Restore the last error status that was set and saved in a
       previous 'set error, <value>, save ' command.
```

#### debug

```
set debug, {"on" | "off"}
```

This command allows the user to enable various DEBUG outputs ...

#### wait

```
set wait, {"on" | "off"}
```

This command allows the user to tailor the 'wait' comand. The default is 'set wait, on'. With 'set wait, on' the 'wait' command in a macro is active. With 'set wait, off' the 'wait' command in a macro will be ignored and the programm continues execution as if the 'wait' command were absent.

# 4.33 show

```
show {"res" | "variables"}
```

The show command displays settings onto your screen. The individual programs discus, kuplot, diffev, mixscat all have specific parameters to the show command as well, see the help at the main program level for details.

```
"res"
```

Many commands produce results that are stored in the result variable res[<i>]. Thise are displayed via "show res". The entry res[0] gives the number of entries in the result variable.

```
"variables"
```

Lists the variables that have been defined, their type and their current values. The command is identical to the "variable show" command.

# 4.34 sleep

# sleep < seconds >

This command causes the program to sleep for <seconds> seconds

# 4.35 socket

```
socket "open",<host>,<port>
socket "close"
socket "exit"
socket "send",<string>
socket <string>
socket "transfer",<slave_var>,<expression>
socket "transfer",<slave_var>,<character expression>,<local_var>
```

These commands connect to a program that has been started with the "-remote" option, sees ==> "Options" for further help. The commands will be send to the slave program where they will be executed as typed.

#### open

```
socket "open",<host>,<port>
```

Opens the connection to the program running on host <host> and listening on port <port>. The server program must have been started beforehand with the "-remote" option

#### close

#### socket close

Temporarily closes the connection to the slave program, which keeps running. You can open to the same program with a new socket open,<pname>.

# exit

# socket exit

Terminates the slave program and closes the connection. To communicate with the slave program again, you must first start this with the "-remote" option and then open the connection with socket "open",<pname>.

# send

```
socket send,<string>
socket <string>
```

The string is send to the slave program and executed as typed. Both forms are equivalent.

#### transfer

```
socket transfer,<slave_var>,<expression>
socket transfer,<slave_var>,<character expression>,<local_var>
```

This command transverse the value of <expression> to the slave variable <slave\_var>. You must define this slave variable prior to a transfer.

# Example

```
system /usr/local/bin/kuplot -remote ! starts kuplot slave
socket open,localhost,3331
socket func r[0]**2,-2,2,0.1
socket transfer,i[1],i[0]
socket tit1 "%d".i[1]
                                      ! define a function to plot
                                      ! transfer local variable
                                      ! set plot title
                                       ! display plot
socket plot
socket mark 1,1
                                       ! change marker interval
socket plot
                                      ! plot again
socket send, mark 0.5,0.5
                                      ! change marker interval
socket send, plot
                                      ! plot again
socket exit
                                       ! terminate kuplot, exit
```

# 4.36 stop

#### stop

This command is active only while reading from a macro file or in interactive mode inside a block structure (do-loops and/or if's).

The current macro file is interrupted and you can type commands as in the normal input mode. You can use the whole range of PROG commands, including the '@' macro command. The 'stop' commands provides a convenient mode to debug a macro by setting a break point at which you can check the value of variables or set new values, run an additional macro etc.

To continue execution of the macro or to continue with the normal PROG mode, use the ==> 'continue' command.

If included in a block structure statement (do-loops and/or if's) in both, macro and interactive mode, the program continues reading all statements that belong to the block structure. During execution of the structure, PROG interrupts this execution if it encounters a 'stop' command. You can issue any PROG command except further do or if commands.

To continue execution of the structure or to continue with the normal PROG mode, use the ==> 'continue' command.

# 4.37 system

```
system <com>
system "string%dstring",<integer expression>
system "string%fstring",<float expression>
```

Executes the single shell command <com>. If the command string is enclosed in "", you can place integer and real format specifiers "%d" "%f" which are then substituted by the corresponding values. The shell command <comm> may be placed in front of the double quotation marks.

Example i[0]=10 system "ls %d.\*" system ls "%d.\*" This would list all files called 10.\*

# 4.38 wait

This command waits for user input. Without a parameter or with "return", the program waits for a simple <RETURN>.

If the parameter is "return", you can type "stop" and then press enter/return to stop the execution of the current macro. The program will return to the regular interactive session within the section menu or submenu at the current point of execution.

If the first parameter is "input", the program expects the user to enter one or more real numbers or expressions. The optional cprompt> can be used to ask the user to input the expressions. This is especially helpful if the prompt has been turned of by ==> set prompt,off. The number of expressions entered by the user is stored in the variable res[0] and the results of the expressions in res[i].

This command allows to write interactive macros, demo macros and tutorials.

With the command **set wait**, {**"on"** | **"off"**}

you can toggle the active state of the wait command on off.

The default is 'set wait, on'. With 'set wait, on' the 'wait' command in a macro is active. With 'set wait, off' the 'wait' command in a macro will be ignored and the programm continues execution as if the 'wait' command were absent.

# 4.39 variable

```
variable {"integer"|"real"}, <name> [, <initial_value>] [, dim:[d1,d2]]
variable {"character"}, <name>
variable show
variable reset
variable delete {,"all"| <name>..]
```

The programs that are part of the DIFFUSE suite offer predefined variables i[\*] and r[\*]. These are an integer and a real array, respectively, into whose element you may store appropriate values. In order to enhance readability of a macro, you can define your own variable names by the use of this command. The variable may either be an integer or a real variable. There is no predefined syntax for the variable names. Optionally you can initialize the variable to <initial\_value>, default is zero. These user defined variables may be used just as the system integer and real variables i[\*] and r[\*]. Character variables may be used to hold a string of text. The variable names may only consist of alphanumerical characters including the underscore "\_". "Real" and "Integer" variables my optionally be declared as one or two dimensional arrays. Specify the dimension as: dim:[12] for a 1-D array of length 12 dim:[3,3] for a 2-D array of

length 3x3 Array indices start at 1. Presently character variables are single value variables. Several commands exist for matrix algrbra. See the help entry ==> 'matrix' for a summary of these commands.

Several system variable exist that are read only. Several of these refer to the refinement section DIFFEV. These variables all start with "REF\_". See the DIFFEV on-line help and manual for further details.

If the first command parameter is "show" the program displays a list of user defined variables and their current values. Refer to the help entry "expressions" for further help.

Both, the "reset" and the "delete, all" parameters specify that the variable list is to be cleared of all user defeined variables. Only the system variables remain.

Alternatively, the "delete, <name>" parameters allow you to delete an individual variable. Examples:

```
variable int, alpha, 90
variable int, beta
variable real, diff
beta = 94
diff = alpha - beta
eval diff
variable real, vector, dim:[3]
vector[2] = 3.1415
evaluate vector[3]
variable real, array, dim:[4,10]
array[4,5] = 3.1415
evaluate array[1,8]
variable character, string
variable character, line
string = "abcdefg"
     = "%3c", string(2:4)
line
var show
```

Variable names that are part of intrinsic functions, keywords like "do", "elseif", "eq", and program specific variables like "r" and "i" are not allowed. Thus a variable called "a" is illegal, since it is part of the intrinsic function "asin".

Internally the program sorts the variable names by length and in inverse alphabetical order. This sorting has no serious consequence for the user other than finding the variable in the printed list when using the 'variable show' command.

A few predefined variables exist, their names are capitalized: PI 3.1415... REF\_GENERATION Current generation number as set by DIFFEV REF\_MEMBER Current population size as set by DIFFEV REF\_CHILDREN Current child population size as set by DIFFEV REF\_DIMENSION Current Number of parameters a set by DIFFEV If the value is changed, you can store more values in ref\_para[], but this does NOT change the actual dimension pop\_dimx that DIFFEV uses. PROGRAM Tells you in which section you are possible values are SUITE=0, DISCUS=1, DIFFEV=2, KUPLOT=3 STATE Tells you whether this is the TOP=0 level, a SECTION=1 or a BRANCH=2. MPI Was the program started with MPI ? MPI\_ON=1, MPI\_OFF=0 MPI\_FIRST Is this the first call to DIFFEVs ==> 'run\_mpi' command with the current GENERATION? FALSE=0 TRUE=1

#### 4.40 errors

The program has been written such that it should handle almost any typing error when giving commands and hopefully all errors that result from calculation with erroneous data. When an error is found an error message is displayed that should get you back on track. See the manual for a complete list of error messages. In this part we refer to the program you are using as DISCUS for convenience.

The error messages concerning the use of the command language are grouped in the following categories:

```
COMM Command language errors
FORT Fortran interpreter errors
I/O Errors regarding input/output
MACR Errors related to macros
MATH General mathematical errors
```

Each error message is displayed together with the corresponding category <ccc> and the error number <numb> in the form:

In the default mode DISCUS returns the standard prompt and you can continue the execution from this point. You can set the error status to "exit" by the ==>'set' command. In this case DISCUS terminates if an error is detected. This option is useful to terminate a faulty sequence of commands when running DISCUS in the batch mode of your operating system.

#### comm

Command language errors These messages describe illegal usage of the command language, such as unknown commands, improper numbers of parameters.

#### Error -1: DISCUS directory not defined

The environment variable DISCUS\_DIR was not defined. Check the chapter on installation for your platform for the appropriate definition.

#### Error -2: Command parameter has zero length

On the command line you probably have a typing error like two comma following each other without significant values in between, or the first non blank character after the command is a comma.

#### Error -3: Could not allocate arrays

The program has to allocate arrays, but received a error message. Does your computer have enough available memory space?

# Error -5: Error in operating system command

The operating system/shell returned an error message. Check the appropriate system manuals for details.

# Error -6: Missing or wrong parameters for command

Either the command needs more parameters than were provided, or the parameters are incorrect. Check the number and type of parameters. Is the sequence of numerical and character parameters correct?

#### Error -8: Unknown command

The command interpreter read an unknown command. Check the spelling of the command or check, whether this command is allowed at the current sublevel.

#### Error -11: Error in subroutine

More or less a system error message, ignore this message.

#### Error -17: Too many parameters

More parameters have been provided than are required by the command. Check the number, and type of parameters supplied, or the occurrence of additional ','.

# fort

Fortran interpreter errors These messages describe erroneous mathematical calculations and improper usage of control structures (do,if, ...).

# Error -1: Nonnumerical Parameters in expression

The interpreter found a nonnumerical string where a number is expected. If an intrinsic function or a variable was intended, check for spelling or missing parentheses.

#### Error -2: Unknown Variable

The expression contains a reference to an unknown variable. Check the spelling of the variable. Chapter 3.7.1 of the manual and the help entry "variables" contains a list of allowed variables. Check whether the variable is a read-only variable and was used on the left side of an expression. Some of the variables associated with microdomains are read-only depending of the circumstances!

#### Error -3: Unknown intrinsic function

The expression contains a reference to an unknown intrinsic function. Check the spelling of the function. Chapter 3.7.4 of the general part in the manual and the help entry "functions' contain a complete list of the allowed intrinsic functions.

# Error -4: Division by zero'

An attempt was made to divide by zero. Check the value of the argument and correct the algorithm that calculates the argument.

# Error -5: Square root of negative number

An attempt was made to calculate the square root of a negative argument. Check the value of the argument and correct the algorithm that calculates the argument.

# Error -6: Missing or wrong Parameters for command

Either the function or variable referenced needs more parameters than were provided, or the parameters are incorrect. Check the number and type of parameters. Is the sequence of numerical and character parameters correct?

# Error -7: Argument for asin, acos greater 1

An attempt was made to calculate asin or acos with an argument greater than 1. Check the value of the argument and correct the algorithm that calculates the argument.

# Error -8: Index outside array limits

The index supplied for the variable is outside the limits of this variable. Check the general part for the dimensions of the variables.

#### Error -9: Number of brackets is not matching

The number of opening and closing brackets "[" and "]" does not match or is illegally nested with parentheses "(", ")" or other operators. Check the string used in the expression and correct it following the FORTRAN rules.

# Error -10: Index for array element is missing

You have used a string like "i[]", where the opening and closing brackets do not contain any expression. Check the string used in the expression and correct it following the FORTRAN rules.

# Error -11: Number of parentheses is not matching

The number of opening and closing parentheses "(" and ")" does not match or is illegally nested with brackets "[", "]" or other operators. Check the string used in the expression and correct it following the FORTRAN rules.

# Error -12: Expression between () is missing

You have used a string like "()", where the opening and closing parentheses "(" and ")" do not contain any expression. Check the string used in the expression and correct it following the FORTRAN rules.

# Error -13: Wrong number of indices for array

The number of indices given for the entered parameter is wrong. Check the help entry 'variables' for the proper number of indices.

# Error -14: Index of DO-loop counter is missing

Here the index for the loop counter of a do-loop is missing. Check the online help for the correct syntax of such loops.

# **Error -15: Too many commands**

The program stores all commands within a control block in an array. The maximum number of commands that can be stored in this array is given by the parameter MAXCOM in file "doloop.inc". The macro or run used more commands than currently allowed by this parameter. Rewrite the macro or list of commands such that less commands are sufficient, or change the value of the parameter and recompile the program.

#### Error -16: Too deeply leveled (do,if) construction

The program stores all commands within a control block in an array. The maximum number of levels for this array is given by the parameter MAXLEV in file "doloop.inc". The macro or run used more levels than currently allowed by this parameter. Rewrite the macro or list of commands such that less levels are sufficient, or change the value of the parameter and recompile the program.

#### Error -18: Unresolvable condition

An error occurred while trying to calculate the value of an arithmetic or logical expression. Check that there is no illegal operation /(division by zero .../ no typing errors, all parentheses are properly matched.

# Error -19: Illegal nesting of control commands

Do loops and/or if constructions have been nested with overlapping segments, missing enddo or endif statements or similar causes. Check for spelling errors on the control statements, and that each control statement is properly terminated by a corresponding enddo or endif statement that is not enclosed within another control block.

# Error -20: Illegal argument for ln(x) function

The argument for the ln must be positive, larger than zero. Check the value of the argument or the value of the expression that serves as argument

# Error -21: Missing 'while comparing stings

An expression of the form ('string' .eq. 'line') was used, where one of the quotation marks has been omitted. Check the respective line.

# Error -22: Maximum number of real variables defined

DISCUS can define a fixed number of user variable names. The maximum number allowed for your installation id displayed by the command variable show If you would like more user definable variable names, change the value of the parameter VAR\_REAL\_MAX in "config.inc"

# Error -23: Maximum number of int. variables defined

DISCUS can define a fixed number of user variable names. The maximum number allowed for your installation id displayed by the command variable show If you would like more user definable variable names, change the value of the parameter VAR\_INTE\_MAX in "config.inc"

#### Error -24: Variable is not defined

You tried to use a name within an expression that was not recognized as a user defined variable name. Check the spelling of the line. Was an intrinsic function to be used, or was the variable not defined? See the ==> 'variable' entry in the help menu regarding the definition of variables. You will also get this error message if you tried to define a variable using the command: variable real,dummy=3 The equal sign "=" may not be used as part of a variable name. If you intend to provide an initializing value, use the command as: variable real,dummy,3

# Error -25: Variable name contains illegal characters

You tried to define a variable name that contains characters other than letters, numbers or the underscore "\_". The variable names are restricted to alphanumerical characters and the underscore "\_".

#### Error -26: Variable name contains illegal characters

Variable names may consist only of letters (lower and upper case), numbers and the underscore "\_". Check the spelling of the variable you tried to define with respect to these rules.

#### Error -27: Function with wrong number of arguments

You called an intrinsic function with the wrong number of arguments. Check the listing of intrinsic functions for the valid number of arguments and the compare to the input line you had typed.

# Error -28: Too deeply leveled break command

Illegal use of the break command. The parameter on the break command signals how many block structure levels are to be exited. Check the value of this parameter with regard to the nesting of do-loops and if-blocks.

# Error -29: Character substring out of bounds', & !-29! fortran

In a statement like variable character, line line = 'abcde' echo "%c",line(1,5) The first index is less than one, or the second index is larger than the number of characters in the strin, or the second index is less than the first.

# Error -30: Right quotation mark missing in format'

A statement like echo "text" is missing the right quotation mark.

# Error -31: Incomplete (do,if) statement

Some part of a ==> 'do' or ==> 'if' statement is missing. Check the line for missing part or typing errors.

# Error -32: Variable name is already defined

The variable that you want to define is already in use as another data type.

#### Error -33: Variable in use; cannot initialize value

A variable name can be redifined as identical data type, in order to be able to use a macro with a variable definition inside a loop. You may, however, not provide an initialisation value, as this would override the current value.

# Error -34: String has length zero', & !-34! fortran

A statement like echo "" or line = " occured in which the single or doluble quotation marks enclose a zero length string.

# i/o

Errors related to input / output An error occurred while attempting to read/write from a file

#### Error -1: File does not exist

DISCUS could not find the file. Check the spelling and the path.

# Error -2: Error opening file

DISCUS could not open a file. The file might be in use by another process.

# Error -3: Error reading file

An error occurred while DISCUS was reading a file. Check whether the contents of the file is correct.

# Error -4: File already exists

An attempt was made to overwrite an existing file. Rename or delete the file in question.

# Error -5: No such entry in online help

You have tried to obtain help for a string that does not have a matching entry in the help file. Check the spelling of the string. Are you at the right sublevel? Use the '?' command to get a listing of available help entries.

#### Error -6: Unexpected end of file

DISCUS has encountered the end of a file, but is still expecting data. Check the file(s) involved, to see whether the data are complete or whether erroneous data are present.

# Error -7: Learning sequence already in progress

You have tried to start a learning sequence by ==>'learn' without closing the active learning sequence. Close the current learning sequence by ==> 'lend' before starting to record a new macro.

#### Error -8: Nothing learned - no macro written

You did not type any commands since the ==>'learn' command. No commands are written to the macro file. You need to give at least one command before closing a learn sequence.

#### Error -9: Error reading user input

An error occurred while reading the last input. Does the string contain any characters where a number is expected, or any control or escape sequences.

# Error -10: IO stream already open

The command 'fopen' was issued while there was already a file open. Close the currently open file with 'fclose'.

# Error -11: No IO stream open to close

The command 'fclose' was issued, but there is no open file.

# Error -12: Error writing to file

An error occurred when reading a file with 'fget'. Check the file for nonnumerical values and check that the number of columns is equal or larger than the number of arguments of 'fget'.

# Error -13: I/O stream number outside valid range

The I/O stream number must be larger than 0 and less than the value defined in macro.inc, which usually is 10.

# Error -14: Filename has zero length

You tried to open a file with ==> 'fopen', whose file name is of length zero. Check the statement for the missing filename, or an additional comma.

#### Error -15: No socket connected

Apparently you tried to use a ==> 'socket' command prior to opening a connection to the remote computer. Use a 'socket open' command first.

#### Error -16: Could not resolve hostname for socket

The hostname to which you want to connect could not be resolved into an IP address. Check the host name for typing errors and the Internet access of your computer.

# Error -17: Could not grab socket

Internal socket debug message.

# Error -18: Could not open socket connection

Internal socket debug message.

# Error -19: Problem sending to socket

Internal socket debug message.

# Error -20: Problem receiving from socket

Internal socket debug message.

# Error -21: Received null string from socket receive

The remote computer send back an answer of zero length. Apparently the connection was terminated prematurely.

Try to connect again.

# Error -22: Socket accept problem

Internal socket debug message.

#### Error -23: Scocket: Rejected connection

Internal socket debug message.

# Error -24: Socket bind problem

Internal socket debug message.

#### Error -25: Socket listen problem

Internal socket debug message.

# Error -26: Second parameter must be >= first Param.

You tried to read a substring with a line like echo "%c",line(1:5) but the second parameter , here a "5" was less than the first, here a "1". The second parameter must be equal to or larger than the first in order to specify a valid substring.

#### macro

Errors related to macro These messages describe situations that result from missing macrofiles, missing macro parameters ...

# Error -1: Too many macro parameters given

The number of parameters given on the macro command line is higher than allowed in your installation. The maximum number of parameters allowed is defined by the parameter MAC\_MAX\_PARA in the file macro.inc. Check the macro command line for any additional "," or rewrite the macro to use less parameters. If necessary adjust the value of the parameter MAC\_MAX\_PARA and recompile the program.

#### Error -12: Macro not found

The file given on the @<name> command does not exist. Check the spelling of <name> and the path.

# Error -13: Macro filename is missing on the command line

The command '@' to execute a macro was called without any macro file name. The file name must start immediately after the "@". Check the '@' command for completeness and blanks after the "@".

#### Error -35: Too deeply leveled macros

The maximum level at which macros may be nested is defined in the file macro.inc in the parameter MAC\_MAX\_LEVEL. Check the nesting of macro file for the level of nesting or possible recursive nesting without proper termination. Rewrite the macros to use less nesting, or change the value of the parameter and recompile the program.

## Error -36: Unexpected EOF in macro file

When DISCUS finds a '@' command inside a macro, it stores the current macro name, the line number inside the current macro and closes the current macro file. After completion of the new macro, the previous macro is read again up to the position stored. The error message is displayed when an end of file is found before the position is reached. Check whether the macro file was damaged, or accidentally deleted during execution of the nested macro.

# Error -41: Not enough macro parameters given

DISCUS read a parameter number inside a macro file that is higher than the number of parameters given on the command line of the macro. Check the parameters inside the macro for correct numbering and spelling. Check the number of parameters supplied on the command and check whether any "," is missing between parameters.