
Kelas D

Jarkom Modul 8

Kegiatan 1. Konfigurasi Access List

 Membuat topologi jaringan dengan menggunakan dua router seri 1841, dua switch seri 2950-24, dan 4 buah PC yang terbagi dalam dua switch tersebut seperti pada gambar di bawah ini.



- Berikan alamat IP pada kedua switch.
 - Switch 1

```
Switch1>en
Switch1$conf term
Enter configuration commands, one per line. End with CNTL/Z.
Switch1(config) $int vlan 1
Switch1(config-if) $ip address 192.160.110.250 255.255.255.0
Switch1(config-if) $no shut

Switch1(config-if) $
$LINK-5-CHANGED: Interface Vlan1, changed state to up

$LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, changed state to up

Switch1(config-if) $ex
```

- Switch 2


```
Switch2*en
Switch2#conf term
Enter configuration commands, one per line. End with CNTL/2.
Switch2(config) #int vlan 1
Switch2(config-if) #ip address 192.168.120.250 255.255.255.0
Switch2(config-if) #no shut

Switch2(config-if) #
*LINK-5-CHANGED: Interface Vlan1, changed state to up

*LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, changed state to up

Switch2(config-if) #ex
Switch2(config-if) #ex
```

3. Berikan alamat IP, subnet mask, dan default gateway pada masing-masing PC.



4. Lakukan routing untuk kedua jaringan tersebut.

- Router 1

```
Routerl>enable
Routerlf
Routerl#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router1(config) #interface FastEthernet0/1
Router1(config-if) #no shutdown
Router1(config-if)#
%LINK-S-CHANGED: Interface FastEthernet0/1, changed state to up
ip address 192.168.10.1 255.255.255.0
Router1(config-if) #ip address 192.168.10.1 255.255.255.0
Router1(config-if)#
Routerl (config-if) fexit
Router1(config) #interface FastEthernet0/0
Routerl(config-if) #no shutdown
Routerl (config-if) #
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up
ip address 192.168.110.254 255.255.255.0
Routerl(config-if) #ip address 192,168,110.254 255,255,255.0
Routerl (config-if) #
*LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1.
changed state to up
Router1>en
Router1#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Routerl(config) #router rip
Router1 (config-router) #network 192,168,110.0
Routerl(config-router) #network 192.168.10.0
Routerl(config-router) #~2
Routerls
*SYS-6-CONFIG_I: Configured from console by console
```

- Router 2

```
Router2>enable
Router2#
Router2#configure terminal
Enter configuration commands, one per line. End with CNTL/2.
Router2(config) #interface FastEthernet0/0
Router2(config-if)#
Router2(config-if) #exit
Router2(config) #interface FastEthernet0/1
Router2(config-if) #no shutdown
Router2(config-if)#
$LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up
*LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1,
changed state to up
ip address 192.168.10.2 255.255.255.0
Router2(config-if) #ip address 192.168.10.2 255.255.255.0
Router2 (config-if) #
Router2 (config-if) #exit
Router2(config) #interface FastEthernet0/0
Router2(config-if) #no shutdown
Router2 (config-if) #
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
Router2>en
Router2#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router2 (config) #router rip
Router2(config-router) #network 192.168.120.0
Router2(config-router) #network 192.168.10.0
Router2(config-router) $^2
Router2#
*SYS-5-CONFIG I: Configured from console by console
```

Lakukan pengecekan tabel routing pada kedua router.

Router 1

```
Routerl#sh ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B -
BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS
inter area

* - candidate default, U - per-user static route, o - ODR
D - periodic downloaded static route

Gateway of last resort is not set

C 192.168.10.0/24 is directly connected, FastEthernet0/1
C 192.168.110.0/24 is directly connected, FastEthernet0/0
R 192.168.120.0/24 [120/1] via 192.168.10.2, 00:00:17,
FastEthernet0/1

Router1#
```

Router 2

```
Router2#sh ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2 E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area

* - candidate default, U - per-user static route, O - ODR P - periodic downloaded static route

Gateway of last resort is not set

C    192.168.10.0/24 is directly connected, FastEthernet0/1 R    192.168.110.0/24 (120/1) via 192.168.10.1, 00:00:14, FastEthernet0/1 C    192.168.120.0/24 is directly connected, FastEthernet0/0
```

Tes koneksi dari PC 1 ke PC 4

```
C:\>ping 192.168.120.4

Pinging 192.168.120.4 with 32 bytes of data:

Reply from 192.168.120.4: bytes=32 time<1ms TTL=126

Reply from 192.168.120.4: bytes=32 time=3ms TTL=126

Reply from 192.168.120.4: bytes=32 time=13ms TTL=126

Reply from 192.168.120.4: bytes=32 time=2ms TTL=126

Ping statistics for 192.168.120.4:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 13ms, Average = 4ms</pre>
```

7. Menerapkan access list pada router.

```
Routerl#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Routerl(config)#access-list 10 permit 192.168.120.0 0.0.255.255
Routerl(config)#end
Routerl#
%SYS-5-CONFIG_I: Configured from console by console
```

 Menerapkan access list ke interface router yang mengarah ke dalam jaringan 192.168.110.0 (int fa0/0)

```
Routerl$conf term
Enter configuration commands, one per line. End with CNTL/Z.
Routerl(config)$int fa 0/0
Routerl(config-if)$ip access-group 10 out
Routerl(config-if)$^Z
Routerl$
$SYS-5-CONFIG_I: Configured from console by console
Routerl$
```

9. Kemudian lihat access list pada router.

```
Routerl#sh access-lists
Standard IP access list 10
10 permit 192.168.0.0 0.0.255.255
```

Routerl#

Show running-config pada router.

```
Routerl#sh running-config
Building configuration...
                                                             interface FastEthernet0/0
                                                              ip address 192.168.110.254 255.255.255.0
                                                              ip access-group 10 out
Current configuration : 718 bytes
                                                              duplex auto
                                                              speed auto
no service timestamps log datetime msec
                                                             interface FastEthernet0/1
                                                              ip address 192.168.10.1 255.255.255.0
no service timestamps debug datetime msec
no service password-encryption
                                                              duplex auto
                                                              speed auto
hostname Routerl
                                                             interface Vlani
                                                              no ip address
                                                               shutdown
                                                             router rip
network 192.160.10.0
                                                              network 192.168.110.0
ip cef
                                                             ip classless
no ipv€ cef
                                                             ip flow-export version 9
                                                             access-list 10 permit 192.168.0.0 0.0.255.255
                                                             line con 0
spanning-tree mode pvst
                                                             line aux 0
                                                             line uty 0 4
                                                              login
interface FastEthernet0/0
                                                             end
```

11. Lakukan tes koneksi antara PC 3 dengan PC 1.

```
C:\>pinging 192.168.110.3 with 32 bytes of data:

Reply from 192.168.110.3: bytes=32 time=lms TTL=126

Reply from 192.168.110.3: bytes=32 time=10ms TTL=126

Reply from 192.168.110.3: bytes=32 time=12ms TTL=126

Reply from 192.168.110.3: bytes=32 time=10ms TTL=126

Ping statistics for 192.168.110.3:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Reproximate round trip times in milli-seconds:

Minimum = lms, Maximum = 12ms, Average = 8ms

C:\>
```

12.Berikan akses hanya pada satu host (PC 4).

```
Router1>en
Router1$conf term
Enter configuration commands, one per line. End with CNTL/2.
Router1(config)$sccess-list 20 permit 192.168.120.4 0.0.0.0
Router1(config)$^2
Router1$
%SYS-5-CONFIG_I: Configured from console by console
```

Routerls

Kemudian terapkan access list 20 tersebut pada interface Ethernet pada Router.

```
Routerigonf term
Enter configuration commands, one per line. End with CNTL/Z.
Routeri (config) sint fa 0/0
Routeri (config-if) sip access-group 20 out
Routeri (config-if) s-2
Routeris
%SYS-5-CONFIG_I: Configured from console by console
Routeris
Show access-lists
Routerish access-lists
Standard IP access list 10
10 permit 192.168.0.0 0.0.255.255 (4 match(es))
Standard IP access list 20
10 permit host 192.169.120.4
```

Routerls

Lakukan tes koneksi dari PC 3 ke PC 1 dan PC 2.

```
Cityping 192.160.110.8 with 92 bytes of data:

Deply from 192.160.10.1: Destination bost unreachable.

Reply from 192.160.10.1: Destination bost unreachable.

Reply from 192.160.10.1: Destination bost unreachable.

Ping statistics for 192.160.10.2: Destination bost unreachable.

Ping statistics for 192.160.110.3:

Fackets: Sent = 4, Deceived = 0, Lost = 4 (100% loss),

Cityping 192.160.110.4

Pinging 192.160.110.4 with 92 bytes of data:

Reply from 192.160.10.1: Destination bost unreachable.

Ping statistics for 192.160.10.1: Destination bost unreachable.

Ping statistics for 192.160.10.1: Destination bost unreachable.
```

15.Lakukan tes koneksi dari PC 4 ke PC 1 dan PC 2

Kegiatan 2. Konfigurasi Extended Access List

Konfigurasi extended access-list

```
Router1#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router1(config)#access-list 100 permit tcp 192.168.120.0 0.0.0.255
192.168.110.3 0.0.0.0 eq telnet
Router1(config)#^Z
Router1#
%SYS-5-CONFIG_I: Configured from console by console
Router1#
```

Menerapkan access list tersebut ke interface router

```
Routerl#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Routerl(config)#int fa 0/1
Routerl(config-if)#ip access-group 100 in
Routerl(config-if)#^Z
Routerl#
%SYS-5-CONFIG_I: Configured from console by console
Routerl#
```