# **SIPPI**

Ed. version 1.0

# **Contents**

1	Inst	allatio	n				1
	1.1	Install	SIPPI .				1
		1.1.1	SGeMS	(optional)	)		1
	1.2	Install	develop	ment vers	sion of SIPPI from github		1
2	Setl	ting up	SIPPI				2
	2.1	prior	The a pr	iori mode	el		2
		2.1.1 Types of a priori models					3
			2.1.1.1	Uniform	distribution		3
			2.1.1.2	1D Gene	eralized Gaussian		3
			2.1.1.3	FFTMA -	- 3D Gaussian model		4
			2.1.1.4	FFTMA -	- 3D Gaussian model wuth variable model properties		6
			2.1.1.5	VISIM .			6
			2.1.1.6	CHOLES	SKY - 3D Gaussian model		7
			2.1.1.7	3D Pluri	Gaussian		8
			2.1.1.8	SNESIM			8
			2	.1.1.8.1	Custom training image		9
			2	.1.1.8.2	Complete customization		9
		2.1.2	Samplin	g the pric	or		10
		2.1.3	Sequent	tial Gibbs	sampling / Conditional Re-sampling		10
			2.1.3.1	Controll	ling sequential Gibbs sampling / Conditional Re-sampling		10
	2.2	data:	Data and	data unce	ertainties/noise		11
		2.2.1	Gaussia	n measure	ement noise		11
			2.2.1.1	Uncorre	elated Gaussian measurement noise		11
			2.2.1.2	Correlat	ted Gaussian measurement noise		12
		2.2.2	Gaussia	n modelir	ng error	. <b></b>	12
	2.3	forwa	rd: The fo	orward mo	odel		12
	2.4	Validating prior, data, and forward					

3	Sam	ıpling t	he a pos	teriori distribution	14		
	3.1	The re	ejection s	ampler	14		
	3.2	The ex	ktended I	Metropolis sampler	15		
		3.2.1	Control	ling the step length	15		
		3.2.2	The inde	ependent extended Metropolis sampler	16		
		3.2.3	Anneali	ng schedule	16		
		3.2.4	Parallel	tempering	16		
	3.3	Simul	ated Ann	ealing	17		
4	Exa	mples			18		
	4.1	Examp	oles of A	priori models	18		
		4.1.1	Multiple	e 1D Gaussian prior model	18		
		4.1.2	Multiva	riate Gaussian prior with unknown covariance model properties	19		
	4.2	Polyn	omial line	fitting	21		
		4.2.1	The for	ward problem	21		
		4.2.2	Referen	ce data, data, forward	21		
		4.2.3	The pric	or model	22		
		4.2.4	Setup a	nd run the Metropolis sampler	23		
		4.2.5	Setup a	nd run the rejection sampler	24		
	4.3	Cross	hole tom	ography	24		
		4.3.1	Referen	ce data set from Arrenæs	24		
		4.3.2	Travel d	elay computation: The forward problem	26		
			4.3.2.1	Ray type forward model (high frequency approximation)	26		
			4.3.2.2	Fat Ray type forward model (finite frequency approximation)	27		
			4.3.2.3	Born type forward model (finite frequency approximation)	27		
			4.3.2.4	The eikonal equation (high frequency approximation)	27		
		4.3.3 AM13 Gaussian: Inversion of cross hole GPR data from Arrenaes data with a Gaussian to priori model					
			4.3.3.1	Setting up the data structure	28		
			4.3.3.2	Setting up the prior model	28		
			4.3.3.3	Setting up the forward structure	28		
			4.3.3.4	Testing the setup	29		
			4.3.3.5	Sampling the a posterior distribution using the extended Metropolis algorithm	30		
			4	.3.3.5.1 Posterior statistics	30		
		4.3.4	AM13 G	aussian, accounting for modeling errors	31		
		4.3.5	AM13 G	aussian with bimodal velocity distribution	32		
		4.3.6	AM13 G	aussian with unknown Gaussian model parameters	34		
	4.4	Probil	istic cova	riance/semivariogram indeference	36		
		4.4.1	Specific	ation of covariance model parameters	36		
		4.4.2	Inferrin	g a 2D covariance model from the Jura data set - Example of point support	37		
			4.4.2.1	Load the Jura data	37		
			4.4.2.2	Setting up SIPPI for covariance parameter inference	38		

SIPPI iv

5	Bibl	ıograpi	ny	41
6	Refe	erence		42
	6.1	SIPPI		42
		6.1.1	sippi_adjust_step_size	42
		6.1.2	sippi_anneal_temperature	42
		6.1.3	sippi_compute_acceptance_rate	43
		6.1.4	sippi_compute_modelization_forward_error	43
		6.1.5	sippi_forward	43
		6.1.6	sippi_get_resim_data	43
		6.1.7	sippi_get_sample	44
		6.1.8	sippi_least_squares	44
		6.1.9	sippi_likelihood	44
		6.1.10	sippi_mcmc_init	45
		6.1.11	sippi_metropolis	45
		6.1.12	sippi_prior	46
		6.1.13	sippi_prior_cholesky	48
		6.1.14	sippi_prior_dsim	49
		6.1.15	sippi_prior_init	49
		6.1.16	sippi_prior_mps	50
		6.1.17	sippi_prior_plurigaussian	50
		6.1.18	sippi_prior_set_steplength	51
		6.1.19	sippi_prior_sisim	51
		6.1.20	sippi_prior_snesim	51
		6.1.21	sippi_prior_snesim_std	53
		6.1.22	sippi_prior_uniform	54
		6.1.23	sippi_prior_visim	54
		6.1.24	sippi_prior_voronoi	55
		6.1.25	sippi_rejection	56
		6.1.26	sippi_set_path	56
	6.2	SIPPI	olotting commands	56
		6.2.1	sippi_colormap	56
		6.2.2	sippi_get_posterior_data	57
		6.2.3	sippi_plot_current_model	57
		6.2.4	sippi_plot_data	57
		6.2.5	sippi_plot_defaults	57
		6.2.6	sippi_plot_loglikelihood	58
		6.2.7	sippi_plot_model	58
		6.2.8	sippi_plot_movie	58

	6.2.9	sippi_plot_posterior	59
	6.2.10	sippi_plot_posterior_2d_marg	59
	6.2.11	sippi_plot_posterior_data	59
	6.2.12	sippi_plot_posterior_loglikelihood	59
	6.2.13	sippi_plot_posterior_sample	60
	6.2.14	sippi_plot_prior	60
	6.2.15	sippi_plot_prior_sample	60
	6.2.16	sippi_plot_set_axis	60
	6.2.17	wiggle	60
6.3	SIPPI t	oolbox: Traveltime tomography	61
	6.3.1	calc_Cd	61
	6.3.2	eikonal	62
	6.3.3	eikonal_raylength	62
	6.3.4	eikonal_traveltime	62
	6.3.5	kernel_buursink_2d	63
	6.3.6	kernel_finite_2d	63
	6.3.7	kernel_fresnel_2d	63
	6.3.8	kernel_fresnel_monochrome_2d	64
	6.3.9	kernel_multiple	64
	6.3.10	kernel_slowness_to_velocity	65
	6.3.11	mspectrum	65
	6.3.12	munk_fresnel_2d	65
	6.3.13	munk_fresnel_3d	65
	6.3.14	sippi_forward_traveltime	66
	6.3.15	tomography_kernel	66
6.4	SIPPI t	oolbox: Covariance inference	66
	6.4.1	sippi_forward_covariance_inference	66

SIPPI vi

# **List of Figures**

4.1	Location of boreholes AM1, AM2, AM3, and AM4 at Arrenæs	25
4.2	Ray coverage between wells left) AM1-AM3, middle) AM2-AM4, right) AM1-4	25
4.3	AM13: One sample (15 realizations) of the prior (Gaussian) model	29
4.4	AM13: Data response from one realization of the prior.	30
4.5	5 realizations from a FFTMA prior model type with top) Gaussian and b) Bimodal distribution	33
4.6	Distribution of one realization using a Gaussian Bimodal target distribution	33
4.7	A sample from a FFTMA type prior model with varying range_1, range_2, and ang_1	35
<b>4</b> 8	Distribution of one sample of a 1D Gaussian distribution describing range 1 range 2 and and 1	36

SIPPI vii

## **About**

SIPPI is a Matlab toolbox (compatible with GNU Octave) that allows Sampling the solution of non-linear Inverse Problems with realistic a Priori Information.

In order to make use of SIPPI one has to

- Install and setup SIPPI
- Define the prior model, in form of the prior data structure
- Define the forward model, in form of the forward data structure, and the sippi\_forward.m m-file
- Define the data and noise model, in form of the prior data structure
- Choose a method for sampling the a posteriori probability density (i.e., solution) of the inverse problem.

Details about the implementation and the methods implemented in SIPPI can be found in [HCM12], [CHM12], [HCLM13a], [HCLM13b] and, [HCM14].

This version of the documentation was compiled on Feb 02, 2016, and refer to SIPPI version 1.3.

SIPPI 1 / 67

## Chapter 1

## **Installation**

### 1.1 Install SIPPI

Download the latest version of SIPPI from http://sippi.sourceforge.net.

Unpack ZIPPI.zip somewhere, for example to 'c:\Users\tmh\SIPPI'. Then setup the Matlab path to point to the appropriate SIPPI directories by typing:

```
addpath c:\Users\tmh\SIPPI
sippi_set_path
```

### 1.1.1 SGeMS (optional)

To make use of the SISIM and SNESIM type prior models, SGeMS needs to be available.

Currently only SGeMS version 2.1 (download) for Windows is supported by SIPPI.

### 1.2 Install development version of SIPPI from github

If you want to test out the current development version of SIPPI (less stable and documented) then you can get the code using git. SIPPI makes heave use of the mGstat toolbox which you will also need:

```
git clone --recursive https://github.com/cultpenguin/sippi.git SIPPI
```

Then add a path to both SIPPI and mGstat in Matlab using

```
>> addpath INSTALL_DIR/SIPPI
>> sippi_set_path
```

SIPPI 2 / 67

## Chapter 2

# Setting up SIPPI

tomography example This section contains information about how to use and control SIPPI, which requires one to

- Define the prior model, in form of the prior data structure
- Define the forward model, in form of the forward data structure, and the sippi\_forward.m m-file
- Define the data and noise model, in form of the prior data structure

[For examples of how to apply SIPPI for different problems, see the section with examples].

### 2.1 prior: The a priori model

A priori information is defined by the prior Matlab structure. Any number of different types of a priori models can be defined. For example a 1D uniform prior can be defined in prior{1}, and 2D Gaussian prior can be defined in prior{2}.

Once a prior data structure has been defined (see examples below), a realization from the prior model can be generated using

```
m=sippi_prior(prior);
```

The realization from the prior can be visualized using

```
sippi_plot_prior(prior,m);
```

A sample (many realizations) from the prior can be visualized using

```
m=sippi_plot_prior_sample(prior);
```

All a priori model types in SIPPI allow to generate a new model in the vicinity of a current model using

```
[m_new,prior]=sippi_prior(prior,m);
```

in such a way that the prior model will be sampled if the process is repeated (see Sequential Gibbs Sampling).

SIPPI 3 / 67

### 2.1.1 Types of a priori models

Six types of a priori models are available, and can be selected by setting the type in the prior structure using e.q. prior{1}.type='gaussian'.

The UNIFORM type prior specifies an uncorrelated ND uniform model.

The GAUSSIAN type prior specifies a 1D generalized Gaussian model.

The FFTMA type prior specifies a 1D-3D Gaussian type a priori model based on the FFT Moving Average method, which is very efficient for unconditional sampling, and for defining a prior Gaussian model with variable/uncertain mean, variance, ranges, and rotation.

The CHOLESKY type prior specifies a 1D-3D Gaussian type a priori model based on Cholesky decomposition of the covariance model,

The VISIM type prior model specifies 1D-3D Gaussian models, utilizing both sequential Gaussian simulation (SGSIM) and direct sequential simulation (DSSIM) that can be conditioned to data of both point- and volume support and linear average data.

The PLURIGAUSSIAN type prior model specifies 1D-3D pluriGaussian. It is a type if truncated Gaussian model that can be used for efficient simulation of categorical values.

The SNESIM type prior model specifies a 1D-3D multiple-point-based statistical prior model, which relies on training images from where the conditional dependencies of the spatial variables are obtained (i.e., learned). This type of prior model requires SGEMS to be installed.

The following section documents the properties of each type of prior model.

Examples of using different types of prior models or combining prior models can be found in the examples section.

#### 2.1.1.1 Uniform distribution

A uniform prior model can be specified using the 'uniform' type prior model

```
prior{1}.type='uniform';
```

The only parameters needed are the minimum (min) and maximum (max) values. A 1D uniform distribution between -1 and 1 can be specified as

```
prior{1}.type='uniform';
prior{1}.min=-1;
prior{1}.max=1;
```

By setting the x, y, and z parameter, a higher order prior (uncorrelated) can be set. For example 3 independent model parameters with a uniform prior distribution between 20 and 50, can be defined as

```
prior{1}.type='uniform';
prior{1}.x=[1 2 3];
prior{1}.min=20;
prior{1}.max=50;
```

Note that using the 'uniform' type priori model, is slightly more computational efficient than using a 'gaussian' type prior model with a high norm.

#### 2.1.1.2 1D Generalized Gaussian

A 1D generalized Gaussian prior model can be specified using the 'gaussian' type prior model

```
prior{1}.type='gaussian';
```

SIPPI 4 / 67

A simple 1D Gaussian distribution with mean 10, and standard deviation 2, can be specified using

```
ip=1;
prior{ip}.type='gaussian';
prior{ip}.m0=10;
prior{ip}.std=2;
```

The norm of a generalized Gaussian can be set using the 'norm' field. A generalized 1D Gaussian with mean 10, standard deviation of 2, and a norm of 70, can be specified using (The norm is equivalent to the beta factor referenced in Wikipedia:Generalized normal distribution)

```
ip=2;
prior{ip}.type='gaussian';
prior{ip}.m0=10;
prior{ip}.std=2;
prior{ip}.norm=70;
```


A 1D distribution with an arbitrary shape can be defined by setting d\_target, which must contain a sample of the distribution that one would like to replicate. For example, to generate a sample from a non-symmetric bimodal distribution, one can use e.g.

```
% Create target distribution
N=10000;
prob_chan=0.3;
d1=randn(1,ceil(N*(1-prob_chan)))*.5+8.5;
d2=randn(1,ceil(N*(prob_chan)))*.5+11.5;
d_target=[d1(:);d2(:)];

% set the target distribution
ip=3;
prior{ip}.type='gaussian';
prior{ip}.d_target=d_target;
```

The following figure shows the 1D histogram of a sample, consisting of 8000 realizations, generated using

```
sippi_plot_prior_sample(prior,1:ip,8000);
```



#### 2.1.1.3 FFTMA - 3D Gaussian model


The FFT moving average method provides an efficient approach for computing unconditional realizations of a Gaussian random field.

The mean and the covariance model must be specified in the m0 and Cm fields. The format for describing the covariance model follows 'gstat' notation, and is described in more details in the mGstat manual.

A 2D covariance model with mean 10, and a Spherical type covariance model can be defined in a 101x101 size grid (1 unit (e.g., meters) between the cells) using

SIPPI 5 / 67

```
im=1;
prior{im}.type='FFTMA';
prior{im}.x=[0:1:100];
prior{im}.y=[0:1:100];
prior{im}.m0=10;
prior{im}.Cm='1 Sph(10)';
```




Optionally one can translate the output of the Gaussian simulation into an arbitrarily shaped 'target' distribution, using normal score transformation. Note that this transformation will ensure a certain 1D distribution of the model parameters to be reproduced, but will alter the assumed covariance model such that the properties of covariance model are not necessarily reproduced. To ensure that both the covariance model properties and the 1D distribution are reproduced, make use of the VISIM type prior model instead because it utilizes direct sequential simulation.

```
im=1;
prior{im}.type='FFTMA';
prior{im}.x=[0:1:100];
prior{im}.y=[0:1:100];
prior{im}.Cm='1 Sph(10)';

% Create target distribution
N=10000;
prob_chan=0.5;
d1=randn(1,ceil(N*(1-prob_chan)))*.5+8.5;
d2=randn(1,ceil(N*(prob_chan)))*.5+11.5;
d_target=[d1(:);d2(:)];
prior{im}.d_target=d_target;
prior{im}.m0=0; % to make sure no trend model is assumed.
```

Alternatively, the normal score transformation can be defined manually such that the tail behavior can be controlled:

```
N=10000;
prob_chan=0.5;
d1=randn(1,ceil(N*(1-prob_chan)))*.5+8.5;
d2=randn(1,ceil(N*(prob_chan)))*.5+11.5;
d_target=[d1(:);d2(:)];
[d_nscore,o_nscore]=nscore(d_target,1,1,min(d_target),max(d_target),0);
prior{im}.o_nscore=o_nscore;
```



SIPPI 6 / 67

#### 2.1.1.4 FFTMA - 3D Gaussian model wuth variable model properties

The FFTMA method also allows treating the parameters defining the Gaussian model, such as the mean, variance, ranges and angles of rotation as a priori model parameters (that can be inferred as part of inversion, see e.g. an example).

First a prior type defining the Gaussian model must be defined (exactly as listed above):

```
im=im+1;
prior{im}.type='FFTMA';
prior{im}.x=[0:.1:10]; % X array
prior{im}.y=[0:.1:20]; % Y array
prior{im}.m0=10;
prior{im}.Cm='1 Sph(10,90,.25)';
```

Now, all parameter such as the mean, variance, ranges and angles of rotations, can be randomized by defining a 1D a priori model type ('uniform' or 'gaussian'), and with a specific 'name' indicating the parameter (see this example for a complete list of names), and by assigning the prior\_master field that points the prior model id for which the parameters should randomized.


For example the range along the direction of maximum continuty can be randomized by defining a prior entry named 'range\_1', and settling the prior\_master to point to the prior with id 1:

```
im=2;
prior{im}.type='uniform';
prior{im}.name='range_1';
prior{im}.min=2;
prior{im}.max=14;
prior{im}.prior_master=1;
I this case the range is randomized following a uniform distribution U[2,14].
```

Likewise, the first angle of rotation can be randomized using for example

```
im=3;
prior{im}.type='gaussian';
prior{im}.name='ang_1';
prior{im}.m0=90;
prior{im}.std=10;
prior{im}.prior_master=1;
```


A sample from such a prior type model will thus show variability also in the range and angle of rotation, as seen here



#### 2.1.1.5 VISIM

SIPPI 7 / 67

```
im=im+1;
prior{im}.type='VISIM';
prior{im}.x=[0:1:100];
prior{im}.y=[0:1:100];
prior{im}.m0=10;
prior{im}.Cm='1 Sph(10)';
```




As with the FFTMA prior model the VISIM prior can make use of a target distribution. However, if a target distribution is set, the use of the VISIM prior model will utilize direct sequential simulation, which will ensure both histogram and covariance reproduction.

Using a target distribution together with the VISIM prior model is similar to that for the FFTMA prior model. Simply the type has to be changed from FFTMA to VISIM:

```
clear all; close all;
im=1;
prior{im}.type='VISIM';
prior{im}.x=[0:1:40];
prior{im}.y=[0:1:40];
prior{im}.m0=10;
prior{im}.Cm='1 Sph(10)';

% Create target distribution
N=10000;
prob_chan=0.5;
d1=randn(1,ceil(N*(1-prob_chan)))*.5+8.5;
d2=randn(1,ceil(N*(prob_chan)))*.5+11.5;
d_target=[d1(:);d2(:)];
prior{im}.d_target=d_target;
```




### 2.1.1.6 CHOLESKY - 3D Gaussian model

The CHOLESKY type prior utilizes Cholesky decomposition of the covariance in order to generate realizations of a Gaussian random field. The CHOLESKY type prior needs a full description of the covariance model, which will be of size [nxyz\*nxyz\*nxyz], unlike using the FFTMA type prior model that only needs a specification of an isotropic covariance models of size [1,nxyz]. Hence, the CHOLESKY type prior is much more demanding on memory, and CPU. However, the CHOLESKY type prior can be used to sample from any covariance model, also non-stationary covariance model.

The CHOLESKY model is can be defined almost identically to the FFTMA type prior model. As an example:

SIPPI 8 / 67



the use of d\_target to specify target distributions is also possible, using the same style as for the FFTMA type prior.

50

100

100

100

100

100

0

50

100

100

Be warned that the 'cholesky' type prior model is much more memory demanding than the 'fftma' and 'visim' type prior models, as a full nxyz\*nxyz covariance model needs to setup (and inverted). Thus, the 'cholesky' type prior is mostly applicable when the number of model parameters (nx\*ny\*nx) is small.

#### 2.1.1.7 3D PluriGaussian

50

••

100

#### 2.1.1.8 **SNESIM**

The 'SNESIM' type prior model utilizes the SNESIM algorithm, as implemented in SGeMS. As opposed to the Gaussian prior models defined above, the SNESIM prior model infer spatial statistics from a training image, which should be a 2D/3D stationary image.

By default a training image (channel structures) from Sebastian Strebelle's PhD theses is used (if no training image is specified). A simple 2D type SNESIM prior model can be defined using the following code:

```
ip=1;
prior{ip}.type='SNESIM';
prior{ip}.x=[0:.1:10]; % X array
prior{ip}.y=[0:.1:20]; % Y array
```

and 5 realizations from this prior can be visualized using


100

0

50

100

```
for i=1:5;
    m=sippi_prior(prior);
    subplot(1,5,i);
    imagesc(prior{1}.x,prior{1}.y,m{1});axis image
end
```




SIPPI 9 / 67

Note that the training image is always assumed to have the same units as the prior model, so in this case each pixel in the training image is assumed to be separated by a distance '0.1'.

Optionally 'scaling' and 'rotation' of the training image can be set. To scale the training image by 0.7 (i.e., structures will appear 30% smaller) and rotate the training 30 degrees from north use

```
ip=1;
prior{ip}.type='SNESIM';
prior{ip}.x=[0:.1:10]; % X array
prior{ip}.y=[0:.1:20]; % Y array
prior{ip}.scaling=.7;
prior{ip}.rotation=30;
```



#### 2.1.1.8.1 Custom training image

A custom training image can be set using the ti field, which must be either a 2D or 3D matrix.

```
% create TI from image
EXAMPLE EXAMPLE

% setup the prior
ip=1;
prior{ip}.type='SNESIM';
prior{ip}.x=[0:.1:10]; % X array
prior{ip}.y=[0:.1:20]; % Y array
prior{ip}.ti=ti;
```

Note that the training image MUST consist of integer index values starting from 0 (i.e. '0', '1', '2', ...).

#### 2.1.1.8.2 Complete customization


If the prior structure is returned from sippi\_prior using

```
[m,prior]=sippi_prior(prior);
```

then an XML structure prior{1}.S.XML will be available. This allows a complete customization of all settings available in SGeMS. For example, the different realizations, using 1, 2, and 3 multiple grids can be obtained using

```
ip=1;
prior{ip}.type='SNESIM';
prior{ip}.x=[0:.1:10]; % X array
prior{ip}.y=[0:.1:20]; % Y array
[m,prior]=sippi_prior(prior);
for i=1:5;
    prior{ip}.S.XML.parameters.Nb_Multigrids_ADVANCED.value=i;
    subplot(1,3,5);
    imagesc(prior{1}.x,prior{1}.y,m{1});axis image
end
```

SIPPI 10 / 67



### 2.1.2 Sampling the prior

Once the prior data structure has been defined/modified, a sample from the prior distribution can be generated using

```
m=sippi_prior(prior);
```

'm' is a Matlab data structure of the same size as the 'prior' data structure. Thus, if two prior distributions have been defined in 'prior{1}' and 'prior{2}', then 'm{1}' will hold a realization of 'prior{1}', and 'm{2}' will hold a realization of 'prior{2}'.

Each time 'm=sippi\_prior(prior)' is called, a new independent realization of the prior will be generated.

### 2.1.3 Sequential Gibbs sampling / Conditional Re-sampling

All the available types of prior models allow perturbing one realization of a prior into a new realization of the prior, where the degree of perturbation can be controlled (from a new independent realization to a very small change).

This means that a random walk, with an arbitrary 'step-length' can be performed for any of the a priori types available in SIPPI

For the a priori types 'FFTMA', 'VISIM', 'CHOLESKY', 'SISIM', 'SNESIM', sequential Gibbs sampling [HCM12] is applied. Sequential Gibbs is in essence a type of conditional re-simulation. From a current realization of a prior model, a number of model parameters are discarded and treated as unknown. The unknown model parameters are then re-simulated conditional to the known model parameters.

In order to generate a new realization 'm2' in the vicinity of the realization 'm1' use

```
[m1,prior]=sippi_prior(prior);
[m2,prior]=sippi_prior(prior,m1);
```

If this process is iterated, then a random walk in the space of a priori acceptable models will be perform. Moreover, the collection of realization obtained in this way will represent a sample from prior distribution.

Note that in order to use sequential Gibbs sampling prior must be given both as an input variable, and as an (possibly update) output variable.

### 2.1.3.1 Controlling sequential Gibbs sampling / Conditional Re-sampling

All properties related to sequential Gibbs sampling can be set in the 'seq\_gibbs' structure (which will be avaiable the first time sippi prior is called, or if sippi prior init is called), for the individual prior models.

The step-length (i.e. the degree of perturbation) is determined by the  $prior\{m\}$ .  $seq\_gibbs.step$  parameter.

For the 'uniform' and 'gaussian' type a priori models a step-length closer to 0 zeros imples a 'shorter' step, while a step-length close to 1, implies a 'longer' step-length. A step length of 1, will generate a new independent realization of the prior, while a step length of 0, will return the same realization of the prior

SIPPI 11 / 67

```
prior{m}.seq_gibbs.step=.1;
[m2,prior]=sippi_prior(prior,m1);
```

For the 'FFTMA', 'VISIM', 'CHOLESKY', 'SISIM', and 'SNESIM' type a priori models two types (defined in the prior $\{m\}$ . seq\_gibbs. type variable).

The default 'type' is 2, defined as

```
prior{m}.seq_gibbs.step=1;
prior{m}.seq_gibbs.type=2;
```

where the step length defines the percentage of the of model parameters (selected at random) defined in prior  $\{im\}$  is conditionally re-sampled. Thus, a step-length closer to 0 zeros implies a 'shorter' step, while a step-length close to 1, implies a 'longer' step-length.

If  $prior\{m\}.seq\_gibbs.step=1$ , then  $prior\{m\}.seq\_gibbs.step$  defines the size of a square rectangle/cube which is to be conditionally re-simulated using sequential Gibbs sampling.

### 2.2 data: Data and data uncertainties/noise

data is a Matlab structure that defines any number of data and the associated uncertainty/noise model.

data{1} defines the first data set (which must always be defined), and any number of additional data sets can be defined in data{2}, data{3}, ...

This allows to consider for example seismic data in data{1}, and electromagnetic data in data{2}.

For each set of data, a Gaussian noise model (both correlated and uncorrelated) can be specified. The noise model for different data types (e.g. data{1} and data{2} are independent).

Once the noise model has been defined, the log-likelihood related to any model, m, with the corresponding forward response, d, can be computed using

```
[d,forward,prior,data]=sippi_forward(m,forward,prior,data)
logL=sippi_likelihood(data,d)
```

where d is the output of sippi forward.

The specification of the noise model can be divided into a description of the measurement noise (mandatory) and the modeling error (optional).

### 2.2.1 Gaussian measurement noise

#### 2.2.1.1 Uncorrelated Gaussian measurement noise

To define a set of observed data, [0,1,2], with an associated uncorrelated uncertainty defined by a Gaussian model with mean 0 and standard deviation 2, use

```
data{1}.d_obs=[0 1 2]';
data{1}.d_std=[2 2 2]';
```

which is equivalent to (as the noise model for each data is the same, and independent)

```
data{1}.d_obs=[0 1 2]';
data{1}.d_std=2;
```

One can also choose to define the uncertainty using a variance as opposed to the standard deviation

```
data{1}.d_obs=[0 1 2]';
data{1}.d_var=4;
```

SIPPI 12 / 67

#### 2.2.1.2 Correlated Gaussian measurement noise

Correlated Gaussian measurement uncertainty can be specified using the Cd field, as for example

```
data{1}.Cd=[4 1 0 ; 1 4 1 ; 0 1 4];
```

Note that data{1}.Cd must be of size [NDxND], where ND is the number of data in data{1}.d\_obs.

### 2.2.2 Gaussian modeling error

The modeling error refers to errors caused by using for example an imperfect forward model, see [HCM14].

A Gaussian model of the modeling error can be specified by the mean, dt, and the covariance, Ct.

For example

```
data{1}.dt=[0 0 0];
data{1}.Ct=[4 4 4; 4 4 4; 4 4 4];
```

is equivalent to

```
data{1}.Ct=4
```

which implies a zero mean modeling error with a covariance model where all model parameters has a covariance of 4.

sippi\_compute\_modelization\_forward\_error can be used to estimate the modeling error related to using an approximate forward model. See the tomography example, for an example of accounting for correlated modeling errors, following [HCM14].

### 2.3 forward: The forward model

The specification of the prior and data is intended to be generic, applicable to any inverse problem considered. The forward problem, on the other hand, is typically specific for each different inverse problem.

In order to make use of SIPPI to sample the posterior distribution of an inverse problem, the solution to the forward problem must be embedded in a Matlab function with the following input and output arguments:

```
[d,forward,prior,data]=sippi_forward(m,forward,prior,data,id)
```

m is a realization of the prior model, and prior and data are the Matlab structures defining the prior and the noise model (see Prior and Data)

id is optional, and can be used to compute the forward response of a subset of the different types of data available (i.e. data{1}, data{2},...)

The forward variable is a Matlab structure that can contain any information needed to solve the forward problem. Thus, the parameters for the forward structure is problem dependent. One option, forward forward function is though generic, and point to the m-file that implements the forward problem.

The output variable d is a Matlab structure of the same size of data. Thus, if 4 types of data have been specified, then d must also be a structures of size 4.

```
length(data) == length(d);
```

Further, d{i} must refer to an array of the same size as data{i}.d\_obs.

An example of an implementation of the forward problem related to a simple line fitting problem is:

SIPPI 13 / 67

```
function [d,forward,prior,data]=sippi_forward_linefit(m,forward,prior,data);
    d{1}=forward.x*m{2}+m{1};
```

This implementation requires that the 'x'-locations, for which the y-values of the straight line is to be computed, is specified through forward.x. Say some y-data has been observed at locations x=[1,5,8], with the values [2,4,9], and a standard deviation of 1 specifying the uncertainty, the forward structure must be set as

```
forward.forward_function='sippi_forward_linefit';
forward.x=[1,5,8];
```

while the data structure will be

```
data{1}.d_obs=[2 4 9]
data{1}.d_std=1;
```

This implementation also requires that the prior model consists of two 1D prior types, such that

```
m=sippi_prior(prior)
```

returns the intercept in  $m\{1\}$  and the gradient in  $m\{2\}$ .

An example of computing the forward response using an intercept of 0, and a gradients of 2 is then

```
m{1}=0;
m{2}=2;
d=sippi_forward(m,forward)
```

and the corresponding log-likelihood of m, can be computed using

```
logL=sippi_likelihood(data,d);
```

[see more details and examples related to polynomial line fitting at polynomial line fitting].

The Examples section contains more example of implementation of different forward problems.

### 2.4 Validating prior, data, and forward

A simple way to test the validity of prior, data, and forward is to test if the following sequence can be evaluated without errors:

```
% Generate a realization, m, of the prior model
m=sippi_prior(prior);
% Compute the forward response
d=sippi_forward(m,forward,prior,data);
% Evaluate the log-likelihood of m
logL=sippi_likelihood(data,d);
```

SIPPI 14 / 67

## Chapter 3

# Sampling the a posteriori distribution

Once the prior, data, and forward data structures have been defined, the associated a posteriori probability can be sampled using the rejection sampler and the extended Metropolis sampler.

### 3.1 The rejection sampler

The rejection sampler provides a simple, and also in many cases inefficient, approach to sample the posterior distribution.

At each iteration of the rejection sample an independent realization,  $m_pro$ , of the prior is generated, and the model is accepted as a realization of the posterior with probability  $Pacc = L(m_pro)/L_max$ . It can be initiated using

```
options.mcmc.nite=400000; % Number of iteration, defaults to 1000 options.mcmc.i_plot=500; % Number of iteration between visual updates, defaults to 500 options=sippi_rejection(data,prior,forward,options);
```

By default the rejection sampler is run assuming a maximum likelihood of 1 (i.e. L\_max = 1). If L\_max is known, then it can be set using in the options.Lmax or options.logLmax fields

```
options.mcmc.Lmax=1e-9;
options=sippi_rejection(data,prior,forward,options);
```

ог

```
options.mcmc.logLmax=log(1e-9);
options=sippi_rejection(data,prior,forward,options);
```

Alternatively, L\_max can be automatically adjusted to reflect the maximum likelihood found while running the rejection sampler using

```
options.mcmc.adaptive_rejection=1
options=sippi_rejection(data,prior,forward,options);
```

An alternative to rejection sampling, also utilizing independent realizations of the prior, that does not require one to set L\_max is the independent extended metropolis sampler, which may be computatinoally superior to the rejection sampler,

SIPPI 15 / 67

### 3.2 The extended Metropolis sampler

The extended Metropolis algorithm is in general a much more efficient algorithm for sampling the a posteriori probability

The extended Metropolis sampler can be run using

One can choose to accept all steps in the Metropolis sampler, which will result in an algorithm sampling the prior model, using

```
options.mcmc.accept_all=1; % default [0]
```

One can choose to accept models that lead to an improvement in the likelihood, which results in an optimization like algorithm using

```
options.mcmc.accept_only_improvements=1; % default [0]
```

See sippi\_metropolis for more details.

### 3.2.1 Controlling the step length

One optionally, as part of running the extended Metropolis sampler, automatically update the 'step'-length of the sequential Gibbs sampler in order to ensure a specific approximate acceptance ratio of the Metropolis sampler. See [CHM12] for details.

The default parameters for adjusting the step length, as given below, are set in the 'prior.seq\_gibbs' structure. These parameters will be set the first time 'sippi\_prior' is called with the 'prior' structure as output. The default parameters.

```
prior{m}.seq_gibbs.step_min=0;
prior{m}.seq_gibbs.step_min=1;
prior{m}.seq_gibbs.i_update_step=50
prior{m}.seq_gibbs.i_update_step_max=1000
prior{m}.seq_gibbs.n_update_history=50
prior{m}.seq_gibbs.P_target=0.3000
```

By default, adjustment of the step length, in order to achieve an acceptance ratio of 0.3 ('prior{m}.seq\_gibbs.P\_target'), will be performed for every 50 ('prior{m}.seq\_gibbs.i\_update\_step') iterations, using the acceptance ratio observed in the last 50 ('prior{m}.seq\_gibbs.i\_update\_history') iterations.

Adjustment of the step length will be performed only in the first 1000 ('prior{m}.seq\_gibbs.i\_update\_step\_max') iterations.

In order to disable automatic adjustment of the step length simply set

```
prior{m}.seq_gibbs.i_update_step_max=0; % disable automatic step length
```

SIPPI 16 / 67

### 3.2.2 The independent extended Metropolis sampler

The 'independent' extended Metropolis sampler, in which each proposed model is independent of the previously visited model, can be chosen by forcing the 'step'-length to be 1 (i.e. leading to independent samples from the prior), using e.g.

```
% force independent prior sampling
for ip=1:length(prior);
  prior{ip}.seq_gibbs.step=1;
  prior{ip}.seq_gibbs.i_update_step_max=0;
end
% run 'independent' extended Metropolis sampling
[options,data,prior,forward,m_current]=sippi_metropolis(data,prior,forward,options)
```

### 3.2.3 Annealing schedule

Simulated annealing like behavior can be controlled in the options.mcmc.anneal structure. By default annealing is disabled.

Annealing consist of setting the temperature (similar to scaling the noise). A temperature foes not affect the exploration. For temperatures larger than 1, the acceptance ratio increases (the exploration of the Metropolis sampler increases). For temperatures below 1, the acceptance ratio decreases (and hence the exploration of the Metropolis sampler).

The temperature is set to options.mcmc.anneal.T\_begin at any iteration before options.mcmc.anneal.i\_begin. The temperature is set to options.mcmc.anneal.T\_end at any iteration after options.mcmc.anneal.i\_end.

In between iteration number options.mcmc.anneal.i\_start and options.mcmc.anneal.i\_end the temperature changes following either an exponential decay (options.mcmc.anneal.type='exp'), or simple linear interpolation (options.mcmc.anneal.type='linear').

An annealing schedule can be used allow a Metropolis sampler that allow exploration of more of the model space in the beginning of the chain. Recall though that the posterior is not sampled until (at least) the annealing has been ended at iteration, options.mcmc.anneal.i\_end, if the options.mcmc.anneal.T\_end=1. This can potentially help not to get trapped in a local minimum.

To use this type of annealing, where the annealing stops after 10000 iterations, after which the algorithm performs like a regular Metropolis sampler, use for example

```
options.mcmc.anneal.i_begin=1; % default, iteration number when annealing begins options.mcmc.anneal.i_end=10000; % iteration number when annealing stops
```

which is equivalent to

```
options.mcmc.anneal.i_begin=1; % default, iteration number when annealing begins options.mcmc.anneal.i_end=10000; % iteration number when annealing stops options.mcmc.anneal.T_begin=5; % start temperature options.mcmc.anneal.T_end=1; % end temperature
```

### 3.2.4 Parallel tempering

Parallel tempering is implemented according to [S13]. It is an extension of the Metropolis algorithm, that start a number of parallel chains of Metropolis sampling algorithms. Each chain is run with a different temperature, and the state of each chain is allowed jump between chains according to some rules that ensure the correct probability density is sampled. This allow the sampling algorithm to better handle a posterior distribution with multiple, disconnected, areas of high probability.

The following three setting enable parallel tempering.

SIPPI 17 / 67

```
TEMPERING

options.mcmc.n_chains=3; % set number of chains (def=1, no multiple chains)

options.mcmc.T=[1 2 3]; % set temperature of chains [1:n_chains]

options.mcmc.chain_frequency_jump=0.1; % probability allowing a jump between two chains
```

options.mcmc.n\_chains defines the number of chains. If not set only one chain is used, and the no parallel tempering is performed.

options.mcmc.T defines the temperature of each chain. A temperature of '1', which is the default, implies no tempering. A higher temperature allow a chain to be more exploratory.

options.mcmc.chain\_frequency\_jump defines the frequency with which a jump from one chain to another is suggested. A value of one means that a jump is proposed at each iteration, while a value of 0.1 (default) means that a jump is only proposed with 10 percentage probability (on average one in 10 iterations).

### 3.3 Simulated Annealing

Simulated annealing type optimization can be setup using an annealing schedule that is enable to the entire run of the Metropolis sampler, and that ends by a noise scaling factor less than 1. This can be obtained using e.g.

```
options.mcmc.anneal.i_begin=1; % default, iteration number when annealing begins options.mcmc.anneal.i_end=options.mcmc.nite; % iteration number when annealing stops options.mcmc.anneal.fac_begin=20; % default, noise is scaled by fac_begin at iteration ← i_begin options.mcmc.anneal.fac_end=0.01; % 1/100 of the noise level
```

SIPPI 18 / 67

## Chapter 4

# **Examples**

SIPPI can be used as a convenient approach for unconditional an conditional simulation.

In order to use SIPPI to solve inverse problems, one must provide the solution to the forward problem. Essentially this amounts to implementing a Matlab function that solves the forward problem in using a specific input/output format. If a solution to the forward problem already exist, this can be quite easily done simply using a Matlab wrapper function.

A few implementations of solutions to forward problems are included as examples as part of SIPPI. These will be demonstrated in the following

### 4.1 Examples of A priori models

### 4.1.1 Multiple 1D Gaussian prior model

A prior model consisting of three independent 1D distributions (a Gaussian, Laplace, and Uniform distribution) can be defined using

```
prior{ip}.type='GAUSSIAN';
prior{ip}.name='Gaussian';
prior{ip}.m0=10;
prior{ip}.std=2;
ip=2;
prior{ip}.type='GAUSSIAN';
prior{ip}.name='Laplace';
prior{ip}.m0=10;
prior{ip}.std=2;
prior{ip}.norm=1;
prior{ip}.type='GAUSSIAN';
prior{ip}.name='Uniform';
prior{ip}.m0=10;
prior{ip}.std=2;
prior{ip}.norm=60;
m=sippi_prior(prior);
m =
    [14.3082]
                  [9.4436]
                              [10.8294]
```

SIPPI 19 / 67

1D histograms of a sample (consisting of 1000 realizations) of the prior models can be visualized using ...

```
sippi_plot_prior_sample(prior);
```

### 4.1.2 Multivariate Gaussian prior with unknown covariance model properties.

The FFT-MA type a priori model allow separation of properties of the covariance model (covariance parameters, such as range, and anisotropy ratio) and the random component of a Gaussian model. This allow one to define a Gaussian a priori model, where the covariance parameters can be treated as unknown variables.


In order to treat the covariance parameters as unknowns, one must define one a priori model of type FFTMA, and then a number of 1D GAUSSIAN type a priori models, one for each covariance parameter. Each gaussian type prior model must have a descriptive name, corresponding to the covariance parameter that is should describe:

A very simple example of a prior model defining a 1D Spherical type covariance model with a range between 5 and 15 meters, can be defined using:

Note that the field prior\_master must be set to point the to the FFT-MA type a priori model (through its id/number) for which it should define a covariance parameter (in this case the range).

10 independent realizations of this type of a priori model are shown in the following figure


SIPPI 20 / 67



Such a prior, as all prior models available in SIPPI, works with sequential Gibbs sampling, allowing a random walk in the space of a prior acceptable models, that will sample the prior model. An example of such a random walk can be performed using

```
prior{1}.seq_gibbs.step=.005;
prior{2}.seq_gibbs.step=0.1;
clear m_real;
for i=1:150;
     [m,prior]=sippi_prior(prior,m);
     m_real(:,i)=m{1};
end
```

An example of such a set of 150 dependent realization of the prior can be seen below



SIPPI 21 / 67

### 4.2 Polynomial line fitting

Here follows simple polynomial (of order 0, 1 or 2) line-fitting is considered. Example m-files can be found in the SIPPI/examples/case\_linefit folder.

First, the forward problem is defined. Then examples of stochastic inversion using SIPPI is demonstrated using a a synthetic data set.

### 4.2.1 The forward problem

The forward problem consists of computing the y-value as a function of the x-position of the data, and the polynomial coefficients determining the line. sippi\_forward\_linefit.m:

```
% sippi_forward_linefit Line fit forward solver for SIPPI
%
% [d,forward,prior,data]=sippi_forward_linefit(m,forward,prior,data);
%
function [d,forward,prior,data]=sippi_forward_linefit(m,forward,prior,data);
if length(m)==1;
    d{1}=forward.x*m{1};
elseif length(m)==2;
    d{1}=forward.x*m{1}+m{2};
else
    d{1}=forward.x.^2*m{1}+forward.x*m{2}+m{3};
end
```

the forward.x must be an array of the x-locations, for which the y-values of the corresponding line will be evaluated.

Note that the prior must be defined such that  $prior\{1\}$  refer to the intercept,  $prior\{2\}$  to the gradient, and  $prior\{3\}$  to the 2nd order polynomial coefficient.


If only one prior type is defined then the forward response will just be a constant, and if two prior types are defined, then the forward response will be a straight line.

### 4.2.2 Reference data, data, forward

A reference data set can be computed using

```
clear all; close all;
rand('seed',1);randn('seed',1);
%% Select reference model
m_ref{1}=-30;
m_ref{2}=2;
m_ref{3}=0;
%% Setup the forward model in the 'forward' structure
forward.x=linspace(1,20,nd);
forward.forward_function='sippi_forward_linefit';
%% Compute a reference set of observed data
d=sippi_forward(m_ref,forward);
d_obs=d{1};
d std=10:
d_obs=d_obs+randn(size(d_obs)).*d_std;
data{1}.d_obs=d_obs;
data{1}.d_std=d_std;
```


SIPPI 22 / 67



### 4.2.3 The prior model


```
%% Setting up the prior model
% the intercept
im=1;
prior{im}.type='gaussian';
prior{im}.name='intercept';
prior{im}.m0=0;
prior{im}.std=30;
prior{im}.m_true=m_ref{1};
\% 1st order, the gradient
im=2;
prior{im}.type='gaussian';
prior{im}.name='gradient';
prior{im}.m0=0;
prior{im}.std=4;
prior{im}.norm=80;
prior{im}.m_true=m_ref{2};
% 2nd order
im=3;
prior{im}.type='gaussian';
prior{im}.name='2nd';
prior{im}.m0=0;
prior{im}.std=1;
prior{im}.norm=80;
prior{im}.m_true=m_ref{3};
sippi_plot_prior_sample(prior);
```

SIPPI 23 / 67





### 4.2.4 Setup and run the Metropolis sampler


Now, information about the model parameters can be inferred by running the extended Metropolis sampler using



SIPPI 24 / 67







### 4.2.5 Setup and run the rejection sampler

In a similar manner the rejection sampler can be setup and run using

```
options.mcmc.adaptive_rejection=1; % automatically adjust the normalizing likelihood options.mcmc.nite=100000; options=sippi_rejection(data,prior,forward,options);
```

### 4.3 Cross hole tomography

SIPPI includes a reference cross hole GPR data from Arrenaes set is also available, and will be used here to demonstrate the use of SIPPI to solve cross hole tomographic inversion in a probabilistic framework.

SIPPI also includes the implementation of multiple methods for computing the travel time delay between a set of sources and receivers. This allows SIPPI to work on for example cross hole tomographic forward and inverse problems.

This section contains examples for setting up and running an cross hole tomographic inversion using SIPPI using the reference data from Arrenæs, different types of a priori and forward models.

Example Matlab scripts for the examples below, and more, are located in examples/case tomography/.

Please see [HCLM13b] for more details on the example of using SIPPI to sample the posterior for cross hole tomographic inverse problems. See [LHC10] for more details on the data from Arrenæs.

### 4.3.1 Reference data set from Arrenæs

A 2D/3D data set of recorded travel time data from a cross hole Georadar experiment is available in the 'data/cross-hole' folder.

4 Boreholes were drilled, AM1, AM2, AM3, and AM4 at the locations shown below

SIPPI 25 / 67




Figure 4.1: Location of boreholes AM1, AM2, AM3, and AM4 at Arrenæs.

Travel time data were collected between boreholes AM1 and AM3, and AM2 and AM4 respectively, in a depth interval between 1m and 12m. The travel times for each of the two 2D data sets are available in the AM13\_data.mat and AM24\_data.mat files. All the data have been combined in the 3D data set available in AM1234\_data.mat.

All mat-files contains the following variable

```
S --> [ndata,ndim] each row contains the position of the source
R --> [ndata,ndim] each row contains the position of the receiver
d_obs --> [ndata,1] each row contains the observed travel time in milliseconds
d_std --> [ndata,1] each row contains the standard deviation of the uncertainty of the 
observed travel time in milliseconds
```

All data are also available as ASCII formatted EAS files in AM13\_data.eas, AM24\_data.eas, and AM1234\_data.eas.

The following 3 Figures show the ray coverage (using straight rays) for each of the AM13, AM24, and AM1234 data sets. The color of each ray indicates the average velocity along the ray computed using  $v_av = raylength/d_obs$ . AM13 ray coverageAM24 ray coverageAM1234 ray coverage.




Figure 4.2: Ray coverage between wells left) AM1-AM3, middle) AM2-AM4, right) AM1-4.

SIPPI 26 / 67

### 4.3.2 Travel delay computation: The forward problem

A number of different methods for solving the problem of computing the first arrival travel time of a seismic or electromagnetic wave traveling between a source in one borehole and a receiver in another borehole has been implemented in the m-file 'sippi\_forward\_traveltime'.

```
[d,forward,prior,data]=sippi_forward_traveltime(m,forward,prior,data,id,im)
```

In order to use this m-file to describe the forward problem specify the 'forward\_function' field in the forward structure using

```
forward.forward_function='sippi_forward_traveltime';
```

In order to use sippi\_forward\_traveltime, the location of the sources and receivers must be specified in the forward.S and forward.R. The number of columns reflect the number of data, and the number of rows reflect whether data are 2D (2 columns) or 3D (3 columns):

```
forward.S % [ndata,ndim]
forward.R % [ndata,ndim]
```

Using for example the data from Arrenæs, the forward geometry can be set up using

```
D=load('AM13_data.mat');
forward.sources=D.S;
forward.receivers=D.R;
```

In addition the method used to compute the travel times must also be given (see below).

In order to use the geometry from the AM13 reference data, and the Eikonal solution to the wave-equation, the forward structure can be defined using

```
D=load('AM13_data.mat');
forward.forward_function='sippi_forward_traveltime';
forward.sources=D.S;
forward.receivers=D.R;
forward.type='eikonal';
```

### 4.3.2.1 Ray type forward model (high frequency approximation)

Ray type models are based on an assumption that the wave propagating between the source and the receiver has infinitely high frequency. Therefore the travel time delay is due to the velocity along a ray connecting the source and receiver.

The linear so-called straight ray approximation, which assumes that the travel time for a wave traveling between a source and a receiver is due to the travel time delay along a straight line connecting the source and receiver, can be chosen using

```
forward.type='ray';
forward.linear=1;
```

The corresponding so-called bended-ray approximation, where the travel time delay is due to the travel time delay along the fast ray path connecting a source and a receiver, can be chosen using

```
forward.type='ray';
forward.linear=0;
```

When sippi\_forward\_traveltime has been called once, the associated forward mapping operator is stored in 'forward.G' such the forward problem can simply be solved by calling e.g. ' $d\{1\}$ =forward.G\*m $\{1\}$ '

SIPPI 27 / 67

#### 4.3.2.2 Fat Ray type forward model (finite frequency approximation)

Fat type model assume that the wave propagating between the source and the receiver has finite high frequency. This means that the travel time is sensitive to an area around the raypath, typically defined using the 1st Fresnel zone.

A linear fat ray kernel can be chosen using

```
forward.type='fat';
forward.linear=1;
forward.freq=0.1;
```

and the corresponding non-linear fat kernel using

```
bforward.type='fat';
forward.linear=0;
forward.freq=0.1;
```

Note that the center frequency of the propagating wave must also be provided in the 'forward.freq' field. The smaller the frequency, the 'fatter' the ray kernel.

For 'fat' type forward models we rely on the method described by Jensen, J. M., Jacobsen, B. H., and Christensen-Dalsgaard, J. (2000). Sensitivity kernels for time-distance inversion. Solar Physics, 192(1), 231-239

### 4.3.2.3 Born type forward model (finite frequency approximation)

Using the Born approximation, considering only first order scattering, can be chosen using

```
forward.type='born';
forward.linear=1;
forward.freq=0.1;
```

For a velocity field with small spatial variability one can compute 'born' type kernels (using 'forward.linear=0', but as the spatial variability increases this is not possible.

For the 'born' type forward model we make use if the method described by Buursink, M. L., Johnson, T. C., Routh, P. S., and Knoll, M. D. (2008). Crosshole radar velocity tomography with finite frequency Fresnel volume sensitivities. Geophysical Journal International, 172(1), 1-17.

### 4.3.2.4 The eikonal equation (high frequency approximation)

The eikonal solution to the wave-equation is a high frequency approximation, such as the one given above.

However, it is computationally more efficient to solve the eikonal equation directly, that to used the 'forward.type='ray';' type forward model.

To choose the eikonal solver to compute travel times use

```
forward.type='eikonal';
```

The Accurate Fast Marching Matlab toolbox: http://www.mathworks.com/matlabcentral/fileexchange/24531-accurate-fast-marching is used to solve the Eikonal equation.

# 4.3.3 AM13 Gaussian: Inversion of cross hole GPR data from Arrenaes data with a Gaussian type a priori model

In the following a simple 2D Gaussian a priori model is defined, and SIPPI is used to sample the corresponding a posteriori distribution. (An example script is available at examples/case\_tomography/sippi\_AM13\_metropolis\_gaussian.m).

SIPPI 28 / 67

#### 4.3.3.1 Setting up the data structure

Initially we load the travel time data obtained at Arrenæs (See Arrenæs Data for more information)

```
D=load('AM13_data.mat');
```

This allow us to setup a SIPPI data structure defining the observed data as well as the associated model of uncertainty

```
%% SETUP DATA
id=1;
data{id}.d_obs=D.d_obs;
data{id}.d_std=D.d_std;
data{id}.dt=0; % Mean modelization error
data{id}.Ct=1; % Covariance describing modelization error
```

In the above example we define a Gaussian modelization error, N(dt,Ct). We do this because we will make use of a forward model, the eikonal solver, that we know will systematically provide faster travel times than can be obtained from the earth. In reality the wave travelling between bore holes never has infinitely high frequency as assumed by using the eikonal solver. The eikonal solver provides the fast travel time along a ray connecting the source and receiver. Therefore we introduce a modelization error, that will allow all the travel times to be biased with the same travel time.

#### 4.3.3.2 Setting up the prior model

The a priori model is defined using the prior data structure. Here a 2D Gaussian type a priori model in a 7x13 m grid (grid cell size .25m) using the FFTMA type a priori model. The a priori mean is 0.145 m/ns, and the covariance function a Spherical type covariance model with a range of 6m, and a sill(variance) of 0.0003 m<sup>2</sup>/ns<sup>2</sup>.

```
%% SETUP PRIOR
im=1;
prior{im}.type='FFTMA';
prior{im}.m0=0.145;
prior{im}.Va='.0003 Sph(6)';
prior{im}.x=[-1:.15:6];
prior{im}.y=[0:.15:13];
```

One could make used of the VISIM type priori model simply by substituting 'FFTMA' with 'VISIM' above.

#### 4.3.3.3 Setting up the forward structure

'sippi\_forward\_traveltime' require that the location of the sources an receivers are provided in 'forward' structure using the 'sources' and 'receivers' field names.

```
D=load('AM13_data.mat');
forward.forward_function='sippi_forward_traveltime';
forward.sources=D.S;
forward.receivers=D.R;
forward.type='eikonal';
```

Here the eikonal solution is chosen to solve the forward problem. See more detail about solving the forward problem related to cross hole first arrival travel time computation here.

SIPPI 29 / 67

### 4.3.3.4 Testing the setup

As the prior, data, and forward have been defined, one can in principle initiate an inversion. However, it is advised to perform a few test before applying the inversion.

First, one should check that independent realization of the prior model resemble the a priori knowledge. A sample from the prior model can be generated and visualized calling sippi\_plot\_prior\_sample:

```
sippi_plot_prior_sample(prior);
```

which provides the following figure




Figure 4.3: AM13: One sample (15 realizations) of the prior (Gaussian) model.

The one can check that the forward solver, and the computation of the likelihood wors as expected using

which produce a figure similar to

SIPPI 30 / 67




Figure 4.4: AM13: Data response from one realization of the prior.

### 4.3.3.5 Sampling the a posterior distribution using the extended Metropolis algorithm

The extended Metropolis sampler can now be run using sippi metropolis.

```
options=sippi_metropolis(data,prior,forward);
```

In practice the user will have to set a few options, controlling the behavior of the algorithm. In the following example the number of iterations is set to 500000; the current model is saved to disc for every 500 iterations; the log-likelihood and current model is shown for every 1000 iterations:

```
options.mcmc.nite=500000; % optional, default:nite=30000
options.mcmc.i_sample=500; % optional, default:i_sample=500;
options.mcmc.i_plot=1000; % optional, default:i_plot=50;
options=sippi_metropolis(data,prior,forward,options);
```

By default no annealing schedule is used. By default the 'step'-length for sequential Gibbs sampling is adjusted (to obtain an average acceptance ratio of 30%) for every 50 iterations until iteration number 1000.

An output folder will be generated with a filename formatted using 'YYYYMMDD-HHMM', followed by a automatic description. In the above case the output folder could be name '20140701\_1450\_sippi\_metropolis\_eikonal'. The actual folder name is return in options.txt.

One can define a description for the folder name by setting options.txt before running sippi metropolis.

The folder contains one mat file, with the same name as the folder name, and N ASCII files (where N=length(prior); one for each a priori type) which contains the models saved to disc. They also have the same name as the folder name, appended with '\_m1.asc', '\_m2.asc', and so forth.

### 4.3.3.5.1 Posterior statistics

The function sippi\_plot\_posterior can be called when sippi\_metropolis (or sippi\_rejection) and will plot the progress of the log-likelihood curve, a sample of the posterior, data response from a sample of the posterior, and (if applicable) 1D and 2D marginal posterior distributions.

Located in the output folder of the inversion use

```
sippi_plot_posterior;
```

If the location of the folder with the output is known (such as options.txt) one can call

```
sippi_plot_posterior(options.txt)
```

SIPPI 31 / 67

### 4.3.4 AM13 Gaussian, accounting for modeling errors

[A Matlab script for the following example is available at examples/case\_tomography/sippi\_AM13\_metropolis\_modeling\_towns.]

The use of any of the forward models defined above, will be approximation to solving the perfect forward problem. This leads to a 'modeling' error as demonstrated by [HCM14]. If one has access to an optimal (but perhaps computational inefficient) forward model, and a faster (less accurate) forward model, then a Gaussian model of the modeling error caused by using the approximate, as opposed to the optima, forward model can be estimated using sippi\_compute\_modelization\_forward\_error. sippi\_compute\_modelization\_forward\_error.

SIPPI allows accounting for such modeling error through the dt and Ct fields for the data structure.

The setup of the data, prior and forward structures is identical to the one described in the previous example.

```
%% Load the travel time data set from ARRENAES
clear all; close all
D=load('AM13_data.mat');
options.txt='AM13';
%% SETUP DATA
id=1;
data{id}.d_obs=D.d_obs;
data{id}.d_std=D.d_std;
data{id}.Ct=D.Ct+1; % Covariance describing modeling error
%% SETUP PRIOR
im=1:
prior{im}.type='FFTMA';
prior{im}.name='Velocity (m/ns)';
prior{im}.m0=0.145;
prior{im}.Va='.0003 Sph(6)';
dx = 0.15;
prior{im}.x=[-1:dx:6];
prior{im}.y=[0:dx:13];
prior{im}.cax=[.1 .18];
% SETUP THE FORWARD MODEL USED IN INVERSION
forward.forward_function='sippi_forward_traveltime';
forward.sources=D.S;
forward.receivers=D.R;
forward.type='fat'; forward.linear=1; forward.freq=0.1;
```

In order to compute the modeling with respect to using the 'Born' type forward model, one can define a new forward structure, here forward\_full, and estimate a Gaussian model for the modeling error using

```
% SETUP THE 'OPTIMAL' FORWARD MODEL
forward_full.forward_function='sippi_forward_traveltime';
forward_full.sources=D.S;
forward_full.receivers=D.R;
forward_full.type='Born'; forward_full.linear=1; forward_full.freq=0.1;

% COMPUTE MODELING ERROR DUE TO USE OF forward AS OPPOSED TO forward_full
N=100;
[Ct,dt,dd]=sippi_compute_modelization_forward_error(forward_full,forward,prior,data,N);

% ASSIGN MODELING ERROR TO DATA
data{1}.dt=dt{1};
data{1}.Ct=Ct{1};
```

Sampling of the posterior can proceed exactly as for the previous example, using

```
options.mcmc.nite=500000; % optional, default:nite=30000
options.mcmc.i_sample=500; % optional, default:i_sample=500;
```

SIPPI 32 / 67

```
options.mcmc.i_plot=1000; % optional, default:i_plot=50;
options=sippi_metropolis(data,prior,forward,options);

% plot posterior statistics
sippi_plot_posterior(options.txt);
```

### 4.3.5 AM13 Gaussian with bimodal velocity distribution

[A Matlab script for the following example is available at examples/case\_tomography/sippi\_AM13\_metropolis\_bimodal.m.

The GAUSSIAN and FFTMAa prior types implicitly assume a normal distribution of the model parameter.

It is however possible to change the Gaussian distribution to any shaped distribution, using a normal score transform. Note that when this is done the given semivariogram model for the FFTMA a priori model will not be reproduced. If this is a concern, then the VISIM type a priori model should be used.

The data and forward structures is identical to the one described in the previous example.

```
%% Load the travel time data set from ARRENAES
clear all;close all
D=load('AM13_data.mat');
options.txt='AM13';

%% SETUP DATA
id=1;
data{id}.d_obs=D.d_obs;
data{id}.d_std=D.d_std;
data{id}.Ct=D.Ct+1; % Covariance describing modeling error

% SETUP THE FORWARD MODEL USED IN INVERSION
forward.forward_function='sippi_forward_traveltime';
forward.sources=D.S;
forward.receivers=D.R;
forward.type='fat';forward.linear=1;forward.freq=0.1;
```

The desired distribution (the 'target' distribution) must be provided as a sample of the target distribution, in the data{id}.d\_target distribution.

```
%% SETUP PRIOR
im=1;
prior{im}.type='FFTMA';
prior{im}.name='Velocity (m/ns)';
prior{im}.m0=0.145;
prior{im}.Va='.0003 Sph(6)';
dx = 0.15;
prior{im}.x=[-1:dx:6];
prior{im}.y=[0:dx:13];
prior{im}.cax=[.1 .18];
% SET TARGET
N=1000;
prob_chan=0.5;
dd=.014*2;
d1=randn(1,ceil(N*(1-prob chan)))*.01+0.145-dd; %0.1125;
d2=randn(1,ceil(N*(prob_chan)))*.01+0.145+dd; %0.155;
d_target=[d1(:);d2(:)];
prior{im}.d_target=d_target;
```

5 realizations from the corresponding a priori model looks like

SIPPI 33 / 67




Figure 4.5: 5 realizations from a FFTMA prior model type with top) Gaussian and b) Bimodal distribution

Figure Figure 4.6 compares the distribution from one realization of both prior models considered above.




Figure 4.6: Distribution of one realization using a Gaussian Bimodal target distribution

As for the examples above, the a posteriori distribution can be samples using e.g.

```
options.mcmc.nite=500000; % optional, default:nite=30000
options.mcmc.i_sample=500; % optional, default:i_sample=500;
options.mcmc.i_plot=1000; % optional, default:i_plot=50;
options=sippi_metropolis(data,prior,forward,options);

% plot posterior statistics
sippi_plot_posterior(options.txt);
```

SIPPI 34 / 67

### 4.3.6 AM13 Gaussian with unknown Gaussian model parameters

[A Matlab script for the following example is available at examples/case\_tomography/sippi\_AM13\_metropolis\_gaussian\_co

One of the most intriguing benefits (in addition to the computational efficiency) of using the FFTMA type a priori model, is that it allows separation of the random component and the covariance model parameters. See [HCLM13a].

This means that one can in SIPPI define an inverse problem, where the a priori model is Gaussian, but where the properties of the Gaussian model (such as the mean, range, anisotropy) can be treated as unknown model parameters

Each property the Gaussian prior model that should be treated as an unknown model parameter, must be defined as a separate 1D type GAUSSIAN type prior model, with a specific name (identifying the covariance model property it describes), and it mist point to the prior model type number for which it describes a covariance model property-

The example below describes a 2D FFTMA type e a priori model (prior with id 1) with an unknown range (prior with id 2) with an a priori distribution described by a close to uniform distribution between 1.5m and 10.5m:

```
im=1:
prior{im}.type='FFTMA';
prior{im}.name='Velocity (m/ns)';
prior{im}.m0=0.145;
prior{im}.Va='.0003 Sph(6)';
dx = 0.25;
prior{im}.x=[-1:dx:6];
prior{im}.y=[0:dx:13];
prior{im}.cax=[.1 .18];
i_master=im;
% range - horizontal
im=im+1:
prior{im}.type='gaussian';
prior{im}.name='range_1'; % the name covariance model property to define
prior{im}.m0=6;
prior{im}.min=1.5;
prior{im}.max=10.5;
prior{im}.norm=50;
prior{im}.prior_master=i_master; % point to the id of the prior it describes
```

Any combination of the following parameters can be set:

```
prior{im}.name='range_1; % Range, along direction of angle_1
prior{im}.name='range_2; % Range, along direction of angle_2
prior{im}.name='range_3; % Range, along direction of angle_3
prior{im}.name='ang_1;
                        % Angle 1, degrees from North
prior{im}.name='ang_2;
                         % Angle 2
prior{im}.name='ang_3;
                         % Angle 3
prior{im}.name='sill;
                         % sill,
prior{im}.name='nu;
                         % the 'nu' parameter, only applies when using the Matern \,\leftrightarrow
    covariance model type.
prior{im}.name='m0;
                         % A priori mean
```

As an example consider case where the two ranges, and the angle of anisotropy fro a 2D Gaussian (FFTMA) a priori type model is treated as model parameters:

```
im=0;
% velocity field
im=im+1;
prior{im}.type='FFTMA';
prior{im}.name='Velocity (m/ns)';
prior{im}.m0=0.145;
prior{im}.Va='.0003 Sph(6)';
```

SIPPI 35 / 67

```
dx = 0.25;
prior{im}.x=[-1:dx:6];
prior{im}.y=[0:dx:13];
prior{im}.cax=[.1 .18];
i_master=im;
% range - horizontal
im=im+1;
prior{im}.type='gaussian';
prior{im}.name='range_1';
prior{im}.min=1.5;
prior{im}.max=10.5;
prior{im}.norm=50;
prior{im}.prior_master=i_master;
% range - horizontal
im=im+1;
prior{im}.type='gaussian';
prior{im}.name='range_2';
prior{im}.min=1.5;
prior{im}.max=5.5;
prior{im}.norm=50;
prior{im}.prior_master=i_master;
% rotation
im=im+1;
prior{im}.type='gaussian';
prior{im}.name='ang_1';
prior{im}.m0=90;
prior{im}.std=20;
prior{im}.norm=2;
prior{im}.prior_master=i_master;
```

### A sample from the corresponding a priori model (FFTMA type) is shown below:




Figure 4.7: A sample from a FFTMA type prior model with varying range\_1, range\_2, and ang\_1.

SIPPI 36 / 67

Samples of the a priori distributions for range\_1, range\_2, and ang\_1 are shown here:




Figure 4.8: Distribution of one sample of a 1D Gaussian distribution describing range 1, range 2, and ang 1

As for the examples above, the a posteriori distribution can be samples using e.g.

```
options.mcmc.nite=500000; % optional, default:nite=30000
options.mcmc.i_sample=500; % optional, default:i_sample=500;
options.mcmc.i_plot=1000; % optional, default:i_plot=50;
options=sippi_metropolis(data,prior,forward,options);

% plot posterior statistics
sippi_plot_posterior(options.txt);
```

### 4.4 Probilistic covariance/semivariogram indeference

This chapter documents how to use SIPPI to infer properties of a covariance/semivariogram model from noisy data (both data of point support and linear average data can be considered)

To perform probabilistic inference of covariance model parameters one must

- 1. define the data and associated uncertainty (if any),
- 2. define a prior model of the covariance model parameters that one wish to infer information about, and
- 3. define the linear forward operator (only applicable if data are not of point support).

The methodology is published in [HCM15].

### 4.4.1 Specification of covariance model parameters

The following covariance model properties can be defined, that allow defining an isotropic or an-isotropic covariance model in 1D, 2D, or 3D:

```
% covariance model type (1->Sph, 2->Exp, 3->Gau)
type
mΘ
                    % the mean
sill
                    % the variance
                    % percentage of the variance assigned to a Nugget
nugget_fraction
                    % range in primary direction
range_1
range_2
                    % range in secondary direction
range_3
                    % range in tertiary direction
                    % first angle of rotation
ang_1
                    % second angle of rotation
ang_2
                    % third angle of rotation
ang_3
```

SIPPI 37 / 67

Inference of a full 1D covariance model requires defining [type,sill,nugget fraction,range 1].

Inference of a full 2D covariance model requires defining [type,sill,nugget fraction,range 1,range 2,ang 1].

Inference of a full 3D covariance model requires defining [type,sill,nugget\_fraction,range\_1,range\_2,range\_3,ang\_1,ang\_1

In order to define which of the covariance model parameters to infer information about, simply define a prior structure for any of these parameters, as 1D type SIPPI prior model.

For example, to simple infer information about the range in the primary direction, with a priori distribution of the range as U[0,3] use

```
forward.Cm='1 Sph(10)';
im=1;
prior{im}.type='uniform';
prior{im}.name='range_1'; % the 'name' field is used to identify the covariance model ←
    parameter!
prior{im}.min=0;
prior{im}.max=3;
```

In this case an range\_1 refers to the isotropic range in the covariance model defined in the forward. Cm field If, instead

```
forward.Cm='1 Sph(10,90,.25)';
```

then range\_1 would refer to the range in the direction of maximum continuity (90 degrees from North). range\_2 will in this case be fixed.

As described above, the covariance model type can be considered as a unknown parameter, that can be inferred during inversion. This may pose some problems as discussed in [HCM15].

To infer the covariance model type, a prior 1D structure should be defined as e.g.

```
im=1;
prior{im}.type='uniform';
prior{im}.name='type'; %
prior{im}.min=0;
prior{im}.max=3;
```

Any value between 0 and 1 defines a spherical type covariance. Any value between 1 and 2 defines an exponential type covariance. Any value between 3 and 3 defines a Gaussian type covariance.

Thus no prior should be defined for the 'type' prior that can provide values below 0, and above 3. In the case above, all three covariance model types has the sane a priori probability.

A detailed description of how to parameterize the inverse covariance model parameter problem, can be found in sippi forward covariance inference.

### 4.4.2 Inferring a 2D covariance model from the Jura data set - Example of point support

The Jura data set (see Goovaerts, 1997) contains a number observations of different properties in 2D. Below is an example of how to infer properties of a 2D covariance model from this data set.

A Matlab script implementing the steps below can be found here: jura\_covariance\_inference.m

#### 4.4.2.1 Load the Jura data

Firs the Jura data is loaded.

SIPPI 38 / 67

```
% jura_covariance_inference
%
% Example of inferring properties of a Gaussian model from point data
%

%% LOAD THE JURA DATA
clear all; close all
[d_prediction,d_transect,d_validation,h_prediction,h_transect,h_validation,x,y,pos_est]= 
    jura;
ix=1;
iy=2;
id=6;

% get the position of the data
pos_known=[d_prediction(:,[ix iy])];

% perform normal score transformation of tha original data
[d,o_nscore]=nscore(d_prediction(:,id));
h_tit=h_prediction{id};
```

### 4.4.2.2 Setting up SIPPI for covariance parameter inference

First a SIPPI 'prior' data structure is setup do infer covariance model parameters for a 2D an-isotropic covariance model. That is, the range\_1, range\_2, ang\_1, and nugget\_fraction are defined using

```
im=0;
% A close to uniform distribution of the range, U[0;3].
im=im+1;
prior{im}.type='uniform';
prior{im}.name='range 1';
prior{im}.min=0;
prior{im}.max=3;
im=im+1;
prior{im}.type='uniform';
prior{im}.name='range_2';
prior{im}.min=0;
prior{im}.max=3;
im=im+1;
prior{im}.type='uniform';
prior{im}.name='ang_1';
prior{im}.min=0;
prior{im}.max=90;
im=im+1;
prior{im}.type='uniform';
prior{im}.name='nugget_fraction';
prior{im}.min=0;
prior{im}.max=1;
```

Thus the a priori information consists of uniform distributions of ranges between 0 and 3, rotation between 0 and 90, and a nugget fraction between 0 and 1 is.

Then the data structure is set up, using the Jura data selected above, while assuming a Gaussian measurement uncertainty with a standard deviation of 0.1 times the standard deviation of the data:

```
%% DATA
```

SIPPI 39 / 67

```
data{1}.d_obs=d; % observed data data{1}.d_std=0.1*std(d);.4; % uncertainty of observed data (in form of standard deviation \ \hookleftarrow of the noise)
```

Finally the forward structure is setup such that sippi\_forward\_covariance\_inference allow inference of covariance model parameters.

In the forward structure the location of the point data needs to be given in the pos\_known field, and the initial mean and covariance needs to be set. Also, the name of the forward function used (in this case sippi\_forward\_covariance\_inferent must be set. Use e.g.:

```
%% FORWARD
forward.forward_function='sippi_forward_covariance_inference';
forward.point_support=1;
forward.pos_known=pos_known;


% initial choice of N(m0,Cm), mean and sill are 0, and 1, due
% due to normal score
forward.m0=mean(d);
forward.Cm=sprintf('%3.1f Sph(2)',var(d));
```

Now, SIPPI is set up for inference of covariance model parameters. Use for example the Metropolis sampler to sample the a posterior distribution over the covariance model parameters using:

```
options.mcmc.nite=100000;
options.mcmc.i_plot=1000;
options.mcmc.i_sample=25;
options.txt=name;
[options,data,prior,forward,m_current]=sippi_metropolis(data,prior,forward,options)
sippi_plot_prior(options.txt);
sippi_plot_posterior(options.txt);
```

Sampling the posterior provides the following 2D marginal distributions

SIPPI 40 / 67



Note how several areas of high density scatter points (i.e. areas with high posterior probability) can be found.

SIPPI 41 / 67

# Chapter 5

# **Bibliography**

[CHM12]	K. S. Cordua, T. M. Hansen, and K. Mosegaard, Monte Carlo full waveform inversion of crosshole GPF
	data using multiple-point geostatistical a priori information PDF, H19H31.
	Geophysics, 77, 2012.

- [HCLM13a] T.M. Hansen, K.S. Cordua, M.C. Looms, and K. Mosegaard, SIPPI: a Matlab toolbox for sampling the solution to inverse problems with complex prior information: Part 1, methodology PDF, 470–480.

  Computers & Geosciences, 52, 03 2013.
- [HCLM13b] T.M. Hansen, K.S. Cordua, M.C. Looms, and K. Mosegaard, SIPPI: a Matlab toolbox for sampling the solution to inverse problems with complex prior information: Part 2, Application to cross hole GPR tomography PDF, 481--492.

  Computers & Geosciences, 52, 03 2013.
- [HCM12] T. M. Hansen, K. C. Cordua, and K. Mosegaard, Inverse problems with non-trivial priors efficient solution through sequential Gibbs sampling PDF, 593--611.
   Computational Geosciences, 16, 2012.
- [HCM14] T. M. Hansen, K. S. Cordua, B. H. Jacobsen, and K. Mosegaard, Accounting for imperfect forward modeling in geophysical inverse problems exemplified for cross hole tomography PDF, H1-H21.

  Geophysics, 39, 2014.
- [HCM15] T. M. Hansen, K. C. Cordua, and K. Mosegaard, A general probabilistic approach for inference of Gaussian model parameters from noise data of point and volume support [PDF], 1-23.

  Mathematical Geosciences, , 2015.
- [LHC10] M. C. Looms, T. M. Hansen, K. S. Cordua, L. Nielsen, K. H. Jensen, and A. Binley, Geostatistical inference using crosshole ground-penetrating radar: Geostatistical inference using GPR PDF, J29--J41.

  Geophysics, 75, 2010.
- [S13] M. Sambridge, A Parallel Tempering algorithm for probabilistic sampling and multimodal optimization, .
   Geophysical Journal International, , 2013.

SIPPI 42 / 67

# Chapter 6

# Reference

### 6.1 SIPPI

### 6.1.1 sippi\_adjust\_step\_size

```
sippi_adjust_step_size Adjust step length length for Metropolis sampler in SIPPI

Call :
    step=sippi_adjust_step_size(step,P_average,P_target);

step : current step
P_current : Current acceptance ratio
P_target : preferred acceptance ratio (def=0.3);

See also sippi_compute_acceptance_rate, sippi_prior_set_steplength
```

### 6.1.2 sippi\_anneal\_temperature

```
sippi_anneal_temperature : compute annealing temperature for
annealing type sampling

%% ANNEALING (TEMPERATURE AS A FUNTION OF ITERAITON NUMBER)
    i % iteration number

mcmc.anneal.i_begin=1; % default, iteration number when annealing begins
mcmc.anneal.i_end=100000; % iteration number when annealing stops
mcmc.anneal.T_begin=5; % Start temperature for annealing
mcmc.anneal.T_end=1; % End temperature for annealing

mcmc.anneal.type='exp'; % Exponential temperature change
mcmc.anneal.type='linear'; % Linear temperature change
Call

[T,mcmc]=sippi_anneal_temperature(i,mcmc);
See also sippi_metropolis
```

SIPPI 43 / 67

### 6.1.3 sippi\_compute\_acceptance\_rate

```
sippi_compute_acceptance_rate Computes acceptance rate for the Metropolis sampler in ←→
SIPPI

Call:
P_acc=sippi_compute_acceptance_rate(acc,n_update_history);
```

### 6.1.4 sippi\_compute\_modelization\_forward\_error

```
sippi_compute_modelization_forward_error Computes an estimate of the modelization erro

Computes and estimate of the Gaussian modelization error, N(dt,Ct)
caused by the use of an imperfect forward kernel

If called with only one output '[Ct]=sippi..]' then the Gaussian model is assumed by centered around 0, (dt{1}=0).

Call

[Ct,dt,dd]=sippi_compute_modelization_forward_error(forward_full,forward_app,prior,N,d) ↔
;

For details see:

Hansen, T.M., Cordua, K. S., Jacobsen, B. J., and Mosegaard, K. (2014)

Accounting for imperfect forward modeling in geophysical inverse problems - exemplified ↔
for cross hole tomography.
Geophsyics, 79(3) H1-H21, 2014. doi:10.1190/geo2013-0215.1
```

### 6.1.5 sippi\_forward

```
sippi_forward Simple forward wrapper for SIPPI

Assumes that the actual forward solver has been defined by forward.forward_function

Call:
    [d,forward,prior,data]=sippi_forward(m,forward)

Optional:
    [d,forward,prior,data]=sippi_forward(m,forward,prior)
    [d,forward,prior,data]=sippi_forward(m,forward,prior,data)
    [d,forward,prior,data]=sippi_forward(m,forward,prior,data,options)
```

### 6.1.6 sippi\_get\_resim\_data

```
sippi_get_resim_data: Get conditional data for resimulation

d_cond=sippi_get_resim_data(m_current,prior,ip);

c_cond [n_cond,4]: col1: x, col2: y, col4: z, col4: d
```

SIPPI 44 / 67

```
See also sippi_prior
```

### 6.1.7 sippi\_get\_sample

```
sippi_get_sample: Get a posterior sample
Call:
 [reals_etype_mean,etype_var,reals_all,reals_ite]=sippi_get_sample(working_directory,im, \hookleftarrow
    n_reals,skip_seq_gibbs);
   im: A priori model type
   n_reals: Number of realizations to return
   skip_seq_gibbs [1] Skip all realization where sequential gibbs is enabled
                  [0] Use all realization
   data: SIPPI data structure
   prior: SIPPI prior structure
   options: options structure when running sippi_metropolis
If located in a SIPPI output folder one can simple use :
   [reals,etype_mean,etype_var,reals_all,reals_ite]=sippi_get_sample(im,n_reals);
   skip_seq_gibbs=0;
   [reals,etype_mean,etype_var,reals_all,reals_ite]=sippi_get_sample(im,n_reals, \leftrightarrow
       skip_seq_gibbs);
```

### 6.1.8 sippi\_least\_squares

### 6.1.9 sippi\_likelihood

```
sippi_likelihood Compute likelihood given an observed dataset

Call
   [logL,L,data]=sippi_likelihood(d,data);

data{1}.d_obs [N_data,1] N_data data observations
   data{1}.d_std [N_data,1] N_data uncorrelated Gaussian STD
```

SIPPI 45 / 67

```
data{1}.d var [N data,1] N data uncorrelated Gaussian variances
Gaussian modelization error, N(dt,Ct), is specified as
data{1}.dt [N_data,1] : Bias/mean of modelization error
data{1}.Ct [N_data,N_data] : Covariance of modelization error
data{1}.Ct [1,1] : Constant Covariance of modelization error
                    imples data{1}.Ct=ones(N_data.N_data)*data{1}.Ct;
data{id}.recomputeCD [default=0], if '1' then data{1}.iCD is recomputed
each time sippi_likelihood is called. This should be used if the noise model
changes between each call to sippi_likelihood.
data{id}.full_likelihood [default=]0; if '1' the the full likelihood
(including the determinant) is computed. This not needed if the data
civariance is constant, but if it changes, then use
data{id}.full_likelihood=1;
A new type of noise model can be used as long as it is available in a
m file staring with 'sippi likelihood '. Further, it should provide the
inputs and outputs as sippi_likelihood.m
If a noise model has been implemented in the m-files
sippi_likelihood_other.m
then this can be used to evaluate the likelhood in sippi using
data{1}.noise_model='sippi_likelihood_other',
```

### 6.1.10 sippi\_mcmc\_init

```
sippi_mcmc_init Initialize McMC options for Metropolis and rejection sampling in SIPPI
Call:
    options=sippi_mcmc_init(options,prior);
```

### 6.1.11 sippi\_metropolis

```
Sippi_metropolis Extended Metropolis sampling in SIPPI

Metropolis sampling.
   See e.g.
    Hansen, T. M., Cordua, K. S., and Mosegaard, K., 2012.
    Inverse problems with non-trivial priors - Efficient solution through Sequential 
        Gibbs Sampling.
    Computational Geosciences. doi:10.1007/s10596-011-9271-1.

    Sambridge, M., 2013 - A Parallel Tempering algorithm for probabilistic sampling and multi-modal optimization.

Call:
    [options,data,prior,forward,m_current]=sippi_metropolis(data,prior,forward,options)
Input:
    data: sippi data structure
    prior: sippi prior structure
```

SIPPI 46 / 67

```
forward : sippi forward structure
options :
  options.mcmc.nite=30000; % [1] : Number if iterations
  options.mcmc.i_sample=100; % : Number of iterations between saving model to disk
  options.mcmc.i_plot=50; % [1]: Number of iterations between updating plots
  options.mcmc.i_save_workspace=10000; % [1]: Number of iterations between
                                           saving the complete workspace
  options.mcmc.i_sample=100; % : Number of iterations between saving model to disk
  options.mcmc.m_init : Manually chosen starting model
  options.mcmc.m_ref : Reference known target model
  options_mcmc.accept_only_improvements [0] : Optimization
  options.txt [string] : string to be used as part of all output file names
  %% PERTURBATION STRATEGY
  % Perturb all model parameter all the time
  options.mcmc.pert_strategy.perturb_all=1; % Perturb all priors in each
                                             % iteration. def =[0]
   options.mcmc.pert_strategy.perturb_all=2; % Perturb a random selection of
                                             % all priors in each iteration. def =[0]
  % Perturb one a prior type at a time, according to some frequency
  options.mcmc.pert_strategy.i_pert = [1,3]; % only perturb prior 1 and 3
  options.mcmc.pert_strategy.i_pert = [2 8]; % perturb prior 3 80% of
                                              % the time and prior 1 20%
                                              % of the time
  % the default pertubation strategt is to select one prior model to
  % perturb at tandom for each iteration
  %% TEMPERING
  options.mcmc.n_chains=1; % set number of chains (def=1)
  options.mcmc.T=1; % set temperature of chains [1:n_chains]
  options.mcmc.chain_frequency_jump=0.1; % probability allowing a jump
                                          % between two chains
  %% ANNEALING (TEMPERATURE AS A FUNCTION OF ITERATION NUMBER)
  options.mcmc.anneal.i_begin=1; % default, iteration number when annealing begins
  options.mcmc.anneal.i_end=100000; % iteration number when annealing stops
  options.mcmc.anneal.T_begin=5; % Start temperature for annealing
  options.mcmc.anneal.T_end=1; % End temperature for annealing
  %% VERBOSITY
  The amount of text info displayed at the prompt, can be controlled by
  setenv('SIPPI_VERBOSE_LEVEL','2') % all: information on chain swapping
  setenv('SIPPI_VERBOSE_LEVEL','1') % information about seq-gibbs step update
  setenv('SIPPI_VERBOSE_LEVEL','0'); % [def] frequent update
  setenv('SIPPI_VERBOSE_LEVEL','-1'); % rare update om finish time
  setenv('SIPPI_VERBOSE_LEVEL','-2'); % indication of stop and start
  setenv('SIPPI_VERBOSE_LEVEL','-3'); % none
See also sippi_rejection
```

### 6.1.12 sippi\_prior

SIPPI 47 / 67

```
sippi_prior A priori models for SIPPI
 To generate a realization of the prior model defined by the prior structure use:
   [m_propose ,prior]=sippi_prior(prior);
 To generate a realization of the prior model defined by the prior structure,
 in the vicinity of a current model (using sequential Gibbs sampling) use:
   [m_propose,prior]=sippi_prior(prior,m_current);
 The following types of a priori models can be used
   % two point statistics bases
   GAUSSIAN
             [1D] : 1D generalized gaussian model
   UNIFORM [1D-3D] : 1D-3D uncorrelated uniform distribution
   CHOLESKY[1D-3D] : based on Cholesky decomposition
           [1D-3D] : based on the FFT-MA method (Multivariate Gaussian)
   FFTMA
   VISIM
           [1D-3D] : based on Sequential Gaussian and Direct Sequential simulation
           [1D-3D] : based on Sequential indicator SIMULATION
   % multiple point based statistics
   SNESIM_STD [1D-3D]: (SGEMS) based on a multiple point statistical model inferref from \leftrightarrow
       a training images. Relies in the SNESIM algorithm
   SNESIM [1D-3D] : (GSLIB STYLE) based on a multiple point statistical model inferref \leftrightarrow
      from a training images. Relies in the SNESIM algorithm
%%% SIMPLE EXAMPLE %%%
% A simple 2D multivariate Gaissian based prior model based on the
% FFT-MA method, can be defined using
   im=1:
   prior{im}.type='FFTMA';
   prior{im}.name='A SIMPLE PRIOR';
   prior{im}.x=[0:1:100];
   prior{im}.y=[0:1:100];
   prior{im}.m0=10;
   prior{im}.Va='1 Sph(10)';
   prior=sippi_prior_init(prior);
% A realization from this prior model can be generated using
   m=sippi_prior(prior);
% This realization can now be plotted using
   sippi_plot_prior(m,prior);
   imagesc(prior{1}.x,prior{1}.y,m{1})
%%% A PRIOR MODEL WITH SEVERAL 'TYPES OF A PRIORI MODEL'
   im=1:
   prior{im}.type='GAUSSIAN';
   prior{im}.m0=100;
   prior{im}.std=50;
   prior{im}.norm=100;
   im=im+1;
   prior{im}.type='FFTMA';
   prior{im}.x=[0:1:100];
   prior{im}.y=[0:1:100];
   prior{im}.m0=10;
   prior{im}.Cm='1 Sph(10)';
   im=im+1:
   prior{im}.type='VISIM';
   prior{im}.x=[0:1:100];
   prior{im}.y=[0:1:100];
   prior{im}.m0=10;
```

SIPPI 48 / 67

```
prior{im}.Cm='1 Sph(10)';
   im=im+1;
   prior{im}.type='SISIM';
   prior{im}.x=[0:1:100];
   prior{im}.y=[0:1:100];
   prior{im}.m0=10;
   prior{im}.Cm='1 Sph(10)';
   im=im+1;
   prior{im}.type='SNESIM';
   prior{im}.x=[0:1:100];
   prior{im}.y=[0:1:100];
   sippi_plot_prior(prior);
%% Sequential Gibbs sampling
   All a priori model types can be perturbed, such that a new realization
   is generated in the vicinity of a current model.
   To do this Sequential Gibbs Sampling is used.
   For more information, see <a href="matlab:web('http://dx.doi.org/10.1007/s10596" \leftrightarrow 
       -011-9271-1')">Hansen, T. M., Cordua, K. S., and Mosegaard, K., 2012. Inverse \ \leftrightarrow
       problems with non-trivial priors - Efficient solution through Sequential Gibbs \ \leftarrow
       Sampling. Computational Geosciences </a>.
   The type of sequential Gibbs sampling can be controlled in the
   'seq_gibbs' structures, e.g. prior{1}.seq_gibbs
   im=1:
   prior{im}.type='SNESIM';
   prior{im}.x=[0:1:100];
   prior{im}.y=[0:1:100];
   [m,prior]=sippi_prior(prior);
   prior{1}.seq_gibbs.step=1; % Large step--> independant realizations
   prior{1}.seq_gibbs.step=.1; % Smaller step--> Dependant realizations
   for i=1:30;
      [m,prior]=sippi_prior(prior,m); % One iteration of Sequential Gibbs
      sippi_plot_prior(prior,m);
   end
 See also: sippi_prior_init, sippi_plot_prior, sippi_plot_prior_sample, \leftrightarrow
     sippi_prior_set_steplength.m
 TMH/2012
```

### 6.1.13 sippi\_prior\_cholesky

```
sippi_prior_cholesky : Cholesky type Gaussian prior for SIPPI

% Example:
    ip=1;
    prior{ip}.type='cholesky';
    prior{ip}.m0=10;
    prior{ip}.Cm='.001 Nug(0) + 1 Gau(10)';
    prior{ip}.Cm='.001 Nug(0) + 1 Gau(10)';
    prior{ip}.x=0:1:100;linspace(0,100,20);
    prior{ip}.y=0:1:50;linspace(0,33,30);
    [m,prior]=sippi_prior_cholesky(prior);
    sippi_plot_prior(prior,m);

% Sequential Gibbs sampling
```

SIPPI 49 / 67

```
prior{1}.seq_gibbs.step=.1;
for i=1:100;
        [m,prior]=sippi_prior_cholesky(prior,m);
        sippi_plot_prior(prior,m);
        caxis([8 12]);drawnow;
end

% Prior covariance model
The prior covarince model can be setup using
    prior{ip}.m0=10;
    prior{ip}.m0=10;
    prior{ip}.Cm='.001 Nug(0) + 1 Gau(10)';
or
    prior{ip}.m0=10;
    and the 'Cmat' variable 'prior{ip}.Cmat' which much the contain a full
    nd X nd size covariance matrix.
    (it is computed the first the sippi_prior_cholesky is called)

See also: gaussian_simulation_cholesky
```

### 6.1.14 sippi\_prior\_dsim

```
sippi_prior_dsim : Direct simulation in SIPPI
Example:
prior{1}.type='dsim';
prior{1}.x=1:1:40;;
prior{1}.y=1:1:30;;
prior{1}.ti=channels;;
m=sippi_prior(prior);
sippi_plot_prior(prior,m);
% OPTIONAL OPTIONS
  prior{1}.options.n_cond [int]: number of conditional points (def=5)
  prior\{1\}.options.n_max_ite [int]: number of maximum iterations through the TI for \leftrightarrow
      matching patterns (def=200)
  prior{1}.options.plot
                          [int]: [0]:none, [1]:plot cond, [2]:storing movie (def=0)
  prior{1}.options.verbose [int]: [0] no infor to screen, [1]:some info (def=1)
TMH/2014
See also: sippi_prior_init, sippi_prior
```

### 6.1.15 sippi\_prior\_init

```
sippi_prior_init Initialize PRIOR structure for SIPPI
Call
```

SIPPI 50 / 67

```
prior=sippi_prior_init(prior);
See also sippi_prior
```

### 6.1.16 sippi\_prior\_mps

```
Sippi_prior_mps : prior based on MPS

Using SNESIM/ENESIM FROM
https://github.com/cultpenguin/mps

% Example:
    ip=1;
    prior{ip}.type='mps';
    prior{ip}.method='mps_snesim';
    prior{ip}.x=1:1:80;
    prior{ip}.y=1:1:80;
    prior{ip}.ti=channels;
    % prior{ip}.ti=maze;

m=sippi_prior(prior);
    sippi_plot_prior(prior,m)
    figure(1);imagesc(prior{ip}.ti);axis image
```

### 6.1.17 sippi prior plurigaussian

```
sippi_prior_plurigaussian: Plurigaussian type prior for SIPPI
% Example:
   % PluriGaussian based on one Gaussian model / truncated Gaussian
   ip=1;
   prior{ip}.type='plurigaussian';
   prior{ip}.x=1:1:80;
   prior{ip}.y=1:1:80;
   prior{ip}.Cm='1 Gau(10)';
   prior{ip}.pg_map=[0 0 0 0 1 1 0 0 2 2 2];
   % PluriGaussian based on two Gaussian models
   ip=ip+1;
   prior{ip}.type='plurigaussian';
   prior{ip}.x=1:1:80;
   prior{ip}.y=1:1:80;
   prior{ip}.pg_prior{1}.Cm=' 1 Gau(10)';
   prior{ip}.pg_prior{2}.Cm=' 1 Sph(10,90,.4)';
   prior{ip}.pg_map=[0 0 0 1 1; 1 2 0 1 1; 1 1 1 1 1];
   [m,prior]=sippi_prior(prior);
   sippi_plot_prior(prior,m);
% Sequential Gibbs sampling
   prior{1}.seq_gibbs.step=.01;
       [m,prior]=sippi_prior(prior,m);
       sippi_plot_prior(prior,m);
       caxis([0 2]);drawnow;
   end
```

SIPPI 51/67

```
See also: sippi_prior, pg_transform
```

### 6.1.18 sippi\_prior\_set\_steplength

```
sippi_prior_set_steplength Set step length for Metropolis sampler in SIPPI
Call
    prior=sippi_prior_set_steplength(prior,mcmc,im);
```

### 6.1.19 sippi\_prior\_sisim

```
sippi_prior_sisim: SISIM (SGeMS) type prior for SIPPI
% Example:
    ip=1;
    prior{ip}.type='sisim';
    prior{ip}.x=1:1:80;
    prior{ip}.y=1:1:80;
    prior{ip}.Cm='1 Sph(60)';
    prior{ip}.marginal_prob=[.1 .4 .5];
    m=sippi_prior(prior);
    sippi_plot_prior(prior,m)
    % optionally a specific random seed can be set using
    prior{ip}.seed=1;
% Sequential Gibbs sampling type 1 (box selection of pixels)
    prior{ip}.seq_gibbs.type=1;%
    prior{ip}.seq_gibbs.step=10; % resim data in 10x10 pixel grids
    [m,prior]=sippi_prior(prior);
    for i=1:10;
       [m,prior]=sippi_prior(prior,m);
       sippi_plot_prior(prior,m);
       drawnow;
    end
% Sequential Gibbs sampling type 2 (random pixels)
    prior{ip}.seq_gibbs.type=2;%
    prior{ip}.seq_gibbs.step=.6; % Resim 60% of data
    [m,prior]=sippi_prior(prior);
    for i=1:10;
       [m,prior]=sippi_prior(prior,m);
       sippi_plot_prior(prior,m);
       drawnow;
    end
 See also: sippi_prior, sgems
```

### 6.1.20 sippi\_prior\_snesim

SIPPI 52 / 67

```
sippi_prior_snesim : SNESIM type Gaussian prior for SIPPI
                      Using SNESIM form
                      https://github.com/SCRFpublic/snesim-standalone
% Example:
   ip=1:
    prior{ip}.type='snesim';
    prior{ip}.x=1:1:80;
    prior{ip}.y=1:1:80;
    prior{ip}.ti=channels;
    % prior{ip}.ti=maze;
    m=sippi_prior(prior);
    sippi_plot_prior(prior,m)
    figure(1);imagesc(prior{ip}.ti);axis image
% Example: scaling and rotation
   ip=1:
    prior{ip}.type='snesim';
    prior{ip}.x=1:1:80;
    prior{ip}.y=1:1:80;
    prior{ip}.ti=channels;
    prior{ip}.scaling=[.1];
    prior{ip}.rotation=[10];
    m=sippi_prior(prior);
    sippi_plot_prior(prior,m)
    figure(1);imagesc(prior{ip}.ti);axis image
  % hard data are given using either matrix of 4 columns (x,y,z,val)
  % or as a 4 column EAS file (x,y,z,val)
   d_hard=[1 1 0 0; 1 2 0 0; 2 2 0 1 ];
   prior{ip}.hard_data=d_hard;
   write_eas('snesim_hard.dat',d_hard);
   prior{ip}.hard_data='snesim_hard.dat';
% Soft data
  % soft mush be provided as a matrix of the same size as the simulation
   % grid
   d_soft(:,:,1)=ones(80,80).*NaN
   d_soft(:,:,2)=1-d_soft(:,:,1);
   prior{ip}.soft_data_grid=d_soft;
  % Optionally the soft data can be provided as point data, in which case
  % a grid, the size of the simulation grid, with soft data values will be computed
   d_soft=[1 1 0 0.2 0.8; 1 2 0 0.1 0.9; 2 2 0 0.05 0.95];
   prior{ip}.soft_data=d_soft;
% Sequential Gibbs sampling type 1 (box selection of pixels)
    prior{ip}.seq_gibbs.type=1;%
    prior{ip}.seq_gibbs.step=10; % resim data in 10x10 pixel grids
    [m,prior]=sippi_prior(prior);
    for i=1:10;
       [m,prior]=sippi_prior(prior,m);
       sippi_plot_prior(prior,m);
       drawnow;
    end
```

SIPPI 53 / 67

```
% Sequential Gibbs sampling type 2 (random pixels)
    prior{ip}.seq_gibbs.type=2;%
    prior{ip}.seq_gibbs.step=.6; % Resim 60% of data
    [m,prior]=sippi_prior(prior);
    for i=1:10;
        [m,prior]=sippi_prior(prior,m);
        sippi_plot_prior(prior,m);
        drawnow;
    end

See also: sippi_prior, ti
```

### 6.1.21 sippi\_prior\_snesim\_std

```
sippi_prior_snesim_std : SNESIM_STD (SGeMS) type Gaussian prior for SIPPI
                      Requires SGeMS version 2.1b, available from
                      http://sgems.sourceforge.net/?q=node/77
% Example:
    ip=1;
    prior{ip}.type='snesim_std';
    prior{ip}.x=1:1:80;
    prior{ip}.y=1:1:80;
    prior{ip}.ti=channels;
    % prior{ip}.ti=maze;
    m=sippi_prior(prior);
    sippi_plot_prior(prior,m)
    figure(1);imagesc(prior{ip}.ti);axis image
% Example: scaling and rotation
    ip=1;
    prior{ip}.type='snesim_std';
    prior{ip}.x=1:1:80;
    prior{ip}.y=1:1:80;
    prior{ip}.ti=channels;
    prior{ip}.scaling=[.1];
    prior{ip}.rotation=[10];
    m=sippi_prior(prior);
    sippi_plot_prior(prior,m)
    figure(1);imagesc(prior{ip}.ti);axis image
% Sequential Gibbs sampling type 1 (box selection of pixels)
    prior{ip}.seq_gibbs.type=1;%
    prior{ip}.seq_gibbs.step=10; % resim data in 10x10 pixel grids
    [m,prior]=sippi_prior(prior);
    for i=1:10;
       [m,prior]=sippi_prior(prior,m);
       sippi_plot_prior(prior,m);
       drawnow;
    end
% Sequential Gibbs sampling type 2 (random pixels)
    prior{ip}.seq_gibbs.type=2;%
    prior{ip}.seq_gibbs.step=.6; % Resim 60% of data
    [m,prior]=sippi_prior(prior);
```

SIPPI 54 / 67

```
for i=1:10;
     [m,prior]=sippi_prior(prior,m);
     sippi_plot_prior(prior,m);
     drawnow;
end

See also: sippi_prior, sippi_prior_snbesim, ti
```

### 6.1.22 sippi\_prior\_uniform

```
sippi_prior_uniform : Uniform prior for SIPPI
% Example 1D uniform
  ip=1;
   prior{ip}.type='uniform';
   prior{ip}.min=10;
   prior{ip}.max=25;
   [m,prior]=sippi_prior_uniform(prior);
   sippi_plot_prior_sample(prior);
% Example 10D uniform
  ip=1;
   prior{ip}.type='uniform';
   prior{ip}.x=1:1:10; % As dimensions are uncorrelated, only the length
                       % of prior{ip}.x matters, not its actual values.
   prior{ip}.min=10;
   prior{ip}.max=25;
   [m,prior]=sippi_prior_uniform(prior);
   sippi_plot_prior_sample(prior);
% Sequential Gibbs sampling
   prior{1}.seq_gibbs.step=.1;
   for i=1:1000;
       [m,prior]=sippi_prior(prior,m);
       mm(i)=m{1};
   end
   subplot(1,2,1);plot(mm);
   subplot(1,2,2);hist(mm);
 TMH/2014
 See also: sippi_prior_init, sippi_prior
```

### 6.1.23 sippi\_prior\_visim

```
sippi_prior_visim : VISIM type Gaussian prior for SIPPI

% Example:
    ip=1;
    prior{ip}.type='visim';
    prior{ip}.x=1:1:80;
    prior{ip}.y=1:1:80;
    prior{ip}. y=nior{ip}. Cm='1 Sph(60)';
    m=sippi_prior(prior);
```

SIPPI 55 / 67

```
sippi_plot_prior(prior,m)
    % optionally a specific random seed can be set using
    prior{ip}.seed=1;
% Sequential Gibbs sampling type 1 (box selection of pixels)
    prior{ip}.seq_gibbs.type=1;
    prior{ip}.seq_gibbs.step=10; % resim data in 10x10 pixel grids
    prior{ip}.cax=[-2 2];
    [m,prior]=sippi_prior(prior);
    for i=1:1000;
       [m,prior]=sippi_prior(prior,m);
       sippi_plot_prior(prior,m);
       drawnow;
    end
% Sequential Gibbs sampling type 2 (random pixels)
    prior{ip}.seq_gibbs.type=2;%
    prior\{ip\}.seq\_gibbs.step=.6; % Resim 60% of data
    [m,prior]=sippi_prior(prior);
    for i=1:10;
       [m,prior]=sippi_prior(prior,m);
       sippi_plot_prior(prior,m);
       drawnow;
    end
% TARGET DISTRIBUTION
 clear prior
 d_target=[7 8 9 10 11 11 12];
 ip=1;
 prior{ip}.type='visim';
 prior{ip}.d_target=d_target;
 prior{ip}.cax=[min(d_target) max(d_target)];
 prior{ip}.x=1:1:80;
 prior{ip}.y=1:1:80;
 prior{ip}.Cm=sprintf('%g Gau(20)',var(d_target));
 [m,prior]=sippi_prior(prior);
 sippi_plot_prior(prior,m);
 See also: sippi_prior, visim
```

### 6.1.24 sippi\_prior\_voronoi

```
sippi_prior_voronoi:

TMH/2014

Ex:
    prior{1}.type='voronoi';
    prior{1}.x=1:1:20;
    prior{1}.y=1:1:20;
    prior{1}.cells_N_min=2;
    prior{1}.cells_N_min=2;
    prior{1}.cells_N_max=100;
    prior{1}.cells_N=10;
    [m,prior]=sippi_prior(prior);
    sippi_plot_prior(prior,m);
```

SIPPI 56 / 67

```
See also: sippi_prior_init, sippi_prior
```

### 6.1.25 sippi\_rejection

```
sippi_rejection Rejection sampling
Call:
    options=sippi_rejection(data,prior,forward,options)
input arguments
  options.mcmc.i_plot
                        % maximum number of iterations
  options.mcmc.nite
  options.mcmc.logLmax [def=1]; % Maximum possible log-likelihood value
 options.mcmc.rejection_normalize_log = log(options.mcmc.Lmax)
  options.mcmc.adaptive_rejection=1, adaptive setting of maximum likelihood
                 (def=[0])
                 At each iteration logLmax will be set if log(L(m_cur)=>options.mcmc. \leftarrow
                     logLmax
  options.mcmc.max_run_time_hours = 1; % maximum runtime in hours
                                       % (overrides options.mcmc.nite if needed)
 options.mcmc.T = 1; % Tempering temperature. T=1, implies no tempering
See also sippi_metropolis
```

### 6.1.26 sippi\_set\_path

```
sippi_set_path Set paths for running sippi
```

### 6.2 SIPPI plotting commands

### 6.2.1 sippi\_colormap

```
sippi_colormap Default colormap for sippi

Call :
    sippi_colormap; % the same as sippi_colormap(3);

or :
    sippi_colormap(1) - Red Green Black
    sippi_colormap(2) - Red Green Blue Black
    sippi_colormap(3) - Jet
```

SIPPI 57 / 67

### 6.2.2 sippi\_get\_posterior\_data

```
sippi_get_posterior_data: load all data stored in mat-file

Call:

[data,prior,options,mcmc]=sippi_get_posterior_data(folder_name);
[data,prior,options,mcmc]=sippi_get_posterior_data(output_stuct);
```

### 6.2.3 sippi\_plot\_current\_model

```
sippi_plot_current_model Plots the current model during Metropolis sampling
Call :
    sippi_plot_current_model(mcmc,data,d,m_current,prior,options);
```

### 6.2.4 sippi\_plot\_data

```
sippi_plot_data: Plot data response
Call:
   sippi_plot_data(d,data);
sippi_plot_data provides a very simple way to plot data.
A more appropriate data plot can be implemented by implementing a new
mfile called "sippi_plot_data" and add it the Matlab path before the
main SIPPI folders
A maximum of options.plot.plot_data_max_data (def:=5) data is plotted.
Change the value in sippi_plot_defaults.m
A specific m-file for handling plotting for a specfic type of data can
be implemented, and can be called instead of sippi_plot_data, if the name
of the m-file is set in the options.sippi_plot_data_functions is set, as
  options.sippi_plot_data_function='sippi_plot_data_gpr';
then
  sippi_plot_data(d,data,[],options)
   sippi_plot_data(d,data,1:length(d),options);
will be equivalent to call
   sippi_plot_data_gpr(d,data);
See also sippi_plot_defaults, sippi_plot_data_gpr
```

### 6.2.5 sippi\_plot\_defaults

SIPPI 58 / 67

```
sippi_plot_defaults: Sets default options for ploting (such as fontsize)

Call :
    options==sippi_plot_defaults(options);

% ALWAYS USE DEFULT SETTING (overrules options.axis)
    overrule=1; % {default overrule=0)
    options==sippi_plot_defaults(options,overrule);

See also: sippi_plot_posterior, sippi_plot_posterior_2d_marg
```

### 6.2.6 sippi\_plot\_loglikelihood

```
sippi_plot_loglikelihood Plot loglikelihood time series

Call :
    acc=sippi_plot_loglikelihood(logL,i_acc,N,itext)
```

### 6.2.7 sippi\_plot\_model

### 6.2.8 sippi\_plot\_movie

```
sippi_plot_movie plot movie of prior and posterior realizations
Call:
 sippi_plot_movie(fname);
 sippi_plot_movie(fname,im_array,n_frames,skip_burnin,i_chain);
    fname : name of folder with results (e.g. options.txt)
    im_array : array of indexes of model parameters to make into movies
    n_frames [200] : number of frames in movie
    skip_burnin [200] : start movie after burn_in;
    i_chain[1]: make movie of chain number 'i_chain' (new 22/05/2014)
sippi_plot_movie('20130812_Metropolis');
sippi_plot_movie(options.txt);
%% 1000 realization including burn-in, for prior number 1
sippi_plot_movie('20130812_Metropolis',1,1000,0);
Using options.plot.skip_seq_gibbs=1, (set in sippi_plot_defaults)
removes realizations obtained using sequential Gibbs sampling
(equivalent to setting skip_burnin=1)
See also: sippi_plot_defaults
```

SIPPI 59 / 67

### 6.2.9 sippi\_plot\_posterior

```
sippi_plot_posterior Plot statistics from posterior sample

Call :
    sippi_plot_posterior(fname,im_arr,prior,options,n_reals);

See also sippi_plot_prior
```

### 6.2.10 sippi\_plot\_posterior\_2d\_marg

```
sippi_plot_posterior_2d_marg: plots 2D posterior marginal distributions

Call:
    [options,reals_all]=sippi_plot_posterior_2d_marg(options,prior,data,fname);

See also: sippi_plot_posterior
```

### 6.2.11 sippi\_plot\_posterior\_data

```
sippi_plot_posterior_data: plots posterior data and noise relaizations

Call
    [options]=sippi_plot_posterior_data(options,prior,data,forward);

See also: sippi_plot_posterior
```

### 6.2.12 sippi plot posterior loglikelihood

SIPPI 60 / 67

### 6.2.13 sippi\_plot\_posterior\_sample

```
sippi_plot_posterior_sample: plots posterior sample statistics

Call
    [options]=sippi_plot_posterior_sample(options,prior,data,forward);

See also: sippi_plot_posterior
```

### 6.2.14 sippi\_plot\_prior

```
Call :
    sippi_plot_prior (prior, m, im_array);

prior : Matlab structure for SIPPI prior model
    m : Matlab structure for SIPPI realization
    im_array : integer array of type of models to plot (typically 1)

Example
    m=sippi_prior(prior);
    sippi_plot_prior(prior, m);

m=sippi_prior(prior);
    sippi_plot_prior(prior, m, 2);

See also sippi_plot_prior, sippi_prior
```

### 6.2.15 sippi\_plot\_prior\_sample

```
sippi_plot_prior_sample Plot a sample of the prior in SIPPI

Call :
    sippi_plot_prior_sample(prior,im_array,n_reals,cax,options);

See also sippi_plot_posterior, sippi_plot_prior, sippi_prior
```

### 6.2.16 sippi\_plot\_set\_axis

```
sippi_plot_set_axis
see also sippi_plot_defaults
```

### 6.2.17 wiggle

SIPPI 61 / 67

```
wiggle : plot wiggle/VA/image plot
Call
  wiggle(Data); % wiggle plot
  wiggle(Data,scale); % scaled wiggle plot
  wiggle(x,t,Data); % wiggle plt
  wiggle(x,t,Data,'VA') % variable Area (pos->black;neg->transp)
  wiggle(x,t,Data,'VA2') % variable Area (pos->black;neg->red)
  wiggle(x,t,Data,'wiggle',scale); % Scaled wiggle
  wiggle(x,t,Data,'wiggle',scale,showmax); % Scaled wiggle and max
                                              showmax traces.
  wiggle(x,t,Data,'wiggle',scale,showmax,plimage); % wiggle + image
  wiggle(x,t,Data,'wiggle',scale,showmax,plimage,caxis); % wiggle +
Data : [nt,ntraces]
x : [1:ntraces] X axis (ex [SegyTraceheaders.offset])
t : [1:nt] Y axis
style : ['VA'] : Variable Area
        ['wiggle'] : Wiggle plot
scale : scaling factor, can be left empty as []
showmax [scalar] : max number of traces to show on display [def=100]
plimage [0/1]: Show image beneath wiggles [def=0];
caxis [min max]/[scalar] : amplitude range for colorscale
```

### 6.3 SIPPI toolbox: Traveltime tomography

### 6.3.1 calc\_Cd

```
Calc cd Setup a covariance model to account for borehole imperfections
Call: Cd=calc_Cd(ant_pos,var_uncor,var_cor1,var_cor2,L)
This function sets up a data covariance matrix that accounts for static
(i.e. correlated) data errors.
Inputs:
st ant_pos: A N x 4 array that contains N combinations of transmitter/source
and receiver positions. The first two columns are the x- and y-coordinates
of the transmitter/source position. The last two columns are the x- and
y-coordiantes of the receiver position.
* var_uncor: The variance of the uncorrelated data errors.
* var_cor1: The variance of the correlated data errors
related to the transmitter/source positions.
* var_cor2: The variance of the correlated data errors
related to the receiver positions.
* L: The correlation length for the correlation between the individual
transmitter/source or receiver positions using an exponential covariance
function. For typical static errors the correlation length is set to a
small number (e.g. 10^-6).
For more details and practical examples see:
Cordua et al., 2008 in Vadose zone journal.
Cordua et al., 2009 in Journal of applied geophysics.
Knud S. Cordua (2012)
```

SIPPI 62 / 67

### 6.3.2 eikonal

```
eikonal Traveltime computation by solving the eikonal equation
 tmap=eikonal(x,y,z,V,Sources,type);
 x,y,z: arrays defining the x,y, and z axis
 V: velocity field, with size (length(y),length(x),length(z));
 Sources [ndata,ndim] : Source positions
 type (optional): type of eikonal solver: [1]:Fast Marching(default), [2]:FD
  tmap\ [size(V)]: travel times computed everywhere in the velocity grid
%Example (2D):
  x=[1:1:100];
  y=1:1:100;
  z=1;
  V=ones(100,100);V(:,1:50)=2;
  Sources = [10 50;75 50];
  t=eikonal(x,y,z,V,Sources);
   subplot(1,2,1);imagesc(x,y,t(:,:,1,1));axis image;colorbar
   subplot(1,2,2); imagesc(x,y,t(:,:,1,2)); axis image; colorbar
 See also eikonal_traveltime
```

### 6.3.3 eikonal\_raylength

```
eikonal_raylength : Computes the raylength from S to R using the eikonal equaiton

Call:
   raylength=eikonal_raylength(x,y,v,S,R,tS,doPlot)
```

### 6.3.4 eikonal\_traveltime

```
eikonal_traveltime Computes traveltime between sources and receivers by solving the eikonal equation

t=eikonal_traveltime(x,y,z,V,Sources,Receivers,iuse,type);

x,y,z: arrays defining the x, y, and z axis
V: velocity field, with size (length(y),length(x),length(z));
Sources [ndata,ndim]: Source positions
Receivers [ndata,ndim]: Receiver positions
iuse (optional): optionally only use subset of data. eg.g i_use=[1 2 4];
type (optional): type of eikonal solver: [1]:Fast Marching(default), [2]:FD

tmap [size(V)]: travel times computed everywhere in the velocity grid

%Example (2%

Example 2d traveltime compuation

Example (2D):
x=[1:1:100];
y=1:1:100;
```

SIPPI 63 / 67

```
z=1;
V=ones(100,100);V(:,1:50)=2;
S=[50 50 1;50 50 1];
R=[90 90 1; 90 80 1];
t=eikonal_traveltime(x,y,z,V,S,R)

Example (3D):
    nx=50;ny=50;nz=50;
    x=1:1:nx;
    y=1:1:ny;
    z=1:1:nz;
V=ones(ny,nx,nz);V(:,1:50,:)=2;
S=[10 10 1;10 10 1;10 9 1];
R=[40 40 40; 40 39 40; 40 40 40];
t=eikonal_traveltime(x,y,z,V,S,R)
See also eikonal
```

### 6.3.5 kernel\_buursink\_2d

### 6.3.6 kernel\_finite\_2d

```
kernel_finite_2d 2D sensitivity kernels

Call:
    [Knorm,K,dt,options]=kernel_finite_2d(v_ref,x,y,S,R,freq,options);
```

### 6.3.7 kernel\_fresnel\_2d

```
kernel_fresnel_2d Sensitivity kernel for amplitude and first arrival

Call:
    [kernel_t,kernel_a,P_omega,omega]=kernel_fresnel_2d(v,x,y,S,R,omega,P_omega);

Based on Liu, Dong, Wang, Zhu and Ma, 2009, Sensitivity kernels for
```

SIPPI 64 / 67

```
seismic Fresenl volume Tomography, Geophysics, 75(5), U35-U46

See also kernel_fresnel_monochrome_2d

Run with no argument for an example.
```

### 6.3.8 kernel\_fresnel\_monochrome\_2d

```
kernel_fresnel_monochrome_2d 2D monchrome kernel for amplitude and first arrival

Call:
    [kernel_t,kernel_a]=kernel_fresnel_monochrome_2d(v,x,y,S,R,omega);
or
    [kernel_t,kernel_a]=kernel_fresnel_monochrome_2d(v,x,y,S,R,omega,L,L1,L2);

Based on Liu, Dong, Wang, Zhu and Ma, 2009, Sensitivity kernels for seismic Fresenl volume Tomography, Geophysics, 75(5), U35-U46

See also, kernel_fresnel_2d
```

### 6.3.9 kernel\_multiple

```
kernel_multiple Computes the sensitivity kernel for a wave traveling
from S to R.
  [K,RAY,Gk,Gray,timeS,timeR,raypath]=kernel_multiple(Vel,x,y,z,S,R,T,alpha,Knorm);
IN:
  Vel [ny,nx] : Velocity field
  x [1:nx]:
  y [1:ny]
  z [1:nz] :
  S [1,3] : Location of Source
  R [1,3] : Location of Receiver
  T : Donminant period
  alpha: controls exponential decay away ray path
  Knorm [1] : normaliztion of K [0]:none, K:[1]:vertical
OUT:
  K : Sensitivity kernel
  R : Ray sensitivity kernel (High Frequency approx)
  timeS : travel computed form Source
  timeR : travel computed form Receiver
  raypath [nraydata,ndim] : the center of the raypath
The sensitivity is the length travelled in each cell.
See also : fast_fd_2d
TMH/2006
```

SIPPI 65 / 67

### 6.3.10 kernel\_slowness\_to\_velocity

```
kernel_slowness_to_velocity Converts from slowness to velocity parameterizations

G : kernel [1,nkernels]

V : Velocity field (

CALL:
    G_vel=kernel_slowness_to_velocity(G,V);

or
    [G_vel,v_obs]=kernel_slowness_to_velocity(G,V,t);

or
    [G_vel,v_obs,Cd_v]=kernel_slowness_to_velocity(G,V,t,Cd);
```

### 6.3.11 mspectrum

```
mspectrum : Amplitude and Power spectrum
Call :
    function [A,P,smoothP,kx]=mspectrum(x,dx)

1D (A)mplitude and (P)owerspectrum of x-series with spacing dx
```

### 6.3.12 munk\_fresnel\_2d

```
2D frechet kernel, First Fresnel Zone

See Jensen, Jacobsen, Christensen-Dalsgaard (2000) Solar Physics 192.

Call:
S=munk_fresnel_2d(T,dt,alpha,As,Ar,K);

T: dominant period
dt:
alpha: degree of cancellation
As: Amplitude fo the wavefield propagating from the source
Ar: Amplitude fo the wavefield propagating from the receiver
K: normalization factor
```

### 6.3.13 munk\_fresnel\_3d

```
3D frechet kernel, First Fresnel Zone

See Jensen, Jacobsen, Christensen-Dalsgaard (2000) Solar Physics 192.

Call:
```

SIPPI 66 / 67

### 6.3.14 sippi\_forward\_traveltime

```
call :
    [d,forward,prior,data]=sippi_forward_traveltime(m,forward,prior,data)

forward.type determines the method used to compute travel times
forward.type='ray';
forward.type='fat';
forward.type='eikonal';
forward.type='born';

forward.sources [ndata,ndim]: Source locations
forward.receivers [ndata,ndim]: Receiver locations
```

### 6.3.15 tomography\_kernel

```
tomography_kernel Computes the sensitivity kernel for a wave traveling from S to R.
  [K,RAY,Gk,Gray,timeS,timeR,raypath]=tomography_kernel(Vel,x,y,z,S,R,T,alpha,Knorm);
IN:
  Vel [ny,nx] : Velocity field
  x [1:nx]:
  y [1:ny]
  z [1:nz] :
  S [1,3] : Location of Source
  R [1,3]: Location of Receiver
  T : Donminant period
  alpha: controls exponential decay away ray path
  Knorm [1] : normaliztion of K [0]:none, K:[1]:vertical
OUT:
  K : Sensitivity kernel
  R : Ray sensitivity kernel (High Frequency approx)
  timeS : travel computed form Source
  timeR : travel computed form Receiver
  raypath [nraydata,ndim] : the center of the raypath
The sensitivity is the length travelled in each cell.
```

### 6.4 SIPPI toolbox: Covariance inference

### 6.4.1 sippi\_forward\_covariance\_inference

```
sippi_forward_covariance_inference : Probabilitsic covariance inference
Call :
```

SIPPI 67 / 67

```
[d,forward,prior,data]=sippi_forward_covariance_inference(m,forward,prior,data,id,im)
 forward.pos_known : [x' y' z'], [ndata,ndim] with position of observed data
 forward.G : Forward operator
 Prior covariance model, N(m0,Cm) is chosen as
 forward.m0 : initial mean model
 forward.Cm/forward.Va : inital covariance model
 prior{im}.m0
 prior{im}.type (round(type) is itype)
 prior{im}.range_1
 prior{im}.range_2
 prior{im}.range_3
 prior{im}.ang_1
 prior{im}.ang_2
 prior{im}.ang_3
 prior{im}.sill
prior{im}.nugget_fraction
See Hansen et al. (201X), A general probabilistic approach for inference of Gaussian \,\leftrightarrow\,
   model parameters from noisy data of point and volume support. Submitted to \ \hookleftarrow
   Mathematical Geosciences, 2014.
See also: sippi_forward
```