Computer networks I- Data Communications


D N Ranasinghe

preliminaries

- Text books and assignments see LMS for details
- Course will be augmented with material from CISCO
- Why study computer networks?
 - ICT 'communication'
 - Working/studying/business from home these days depends on communication
 - Cloud services provision depends on it
 - New developments software defined networks
 - Etc., etc.,

fundamentals

- Infrastructure and protocols for Information sharing
 - infrastructure network channels (wired, wireless, fixed, mobile, point to point and broadcast etc,)
 - channel properties (bandwidth, noise, delay distortion, attenuation)
 - protocols bipartisan agreement for information exchange (start, exchange while correcting errors, terminate)
- types of information
 - man made, machine made, continuous, discrete, 1-D, 2-D etc.
- what is information: quantified by Claude Shannon; e.g., a single tone does not carry any 'useful' information




physics of communication


- time domain and frequency domain (spectrum) representations
- Fourier series representation of any time domain periodic signal as the sum of a dc component and a mix of sine/cosine harmonics
- e.g., spectrum of a pulse train as a Sinc function with infinite number of frequency components
- the need to limit the spread of frequency components to fit into the available bandwidth

 $g(t) = \frac{1}{2} \cdot c + \sum_{\alpha n \in Sin} h \omega t) +$ When $w = 2\pi - P$; $f = \frac{1}{T} \frac{\text{cycles/sec}}{\text{sec}}$ and: $c = \frac{2}{7} \int_{0}^{7} g(t) \cdot At$ an = 2 (Tg(t). Sin hat) dt Notational Leis to A.c. term and the rest, sine a Cosin Frequencies

Consider a typical discrete signal. Fu this, $c = \frac{2}{7} \int_{0}^{1/2} dt = \frac{2}{7} \int_{0}^{1/2} dt$ $\alpha_{n} = \frac{2}{7} \left(g.t. \right) \sin(n\omega t) At = \frac{1}{2}$ = 2 STA. SILINGON AL = Z [- GSNGT]TA oltained by substituting with [1-(05 ntl)]/ Similarly we an obtain bn = 2 Sin nt. The reform, 9(+)===c+Zan. Sin nwt+Zbn. losnwt = 1.1 + 2 1. [1- (orn T). 5m (wt) n=1 + 9 - SIGNTT. 65 (W t)// Is the Fourier senes representation for Ne binary (disante) signal alove AM Gs (nwb) terms are gers for = 1.. 00 TILUS: g(t)= 12 + 1 [SIN 60 t + 2 SIN 360 t + 2 SIN 560 t

Free (1) (1) Freg speiform & de + all harmonies.






• Exercises:

- For the pulse train given, obtain the Fourier series representation
- What happens to the reconstructed signal if higher harmonics are truncated?

- continuous time to discrete time and vice-versa conversion
 - Continuous time -> discrete time is typically by sampling followed by quantizing each sample
 - Discrete time -> recovery of original continuous time signal is by low pass filtering (subject to Nyquist sampling condition)
- multiply continuous time signal by a sampling signal, quantize each sample (assign a bit length representation for each signal amplitude)
- at the receiver, reverse the process using DAC and Low pass filter; resultant replicated frequency spectrum



Suppose the frequency spectrum of $f(t) \rightarrow f(\omega)$: thin the spectrum of s(t) x f(t) WOUND look like which is a replicated version of FW) Here, sampling vate S = 1 samples per

Nyquist's sampling theorem

- Digitisation of analogue signals
 - First, band limit the analogue signal to fmax
 - Sample the analogue signal at rate S samples per second
 - Quantize each analogue sample as n-bits per sample (i.e., 2ⁿ discrete levels per sample)
 - frequency spectrum of the sampled analogue signal looks like a repeated pattern of original analogue spectrum at each S frequency component
 - To avoid 'aliasing' (overlapping of spectra), it can be seen that the sampling rate should be S > 2fmax.

The replicated version of F(w) over S(w) mould not exhibit spectrum overlaps. That is, (2 - +) 32 fmax; interval 7 separation. 5>2 fmax. Quantisation Ead andoque sample can be quantises & n-bits (= 2" levels).

Exercises

- Find out a mistake in one of the diagrams here
- What happens if S < 2fmax?

- bits/second (bit rate) = sampling rate or baud rate (samples/sec) x quantisation (bits/sample)
- Suppose S = 2fmax, then the raw bit rate of the digitized analogue signal is n.S (bits per second)
- Simple example of PSTN PCM coding
 - at 4kHz voice, the sampling rate is 8000 samples /sec
 - For typical voice, 8 bits/sample suffices
 - So, the raw PCM bit rate is 64kbps. For example in ADSL to the home, the bandwidth restriction is removed and a higher data rates in the order of a few Mbps is achieved

- Now consider data signals.
- when encoded as a voltage, signal looks like 1 bit per sample, and 1 sample in each T seconds (= 1/T samples per second)
- Since bit rate (bits per second) = bits per sample x samples per second, for any given fixed sample rate (= Baud rate), we can increase the bit rate by increasing the number of bits/sample encoding
- For example, we can group 2 bits per sample, leading to 4 distinct quantisation levels (voltage, phase as in QPSK, wavelength as in WDM etc).
- Bit rate will increase but the down side is the increased quantized levels will interfere with the channel noise

Typical data signal:

110010110011011110016...

Here, we could take one bit for sample; 2 bits per sample 3 bits per sample er in bit groups.

TLa i

1,1,0,0,1,0,1,1,0,0....

11,00,10,11,00,11,01,-...

110,010,110,011,011, et

and uncolo each bit group as

one Voltage level

Let ead bitgroup be a sample of T (sec) duration.

OV,

T T T T

10

10

1. T T

Manual Manual

Win 2. bits pur sample.

Hevers of quantisation (00,01,10,11).

Authoritime T is fixed, where I bit or

multiple bits. Noise can interfere, when multiple

a newtration (exist

Shannon's noisy channel capacity theorem

- Says that the maximum bit rate that can be supported by a channel of bandwidth W with a signal to noise of SNR is W.log2 (1 + SNR)
- Signal quality of a channel is measured by the Signal to Noise Ratio (SNR) given in deci Bels (dB) a logarithmic value.
- For example, if SNR is 30dB, then 30 (dB) = 10 log (base 10) SNR, where SNR is 10³ or 1000 in linear terms
- Therefore for a 4 kHz channel with 30dB SNR, the max. bit rate is around 40kbps according to Shannon's theorem

- Aligning with the Nyquists sampling theorem, with a minimum sampling rate of 2x4k samples per second, to reach a bit rate of 40kbps, the maximum quantisation allowed is (40/8 = 5) bits per sample encoding
- this gives the allowed number of quantisation levels as 2^5
- Therefore for a 4KHz channel, in the presence of a noise level of 30dB, we cannot quantize at 8 bits/sample, but only at 5 bits/sample, just to avoid the discrete signal being corrupted by noise, and to recover the bits correctly at the receive end

Shannor's noisy channel theorem: max bit rate = W. (09 (1+5NR). 30 (dociber) = 12/09 SWR SNN (linear) = 103 ~ 1823 :. max bot rote = 4x103 log (1024) for W = 4 KHz. :. max 6 mitt = 40 Kb p5 // How many bits/sample grouping will the represent? using bps = sampleysec x Lats/sample 46×103 = (2×4000) x b x /sxmple ... (max) bits/sample = 5.


Exercises


- In some text books Shannon's theorem for the noisy channel and Nyquist's theorem for the noiseless channel is presented separately. Here we do not do so. Try to reason why.
- With the sampling rate fixed, why cannot the number of quantisation levels be increased indefinitely to achieve a higher bit rate?

Signal Encoding

- How to condition information to be sent over a channel?
- a simple data stream can be encoded in to a voltage signal (to be transmitted over wire) in the form of a NRZ (non-return-to-zero) format
- main problem with this encoding is that it has lost clock information; when a series of 11...1 are transmitted there is no (1->0) transition that can be detected by receiver, in order to lock on to the signal
- For the correct sampling of the data sent by the transmitter, the receiver requires clock synchronization
- self-clocking information can be embedded if NRZ is converted to RTZ (return-to-zero)

- Manchester code is an example of a self clocking signal encoding; also its spectrum has no dc component as it is bipolar (+/-v)
- if self-clocking is embedded in data, it is called 'asynchronous', else if data is followed by special clock pattern, then it is called 'synchronous'
- No free lunch when clocking is embedded, the encoded signal has twice the sampling rate due to halved sampling width (each sample width is now T/2, and not T), so it requires twice the bandwidth as the original






Signal multiplexing

- combining signals to make full use of the available wide bandwidth of 'trunk' infrastructure
- FDM, TDM and statistical TDM
- FDM analogue signal channels are spaced over in 'raised blocks of frequency'
- TDM digital signal channels are spaced over in time with a distinct slot per channel of 125 microsecond duration containing 8 bits of that channel
- e.g., 30 channels of (equivalent 4kHz analogue voice) each 64kbps data stream can be combined to obtain a 1.92 Mbps trunk
- since clocking is not embedded, 2 additional channels with clocking/signalling is added, so this becomes a 'synchronous' transmission
- called a 30B+2D PCM trunk with a data rate (64 x 32 =)2.048 Mbps

FDM

Typical 4KHz viria channels combined on a 'movedup' frequency axis. Broad bandwidth can carry many maltiplused channels.



- statistical TD multiplexing consider two broad traffic types 'digitized voice/video' and database query/web browsing
- browsing/query is intermittent whereas the other is continuous in time
- if data flows continuously, can allocate channels incrementally (i.e., TDM) and if data is intermittent, in order to avoid waste of empty slots, channels should be randomly allocated based on the activity level (i.e., statistical multiplexing)
- in TDM, both Tx and Rx know that channels rotate in sequence
- in statistical multiplexing only way to inform Rx of the identity of the data slot, is by attaching a 'label' to the data 'packet'; this label is the 'address' and forms the basis of packet switching

Statistical TDM Wastog resident, allocate channel slots if contempending shehrers are Streaming data intermittent data voice/video de query/browsing ch - dr ch3 ch5 ch16 ch1, ch2 ch3 - ch · only active channels combined istatistically combined TDM

Stat. TDM grue Vise to Packet switzling. WhyT Without Synchronisation possible as in Thm, only way to Rx to Identify channel content was ty a latel, or address of the (ontent (packet) Data packet (SOUVCE Stat Tom Channel + Nest)

Error detection and correction

- 3 modes of communication simplex (one way only), half duplex (one way at a time), full duplex (both ways simultaneously)
- error correction applies for simplex: receiver must self-correct as it cannot request for repeat transmits
- military and space communications as simplex scenarios
- a typical data packet can contain a linear, cyclic or polynomial codes based code block to automatically correct data errors
- in duplex, error detection and request for retransmission can be used; simple parity check as a 1-bit error detection code
- More the redundancy built into data, easier to detect/correct errors

one way transmission (simplex) two way transmission (duples) EVVOV VE 10 ULVY (& ask TX 1. resend) if Simplex only. duplex ok

Evver detection - simple parilty bit data triplicate add officity 000 000: 111 . [11:0 Party but can detect only 1-bit evrors, not multiplebut errors.

Exercises

- Compare Manchester encoding of a data signal with that of HDB3 encoding. What are the differences?
- What is the significance of a signal encoding having zero dc component?
- In the 30 channel TDM/PCM scheme, how do we get a channel width of 125 microseconds?

Exercises

- Another way to classify traffic is real time traffic vs. store-andforward traffic. Where would voice/video fall?
- If we use TDM for store-andforward traffic, the overall trunk utilization efficiency will fall. Discuss.
- Show that the 3-bit code shown in the diagram can not only detect errors, but also can correct errors.

Multiple access schemes


- Allocating a common or shared channel resource (time, bandwidth) among many competitive senders and receivers
- Scheme depends on the traffic type: if traffic is streaming like (e.g. 64kbps -> 128 packets/sec of 64 byte packets) then it is fair to assign a permanent slot in time or frequency for that channel (e.g. TDM/single Tx or TDMA/multiple Tx, for slotted time)
- Granting a permanent slot (like the priority bus lane on a shared road) is a *static* resource allocation method

Straming

Poisson traffic model If inter-arrival times are exponentially distributed, i.e., PAF(inter-orriver)= > e - >+ wher I is mean there are val duration, then we say, the number of arrivals it within an interval [0, T] is given by xk.e-x; ulidisa Poisson pAf

- alternative to static channel allocation is dynamic channel allocation, i.e., allocate on demand
- data traffic (like those ~30 years ago) had a Poisson arrival process (inter arrival times exponentially distributed leading to the number of arrivals in an interval (0,T) being Poisson distributed)
- such traffic is best assigned the resources, on demand
- Statistical TDM studied earlier is an 'on demand' allocation method for single Tx case
- For multiple Tx, dynamic channel allocation can be done deterministically (Token rotating in round robin) or probabilistically (random access, with a chance of collision)

For data with Poisson Feature $\top \times 1$ channel allocation




- probabilistic schemes: aloha, carrier sense multiple access (CSMA) and variants like CSMA/CD, CSMA/CA...
- fundamental principle in probabilistic schemes: listen before talk as it takes finite time for signal propagation and to avoid collisions

Exercises

 Dynamic or 'on demand' channel allocation is more suitable for Poisson like data traffic. Here too, we have two options: deterministic or probabilistic channel access. Under heavy traffic conditions deterministic access is preferred to probabilistic access. Why?

Aloha

- One of the earliest attempts in packet data communications (1970's)
- fixed multiple radio Tx/Rx units within overlapping radio coverage areas broadcasting packets at arbitrary time instances
- Packets are generated at random intervals (inter packet gaps = exponentially distributed) at each Tx
- Protocol
 - If Tx has data to send, send data packet
 - If Tx, while transmitting data, also receives data from another Tx, then a 'collision' has occurred; re send data



Aloha

$$\frac{T_{X}}{R_{X}} | \otimes Z$$

$$\frac{T_$$

- Suppose the packet transmit time is tau (a constant), then the vulnerable period is 2.tau (see explanation)
- Suppose the total traffic load on the shared channel is G (packets per tau interval), then G is distributed with a Poisson pdf
- Within a (0, 2tau) interval the total load is 2G and that the probability $[k=0 \text{ colliding events in } (0, 2tau)] = e^-2G$.
- Therefore, the carried load (or the throughput) = S = G.e^-2G. Plot of Aloha shows that maximum efficiency is around 20%, and this is due to too many collisions caused by transmitting haphazardly

Vulnerable period Aloha For TX-B packet transmitting at to: (1) If TX-A starts at E,7 to-Z or (ii) if Tx-c starts at t2 < to+7 TX-B 1 = (Ket will collide Lin either We define vulnerable period of TX-B as t2-t1 = 22.


Grenerally on any probabilistic Shared access channel: total load = carried load

(5064 throughput)

(packet)

(retransmissions)

time Suppose the total load seen on Alcha channel = a (packets per Which should be Poisson distillated. That is: PAF(IOad) = G. exr(-G) = Pr[K-events in (0, T)]



Since the load seen within a 2T-vulherable Period is 2G. PV [K=0 evants in (0, 20)]= 25, e $p \sim [no collision] = e^{-2Q}$ in The fraction of total load Grahis which suffers no comissions = G. e-2G = good twoughput = carried load =S. //


Exercises

• (pure) aloha is a fundamental model of probabilistic multi access schemes. Prove that its maximum throughput is 1/2e and that occurs at G=0.5, as confirmed by the graph.

CSMA/CD principles

- Carrier Sense Multiple Access with Collision Detection
- Carrier sensing (listen before talk) can improve efficiency; stopping when a collision is detected can improve further
- CSMA/CD is used in Ethernet (IEEE standard 802.3)
- Protocol on a bus based shared medium:
 - If medium 'silent' then send
 - Listen while sending; if collision detected stop sending and retry later
- Suppose the distance between two nodes A and B is d (meters) then, time for A's first bit to reach B is (tau = d/c), where c=EM propagation velocity; if B, sensing the channel idle, has also been transmitting during this time, the first bit of B will collide with first bit of A at t=tau; this collision will be heard by A, only after a further tau time, that is at (2.d/c)

csmA/cD or a bus based shared channel now transmitting Sand



CSMB C)

According to the propagation diagram

A'should transmit for at least 2 T (where T = A) time, to properly Auteut any whision with B' Nous T(sec) = distana hetwich AKB (d) E-m veloity on makia (<) If Aata transmit vate of A is R (bps) then, PROKET length (orner ponding to 2T = R. 27 = R. (2d) bits. Packet = minimum /

Exercises

- CSMA/CD is well studied because of its Ethernet origins. For a copper cable of length 1km acting as the shared medium, with each node able to transmit data at 3Mbps, what is the permissible minimum packet length? Assume c=2x10E8 m/s.
- What is the total time wasted in the case of a worse case collision?

- In other words, A's packet length should be at least R.(2d/c), in order that A detects a possible collision with B, where R is the source transmission rate
- On a collision, A and B both will stop transmitting and will only re-start to sense the channel after a random interval (exponentially lengthening after each successive collision)
- Ethernet technology is widely used starting from 3Mbps, 10Mbps etc but now, the shared access resolution protocol is superseded by switched Ethernet at 100Mbps, 1Gbps and 10Gbps over copper and fibre
- Under heavy traffic, shared Ethernet has a low efficiency of around 40% but better than aloha