# GBDK 2020 Docs

4.3.0

Generated by Doxygen 1.9.1

Mon May 13 2024 22:45:24

1 General Documentation	1
1.1 Introduction	2
1.2 About the Documentation	2
1.3 About GBDK	2
1.4 Historical Info and Links	2
2 Getting Started	2
2.1 1. Download a Release and unzip it	3
2.1.1 Known Issue: Windows and folder names with spaces on non-C drives	3
2.2 2. Compile Example projects	3
2.2.1 Windows (without Make installed):	3
2.2.2 Linux / macOS / Windows with Make installed:	3
2.3 3. Use a Template	4
2.4 4. If you use GBTD / GBMB, get the fixed version	4
2.5 5. Review Coding Guidelines	4
2.6 6. Hardware and Resources	4
2.7 7. Set up C Source debugging	4
2.8 8. Try a GBDK Tutorial	5
2.9 9. Read up!	5
2.10 10. Need help?	5
2.11 Migrating From Pre-GBDK-2020 Tutorials	5
2.11.1 Also see:	5
2.11.2 Use auto-banking	5
2.11.3 Non-standard types (UINT8, etc)	5
2.11.4 If using GBTD / GBMB, get the fixed version	5
2.11.5 LCC and SDCC flags that are not needed	5
2.11.6 ROM Header Settings (such as Color, SGB, etc)	6
2.11.7 GBDK Header include changes	6
2.11.8 Include .h headers, not .c source files	6
2.11.9 Use the Template Projects	6
2.11.10 Use hUGEtracker instead of gbt_player	6
3 Links, Tools and Debugging	6
3.1 SDCC Compiler Suite User Manual	6
3.2 Getting Help	6
3.3 Game Boy Documentation	7
3.4 Sega Master System / Game Gear Documentation	7
3.5 Tutorials	7
3.6 Example code	7
3.7 Graphics Tools	7
3.8 Music And Sound Effects	8
3.9 Emulators	8
3.10 Debugging tools	8

	3.11 Optimizing Assembly	9
	3.12 Continuous Integration and Deployment	9
4	Using GBDK	9
	4.1 Interrupts	9
	4.1.1 Available Interrupts	10
	4.1.2 Adding your own interrupt handler	10
	4.1.3 Using your own Interrupt Dispatcher	10
	4.1.4 Returning from Interrupts and STAT mode	11
	4.2 What GBDK does automatically and behind the scenes	11
	4.2.1 NES console	11
	4.2.2 OAM (VRAM Sprite Attribute Table)	11
	4.2.3 Graphics Tile Maps and Data on Startup	11
	4.2.4 Font tiles when using stdio.h	11
	4.2.5 Default Interrupt Service Handlers (ISRs)	11
	4.2.6 Ensuring Safe Access to Graphics Memory	11
	4.3 Compression	12
	4.4 Copying Functions to RAM and HIRAM	12
	4.5 Mixing C and Assembly	12
	4.5.1 Inline ASM within C source files	12
	4.5.2 In Separate ASM files	13
	4.6 Including binary files in C source with incbin	13
	4.7 Known Issues and Limitations	13
	4.7.1 SDCC	13
5	Coding Guidelines	14
	5.1 Learning C / C fundamentals	14
	5.1.1 General C tutorials	14
	5.1.2 Embedded C introductions	14
	5.1.3 Game Boy games in C	14
	5.2 Understanding the hardware	14
	5.3 Writing optimal C code for the Game Boy and SDCC	14
	5.3.1 Tools	14
	5.3.2 Avoid Reading from VRAM	15
	5.3.3 Variables	15
	5.3.4 Code structure	16
	5.3.5 GBDK API/Library	16
	5.3.6 Toolchain	17
	5.3.7 Constants, Signed-ness and Overflows	17
	5.3.8 Chars and vararg functions	18
	5.4 When C isn't fast enough	18
	5.4.1 Reusable Local Labels and Inline ASM	18
	5.4.2 Variables and registers	18

	5.4.3 Segments / Areas	19
	5.4.4 Calling convention	19
6 I	ROM/RAM Banking and MBCs	20
	6.1 ROM/RAM Banking and MBCs (Memory Bank Controllers)	20
	6.1.1 Non-banked cartridges	21
	6.1.2 MBC Banked cartridges (Memory Bank Controllers)	21
	6.1.3 Recommended MBC type	21
	6.2 Working with Banks	21
	6.2.1 Setting the ROM bank for a Source file	21
	6.2.2 Setting the RAM bank for a Source file	22
	6.2.3 Setting the MBC and number of ROM & RAM banks available	22
	6.2.4 MBC Type Chart	22
	6.2.5 Getting Bank Numbers	23
	6.2.6 Banking and Functions	23
	6.2.7 Const Data (Variables in ROM)	24
	6.2.8 Variables in RAM	24
	6.2.9 Far Pointers	25
	6.2.10 Bank switching	25
	6.2.11 Wrapper Function for Accessing Banked Data	25
	6.2.12 Currently active bank: CURRENT_BANK	25
	6.3 Auto-Banking	25
	6.4 Errors related to banking (overflow, multiple writes to same location)	26
	6.5 Bank space usage	26
	6.5.1 Other important notes	26
	6.6 Banking example projects	27
	6.7 SMS/Game Gear Banking	27
	6.7.1 Auto-Banking	27
7 (	GBDK Toolchain	28
	7.1 Overview	28
	7.2 Data Types	28
	7.3 Changing Important Addresses	28
	7.4 Compiling programs	29
	7.4.1 Makefiles	29
	7.4.2 Using Makefiles	29
	7.4.3 Linker Files and ROM Auto Banking	30
	7.5 Build Tools	30
	7.5.1 lcc	30
	7.5.2 sdcc	30
	7.5.3 sdasgb	30
	7.5.4 bankpack	31
	7.5.5 sdldgb	31

7.5.6 ihxcheck	(	31
7.5.7 makebin	(	31
7.6 GBDK Utilities	(	31
7.6.1 GBCompress	(	31
7.6.2 png2asset		32
7.6.3 makecom		33
7.6.4 png2hicolorgb		33
7.6.5 romusage	(	34
8 Supported Consoles & Cross Compiling	;	34
8.1 Consoles Supported by GBDK	(	34
8.2 Cross Compiling for Different Consoles	(	34
8.2.1 lcc		34
8.2.2 sdcc		35
8.2.3 Console Port and Platform Settings		35
8.3 Cross-Platform Constants		36
8.3.1 Console Identifiers	(	36
8.3.2 Console Hardware Properties		36
8.4 Using <gbdk></gbdk> headers	(	37
8.5 Cross Platform Example Projects	(	37
8.5.1 Cross Platform Asset Example	(	37
8.6 Hardware Summaries	(	37
8.6.1 Safe VRAM / Display Controller Access		39
8.7 Using Game Boy Color (GBC/CGB) Features		39
8.7.1 Differences Versus the Regular Game Boy (DMG/GBP/SGB)		39
8.7.2 Game Boy Color features in GBDK		39
8.7.3 CGB Examples	4	40
8.8 Porting Between Supported Consoles	4	40
8.8.1 From Game Boy to Analogue Pocket	4	40
8.8.2 From Game Boy to SMS/GG	4	41
8.8.3 From Game Boy to NES		42
8.8.4 From Game Boy to Mega Duck / Cougar Boy	4	46
9 Example Programs	4	48
9.1 banks (various projects)	4	48
9.2 comm	4	48
9.3 crash	4	48
9.4 colorbar	4	48
9.5 dscan	4	48
9.6 filltest	4	48
9.7 fonts	4	48
9.8 galaxy	4	48
9.9 gb-dtmf		48

	9.10 gbdecompress	48
	9.11 irq	49
	9.12 large map	49
	9.13 metasprites	49
	9.14 lcd isr wobble	49
	9.15 paint	49
	9.16 rand	49
	9.17 ram_fn	49
	9.18 rpn	49
	9.19 samptest	49
	9.20 sgb (various)	49
	9.21 sound	50
	9.22 space	50
	9.23 templates	50
10	Frequently Asked Questions (FAQ)	50
	10.1 General	
	10.2 Licensing	
	10.3 Graphics and Resources	
	10.4 ROM Header Settings	
	10.5 Editors	
	10.6 Errors and Warnings	51
	10.7 Debugging / Compiling / Toolchain	53
	10.8 API / Utilities	
11	Migrating to new GBDK Versions	54
	11.1 GBDK-2020 versions	
	11.1.1 Porting to GBDK-2020 4.3.0	
	11.1.2 Porting to GBDK-2020 4.2.0	54
	11.1.3 Porting to GBDK-2020 4.1.1	54
	11.1.4 Porting to GBDK-2020 4.1.0	55
	11.1.5 Porting to GBDK-2020 4.0.6	55
	11.1.6 Porting to GBDK-2020 4.0.5	55
	11.1.7 Porting to GBDK-2020 4.0.4	56
	11.1.8 Porting to GBDK-2020 4.0.3	56
	11.1.9 Porting to GBDK-2020 4.0.2	56
	11.1.10 Porting to GBDK-2020 4.0.1	56
	11.1.11 Porting to GBDK-2020 4.0	56
	11.1.12 Porting to GBDK-2020 3.2	56
	11.1.13 Porting to GBDK-2020 3.1.1	56
	11.1.14 Porting to GBDK-2020 3.1	56
	11.1.15 Porting to GBDK-2020 3.0.1	57
	11.2 Historical GBDK versions	57

11.2.1 GBDK 1.1 to GBDK 2.0	57
12 GBDK Release Notes	57
12.1 GBDK-2020 Release Notes	57
12.1.1 GBDK-2020 4.3.0	57
12.1.2 GBDK-2020 4.2.0	60
12.1.3 GBDK-2020 4.1.1	61
12.1.4 GBDK-2020 4.1.0	61
12.1.5 GBDK-2020 4.0.6	63
12.1.6 GBDK-2020 4.0.5	65
12.1.7 GBDK-2020 4.0.4	66
12.1.8 GBDK-2020 4.0.3	67
12.1.9 GBDK-2020 4.0.2	68
12.1.10 GBDK-2020 4.0.1	68
12.1.11 GBDK-2020 4.0	69
12.1.12 GBDK-2020 3.2	69
12.1.13 GBDK-2020 3.1.1	69
12.1.14 GBDK-2020 3.1	70
12.1.15 GBDK-2020 3.0.1	70
12.1.16 GBDK-2020 3.0	70
12.2 Historical GBDK Release Notes	70
12.2.1 GBDK 2.96	70
12.2.2 GBDK 2.95-3	71
12.2.3 GBDK 2.95-2	71
12.2.4 GBDK 2.95	71
12.2.5 GBDK 2.94	72
12.2.6 GBDK 2.93	72
12.2.7 GBDK 2.92-2 for win32	73
12.2.8 GBDK 2.92	73
12.2.9 GBDK 2.91	73
12.2.10 GBDK 2.1.5	74
12.2.11 GBDK 2.0b11 (DOS binary only) - 24 November 1997	74
12.2.12 GBDK 2.0b10 (DOS binary only) - 6 November 1997	74
12.2.13 GBDK 2.0b9 (DOS binary only)	74
12.2.14 GBDK 2.0b8 (DOS binary only)	74
12.2.15 GBDK 2.0b7 (DOS binary only)	74
12.2.16 GBDK 2.0b6	75
12.2.17 GBDK 2.0b5	75
12.2.18 GBDK 2.0b4	75
12.2.19 GBDK 2.0b3	75
12.2.20 GBDK 2.0b2	75
12.2.21 GBDK 2.0b1	76

12.2.23 GBDK 1.0-1 1996	
	76
13 Toolchain settings	76
13.1 lcc settings	76
13.2 sdcc settings	77
13.3 sdasgb settings	78
13.4 sdasz80 settings	79
13.5 sdas6500 settings	79
13.6 bankpack settings	80
13.7 sdldgb settings	80
13.8 sdldz80 settings	80
13.9 sdld6808 settings	81
13.10 ihxcheck settings	81
13.11 makebin settings	81
13.12 makecom settings	82
13.13 gbcompress settings	82
13.14 png2asset settings	82
13.15 png2hicolorgb settings	83
13.16 romusage settings	83
14 Todo List	84
15 Module Index	84
15.1 C modules	84
16 Data Structure Index	84
16.1 Data Structures	84
Ton Data Gradulation 1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.	0.
17 File Index	84
17 File Index         17.1 File List	<b>84</b>
	_
17.1 File List	84
17.1 File List	84 <b>87</b>
17.1 File List	84 <b>87</b> 87
17.1 File List	84 <b>87</b> 87
17.1 File List	84 87 87 87
17.1 File List	84 87 87 87 87
17.1 File List	84 87 87 87 87 87
17.1 File List	84 87 87 87 87 87
17.1 File List	84 87 87 87 87 87 87 88
17.1 File List	844 877 877 877 877 8787 8888 8888

	19.3.1 Field Documentation	89
	19.4 isr_nested_vector_t Struct Reference	89
	19.4.1 Field Documentation	89
	19.5 isr_vector_t Struct Reference	89
	19.5.1 Field Documentation	90
	19.6 joypads_t Struct Reference	90
	19.6.1 Detailed Description	91
	19.6.2 Field Documentation	91
	19.7 metasprite_t Struct Reference	91
	19.7.1 Detailed Description	92
	19.7.2 Field Documentation	93
	19.8 OAM_item_t Struct Reference	93
	19.8.1 Detailed Description	93
	19.8.2 Field Documentation	94
	19.9 sfont_handle Struct Reference	94
	19.9.1 Detailed Description	94
	19.9.2 Field Documentation	94
20	File Documentation	95
20	20.1 docs/pages/01_getting_started.md File Reference	<b>95</b>
	20.2 docs/pages/02_links_and_tools.md File Reference	95
	20.3 docs/pages/03_using_gbdk.md File Reference	95
	20.4 docs/pages/04_coding_guidelines.md File Reference	95
	20.5 docs/pages/05_banking_mbcs.md File Reference	95
	20.6 docs/pages/06_toolchain.md File Reference	95
	· · · · · · · · · · · · · · · · · · ·	
	20.13 docs/pages/docs_index.md File Reference	95
	20.14 gbdk-lib/include/asm/mos6502/provides.h File Reference	95
	20.14.1 Macro Definition Documentation	95
	20.15.1 Macro Definition Documentation	96
	20.16 gbdk-lib/include/asm/z80/provides.h File Reference	96
	20.18 abdk-lib/include/asm/sm83/stdarq.h File Reference	
	20.7 docs/pages/06b_supported_consoles.md File Reference          20.8 docs/pages/07_sample_programs.md File Reference          20.9 docs/pages/08_faq.md File Reference          20.10 docs/pages/09_migrating_new_versions.md File Reference	95 95 95
	· · · · · · · · · · · · · · · · · · ·	95 95
	20.11 docs/pages/10_release_notes.md File Reference	95
	20.12 docs/pages/20_toolchain_settings.md File Reference	95
	20.15 gbdk-lib/include/asm/sm83/provides.h File Reference	95
	20.16.1 Macro Definition Documentation	96
	20.17 gbdk-lib/include/asm/mos6502/stdarg.h File Reference	96
	20.17.1 Macro Definition Documentation	96
	20.17.2 Typedef Documentation	97
	20.18 abdk-lib/include/asm/sm83/stdara h File Beference	97

20.18.1 Macro Definition Documentation	97
20.18.2 Typedef Documentation	97
20.19 gbdk-lib/include/asm/z80/stdarg.h File Reference	97
20.19.1 Macro Definition Documentation	97
20.19.2 Typedef Documentation	98
20.20 gbdk-lib/include/stdarg.h File Reference	98
20.21 gbdk-lib/include/asm/mos6502/string.h File Reference	98
20.21.1 Detailed Description	98
20.21.2 Macro Definition Documentation	98
20.21.3 Function Documentation	99
20.22 gbdk-lib/include/asm/sm83/string.h File Reference	ე2
20.22.1 Detailed Description	ე2
20.22.2 Function Documentation	ე2
20.22.3 Variable Documentation	
20.23 gbdk-lib/include/asm/z80/string.h File Reference	Э6
20.23.1 Detailed Description	Э6
20.23.2 Function Documentation	Э6
20.24 gbdk-lib/include/string.h File Reference	
20.24.1 Detailed Description	
20.25 gbdk-lib/include/asm/mos6502/types.h File Reference	10
20.25.1 Detailed Description	
20.25.2 Macro Definition Documentation	
20.25.3 Typedef Documentation	
20.26 gbdk-lib/include/asm/sm83/types.h File Reference	
20.26.1 Detailed Description	
20.26.2 Macro Definition Documentation	
20.26.3 Typedef Documentation	11
20.27 gbdk-lib/include/asm/types.h File Reference	
20.27.1 Detailed Description	
20.27.2 Macro Definition Documentation	
20.27.3 Typedef Documentation	
20.28 gbdk-lib/include/asm/z80/types.h File Reference	
20.28.1 Detailed Description	
20.28.2 Macro Definition Documentation	
20.28.3 Typedef Documentation	
20.29 gbdk-lib/include/types.h File Reference	
20.29.1 Detailed Description	
20.29.2 Macro Definition Documentation	
20.29.3 Typedef Documentation	
20.30 gbdk-lib/include/assert.h File Reference	
20.30.1 Macro Definition Documentation	
20.30.2 Function Documentation	16

20.31 gbdk-lib/include/ctype.h File Reference
20.31.1 Detailed Description
20.31.2 Function Documentation
20.32 gbdk-lib/include/gb/bcd.h File Reference
20.32.1 Detailed Description
20.32.2 Macro Definition Documentation
20.32.3 Typedef Documentation
20.32.4 Function Documentation
20.33 gbdk-lib/include/gbdk/bcd.h File Reference
20.34 gbdk-lib/include/sms/bcd.h File Reference
20.34.1 Detailed Description
20.34.2 Macro Definition Documentation
20.34.3 Typedef Documentation
20.34.4 Function Documentation
20.35 gbdk-lib/include/gb/bgb_emu.h File Reference
20.35.1 Detailed Description
20.36 gbdk-lib/include/gb/cgb.h File Reference
20.36.1 Detailed Description
20.36.2 Macro Definition Documentation
20.36.3 Typedef Documentation
20.36.4 Function Documentation
20.37 gbdk-lib/include/gb/crash_handler.h File Reference
20.37.1 Detailed Description
20.37.2 Function Documentation
20.38 gbdk-lib/include/gb/drawing.h File Reference
20.38.1 Detailed Description
20.38.2 Macro Definition Documentation
20.38.3 Function Documentation
20.39 gbdk-lib/include/gb/emu_debug.h File Reference
20.39.1 Detailed Description
20.40 gbdk-lib/include/gbdk/emu_debug.h File Reference
20.40.1 Detailed Description
20.40.2 Macro Definition Documentation
20.40.3 Function Documentation
20.40.4 Variable Documentation
20.41 gbdk-lib/include/gb/gb.h File Reference
20.41.1 Detailed Description
20.41.2 Macro Definition Documentation
20.41.3 Typedef Documentation
20.41.4 Function Documentation
20.41.5 Variable Documentation
20.42 abdk-lib/include/ab/abdecompress h File Reference

20.42.1 Detailed Description
20.42.2 Function Documentation
20.43 gbdk-lib/include/gbdk/gbdecompress.h File Reference
20.44 gbdk-lib/include/sms/gbdecompress.h File Reference
20.44.1 Function Documentation
20.44.2 Variable Documentation
20.45 gbdk-lib/include/gb/hardware.h File Reference
20.45.1 Detailed Description
20.45.2 Macro Definition Documentation
20.45.3 Variable Documentation
20.46 gbdk-lib/include/msx/hardware.h File Reference
20.46.1 Detailed Description
20.46.2 Macro Definition Documentation
20.46.3 Variable Documentation
20.47 gbdk-lib/include/nes/hardware.h File Reference
20.47.1 Detailed Description
20.47.2 Macro Definition Documentation
20.47.3 Function Documentation
20.47.4 Variable Documentation
20.48 gbdk-lib/include/sms/hardware.h File Reference
20.48.1 Detailed Description
20.48.2 Macro Definition Documentation
20.48.3 Variable Documentation
20.49 gbdk-lib/include/gb/hblankcpy.h File Reference
20.49.1 Function Documentation
20.49.2 Variable Documentation
20.50 gbdk-lib/include/gb/isr.h File Reference
20.50.1 Detailed Description
20.50.2 Macro Definition Documentation
20.50.3 Typedef Documentation
20.51 gbdk-lib/include/gb/metasprites.h File Reference
20.51.1 Detailed Description
20.51.2 Metasprite support
20.51.3 Metasprites composed of variable numbers of sprites
20.51.4 Metasprites and sprite properties (including cgb palette)
20.51.5 Macro Definition Documentation
20.51.6 Typedef Documentation
20.51.7 Function Documentation
20.51.8 Variable Documentation
20.52 gbdk-lib/include/gbdk/metasprites.h File Reference
20.53 gbdk-lib/include/msx/metasprites.h File Reference
20.53.1 Macro Definition Documentation

20.53.2 Typedef Documentation	46
20.53.3 Function Documentation	46
20.53.4 Variable Documentation	47
20.54 gbdk-lib/include/nes/metasprites.h File Reference	48
20.54.1 Detailed Description	48
20.54.2 Metasprite support	48
20.54.3 Macro Definition Documentation	49
20.54.4 Typedef Documentation	49
20.54.5 Function Documentation	49
20.54.6 Variable Documentation	53
20.55 gbdk-lib/include/sms/metasprites.h File Reference	53
20.55.1 Detailed Description	54
20.55.2 Metasprite support	54
20.55.3 Metasprite support	54
20.55.4 Macro Definition Documentation	54
20.55.5 Typedef Documentation	54
20.55.6 Function Documentation	55
20.55.7 Variable Documentation	58
20.56 gbdk-lib/include/gb/sgb.h File Reference	58
20.56.1 Detailed Description	59
20.56.2 Macro Definition Documentation	59
20.56.3 Function Documentation	60
20.56.4 Variable Documentation	61
20.57 gbdk-lib/include/gbdk/console.h File Reference	61
20.57.1 Detailed Description	61
20.57.2 Function Documentation	61
20.58 gbdk-lib/include/gbdk/far_ptr.h File Reference	62
20.58.1 Detailed Description	63
20.58.2 Macro Definition Documentation	63
20.58.3 Typedef Documentation	64
20.58.4 Function Documentation	64
20.58.5 Variable Documentation	65
20.59 gbdk-lib/include/gbdk/font.h File Reference	65
20.59.1 Detailed Description	65
20.59.2 Macro Definition Documentation	66
20.59.3 Typedef Documentation	66
20.59.4 Function Documentation	66
20.60 gbdk-lib/include/gbdk/gbdk-lib.h File Reference	67
20.60.1 Detailed Description	67
20.61 gbdk-lib/include/gbdk/incbin.h File Reference	67
20.61.1 Detailed Description	67
20.61.2 Macro Definition Documentation	67

20.62 gbdk-lib/include/gbdk/platform.h File Reference	59
20.63 gbdk-lib/include/gbdk/rledecompress.h File Reference	39
20.63.1 Detailed Description	39
20.63.2 Macro Definition Documentation	39
20.63.3 Function Documentation	69
20.64 gbdk-lib/include/gbdk/version.h File Reference	70
20.64.1 Macro Definition Documentation	70
20.65 gbdk-lib/include/limits.h File Reference	70
20.65.1 Macro Definition Documentation	70
20.66 gbdk-lib/include/msx/msx.h File Reference	72
20.66.1 Detailed Description	75
20.66.2 Macro Definition Documentation	75
20.66.3 Typedef Documentation	32
20.66.4 Function Documentation	33
20.66.5 Variable Documentation	96
20.67 gbdk-lib/include/nes/nes.h File Reference	98
20.67.1 Detailed Description	)1
20.67.2 Macro Definition Documentation	)1
20.67.3 Typedef Documentation	ე9
20.67.4 Function Documentation	ე9
20.67.5 Variable Documentation	35
	36
20.68 gbdk-lib/include/nes/rgb_to_nes_macro.h File Reference	00
20.68 gbdk-lib/include/nes/rgb_to_nes_macro.h File Reference	
	36
20.68.1 Macro Definition Documentation	36 36
20.68.1 Macro Definition Documentation	36 36 37
20.68.1 Macro Definition Documentation	36 36 37 37
20.68.1 Macro Definition Documentation 33 20.69 gbdk-lib/include/rand.h File Reference 33 20.69.1 Detailed Description 33 20.69.2 Macro Definition Documentation 33 20.69.3 Function Documentation 33	36 36 37 37
20.68.1 Macro Definition Documentation 33 20.69 gbdk-lib/include/rand.h File Reference 33 20.69.1 Detailed Description 33 20.69.2 Macro Definition Documentation 33 20.69.3 Function Documentation 33	36 37 37 37
20.68.1 Macro Definition Documentation 33 20.69 gbdk-lib/include/rand.h File Reference 33 20.69.1 Detailed Description 33 20.69.2 Macro Definition Documentation 33 20.69.3 Function Documentation 33 20.69.4 Variable Documentation 33	36 36 37 37 38
20.68.1 Macro Definition Documentation 33 20.69 gbdk-lib/include/rand.h File Reference 33 20.69.1 Detailed Description 33 20.69.2 Macro Definition Documentation 33 20.69.3 Function Documentation 33 20.69.4 Variable Documentation 33 20.70 gbdk-lib/include/setjmp.h File Reference 33	36 36 37 37 38 38
20.68.1 Macro Definition Documentation  20.69 gbdk-lib/include/rand.h File Reference  20.69.1 Detailed Description  20.69.2 Macro Definition Documentation  20.69.3 Function Documentation  20.69.4 Variable Documentation  20.70 gbdk-lib/include/setjmp.h File Reference  20.70.1 Macro Definition Documentation  33  34	36 37 37 38 38 38
20.68.1 Macro Definition Documentation  20.69 gbdk-lib/include/rand.h File Reference  20.69.1 Detailed Description  20.69.2 Macro Definition Documentation  20.69.3 Function Documentation  20.69.4 Variable Documentation  20.70 gbdk-lib/include/setjmp.h File Reference  20.70.1 Macro Definition Documentation  20.70.2 Typedef Documentation  3332267678787878787878787878787878787878787	36 37 37 38 38 38 39
20.68.1 Macro Definition Documentation  20.69 gbdk-lib/include/rand.h File Reference  20.69.1 Detailed Description  20.69.2 Macro Definition Documentation  20.69.3 Function Documentation  20.69.4 Variable Documentation  20.70 gbdk-lib/include/setjmp.h File Reference  20.70.1 Macro Definition Documentation  20.70.2 Typedef Documentation  30.70.3 Function Documentation  31.70.70.3 Function Documentation  32.70.3 Function Documentation  33.70.70.3 Function Documentation  34.70.70.3 Function Documentation  35.70.70.70.70.70.70.70.70.70.70.70.70.70.	36 37 37 38 38 38 39
20.68.1 Macro Definition Documentation  20.69 gbdk-lib/include/rand.h File Reference  20.69.1 Detailed Description  20.69.2 Macro Definition Documentation  20.69.3 Function Documentation  20.69.4 Variable Documentation  20.70 gbdk-lib/include/setjmp.h File Reference  20.70.1 Macro Definition Documentation  20.70.2 Typedef Documentation  20.70.3 Function Documentation  30.20.71 gbdk-lib/include/sms/sms.h File Reference  31.20.71 gbdk-lib/include/sms/sms.h File Reference  32.20.71 gbdk-lib/include/sms/sms.h File Reference	36 37 37 38 38 39 39
20.68.1 Macro Definition Documentation       33         20.69 gbdk-lib/include/rand.h File Reference       33         20.69.1 Detailed Description       33         20.69.2 Macro Definition Documentation       33         20.69.3 Function Documentation       33         20.69.4 Variable Documentation       33         20.70 gbdk-lib/include/setjmp.h File Reference       33         20.70.1 Macro Definition Documentation       33         20.70.2 Typedef Documentation       33         20.70.3 Function Documentation       33         20.71 gbdk-lib/include/sms/sms.h File Reference       33         20.71 gbdk-lib/include/sms/sms.h File Reference       33         20.71.1 Detailed Description       34	36 37 37 38 38 39 39 43 43
20.68.1 Macro Definition Documentation       33         20.69 gbdk-lib/include/rand.h File Reference       33         20.69.1 Detailed Description       33         20.69.2 Macro Definition Documentation       33         20.69.3 Function Documentation       33         20.69.4 Variable Documentation       33         20.70 gbdk-lib/include/setjmp.h File Reference       33         20.70.1 Macro Definition Documentation       33         20.70.2 Typedef Documentation       33         20.70.3 Function Documentation       33         20.71 gbdk-lib/include/sms/sms.h File Reference       33         20.71.1 Detailed Description       34         20.71.2 Macro Definition Documentation       34	36 37 37 38 38 39 39 43 43
20.68.1 Macro Definition Documentation       33         20.69 gbdk-lib/include/rand.h File Reference       33         20.69.1 Detailed Description       33         20.69.2 Macro Definition Documentation       33         20.69.3 Function Documentation       33         20.69.4 Variable Documentation       33         20.70 gbdk-lib/include/setjmp.h File Reference       33         20.70.1 Macro Definition Documentation       33         20.70.2 Typedef Documentation       33         20.70.3 Function Documentation       33         20.71 gbdk-lib/include/sms/sms.h File Reference       33         20.71.1 Detailed Description       34         20.71.2 Macro Definition Documentation       34         20.71.3 Typedef Documentation       36	36 37 37 38 38 39 39 43 43 51
20.68.1 Macro Definition Documentation       33         20.69 gbdk-lib/include/rand.h File Reference       33         20.69.1 Detailed Description       33         20.69.2 Macro Definition Documentation       33         20.69.3 Function Documentation       33         20.69.4 Variable Documentation       33         20.70 gbdk-lib/include/setjmp.h File Reference       33         20.70.1 Macro Definition Documentation       33         20.70.2 Typedef Documentation       33         20.70.3 Function Documentation       33         20.71 gbdk-lib/include/sms/sms.h File Reference       33         20.71.1 Detailed Description       34         20.71.2 Macro Definition Documentation       34         20.71.3 Typedef Documentation       34         20.71.4 Function Documentation       35         20.71.4 Function Documentation       36	36 37 37 38 38 39 39 43 43 51 51
20.68.1 Macro Definition Documentation       33         20.69 gbdk-lib/include/rand.h File Reference       33         20.69.1 Detailed Description       33         20.69.2 Macro Definition Documentation       33         20.69.3 Function Documentation       33         20.69.4 Variable Documentation       33         20.70 gbdk-lib/include/setjmp.h File Reference       33         20.70.1 Macro Definition Documentation       33         20.70.2 Typedef Documentation       33         20.70.3 Function Documentation       33         20.71 gbdk-lib/include/sms/sms.h File Reference       33         20.71.1 Detailed Description       34         20.71.2 Macro Definition Documentation       36         20.71.3 Typedef Documentation       36         20.71.4 Function Documentation       36         20.71.5 Variable Documentation       36	36 37 37 38 38 39 39 43 43 51 65 66
20.68.1 Macro Definition Documentation       33         20.69 gbdk-lib/include/rand.h File Reference       33         20.69.1 Detailed Description       33         20.69.2 Macro Definition Documentation       33         20.69.3 Function Documentation       33         20.69.4 Variable Documentation       33         20.70 gbdk-lib/include/setjmp.h File Reference       33         20.70.1 Macro Definition Documentation       33         20.70.2 Typedef Documentation       33         20.70.3 Function Documentation       33         20.71 gbdk-lib/include/sms/sms.h File Reference       33         20.71.1 Detailed Description       34         20.71.2 Macro Definition Documentation       34         20.71.3 Typedef Documentation       34         20.71.4 Function Documentation       34         20.71.5 Variable Documentation       36         20.72 gbdk-lib/include/stdatomic.h File Reference       36	36 37 37 38 38 39 39 43 51 51 65 66

1 General Documentation 1

20.74 gbdk-lib/include/stddef.h File Reference	 . 367
20.74.1 Macro Definition Documentation	 . 367
20.74.2 Typedef Documentation	 . 368
20.75 gbdk-lib/include/stdint.h File Reference	 . 368
20.75.1 Macro Definition Documentation	 . 369
20.75.2 Typedef Documentation	 . 372
20.76 gbdk-lib/include/stdio.h File Reference	 . 374
20.76.1 Detailed Description	 . 374
20.76.2 Function Documentation	 . 374
20.77 gbdk-lib/include/stdlib.h File Reference	 . 375
20.77.1 Function Documentation	 . 376
20.78 gbdk-lib/include/stdnoreturn.h File Reference	 . 379
20.78.1 Macro Definition Documentation	 . 379
20.79 gbdk-lib/include/time.h File Reference	 . 379
20.79.1 Detailed Description	 . 379
20.79.2 Macro Definition Documentation	 . 379
20.79.3 Typedef Documentation	 . 379
20.79.4 Function Documentation	 . 380
20.80 gbdk-lib/include/typeof.h File Reference	 . 380
20.80.1 Macro Definition Documentation	 . 381
Index	383

# 1 General Documentation

- Getting Started
- Links, Tools and Debugging
- Using GBDK
- Coding Guidelines
- ROM/RAM Banking and MBCs
- Supported Consoles & Cross Compiling
- GBDK Toolchain
- Example Programs
- Frequently Asked Questions (FAQ)
- Migrating to new GBDK Versions
- GBDK Release Notes
- Toolchain settings

## 1.1 Introduction

Welcome to GBDK-2020! The best thing to do is head over to the Getting Started section to get up and running.

If you are upgrading please check GBDK Release Notes and Migrating to new GBDK Versions

### 1.2 About the Documentation

This documentation is partially based on material written by the original GBDK authors in 1999 and updated for GBDK-2020. The API docs are automatically generated from the C header files using Doxygen.

GBDK-2020 is an updated version of the original GBDK with a modernized SDCC toolchain and many API improvements and fixes. It can be found at: https://github.com/gbdk-2020/gbdk-2020/.

The original GBDK sources, documentation and website are at: http://gbdk.sourceforge.net/

## 1.3 About GBDK

The GameBoy Developer's Kit (GBDK, GBDK-2020) is used to develop games and programs for the Nintendo Game Boy (and some other consoles) in C and assembly. GBDK includes a set of libraries for the most common requirements and generates image files for use with a real GameBoy or emulators.

GBDK features:

- C and ASM toolchain based on SDCC with some support utilities
- · A set of libraries with source code
- · Example programs in ASM and in C
- · Support for multiple ROM bank images and auto-banking
- Support for multiple consoles: Game Boy, Analogue Pocket, Mega Duck, Master System and Game Gear and NES

GBDK is freeware. Most of the tooling code is under the GPL. The runtime libraries should be under the LGPL. Please consider mentioning GBDK in the credits of projects made with it.

## 1.4 Historical Info and Links

Work on the original GBDK (pre-2020) was by:

Pascal Felber, Lars Malmborg, Michael Hope, David Galloway (djmips), John Fuge, and others.

The following is from the original GBDK documentation:

Thanks to quang for many of the comments to the gb functions. Some of the comments are ripped directly from the Linux Programmers manual, and some directly from the pan/k00Pa document.

```
quangDX.com
The (original) gbdk homepage
Jeff Frohwein's GB development page. A extensive source of Game Boy related information, including GeeBee's GB faq and the pan/k00Pa document.
```

# 2 Getting Started

Follow the steps in this section to start using GBDK-2020.

## 2.1 1. Download a Release and unzip it

You can get the latest releases from here: https://github.com/gbdk-2020/gbdk-2020/releases

## 2.1.1 Known Issue: Windows and folder names with spaces on non-C drives

There is a known issue on Windows where sdcc will fail when run from folder names with spaces on non-C drives. For the time being the workaround is as follows (with D:\My Stuff\ as an example folder):

- · Run Windows Command as administrator
- Run: fsutil.exe 8dot3name query D:
  - Output: The volume state is: 1 (8dot3 name creation is disabled). The registry state is: 2 (Per volume setting - the default). Based on the above settings, 8dot3 name creation is disabled on D:
- Run: fsutil 8dot3name set D: 0
  - Output: Successfully enabled 8dot3name generation on D:
- Run: fsutil.exe 8dot3name query D:
  - Output: The volume state is: 0 (8dot3 name creation is enabled). The registry state is: 2 (Per volume setting - the default). Based on the above settings, 8dot3 name creation is enabled on D:
- Only folders created AFTER the setting has been enabled will get 8.3 filename support, renaming folders
  does NOT appear to generate 8.3 filename support. However it is possible to manually generate a short path
  name for an existing folder:
  - Run: D:\>fsutil file setshortname "D:\My stuff" "mystuf~1"

# 2.2 2. Compile Example projects

Make sure your GBDK-2020 installation is working correctly by compiling some of the included example projects. If everything works in the steps below and there are no errors reported then each project that was built should have its own .gb ROM file (or suitable extension for the other supported targets).

## 2.2.1 Windows (without Make installed):

Navigate to a project within the example projects folder ("examples\gb\" under your GBDK-2020 install folder) and open a command line. Then type:

```
compile

or

compile.bat
```

This should build the example project. You can also navigate into other example project folders and build in the same way.

## 2.2.2 Linux / macOS / Windows with Make installed:

Navigate to the example projects folder ("examples/gb/" under your GBDK-2020 install folder) and open a command line. Then type:

make

This should build all of the examples sequentially. You can also navigate into an individual example project's folder and build it by typing make.

**2.2.2.1 macOS security warnings** If you get a security warning on macOS that says ("`... developer cannot be verified, macOS cannot verify that this app is free from malware`"), it does not mean that GBDK is malware. It just means the GBDK toolchain binaries are not signed by Apple, so it won't run them without an additional step. You will need to unquarrantine the files in the bin folder in order to run them. This can be fixed using the following steps.

Open a terminal and navigate to the gbdk bin folder ("bin/" under your GBDK-2020 install folder). Then type:

```
xattr -d com.apple.quarantine \star
```

# 2.3 3. Use a Template

### To create a new project use a template!

There are template projects included in the GBDK example projects to help you get up and running. Their folder names start with template\_.

- 1. Copy one of the template folders to a new folder name.
- 2. If you moved the folder out of the GBDK examples then you **must** update the GBDK path variable and/or the path to LCC in the Makefile or compile.bat so that it will still build correctly.
- 3. Type make on the command line in that folder to verify it still builds.
- 4. Open main.c to start making changes.

# 2.4 4. If you use GBTD / GBMB, get the fixed version

If you plan to use GBTD / GBMB for making graphics, make sure to get the version with the const fix and other improvements. See const gbtd gbmb.

## 2.5 5. Review Coding Guidelines

Take a look at the coding guidelines, even if you have experience writing software for other platforms. There is important information to help you get good results and performance on the Game Boy.

If you haven't written programs in C before, check the C tutorials section.

### 2.6 6. Hardware and Resources

If you have a specific project in mind, consider what hardware you want to target. It isn't something that has to be decided up front, but it can influence design and implementation.

What size will your game or program be?

- · 32K Cart (no-MBC required)
- · Larger than 32K (MBC required)
- See more details about ROM Banking and MBCs

What console platform(s) will it run on?

- Game Boy (GB/GBC)
- Analogue Pocket (AP)
- Sega Master System (SMS)
- · Game Gear (GG)
- · Mega Duck (DUCK)
- See Supported Consoles & Cross Compiling

If targeting the Game Boy, what hardware will it run on?

- · Game Boy (& Game Boy Color)
- · Game Boy Color only
- · Game Boy & Super Game Boy
- See how to set the compatibility type in the cartridge header. Read more about hardware differences in the Pandocs

## 2.7 7. Set up C Source debugging

Tracking down problems in code is easier with a debugger. Emulicious has a debug adapter that provides C source debugging with GBDK-2020.

# 2.8 8. Try a GBDK Tutorial

You might want to start off with a guided GBDK tutorial from the GBDK Tutorials section.

• **Note:** Tutorials (or parts of them) may be based on the older GBDK from the 2000's before it was updated to be GBDK-2020. The general principles are all the same, but the setup and parts of the toolchain (compiler/etc) may be somewhat different and some links may be outdated (pointing to the old GBDK or old tools).

## 2.9 9. Read up!

- It is strongly encouraged to read more GBDK-2020 General Documentation.
- Learn about the Game Boy hardware by reading through the Pandocs technical reference.

## 2.10 10. Need help?

Check out the links for online community and support and read the FAQ.

# 2.11 Migrating From Pre-GBDK-2020 Tutorials

Several popular GBDK Tutorials, Videos and How-to's were made before GBDK-2020 was available, as a result some information they include is outdated or incompatible. The following summarizes changes that should be made for best results.

# 2.11.1 Also see:

- · Migrating to new GBDK Versions
- Coding Guidelines
- Getting Started (the section above this)

### 2.11.2 Use auto-banking

GBDK-2020 now supports auto-banking (rom\_autobanking). In most cases using auto-banking will be easier and less error prone than manually assigning source and assets to banks.

• There is a source example banks\_autobank project.

## 2.11.3 Non-standard types (UINT8, etc)

The old GBDK types UINT8, INT8, UINT16, INT16 are non-standard and less portable.

The following should be used instead: uint8\_t, int16\_t, uint16\_t, int32\_t, uint32\_t and bool. These are standard types defined in stdint.h (#include <stdint.h>) and stdbool.h (#include <stdbool.h>).

## 2.11.4 If using GBTD / GBMB, get the fixed version

If you plan to use GBTD / GBMB for making graphics, make sure to get the version with the const fix and other improvements. See const\_gbtd\_gbmb.

### 2.11.5 LCC and SDCC flags that are not needed

The following flag is no longer needed with lcc and sdcc, it can be removed without any loss of performance.

- -DUSE\_SFR
  - Behavior formerly enabled by USE\_SFR\_FOR\_REG is on by default now (no need to specify it, it isn't a tested #ifdef anymore). Check here why: https://gbdev.gg8.← se/forums/viewtopic.php?id=697

### 2.11.6 ROM Header Settings (such as Color, SGB, etc)

Setting ROM bytes directly with -Wl-yp0x<address>=0x<value> is no longer supported. Instead use makebin flags. For example, use -Wm-yC instead of -Wl-yp0x143=0xC0. See faq\_gb\_type\_header\_setting.

### 2.11.7 GBDK Header include changes

The following header files which are now cross platform were moved from gb/to gbdk/: bcd.h, console.h, far\_ptr.h, font.h, gbdecompress.h, gbdk-lib.h, incbin.h, metasprites.h, platform.h, version.h

• When including them use #include <gbdk/...> instead of #include <gb/>

# 2.11.8 Include .h headers, not .c source files

Do not #include .c source files into other .c source files. Instead create .h header files for them and include those.

https://www.tutorialspoint.com/cprogramming/c\_header\_files.htm

### 2.11.9 Use the Template Projects

Modern project templates are included with GBDK-2020. Using them (and their Makefile or compile.bat) as a starting point for projects is recommended and can help ensure better default settings and project organization.

### 2.11.10 Use hUGEtracker instead of gbt\_player

hUGEtracker and its driver hUGEdriver are smaller, more efficient and more versatile than gbt player.

# 3 Links, Tools and Debugging

This is a brief list of useful tools and information. It is not meant to be complete or exhaustive, for a larger list see the Awesome Game Boy Development list.

# 3.1 SDCC Compiler Suite User Manual

• GBDK-2020 uses the SDCC compiler and related tools. The SDCC manual goes into much more detail about available features and how to use them.

```
http://sdcc.sourceforge.net/doc/sdccman.pdf
http://sdcc.sourceforge.net
```

• The SDCC assembler and linker (sdas / asxxxx and aslink) manual.

 $\verb|https://sourceforge.net/p/sdcc/code/HEAD/tree/trunk/sdcc/sdas/doc/asmlnk. \leftarrow txt|$ 

# 3.2 Getting Help

· GBDK Discord community:

```
https://github.com/gbdk-2020/gbdk-2020/#discord-servers
```

· Game Boy discussion forum:

```
https://gbdev.gg8.se/forums/
```

## 3.3 Game Boy Documentation

Pandocs

Extensive and up-to-date technical documentation about the Game Boy and related hardware.

https://gbdev.io/pandocs/

### Awesome Game Boy Development list

A list of Game Boy/Color development resources, tools, docs, related projects and homebrew.

https://gbdev.io/resources.html

## 3.4 Sega Master System / Game Gear Documentation

SMS Power!

Community site with technical documentation, reviews and other content related to the Sega 8-bit systems.

https://www.smspower.org/

### 3.5 Tutorials

### · Larold's Jubilant Junkyard Tutorials

Several walk throughs about the fundamentals of developing for the Game Boy with GBDK-2020. There are simple examples with source code.

https://laroldsjubilantjunkyard.com/tutorials/

### Gaming Monsters Tutorials

Several video tutorials and code for making games with GBDK/GBDK-2020.

https://www.youtube.com/playlist?list=PLeEj4c2zF7PaFv5MPYhNAkBGrkx4i↔PGJo

https://github.com/gingemonster/GamingMonstersGameBoySampleCode

### · Pocket Leage Tutorial

https://blog.ty-porter.dev/development/2021/04/04/writing-a-gameboy-game-in-2021-pthtml

## 3.6 Example code

· Simplified GBDK examples

https://github.com/mrombout/gbdk\_playground/commits/master

# 3.7 Graphics Tools

### Game Boy Tile Designer and Map Builder (GBTD / GBMB)

Sprite / Tile editor and Map Builder that can export to C that works with GBDK.

This is an updated version with const export fixed and other improvements.

https://github.com/gbdk-2020/GBTD\_GBMB

A GIMP plugin to read/write GBR/GBM files and do map conversion:

https://github.com/bbbbbr/gimp-tilemap-gb

Command line version of the above tool that doesn't require GIMP (png2gbtiles):

https://github.com/bbbbbr/gimp-tilemap-gb/tree/master/console

### Tilemap Studio

A tilemap editor for Game Boy, GBC, GBA, or SNES projects.

https://github.com/Rangi42/tilemap-studio/

## 3.8 Music And Sound Effects

### hUGEtracker and hUGEdriver

A tracker and music driver that work with GBDK and RGBDS. It is smaller, more efficient and more versatile than gbt\_player.

```
https://github.com/SuperDisk/hUGEDriver
https://github.com/SuperDisk/hUGETracker
```

### · CBT-FX

A sound effects driver which can play effects created in FX Hammer. https://github.← com/datquywitha3ds/CBT-FX

### VGM2GBSFX

A sound effects converter and driver for DMG VGM files, FX Hammer and PCM WAV files. https://github.com/untoxa/VGM2GBSFX

# GBT Player

A .mod converter and music driver that works with GBDK and RGBDS.

```
https://github.com/AntonioND/gbt-player
```

Docs from GBStudio that should mostly apply: https://www.gbstudio.dev/docs/music/

### 3.9 Emulators

### Emulicious

An accurate emulator with extensive tools including source level debugging.  $https://emulicious. \leftarrow net/$ 

### • BGB

Accurate emulator, has useful debugging tools.

```
http://bgb.bircd.org/
```

Intellisense in VSCode may have trouble identifying some GBDK types or functions, and therefore flag them as warnings or unidentified.

GBDK platform constants can be declared so that header files are parsed more completely in VSCode. The following c\_cpp\_properties.json example may be adapted for your own project.

## 3.10 Debugging tools

## · Emulicious debug adapter

Provides source-level debugging in VS Code and Sublime Text that works with GBDK2020.

https://marketplace.visualstudio.com/items?itemName=emulicious.emulicious-debugger

If compiler optimization is making the program source hard to step through in the debugger then adding
this flag to lcc can help. Note that using this flag will likely reduce code performance and increase code
size while enabled, so it is best to only use it temporarily.

```
* -Wf--max-allocs-per-node0
```

### romusage

Calculate used and free space in banks (ROM/RAM) and warn about errors such as bank overflows. See romusage-settings

### · noi file to sym conversion for bgb

Debug information in .noi files can be converted to a symbol format that BGB recognizes using:

```
- lcc: -Wm-yS (with --debug, or -Wl-j to create the .noi)
```

- directly with makebin : -yS (with -j passed to the linker)

#### src2sym.pl

# 3.11 Optimizing Assembly

### Optimizing Assembly Code

Pret has a useful guide to optimizing assembly for the Game Boy for times when asm using in a project in addition to C. https://github.com/pret/pokecrystal/wiki/Optimizing-assembly-code

# 3.12 Continuous Integration and Deployment

### · GBDK GitHub Action Builder

A Github Action which provides basic CI/CD for building projects based on GBDK (not for building GBDK itself)

https://github.com/wujood/gbdk-2020-github-builder

# 4 Using GBDK

## 4.1 Interrupts

Interrupts allow execution to jump to a different part of your code as soon as an external event occurs - for example the LCD entering the vertical blank period, serial data arriving or the timer reaching its end count. For an example see the irq.c sample project.

Interrupts in GBDK are handled using the functions disable\_interrupts(), enable\_interrupts(), set\_interrupts(uint8\_t ier) and the interrupt service routine (ISR) linkers add\_VBL(), add\_TIM, add\_low\_priority\_TIM, add\_LCD, add\_SIO and add\_JOY which add interrupt handlers for the vertical blank, timer, LCD, serial link and joypad interrupts respectively.

Since an interrupt can occur at any time an Interrupt Service Request (ISR) cannot take any arguments or return anything. Its only way of communicating with the greater program is through the global variables. When interacting with those shared ISR global variables from main code outside the interrupt, it is a good idea to wrap them in a critical {} section in case the interrupt occurs and modifies the variable while it is being used.

Interrupts should be disabled before adding ISRs. To use multiple interrupts, *logical OR* the relevant IFLAGs together.

ISRs should be kept as small and short as possible, do not write an ISR so long that the Game Boy hardware spends all of its time servicing interrupts and has no time spare for the main code.

For more detail on the Game Boy interrupts consider reading about them in the Pandocs.

## 4.1.1 Available Interrupts

The GameBoy hardware can generate 5 types of interrupts. Custom Interrupt Service Routines (ISRs) can be added in addition to the built-in ones available in GBDK.

- VBL : LCD Vertical Blanking period start
  - The default VBL ISR is installed automatically.
    - \* See add\_VBL() and remove\_VBL()
- · LCD: LCDC status (such as the start of a horizontal line)
  - See add\_LCD() and remove\_LCD()
  - Example project: lcd\_isr\_wobble
- · TIM: Timer overflow
  - See add\_TIM() (or add\_low\_priority\_TIM() ) and remove\_TIM()
  - Example project: tim
- · SIO: Serial Link I/O transfer end
  - The default SIO ISR gets installed automatically if any of the standard SIO calls are used (send\_byte(), receive\_byte()).
  - Once installed the default SIO ISR cannot be removed. Only secondary chained SIO ISRs (added with add\_SIO()) can be removed.
  - See add SIO() and remove SIO()
  - Example project: comm
- · JOY: Transition from high to low of a joypad button
  - See add\_JOY() and remove\_JOY()

### 4.1.2 Adding your own interrupt handler

It is possible to install your own interrupt handlers (in C or in assembly) for any of these interrupts. Up to 4 chained handlers may be added, with the last added being called last. If the remove\_VBL() function is to be called, only three may be added for VBL.

Interrupt handlers are called in sequence. To install a new interrupt handler, do the following:

- 1. Write a function (say foo()) that takes no parameters, and that returns nothing. Remember that the code executed in an interrupt handler must be short.
- 2. Inside a \_\_critical { ... } section, install your interrupt handling routines using the add\_XXX() function, where XXX is the interrupt that you want to handle.
- 3. Enable interrupts for the IRQ you want to handle, using the set\_interrupts() function. Note that the VBL interrupt is already enabled before the main() function is called. If you want to set the interrupts before main() is called, you must install an initialization routine.

See the irg example project for additional details for a complete example.

## 4.1.3 Using your own Interrupt Dispatcher

If you want to use your own Interrupt Dispatcher instead of the GBDK chained dispatcher (for improved performance), then don't call the add\_...() function for the respective interrupt and its dispatcher won't be installed.

- Exception: the VBL dispatcher will always be linked in at compile time.
- For the SIO interrupt, also do not make any standard SIO calls to avoid having its dispatcher installed.

Then, ISR VECTOR() or ISR NESTED VECTOR() can be used to install a custom ISR handler.

## 4.1.4 Returning from Interrupts and STAT mode

By default when an Interrupt handler completes and is ready to exit it will check STAT\_REG and only return at the BEGINNING of either LCD Mode 0 or Mode 1. This helps prevent graphical glitches caused when an ISR interrupts a graphics operation in one mode but returns in a different mode for which that graphics operation is not allowed. You can change this behavior using nowait\_int\_handler() which does not check STAT\_REG before returning. Also see wait\_int\_handler().

## 4.2 What GBDK does automatically and behind the scenes

### 4.2.1 NES console

For implementation details on the NES console in GBDK, see the NES entry in Supported Consoles & Cross Compiling

### 4.2.2 OAM (VRAM Sprite Attribute Table)

GBDK sets up a Shadow OAM which gets copied automatically to the hardware OAM by the default V-Blank ISR. The Shadow OAM allows updating sprites without worrying about whether it is safe to write to them or not based on the hardware LCD mode.

## 4.2.3 Graphics Tile Maps and Data on Startup

By default for the Game Boy GBDK assigns:

- Background and Window Tile data starting at 0x8800
- Background Tile Map starting at 0x9800
- Window Tile Map starting at 0x9C00
- Sprites to 8x8 mode

### 4.2.4 Font tiles when using stdio.h

Including stdio.h and using functions such as printf() will use a large number of the background tiles for font characters. If stdio.h is not included then that space will be available for use with other tiles instead.

### 4.2.5 Default Interrupt Service Handlers (ISRs)

- V-Blank: A default V-Blank ISR is installed on startup which copies the Shadow OAM to the hardware OAM and increments the global sys\_time variable once per frame.
- Serial Link I/O: If any of the GBDK serial link functions are used such as send\_byte() and receive\_byte(), the default SIO serial link handler will be installed automatically at compile-time.
- APA Graphics Mode: When this mode is used (via drawing.h) custom VBL and LCD ISRs handlers will be installed (drawing\_vbl and drawing\_lcd). Changing the mode to (mode (M\_TEXT\_OUT);) will cause them to be de-installed. These handlers are used to change the tile data source at start-of-frame and mid-frame so that 384 background tiles can be used instead of the typical 256.

## 4.2.6 Ensuring Safe Access to Graphics Memory

There are certain times during each video frame when memory and registers relating to graphics are "busy" and should not be read or written to (otherwise there may be corrupt or dropped data). GBDK handles this automatically for most graphics related API calls. It also ensures that ISR handlers return in such a way that if they interrupted a graphics access then it will only resume when access is allowed.

The ISR return behavior can be turned off using the nowait int handler.

For more details see the related Pandocs section: https://gbdev.io/pandocs/Accessing\_VRAM← \_and\_OAM.html

### 4.3 Compression

For programs that would benefit from compression GBDK includes the gbcompress utility and companion API functions.

In addition to the built-in compression unapack is another option:

- UnaPACK aPack decompression by Toxa: https://github.com/untoxa
- apultra aPack compression: https://github.com/emmanuel-marty/apultra

Another way to save space is using 1 bit-per-pixel (bpp) tile pattern data instead of 2-bpp or 4-bpp data. This can reduce the ROM size for groups of tiles which only require two shades of color.

• See: set\_1bpp\_colors(), set\_bkg\_1bpp\_data(), set\_win\_1bpp\_data(), set\_sprite\_1bpp\_data()

Use of 1-bpp tile pattern data may be combined with the compression described above to save even more space, however that approach requires using an intermediary RAM buffer before the tile pattern data can be written to VRAM with the set \* 1bpp data() functions.

## 4.4 Copying Functions to RAM and HIRAM

See the ram\_function example project included with GBDK which demonstrates copying functions to RAM and HIRAM.

Warning! Copying of functions is generally not safe since they may contain jumps to absolute addresses that will not be converted to match the new location.

It is possible to copy functions to RAM and HIRAM (using the memcpy() and hiramcpy() functions), and execute them from C. Ensure you have enough free space in RAM or HIRAM for copying a function.

There are basically two ways for calling a function located in RAM, HIRAM, or ROM:

- · Declare a pointer-to-function variable, and set it to the address of the function to call.
- Declare the function as extern, and set its address at link time using the -WI-gXXX=# flag (where XXX is the name of the function, and # is its address).

The second approach is slightly more efficient. Both approaches are demonstrated in the ram\_function.c example.

## 4.5 Mixing C and Assembly

The following is primarily oriented toward the Game Boy and related clones (sm83 devices), other targets such as sms/gg may vary.

You can mix C and assembly (ASM) in two ways as described below.

• For additional detail see the links\_sdcc\_docs and SDCC Calling Conventions.

## 4.5.1 Inline ASM within C source files

- The optional NAKED keyword may be used to indicate that the funtion setup and return should have no handling done by the compiler, and will instead be handled entirely by user code.
- If the entire function preserves some registers the optional PRESERVES\_REGS keyword may be used as additional hinting for the compiler. For example PRESERVES\_REGS (b, c). By default it is assumed by the compiler that no registers are preserved.

Example:

### 4.5.2 In Separate ASM files

main.c

It is possible to assemble and link files written in ASM alongside files written in C.

- A C identifier i will be called \_i in assembly.
- Parameters will be passed, registers saved and results returned in a manner based on the SDCC Calling Convention
  used and how the function is declared.
- Assembly identifiers are exported using the .glob1 directive.
- · See global.s for examples of hardware register deginitions.

Here is an example of how to mix assembly with C:

```
uint16_t add(uint16_t, uint16_t);
main()
  uint16_t i;
  i = add(1, 3);
add.s
.globl _add
.area _CODE
              ; uint16_t add(uint16_t First, uint16_t Second)
_add:
              ; In this particular example there is no use and modification of the stack
              ; No need to save and restore registers
              ; For calling convention __sdcccall(1)
              ; - first 16 bit param is passed in DE
              ; - second 16 bit param is passed in BC \,
; Load Second Parameter ("Second") into HL
ld 1, c
ld h, b
; Add Parameters "Second" + "First"
add hl, de
; Return result in BC
ld c, 1
ld b, h
ret
              ; 16 bit values are returned in BC
```

## 4.6 Including binary files in C source with incbin

Data from binary files can be included in C source files as a const array using the INCBIN() macro. See the incbin example project for a demo of how to use it.

## 4.7 Known Issues and Limitations

## 4.7.1 SDCC

- Const arrays declared with somevar [n] = {x} will **NOT** get initialized with value x. This may change when the SDCC RLE initializer is fixed. Use memset for now if you need it.
- SDCC banked calls and far\_pointers in GBDK only save one byte for the ROM bank, so for example they are limited to **bank 15** max for MBC1 and **bank 255** max for MBC5. See banked\_calls for more details.
- In SDCC pre-initializing a variable assigned to SRAM with -Wf-ba\* will force that variable to be in WRAM instead.

- The following is a workaround for initializing a variable in SRAM. It assignes value 0xA5 to a variable in bank 0 and assigned to address 0xA000 using the AT() directive:

```
// Workaround for initializing variable in SRAM
// (MBC RAM and Bank needs to get enabled during GSINIT loading)
static uint8_t AT(0x0000) __rRAMG = 0x0a; // Enable SRAM
static uint8_t AT(0x4000) __rRAMB = 0x00; // Set SRAM bank 0
// Now SRAM is enabled so the variable can get initialized
uint8_t AT(0xA000) initialized_sram_var = 0xA5u;
```

# 5 Coding Guidelines

# 5.1 Learning C / C fundamentals

Writing games and other programs with GBDK will be much easier with a basic understanding of the C language. In particular, understanding how to use C on "Embedded Platforms" (small computing systems, such as the Game Boy) can help you write better code (smaller, faster, less error prone) and avoid common pitfalls.

### 5.1.1 General C tutorials

- https://www.learn-c.org/
- https://www.tutorialspoint.com/cprogramming/index.htm
- https://www.chiark.greenend.org.uk/~sgtatham/cdescent/

### 5.1.2 Embedded C introductions

- http://dsp-book.narod.ru/CPES.pdf
- https://www.phaedsys.com/principals/bytecraft/bytecraftdata/bcfirststeps. $\leftarrow$  pdf

## 5.1.3 Game Boy games in C

https://gbdev.io/resources.html#c

## 5.2 Understanding the hardware

In addition to understanding the C language it's important to learn how the Game Boy hardware works. What it is capable of doing, what it isn't able to do, and what resources are available to work with. A good way to do this is by reading the Pandocs and checking out the awesome\_gb list.

## 5.3 Writing optimal C code for the Game Boy and SDCC

The following guidelines can result in better code for the Game Boy, even though some of the guidance may be contrary to typical advice for general purpose computers that have more resources and speed.

# 5.3.1 Tools

**5.3.1.1 GBTD / GBMB, Arrays and the "const" keyword Important**: The old GBTD/GBMB fails to include the const keyword when exporting to C source files for GBDK. That causes arrays to be created in RAM instead of ROM, which wastes RAM, uses a lot of ROM to initialize the RAM arrays and slows the compiler down a lot.

Use of toxa's updated GBTD/GBMB is highly recommended.\_

If you wish to use the original tools, you must add the const keyword every time the graphics are re-exported to C source files.

## 5.3.2 Avoid Reading from VRAM

In general avoid reading from VRAM since that memory is not accessible at all times. If GBDK a API function which reads from VRAM (such as <a href="mailto:get\_bkg\_tile\_xy">get\_bkg\_tile\_xy</a>()) is called during a video mode when VRAM is not accessible, then that function call will delay until VRAM becomes accessible again. This can cause unnecessary slowdowns when running programs on the Game Boy. It is also not supported by GBDK on the NES platform.

Instead it is better to store things such as map data in general purpose RAM which does not have video mode access limitations.

For more information about video modes and VRAM access see the pan docs:

https://gbdev.io/pandocs/STAT.html#stat-modes

#### 5.3.3 Variables

- Use 8-bit values as much as possible. They will be much more efficient and compact than 16 and 32 bit types.
- Prefer unsigned variables to signed ones: the code generated will be generally more efficient, especially when comparing two values.
- Use explicit types so you always know the size of your variables. int8\_t, uint8\_t, int16\_← t, uint16\_t, int32\_t, uint32\_t and bool. These are standard types defined in stdint.h (#include <stdint.h>) and stdbool.h (#include <stdbool.h>).
- Global and local static variables are generally more efficient than local non-static variables (which go on the stack and are slower and can result in slower code).
  - An exception to this when there are a small number of local variables (one or two) and the code is not complex. Then the compiler may allocate those variables to CPU registers instead which may be faster.
  - Functions which use global or static local variables will loose re-entrancy. In most cases it is not a
    problem, but important to keep in mind.
  - In particular avoid putting big arrays on the stack, consider static local or global.
- Keep the number of arguments passed to functions small (ideally one or two arguments at most). When there
  are a large number of arguments they get pushed onto the stack and result in more overhead for function
  calls. See the Calling Conventions in the SDCC compiler manual for details.
- const keyword: use const for arrays, structs and variables with read-only (constant) data. It will reduce ROM, RAM and CPU usage significantly. Non-const values are loaded from ROM into RAM inefficiently, and there is no benefit in loading them into the limited available RAM if they aren't going to be changed.
- Here is how to declare const pointers and variables:
  - non-const pointer to a const variable: const uint8\_t \* some\_pointer;
  - const pointer to a non-const variable: uint8\_t \* const some\_pointer;
  - const pointer to a const variable: const uint8\_t \* const some\_pointer;
  - https://codeforwin.org/2017/11/constant-pointer-and-pointer-to-constant-in-c.←
     html
  - https://stackoverflow.com/questions/21476869/constant-pointer-vs-pointer-to-con
- For calculated values that don't change, pre-compute results once and store the result. Using lookup-tables and similar approaches can improve speed and reduce code size. Macros can sometimes help. It may be beneficial to do the calculations with an outside tool and then include the result as C code in a const array.
- Use an advancing pointer (someStruct->var = x; someStruct++) to loop through arrays of structs instead of using indexing each time in the loop someStruct[i].var = x.
- When modifying variables that are also changed in an Interrupt Service Routine (ISR), wrap them the relevant code block in a \_\_critical { } block. See http://sdcc.sourceforge.← net/doc/sdccman.pdf#section.3.9
- When using constants and literals the  ${\tt U},\, {\tt L}$  and  ${\tt UL}$  postfixes can be used.
  - U specifies that the constant is unsigned

- L specifies that the constant is long.
- NOTE: In SDCC 3.6.0, the default for char changed from signed to unsigned. The manual says to use
   —fsigned-char for the old behavior, this option flag is included by default when compiling through lcc.
- A fixed point type (fixed) is included with GBDK when precision greater than whole numbers is required for 8 bit range values (since floating point is not included in GBDK).

See the "Simple Physics" sub-pixel example project. Code example:

```
fixed player[2];
...
// Modify player position using its 16 bit representation
player[0].w += player_speed_x;
player[1].w += player_speed_y;
...
// Use only the upper 8 bits for setting the sprite position
move_sprite(0, player[0].h ,player[1].h);
```

### 5.3.4 Code structure

- Do not #include .c source files into other .c source files. Instead create .h header files for them and include those. https://www.tutorialspoint.com/cprogramming/c\_header\_files. ← htm
- Instead of using a blocking delay() for things such as sprite animations/etc (which can prevent the rest of the game from continuing) many times it's better to use a counter which performs an action once every N frames. sys time may be useful in these cases.
- When processing for a given frame is done and it is time to wait before starting the next frame, vsync() can be used. It uses HALT to put the CPU into a low power state until processing resumes. The CPU will wake up and resume processing at the end of the current frame when the Vertical Blanking interrupt is triggered.
- Minimize use of multiplication, modulo with non-powers of 2, and division with non-powers of 2. These operations have no corresponding CPU instructions (software functions), and hence are time costly.
  - SDCC has some optimizations for:
    - \* Division by powers of 2. For example  $n \neq 4u$  will be optimized to n >>= 2.
    - \* Modulo by powers of 2. For example: (n % 8) will be optimized to (n & 0x7).
  - If you need decimal numbers to count or display a score, you can use the GBDK BCD ( binary coded decimal) number functions. See: bcd.h and the BCD example project included with GBDK.
- Avoid long lists of function parameters. Passing many parameters can add overhead, especially if the function is called often. Globals and local static vars can be used instead when applicable.
- Use inline functions if the function is short (with the inline keyword, such as inline uint8\_t my ← Function() { ... }).
- · Do not use recursive functions.

### 5.3.5 GBDK API/Library

- stdio.h: If you have other ways of printing text, avoid including stdio.h and using functions such as printf(). Including it will use a large number of the background tiles for font characters. If stdio.h is not included then that space will be available for use with other tiles instead.
- drawing.h: The Game Boy graphics hardware is not well suited to frame-buffer style graphics such as the kind provided in drawing.h. Due to that, most drawing functions (rectangles, circles, etc) will be slow. When possible it's much faster and more efficient to work with the tiles and tile maps that the Game Boy hardware is built around.

- waitpad() and waitpadup check for input in a loop that doesn't HALT at all, so the CPU will be maxed out until it returns. One alternative is to write a function with a loop that checks input with joypad() and then waits a frame using vsync() (which idles the CPU while waiting) before checking input again.
- joypad(): When testing for multiple different buttons, it's best to read the joypad state *once* into a variable and then test using that variable (instead of making multiple calls).

#### 5.3.6 Toolchain

- See SDCC optimizations: http://sdcc.sourceforge.net/doc/sdccman.pdf#section. $\leftrightarrow$  8.1
- For details about default Compiler data types, see the SDCC Manual (follow links and scroll down 1 page)
  - https://sdcc.sourceforge.net/doc/sdccman.pdf#section.1.1
  - Note: by default GBDK enables --fsigned-char (via lcc) for SDCC
- Use profiling. Look at the ASM generated by the compiler, write several versions of a function, compare them and choose the faster one.
- Use the SDCC --max-allocs-per-node flag with large values, such as 50000. --opt-code-speed has a much smaller effect.
  - GBDK-2020 (after v4.0.1) compiles the library with --max-allocs-per-node 50000, but it must be turned on for your own code.
     (example: lcc ... -Wf--max-allocs-per-node50000 or sdcc ... --max-allocs-per-node 50000).
  - The other code/speed flags are --opt-code-speed or --opt-code-size.
- Use current SDCC builds from <a href="http://sdcc.sourceforge.net/snap.php">http://sdcc.sourceforge.net/snap.php</a>
  The minimum required version of SDCC will depend on the GBDK-2020 release. See GBDK Release Notes
- Learn some ASM and inspect the compiler output to understand what the compiler is doing and how your code gets translated. This can help with writing better C code and with debugging.

## 5.3.7 Constants, Signed-ness and Overflows

There are a some scenarios where the compiler will warn about overflows with constants. They often have to do with mixed signedness between constants and variables. To avoid problems use care about whether or not constants are explicitly defined as unsigned and what type of variables they are used with.

```
WARNING: overflow in implicit constant conversion
```

- A constant can be used where the the value is too high (or low) for the storage medium causing an value overflow.
  - For example this constant value is too high since the max value for a signed 8 bit char is 127.

```
#define TOO_LARGE_CONST 255
int8_t signed_var = TOO_LARGE_CONST;
```

- This can also happen when constants are not explicitly declared as unsigned (and so may get treated by the compiler as signed) and then added such that the resulting value exceeds the signed maximum.
  - For example, this results in an warning even though the sum total is 254 which is less than the 255, the max value for a unsigned 8 bit char variable.

```
#define CONST_UNSIGNED 127u
#define CONST_SIGNED 127
uint8_t unsigned_var = (CONST_SIGNED + CONST_UNSIGNED);
```

It can be avoided by always using the unsigned u when the constant is intended for unsigned operations.

```
#define CONST_UNSIGNED 127u
#define CONST_ALSO_UNSIGNED 127u // <-- Added "u", now no warning
uint8_t unsigned_var = (CONST_UNSIGNED + CONST_ALSO_UNSIGNED);</pre>
```

### 5.3.8 Chars and vararg functions

Parameters (chars, ints, etc) to printf / sprintf should always be explicitly cast to avoid type related parameter passing issues.

For example, below will result in the likely unintended output:

```
printf(str_temp, "%u, %d, %x\n", UINT16_MAX, INT16_MIN, UINT16_MAX);
// Will output: "65535, 0, 8000"
Instead this will give the intended output:
printf(str_temp, "%u, %d, %x\n", (uint16_t)UINT16_MAX, (int16_t)INT16_MIN, (uint16_t)UINT16_MAX);
// Will output: "65535, -32768, FFFF"
```

**5.3.8.1 Chars** In standard C when chars are passed to a function with variadic arguments (varargs, those declared with . . . as a parameter), such as printf(), those chars get automatically promoted to ints. For an 8 bit CPU such as the Game Boy's, this is not as efficient or desirable in most cases. So the default SDCC behavior, which GBDK-2020 expects, is that chars will remain chars and *not* get promoted to ints when **explicitly cast as chars while calling a varargs function**.

- They must be explicitly re-cast when passing them to a varargs function, even though they are already declared as chars.
- · Discussion in SDCC manual:

```
http://sdcc.sourceforge.net/doc/sdccman.pdf#section.1.5
http://sdcc.sourceforge.net/doc/sdccman.pdf#subsection.3.5.10
```

• If SDCC is invoked with -std-cxx (-std-c89, -std-c99, -std-c11, etc) then it will conform to standard C behavior and calling functions such as printf() with chars may not work as expected.

For example:

```
unsigned char i = 0x5A;
// NO:
// The char will get promoted to an int, producing incorrect printf output
// The output will be: 5A 00
printf("%hx %hx", i, i);
// YES:
// The char will remain a char and printf output will be as expected
// The output will be: 5A 5A
printf("%hx %hx", (unsigned char)i, (unsigned char)i);
```

Some functions that accept varargs:

• EMU\_printf, gprintf(), printf(), sprintf()

Also See:

• Other cases of char to int promotion: http://sdcc.sourceforge.net/doc/sdccman. ← pdf#chapter.6

## 5.4 When C isn't fast enough

For many applications C is fast enough but in intensive functions are sometimes better written in assembly. This section deals with interfacing your core C program with fast assembly sub routines.

### 5.4.1 Reusable Local Labels and Inline ASM

When functions are written assembly it's generally better to not mix the inline ASM with C code and instead write the whole function in assembly.

If they are mixed then descriptive named labels should not be used for inline ASM. This is due to descriptive labels interfering with the expected scope of the reusable local labels generated from the compiled C code. The compiler will not detect this problem and the resulting code may fail to execute correctly without warning.

Instead use reusable local symbols/labels (for example 1\$:). To learn more about them check the SDAS manual section "1.3.3 Reusable Symbols"

## 5.4.2 Variables and registers

Getting at C variables is slightly tricky due to how local variables are allocated on the stack. However you shouldn't be using the local variables of a calling function in any case. Global variables can be accessed by name by adding an underscore.

## 5.4.3 Segments / Areas

The use of segments/areas for code, data and variables is more noticeable in assembler. GBDK and SDCC define a number of default ones. The order they are linked is determined by crt0.s and is currently as follows for the Game Boy and related clones.

- · ROM (in this order)
  - \_HEADER: For the Game Boy header
  - \_CODE: CODE is specified as after BASE, but is placed before it due to how the linker works.
  - \_HOME
  - \_BASE
  - **-** \_CODE\_0
  - \_INITIALIZER: Constant data used to init RAM data
  - \_LIT
  - \_GSINIT: Code used to init RAM data
  - \_GSFINAL
- · Banked ROM
  - \_CODE\_x Places code in ROM other than Bank 0, where x is the 16kB bank number.
- · WRAM (in this order)
  - \_DATA: Uninitialized RAM data
  - **-** \_BSS
  - INITIALIZED: Initialized RAM data
  - \_HEAP: placed after \_INITIALIZED so that all spare memory is available for the malloc routines.
  - STACK: at the end of WRAM

### 5.4.4 Calling convention

The following is primarily oriented toward the Game Boy and related clones (sm83 devices), other targets such as sms/gg may vary.

SDCC in common with almost all C compilers prepends a  $\_$  to any function names. For example the function printf(...) begins at the label  $\_printf$ :. Note that all functions are declared global.

Functions can be marked with OLDCALL which will cause them to use the  $\_\_sdccall(0)$  calling convention (the format used prior to SDCC 4.2 & GBDK-2020 4.1.0).

Starting with SDCC 4.2 and GBDK-2020 4.1.0 the new default calling convention is\_\_sdcccall(1).

For additional details about the calling convetions, see sections SM83 calling conventions and Z80, Z180 and Z80N calling conventions in the SDCC manual.

- http://sdcc.sourceforge.net/doc/sdccman.pdf
- Section 4.3.9 isn't specific about it, but gbz80/sm83 generally share this subheading with z80 (Game Boy is partially a sub-port of z80 in SDCC). https://sdcc.sourceforge.net/doc/sdccman.← pdf#subsection.4.3.9
- **5.4.4.1 Banked Calling Convention** The following is primarily oriented toward the Game Boy and related clones (sm83 devices), other targets such as sms/gg may vary.

  Key Points:
  - · Function arguments (if present) are always placed on the stack, right to left without particular alignment
  - A fixed stack offset (sm83:+4, z80:+3) is added by the Callee (to skip the pushed Caller Bank and additional Trampoline Return Address)

• Return values follow the calling convention (\_\_sdcccall (1), or \_\_sdcccall (0) for OLDCALL)

### Terminology:

- Caller: the code which is calling the requested function
- Callee: the function to be called (declared as BANKED or \_\_banked)
- Trampoline: The intermediary which performs the bank switching and does hand-off between Caller and Callee during the call and then return.

### Banked Call Trampoline

- Banked calls are performed via a trampoline in the non-banked region 0000-3ffff
- The \_\_sdcc\_bcall\_ehl trampoline is used by default
  - With it both calling conventions are supported: \_\_sdcccall(1) (default) or \_\_sdcccall(0) for OLDCALL.
- If --legacy-banking is specified to SDCC the \_\_sdcc\_bcall trampoline is used.
  - This may only be used with \_\_sdcccall(0)

Process for a banked call (using \_\_sdcc\_bcall\_ehl, the default)

- 1. The Caller
  - · Function arguments (if present) are always placed on the stack, right to left without particular alignment
  - · The Bank of Callee function is placed into register E
  - The Address of Callee function is placed in HL
  - Calls the bank switch Trampoline (which adds Caller return address to the stack)
- 2. The Trampoline
  - · Saves the Current Bank onto the stack (pushed as AF, so 16 bits)
  - Switches to the Bank of Callee function (in register E)
  - · Calls the Callee function address in HL (which adds Trampoline return address to the stack)
- 3. The Callee Function
  - · SDCC will use an offset to skip the first N bytes of the stack
    - For sm83 (GB/AP/DUCK): skip first 4 bytes
    - For z80 (GG/SMS/etc): skip first 3 bytes
  - Return values follow the calling convention (\_\_sdcccall(1), or \_\_sdcccall(0) for OLDCALL)
  - · Executes a return to Trampoline
- 4. The Trampoline
  - · Switches to the Bank of the Caller saved on the stack (and moves Stack Pointer past it)
  - · Executes a return to Caller
- 5. The Caller
  - · Cleans up the stack and uses return value (if present)

# 6 ROM/RAM Banking and MBCs

## 6.1 ROM/RAM Banking and MBCs (Memory Bank Controllers)

The standard Game Boy cartridge with no MBC has a fixed 32K bytes of ROM. In order to make cartridges with larger ROM sizes (to store more code and graphics) MBCs can be used. They allow switching between multiple ROM banks that use the same memory region. Only one of the banks can be selected as active at a given time, while all the other banks are inactive (and so, inaccessible).

The majority of this section about banking is focused on the Game Boy since that is the original GBDK platform. Much of it still applies for the Game Gear(GG) and Sega Master System(SMS). For additional details about banking specifically related to these two systems see the SMS/GG Banking section.

### 6.1.1 Non-banked cartridges

Cartridges with no MBC controller are non-banked, they have 32K bytes of fixed ROM space and no switchable banks. For these cartridges the ROM space between 0000h and 7FFFh can be treated as a single large bank of 32K bytes, or as two contiguous banks of 16K bytes in Bank 0 at 0000h - 3FFFh and Bank 1 at 4000h to 7FFFh.

### 6.1.2 MBC Banked cartridges (Memory Bank Controllers)

Cartridges with MBCs allow the Game Boy to work with ROMS up to 8MB in size and with RAM up to 128kB. Each bank is 16K Bytes. The following are *usually* true, with some exceptions:

- Bank 0 of the ROM is located in the region at 0000h 3FFFh. It is fixed (non-banked) and cannot be switched out for another bank.
- Banks 1 .. N can be switched into the upper region at 4000h 7FFFh. The upper limit for N is determined by the MBC used and available cartridge space.
- It is not necessary to manually assign Bank 0 for source files, that will happen by default if no bank is specified.

See the Pandocs for more details about the individual MBCs and their capabilities.

### 6.1.3 Recommended MBC type

For most projects we recommend MBC5.

- The SWITCH\_ROM() / ref SWITCH\_RAM() macros work with MBC5 (up to ROM bank 255, SWITCH\_ROM\_MBC5\_8M may be used if a larger size is needed).
- MBC1 is not recommended. Some banks in it's range are unavailable. See pandocs for more details. https://gbdev.io/pandocs/MBC1
- **6.1.3.1** Bank 0 Size Limit and Overflows When Using MBCs When using MBCs and bank switching the space used in the lower fixed Bank 0 must be <= 16K bytes. Otherwise it's data will overflow into Bank 1 and may be overwriten or overwrite other data, and can get switched out when banks are changed. See the FAQ entry about bank overflow errors.
- **6.1.3.2** Conserving Bank 0 for Important Functions and Data When using MBCs, Bank 0 is the only bank which is always active and it's code can run regardless of what other banks are active. This means it is a limited resource and should be prioritized for data and functions which must be accessible regardless of which bank is currently active.

### 6.2 Working with Banks

To assign code and constant data (such as graphics) to a ROM bank and use it:

- Place the code for your ROM bank in one or several source files.
- · Specify the ROM bank to use, either in the source file or at compile/link time.
- Specify the number of banks and MBC type during link time.
- When the program is running and wants to use data or call a function that is in a given bank, manually or automatically set the desired bank to active.

### 6.2.1 Setting the ROM bank for a Source file

The ROM and RAM bank for a source file can be set in a couple different ways. Multiple different banks cannot be assigned inside the same source file (unless the \_\_addressmod method is used), but multiple source files can share the same bank.

If no ROM and RAM bank are specified for a file then the default \_CODE, \_BSS and \_DATA segments are used. Ways to set the ROM bank for a Source file:

- #pragma bank <N> at the start of a source file. Example (ROM bank 2): #pragma bank 2
- The lcc switch for ROM bank -Wf-bo<N>. Example (ROM bank 2): -Wf-bo2
- · Using rom autobanking

Note: You can use the NONBANKED keyword to define a function as non-banked if it resides in a source file which has been assigned a bank.

### 6.2.2 Setting the RAM bank for a Source file

• Using the lcc switch for Cartridge SRAM bank -Wf-ba<N>. Example (Cartridge SRAM bank 3): -Wf-ba3

### 6.2.3 Setting the MBC and number of ROM & RAM banks available

At the link stage this is done with lcc using pass-through switches for makebin.

- -Wm-yo<N> where <N> is the number of ROM banks. 2, 4, 8, 16, 32, 64, 128, 256, 512
  - -Wm-yoA may be used for automatic bank size.
- -Wm-ya<N> where <N> is the number of RAM banks. 2, 4, 8, 16, 32
- -Wm-yt<N> where <N> is the type of MBC cartridge (see chart below).
  - Example: Wm-yt0x1A
- If passing the above arguments to makebin directly without using lcc, then the -Wm part should be omitted.
  - Note: Some makebin switches (such as -yo A) require a space when passed directly. See makebin-settings for details.

The MBC settings below are available when using the makebin -W1-yt < N > switch.

Source: Pandocs. Additional details available at Pandocs

For SMS/GG, the ROM file size must be at least 64K to enable mapper support for RAM banks in emulators.

• If the generated ROM is too small then  $-y \circ 4$  for makebin (or  $-Wm-y \circ 4$  for LCC) can be used to set the size to 64K.

### 6.2.4 MBC Type Chart

```
0147: Cartridge type:
0x00: ROM ONLY
                                0x12: ROM+MBC3+RAM
0x01: ROM+MBC1
                                0x13: ROM+MBC3+RAM+BATT
0x02: ROM+MBC1+RAM
                                0x19: ROM+MBC5
                                0x1A: ROM+MBC5+RAM
0x03: ROM+MBC1+RAM+BATT
0x05: ROM+MBC2
                                0x1B: ROM+MBC5+RAM+BATT
                                0x1C: ROM+MBC5+RUMBLE
0x06: ROM+MBC2+BATTERY
                                0x1D: ROM+MBC5+RUMBLE+SRAM
0x08: ROM+RAM
0x09: ROM+RAM+BATTERY
                                0x1E: ROM+MBC5+RUMBLE+SRAM+BATT
0x0B: ROM+MMM01
                                0x1F: Pocket Camera
0x0C: ROM+MMM01+SRAM
                                0xFD: Bandai TAMA5
0x0D: ROM+MMM01+SRAM+BATT
                                0xFE: Hudson HuC-3
0x0F: ROM+MBC3+TIMER+BATT
                                0xFF: Hudson HuC-1
0x10: ROM+MBC3+TIMER+RAM+BATT
0x11: ROM+MBC3
```

Hex Code	MBC Type	SRAM	Battery	RTC	Rumble	Extra	Max ROM Size (1)
0x00	ROM ONLY						32 K
0x01	MBC-1 (2)						2 MB
0x02	MBC-1 (2)	SRAM					2 MB
0x03	MBC-1 (2)	SRAM	BATTERY				2 MB
0x05	MBC-2						256 K
0x06	MBC-2		BATTERY				256 K
0x08	ROM (3)	SRAM					32 K
0x09	ROM (3)	SRAM	BATTERY				32 K

Hex Code	MBC Type	SRAM	Battery	RTC	Rumble	Extra	Max ROM Size (1)
0x0B	MMM01						8 MB / N
0x0C	MMM01	SRAM					8 MB / N
0x0D	MMM01	SRAM	BATTERY				8 MB / N
0x0F	MBC-3		BATTERY	RTC			2 MB
0x10	MBC-3 (4)	SRAM	BATTERY	RTC			2 MB
0x11	MBC-3						2 MB
0x12	MBC-3 (4)	SRAM					2 MB
0x13	MBC-3 (4)	SRAM	BATTERY				2 MB
0x19	MBC-5						8 MB
0x1A	MBC-5	SRAM					8 MB
0x1B	MBC-5	SRAM	BATTERY				8 MB
0x1C	MBC-5				RUMBLE		8 MB
0x1D	MBC-5	SRAM			RUMBLE		8 MB
0x1E	MBC-5	SRAM	BATTERY		RUMBLE		8 MB
0x20	MBC-6						$\sim$ 2MB
0x22	MBC-7	SRAM	BATTERY		RUMBLE	SENSOR	2MB
0xFC	POCKET CAMERA						To Do
0xFD	BANDAI TAMA5						To Do
0xFE	HuC3			RTC		<u>.</u>	To Do
0xFF	HuC1	SRAM	BATTERY			IR	To Do

- 1: Max possible size for MBC is shown. When used with generic SWITCH\_ROM() the max size may be smaller. For example:
  - The max for MBC1 becomes Bank 31 (512K)
  - The max for MBC5 becomes Bank 255 (4MB). To use the full 8MB size of MBC5 see SWITCH ROM MBC5 8M().
- 2: For MBC1 some banks in it's range are unavailable. See pandocs for more details <a href="https://gbdev.\infty] io/pandocs/MBC1</a>
- 3: No licensed cartridge makes use of this option. Exact behaviour is unknown.
- 4: MBC3 with RAM size 64 KByte refers to MBC30, used only in Pocket Monsters Crystal Version for Japan.

## 6.2.5 Getting Bank Numbers

The bank number for a banked function, variable or source file can be stored and retrieved using the following macros:

- BANKREF(): create a reference for retrieving the bank number of a variable or function
- BANK(): retrieve a bank number using a reference created with BANKREF()
- BANKREF\_EXTERN(): Make a BANKREF() reference residing in another source file accessible in the current file for use with BANK().

## 6.2.6 Banking and Functions

# 6.2.6.1 BANKED/NONBANKED Keywords for Functions

- BANKED (is a calling convention):
  - The function will use banked (far) sdcc calls (which switch to the function's ROM bank automatically).
  - Placed in the bank selected by its source file (or compiler switches).
  - This keyword only specifies the calling convention for the function, it does not set a bank itself.
- NONBANKED (is a storage attribute):
  - Placed in the non-banked lower 16K region (bank 0), regardless of the bank selected by its source file.

- Forces the .area to \_HOME.
- <not-specified>:
  - The function does not use sdcc banked calls (near instead of far/banked sdcc calls)
  - Placed in the bank selected by its source file (or compiler switches).

#### 6.2.6.2 Banked Function Calls Functions in banks can be called as follows:

- When defined with the BANKED keyword. Example: void my\_function() BANKED { do stuff } in a source file which has had its bank set (see above).
- Using far\_pointers
- When defined with an area set up using the \_\_addressmod keyword (see the banks\_new example project and the SDCC manual for details).
- Using SWITCH\_ROM() (and related functions for other MBCs) to manually switch in the required bank and then call the function.

Non-banked functions (either in fixed Bank 0, or in an non-banked ROM with no MBC):

- · May call functions in any bank: YES
- · May use data in any bank: YES

Banked functions (located in a switchable ROM bank)

- · May call functions in fixed Bank 0: YES
- · May call BANKED functions in any bank: YES
  - The compiler and library will manage the bank switching automatically using the bank switching trampoline.
- May use data in any bank: NO
  - May only use data from fixed Bank 0 and the currently active bank.
  - A NONBANKED wrapper function may be used to access data in other banks.
  - Banks cannot be switched manually from inside a BANKED function (otherwise it will switch out it's own function code as it is executing it, likely leading to a crash).

#### Limitations:

• SDCC banked calls and far\_pointers in GBDK only save one byte for the ROM bank. So, for example, they are limited to **bank 31** max for MBC1 and **bank 255** max for MBC5. This is due to the bank switching for those MBCs requiring a second, additional write to select the upper bits for more banks (banks 32+ in MBC1 and banks 256+ in MBC5).

## Calling Convention:

For details see Banked Calling Convention

## 6.2.7 Const Data (Variables in ROM)

Data declared as const (read only) will be stored in ROM in the bank associated with it's source file (if none is specified it defaults to Bank 0). If that bank is a switchable bank then the data is only accesible while the given bank is active.

## 6.2.8 Variables in RAM

Todo Variables in RAM

6.3 Auto-Banking 25

#### 6.2.9 Far Pointers

Far pointers include a segment (bank) selector so they are able to point to addresses (functions or data) outside of the current bank (unlike normal pointers which are not bank-aware). A set of macros is provided by GBDK 2020 for working with far pointers.

**Warning:** Do not call the far pointer function macros from inside interrupt routines (ISRs). The far pointer function macros use a global variable that would not get restored properly if a function called that way was interrupted by another one called the same way. However, they may be called recursively.

See FAR\_CALL, TO\_FAR\_PTR and the banks\_farptr example project.

#### 6.2.10 Bank switching

You can manually switch banks using the SWITCH\_ROM(), SWITCH\_RAM(), and other related macros. See banks.c project for an example.

Note: You can only do a switch\_rom\_bank call from non-banked \_CODE since otherwise you would switch out the code that was executing. Global routines that will be called without an expectation of bank switching should fit within the limited 16k of non-banked \_CODE.

## 6.2.11 Wrapper Function for Accessing Banked Data

In order to load Data in one bank from code running in another bank a NONBANKED wrapper function can be used. It can save the current bank, switch to another bank, operate on some data, restore the original bank and then return.

An example function which can:

- Load background data from any bank
- And which can be called from code residing in any bank

```
// This function is NONBANKED so it resides in fixed Bank 0
void set_banked_bkg_data(uint8_t first_tile, uint8_t nb_tiles, const uint8_t *data, uint8_t bank) NONBANKED
{
    uint8_t save = CURRENT_BANK;
    SWITCH_ROM(bank);
    set_bkg_data(first_tile, nb_tiles, data);
    SWITCH_ROM(save);
}
// And then it can be called from any bank:
set_banked_bkg_data(<first_tile>, <num tiles>, tile_data, BANK(tile_data));
```

## 6.2.12 Currently active bank: CURRENT\_BANK

The global variable CURRENT\_BANK (a macro for \_current\_bank) is updated automatically when calling SWITCH\_ROM(), SWITCH\_ROM\_MBC1() and SWITCH\_ROM\_MBC5, or when a BANKED function is called. Normaly banked calls are used and the active bank does not need to be directly managed, but in the case that it does the following shows how to save and restore it.

```
// The current bank can be saved
uint8_t _saved_bank = CURRENT_BANK;
// Call some function which changes the bank but does not restore it
// ...
// And then restored if needed
SWITCH_ROM(_saved_bank);
```

## 6.3 Auto-Banking

A ROM bank auto-assignment feature was added in GBDK 2020 4.0.2.

Instead of having to manually specify which bank a source file will reside in, the banks can be assigned automatically to make the best use of space. The bank assignment operates on object files, after compiling/assembling and before linking.

To turn on auto-banking, use the -autobank argument with lcc.

For a source example see the banks\_autobank project.

In the source files you want auto-banked, do the following:

- Set the source file to be autobanked #pragma bank 255 (this sets the temporary bank to 255, which bankpack then updates when repacking).
- Create a reference to store the bank number for that source file: BANKREF (<some-bank-reference-name>).

More than one BANKREF () may be created per file, but they should always have unique names.

In the other source files you want to access the banked data from, do the following:

- Create an extern so the bank reference in another file is accessible: BANKREF\_EXTERN (<some-bank-reference-name)
- Obtain the bank number using BANK (<some-bank-reference-name>).

```
Example: level_1_map.c
#pragma bank 255
BANKREF(level_1_map)
...
const uint8_t level_1_map[] = {... some map data here ...};
Accessing that data: main.c
BANKREF_EXTERN(level_1_map)
...
SWITCH_ROM( BANK(level_1_map) );
// Do something with level_1_map[]
```

• Fixed banked source files can be used in the same project as auto-banked source files. The bankpack tool will attempt to pack the auto-banked source files as efficiently as possible around the fixed-bank ones.

Making sure bankpack checks all files:

Features and Notes:

• In order to correctly calculate the bank for all files every time, it is best to use the -ext= flag and save the auto-banked output to a different extension (such as .rel) and then pass the modified files to the linker. That way all object files will be processed each time the program is compiled.

```
Recommended:
.c and .s -> (compiler) .o -> (bankpack) -> .rel -> (linker) ... -> .gb
```

- It is important because when bankpack assigns a bank for an autobanked (bank=255) object file (.o) it rewrites the bank and will then no longer see the file as one that needs to be auto-banked. That file will then remain in its previously assigned bank until a source change causes the compiler to rebuild it to an object file again which resets its bank to 255.
- For example consider a fixed-bank source file growing too large to share a bank with an auto-banked source file that was previously assigned to it. To avoid a bank overflow it would be important to have the auto-banked file check every time whether it can share that bank or not.
- · See bankpack for more options and settings.

#### 6.4 Errors related to banking (overflow, multiple writes to same location)

A bank overflow during compile/link time (in makebin) is when more code and data are allocated to a ROM bank than it has capacity for. The address for any overflowed data will be incorrect and the data is potentially unreachable since it now resides at the start of a different bank instead of the end of the expected bank.

See the FAQ entry about bank overflow errors.

The current toolchain can only detect and warn (using ihxcheck) when one bank overflows into another bank that has data at its start. It cannot warn if a bank overflows into an empty one. For more complete detection, you can use the romusage tool.

# 6.5 Bank space usage

In order to see how much space is used or remains available in a bank you can use the romusage tool.

# 6.5.1 Other important notes

• The SWITCH\_ROM\_MBC5 macro is not interrupt-safe. If using less than 256 banks you may always use SWITCH\_ROM - that is faster. Even if you use mbc5 hardware chip in the cart.

# 6.6 Banking example projects

There are several projects in the GBDK 2020 examples folder which demonstrate different ways to use banking.

- Banks: a basic banking example
- Banks\_new: examples of using new bank assignment and calling conventions available in GBDK 2020 and its updated SDCC version.
- Banks\_farptr: using far pointers which have the bank number built into the pointer.
- Banks\_autobank: shows how to use the bank auto-assignment feature in GBDK 2020 4.0.2 or later, instead of having to manually specify which bank a source file will reside it.

"SMS/GG Banking" section.

## 6.7 SMS/Game Gear Banking

The memory banking setup for SMS and Game Gear in GBDK is different than it is for the Game Boy. Instead of a single switchable bank in the  $0 \times 4000 - 0 \times 7 FFF$  range, there are two switchable frames at different address ranges. The configuration is as follows:

- Frame 0: Non-banked, at address 0x0000 0x3FFF
- Frame 1: CODE <N>, at address 0x4000 0x7FFF
  - Use for: Banked Code and Assets
  - Example: #pragma codeseg CODE\_2 or #pragma codeseg CODE\_255 for autobanking (no leading underscore)
  - Select the active bank using: SWITCH\_ROM(). The current active bank can be queried using CURRENT\_BANK or MAP\_FRAME1
- Frame 2: \_LIT\_<N>, at address 0x8000- 0xBFFF
  - Use for: Assets
  - \_DATA\_N may also be mapped into Frame 2 (RAM)
  - Example: #pragma codeseg LIT\_2 or #pragma codeseg LIT\_255 for autobanking (no leading underscore)
  - Select the active bank using SWITCH\_ROM2(). The current active bank can be queried using MAP\_←
    FRAME2

Banked code and any pointers associated with it will only work correctly when active in Frame 1 (at 0x4000), so it must use CODE\_<N>. Graphics and other assets may go in either Frame 1 (at 0x4000) or, if designed for it then Frame 2 (at 0x8000).

## 6.7.1 Auto-Banking

CODE and LIT cannot share the same bank number. For example, if CODE is assigned to bank 3 then LIT cannot be in bank 3 as well.

bankpack is aware of this requirement and will group CODE and LIT separately when packing for autobanking. It's process is as follows:

- 1. Note: CODE and LIT are not sorted before packing
- 2. Assign fixed banks first (for both CODE and LIT). An error will be generated if both types assigned to the same bank. Banks are marked exclusive to whichever type is assigned in them first.
- 3. Then autobanked entries (both CODE and LIT) are assigned to banks, they are only assigned to banks of a matching type or an unused bank. Same as above, the first type to use a bank makes it exclusive to that type.

The bankpack option <code>-banktype=</code> may be used to set a bank to use specific type (<code>CODE</code> or <code>LIT</code>). This will take effect before bankpack tries to perform any bank assignment. For example: <code>-banktype=2:LIT</code> (or <code>-Wb-banktype=2:LIT</code> when used with <code>lcc</code>) sets bank 2 to exclusively use type <code>LIT</code>.

## 7 GBDK Toolchain

#### 7.1 Overview

GBDK 2020 uses the SDCC compiler along with some custom tools to build Game Boy ROMs.

- All tools are located under bin/
- The typical order of tools called is as follows (when using lcc these steps are usually performed automatically).
  - 1. Compile and assemble source files (.c, .s, .asm) with sdcc and sdasgb
  - 2. Optional: perform auto banking with bankpack on the object files
  - 3. Link the object files into .ihx file with sdldgb
  - 4. Validate the .ihx file with ihxcheck
  - 5. Convert the .ihx file to a ROM file (.gb, .gbc) with makebin

To see individual arguments and options for a tool, run that tool from the command line with either no arguments or with -h.

# 7.2 Data Types

For data types and special C keywords, see asm/sm83/types.h and asm/types.h.

Also see the SDCC manual (scroll down a little on the linked page): http://sdcc.sourceforge.

net/doc/sdccman.pdf#section.1.1

# 7.3 Changing Important Addresses

It is possible to change some of the important addresses used by the toolchain at link time using the -WI-g XXX=YYY and =WI-b XXX=YYY flags (where XXX is the name of the data, and YYY is the new address). lcc will include the following linker defaults for sdldgb if they are not defined by the user.

- \_shadow\_OAM
  - Location of sprite ram (requires 0xA0 bytes).
  - Default -Wl-g \_shadow\_OAM=0xC000
- .STACK
  - Initial stack address
  - Default -Wl-g .STACK=0xE000
- .refresh\_OAM
  - Address to which the routine for refreshing OAM will be copied (must be in HIRAM). Default
  - Default -Wl-q .refresh\_OAM=0xFF80
- \_DATA
  - Start of RAM section (starts after Shadow OAM)
  - Default -W1-b \_DATA=0xc0A0
- \_CODE
  - Start of ROM section
  - Default -W1-b \_CODE=0x0200

# 7.4 Compiling programs

The lcc program is the front end compiler driver for the actual compiler, assembler and linker. It works out what you want to do based on command line options and the extensions of the files you give it, computes the order in which the various programs must be called and then executes them in order. Some examples are:

Compile the C source 'source.c', assemble and link it producing the Gameboy image 'image.gb'

```
lcc -o image.gb source.c
```

· Assemble the file 'source.s' and link it producing the Gameboy image 'image.gb'

```
lcc -o image.gb source.s
```

· Compile the C program 'source1.c' and assemble it producing the object file 'object1.o' for later linking.

```
lcc -c -o object1.o source1.c
```

· Assemble the file 'source2.s' producing the object file 'object2.o' for later linking

```
lcc -c -o object2.o source2.s
```

· Link the two object files 'object1.o' and 'object2.o' and produce the Gameboy image 'image.gb'

```
lcc -o image.gb object1.o object2.o
```

• Do all sorts of clever stuff by compiling then assembling source1.c, assembling source2.s and then linking them together to produce image.gb.

```
lcc -o image.gb source1.c source2.s
```

Arguments to the assembler, linker, etc can be passed via lcc using -Wp..., -Wf..., -Wa... and -Wl... to pass options to the pre-processor, compiler, assembler and linker respectively. Some common options are:

· To generate an assembler listing file.

```
-Wa-1
```

· To generate a linker map file.

```
-W1-m
```

• To bind var to address 'addr' at link time.

```
-Wl-gvar=addr
```

For example, to compile the example in the memory section and to generate a listing and map file you would use the following. Note the leading underscore that C adds to symbol names.

```
lcc -Wa-l -Wl-m -Wl-g_snd_stat=0xff26 -o image.gb hardware.c
```

#### 7.4.1 Makefiles

## 7.4.2 Using Makefiles

Please see the sample projects included with GBDK-2020 for a couple different examples of how to use Makefiles. You may also want to read a tutorial on Makefiles. For example:

```
https://makefiletutorial.com/
https://www.tutorialspoint.com/makefile/index.htm
```

## 7.4.3 Linker Files and ROM Auto Banking

When bankpack is called through lcc it will now always use linkerfile output (-lkout=) for passing files to the linker (all input object files and linkerfiles will get get consolidated to a single linkerfile). Bankpack:

- lkin=<filename>: Adds a input linkerfile (can specify multiple ones)
- -lkout=<filename>: Enables linkerfile output and sets name (only one can be specified). ALL loaded object files, both from the command line and any loaded from linkerfiles will have their names written to this single output.

#### LCC + Bankpack:

- lcc passes all input linkerfiles (from -Wl-f<name>) to bankpack (-lkin=)
- Linkerfile output is always used when lcc calls bankpack (-lkout=)
- · A temporary file name is used for bankpack linkerfile output.
- 1cc clears out the linker object file and linkerfile lists, then uses the single linkerfile generated by bankpack

Also see the linkerfile example project.

## 7.5 Build Tools

#### 7.5.1 Icc

Icc is the compiler driver (front end) for the GBDK/sdcc toolchain.

For detailed settings see lcc-settings

It can be used to invoke all the tools needed for building a rom. If preferred, the individual tools can be called directly.

- the -v flag can be used to show the exact steps lcc executes for a build
- lcc can compile, link and generate a binary in a single pass: lcc -o somerom.qb somesource.c
- Icc now has a -debug flag that will turn on the following recommended flags for debugging
  - --debug for sdcc (lcc equiv: -Wf-debug)
  - y enables .cdb output for sdldgb (lcc equiv: -Wl-y)
  - -j enables .noi output for sdldgb (lcc equiv: -Wl-j)

# 7.5.2 sdcc

SDCC C Source compiler.

For detailed settings see sdcc-settings

• Arguments can be passed to it through lcc using -Wf-<argument> and -Wp-<argument> (preprocessor)

## 7.5.3 sdasgb

SDCC Assembler for the Game Boy. For detailed settings see sdasgb-settings

• Arguments can be passed to it through <a href="mailto:loc">lcc using -Wa-<a href="mailto:wa-4">-Wa-<a href="mailto:lcc">-Wa-<a href="mailto:lcc">argument></a>

7.6 GBDK Utilities 31

## 7.5.4 bankpack

Automatic Bank packer.

For detailed settings see bankpack-settings

When enabled, automatically assigns banks for object files where bank has been set to 255, see rom\_autobanking. Unless an alternative output is specified the given object files are updated with the new bank numbers.

- Can be enabled by using the -autobank argument with lcc.
- Must be called after compiling/assembling and before linking.
- Arguments can be passed to it through lcc using -Wb-<argument>

## 7.5.5 sdldgb

The SDCC linker for the gameboy.

For detailed settings see sdldgb-settings

Links object files (.o) into a .ihx file which can be processed by makebin

Arguments can be passed to it through lcc using -W1-<argument>

#### 7.5.6 ihxcheck

IHX file validator.

For detailed settings see ihxcheck-settings

Checks .ihx files produced by sdldgb for correctness.

- It will warn if there are multiple writes to the same ROM address. This may indicate mistakes in the code or ROM bank overflows
- Arguments can be passed to it through lcc using -Wi-<argument>

#### 7.5.7 makebin

IHX to ROM converter.

- For detailed settings see makebin-settings
- For makebin -yt MBC values see setting\_mbc\_and\_rom\_ram\_banks

Converts .ihx files produced by sdldgb into ROM files (.gb, .gbc). Also used for setting some ROM header data.

Arguments can be passed to it through lcc using -Wm-<argument>

# 7.6 GBDK Utilities

## 7.6.1 GBCompress

Compression utility.

For detailed settings see gbcompress-settings

Compresses (and decompresses) binary file data with the gbcompress algorithm (also used in GBTD/GBMB). Decompression support is available in GBDK:

- gb\_decompress(), gb\_decompress\_bkg\_data(), gb\_decompress\_win\_data(), gb\_decompress\_sprite\_data()
- The cross-platform/gbdecompress example demonstrates how to use this compression

The utility can also compress (and decompress) using block style RLE encoding with the --alg=rle flag. Decompression support is available in GBDK:

- rle\_init(), rle\_decompress()
- The cross-platform/rle\_map example demonstrates how to use this compression

## 7.6.2 png2asset

Tool for converting PNGs into GBDK format MetaSprites and Tile Maps.

- Convert single or multiple frames of graphics into metasprite structured data for use with the ...metasprite...() functions.
- When -map is used, converts images into Tile Maps and matching Tile Sets
- · Supports Game Boy / Color, SGB borders, SMS/GG, NES

For detailed settings see png2asset-settings

For working with sprite properties (including cgb palettes), see metasprite\_and\_sprite\_properties For API support see move metasprite() and related functions in metasprites.h

#### 7.6.2.1 Working with png2asset

- The origin (pivot) for the metasprite is not required to be in the upper left-hand corner as with regular hardware sprites. See -px and -py.
- The conversion process supports using both SPRITES\_8x8 (-spr8x8) and SPRITES\_8x16 mode (-spr8x16). If 8x16 mode is used then the height of the metasprite must be a multiple of 16.

# **7.6.2.1.1 Terminology** The following abbreviations are used in this section:

- · Original Game Boy and Game Boy Pocket style hardware: DMG
- Game Boy Color: CGB

**7.6.2.1.2 Conversion Process** png2asset accepts any png as input, although that does not mean any image will be valid. The program will follow the next steps:

- The image will be subdivided into tiles of 8x8 or 8x16.
- · For each tile a palette will be generated.
- If there are more than 4 colors in the palette it will throw an error.
- The palette will be sorted from darkest to lightest. If there is a transparent color that will be the first one (this will create a palette that will also work with DMG devices).
- If there are more than 8 palettes the program will throw an error.

With all this, the program will generate a new indexed image (with palette), where each 4 colors define a palette and all colors within a tile can only have colors from one of these palettes

It is also posible to pass a indexed 8-bit png with the palette properly sorted out, using -keep palette order

- Palettes will be extracted from the image palette in groups of 4 colors.
- Each tile can only have colors from one of these palettes per tile.
- The maximum number of colors is 32.

For indexed color images, sometimes RGB paint programs mix up indexed colors in tiles if the same color exists in multiple palettes.

• -repair\_indexed\_pal can be used to fix this problem, though tiles must still follow the rule of using only one palette per tile.

Using this image a tileset will be created

- · Duplicated tiles will be removed.
- Tiles will be matched without mirror, using vertical mirror, horizontal mirror or both (use -noflip to turn off matching mirrored tiles).
- The palette won't be taken into account for matching, only the pixel color order, meaning there will be a match between tiles using different palettes but looking identical on grayscale.

7.6 GBDK Utilities 33

**7.6.2.1.3 Maps** Passing –map the png can be converted to a map that can be used in both the background and the window. In this case, png2asset will generate:

- · The palettes
- · The tileset
- · The map
- · The color info
  - By default, an array of palette index for each tile. This is not the way the hardware works but it takes
    less space and will create maps compatibles with both DMG and CGB devices.
  - Passing -use\_map\_attributes will create an array of map attributes. It will also add mirroring info for each tile and because of that maps created with this won't be compatible with DMG.
    - \* Use -noflip to make background maps which are compatible with DMG devices.

**7.6.2.1.4 Meta sprites** By default the png will be converted to metasprites. The image will be subdivided into meta sprites of -sw x - sh. In this case png2asset will generate:

- · The metasprites, containing an array of:
  - tile index
  - y offset
  - x offset
  - flags, containing the mirror info, the palettes for both DMG and GBC and the sprite priority
- · The metasprites array

**7.6.2.1.5** Super Game Boy Borders (SGB) Screen border assets for the Super Game Boy can be generated using png2asset.

The following flags should be used to perform the conversion:

- <input\_border\_file.png> -map -bpp 4 -max\_palettes 4 -pack\_mode sgb -use← \_map\_attributes -c <output\_border\_data.c>
- Where <input\_border\_file.png> is the image of the SGB border (256x224) and <output\_← border\_data.c> is the name of the source file to write the assets out to.

See the sgb\_border example project for more details.

#### 7.6.3 makecom

Converts a binary .rom file to .msxdos com format, including splitting the banks up into separate files.

• For detailed settings see makecom-settings

#### 7.6.4 png2hicolorgb

An updated version of Glen Cook's Windows GUI "hicolour.exe" 1.2 conversion tool for the Game Boy Color. The starting code base was the 1.2 release.

• For detailed settings see Hi Color on the Game Boy Color is a technique for displaying backgrounds with thousands of colors instead being limited to 32 colors for the entire screen background. It achieves this by changing ~16 colors of the background palette per scanline. The main tradeoffs are that it uses much of the Game Boy's available cpu processing per frame and requires more ROM space. The tile patterns, map, attributes and per-scanline palettes are pre-calculated using the PC based conversion tool.

For the current GBDK example ISR implementation there is a limit of 6 sprites per line before the hi-color timing breaks down and there start to be background artifacts.

Example: png2hicolorgb myimage.png --csource -o=my\_output\_filename Example with higher quality (slower conversion): png2hicolorgb myimage.png --csource -o=my\_output\_← filename --type=3 -L=2 -R=2 Historical credits and info:
Original Concept: Icarus Productions
Original Code: Jeff Frohwein
Full Screen Modification: Anon
Adaptive Code: Glen Cook
Windows Interface: Glen Cook
Additional Windows Programming: Rob Jones
Original Quantiser Code: Benny
Quantiser Conversion: Glen Cook

**7.6.4.1 Additional Details** For technical details about the conversion process and rendering, see: https↔://github.com/bbbbbr/png2hicolorgb

#### 7.6.5 romusage

A utility for estimating usage of Game Boy and SMS/GG ROMs from .noi and .map files, binary ROMs and more.

For detailed settings see romusage-settings

Example: romusage myprogram.noi -g

# 8 Supported Consoles & Cross Compiling

## 8.1 Consoles Supported by GBDK

As of version 4.2.0 GBDK includes support for other consoles in addition to the Game Boy.

- · Game Boy and related clones
  - Nintendo Game Boy / Game Boy Color (GB/GBC)
  - Analogue Pocket (AP)
  - Mega Duck / Cougar Boy (DUCK)
- · Sega Consoles
  - Sega Master System (SMS)
  - Sega Game Gear (GG)
- NES/Famicom (NES)
- MSX DOS (MSXDOS) (partial support)

While the GBDK API has many convenience functions that work the same or similar across different consoles, it's important to keep their different capabilities in mind when writing code intended to run on more than one. Some (but not all) of the differences are screen sizes, color capabilities, memory layouts, processor type (z80 vs gbz80/sm83) and speed.

## 8.2 Cross Compiling for Different Consoles

# 8.2.1 Icc

When compiling and building through lcc use the -m < port > : < plat > flag to select the desired console via its port and platform combination. See below for available settings.

#### 8.2.2 sdcc

When building directly with the sdcc toolchain, the following must be specified manually (when using lcc it will populate these automatically based on -m < port > : < plat >). When compiling with sdcc:

```
• -m<port>, -D__PORT_<port> and -D__TARGET_<plat>
```

When assembling select the appropriate include path: -I<qbdk-path>lib/<plat>.

The assemblers used are:

- sdasgb (for GB/AP)
- sdasz80 (for SMS/GG)
- sdas6500 (for NES)

#### When linking:

- Select the appropriate include paths: -k <gbdk-path>lib/<port>, -k <gbdk-path>lib/<plat>
- Include the appropriate library files -1 <port>.lib, -1 <plat>.lib
- The crt will be under <gbdk-path>lib/<plat>/crt0.o

The linkers used are:

- sdldgb (for GB/AP)
- sdldz80 (for SMS/GG or MSXDOS)
- sdld6808 (for NES)

MSXDOS requires an additional build step with makecom after makebin to create the final binary:

```
• makecom <image.bin> [<image.noi>] <output.com>
```

## 8.2.3 Console Port and Platform Settings

Note: Starting with GBDK-2020 4.1.0 and SDCC 4.2, the Game Boy and related clones use sm83 for the port instead of gbz80

- · Nintendo Game Boy / Game Boy Color
  - lcc: -msm83:gb
  - port:sm83, plat:gb
- Analogue Pocket
  - lcc: -msm83:ap
  - port:sm83, plat:ap
- · Mega Duck / Cougar Boy
  - lcc: -msm83:duck
  - port:sm83, plat:duck
- · Sega Master System
  - lcc: -mz80:sms
  - port:z80, plat:sms
- Sega Game Gear
  - lcc:-mz80:gg

- port:z80, plat:gg
- NES
  - lcc: -mmos6502:nes
  - port:mos6502, plat:nes
- MSX DOS
  - lcc: -mz80:msxdos
  - port:z80, plat:msxdos

#### 8.3 Cross-Platform Constants

There are several constant #defines that can be used to help select console specific code during compile time (with #ifdef, #ifndef).

#### 8.3.1 Console Identifiers

- When <gb/>gb.h> is included (either directly or through <gbdk/platform.h>)
  - When building for Game Boy:
    - \* NINTENDO will be #defined
    - \* GAMEBOY will be #defined
  - When building for Analogue Pocket
    - \* NINTENDO will be #defined
    - \* ANALOGUEPOCKET will be #defined
  - When building for Mega Duck / Cougar Boy
    - \* NINTENDO will be #defined
    - \* MEGADUCK will be #defined
- When <sms/sms.h> is included (either directly or through <qbdk/platform.h>)
  - When building for Master System
    - \* SEGA will be #defined
    - \* MASTERSYSTEM will be #defined
  - When building for Game Gear
    - \* SEGA will be #defined
    - \* GAMEGEAR will be #defined
- When <nes/nes.h> is included (either directly or through <gbdk/platform.h>)
  - NINTENDO NES will be #defined
- When <msx/msx.h> is included (either directly or through <qbdk/platform.h>)
  - MSXDOS will be #defined

# 8.3.2 Console Hardware Properties

Constants that describe properties of the console hardware are listed below. Their values will change to reflect the current console target that is being built.

- DEVICE\_SCREEN\_X\_OFFSET, DEVICE\_SCREEN\_Y\_OFFSET
- · DEVICE SCREEN WIDTH, DEVICE SCREEN HEIGHT
- DEVICE\_SCREEN\_BUFFER\_WIDTH, DEVICE\_SCREEN\_BUFFER\_HEIGHT
- DEVICE\_SCREEN\_MAP\_ENTRY\_SIZE

- DEVICE\_SPRITE\_PX\_OFFSET\_X, DEVICE\_SPRITE\_PX\_OFFSET\_Y
- · DEVICE SCREEN PX WIDTH, DEVICE SCREEN PX HEIGHT
- MAX HARDWARE SPRITES
- · HARDWARE SPRITE CAN FLIP X, HARDWARE SPRITE CAN FLIP Y

# 8.4 Using <gbdk/...> headers

Some include files under < gbdk/..> are cross platform and others allow the build process to auto-select the correct include file for the current target port and platform (console). For example, the following can be used

```
#include <gbdk/platform.h>
#include <gbdk/metasprites.h>
Instead of

#include <gb/gb.h>
#include <gb/metasprites.h>
and

#include <sms/sms.h>
#include <sms/metasprites.h>
```

# 8.5 Cross Platform Example Projects

GBDK includes an number of cross platform example projects. These projects show how to write code that can be compiled and run on multiple different consoles (for example Game Boy and Game Gear) with, in some cases, minimal differences.

They also show how to build for multiple target consoles with a single build command and Makefile. The Makefile.targets allows selecting different port and plat settings when calling the build stages.

#### 8.5.1 Cross Platform Asset Example

The cross-platform Logo example project shows how assets can be managed for multiple different console targets together.

In the example utility\_png2asset is used to generate assets in the native format for each console at compile-time from separate source PNG images. The Makefile is set to use the source PNG folder which matches the current console being compiled, and the source code uses <a href="mailto:set\_bkg\_native\_data">set\_bkg\_native\_data</a>() to load the assets tiles in native format to the tile memory used for background tiles on that platform.

## 8.6 Hardware Summaries

The specs below reflect the typical configuration of hardware when used with GBDK and is not meant as a complete list of their capabilities.

GB/AP/DUCK

- · Sprites:
  - 256 tiles (upper 128 are shared with background) (amount is doubled in CGB mode)
  - tile flipping/mirroring: yes
  - 40 total, max 10 per line
  - 2 x 4 color palette (color 0 transparent). 8 x 4 color palettes in CGB mode
- Background: 256 tiles (typical setup: upper 128 are shared with sprites) (amount is doubled in CGB mode)
  - tile grid size: 8x8
  - tile attribute grid size: 8x8 (CGB mode only)
  - tile flipping/mirroring: no (yes in CGB mode)

- 1 x 4 color palette. 8 x 4 color palettes in CGB mode
- · Window "layer": available
- Screen: 160 x 144
- Hardware Map: 256 x 256

#### SMS/GG

- · Sprites:
  - 256 tiles (a bit less in the default setup)
  - tile flipping/mirroring: no
  - 64 total, max 8 per line
  - 1 x 16 color palette (color 0 transparent)
- Background: 512 tiles (upper 256 are shared with sprites)
  - tile grid size: 8x8
  - tile attribute grid size: 8x8
  - tile flipping/mirroring: yes
  - 2 x 16 color palettes
- · Window "layer": not available
- SMS
  - Screen: 256 x 192
  - Hardware Map: 256 x 224
- GG
  - Screen: 160 x 144
  - Hardware Map: 256 x 224

## NES/Famicom

- · Sprites:
  - 8x8 or 8x16
  - 256 tiles
  - tile flipping/mirroring: yes
  - 64 total, max 8 per line
  - 4 x 4 color palette (color 0 transparent)
- · Background: 256 tiles
  - tile grid size: 8x8
  - tile attribute grid size: 16x16 (bit packed into 32x32)
  - tile flipping/mirroring: no
  - 4 x 4 color palette (color 0 same for all sub-palettes)
- · Window "layer": not available
- Screen: 256 x 240
- · Hardware Map: Depends on mirroring mode
  - 256 x 240 (single-screen mirroring)
  - 512 x 240 (vertical mirroring / horizontal scrolling)
  - 256 x 480 (horizontal mirroring / vertical scrolling)
  - 512 x 480 (4-screen layout. Requires additional RAM on cartridge)

## 8.6.1 Safe VRAM / Display Controller Access

#### GB/AP

- · VRAM / Display Controller (PPU)
  - VRAM and some other display data / registers should only be written to when the STATF\_B\_BUSY bit
    of STAT\_REG is off. Most GBDK API calls manage this automatically.

#### SMS/GG

- Display Controller (VDP)
  - Writing to the VDP should not be interrupted while an operation is already in progress (since that will
    interfere with the internal data pointer causing data to be written to the wrong location).
  - Recommended approach: Avoid writing to the VDP (tiles, map, scrolling, colors, etc) during an interrupt routine (ISR).
  - Alternative (requires careful implementation): Make sure writes to the VDP during an ISR are only performed when the \_shadow\_OAM\_OFF flag indicates it is safe to do so.

#### NES/Famicom

· See NES technical details

## 8.7 Using Game Boy Color (GBC/CGB) Features

## 8.7.1 Differences Versus the Regular Game Boy (DMG/GBP/SGB)

These are some of the main hardware differences between the Regular Game Boy and the Game Boy Color.

- · CPU: Optional 2x Speed mode
- · Serial Link: Additional Speeds 2KB/s, 32KB/s, 64KB/s
- · IR Port
- · Sprites:
  - 2 banks x 256 tile patterns (2x as many) (typically upper 128 of each bank shared with background)
  - 8 x 4 color palettes in CGB mode (BGR-555 per color, 32768 color choices)
- · Background:
  - 2 banks x 256 tile patterns (2x as many) (typically upper 128 of each bank shared with sprites)
  - Second map bank for tile attributes (color, flipping/mirroring, priority, bank)
  - 8 x 4 color palettes in CGB mode (BGR-555 per color, 32,768 color choices))
  - BG and Window master priority
- WRAM: 8 x 4K WRAM banks in the 0xD000 0xDFFF region
- LCD VRAM DMA

## 8.7.2 Game Boy Color features in GBDK

These are some of the main GBDK API features for the CGB. Many of the items listed below link to additional information.

- ROM header settings:
  - See the FAQ entry How do I set SGB, Color only and Color compatibility in the ROM header?
- · Tile and Pattern data:
  - Select VRAM Banks: VBK\_REG (used with set\_bkg/win/sprite\_\*())

- set\_bkg\_attributes(), set\_bkg\_submap\_attributes()
- · Color:
  - set\_bkg\_palette(), set\_bkg\_palette\_entry()
  - set\_sprite\_palette(), set\_sprite\_palette\_entry()
  - set\_default\_palette()
  - RGB(), RGB8(), RGBHTML()
- Detect and change CPU speed: if ( cpu == CGB TYPE), cpu fast()
- More details in cgb.h (#include <gb/cgb.h>)

#### 8.7.3 CGB Examples

Several examples in GBDK show how to use CGB features, including the following:

• gb/colorbar, gb/dscan, cross-platform/large\_map, cross-platform/logo, cross-platform/meta

## 8.8 Porting Between Supported Consoles

## 8.8.1 From Game Boy to Analogue Pocket

The Analogue Pocket operating in .pocket mode is (for practical purposes) functionally identical to the Game Boy / Color though it has a couple changes listed below. These are handled automatically in GBDK as long as the practices outlined below are followed.

#### 8.8.1.1 Official differences:

- · Altered register flag and address definitions
  - STAT & LCDC: Order of register bits is reversed
    - \* Example: LCD on/off is LCDC.0 instead of .7
    - \* Example: LYC Interrupt enable is STAT.1 instead of .6
  - LCDC address is 0xFF4E instead of 0xFF40
- Different logo data in the header at address 0x0104:

```
- 0x01, 0x10, 0xCE, 0xEF, 0x00, 0x00, 0x44, 0xAA, 0x00, 0x74, 0x00, 0x18, 0x11, 0x95, 0x00, 0x34, 0x00, 0x1A, 0x00, 0xD5, 0x00, 0x22, 0x00, 0x69, 0x6F, 0xF6, 0xF7, 0x73, 0x09, 0x90, 0xE1, 0x10, 0x44, 0x40, 0x9A, 0x90, 0xD5, 0xD0, 0x44, 0x30, 0xA9, 0x21, 0x5D, 0x48, 0x22, 0xE0, 0xF8, 0x60
```

## 8.8.1.2 Observed differences:

- MBC1 and MBC5 are supported, MBC3 won't save and RTC doesn't progress when game is not running, the HuC3 isn't supported at all (via JoseJX and sg).
- The Serial Link port does not work
- The IR port in CGB mode does not work as reliably as the Game Boy Color

In order for software to be easily ported to the Analogue Pocket, or to run on both, use the following practices.

**8.8.1.3** Registers and Flags Use API defined registers and register flags instead of hardwired ones.

```
    LCDC register: LCDC_REG or rLCDC
```

- STAT register: STAT\_REG or rSTAT
- LCDC flags: -> LCDCF\_... (example: LCDCF\_ON)
- STAT flags: -> STATF\_... (example: STATF\_LYC)

**8.8.1.4 Boot logo** As long as the target console is set during build time then the correct boot logo will be automatically selected.

#### 8.8.2 From Game Boy to SMS/GG

#### 8.8.2.1 RAM Banks

- The SMS/GG ROM file size must be at least 64K to enable mapper support for RAM banks in emulators.
  - If the generated ROM is too small then  $-y \circ 4$  for makebin (or  $-wm-y \circ 4$  for LCC) can be used to set the size to 64K.

## 8.8.2.2 Tile Data and Tile Map loading

## 8.8.2.2.1 Tile and Map Data in 2bpp Game Boy Format

- set bkg data() and set sprite data() will load 2bpp tile data in "Game Boy" format on both GB and SMS/GG.
- On the SMS/GG set\_2bpp\_palette() sets 4 colors that will be used when loading 2bpp assets with set\_bkg\_data(). This allows GB assets to be easily colorized without changing the asset format. There is some performance penalty for using the conversion.
- set bkg tiles() loads 1-byte-per-tile tilemaps both for the GB and SMS/GG.

# **8.8.2.2.2 Tile and Map Data in Native Format** Use the following api calls when assets are available in the native format for each platform.

set\_native\_tile\_data()

- · GB/AP: loads 2bpp tiles data
- · SMS/GG: loads 4bpp tile data

#### set\_tile\_map()

- GB/AP: loads 1-byte-per-tile tilemaps
- SMS/GG: loads 2-byte-per-tile tilemaps

There are also bit-depth specific API calls:

- 1bpp: set\_1bpp\_colors, set\_bkg\_1bpp\_data, set\_sprite\_1bpp\_data
- 2bpp: set\_2bpp\_palette, set\_bkg\_2bpp\_data, set\_sprite\_2bpp\_data, set\_tile\_2bpp\_data (sms/gg only)
- 2bpp: set\_bkg\_4bpp\_data (sms/gg only), set\_sprite\_4bpp\_data (sms/gg only)

## **8.8.2.3 Colors and Palettes** The SMS/GG have 2 x 16 color palettes:

- · The first (0) is just for the background
- The second (1) is shared between sprites and the background (and for sprites a single color 0 of that palette is transparent)

#### On the Game Gear

- Each Palette is 32 bytes in size: 16 colors x 2 bytes per palette color entry.
- Each color (16 per palette) is packed as BGR-444 format (x:4:4:4, MSBits [15..12] are unused).
- Each component (R, G, B) may have values from 0 15 (4 bits), 15 is brightest.

## On the SMS

- On SMS each Palette is 16 bytes in size: 16 colors x 1 byte per palette color entry.
- Each color (16 per palette) is packed as BGR-222 format (x:2:2:2, MSBits [7..6] are unused).

• Each component (R, G, B) may have values from 0 - 3 (2 bits), 3 is brightest.

For setting palette data:

- set\_palette\_entry(): Will set a single color in a palette
- set palette(): Can set all the colors for one or both palettes
- set\_bkg\_palette(): Is just an alias for set\_palette(). The full 16 colors can be set using this call.
- set sprite palette(): Is also an alias for set palette(), but it offsets to write to the second 16 color palette.
- Also see: RGB(), RGB8(), RGBHTML()

**8.8.2.3.1** Emulated Game Boy Color map attributes on the SMS/Game Gear On the Game Boy Color, VBK\_REG is used to select between the regular background tile map and the background attribute tile map (for setting tile color palette and other properties).

This behavior is emulated for the SMS/GG when using set\_bkg\_tiles() and VBK\_REG. It allows writing a 1-byte tile map separately from a 1-byte attributes map.

Note

Tile map attributes on SMS/Game Gear use different control bits than the Game Boy Color, so a modified attribute map must be used.

## 8.8.3 From Game Boy to NES

The NES graphics architecture is similar to the GB's. However, there are a number of design choices in the NES hardware that make the NES a particularly cumbersome platform to develop for, and that will require special attention.

Most notably:

- PPU memory can only be written in a serial fashion using a data port at 0x2007 (PPUDATA)
- PPU memory can only be written to during vblank, or when manually disabling rendering via PPUMASK. Hblank writes to PPU memory are not possible
- PPU memory write address is re-purposed for scrolling coordinates when rendering is enabled which means PPU memory updates / scrolling must cooperate
- PPU internal palette memory is also mapped to external VRAM area making palette updates during rendering very expensive and error-prone
- The base NES system has no support for any scanline interrupts. And cartridge mappers that add scanline interrupts do so using wildly varying solutions
- There's no easy way to determine the current scanline or CPU-to-PPU alignment meaning timed code is often required on the NES
- The PAL variant of the NES has very different CPU / PPU timings, as do the Dendy clone and other clone systems
- The stock 2 kB CPU RAM is just 1/4th the 8kB CPU RAM on a Game Boy
  - Free RAM after accounting for ZP, stack, OAM page and system variables further cuts this in half
  - This means a lot of GB code will need to be carefully optimized for RAM usage when ported to the NES
  - In particular, make sure to use the "const" modifier for arrays that are read-only, to make sure they don't end up in RAM

To provide an easier experience, gbdk-nes attempts to hide most of these quirks so that in theory the programming experience for gbdk-nes should be as close as possible to that of the GB/GBC. However, to avoid surprises it is recommended to familiarize yourself with the NES-specific quirks and implementation choices mentioned here. This entire section is written as a guide on porting GB projects to NES. If you are new to GBDK, you may wish to

This entire section is written as a guide on porting GB projects to NES. If you are new to GBDK, you may wish to familiarize yourself with using GBDK for GB development first as the topics covered will make a lot more sense after gaining experience with GB development.

**8.8.3.1** Mapper Currently the NES support in GBDK uses UNROM-512 (Mapper30) with single-screen mirroring.

**8.8.3.2 Buffered mode vs direct mode** On the GB, the vblank period serves as an optimal time to write data to PPU memory, and PPU memory can also be written efficiently with VRAM DMA.

On the NES, writing PPU memory during the vblank period is not optional. Whenever rendering is turned on the PPU is in a state where accessing PPU memory results in undefined behavior outside the short vblank period. The NES also has no VRAM DMA hardware to help with data writes. This makes the vblank period not only more precious, but important to never exceed to avoid glitched games.

To deal with this limitation, all functions in gbdk-nes that write to PPU memory can run in either *Buffered* or *Direct* mode.

The good news is that switching between buffered and direct mode in gbdk-nes is usually done behind-the-scenes and normally shouldn't affect your code too much, as long as you use the portable GBDK functions and macros to do this.

- DISPLAY\_ON / SHOW\_BG / SHOW\_SPR will all switch the system into buffered mode, allowing limited amounts of transfers during vblank, not the display of graphics
- DISPLAY\_OFF will switch the system into direct mode, allowing much larger/faster transfers while the screen is blanked

The following sections describe how the buffered / direct modes work in more detail. As buffered / direct mode is mostly hidden by the API calls, feel free to skip these sections if you wish.

**8.8.3.2.1 Buffered mode implementation details** To take maximum advantage of the short vblank period, gbdk-nes implements the same system as nearly every other NES engine: An unrolled loop that pulls prepared data bytes from the stack.

```
PLA
STA PPUDATA
...
PLA
STA PPUDATA
RTS
```

The data structure to facilitate this is usually called a vram transfer buffer, often affectionately called a "popslide" buffer after Damian Yerrick's implementation. This buffer essentially forms a list of commands where each comand sets up a new PPU address and then writes a sequence of bytes with an auto-increment of either +1 or +32. Each such command is often called a "stripe" in the nesdev community.

It starts at 0x100 and takes around half of the hardware stack page. You can think of the transfer buffer as a software-implemented DMA that allows writing bytes at the optimal rate of 8 cycles / byte. (ignoring the PPU address setup cost)

The buffer allows writing up to 32 continuous bytes at a time. This allows updating a full screen row / column, or two 8x8 tiles worth of tile data in one command / "stripe".

By doing writes to this buffer during game logic, your game will effectively keep writing data transfer commands for the vblank NMI handler to process in the next vblank period, without having to wait until the vblank.

Given that transfer buffer only has space for around 100 data bytes, it is important to not overfill the buffer, as this will bring code execution to a screeching halt, until the NMI handler empties the old contents of the buffer to free up space to allow new commands to be written.

Buffered mode is typically used for scrolling updates or dynamically animated tiles, where only a small amount of bytes need updating per frame.

**8.8.3.2.2 Direct mode implementation details** During direct mode, all graphics routines will write directly to the PPUADDR / PPUDATA ports and the transfer buffer limit is never a concern because the transfer buffer is effectively avoided.

Direct mode is typically used for initializing large amounts of tile data at boot and/or level loading time. Unless you plan to have an animated loading screen and decompress a lot of data, it makes more sense to just fade the screen to black and allow direct mode to write data as fast as possible.

**8.8.3.2.3 Caveat: Make sure the transfer buffer is emptied before switching to direct mode** Because the switch to the direct mode is instant and doesn't wait for the next invocation of the vblank, it is possible to create

situations where there is still remaining data in the transfer buffer that would only get written once the system is switched back to buffered mode.

To avoid this situation, make sure to always "drain" the buffer by doing a call to wait\_vbl\_done when you expect your code to finish.

**8.8.3.2.4 Caveat: Only update the PPU palette during buffered mode** The oddity that PPU palette values are accessed through the same mechanism as other PPU memory bytes comes with the side effect that the vblank NMI handler will only write the palette values in buffered mode.

The reason for this design choice is two-fold:

- Having the NMI handler keep doing the palette updates when in direct mode would result in a race condition
  when the NMI handler interrupts the direct mode code and messes with the PPUADDR state that the direct
  mode code expects to remain unchanged
- Having the palette updates also switch to direct mode would run into another quirk of the system: Pointing PPUADDR at palette registers when display is turned off will make the display output that palette color instead of the common background color. The result would be glitchy artifacts on screen when updating the palette, leading to slightly-glitchy looking game whenever the palette is updated with the screen off

To work around this, you are advised to never fully turn the display off during a palette fade. If you don't follow this advice all your palette updates will get delayed until the screen is turned back on.

**8.8.3.3** Shadow PPU registers Like the SMS, the NES hardware is designed to only allow loading the full X/Y scroll on the very first scanline. i.e., under normal operation you are only allowed to change the Y-scroll once. In contrast to the SMS, this limitation can be circumvented with a specific set of out-of-order writes to the PPUSCROLL/PPUADDR registers, taking advantage of the quirk that the PPUADDR and PPUSCROLL share register bits. But this write sequence is very timing-sensitive as the writes need to fall into (a smaller portion of) the hblank period in order to avoid race conditions when the CPU and PPU both try to update the same register during scanline rendering.

To simplify the programming interface, gbdk-nes functions like move\_bkg / scroll\_bkg only ever update shadow registers in RAM. The vblank NMI handler will later pick these values up and write them to the actual PPU registers registers.

**8.8.3.4** Implementation of (fake) vbl / lcd handlers GBDK provides an API for installing Interrupt Service Routines that execute on start of vblank (VBL handler), or on a specific scanline (LCD handler). But the base NES system has no suitable scanline interrupts that can provide such functionality. So instead, gbdknes API allows *fake* handlers to be installed in the goal of keeping code compatible with other platforms.

- An installed VBL handler will be called immediately when calling wait\_vbl\_done. This handler should only
  update PPU shadow registers
- An installed LCD handler for a specific scanline will be called after the vblank NMI handler has finished execution, and will then manually run a delay loop to reach that scanline before calling your installed LCD handler.

Because the LCD "ISR" is actually implemented with a delay loop, it will burn a lot of CPU cycles in the frame - the further down the scanline is the larger the CPU cycle loss. In practice this makes this faked-LCD-ISR functionality only suited for status bars at the top screen, or simple parallax cutscenes where the CPU has little else to do.

Note

The support for VBL and LCD handlers is currently under consideration and subject to change in newer versions of gbdk-nes.

- **8.8.3.5 Caveat: Make sure to call wait\_vbl\_done on every frame** On the GB, the call to wait\_vbl\_done is an optional call that serves two purposes:
  - 1. It provides a consistent frame timing for your game
  - 2. It allows future register writes to be synchronized to the screen

On gbdk-nes the second point is no longer true, because writes need to be made to the shadow registers *before* wait vbl done is called.

But the wait vbl done call serves two other very important purposes:

A. It calls the optional VBL handler, where shadow registers can be written (and will later be picked up by the actual vblank NMI handler) B. It calls flush\_shadow\_attributes so that updates to background attributes actually get written to PPU memory

For these reasons you should always include a call to wait\_vbl\_done if you expect to see any graphical updates on the screen.

#### 8.8.3.6 Tile Data and Tile Map loading

## 8.8.3.6.1 Tile and Map Data in 2bpp Game Boy Format

- set\_bkg\_data() and set\_sprite\_data() will load 2bpp tile data in "Game Boy" format on both GB and NES.
- set bkg tiles() loads 1-byte-per-tile tilemaps both for the GB and NES.

**8.8.3.6.2** Tile and Map Data in Native Format Use the following api calls when assets are available in the native format for each platform.

set native tile data()

- · GB/AP: loads 2bpp tiles data
- · NES: loads 2bpp tiles data

set\_tile\_map()

- GB/AP: loads 1-byte-per-tile tilemaps
- · NES: loads 1-byte-per-tile tilemaps

Bit-depth specific API calls:

- 1bpp: set\_1bpp\_colors, set\_bkg\_1bpp\_data, set\_sprite\_1bpp\_data
- 2bpp: set\_2bpp\_palette, set\_bkg\_2bpp\_data, set\_sprite\_2bpp\_data

Platform specific API calls:

set\_bkg\_attributes\_nes16x16(), set\_bkg\_submap\_attributes\_nes16x16(), set\_bkg\_attribute\_xy\_nes16x16()

**8.8.3.6.3** Game Boy Color map attributes on the NES On the Game Boy Color, VBK\_REG is used to select between the regular background tile map and the background attribute tile map (for setting tile color palette and other properties).

This behavior of setting VBK\_REG to specify tile indices/attributes is not supported on the NES platform. Instead the dedicated functions for attribute setting should be used. These will work on other platforms as well and are the preferred way to set attributes.

To maintain API compatibility with other platforms that have attributes on an 8x8 grid specified with a whole byte per attribute, the NES platform supports the dedicated calls for setting attributes on an 8x8 grid:

- set\_bkg\_attributes()
- set\_bkg\_submap\_attributes()
- set\_bkg\_attribute\_xy()

This allows code to for attribute setting to remain unchanged between platforms. The effect of using these calls is that some attribute setting will be redundant due to the coarser attribute grid. i.e., setting the attribute at coordinates (4, 4), (4,5), (5, 4) and (5, 5) will all set the same attribute.

There is one more platform specific difference to note: While the set\_bkg\_attribute\_xy() function takes coordinates on a 8x8 grid, the set\_bkg\_attributes() and set\_bkg\_submap\_attributes() functions take a pointer to data in NES packed attribute format, where each byte contains data for 4 16x16 attribute. i.e. a 32x32 region.

While this implementation detail of how the attribute map is encoded is usually hidden by the API functions it does mean that code which manually tries to read the attribute data is *NOT* portable between NES/other platforms, and is not recommended.

Note

Tile map attributes on NES are on a 16x16 grid and use different control bits than the Game Boy Color.

- NES 16x16 Tile Attributes are bit packed into 4 attributes per byte with each 16x16 area of a 32x32 pixel block using the bits as follows:
  - D1-D0: Top-left 16x16 pixels
  - D3-D2: Top-right 16x16 pixels
  - D5-D4: Bottom-left 16x16 pixels
  - D7-D6: Bottom-right 16x16 pixels
  - https://www.nesdev.org/wiki/PPU attribute tables

# 8.8.4 From Game Boy to Mega Duck / Cougar Boy

The Mega Duck is (for practical purposes) functionally identical to the Original Game Boy though it has a couple changes listed below.

#### 8.8.4.1 Summary of Hardware changes:

- · Cartridge Boot Logo: not present on Mega Duck
- · Cartridge Header data: not present on Mega Duck
- Program Entry Point: 0x0000 (on Game Boy: 0x0100)
- · Display registers and flag definitions: Some changed
- · Audio registers and flag definitions: Some changed
- MBC ROM bank switching register address: 0x0001 (many Game Boy MBCs use 0x2000 0x3FFF)
- **8.8.4.2 Best Practices** In order for software to be easily ported to the Mega Duck, or to run on both, use these practices. That will allow GBDK to automatically handle *most* of the differences (for the exceptions see Sound Register Value Changes).
  - · Set the target console during build time
  - · Use the GBDK definitions and macros for:
    - Video Registers and Flags (examples: LCDC\_REG, LCDCF\_BG8000, etc)
    - Audio Registers and Flags (examples: NR12 REG, NR43 REG, etc)
    - Use the default SWITCH\_ROM macro for changing ROM banks
- **8.8.4.3 Sound Register Value Changes** There are two hardware changes which will not be handled automatically when following the practices mentioned above.

These changes may be required when using existing Sound Effects and Music Drivers written for the Game Boy.

- 1. Registers NR12\_REG, NR22\_REG, NR42\_REG, and NR43\_REG have their contents nybble swapped.
  - To maintain compatibility the value to write (or the value read) can be converted this way: ((uint8← \_t) (value << 4) | (uint8\_t) (value >> 4))
- 2. Register NR32\_REG has the volume bit values changed.

```
• Game Boy: Bits:6..5 : 00 = \text{mute}, 01 = 100\%, 10 = 50\%, 11 = 25\%
• Mega Duck: Bits:6..5 : 00 = \text{mute}, 01 = 25\%, 10 = 50\%, 11 = 100\%
```

- To maintain compatibility the value to write (or the value read) can be converted this way  $\leftarrow$  : ((( $\sim$ (uint8\_t)value) + (uint8\_t)0x20u) & (uint8\_t)0x60u)
- **8.8.4.4 Graphics Register Bit Changes** These changes are handled automatically when their GBDK definitions are used.

LCDC_REG Flag	Game Boy	Mega Duck		Purpose
LCDCF_B_ON	.7	.7	(same)	Bit for LCD On/Off Select
LCDCF_B_WIN9C00	.6	.3		Bit for Window Tile Map Region Select
LCDCF_B_WINON	.5	.5	(same)	Bit for Window Display On/Off Control
LCDCF_B_BG8000	.4	.4	(same)	Bit for BG & Window Tile Data Region Select
LCDCF_B_BG9C00	.3	.2		Bit for BG Tile Map Region Select
LCDCF_B_OBJ16	.2	.1		Bit for Sprites Size Select
LCDCF_B_OBJON	.1	.0		Bit for Sprites Display Visible/Hidden Select
LCDCF_B_BGON	.0	.6		Bit for Background Display Visible Hidden Select

**8.8.4.5 Detailed Register Address Changes** These changes are handled automatically when their GBDK definitions are used.

Register	Game Boy	Mega Duck
LCDC_REG	0xFF40	0xFF10
STAT_REG	0xFF41	0xFF11
SCY_REG	0xFF42	0xFF12
SCX_REG	0xFF43	0xFF13
LY_REG	0xFF44	0xFF18
LYC_REG	0xFF45	0xFF19
DMA_REG	0xFF46	0xFF1A
BGP_REG	0xFF47	0xFF1B
OBP0_REG	0xFF48	0xFF14
OBP1_REG	0xFF49	0xFF15
WY_REG	0xFF4A	0xFF16
WX_REG	0xFF4B	0xFF17
-	-	-
NR10_REG	0xFF10	0xFF20
NR11_REG	0xFF11	0xFF22
NR12_REG	0xFF12	0xFF21
NR13_REG	0xFF13	0xFF23
NR14_REG	0xFF14	0xFF24
-	-	-
NR21_REG	0xFF16	0xFF25
NR22_REG	0xFF17	0xFF27
NR23_REG	0xFF18	0xFF28
NR24_REG	0xFF19	0xFF29
-	-	-
NR30_REG	0xFF1A	0xFF2A
NR31_REG	0xFF1B	0xFF2B
NR32_REG	0xFF1C	0xFF2C
NR33_REG	0xFF1D	0xFF2E
NR34_REG	0xFF1E	0xFF2D
-	-	-
NR41_REG	0xFF20	0xFF40
NR42_REG	0xFF21	0xFF42
NR43_REG	0xFF22	0xFF41
NR44_REG	0xFF23	0xFF43
-	-	-
NR50_REG	0xFF24	0xFF44
NR51_REG	0xFF25	0xFF46
NR52_REG	0xFF26	0xFF45

Register	Game Boy	Mega Duck	
-	-	-	

# 9 Example Programs

GBDK includes several example programs both in C and in assembly. They are located in the examples directory, and in its subdirectories. They can be built by typing make in the corresponding directory.

# 9.1 banks (various projects)

There are several different projects showing how to use ROM banking with GBDK.

## 9.2 comm

Illustrates how to use communication routines.

#### 9.3 crash

Demonstrates how to use the optional GBDK crash handler which dumps debug info to the Game Boy screen in the event of a program crash.

#### 9.4 colorbar

The colorbar program, written by Mr. N.U. of TeamKNOx, illustrates the use of colors on a Color GameBoy.

#### 9.5 dscan

Deep Scan is a game written by Mr. N.U. of TeamKNOx that supports the Color GameBoy. Your aim is to destroy the submarines from your boat, and to avoid the projectiles that they send to you. The game should be self-explanatory. The following keys are used:

RIGHT/LEFT : Move your boat

A/B : Send a bomb from one side of your boat

START : Start game or pause game

When game is paused:

SELECT : Invert A and B buttons

RIGHT/LEFT : Change speed UP/DOWN : Change level

# 9.6 filltest

Demonstrates various graphics routines.

#### 9.7 fonts

Examples of how to work with the built in font and printing features.

## 9.8 galaxy

A C translation of the space.s assembly program.

## 9.9 qb-dtmf

The gb-dtmf, written by Osamu Ohashi, is a Dual Tone Multi-Frequency (DTMF) generator.

## 9.10 gbdecompress

Demonstrates using gbdecompress to load a compressed tile set into VRAM.

9.11 irq 49

#### 9.11 irq

Illustrates how to install interrupt handlers.

## 9.12 large map

Shows how to scroll with maps larger than 32 x 32 tiles using <u>set\_bkg\_submap()</u>. It fills rows and columns at the edges of the visible viewport (of the hardware Background Map) with the desired sub-region of the large map as it scrolls.

## 9.13 metasprites

Demonstrates using the metasprite features to move and animate a large sprite.

- · Press A button to show / hide the metasprite
- · Press B button to cycle through the metasprite animations
- Press SELECT button to cycle the metasprite through Normal / Flip-Y / Flip-XY / Flip-X
- · Up / Down / Left / Right to move the metasprite

#### 9.14 lcd isr wobble

An example of how to use the LCD ISR for visual special effects.

## **9.15** paint

The paint example is a painting program. It supports different painting tools, drawing modes, and colors. At the moment, it only paints individual pixels. This program illustrates the use of the full-screen drawing library. It also illustrates the use of generic structures and big sprites.

```
Arrow keys : Move the cursor
SELECT : Display/hide the tools palette
A : Select tool
```

## 9.16 rand

The rand program, written by Luc Van den Borre, illustrates the use of the GBDK random generator.

## 9.17 ram\_fn

The ram\_fn example illustrates how to copy functions to RAM or HIRAM, and how to call them from C.

# 9.18 rpn

A basic RPN calculator. Try entering expressions like 12 134\* and then 1789+.

## 9.19 samptest

Demonstration of playing a sound sample.

## 9.20 sgb (various)

A collection of examples showing how to use the Super Game Boy API features.

# 9.21 sound

The sound example is meant for experimenting with the sound generator of the GameBoy (to use on a real Game← Boy). The four different sound modes of the GameBoy are available. It also demonstrates the use of bit fields in C (it's a quick hack, so don't expect too much from the code). The following keys are used:

```
UP/DOWN : Move the cursor
RIGHT/LEFT : Increment/decrement the value
RIGHT/LEFT+A : Increment/decrement the value by 10
RIGHT/LEFT+B : Set the value to maximum/minimum
START : Play the current mode's sound (or all modes if in control screen)
START+A : Play a little music with the current mode's sound
SELECT : Change the sound mode (1, 2, 3, 4 and control)
SELECT+A : Dump the sound registers to the screen
```

## **9.22** space

The space example is an assembly program that demonstrates the use of sprites, window, background, fixed-point values and more. The following keys are used:

```
Arrow keys : Change the speed (and direction) of the sprite
Arrow keys + A : Change the speed (and direction) of the window
Arrow keys + B : Change the speed (and direction) of the background
START : Open/close the door
SELECT : Basic fading effect
```

## 9.23 templates

Two basic template examples are provided as a starting place for writing your GBDK programs.

# 10 Frequently Asked Questions (FAQ)

#### 10.1 General

- · How can sound effects be made?
  - The simplest way is to use the Game Boy sound hardware directly. See the Sound Example for a way
    to test out sounds on the hardware.
  - Further discussion on using the Sound Example rom can be found in the ZGB wiki. Note that some example code there is ZGB specific and not part of the base GBDK API: <a href="https://github.com/Zal0/ZGB/wiki/Sounds">https://github.com/Zal0/ZGB/wiki/Sounds</a>

## 10.2 Licensing

- · What license information is required when distributing the compiled ROM (binary) of my game or program?
  - There is no requirement to include or credit any of the GBDK-2020 licenses or authors, although credit of GBDK-2020 is appreciated.
  - This is different and separate from redistributing the GBDK-2020 dev environment itself (or the GBDK-2020 sources) which does require the licenses.

## 10.3 Graphics and Resources

- · How do I use a tile map when its tiles don't start at index zero?
  - The two main options are:
    - Use set\_bkg\_based\_tiles(), set\_bkg\_based\_submap(), set\_win\_based\_tiles(), set\_win\_based\_submap()
      and provide a tile origin offset.
    - \* Use utility\_png2asset with -tile\_origin to create a map with the tile index offsets built in.
- Is it normal for sprites to disappear when they reach the left border of the screen? (NES/SMS/MSX)
  - You can hide the leftmost column using HIDE LEFT COLUMN to work around this.

 The behavior is due to NES/SMS/MSX having 8-bit Sprite x coordinates while the screen width is also 256 pixels. GB/GG don't have this problem since their screen is smaller and the x-coordinates are larger than the visible screen.

# 10.4 ROM Header Settings

- · How do I set the ROM's title?
  - Use the makebin -yn flag. For example with lcc -Wm-yn"MYTITLE" or with makebin directly -yn "MYTITLE". The maximum length is up to 15 characters, but may be shorter.
  - See "0134-0143 Title" in Pandocs for more details.
- · How do I set SGB, Color only and Color compatibility in the ROM header?
  - Use the following makebin flags. Prefix them with -₩m if using lcc.
    - \* -yc: GameBoy Color compatible
    - \* -yC: GameBoy Color only
    - \* -ys: Super GameBoy compatible
- How do I set the ROM MBC type, and what MBC values are available to use with the -yt makebin flag?
  - See setting mbc and rom ram banks

#### 10.5 Editors

- · Why is VSCode flagging some GBDK types or functions as unidentified or giving warnings about them?
  - See code editors hinting
  - GBDK platform constants can be declared so that header files are parsed more completely in VSCode.

## 10.6 Errors and Warnings

- What does the error old "gbz80" SDCC PORT name specified (in "-mgbz80:gb"). Use "sm83" instead. You must update your build settings. mean?
  - The PORT name for the Game Boy and related clones changed from gbz80 to sm83 in the SDCC version used in GBDK-2020 4.1.0 and later. You must change your Makefile, Build settings, etc to use the new name. Additional details in the Console Port and Platform Settings section.
- What does the warning ?ASlink-Warning-Conflicting sdcc options: "-msm83" in module "\_\_\_\_\_" and "-mgbz80" in module "\_\_\_\_\_". mean?
  - One object file was compiled with the PORT setting as gbz80 (meaning a version of SDCC / GBDK-2020 OLDER than GBDK-2020 4.1.0).
  - The other had the PORT setting as sm83 (meaning GBDK-2020 4.1.0 or LATER).
  - You must rebuild the object files using sm83 with GBDK-2020 4.1.0 or later so that the linker is able
    to use them with the other object files. Additional details in the Console Port and Platform Settings
    section.
- What does z80instructionSize() failed to parse line node, assuming 999 bytes mean?

- This is a known issue with SDCC Peephole Optimizer parsing and can be ignored. A bug report has been filed for it.
- What do these kinds of warnings / errors mean? WARNING: possibly wrote twice at addr 4000 (93->3E) Warning: Write from one bank spans into the next. 7ff7  $\rightarrow$  8016 (bank 1  $\rightarrow$  2)
  - You may have a overflow in one of your ROM banks. If there is more data allocated to a bank than it can hold it then will spill over into the next bank.
    - A common problem is when there is too much data in ROM0 (the lower 16K unbanked region) and it spills over into ROM1 (the first upper 16K banked region). Make sure ROM0 has 16K or less in it.
    - The warnings are generated by ihxcheck during conversion of an .ihx file into a ROM file.
    - See the section ROM/RAM Banking and MBCs for more details about how banks work and what their size is. You may want to use a tool such as romusage to calculate the amount of free and used space.
- What does error: size of the buffer is too small mean?
  - Your program is using more banks than you have configured in the toolchain. Either the MBC type was not set, or the number of banks or MBC type should be changed to provide more banks.
     See the section setting mbc and rom ram banks for more details.
- What do the following kinds of warnings / errors mean? info 218: z80instructionSize() failed to parse line node, assuming 999 bytes
  - This is a known issue with SDCC, it should not cause actual problems and you can ignore the warning.
- · Why is the compiler so slow, or why did it suddenly get much slower?
  - This may happen if you have large initialized arrays declared without the const keyword. It's important
    to use the const keyword for read-only data. See const\_gbtd\_gbmb and const\_array\_data
  - It can also happen if C source files are #included into other C source files, or if there is a very large source file.
- What does warning 283: function declarator with no prototype mean?
  - Function forward declarations and definitions which have no arguments should be changed from func() to func(void).
  - In C func() and func(void) do not mean the same thing. () means any number of parameters, (void) means no parameters. For example if a function with no arguments is declared with () then there may not be an error or warning when mistakenly trying to pass arguments to it.
- What do the warnings warning 126: unreachable code and warning 110: conditional flow changed by optimizer: so said EVELYN the modified DOG mean?
  - There is source code which the compiler has determined will never get executed based on the input values. So either a warning is omitted, or in some cases the optimizer has changed the program so that it skips code that will never run.
- On macOS, what does ... developer cannot be verified, macOS cannot verify that this app is free from malware mean?
  - It does not mean that GBDK is malware. It just means the GBDK toolchain binaries are not signed by Apple, so it won't run them without an additional step.
  - For the workaround, see the macOS unsigned binary workaround for details.

# 10.7 Debugging / Compiling / Toolchain

- · What flags should be enabled for debugging?
  - You can use the lcc debug flag -debugto turn on debug output. It covers most uses and removes the need to specify multiple flags such as -Wa-l -Wl-m -Wl-j. Also see tools\_debug.
- Is it possible to generate a debug symbol file (.sym) compatible with an emulator?
  - Yes, turn on .noi output (LCC argument: -Wl-j or -debug and then use -Wm-yS with LCC (or -yS with makebin directly).
- How do I move the start of the DATA section and the Shadow OAM location?
  - The default locations are: \_shadow\_OAM=0xC000 and 240 bytes after it \_DATA=0xC0A0
  - So, for example, if you wanted to move them both to start 256(0x100) bytes later, use these command line arguments for LCC:
    - \* To change the Shadow OAM address: -Wl-g\_shadow\_OAM=0xC100
    - \* To change the DATA address (again, 240 bytes after the Shadow OAM): -Wl-b\_DATA=0xcla0
- What does this warning mean? WARNING: overflow in implicit constant conversion
  - See Constants, Signed-ness and Overflows
- · Known issue: SDCC may fail on Windows when run from folder names with spaces on non-C drives.

#### 10.8 API / Utilities

- Is there a list of all functions in the API?
  - Functions
  - Variables
- Can I use the float type to do floating point math?
  - There is no support for 'float' in GBDK-2020.
  - Instead consider some form of fixed point math (including the fixed type included in GBDK).
- Why are 8 bit numbers not printing correctly with printf()?
  - To correctly pass chars/uint8s for printing, they must be explicitly re-cast as such when calling the function. See docs\_chars\_varargs for more details.
- How can maps larger than 32x32 tiles be scrolled? & Why is the map wrapping around to the left side when setting a map wider than 32 tiles with set bkg data()?
  - The hardware Background map is 32 x 32 tiles. The screen viewport that can be scrolled around that map is 20 x 18 tiles. In order to scroll around within a much larger map, new tiles must be loaded at the edges of the screen viewport in the direction that it is being scrolled. set\_bkg\_submap can be used to load those rows and columns of tiles from the desired sub-region of the large map.
  - See the "Large Map" example program and set\_bkg\_submap().
  - Writes that exceed coordinate 31 of the Background tile map on the x or y axis will wrap around to the Left and Top edges.

- When using gbt\_player with music in banks, how can the current bank be restored after calling gbt\_update()? (since it changes the currently active bank without restoring it).
  - See restoring the current bank
- · How can CGB palettes and other sprite properties be used with metasprites?
  - See Metasprites and sprite properties
- Weird things are happening to my sprite colors when I use png2asset and metasprites. What's going on and how does it work?
  - See utility\_png2asset for details of how the conversion process works.

# 11 Migrating to new GBDK Versions

This section contains information that may be useful to know or important when upgrading to a newer GBDK release.

## 11.1 GBDK-2020 versions

# 11.1.1 Porting to GBDK-2020 4.3.0

- GBDK now requires  $\sim$ SDCC 4.4 or higher with GBDK-2020 patches for the z80 and NES
- Changed to new calling convention for printf(), sprintf(), abs()
- Changed to new SDCC calling convention for set\_bkg\_tile\_xy(), set\_win\_tile\_xy()
- · Recommend using:
  - CURRENT\_BANK instead of \_current\_bank
  - BANKED macro instead of \_\_banked

# 11.1.2 Porting to GBDK-2020 4.2.0

- GBDK now requires  $\sim$ SDCC 4.3 or higher with GBDK-2020 patches for the z80 and NES
- The following new functions replace old ones:
  - While the old functions will continue to work for now, migration to new versions is strongly encouraged
  - vsync(): replaces wait\_vbl\_done()
  - set\_default\_palette(): replaces cgb\_compatibility()
  - move\_metasprite\_flipy(): replaces move\_metasprite\_hflip()
  - move\_metasprite\_flipx(): replaces move\_metasprite\_vflip()
  - move\_metasprite\_flipxy(): replaces move\_metasprite\_hvflip()
  - move\_metasprite\_ex(): replaces move\_metasprite()
- The unused <code>-DINT\_16\_BITS</code> argument was removed from the default SDCC compiler and preprocessor arguments (used in pre-GBDK2020 <code>gbdk/include-gb/types.h</code>)
- Removed legacy MBC register definitions .MBC1\_ROM\_PAGE and .MBC\_ROM\_PAGE
- · SMS/GG
  - Swapped A and B buttons to match game boy buttons

## 11.1.3 Porting to GBDK-2020 4.1.1

· No significant changes required

## 11.1.4 Porting to GBDK-2020 4.1.0

- GBDK now requires SDCC 4.2 or higher with GBDK-2020 patches for the z80 linker
- The default calling convention changed in SDCC 4.2, see Calling Conventions for more details.
  - If you are linking to libraries compiled with an older version of SDCC / GBDK then you may have to recompile them.
  - If there are existing functions written in ASM which receive parameters they should also be reviewed
    to make sure they work with the new \_\_\_sdccall(1) calling convention, or have their header declaration changed to use OLDCALL.
  - If there are existing functions written in ASM which call other functions written in C the callee C function should be declared OLDCALL.
  - Function pointer declarations should be checked to see if they need OLDCALL added to the declaration.
    - \* Example (add OLDCALL at the end)
    - \* FROM: typedef void (\*someFunc) (uint8\_t, uint8\_t);
    - \* TO: typedef void (\*someFunc) (uint8\_t, uint8\_t) OLDCALL;
  - If you are using tools such as rgb2sdas (from hUGETracker/Driver) you may need to edit the resulting
     o file and replace -mgbz80 with -msm83 in addition to using OLDCALL
- The SDCC PORT name for the Game Boy and related clones changed from qbz80 to sm83.
  - Additional details in the Console Port and Platform Settings section and FAQ entry. Icc will error out if the old PORT name is passed in.
- The library base path changed from lib/small/asxxxx/ to lib/.
  - For example lib/small/asxxxx/gb becomes lib/gb
- · Allocations for ISR chain lengths were fixed.
  - Now they are VBL: 4 user handlers, LCD: 3 user handlers, SIO/TIM/JOY: 4 user handlers

#### 11.1.5 Porting to GBDK-2020 4.0.6

- Renamed bgb\_emu.h to emu\_debug.h and BGB\_\* functions to EMU\_\*
  - Aliases for the BGB\_\* ones and a bgb\_emu.h shim are present for backward compatibility, but updating to the new naming is recommended

## 11.1.6 Porting to GBDK-2020 4.0.5

- · GBDK now requires SDCC 12259 or higher with GBDK-2020 patches
- · Variables in static storage are now initialized to zero per C standard (but remaining WRAM is not cleared)
- png2asset is the new name for the png2mtspr utility
- lcc : Changed default output format when not specified from .ihx to .gb (or other active rom extension)
- The \_BSS area is deprecated (use \_DATA instead)
- The \_BASE area is renamed to \_HOME
- · Variables in static storage are now initialized to zero per C standard (but remaining WRAM is not cleared)
- itoa(), uitoa(), Itoa(), ultoa() all now require a radix value (base) argument to be passed. On the Game Boy and Analogue Pocket the parameter is required but not utilized.
- set\_bkg\_1bit\_data has been renamed to set\_bkg\_1bpp\_data
- The following header files which are now cross platform were moved from gb/ to gbdk/←: bcd.h, console.h, far\_ptr.h, font.h, gbdecompress.h, gbdk-lib.h, incbin.h, metasprites.h, platform.h, version.h
  - When including them use #include <gbdk/...> instead of #include <gb/>

## 11.1.7 Porting to GBDK-2020 4.0.4

- · GBDK now requires SDCC 12238 or higher
- · Made sample.h, cgb.h and sgb.h independent from gb.h

#### 11.1.8 Porting to GBDK-2020 4.0.3

· No significant changes required

## 11.1.9 Porting to GBDK-2020 4.0.2

- The default font has been reduced from 256 to 96 characters.
  - Code using special characters may need to be updated.
  - The off-by-1 character index offset was removed for fonts. Old fonts with the offset need to be readjusted.

#### 11.1.10 Porting to GBDK-2020 4.0.1

- Important! : The WRAM memory region is no longer automatically initialized to zeros during startup.
  - Any variables which are declared without being initialized may have indeterminate values instead of 0 on startup. This might reveal previously hidden bugs in your code.
  - Check your code for variables that are not initialized before use.
  - In BGB you can turn on triggering exceptions (options panel) reading from unitialized RAM. This allows for some additional runtime detection of uninitialized vars.
- In .ihx files, multiple writes to the same ROM address are now warned about using ihxcheck.
- set\_\*\_tiles() now wrap maps around horizontal and vertical boundaries correctly. Code relying on it not wrapping correctly may be affected.

## 11.1.11 Porting to GBDK-2020 4.0

- GBDK now requires SDCC 4.0.3 or higher
- The old linker link-gbz80 has been REMOVED, the linker sdldgb from SDCC is used.
  - Due to the linker change, there are no longer warnings about multiple writes to the same ROM address.
- GBDK now generates .ihx files, those are converted to a ROM using makebin (lcc can do this automatically in some use cases)
- Setting ROM bytes directly with -W1-yp0x<address>=0x<value> is no longer supported. Instead use makebin flags. For example, use -Wm-yC instead of -W1-yp0x143=0xC0. See faq\_gb\_type\_header\_setting.
- OAM symbol has been renamed to \_shadow\_OAM, that allows accessing shadow OAM directly from C code

# 11.1.12 Porting to GBDK-2020 3.2

· No significant changes required

# 11.1.13 Porting to GBDK-2020 3.1.1

· No significant changes required

## 11.1.14 Porting to GBDK-2020 3.1

• Behavior formerly enabled by USE\_SFR\_FOR\_REG is on by default now (no need to specify it, it isn't a tested #ifdef anymore). check here why: https://gbdev.gg8.se/forums/viewtopic. ← php?id=697

#### 11.1.15 Porting to GBDK-2020 3.0.1

- · LCC was upgraded to use SDCC v4.0. Makefile changes may be required
  - The symbol format changed. To get bgb compatible symbols turn on .noi output (LCC argument: -Wl-j or -debug) and use -Wm-yS
  - ?? Suggested: With LCC argument: -Wa-l (sdasgb:-a All user symbols made global)
  - In SDCC 3.6.0, the default for char changed from signed to unsigned.
    - \* If you want the old behavior use --fsigned-char.
    - \* lcc includes --fsigned-char by default
    - \* Explicit declaration of unsigned vars is encouraged (for example, '15U' instead of '15')
  - .init address has been removed

#### 11.2 Historical GBDK versions

#### 11.2.1 GBDK 1.1 to GBDK 2.0

- Change your int variables to long if they have to be bigger than 255. If they should only contain values between 0 and 255, use an unsigned int.
- · If your application uses the delay function, you'll have to adapt your delay values.
- Several functions have new names. In particular some of them have been changed to macros (e.g. show\_←
  bkg() is now SHOW\_BKG).
- You will probably have to change the name of the header files that you include.

## 12 GBDK Release Notes

# 12.1 GBDK-2020 Release Notes

## 12.1.1 GBDK-2020 4.3.0

~2024/05

- Includes SDCC version  $\sim$ 4.4 ( $\sim$ 14635) with GBDK-2020 patches for Z80 and NES
  - Patched SDCC Builds with support for Sega GG/SMS and the Nintendo NES are used.
  - See the github workflow for details.
- · Added native GBDK build for Apple ARM cpus
- · Known Issues
  - SDCC may fail on Windows when run from folder names with spaces on non-C drives.
- Library
  - Added get\_system() which indicates system speed
    - \* SYSTEM\_60HZ, SYSTEM\_50HZ, SYSTEM\_BITS\_DENDY, SYSTEM\_BITS\_NTSC, SYSTEM\_BITS\_PAL, SYSTEM\_NTSC
  - Changed to new calling convention for printf(), sprintf(), abs()
  - Changed EMU printf() to remove dependency on stdio.h added similar EMU fmtbuf()
  - Fixed emu\_debug.h macros missing a trailing space
  - NES
    - \* Added PAL support
    - \* Fixed \_map\_tile\_offset not being applied for set\_bkg\_based\_tiles()

- \* Fixed VRAM transfer buffer bug (ensure stack page cleared on reset)
- \* Fixed support for 4-player controllers using fourscore
- \* Updated libc to latest from sdcc 4.4.0

#### - SMS/GG

- \* Added SHOW SPRITES, HIDE SPRITES (no hiding mid-frame)
- \* Added DIV REG emulation for the Z80 systems, may be useful for seeding RNG (also for MSX)
- \* Added S BANK tile attribute
- \* Added 6 button controller support in joypad()
- \* Added bcd.h implementation
- Added ability to move VDP SAT and name table to other locations by writing to VDP R2 and VDP R5.
  - · Set name table to 0x1800 and SAT to 0x1F00 by default to free up some sprite tile space
  - · Added R5 SAT 0x1F00 definition for the R5 value controlling SAT position in VRAM
- Added \_\_WRITE\_VDP\_REG\_UNSAFE() VDP macro while interrupts are disabled (such as in ISR handlers)
- \* Added Game Gear registers and definitions
  - · GG\_STATE: GGSTATE\_STT, GGSTATE\_NJAP, GGSTATE\_NNTS
  - · GG EXT 7BIT
  - · GG\_EXT\_CTL: GGEXT NINIT
  - · GG\_SIO\_SEND
  - · GG SIO RECV
  - · GG\_SIO\_CTL: SIOCTL\_TXFL, SIOCTL\_RXRD, SIOCTL\_FRER, SIOCTL\_INT, SIOCTL\_TON, SIOCTL\_BON, SIOCTL\_BS0, SIOCTL\_BS1
  - · GG\_SOUND\_PAN: SOUNDPAN\_TN1R, SOUNDPAN\_TN2R, SOUNDPAN\_TN3R, SOUNDPAN\_NOSR, SOUNDPAN\_TN1L, SOUNDPAN\_TN2L, SOUNDPAN\_TN3L, SOUNDPAN\_NOSL
- \* Changed to allow nested locking of the shadow SAT copying on VBlank (also for MSX)
- \* Changed VDP to reduce chances of dangerous ISR nesting (see SDCC issue https://sourceforge.net/p/sdcc/bugs/3721/) (also for MSX)
- Optimized native tile data loading routines
- \* Fixed tilemap wrapping over the low bound of the VDP name table
- \* Fixed waitpad() (also for MSX)
- \* Fixed scroll sprite()
- \* Fixed missing sms.h in sms/metasprites.h
- \* Fixed return result of "`set\_tile x, y`" family functions (also for MSX)

# Game Boy

- \* Added HBlank copy routines: hblank\_copy\_vram(), hblank\_cpy\_vram(), hblank\_copy()
- \* Added SCF\_START, SCF\_SOURCE, SCF\_SPEED aliases for SIO (Serial/Link port) control register control constants
- \* Added clamping and changed to new SDCC calling convention for set\_bkg\_tile\_xy(), set\_win\_tile\_xy()
- \* Added S\_BANK tile attribute
- \* Fixed 8-bit signed modulus
- MegaDuck
  - \* Fixed ROM bank switching on hardware when trying to enable or switch SRAM banks
- · Toolchain / Utilities
  - Added romusage utility for viewing free/used ROM and RAM in compiled programs
  - Icc
    - \* Changed -debug to add the following flags: -Wa-l -Wl-u -Wl-w
  - png2asset

- \* Added -sprite\_no\_optimize: sprite conversion will keep duplicate and empty sprite tiles
- \* Added -entity\_tileset: mark entity locations on maps during conversion with an entity tileset
- \* Added -rel\_paths: paths to tilesets are relative to the input file path
- \* Changed -keep\_palette\_order to round up to at least one palette
- \* Changed -use\_structs + -source\_tileset behavior
  - · Point tile data to external source tileset
  - Add extra\_tiles struct member pointing to map tiles not found in source tileset (null if none found)
- \* Changed -use structs to use designated initializers
- \* Fixed garbage in unused colors of palettes (set unused colors to black)
- \* Fixed -bin mode not honoring -tiles\_only and -maps\_only
- \* Fixed segfault and wrong data size for -pack\_mode sgb + -bin
- \* Fixed missing Palette ID in attributes for multi-palette SMS/GG backgrounds
- \* Fixed not taking -bpp into account when converting metasprites and emitting <symbol>\_ tile\_pals[]
- \* Fixed crash when filename for -o and -c not specified
- \* Fixed some attributes missing for metasprite export

#### - makebin

\* Fixed crash when using -yS (-Wm-yS with lcc)

### bankpack

- \* Added -banktype= to allow forcing a bank type to CODE or LIT before packing starts
- \* Changed minimum bank for auto packing from 1 to 0 (required for the NES)

#### Examples

- Added HBlank copy example for GB/AP/Duck
- Added Reading SNES joypads on NES example
- Added Game Boy Printer example
- Added Joypad testing example
- Added Display System example to demonstrate get\_system()
- Added Platformer example
- Added GBDK\_DEBUG Makefile environment var for turning on/off debug flags
- Changed wav sample: play waveforms on the SMS/GG PSG
- Changed Random Number example: only call initrand() once
- Changed Large Map: support modified initial camera position
- Changed all examples: use BANKED macro instead of \_\_banked
  - \* Also change some to use CURRENT\_BANK instead of \_current\_bank
- Fixes for SMS/GG: Fonts, Large Map, gbdecompress
- Fixed Simple Physics: joypad input caching was wrong
- Fixed Banks Non-Intrinsic: mismatched SRAM banks for final calculation, improved naming
- Removed Analogue Pocket examples that were just duplicates of Game Boy ones

#### · Docs:

- Fixed search where some exact matches didn't return a result
- Various updates and improvements
- Added more historical release notes

## 12.1.2 GBDK-2020 4.2.0

#### 2023/08

- Includes SDCC version  $\sim$ 4.3 with GBDK-2020 patches for Z80 and NES
  - Patched SDCC Builds with support for Sega GG/SMS and the Nintendo NES are used. See the github workflow for details
- · Known Issues
  - SDCC may fail on Windows when run from folder names with spaces on non-C drives.
- · Library
  - Added NORETURN definition (for \_Noreturn)
  - Added: set\_bkg\_attributes(), set\_bkg\_submap\_attributes(), set\_bkg\_attribute\_xy()
  - The following new functions replace old ones. The old functions will continue to work for now, but migration to new versions is strongly encouraged.
    - \* vsync(): replaces wait\_vbl\_done()
    - \* set\_default\_palette(): replaces cgb\_compatibility()
  - metasprites: added metasprite functions which can set base sprite property parameter (\_\_current ← \_\_base\_prop) for GB/GBC and NES
    - \* move\_metasprite\_flipy(): replaces move\_metasprite\_hflip()
    - \* move\_metasprite\_flipx(): replaces move\_metasprite\_vflip()
    - \* move\_metasprite\_flipxy(): replaces move\_metasprite\_hvflip()
    - \* move\_metasprite\_ex(): (replaces move\_metasprite()
  - NES
    - \* Added support for much of the GBDK API
    - \* Banking support (library and sdcc toolchain)
    - \* Added set\_bkg\_attributes\_nes16x16(), set\_bkg\_submap\_attributes\_nes16x16(), set\_bkg\_attribute\_xy\_nes16x16()
  - SMS/GG
    - \* Swapped A and B buttons to match game boy buttons
    - \* X coordinate metasprite clipping on the screen edges
  - Game Boy
    - \* Minor crt0 optimizations
    - Faster vmemcpy(), set\_data(), get\_data()
    - \* Fixed hide sprites range(39u, 40u); overflow shadow OAM
    - \* Increased sgb\_transfer() maximum packet length to 7 x 16 bytes
    - \* Convert gb decompress routines to the new calling convention
    - \* Convert rle\_decompress routines to the new calling convention
    - \* Removed legacy MBC register definitions .MBC1\_ROM\_PAGE and .MBC\_ROM\_PAGE
    - \* Workaround for possible HALT bug in Crash Handler
  - Refactored interrupts to use less space
- · Toolchain / Utilities
  - Added png2hicolorgb
  - lcc
    - \* Fixed --sdccbindir
    - Removed the unused -DINT\_16\_BITS from the default SDCC compiler and preprocessor arguments
    - \* Improved improved Game Gear header compatibility (change header region code from 4 to 6)
  - png2asset

- \* Added -o as a more standard version of the -c argument
- \* Added -repair\_index\_pal: Tries to repair tile palettes for indexed color pngs (such as when RGB paint programs mix up indexed colors if the same color exists in multiple palettes). Implies -keep\_palette\_order
- \* Added -no\_palettes: Do not export palette data
- \* Fixed support for indexed color pngs with less than 8 bits color depth
- \* Fixed incorrect palettes when different colors have same luma value (use RGB values as less-significant bits)
- \* Fixed -keep\_duplicate\_tiles not working with -source\_tileset
- Changed to use cross-platform constants for metasprite properties (S\_FLIPX, S\_FLIPY and S\_← PAL)

## - makebin

- Warn if RAM banks specified and file size of ROM is less than the 64K required to enable them with in emulators
- Added sdld6808 (for NES)

## · Examples

- Fixed mkdir broken in some compile.bat files (remove unsupported -p flag during bat file conversion)
- Sound Test: Added MegaDuck support
- Wav Playback: Improved support on AGB/AGS hardware
- Metasprites: Added sub-palette switching for GBC and NES, software metasprite flipping for sms/gg
- Large Map: Added color for supported platforms
- LCD ISR Wobble: Improved interrupt flag settings
- Added GB-Type example
- Added Game Boy Color Hi-Color example using png2hicolorgb

### · Docs:

- Improved search to do partial matches instead of matching start of string only
- Added SDAS assembler manual (asmlnk\_manual.txt)
- Added section on NES support
- Added Using Game Boy Color Features
- Updated MegaDuck hardware documentation
- Added Banked Calling Convention
- Added mention of MAX HARDWARE SPRITES

### 12.1.3 GBDK-2020 4.1.1

#### 2022/11

- Includes SDCC version 13350 with GBDK-2020 patches for Z80
- Library
  - Fixed RGB() and RGB8() macros

## 12.1.4 GBDK-2020 4.1.0

#### 2022/10

- Includes SDCC version 13350 with GBDK-2020 patches for Z80
- · Known Issues
  - The compile.bat batch files for Windows use the an invalid -p option for mkdir

# Building GBDK

- The linux port of SDCC is custom built on Ubuntu 16.04 due to reduced GLIBC compatibility issues in more recent SDCC project builds.
- Added Windows 32-Bit build

#### Platforms

- SDCC has renamed the gbz80 port to sm83 see faq gbz80\_sm83\_old\_port\_name\_error
- Added experimental support for MSXDOS (msxdos) and NES (nes). These platforms are not fully functional at this time. See Supported Consoles & Cross Compiling

### · Licensing

- Clarified licensing status with consent from GBDK original authors, added licensing folder to distribution

#### Library

- SGB: Use longer wait between the SGB packet transfers
- SMS/GG: less garbage on screen when clearing VRAM in the init code
- SMS/GG: Added cgb compatibility() to set default palette with the four shades of gray
- Fixed: get\_sprite\_data(), get\_bkg\_data() , get\_win\_data() when LCDCF\_BG8000 bit of LCDC\_REG is set
- Fixed ISR chain lengths. VBL: 4 user handlers, LCD: 3 user handlers, SIO/TIM/JOY: 4 user handlers
- Added new constants for the Game Boy Color (CGB):
  - \* VBK\_BANK\_0, VBK\_BANK\_1
  - \* VBK TILES, VBK ATTRIBUTES
  - \* BKGF PRI, BKGF YFLIP, BKGF XFLIP, BKGF BANK0, BKGF BANK1
  - \* BKGF\_CGB\_PAL0, BKGF\_CGB\_PAL1, BKGF\_CGB\_PAL2, BKGF\_CGB\_PAL3, BKGF\_CGB\_PAL4, BKGF\_CGB\_PAL5, BKGF\_CGB\_PAL6, BKGF\_CGB\_PAL7
  - \* VBK TILES, VBK ATTRIBUTES

# • Toolchain / Utilities

## - lcc

 $\star$  Changed to Error out and warn when <code>gbz80</code> port is used instead of <code>sm83</code>

# png2asset

- \* Added -tiles\_only: Export tile data only
- \* Added -maps only: Export map tilemap only
- \* Added -metasprites\_only: Export metasprite descriptors only
- \* Added -source\_tileset: Use source tileset image with common tiles
- \* Added -keep\_duplicate\_tiles: Do not remove duplicate tiles
- \* Added -bin: Export to binary format (includes header files)
- \* Added -transposed: Export transposed (column-by-column instead of row-by-row)
- \* Added basic MSXDOS support
  - · Added 1bpp packing mode (BPP1)
  - · -spr16x16msx
- \* Added basic NES support
  - · -use\_nes\_attributes
  - · -use\_nes\_colors
- \* Changed to only export \_tile\_pals[] arrays when -use-structs is set (ZGB specific)

# - gbcompress

- \* Added --bank=<num> Add Bank Ref: 1 511 (default is none, with --cout only)
- \* Fixed failure to flush data at end of compression (uncommitted bytes)
- \* Fixed Warning: File read size didn't match expected

#### - lcc

- \* When -autobank is specified lcc will automatically add -yoA for makebin if no -yo\* entry is present
- \* Fixed broken -E Preprocess only flag

#### - makecom

\* Added makecom for post-processing msxdos binaries

## - makebin

- \* Fixed (via sdcc) bug with -yp not always working correctly
  - https://sourceforge.net/p/sdcc/code/12975/

## - bankpack

- \* Added support for the Game Boy Camera MBC
- \* Added -reserve=<bank>:<size> option to reserve space during autobank packing
  - · Workaround for libraries that contain objects in banks (such as gbt-player)

#### - ihxcheck

- \* Check and warn for bank overflows under specific conditions
  - · A multiple write to the same address must occur. The address where the overlap ends is used as BANK.
  - There must also be a write which spans multiple banks, the ending address of that must match BANK. The starting addresses is the OVERFLOW-FROM BANK.

#### Examples

- Changed Logo example to use new GBDK logo art from user "Digit"
- Added example for APA image mode with more than 256 tiles
- Added SGB Sound Effects example
- Changed to new WAV sound example

#### Docs

- Added improved MBC Type chart
- Include SDCC manual in pdf format
- Various doc updates and improvements

# 12.1.5 GBDK-2020 4.0.6

# 2022/02

- Includes SDCC version 12539 with GBDK-2020 patches for Z80
- Building GBDK
  - Changed to target older version of macOS (10.10) when building for better compatibility
- Platforms
  - Added support for Mega Duck / Cougar Boy (duck). See Supported Consoles & Cross Compiling
- Library
  - Added memcmp()
  - Added add\_low\_priority\_TIM() function for timer interrupts which allow nesting for GB/CGB
  - Added set\_bkg\_based\_tiles(), set\_bkg\_based\_submap(), set\_win\_based\_tiles(), set\_win\_based\_submap()
     for when a map's tiles don't start at VRAM index zero
  - Added clock() for SMS/GG
  - Added macro definitions for SDCC features:

- \* #define SFR \_\_sfr
- \* #define AT(A) \_\_at(A)
- Added check for OAM overflow to metasprite calls for GB/CGB
- Added constant definitions PSG\_LATCH, PSG\_CH0, PSG\_CH1, PSG\_CH2, PSG\_CH3, PSG\_VOLUME for SMS/GG
- Renamed bgb emu.h to emu debug.h and BGB \* functions to EMU \*.
  - \* Aliases for the BGB\_\* ones and a bgb\_emu.h shim are present for backward compatibility
- Changed headers to wrap SDCC specific features (such as NONBANKED) with #ifdef \_\_\_SDCC
- Changed rand() and arand() to return uint8\_t instead of int8\_t (closer to the standard)
- Fixed declaration for PCM SAMPLE and definition for AUD3WAVE
- Fixed definition of size\_t to be unsigned int instead of int
- Fixed vmemcpy() and memmove() for SMS/GG
- Fixed random number generation for SMS/GG
- Fixed letter U appearing as K for min font
- Fixed define name in crash handler.h
- Exposed \_\_rand\_seed
- · Toolchain / Utilities
  - png2asset
    - \* Added SMS/GG graphics format support
    - \* Added 4bpp and SGB borders
    - \* Added warning when image size is not an even multiple of tile size
    - \* Added -tile\_origin offset option for when map tiles do not start at tile 0 in VRAM
    - \* Added \*\_TILE\_COUNT definition to output
    - \* Fixed CGB ...s\_map\_attributes type definition in output
    - \* Fixed values for num\_palettes in output
    - \* Fixed incorrect TILE\_COUNT value when not -using\_structs
  - lcc
    - Changed makebin flags to turn off Nintendo logo copy for GB/CGB (use version in crt instead)
    - \* Fixed lcc handling of makebin -x\* arguments
- · Examples
  - Added logo example (cross-platform)
  - Added ISR\_VECTOR example of a raw ISR vector with no dispatcher for GB/CGB
  - Changed sgb\_border example to use png2asset for graphics
  - Changed use of set\_interrupts() in examples so it's outside critical sections (since it disables/enables interrupts)
  - Changed cross-platform auto-banks example to use .h header files
  - Changed SGB border example to also work with SGB on PAL SNES
- Docs
  - Added new section: Migrating From Pre-GBDK-2020 Tutorials

#### 12.1.6 GBDK-2020 4.0.5

#### 2021/09

- · Includes SDCC version 12539 with GBDK-2020 patches for Z80
- · Known Issues
  - SDCC: z80instructionSize() failed to parse line node, assuming 999 bytes
    - \* This is a known issue with the SDCC Peephole Optimizer parsing and can be ignored.
  - -bo<n> and -ba<n> are not supported by the Windows build of sdcc
  - On macOS the cross platform banks example has problems parsing the filename based ROM and RAM bank assignments into -bo<n> and -ba<n>
- · Added support for new consoles. See Supported Consoles & Cross Compiling
  - Analogue Pocket (ap)
  - Sega Master System (sms) and Game Gear (gg)
- Library
  - Fixed error when calling get\_bkg\_tile\_xy: '?ASlink-Warning-Undefined Global '.set\_tile\_xy' referenced by module `?ASlink-Warning-Byte PCR relocation error for symbol .set\_tile\_xy
  - Variables in static storage are now initialized to zero per C standard (but remaining WRAM is not cleared)
  - Added many new register flag constants and names. For example:
    - \* rLCDC is a new alias for LCDC REG
    - \* LCDCF\_WINON, LCDCF\_WINOFF, LCDCF\_B\_WINON
  - Added BANK(), BANKREF(), BANKREF EXTERN()
  - Added INCBIN(), BANK(), INCBIN SIZE(), INCBIN EXTERN()
  - Added generic SWITCH\_ROM() and SWITCH\_RAM()
  - Added BGB\_printf() and updated emulator debug output.
  - Added set\_native\_tile\_data(), set\_tile\_map(), set\_1bpp\_colors, set\_bkg\_1bpp\_data, set\_sprite\_1bpp\_data, set\_2bpp\_palette, set\_bkg\_2bpp\_data, set\_sprite\_2bpp\_data, set\_tile\_2bpp\_data (sms/gg only), set\_bkg\_4bpp\_data (sms/gg only), set\_sprite\_4bpp\_data (sms/gg only)
  - Added RLE decompression support: rle\_init(), rle\_decompress(),
  - Changed itoa(), uitoa(), Itoa(), ultoa() to now require a radix value (base) argument to be passed. On
    the Game Boy and Analogue Pocket the parameter is required but not utilized.
- Examples
  - Added cross-platform examples (build for multiple consoles: gb, ap, sms, gg)
  - Added sms, gg, pocket(ap) examples
  - Added incbin example
  - Added simple physics sub-pixel / fixed point math example
  - Added rle decompression example
  - Changed windows make.bat files to compile.bat
  - Bug fixes and updates for existing examples
- · Toolchain / Utilities
  - png2asset
    - \* png2asset is the new name for the png2mtspr utility
    - \* Added collision rectangle width and height (-pw, -ph)
    - \* Added option to use the palette from the source png (-keep\_palette\_order)

- \* Added option to disable tile flip (-noflip)
- \* Added export as map: tileset + bg (-map)
- \* Added option to use CGB BG Map attributes (-use\_map\_attributes)
- \* Added option to group the exported info into structs (-use\_structs)

#### - lcc

- \* Use -m to select target port and platform: "-m[port]:[plat]" ports:gbz80,z80 plats $\leftarrow$  :ap,gb,sms,gg
- Changed default output format when not specified from .ihx to .gb (or other active rom extension)
- \* Changed Icc to always use the linkerfile -lkout= option when calling bankpack
- \* Fixed name generation crash when outfile lacks extension

#### bankpack

- \* Added linkerfile input and output: -lkin=<file>, -lkout=<file>
- \* Added selector for platform specific behavior plat=<plat> (Default:gb, Avaialble:gb, sms). sms/gg targets prohibits packing LIT\_N areas in the same banks as CODE\_N areas
- \* Added randomization for auto-banks (-random) for debugging and testing

## - utility\_gbcompress

- \* Added C source array format output (-cout) (optional variable name argument -varname=)
- \* Added C source array format input (-cin) (experimental)
- \* Added block style rle compression and decompression mode: --alg=rle
- \* Fixed comrpession errors when input size was larger than 64k

# • Docs

- Added Supported Consoles & Cross Compiling section
- Various doc updates and improvements

### 12.1.7 GBDK-2020 4.0.4

## 2021/06

- Library
  - Support SDCC INITIALIZER area (SDCC ~12207+)
  - Added get vram byte() / get win tile xy() / get bkg tile xy()
  - Added set tile data()
  - Fixed SGB detection
  - Fixed broken get\_tiles() / set\_tiles()
  - Fixed broken token handling in gb\_decompress\_sprite\_data() / gb\_decompress\_bkg\_data() / gb\_decompress\_win\_data()
  - Changed all headers to use standard stdint.h types (ex: uint8\_t instead of UINT8/UBYTE)
  - Made sample.h, cgb.h and sgb.h independent from gb.h

#### Examples

- Added project using a .lk linkerfile
- Changed all examples to use standard stdint.h types
- Moved banks\_farptr and banks\_new examples to "broken" due to SDCC changes
- · Toolchain / Utilities
  - png2mtspr
    - \* Added option to change default value for sprite property/attributes in (allows CGB palette, BG/WIN priority, etc).

- \* Improved: Turn off suppression of "blank" metasprite frames (composed of entirely transparent sprites)
- \* Fixed endless loop for png files taller than 255 pixels
- bankpack
  - \* Fixed -yt mbc specifier to also accept Decimal
  - \* Improved: bank ID can be used in same file it is declared. Requires SDCC 12238+ with -n option to defer symbol resolution to link time.
- gbcompress
  - \* Added C source input (experimental) and output
  - \* Added size #defines
- lcc
  - \* Added -no-libs and -no-crt options
  - \* Added support for .lk linker files (useful when number of files on lcc command line exceeds max size on windows)
  - \* Added support for converting .ihx to .gb
  - \* Added rewrite .o files -> .rel for linking when called with -autobank and -Wb-ext=.rel
  - \* Workaround makebin -Wl-yp formatting segfault
- Docs
  - Improved utility png2mtspr documentation
  - Various doc updates and improvements

## 12.1.8 GBDK-2020 4.0.3

#### 2021/03

- Library
  - Added set\_vram\_byte()
  - Added set\_bkg\_tile\_xy() / set\_win\_tile\_xy()
  - Added get\_bkg\_xy\_addr() / get\_win\_xy\_addr()
  - Added set\_bkg\_submap() / set\_win\_submap()
  - Added metasprite api support
  - Added gb decompress support
  - Added calloc / malloc / realloc / free and generic memmove
  - Improved printf(): ignore %0 padding and %1-9 width specifier instead of not printing, support upper case X
  - Fixed line(): handle drawing when x1 is less than x2
- · Examples
  - Added large\_map: showing how to use set\_bkg\_submap()
  - Added scroller: showing use of get\_bkg\_xy\_addr(), set\_bkg\_tile\_xy() and set\_vram\_byte
  - Added gbdecompress: de-compressing tile data into vram
  - Added metasprites: show creating a large sprite with the new metasprite api
  - Added template projects
  - Fixed build issue with banks autobank example
  - Improved sgb\_border
- · Toolchain / Utilities
  - Added utility\_gbcompress utility
  - Added utility\_png2mtspr metasprite utility
- Docs
  - Added extensive documentation (some of which is imported and updated from the old gbdk docs)
  - Added PDF version of docs

## 12.1.9 GBDK-2020 4.0.2

#### 2021/01/17

- Includes SDCC snapshot build version 12016 (has a fix for duplicate debug symbols generated from inlined header functions which GBDK 4.0+ uses)
- · Updated documentation
- · Library was improved
  - Linking with stdio.h does not require that much ROM now
  - Default font is changed to the smaller one (102 characters), that leaves space for user tiles
  - Fixed broken support for multiplying longs
  - memset/memcpy minor enhancements
  - safer copy-to-VRAM functions
  - loading of 1bit data fixed, also now it is possible to specify pixel color
  - Improved code generation for the GBDK Library with SDCC switch on by default: --max-allocs-per-node
     50000
  - fixed wrong parameter offsets in hiramcpy() (broken ram\_function example)
  - Multiple minor improvements
- New bankpack feature, allows automatic bank allocation for data and code, see banks\_autobank example, feature is in beta state, use with care
- · Lcc improvements
  - Fixed option to specify alternate base addresses for shadow\_OAM, etc
- · Examples: Added bgb debug example

# 12.1.10 GBDK-2020 4.0.1

## 2020/11/14

- · Updated API documentation
- IHX is checked for correctness before the makebin stage. That allows to warn about overwriting the same ROM addresses (SDCC toolchain does not check this anymore).
- · Library was improved
  - set\_\*\_tiles() now wrap maps around horizontal and vertical boundaries correctly
  - new fill\_\*\_rect() functions to clear rectangle areas
  - runtime initialization code now does not initialize whole WRAM with zeros anymore, that allows BGB to raise exceptions when code tries to read WRAM that was not written before.
  - enhanced SGB support
    - joypad\_init() / joypad\_ex() support for multiple joypads
    - \* SGB border example
  - \_current\_bank variable is updated when using bank switching macros
  - Reorganized examples: each example is in separate folder now, that simplifies understanding.
  - Lcc improvements
    - \* Fix -S flag
    - \* Fix default stack location from 0xDEFF to 0xE000 (end of WRAM1)
    - \* Fix cleanup of .adb files with -Wf-debug flag
    - \* Fix output not working if target is -o some\_filename.ihx

#### 12.1.11 GBDK-2020 4.0

#### 2020/10/01

- GBDK now requires SDCC 4.0.3 or higher, that has fully working toolchain. Old link-gbz80 linker is not used anymore, sdldgb and makebin are used to link objects and produce binary roms; maccer tool is no longer needed either
  - SDCC 4.0.3 has much better code generator which produces smaller and faster code. Code is twice faster.
  - SOURCE LEVEL DEBUGGING is possible now! Native toolchain produces \*.CDB files that contain detailed debug info. Look for EMULICIOUS extension for vs.code. It supports breakpoints, watches, inspection of local variables, and more!
  - SDCC 4.0.4 has fixed RGBDS support; library is not updated to support that in full yet, but it is possible to assemble and link code emitted by SDCC with RGDBS
  - New banked trampolines are used, they are faster and smaller
  - New (old) initialization for non-constant arrays do NOT require 5 times larger rom space than initialized array itself, SDCC even tries to compress the data
- · Library was improved
  - itoa/Itoa functions were rewritten, div/mod is not required now which is about 10 times faster
  - sprite functions are inline now, which is faster up to 12 times and produces the same or smaller code;
     OAM symbol is renamed into \_shadow\_OAM that allows accessing shadow OAM directly from C code
  - interrupt handling was revised, it is now possible to make dedicated ISR's, that is important for timesensitive handlers such as HBlank.
  - printf/sprintf were rewritten and splitted, print functions are twice faster now and also requre less rom space if you use sprintf() only, say, in bgb\_emu.h
  - crash\_handler.h crash handler that allows to detect problems with ROMs after they are being released (adapted handler, originally written by ISSOtm)
  - improved and fixed string.h
  - many other improvements and fixes thanks to all contributors!
- · Revised examples
- · Improved linux support
- · Lcc has been updated
  - it works with the latest version of sdcc
  - quoted paths with spaces are working now

#### 12.1.12 GBDK-2020 3.2

### 2020/06/05

- · Fixed OAM initialization that was causing a bad access to VRAM
- Interrupt handlers now wait for lcd controller mode 0 or 1 by default to prevent access to inaccessible VRAM
  in several functions (like set\_bkg\_tiles)
- · Several optimizations here and there

#### 12.1.13 GBDK-2020 3.1.1

## 2020/05/17

· Fixed issues with libgcc s dw2-1.dll

## 12.1.14 GBDK-2020 3.1

#### 2020/05/16

- Banked functions are working! The patcher is fully integrated in link-gbz80, no extra tools are needed. It is based on Toxa's work
  - Check this post for more info
  - Check the examples/gb/banked code for basic usage
- Behavior formerly enabled by USE\_SFR\_FOR\_REG is on by default now (no need to specify it, it isn't a tested #ifdef anymore). check here why: https://gbdev.gg8.se/forums/viewtopic.← php?id=697
- Fixed examples that were not compiling in the previous version and some improvements in a few of them. Removed all warnings caused by changing to the new SDCC
- · Fixed bug in lcc that was causing some files in the temp folder not being deleted
- Removed as-gbz80 (the lib is now compiled with sdasgb thanks to this workaround) https↔ ://github.com/gbdk-2020/gbdk-2020/commit/d2caafa4a66eb08998a14b258cb66af041a0e5c8
- · Profile support with bgb emulator
  - Basic support including <gb/bgb\_emu.h> and using the macros BGB\_PROFILE\_BEGIN and BGB← \_PROFILE\_END. More info in this post https://gbdev.gg8.se/forums/viewtopic.← php?id=703
  - For full profiling check this repo and this post https://github.com/untoxa/bgb\_← profiling\_toolkit/blob/master/readme.md https://gbdev.gg8.se/forums/viewtopic.← php?id=710

### 12.1.15 GBDK-2020 3.0.1

#### 2020/04/12

- Updated SDCC to v.4.0
- · Updated LCC to work with the new compiler

## 12.1.16 GBDK-2020 3.0

#### 2020/04/12

Initial GBDK-2020 release Updated SDCC to v4.0 The new linker is not working so the old version is still there
 There is an issue with sdagb compiling drawing.s (the JP in line 32 after ".org .MODE\_TABLE+4\*.G\_MODE"
 it's writing more than 4 bytes invading some addresses required by input.s:41) Because of this, all .s files in
 libc have been assembled with the old as-gbz80 and that's why it is still included

## 12.2 Historical GBDK Release Notes

## 12.2.1 GBDK 2.96

17 April, 2000 Many changes.

- · Code generated is now much more reliable and passes all of sdcc's regression suite.
- Added support for large sets of local variables (>127 bytes).
- · Added full 32 bit long support.
- · Still no floating pt support.

#### 12.2.2 GBDK 2.95-3

19th August, 2000

- · Stopped lcc with sdcc from leaking .cdb files all across /tmp.
- Optimised < and > for 16 bit varibles.
- Added a new lexer to sdcc. Compiling files with large initalised arrays takes 31% of the time (well, at least samptest.c does:)

This is an experimental release for those who feel keen. The main change is a new lexer (the first part in the compilation process which recognises words and symbols like '!=' and 'char' and turns them into a token number) which speeds up compilation of large initialised arrays like tile data by a factor of three. Please report any bugs that show up - this is a big change.

I have also included a 'minimal' release for win32 users which omits the documentation, library sources, and examples. If this is useful I will keep doing it.

## 12.2.3 GBDK 2.95-2

5th August, 2000 Just a small update. From the README:

- Added model switching support –model-medium uses near (16 bit) pointers for data, and banked calls for anything not declared as 'nonbanked' –model-small uses near (16 bit) pointers for data and calls. Nothing uses banked calls. 'nonbanked' functions are still placed in HOME. Libraries are under lib/medium and lib/small.
- · Added the gbdk version to 'sdcc -version'
- · Changed the ways globals are exported, reducing the amount of extra junk linked in.
- Turned on the optimisations in flex. Large constant arrays like tile data should compile a bit faster.

## 12.2.4 GBDK 2.95

22nd July, 2000

- Fixed 'a << c' for c = [9..15]</li>
- no\$gmb doesn't support labels of > 32 chars. The linker now trims all labels to 31 chars long.
- · Fixed wait vbl for the case where you miss a vbl
- Fixed + and for any type where size of == 2 and one of the terms was on the stack. This includes pointers and ints. Fixes the text output bug in the examples. Should be faster now as well. Note that + and for longs is still broken.
- Fixed the missing \*/ in gb.h
- Added basic far function support. Currently only works for isas and rgbasm. See examples/gb/far/\*
- bc is now only pushed if the function uses it. i.e. something like: int silly(int i) { return i; } will not have the push bc; pop bc around it.
- Better rgbasm support. Basically: o Use "sdcc -mgbz80 --asm=rgbds file.c" for each file.c o Use "sdcc -mgbz80 --asm=rgbds crt0.o gbz80.lib gb.lib file1.o file2.o..."

to link everything together. The .lib files are generated using astorgb.pl and sdcc to turn the gbdk libraries into something rgbds compatible. The libraries are *not* fully tested. Trust nothing. But give it a go:)

· Ran a spell checker across the README and ChangeLog

This is a recommended upgrade. Some of the big features are:

Decent rgbds support. All the libraries and most of the examples can now compile with rgbds as the assembler. Banked function support. It is now easier to break the 32k barrier from within C. Functions can live in and be called transparently from any bank. Only works with rgbds Fixed some decent bugs with RSH, LSH, and a nasty bug with + and - for int's and pointers. Various optimisations in the code generator.

7th July, 2000 Information on float and long support. Someone asked about the state of float/long support recently. Heres my reply:

long support is partly there, as is float support. The compiler will correctly recognise the long and float keywords, and will generate the code for most basic ops (+, -, &, | etc) for longs correctly and will generate the function calls for floats and hard long operations (\*, /, %) correctly. However it wont generate float constants in the correct format, nor will it 'return' a long or float - gbdk doesn't yet support returning types of 4 bytes. Unfortunately its not going to make it into 2.95 as there's too much else to do, but I should be able to complete long support for 2.96

#### 12.2.5 GBDK 2.94

7th May, 2000 Many fixes - see the README for more.

7th May - Library documentation up. A good size part of the libraries that go with gbdk have been documented - follow the HTML link above to have a look. Thanks to quang for a good chunk of the gb.h documentation. Please report any errors:)

- Fixed #define BLAH 7 // Unterminated 'error in sdcpp
  - Fixed SCY\_REG += 2, SCY\_REG -= 5 (add and subtract in indirect space) as they were both quite broken.
  - externs and static's now work as expected.
  - You can now specify which bank code should be put into using a #pragma e.g: #pragma bank=HOME Under rgbds and asxxxx putting code in the HOME bank will force the code into bank 0 useful for library functions. The most recent #pragma bank= will be the one used for the whole file.
  - Fixed an interesting bug in the caching of lit addresses
  - Added support for accessing high registers directly using the 'sfr' directive. See libc/gb/sfr.s and gb/hardware.h for an example. It should be possible with a bit of work to make high ram directly usable by the compiler; at the moment it is experimental. You can test sfr's by enabling USE\_SFR\_FOR\_← REG=1
  - Added remove\_VBL etc functions.
  - Documented the libs see the gbdk-doc tarball distributed seperatly.
  - Two dimensional arrays seem to be broken.

# 12.2.6 GBDK 2.93

6th April, 2000 From the README

- · Added multi-bank support into the compiler The old -Wf-boxx and -Wf-baxx options now work
- Has preliminary support for generating rgbds and ISAS compatible assembler. Try -W-asm=rgbds or -W-asm=isas. The ISAS code is untested as I dont have access to the real assembler.
- · RSH is fixed
- · AND is fixed
- The missing parts of 2.1.0's libs are there. Note: They are untested.
- The dscan demo now fully works (with a hack :)
- There is a bug with cached computed values which are later used as pointers. When the value is first used as a BYTE arg, then later as a pointer the pointer fails as the high byte was never computed and is now missing. A temporary fix is to declare something appropriate as 'volatile' to stop the value being cached. See dscan.c/bombs() for an example.

#### 12.2.7 GBDK 2.92-2 for win32

26th March, 2000 This is a maintenance release for win32 which fixes some of the niggly install problems, especially:

- · win32 only. Takes care of some of the install bugs, including:
  - Now auto detects where it is installed. This can be overridden using set GBDKDIR=...
  - Problems with the installer (now uses WinZip)
  - Problems with the temp directory Now scans TMP, TEMP, TMPDIR and finally c: tmp
  - cygwin1.dll and 'make' are no longer required gbdk is now built using mingw32 which is win32 native make.bat is automagically generated from the Makefile
  - I've reverted to using WORD for signed 16 bit etc. GBDK\_2\_COMPAT is no longer required.

WORDS are now back to signed. GBDK\_2\_COMPAT is no longer needed. Temporary files are created in TMP, TEMP, or TMPDIR instead of c: tmp The installer is no more as it's not needed. There is a WinZip wrapped version for those with the extra bandwidth:). gbdk autodetects where it is installed - no more environment variables. cygwin1.dll and make are no longer required - gbdk is now compiled with mingw32.

See the ChangeLog section in the README for more information.

21st March, 2000 Problems with the installer. It seems that the demo of InstallVISE has an unreasonably short time limit. I had planed to use the demo until the license key came through, but there's no sign of the key yet and the 3 day evaluation is up. If anyone knows of a free Windows installer with the ability to modify environment variables, please contact me. I hear that temporarily setting you clock back to the 15th works...

18th March, 2000 libc5 version available / "Error creating temp file" Thanks to Rodrigo Couto there is now a Linux/libc5 version of gbdk3-2.92 available - follow the download link above. At least it will be there when the main sourceforge site comes back up... Also some people have reported a bug where the compiler reports '\*\*\* Error creating temp file'. Try typing "mkdir c: tmp" from a DOS prompt and see if that helps.

### 12.2.8 GBDK 2.92

8th March, 2000 Better than 2.91 :). Can now be installed anywhere. All the demos work. See the README for more.

- All the examples now work (with a little bit of patching :)
  - Fixed problem with registers being cached instead of being marked volatile.
  - More register packing should be a bit faster.
  - You can now install somewhere except c: gbdk | /usr/lib/gbdk
  - Arrays initialised with constant addresses a'la galaxy.c now work.
  - Fixed minor bug with 104\$: labels in as.
  - Up to 167d/s...

### 12.2.9 GBDK 2.91

27th Feb, 2000 Better than 2.90 and includes Linux, win32 and a source tar ball. Some notes:

Read the README first Linux users need libgc-4 or above. Debian users try apt-get install libgc5. All the types have changed. Again, please read the README first. I prefer release early, release often. The idea is to get the bugs out there so that they can be squashed quickly. I've split up the libs so that they can be used on other platforms and so that the libs can be updated without updating the compiler. One side effect is that gb specific files have been shifted into their own directory i.e. gb.h is now gb/gb.h.

23rd Feb, 2000 First release of gbdk/sdcc. This is an early release - the only binary is for Linux and the source is only available through cvs. If your interested in the source, have a look at the cvs repository gbdk-support first, which will download all the rest of the code. Alternatively, look at gbdk-support and gbdk-lib at cvs.gbdk.sourceforge.net and sdcc at cvs.sdcc.sourceforge.net. I will be working on binaries for Win32 and a source tar ball soon. Please report any bugs through the bugs link above.

31st Jan, 2000 Added Dermot's far pointer spec. It's mainly here for comment. If sdcc is ported to the Gameboy then I will be looking for some way to do far calls.

8th Jan, 2000 Moved over to sourceforge.net. Thanks must go to David Pfeffer for gbdk's previous resting place, www.gbdev.org. The transition is not complete, but cvs and web have been shifted. Note that the cvs download instructions are stale - you should now look to cvs.gbdk.sourceforge.net. I am currently working on porting sdcc over to the Z80. David Nathan is looking at porting it to the GB.

6th Jan, 2000 Icehawk wrote "I did write some rumble pack routines. Just make sure to remind people to add -WI-yt0x1C or -WI-yt0x1D or -WI-yt0x1E depending on sram and battery usage. Find the routines on my site (as usual). =)"

18th Oct, 1999 Bug tracking / FAQ up. Try the link on the left to report any bugs with GBDK. It's also the first place to look if your having problems.

#### 12.2.10 GBDK 2.1.5

17th Oct. 1999

The compiler is the same, but some of the libraries have been improved. memset() and memcpy() are much faster, malloc() is fixed, and a high speed fixed block alternative malloc() was added.

## 12.2.11 GBDK 2.0b11 (DOS binary only) - 24 November 1997

• Fixed another bug in code generation, that could happen when performing logical operations on 1-byte variables.

## 12.2.12 GBDK 2.0b10 (DOS binary only) - 6 November 1997

- Fixed a nasty bug in code generation, that could happen when performing arithmetic operations on 1-byte variables.
- Changed the name of same files of the gb-dtmf example so that it compiles on DOS.

#### 12.2.13 GBDK 2.0b9 (DOS binary only)

· Several bug fixes in the compiler and in the libraries.

# 12.2.14 GBDK 2.0b8 (DOS binary only)

- Limited all file names to 8 characters to solve problems on DOS.
- Added communication routines that enable to send data through the link port of the GameBoy. Unfortunately, these routines do not always work; so use them with care until the next GBDK release.
- · Added the comm.c example which illustrates how to use communication routines.
- It is possible to specify the name of the program (to be written in the image header) at link time using the
  -WI-yn="XXX" flag (where X is the name of the program, which can contain up to 16 characters in quotes,
  including spaces; on Unix, depending on your shell, you must add backslashes before quotes and spaces like
  in -WI-yn="My\ Game").
- · Several bug fixes in the compiler.

# 12.2.15 GBDK 2.0b7 (DOS binary only)

- GBDK now uses a pre-release of lcc 4.1 (DOS binary only), that fixes a couple of problems in code generation.
- A couple of important points have been documented in the GBDK Programming Guidelines and Known Problems sections.
- · Several improvements and optimizations to the code generator.

#### 12.2.16 GBDK 2.0b6

- Added a peephole optimizer (with few rules at the moment).
- Changed the name of the hardware registers to match the "official" names.
- Added support for copying complete functions to RAM or HIRAM (memcpy() and hiramcpy() functions). The
  compiler now automatically generates two symbol for the start and the end of each function, named start\_X
  and end\_X (where X is the name of the function). This enables to calculate the length of a function when
  copying it to RAM.
- · Added the ram\_fn.c example which illustrates how to copy functions to RAM and HIRAM.
- · Added support for installing IRQ handlers.
- · Added the irq.c example which illustrates how to install IRQ handlers.
- Added RAM banks support (switch\_ram\_bank() function). The switch\_bank() function has been renamed to switch\_rom\_bank(). The banks.c example has been updated. The flags for generating multiple bank images have been modified.
- It is possible to set the sprite ram location at link time using the -WI-g.OAM=# flag (where # is the address of the sprite ram). The sprite ram address must begin at an address multiple of 0x100, and is 0xA0 bytes long.

## 12.2.17 GBDK 2.0b5

- · New documentation (not finished yet).
- · Fixed a bug that could generate wrong code in switch statements.
- · Fixed a bug in int comparison.
- · Added a DTMF program written by Osamu Ohashi.
- Added a game (Deep Scan) written by a friend of Osamu.
- Modified the delay() function so that it takes a long parameter. It can be used to wait between 1 and 65536 milliseconds (0 = 65536). The pause() function has been removed.

# 12.2.18 GBDK 2.0b4

- Fixed a bug that could generate wrong code when using hexadecimal constants.
- A new example (galaxy.c) has been added. It is the C version of the space.s example. sprite.c has been removed.
- Most of the libraries have been split into small modules for reducing final code size.

## 12.2.19 GBDK 2.0b3

- GBDK can generate multiple-banks images, i.e. images greater than 32kB (see the banks example).
- It is possible to set the stack pointer at link time using the -WI-g.STACK=# flag (where # is the address of the stack pointer). Several functions (e.g. show\_bkg()) have been changed into macros (e.g. SHOW\_BKG). The delay() function waits exactly 1 millisecond, and the pause() waits 256 milliseconds. Linking with the standard libraries is no more required. The lib/gb.lib (lib\gb.lib on DOS) text file contains a list of modules in which to look for undefined symbols. The linker will parse this file, and link your code with the required modules only. The stdio library has been split in several object files, and only necessary modules will be added to your code, thus reducing its size. The GBDK distribution can be located anywhere in your system if you use the -Wo-lccdir=GBDK-DIR flag when invoking lcc. Bug fixes.

# 12.2.20 GBDK 2.0b2

- · Lots of bug fixes.
- GBDK has to be in the \GBDK-2.0 directory on DOS machines.

#### 12.2.21 GBDK 2.0b1

- The code generator has been completely rewritten with the new version of lcc. It produces much smaller and more efficient code. The size of the code is generally between 20 and 50% smaller. A number of small optimizations are still to be done.
- · The size of basic types has been changed:
  - An int is 8 bits.
  - A long is 16 bits.
- This change was required for the code generator to produce better code, because the Z80 is actually an 8-bit processor.
- The linker generates the complement checksum correctly now.
- The libraries and example programs have been modified for the new code generator.

#### 12.2.22 GBDK 1.1

- · Removed Xloadimage from the GBDK distribution. It is now available as a separate archive.
- · A compiled DOS version is now available (cross-compiled on my Sun Workstation!).
- · The libraries and the example programs have been improved.
- The make script has been improved. Compiling on UNIX should be easier.
- · Many bugfixes.

## 12.2.23 GBDK 1.0-1 1996

# 13 Toolchain settings

## 13.1 lcc settings

```
./lcc [ option | file ]...
    except for -1, options are processed left-to-right before files
    unrecognized options are taken to be linker options
-A
                warn about nonANSI usage; 2nd -A warns more
               emit expression-level profiling code; see bprint(1)
use the compiler named 'dir/rcc'
-b
-Bdir/
               compile only
-c
                set switch statement density to 'n'
              Turns on --debug for compiler, -y (.cdb), -j (.noi), -w (wide .map format) for linker
-debug
                        -Wa-l (assembler .lst), -Wl-u (.lst -> .rst address update)
-Dname=def define the preprocessor symbol 'name'
-E only run preprocessor on named .c and .h files files -> stdout --save-preproc Use with -E for output to *.i files instead of stdout
               produce symbol table information for debuggers
-help or -?
               print this message
-Idir
                add 'dir' to the beginning of the list of #include directories
-K
               don't run ihxcheck test on linker ihx output
-1x
               search library
               select port and platform: "-m[port]:[plat]" ports:sm83,z80,mos6502
-m
      plats:ap, duck, gb, sms, gg, nes
-N
              do not search the standard directories for #include files
                emit code to check for dereferencing zero pointers
-n
-no-crt
                do not auto-include the gbdk \operatorname{crt0.o} runtime in linker list
               do not auto-include the gbdk libs in linker list
-no-libs
-0
                is ignored
              leave the output in 'file'
-o file
               print ANSI-style declarations for globals
-P
-p -pg
                emit profiling code; see prof(1) and gprof(1)
-s
               compile to assembly language
               auto-assign banks set to 255 (bankpack) specify static libraries (default is dynamic)
-autobank
-static
                emit function tracing calls to printf or to 'name'
-t -tname
-target name
              is ignored
               place temporary files in 'dir/'; default=/tmp
-tempdir=dir
-Uname
                undefine the preprocessor symbol 'name'
-\nabla
                show commands as they are executed; 2nd -v suppresses execution
                suppress warnings
                specify system-specific 'arg'
-Woarg
-W[pfablim]arg pass 'arg' to the preprocessor, compiler, assembler, bankpack, linker, ihxcheck, or makebin
```

13.2 sdcc settings 77

# 13.2 sdcc settings

```
SDCC : z80/sm83/mos6502/mos65c02 TD- 4.4.0 #14620 (Linux)
published under GNU General Public License (GPL)
-
Usage : sdcc [options] filename
General options:
      --help
                               Display this help
                               Display sdcc's version
      --version
                               Trace calls to the preprocessor, assembler, and linker
      --verbose
                               Execute verbosely. Show sub commands as they are run
                               Output list of macro definitions in effect. Use with -E
                               Define macro as in -Dmacro
  -D
  — Т
                               Add to the include (*.h) path, as in -Ipath
  -A
  -II
                               Undefine macro as in -Umacro
  -M
                               Preprocessor option
                               Pass through options to the pre-processor (p), assembler (a) or linker (1)
                               Pre-include a file during pre-processing
      --include
  -E
      --preprocessonly
                               Preprocess only, do not compile
      --syntax-only
                               Parse and verify syntax only, do not compile
  -S
                               Compile only; do not assemble or link
                               Compile and assemble, but do not link
      --compile-only
  -c
                               Act in c1 mode. The standard input is preprocessed code, the output is assembly
       --c1mode
       code.
                               Place the output into the given path resp. file
  -0
                              Optional file type override (c, c-header or none), valid until the next -x display the directories in the compiler's search path messages are compatible with Microoft visual studio
      --print-search-dirs
      --vc
      --use-stdout
                               send errors to stdout instead of stderr
                               Do not include the standard library directory in the search path Do not include the standard include directory in the search path
      --nostdlib
      --nostdinc
      --less-pedantic
                               Disable some of the more pedantic warnings
      --disable-warning
                               <nnnn> Disable specific warning
                               Treat the warnings as errors
      --Werror
      --debug
                               Enable debugging symbol output
      --cyclomatic
                               Display complexity of compiled functions
      --std
                               Determine the language standard (c89, c99, c11, c23, sdcc89 etc.)
      --fdollars-in-identifiers Permit '$' as an identifier character
--fsigned-char Make "char" signed by default
      --use-non-free
                               Search / include non-free licensed libraries and header files
Code generation options:
                               Set the port to use e.g. -mz80.
                               Select port specific processor e.g. -mpic14 -p16f84
  -p
      --stack-auto
                               Stack automatic variables
      --xstack
                               Use external stack
                              Use reentrant calls on the int and long support functions Use reentrant calls on the float support functions
      --int-long-reent
      --float-reent
      --xram-movc
                               Use movc instead of movx to read xram (xdata)
                               <func[,func,...] > Cause the called function to save registers instead of the
      --callee-saves
       caller
      --fomit-frame-pointer Leave out the frame pointer.
      --all-callee-saves
                              callee will always save registers used
                               insert call to function __stack_probe at each function prologue
      --stack-probe
                               don't memcpy initialized xram from code
      --no-xinit-opt
      --no-c-code-in-asm
                               don't include c-code as comments in the asm file
      --no-peep-comments
                               don't include peephole optimizer comments
      --codeseq
                               <name> use this name for the code segment
                               <name> use this name for the const segment
      --constseq
       --dataseg
                               <name> use this name for the data segment
Optimization options:
        -opt-code-speed
                               Optimize for code speed rather than size
      --opt-code-size
                               Optimize for code size rather than speed
      --max-allocs-per-node Maximum number of register assignments considered at each node of the tree
       decomposition
                               On some ports, disable passing some parameters in registers {\tt Disable} optimization of calls to standard library
      --no-reg-params
      --nostdlibcall
                               Disable overlaying leaf function auto variables
      --nooverlav
                               Disable the GCSE optimisation
      --nogcse
      --nolospre
                               Disable lospre
      --nogenconstprop
                               Disable generalized constant propagation
      --nolabelopt
                               \hbox{\tt Disable label optimisation}
      --noinvariant
                               Disable optimisation of invariants
      --noinduction
                               Disable loop variable induction
      --noloopreverse
                               Disable the loop reverse optimisation
      --no-peep
                               Disable the peephole assembly file optimisation
      --peep-asm
                               Enable peephole optimization on inline assembly
                               Enable peephole optimization for return instructions
      --peep-return
                               Disable peephole optimization for return instructions
      --no-peep-return
      --peep-file
                               <file> use this extra peephole file
      --allow-unsafe-read
                               Allow optimizations to read any memory location anytime
Internal debugging options:
      --dump-ast
                               Dump front-end AST before generating i-code
      --dump-i-code
                               Dump the i-code structure at all stages
                               Dump graphs (control-flow, conflict, etc)
Include i-code as comments in the asm file
      --dump-graphs
      --i-code-in-asm
      --fverbose-asm
                               Include code generator comments in the asm output
```

```
Linker options:
                            Include the given library in the link
  -T.
                           Add the next field to the library search path
     --lib-path
                            <path> use this path to search for libraries
     --out-fmt-ihx
                           Output in Intel hex format
      --out-fmt-s19
                           Output in S19 hex format
                           <nnnn> External Ram start location
      --xram-loc
                            <nnnn> External Ram size
     --xram-size
      --iram-size
                           <nnnn> Internal Ram size
     --xstack-loc
                           <nnnn> External Stack start location
                           <nnnn> Code Segment Location
      --code-loc
      --code-size
                           <nnnn> Code Segment size
      --stack-loc
                           <nnnn> Stack pointer initial value
                           <nnnn> Direct data start location
      --data-loc
     --idata-loc
      --no-optsdcc-in-asm
                          Do not emit .optsdcc in asm
Special options for the z80 port:
                           Force a called function to always save BC
     --callee-saves-bc
     --portmode=
                           Determine PORT I/O mode (z80/z180)
     -bo
                            <num> use code bank <num>
     -ba
                           <num> use data bank <num>
     --asm=
                           Define assembler name (rgbds/asxxxx/isas/z80asm/gas)
      --codeseq
                           <name> use this name for the code segment
                           <name> use this name for the const segment
     --constseq
                            <name> use this name for the data segment
     --dataseg
                           Do not link default crt0.rel
      --no-std-crt0
                           Do not use IY (incompatible with --fomit-frame-pointer)
      --reserve-regs-iy
      --fno-omit-frame-pointer Do not omit frame pointer
                        Emit externs list in generated asm
      --emit-externs
      --legacy-banking
                           Use legacy method to call banked functions
     --nmos-z80
                           Generate workaround for NMOS Z80 when saving IFF2
      --sdcccall
                           Set ABI version for default calling convention
      --allow-undocumented-instructions Allow use of undocumented instructions
Special options for the sm83 port:
     -bo
                           <num> use code bank <num>
                            <num> use data bank <num>
     -ba
                           Define assembler name (rgbds/asxxxx/isas/z80asm/gas)
     --asm=
      --callee-saves-bc Force a called function to always save BC
      --codesea
                           <name> use this name for the code segment
     --constseg
                           <name> use this name for the const segment
     --dataseg
                           <name> use this name for the data segment
      --no-std-crt0
                           Do not link default crt0.rel
     --legacy-banking
                           Use legacy method to call banked functions
                           Set ABI version for default calling convention
      --sdcccall
Special options for the mos6502 port:
      --model-small 8-bit address space for data
     --model-large
                           16-bit address space for data (default)
     --no-zp-spill
                           place register spills in 16-bit address space
      --no-std-crt0
                           Do not link default crt0.rel
Special options for the mos65c02 port:
     --model-small
                           8-bit address space for data
     --model-large
                           16-bit address space for data (default)
     --no-zp-spill
                           place register spills in 16-bit address space
     --no-std-crt0
                           Do not link default crt0.rel
```

# 13.3 sdasgb settings

```
sdas Assembler V02.00 + NoICE + SDCC mods (GameBoy)
Copyright (C) 2012 Alan R. Baldwin
This program comes with ABSOLUTELY NO WARRANTY.
Usage: [-Options] [-Option with arg] file
Usage: [-Options] [-Option with arg] outfile file1 [file2 ...]
 -h or NO ARGUMENTS Show this help list
Input:
      Add the named directory to the include file
  -I
       search path. This option may be used more than once.
       Directories are searched in the order given.
Output:
       Create list file/outfile[.lst]
       Create object file/outfile[.rel]
  -0
       Create symbol file/outfile[.sym]
  -5
Listing:
  -d Decimal listing
       Octal listing
  -q
       Hex
               listing (default)
       Display .define substitutions in listing
  -b
       and display without .define substitutions
Disable instruction cycle count in listing
       Flag relocatable references by
                                             in listing file
  -ff Flag relocatable references by mode in listing file
       Disable automatic listing pagination
  -р
       Disable .list/.nlist processing
Wide listing format for symbol table
  -11
  -w
Assembly:
       Enable out of range signed / unsigned errors
Symbols:
```

```
-a All user symbols made global
-g Undefined symbols made global
-n Don't resolve global assigned value symbols
-z Disable case sensitivity for symbols
Debugging:
-j Enable NoICE Debug Symbols
-y Enable SDCC Debug Symbols
```

# 13.4 sdasz80 settings

```
sdas Assembler V02.00 + NoICE + SDCC mods (Zilog Z80 / Hitachi HD64180 / ZX-Next / eZ80 / R800)
Copyright (C) 2012 Alan R. Baldwin
This program comes with ABSOLUTELY NO WARRANTY.
Usage: [-Options] [-Option with arg] file
Usage: [-Options] [-Option with arg] outfile file1 [file2 ...]
  -h or NO ARGUMENTS Show this help list
Input:
     Add the named directory to the include file
        search path. This option may be used more than once.
       Directories are searched in the order given.
Output:
       Create list
                       file/outfile[.lst]
  -1
       Create object file/outfile[.rel]
       Create symbol file/outfile[.sym]
Listing:
       Decimal listing
  -d
  -q
       Octal listing
Hex listing (default)
  -x
       Display .define substitutions in listing
       and display without .define substitutions
  -c Disable instruction cycle count in listing
-f Flag relocatable references by ' in listing file
-ff Flag relocatable references by mode in listing file
       Disable automatic listing pagination
  -p
       Disable .list/.nlist processing
       Wide listing format for symbol table
Assembly:
       Enable out of range signed / unsigned errors
  -\nabla
Symbols:
  -a All user symbols made global
       Undefined symbols made global
  -g
       Don't resolve global assigned value symbols
       Disable case sensitivity for symbols
Debugging:
       Enable NoICE Debug Symbols
       Enable SDCC Debug Symbols
```

## 13.5 sdas6500 settings

```
sdas Assembler V02.00 + NoICE + SDCC mods (Rockwell 6502/6510/65C02)
Copyright (C) 2012 Alan R. Baldwin
This program comes with ABSOLUTELY NO WARRANTY.
Usage: [-Options] [-Option with arg] file
Usage: [-Options] [-Option with arg] outfile file1 [file2 ...]
  -h or NO ARGUMENTS Show this help list
Input:
      Add the named directory to the include file
       search path. This option may be used more than once.
       Directories are searched in the order given.
Output:
  -l Create list
                     file/outfile[.lst]
       Create object file/outfile[.rel]
  -0
       Create symbol file/outfile[.sym]
Listing:
  -d
       Decimal listing
       Octal listing
Hex listing (default)
  -q
       Display .define substitutions in listing
       and display without .define substitutions
       Disable instruction cycle count in listing
  - f
       Flag relocatable references by ' in listing file
  -ff Flag relocatable references by mode in listing file
-p Disable automatic listing pagination
       Disable .list/.nlist processing
  -u
       Wide listing format for symbol table
Assembly:
  -77
       Enable out of range signed / unsigned errors
Symbols:
       All user symbols made global
  -a
       Undefined symbols made global
  -q
       Don't resolve global assigned value symbols
       Disable case sensitivity for symbols
Debugging:
       Enable NoICE Debug Symbols
```

```
-y Enable SDCC Debug Symbols
```

# 13.6 bankpack settings

```
bankalloc [options] objfile1 objfile2 etc
Use: Read .o files and auto-assign areas with bank=255.
     Typically called by Lcc compiler driver before linker.
Options
                 : Show this help
-h
-lkin=<file>
                 : Load object files specified in linker file <file>
-lkout=<file>
                 : Write list of object files out to linker file <file>
-yt<mbctype>
                 : Set MBC type per ROM byte 149 in Decimal or Hex (0xNN)
                 ([see pandocs](https://gbdev.io/pandocs/The_Cartridge_Header.html#0147---cartridge-type)): Similar to -yt, but sets MBC type directly to N instead
-mbc=N
                  of by intepreting ROM byte 149
                  mbc1 will exclude banks {0x20,0x40,0x60} max=127
                  mbc2 max=15, mbc3 max=127, mbc5 max=255 (not 511!)
-min=N
                 : Min assigned ROM bank is N (default 1) \,
                : Max assigned ROM bank is N, error if exceeded
: Write files out with <.ext> instead of source extension
: Write files out to <path> (<path> *MUST* already exist)
-max=N
-ext=<.ext>
-path=<path>
-cartsize
                 : Print min required cart size as "autocartsize:<NNN>"
-plat=<plat>
                : Select platform specific behavior (default:gb) (gb,sms)
-random
                 : Distribute banks randomly for testing (honors -min/-max)
-reserve=<b:n> : Reserve N bytes (hex) in bank B (decimal)
                   Ex: -reserve=105:30F reserves 0x30F bytes in bank 105
-banktype=<b:t>: Set bank B (decimal) to use type T (CODE or LIT). For sms/gg
                   Ex: -banktype=2:LIT sets bank 2 to type LIT
                 : Verbose output, show assignments
Example: "bankpack -ext=.rel -path=some/newpath/ file1.o file2.o"
Unless -ext or -path specify otherwise, input files are overwritten.
Default MBC type is not set. It *must* be specified by -mbc= or -yt!
The following will have FF and 255 replaced with the assigned bank:
A _CODE_255 size <size> flags <flags> addr <address>
S b_<function name> Def0000FF
     bank <const name> Def0000FF
     (Above can be made by: const void __at(255) __bank_<const name>;
```

## 13.7 sdldqb settings

```
sdld Linker V03.00/V05.40 + sdld
Usage: [-Options] [-Option with arg] file
Usage: [-Options] [-Option with arg] outfile file1 [file2 ...]
Startup:
     Echo commands to stdout (default)
  -p
       No echo of commands to stdout
  -n
Alternates to Command Line Input:
                       ASlink » prompt input
  -c
  _ f
       file[.lk]
                       Command File input
Libraries:
  -k Library path specification, one per -k
       Library file specification, one per -1
Relocation:
     area base address = expression
  -q
       global \ symbol = expression
       (platform) Select platform specific virtual address translation
Map format:
       Map output generated as (out)file[.map]
  -m
       Wide listing format for map file Hexadecimal (default)
  -w
  -d
       Decimal
       Octal
  -q
Output:
       Intel Hex as (out)file[.ihx]
       Motorola S Record as (out)file[.s19]
  -s
       NoICE Debug output as (out)file[.noi]
  -i
       SDCDB Debug output as (out)file[.cdb]
List:
       Update listing file(s) with link data as file(s)[.rst]
  -11
Case Sensitivity:
-z Disable Case Sensitivity for Symbols
End:
       or null line terminates input
```

#### 13.8 sdldz80 settings

```
No echo of commands to stdout
  -n
Alternates to Command Line Input:
                      ASlink » prompt input
 -f
      file[.lk]
                     Command File input
Libraries:
 -k Library path specification, one per -k
-l Library file specification, one per -l
      area base address = expression
  -b
      global \ symbol = expression
  -q
       -a
Map format:
      Map output generated as (out)file[.map]
  -m
      Wide listing format for map file
      Hexadecimal (default)
 -d
      Decimal
  -q
      Octal
Output:
     Intel Hex as (out) file[.ihx]
      Motorola S Record as (out)file[.s19]
      NoICE Debug output as (out)file[.noi]
      SDCDB Debug output as (out)file[.cdb]
List:
      Update listing file(s) with link data as file(s)[.rst]
 -11
Case Sensitivity:
  -z Disable Case Sensitivity for Symbols
End:
      or null line terminates input
13.9 sdld6808 settings
sdld Linker V03.00/V05.40 + sdld
Usage: [-Options] [-Option with arg] file
Usage: [-Options] [-Option with arg] outfile file1 [file2 ...]
Startup:
```

```
-p Echo commands to stdout (default)-n No echo of commands to stdout
Alternates to Command Line Input:
                        ASlink » prompt input
  -c
                        Command File input
     file[.lk]
  -f
Libraries:
  -k Library path specification, one per -k
  _ 1
       Library file specification, one per -1
Relocation:
  -b area base address = expression
       global symbol = expression
  -q
       (platform) Select platform specific virtual address translation
  -a
Map format:
       Map output generated as (out)file[.map]
  -w
       Wide listing format for map file
  -x
       Hexadecimal (default)
  -d
      Decimal
  -q
       Octal
Output:
       Intel Hex as (out)file[.ihx]
  -s
       Motorola S Record as (out)file[.s19]
      NoICE Debug output as (out)file[.noi] SDCDB Debug output as (out)file[.cdb]
  - i
List:
       Update listing file(s) with link data as file(s)[.rst]
Case Sensitivity:
       Disable Case Sensitivity for Symbols
End:
       or null line terminates input
```

# 13.10 ihxcheck settings

```
ihx_check input_file.ihx [options]
Options
-h : Show this help
-e : Treat warnings as errors
Use: Read a .ihx and warn about overlapped areas.
Example: "ihx_check build/MyProject.ihx"
```

# 13.11 makebin settings

```
Also see setting_mbc_and_rom_ram_banks
```

```
-z
                  generate GameBoy format binary file
  -S
                  generate Sega Master System format binary file
  -N
                  generate Famicom/NES format binary file
 -o bytes
                  skip amount of bytes in binary file
SMS format options (applicable only with -S option):
                  header rom size (0xa-0x2) (default: 0xc)
  -xo n
                  set region code (3-7) (default: 4)
  -xj n
                  version number (0-15) (default: 0)
                  number of rom banks (default: 2) (autosize: A)
  -yo n
 -ya n
                  number of ram banks (default: 0)
GameBoy format options (applicable only with \mbox{-}\mbox{Z} option):
  -vo n
                  number of rom banks (default: 2) (autosize: A)
                  number of ram banks (default: 0)
  -va n
                  MBC type (default: no MBC)
  -yt n
  -yl n
                  old licensee code (default: 0x33)
  -yk cc
                  new licensee string (default: 00)
  -yn name
                  cartridge name (default: none)
                  GameBoy Color compatible GameBoy Color only
  -vc
  -уС
                  Super GameBoy
  -ys
                  Convert .noi file named like input file to .sym
                  set non-Japanese region flag
  -vN
                  do not copy big N validation logo into ROM header
  -yp addr=value Set address in ROM to given value (address 0x100-0x1FE)
Arguments:
                  optional IHX input file, '-' means stdin. (default: stdin) optional output file, '-' means stdout. (default: stdout)
  <in_file>
  <out_file>
```

# 13.12 makecom settings

makecom image.rom image.noi output.com
Use: convert a binary .rom file to .msxdos com format.

# 13.13 gbcompress settings

```
gbcompress [options] infile outfile
Use: compress a binary file and write it out.
Options
          : Show this help screen
          : Decompress (default is compress)
-d
         : Verbose output
-v
         : Read input as .c source format (8 bit char ONLY, uses first array found)
--cin
--cout
         : Write output in .c / .h source format (8 bit char ONLY)
--varname=<NAME> : specify variable name for c source output
--alg=<type> : specify compression type: 'rle', 'gb' (default)
--bank=<num>
                 : Add Bank Ref: 1 - 511 (default is none, with --cout only)
Example: "gbcompress binaryfile.bin compressed.bin"
Example: "gbcompress -d compressedfile.bin decompressed.bin"
Example: "gbcompress --alg=rle binaryfile.bin compressed.bin"
The default compression (gb) is the type used by gbtd/gbmb
The rle compression is Amiga IFF style
```

## 13.14 png2asset settings

```
<file>.png [options]
ouput file (if not used then default is <png file>.c)
usage: png2asset
-o <filename>
-c <filename>
                      deprecated, same as -o
                      metasprites width size (default: png width)
-sw <width>
                      metasprites height size (default: png height)
-sh <height>
-sp cprops>
                      change default for sprite OAM property bytes (in hex) (default: 0x00)
-px <x coord>
                      metasprites pivot x coordinate (default: metasprites width / 2) metasprites pivot y coordinate (default: metasprites height / 2)
-pv <v coord>
-pw <width>
                      metasprites collision rect width (default: metasprites width)
-ph <height>
                      metasprites collision rect height (default: metasprites height)
-spr8x8
                      use SPRITES_8x8
-spr8x16
                      use SPRITES_8x16 (this is the default)
-spr16x16msx
                      use SPRITES_16x16
-sprite_no_optimize keep empty sprite tiles, do not remove duplicate tiles
                      bank (default: fixed bank)
-b <bank>
-keep_palette_order use png palette
-repair_indexed_pal try to repair indexed tile palettes (implies "-keep_palette_order")
-noflip
                      disable tile flip
                      Export as map (tileset + bg) instead of default metasprite output
-map
-use_map_attributes Use CGB BG Map attributes -use_nes_attributes Use NES BG Map attributes
                      Convert RGB color values to NES PPU colors
-use_nes_colors
                      Group the exported info into structs (default: false) (used by ZGB Game Engine)
-use structs
                      bits per pixel: 1, 2, 4 (default: 2)
-bpp
-max_palettes
                      max number of palettes allowed (default: 8)
                      (note: max colors = max_palettes x num colors per palette)
gb, nes, sgb, sms, 1bpp (default: gb)
-pack mode
                      tile index offset for maps (default: 0)
-tile_origin
-tiles_only
                      export tile data only
```

```
-maps_only export map tilemap only
-metasprites_only export metasprite descriptors only
-source_tileset use source tileset (image with common tiles)
-entity_tileset (maps only) mark matching tiles counting from 255 down, entity patterns not exported
-keep_duplicate_tiles do not remove duplicate tiles (default: not enabled)
-no_palettes do not export palette data
-bin export to binary format
-transposed export transposed (column-by-column instead of row-by-row)
-rel_paths paths to tilesets are relative to the input file path
decoder error empty input buffer given to decoder. Maybe caused by non-existing file?
```

# 13.15 png2hicolorgb settings

```
png2hicolorgb input_image.png [options]
version 1.4.1: bbbbbr. Based on Glen Cook's Windows GUI "hicolour.exe" 1.2
Convert an image to Game Boy Hi-Color format
Options
           : Show this help
: Set log level: "-v" verbose, "-vQ" quiet, "-vE" only errors, "-vD" debug
: Set base output filename (otherwise from input image)
-h
-v*
-o <file>
--csource : Export C source format with incbins for data files
--bank=N
            : Set bank number for C source output where N is decimal bank number 1-511
--type=N
           : Set conversion type where N is one of below
               1: Median Cut - No Dither (*Default*)
2: Median Cut - With Dither
               3: Wu Ouantiser
-p
            : Show screen attribute pattern options (no processing)
            : Set Left screen attribute pattern where N is decimal entry (-p to show patterns)
            : Set Right screen attribute pattern where N is decimal entry (-p to show patterns)
--vaddrid : Map uses vram id (128->255->0->127) instead of (*Default*) sequential tile order (0->255)
--nodedupe : Turn off tile pattern deduplication
Example 1: "png2hicolorgb myimage.png"
Example 2: "png2hicolorgb myimage.png --csource -o=my_output_filename"
 Default settings provide good results. Better quality but slower: "--type=3 -L=2 -R=2"
Historical credits and info:
   Original Concept : Icarus Productions
   Original Code : Jeff Frohwein
   Full Screen Modification : Anon
   Adaptive Code : Glen Cook
   Windows Interface : Glen Cook
   Additional Windows Programming : Rob Jones
   Original Quantiser Code : Benny
   Quantiser Conversion : Glen Cook
```

## 13.16 romusage settings

```
romusage input_file.[map|noi|ihx|cdb|.gb[c]|.pocket|.duck|.gg|.sms] [options]
version 1.2.8, by bbbbbr
Options
-p:SMS_GG : Set platform to GBDK SMS/Game Gear (changes memory map templates)
-a : Show Areas in each Bank. Optional sort by, address: "-aA" or size: "-aS"

    -g : Show a small usage graph per bank (-gA for ascii style)
    -G : Show a large usage graph per bank (-GA for ascii style)

-B : Brief (summarized) output for banked regions. Auto scales max bank
       shows [Region]_[Max Used Bank] / [auto-sized Max Bank Num]
-F
   : Force Max ROM and SRAM bank num for -B. (0 based) -F:ROM:SRAM (ex: -F:255:15)
-m : Manually specify an Area -m:NAME:HEXADDR:HEXLENGTH
    : Manually specify an Area that should not overlap -e:NAME:HEXADDR:HEXLENGTH
-е
-E : All areas are exclusive (except HEADERs), warn for any overlaps -q : Quiet, no output except warnings and errors
    : Suppress output of warnings and errors
-R : Return error code for Area warnings and errors
-sR : [Rainbow] Color output (-sRe for Row Ends, -sRd for Center Dimmed, -sRp % based) -sP : Custom Color Palette. Colon separated entries are decimal VT100 color codes
       -sP:DEFAULT:ROM:VRAM:SRAM:WRAM:HRAM (section based color only)
-sC : Show Compact Output, hide non-essential columns
-sH : Show HEADER Areas (normally hidden)
-smROM : Show Merged ROM_0 and ROM_1 output (i.e. bare 32K ROM)
-smWRAM : Show Merged WRAM_0 and WRAM_1 output (i.e DMG/MGB not CGB)
            -\text{sm}\star compatible with banked ROM_x or WRAM_x when used with -\text{B}
-sJ: Show JSON output. Some options not applicable. When used, -Q recommended -nB: Hide warning banner (for .cdb output)
-nA: Hide areas (shown by default in .cdb output)
 z : Hide areas smaller than SIZE -z:DECSIZE
Use: Read a .map, .noi, .cdb or .ihx file to display area sizes
Example 1: "romusage build/MyProject.map"
Example 2: "romusage build/MyProject.noi -a -e:STACK:DEFF:100 -e:SHADOW_OAM:C000:A0"
Example 3: "romusage build/MyProject.ihx -g"
Example 4: "romusage build/MyProject.map -q -R"
Example 5: "romusage build/MyProject.noi -sR -sP:90:32:90:35:33:36"
Example 6: "romusage build/MyProject.map -sRp -g -B -F:255:15 -smROM -smWRAM"
  * GBDK / RGBDS map file format detection is automatic.
```

* Estimates are as close as possible, but may not be complete.  Unless specified with -m/-e they *do not* factor regions lacking complete ranges in the Map/Noi/Thx file, for example Shadow OAM and Stack.  * IHX files can only detect overlaps, not detect memory region overflows.  * CDB file output ONLY counts (most) data from C sources.  It cannot count functions and data from ASM and LIBs, so bank totals may be incorrect/missing.  * GB/GBC/ROM files are just guessing, no promises.	
14 Todo List	
File far_ptr.h	
Add link to a discussion about banking (such as, how to assign code and variables to banks)  Page ROM/RAM Banking and MBCs	
Variables in RAM	
15 Module Index	
15.1 C modules	
Here is a list of all modules:	
List of gbdk fonts	87
16 Data Structure Index	
16.1 Data Structures	
Here are the data structures with brief descriptions:	
far_ptr	87
_fixed	88
atomic_flag	89
isr_nested_vector_t	89
isr_vector_t	89
joypads_t	90
metasprite_t	91
OAM_item_t	93
sfont_handle	94
17 File Index	
17.1 File List	
Here is a list of all files with brief descriptions:	
gbdk-lib/include/assert.h	115
gbdk-lib/include/ctype.h	116
gbdk-lib/include/limits.h	270

17.1 File List 85

gbdk-lib/include/rand.h	336
gbdk-lib/include/setjmp.h	338
gbdk-lib/include/stdarg.h	98
gbdk-lib/include/stdatomic.h	366
gbdk-lib/include/stdbool.h	367
gbdk-lib/include/stddef.h	367
gbdk-lib/include/stdint.h	368
gbdk-lib/include/stdio.h	374
gbdk-lib/include/stdlib.h	375
gbdk-lib/include/stdnoreturn.h	379
gbdk-lib/include/string.h	109
gbdk-lib/include/time.h	379
gbdk-lib/include/typeof.h	380
gbdk-lib/include/types.h	115
gbdk-lib/include/asm/types.h	112
gbdk-lib/include/asm/mos6502/provides.h	95
gbdk-lib/include/asm/mos6502/stdarg.h	96
gbdk-lib/include/asm/mos6502/string.h	98
gbdk-lib/include/asm/mos6502/types.h	110
gbdk-lib/include/asm/sm83/provides.h	95
gbdk-lib/include/asm/sm83/stdarg.h	97
gbdk-lib/include/asm/sm83/string.h	102
gbdk-lib/include/asm/sm83/types.h	111
gbdk-lib/include/asm/z80/provides.h	96
gbdk-lib/include/asm/z80/stdarg.h	97
gbdk-lib/include/asm/z80/string.h	106
gbdk-lib/include/asm/z80/types.h	114
gbdk-lib/include/gb/bcd.h	117
gbdk-lib/include/gb/bgb_emu.h	121
gbdk-lib/include/gb/cgb.h	121
gbdk-lib/include/gb/crash_handler.h	127
gbdk-lib/include/gb/drawing.h	128

gbdk-lib/include/gb/emu_debug.h	132
gbdk-lib/include/gb/gb.h	136
gbdk-lib/include/gb/gbdecompress.h	185
gbdk-lib/include/gb/hardware.h	188
gbdk-lib/include/gb/hblankcpy.h	235
gbdk-lib/include/gb/isr.h	237
gbdk-lib/include/gb/metasprites.h	238
gbdk-lib/include/gb/sgb.h	258
gbdk-lib/include/gbdk/bcd.h	119
gbdk-lib/include/gbdk/console.h	261
gbdk-lib/include/gbdk/emu_debug.h	133
gbdk-lib/include/gbdk/far_ptr.h	262
gbdk-lib/include/gbdk/font.h	265
gbdk-lib/include/gbdk/gbdecompress.h	187
gbdk-lib/include/gbdk/gbdk-lib.h	267
gbdk-lib/include/gbdk/incbin.h	267
gbdk-lib/include/gbdk/metasprites.h	245
gbdk-lib/include/gbdk/platform.h	269
gbdk-lib/include/gbdk/rledecompress.h	269
gbdk-lib/include/gbdk/version.h	270
gbdk-lib/include/msx/hardware.h	211
gbdk-lib/include/msx/metasprites.h	245
gbdk-lib/include/msx/msx.h	272
gbdk-lib/include/nes/hardware.h	218
gbdk-lib/include/nes/metasprites.h	248
gbdk-lib/include/nes/nes.h	298
gbdk-lib/include/nes/rgb_to_nes_macro.h	336
gbdk-lib/include/sms/bcd.h	119
gbdk-lib/include/sms/gbdecompress.h	187
gbdk-lib/include/sms/hardware.h	222
gbdk-lib/include/sms/metasprites.h	253
abdk-lib/include/sms/sms.h	339

18 Module Documentation 87

# 18 Module Documentation

# 18.1 List of gbdk fonts

# 18.1.1 Description

#### **Variables**

```
uint8_t font_spect []uint8_t font_italic []uint8_t font_ibm []uint8_t font_min []uint8_t font_ibm_fixed []
```

## 18.1.2 Variable Documentation

```
18.1.2.1 font_spect uint8_t font_spect[] [extern]
The default fonts

18.1.2.2 font_italic uint8_t font_italic[]

18.1.2.3 font_ibm uint8_t font_ibm[]

18.1.2.4 font_min uint8_t font_min[]

18.1.2.5 font_ibm_fixed uint8_t font_ibm_fixed[] [extern]
Backwards compatible font
```

# 19 Data Structure Documentation

# 19.1 \_\_far\_ptr Union Reference

```
#include <gbdk-lib/include/gbdk/far_ptr.h>
```

# **Data Fields**

```
FAR_PTR ptr
struct {
    void * ofs
    uint16_t seg
} segofs
struct {
    void(* fn )(void)
    uint16_t seg
} segfn
```

# 19.1.1 Detailed Description

Union for working with members of a FAR\_PTR

# 19.1.2 Field Documentation

```
19.1.2.1 ptr FAR_PTR __far_ptr::ptr

19.1.2.2 ofs void* __far_ptr::ofs

19.1.2.3 seg uint16_t __far_ptr::seg

19.1.2.4 struct { ... } __far_ptr::segofs

19.1.2.5 fn void(* __far_ptr::fn) (void)

19.1.2.6 struct { ... } __far_ptr::segfn
The documentation for this union was generated from the following file:
```

• gbdk-lib/include/gbdk/far\_ptr.h

# 19.2 \_fixed Union Reference

#include <gbdk-lib/include/asm/types.h>

# Data Fields

• UWORD w

## 19.2.1 Detailed Description

Useful definition for working with 8 bit + 8 bit fixed point values Use .w to access the variable as unsigned 16 bit type. Use .b.h and .b.l (or just .h and .l) to directly access it's high and low unsigned 8 bit values.

## 19.2.2 Field Documentation

```
19.2.2.3 struct { ... }
19.2.2.4 struct { ... } _fixed::b
```

### **19.2.2.5 W UWORD \_**fixed::w

The documentation for this union was generated from the following file:

• gbdk-lib/include/asm/types.h

# 19.3 atomic\_flag Struct Reference

#include <gbdk-lib/include/stdatomic.h>

## **Data Fields**

· unsigned char flag

#### 19.3.1 Field Documentation

## 19.3.1.1 flag unsigned char atomic\_flag::flag

The documentation for this struct was generated from the following file:

• gbdk-lib/include/stdatomic.h

# 19.4 isr\_nested\_vector\_t Struct Reference

#include <gbdk-lib/include/gb/isr.h>

# **Data Fields**

- uint8\_t opcode [2]
- void \* func

# 19.4.1 Field Documentation

```
19.4.1.1 opcode uint8_t isr_nested_vector_t::opcode[2]
```

# 19.4.1.2 func void\* isr\_nested\_vector\_t::func

The documentation for this struct was generated from the following file:

• gbdk-lib/include/gb/isr.h

# 19.5 isr\_vector\_t Struct Reference

#include <gbdk-lib/include/gb/isr.h>

## **Data Fields**

- · uint8\_t opcode
- void \* func

## 19.5.1 Field Documentation

# 19.6 joypads\_t Struct Reference

```
#include <gbdk-lib/include/gb/gb.h>
```

## **Data Fields**

```
• uint8_t npads
• union {
    struct {
      uint8_t joy0
      uint8_t joy1
      uint8 t joy2
      uint8_t joy3
    }
    uint8_t joypads [4]
  };
• union {
    struct {
      uint8_t joy0
      uint8_t joy1
      uint8_t joy2
      uint8_t joy3
    }
    uint8_t joypads [4]
  };
• union {
    struct {
      uint8 t joy0
      uint8_t joy1
      uint8_t joy2
      uint8_t joy3
    uint8_t joypads [4]
  };
• union {
    struct {
      uint8_t joy0
      uint8_t joy1
      uint8_t joy2
      uint8_t joy3
    uint8_t joypads [4]
  };
```

## 19.6.1 Detailed Description

Multiplayer joypad structure.

Must be initialized with joypad\_init() first then it may be used to poll all avaliable joypads with joypad\_ex()

## 19.6.2 Field Documentation

```
19.6.2.1 npads uint8_t joypads_t::npads
19.6.2.2 joy0 uint8_t joypads_t::joy0
19.6.2.3 joy1 uint8_t joypads_t::joy1
19.6.2.4 joy2 uint8_t joypads_t::joy2
19.6.2.5 joy3 uint8_t joypads_t::joy3
19.6.2.6 joypads uint8_t joypads_t::joypads[4]
19.6.2.7 union { ... }
19.6.2.8 union { ... }
```

The documentation for this struct was generated from the following files:

- gbdk-lib/include/gb/gb.h
- gbdk-lib/include/msx/msx.h
- gbdk-lib/include/nes/nes.h
- gbdk-lib/include/sms/sms.h

# 19.7 metasprite\_t Struct Reference

#include <gbdk-lib/include/gb/metasprites.h>

## **Data Fields**

- int8\_t dy
- int8\_t dx
- uint8\_t dtile
- uint8\_t props

	Description

Metasprite sub-item structure

#### **Parameters**

dy	(int8_t) Y coordinate of the sprite relative to the metasprite origin (pivot)
dx	(int8_t) X coordinate of the sprite relative to the metasprite origin (pivot)
dtile	(uint8_t) Start tile relative to the metasprites own set of tiles
props	(uint8_t) Property Flags

Metasprites are built from multiple metasprite\_t items (one for each sub-sprite) and a pool of tiles they reference. If a metasprite has multiple frames then each frame will be built from some number of metasprite\_t items (which may vary based on how many sprites are required for that particular frame).

A metasprite frame is terminated with a {metasprite\_end} entry.

Metasprite sub-item structure

#### **Parameters**

dy	(int8_t) Y coordinate of the sprite relative to the metasprite origin (pivot)
dx	(int8_t) X coordinate of the sprite relative to the metasprite origin (pivot)
dtile	(uint8_t) Start tile relative to the metasprites own set of tiles

Metasprites are built from multiple metasprite\_t items (one for each sub-sprite) and a pool of tiles they reference. If a metasprite has multiple frames then each frame will be built from some number of metasprite\_t items (which may vary based on how many sprites are required for that particular frame).

A metasprite frame is terminated with a {metasprite\_end} entry.

## 19.7.2 Field Documentation

```
19.7.2.1 dy int8_t metasprite_t::dy

19.7.2.2 dx int8_t metasprite_t::dx

19.7.2.3 dtile uint8_t metasprite_t::dtile
```

# **19.7.2.4 props** uint8\_t metasprite\_t::props

The documentation for this struct was generated from the following file:

• gbdk-lib/include/gb/metasprites.h

# 19.8 OAM\_item\_t Struct Reference

#include <gbdk-lib/include/gb/gb.h>

## **Data Fields**

- uint8\_t y
- uint8\_t x
- uint8\_t tile
- uint8\_t prop

## 19.8.1 Detailed Description

Sprite Attributes structure

#### **Parameters**

X	X Coordinate of the sprite on screen
У	Y Coordinate of the sprite on screen
tile	Sprite tile number (see set_sprite_tile)
prop	OAM Property Flags (see set_sprite_prop)

## Sprite Attributes structure

#### **Parameters**

X	X Coordinate of the sprite on screen
У	Y Coordinate of the sprite on screen - 1
tile	Sprite tile number (see set_sprite_tile)
prop	OAM Property Flags (see set_sprite_prop)

## 19.8.2 Field Documentation

```
19.8.2.1 y uint8_t OAM_item_t::y
```

```
19.8.2.2 X uint8_t OAM_item_t::x
```

```
19.8.2.3 tile uint8_t OAM_item_t::tile
```

# **19.8.2.4 prop** uint8\_t OAM\_item\_t::prop

The documentation for this struct was generated from the following files:

- gbdk-lib/include/gb/gb.h
- gbdk-lib/include/msx/msx.h
- gbdk-lib/include/nes/nes.h

# 19.9 sfont\_handle Struct Reference

#include <gbdk-lib/include/gbdk/font.h>

# **Data Fields**

- uint8\_t first\_tile
- void \* font

# 19.9.1 Detailed Description

Font handle structure

# 19.9.2 Field Documentation

**19.9.2.1 first\_tile uint8\_t sfont\_handle::first\_tile** First tile **used** for font

20 File Documentation 95

```
19.9.2.2 font void* sfont_handle::font
```

Pointer to the base of the font

The documentation for this struct was generated from the following file:

gbdk-lib/include/gbdk/font.h

## 20 File Documentation

- 20.1 docs/pages/01\_getting\_started.md File Reference
- 20.2 docs/pages/02\_links\_and\_tools.md File Reference
- 20.3 docs/pages/03\_using\_gbdk.md File Reference
- 20.4 docs/pages/04\_coding\_guidelines.md File Reference
- 20.5 docs/pages/05\_banking\_mbcs.md File Reference
- 20.6 docs/pages/06\_toolchain.md File Reference
- 20.7 docs/pages/06b\_supported\_consoles.md File Reference
- 20.8 docs/pages/07\_sample\_programs.md File Reference
- 20.9 docs/pages/08\_faq.md File Reference
- 20.10 docs/pages/09\_migrating\_new\_versions.md File Reference
- 20.11 docs/pages/10\_release\_notes.md File Reference
- 20.12 docs/pages/20\_toolchain\_settings.md File Reference
- 20.13 docs/pages/docs\_index.md File Reference
- 20.14 gbdk-lib/include/asm/mos6502/provides.h File Reference

## Macros

- #define USE C MEMCPY 0
- #define USE\_C\_STRCPY 0
- #define USE\_C\_STRCMP 0

## 20.14.1 Macro Definition Documentation

```
20.14.1.1 USE_C_MEMCPY #define USE_C_MEMCPY 0
```

20.14.1.2 USE\_C\_STRCPY #define USE\_C\_STRCPY 0

20.14.1.3 USE\_C\_STRCMP #define USE\_C\_STRCMP 0

## 20.15 gbdk-lib/include/asm/sm83/provides.h File Reference

## **Macros**

- #define USE\_C\_MEMCPY 0
- #define USE\_C\_STRCPY 0
- #define USE\_C\_STRCMP 0

### 20.15.1 Macro Definition Documentation

```
20.15.1.1 USE_C_MEMCPY #define USE_C_MEMCPY 0
20.15.1.2 USE_C_STRCPY #define USE_C_STRCPY 0
20.15.1.3 USE_C_STRCMP #define USE_C_STRCMP 0
```

## 20.16 gbdk-lib/include/asm/z80/provides.h File Reference

#### **Macros**

- #define USE\_C\_MEMCPY 0
  #define USE\_C\_STRCPY 0
  #define USE\_C\_STRCMP 1
- 20.16.1 Macro Definition Documentation

```
20.16.1.1 USE_C_MEMCPY #define USE_C_MEMCPY 0
20.16.1.2 USE_C_STRCPY #define USE_C_STRCPY 0
20.16.1.3 USE_C_STRCMP #define USE_C_STRCMP 1
```

## 20.17 gbdk-lib/include/asm/mos6502/stdarg.h File Reference

### Macros

- #define va\_start(list, last) list = (unsigned char \*)&last + sizeof(last)
   #define va\_arg(list, type) \*((type \*)((list += sizeof(type)) sizeof(type)))
   #define va\_end(list)
- **Typedefs**

• typedef unsigned char \* va list

## 20.17.1 Macro Definition Documentation

```
20.17.1.3 va_end #define va_end(
```

## 20.17.2 Typedef Documentation

```
20.17.2.1 va_list typedef unsigned char* va_list
```

## 20.18 gbdk-lib/include/asm/sm83/stdarg.h File Reference

#### **Macros**

- #define va\_start(list, last) list = (unsigned char \*)&last + sizeof(last)
- #define va\_arg(list, type) \*((type \*)((list += sizeof(type)) sizeof(type)))
- #define va\_end(list)

## **Typedefs**

• typedef unsigned char \* va\_list

### 20.18.1 Macro Definition Documentation

## 20.18.2 Typedef Documentation

```
20.18.2.1 va_list typedef unsigned char* va_list
```

## 20.19 gbdk-lib/include/asm/z80/stdarg.h File Reference

## **Macros**

- #define va\_start(list, last) list = (unsigned char \*)&last + sizeof(last)
   #define va\_arg(list, type) \*((type \*)((list += sizeof(type)) sizeof(type)))
- #define va\_end(list)

## **Typedefs**

• typedef unsigned char \* va\_list

## 20.19.1 Macro Definition Documentation

## 20.20 gbdk-lib/include/stdarg.h File Reference

#include <asm/sm83/stdarq.h>

## 20.21 gbdk-lib/include/asm/mos6502/string.h File Reference

#include <types.h>

## Macros

• #define memcpy(dst, src, n) \_\_memcpy(dst, src, n)

## **Functions**

- char \* strcpy (char \*dest, const char \*src) OLDCALL
- int strcmp (const char \*s1, const char \*s2)
- void \* \_\_memcpy (void \*dest, const void \*src, size\_t len)
- void \* memmove (void \*dest, const void \*src, size\_t n) OLDCALL
- void \* memset (void \*s, int c, size\_t n)
- char \* reverse (char \*s) NONBANKED
- char \* strcat (char \*s1, const char \*s2) NONBANKED
- int strlen (const char \*s) OLDCALL
- char \* strncat (char \*s1, const char \*s2, int n) NONBANKED
- int strncmp (const char \*s1, const char \*s2, int n) NONBANKED
- char \* strncpy (char \*s1, const char \*s2, int n) NONBANKED
- int memcmp (const void \*buf1, const void \*buf2, size\_t count)

## 20.21.1 Detailed Description

Generic string functions.

## 20.21.2 Macro Definition Documentation

```
20.21.2.1 memcpy #define memcpy( dst, src, n) __memcpy(dst, src, n)
```

#### 20.21.3 Function Documentation

```
20.21.3.1 strcpy() char* strcpy ( char * dest, const char * src )
```

Copies the string pointed to by **src** (including the terminating '\0' character) to the array pointed to by **dest**. The strings may not overlap, and the destination string dest must be large enough to receive the copy.

## **Parameters**

dest	Array to copy into
src	Array to copy from

#### Returns

A pointer to dest

```
20.21.3.2 strcmp() int strcmp ( const char * s1, const char * s2)
```

Compares strings

## **Parameters**

s1	First string to compare
s2	Second string to compare

## Returns:

- > 0 if s1 > s2
- 0 if s1 == s2
- < 0 if s1 < s2

Copies n bytes from memory area src to memory area dest.

The memory areas may not overlap.

#### **Parameters**

dest	Buffer to copy into
src	Buffer to copy from
len	Number of Bytes to copy

Copies n bytes from memory area src to memory area dest, areas may overlap

Fills the memory region **s** with **n** bytes using value **c** 

#### **Parameters**

s	Buffer to fill
С	char value to fill with (truncated from int)
n	Number of bytes to fill

```
20.21.3.6 reverse() char* reverse ( char * s)
```

Reverses the characters in a string

#### **Parameters**

s Pointer to string to reverse.

For example 'abcdefg' will become 'gfedcba'.

Banked as the string must be modifiable.

Returns: Pointer to s

Concatenate Strings. Appends string s2 to the end of string s1

#### **Parameters**

s1	String to append onto
s2	String to copy from

For example 'abc' and 'def' will become 'abcdef'.

String **s1** must be large enough to store both **s1** and **s2**.

Returns: Pointer to s1

## 20.21.3.8 strlen() int strlen ( const char \* s )

Calculates the length of a string

## **Parameters**

s String to calculate length of

Returns: Length of string not including the terminating '\0' character.

```
20.21.3.9 strncat() char* strncat ( char * s1, const char * s2, int n)
```

Concatenate at most  $\bf n$  characters from string  $\bf s2$  onto the end of  $\bf s1$ .

#### **Parameters**

s1	String to append onto
s2	String to copy from
n	Max number of characters to copy from s2

String s1 must be large enough to store both s1 and n characters of s2

Returns: Pointer to s1

```
20.21.3.10 strncmp() int strncmp (
const char * s1,
const char * s2,
int <math>n)
```

Compare strings (at most n characters):

#### **Parameters**

s1	First string to compare
s2	Second string to compare
n	Max number of characters to compare

## Returns:

- ullet > 0 if  $\mathbf{s1}$  >  $\mathbf{s2}$
- 0 if s1 == s2
- $\cdot$  < 0 if s1 < s2

```
20.21.3.11 strncpy() char* strncpy ( char * s1, const char * s2, int n)
```

Copy n characters from string s2 to s1

### **Parameters**

s1	String to copy into
s2	String to copy from
n	Max number of characters to copy from s2

If s2 is shorter than n, the remaining bytes in s1 are filled with 0.

Warning: If there is no \0 in the first **n** bytes of **s2** then **s1** will not be null terminated.

Returns: Pointer to s1

```
20.21.3.12 memcmp() int memcmp (
```

```
const void * buf1,
const void * buf2,
size_t count )
```

## Compares buffers

### **Parameters**

buf1	First buffer to compare
buf2	Second buffer to compare
count	Buffer length

#### Returns:

- > 0 if buf1 > buf2
- 0 if **buf1** == **buf2**
- < 0 if **buf1** < **buf2**

## 20.22 gbdk-lib/include/asm/sm83/string.h File Reference

```
#include <types.h>
```

## **Functions**

- char \* strcpy (char \*dest, const char \*src) OLDCALL PRESERVES\_REGS(b
- int strcmp (const char \*s1, const char \*s2) OLDCALL PRESERVES\_REGS(b
- void \* memcpy (void \*dest, const void \*src, size t len)
- void \* memmove (void \*dest, const void \*src, size\_t n)
- void \* memset (void \*s, int c, size\_t n) OLDCALL PRESERVES\_REGS(b
- char \* reverse (char \*s) OLDCALL PRESERVES\_REGS(b
- char \* strcat (char \*s1, const char \*s2)
- int strlen (const char \*s) OLDCALL PRESERVES\_REGS(b
- char \* strncat (char \*s1, const char \*s2, int n)
- int strncmp (const char \*s1, const char \*s2, int n)
- char \* strncpy (char \*s1, const char \*s2, int n)
- int memcmp (const void \*buf1, const void \*buf2, size\_t count) OLDCALL

## **Variables**

• char c

## 20.22.1 Detailed Description

Generic string functions.

## 20.22.2 Function Documentation

Copies the string pointed to by **src** (including the terminating '\0' character) to the array pointed to by **dest**. The strings may not overlap, and the destination string dest must be large enough to receive the copy.

dest	Array to copy into
src	Array to copy from

### Returns

A pointer to dest

```
20.22.2.2 strcmp() int strcmp ( const char * s1, const char * s2 )
```

Compares strings

## **Parameters**

s1	First string to compare
s2	Second string to compare

### Returns:

- ullet > 0 if  $\mathbf{s1}$  >  $\mathbf{s2}$
- 0 if s1 == s2
- ${ullet}$  < 0 if  ${f s1}$  <  ${f s2}$

Copies n bytes from memory area src to memory area dest.

The memory areas may not overlap.

#### **Parameters**

dest	Buffer to copy into
src	Buffer to copy from
len	Number of Bytes to copy

Copies n bytes from memory area src to memory area dest, areas may overlap

Fills the memory region **s** with **n** bytes using value **c** 

s	Buffer to fill
С	char value to fill with (truncated from int)
n	Number of bytes to fill

## 20.22.2.6 reverse() char\* reverse ( char \* s )

Reverses the characters in a string

#### **Parameters**

s Pointer to string to reverse.

For example 'abcdefg' will become 'gfedcba'.

Banked as the string must be modifiable.

Returns: Pointer to s

Concatenate Strings. Appends string s2 to the end of string s1

#### **Parameters**

s1	String to append onto
s2	String to copy from

For example 'abc' and 'def' will become 'abcdef'.

String  $\mathbf{s1}$  must be large enough to store both  $\mathbf{s1}$  and  $\mathbf{s2}$ .

Returns: Pointer to s1

# 20.22.2.8 strlen() int strlen ( const char \*s)

Calculates the length of a string

## **Parameters**

s String to calculate length of

Returns: Length of string not including the terminating '\0' character.

```
20.22.2.9 strncat() char* strncat (
char * s1,
const char * s2,
int <math>n)
```

Concatenate at most  $\bf n$  characters from string  $\bf s2$  onto the end of  $\bf s1$ .

## Parameters

s1	String to append onto
s2	String to copy from
n	Max number of characters to copy from s2

String s1 must be large enough to store both s1 and n characters of s2

Returns: Pointer to s1

```
20.22.2.10 strncmp() int strncmp (

const char * s1,

const char * s2,

int n)
```

Compare strings (at most **n** characters):

#### **Parameters**

s1	First string to compare
s2	Second string to compare
n	Max number of characters to compare

Returns zero if the strings are identical, or non-zero if they are not (see below). Returns:

- > 0 if s1 > s2 (at first non-matching byte)
- 0 if s1 == s2
- < 0 if **s1** < **s2** (at first non-matching byte)

```
20.22.2.11 strncpy() char* strncpy (
char * s1,
const char * s2,
int <math>n)
```

Copy n characters from string s2 to s1

## **Parameters**

s1	String to copy into
s2	String to copy from
n	Max number of characters to copy from s2

If s2 is shorter than n, the remaining bytes in s1 are filled with 0.

Warning: If there is no  $\0$  in the first n bytes of s2 then s1 will not be null terminated.

Returns: Pointer to s1

Compare up to count bytes in buffers buf1 and buf2

## **Parameters**

buf1	Pointer to First buffer to compare
buf2	Pointer to Second buffer to compare
count	Max number of bytes to compare

Returns zero if the buffers are identical, or non-zero if they are not (see below). Returns:

- > 0 if **buf1** > **buf2** (at first non-matching byte)
- 0 if buf1 == buf2
- < 0 if buf1 < buf2 (at first non-matching byte)</li>

### 20.22.3 Variable Documentation

```
20.22.3.1 c void c
```

## 20.23 gbdk-lib/include/asm/z80/string.h File Reference

```
#include <types.h>
```

### **Functions**

- char \* strcpy (char \*dest, const char \*src) OLDCALL
- int strcmp (const char \*s1, const char \*s2)
- void \* memcpy (void \*dest, const void \*src, size\_t len)
- void \* memmove (void \*dest, const void \*src, size t n) OLDCALL
- void \* memset (void \*s, int c, size\_t n) Z88DK\_CALLEE
- char \* reverse (char \*s) NONBANKED
- char \* strcat (char \*s1, const char \*s2) NONBANKED
- int strlen (const char \*s) OLDCALL
- char \* strncat (char \*s1, const char \*s2, int n) NONBANKED
- int strncmp (const char \*s1, const char \*s2, int n) NONBANKED
- char \* strncpy (char \*s1, const char \*s2, int n) NONBANKED
- int memcmp (const void \*buf1, const void \*buf2, size\_t count) Z88DK\_CALLEE

## 20.23.1 Detailed Description

Generic string functions.

## 20.23.2 Function Documentation

```
20.23.2.1 strcpy() char* strcpy ( char * dest, const char * src )
```

Copies the string pointed to by **src** (including the terminating '\0' character) to the array pointed to by **dest**. The strings may not overlap, and the destination string dest must be large enough to receive the copy.

## **Parameters**

dest	Array to copy into
src	Array to copy from

#### Returns

A pointer to dest

```
20.23.2.2 strcmp() int strcmp (
```

```
const char * s1,
const char * s2 )
```

## Compares strings

#### **Parameters**

s1	First string to compare
s2	Second string to compare

## Returns:

- $\, \cdot \, > 0 \ \text{if s1} > \text{s2} \,$
- 0 if s1 == s2
- ullet < 0 if s1 < s2

Copies n bytes from memory area src to memory area dest.

The memory areas may not overlap.

#### **Parameters**

dest	Buffer to copy into
src	Buffer to copy from
len	Number of Bytes to copy

Copies n bytes from memory area src to memory area dest, areas may overlap

Fills the memory region **s** with **n** bytes using value **c** 

## **Parameters**

s	Buffer to fill
С	char value to fill with (truncated from int)
n	Number of bytes to fill

```
20.23.2.6 reverse() char* reverse ( char * s)
```

Reverses the characters in a string

s Pointer to string to reverse.

For example 'abcdefg' will become 'gfedcba'.

Banked as the string must be modifiable.

Returns: Pointer to s

```
20.23.2.7 strcat() char* strcat ( char * s1, const char * s2)
```

Concatenate Strings. Appends string s2 to the end of string s1

#### **Parameters**

s1	String to append onto
s2	String to copy from

For example 'abc' and 'def' will become 'abcdef'.

String s1 must be large enough to store both s1 and s2.

Returns: Pointer to s1

```
20.23.2.8 strlen() int strlen ( const char *s)
```

Calculates the length of a string

### **Parameters**

s String to calculate length of

Returns: Length of string not including the terminating '\0' character.

```
20.23.2.9 strncat() char* strncat ( char * s1, const char * s2, int n)
```

Concatenate at most  ${\bf n}$  characters from string  ${\bf s2}$  onto the end of  ${\bf s1}$ .

#### **Parameters**

s1	String to append onto
s2	String to copy from
n	Max number of characters to copy from s2

String  ${\bf s1}$  must be large enough to store both  ${\bf s1}$  and  ${\bf n}$  characters of  ${\bf s2}$ 

Returns: Pointer to s1

```
20.23.2.10 strncmp() int strncmp ( const char * s1, const char * s2, int n)
```

Compare strings (at most n characters):

## **Parameters**

s1	First string to compare

s2	Second string to compare
n	Max number of characters to compare

## Returns:

- ullet > 0 if  ${f s1}$  >  ${f s2}$
- 0 if s1 == s2
- $\cdot$  < 0 if s1 < s2

```
20.23.2.11 strncpy() char* strncpy ( char * s1, const char * s2, int n)
```

Copy n characters from string s2 to s1

### **Parameters**

s1	String to copy into
s2	String to copy from
n	Max number of characters to copy from s2

If s2 is shorter than n, the remaining bytes in s1 are filled with  $\0$ .

Warning: If there is no \0 in the first **n** bytes of **s2** then **s1** will not be null terminated.

Returns: Pointer to s1

Compares buffers

#### **Parameters**

buf1	First buffer to compare
buf2	Second buffer to compare
count	Buffer length

## Returns:

- > 0 if buf1 > buf2
- 0 if buf1 == buf2
- < 0 if buf1 < buf2

## 20.24 gbdk-lib/include/string.h File Reference

#include <asm/sm83/string.h>

## 20.24.1 Detailed Description

Generic string functions.

## 20.25 gbdk-lib/include/asm/mos6502/types.h File Reference

#### **Macros**

• #define \_\_SIZE\_T\_DEFINED

## **Typedefs**

- typedef signed char INT8
- typedef unsigned char UINT8
- typedef signed int INT16
- typedef unsigned int UINT16
- typedef signed long INT32
- typedef unsigned long UINT32
- typedef unsigned int size\_t
- · typedef unsigned int clock\_t

## 20.25.1 Detailed Description

Types definitions for the gb.

#### 20.25.2 Macro Definition Documentation

```
20.25.2.1 __SIZE_T_DEFINED #define __SIZE_T_DEFINED
```

## 20.25.3 Typedef Documentation

```
20.25.3.1 INT8 typedef signed char INT8 Signed eight bit.
```

```
20.25.3.2 UINT8 typedef unsigned char UINT8 Unsigned eight bit.
```

```
20.25.3.3 INT16 typedef signed int INT16 Signed sixteen bit.
```

**20.25.3.4 UINT16** typedef unsigned int UINT16 Unsigned sixteen bit.

20.25.3.5 INT32 typedef signed long INT32 Signed 32 bit.

**20.25.3.6 UINT32** typedef unsigned long UINT32 Unsigned 32 bit.

 $\textbf{20.25.3.7} \quad \textbf{size\_t} \quad \texttt{typedef unsigned int size\_t}$ 

 $\begin{array}{lll} \textbf{20.25.3.8} & \textbf{clock\_t} & \texttt{typedef unsigned int clock\_t} \\ \textbf{Returned from clock} \end{array}$ 

See also

clock

## 20.26 gbdk-lib/include/asm/sm83/types.h File Reference

#### **Macros**

• #define \_\_SIZE\_T\_DEFINED

## **Typedefs**

- typedef signed char INT8
- typedef unsigned char UINT8
- typedef signed int INT16
- typedef unsigned int UINT16
- typedef signed long INT32
- typedef unsigned long UINT32
- typedef unsigned int size\_t
- · typedef unsigned int clock\_t

### 20.26.1 Detailed Description

Types definitions for the gb.

#### 20.26.2 Macro Definition Documentation

```
20.26.2.1 __SIZE_T_DEFINED #define __SIZE_T_DEFINED
```

## 20.26.3 Typedef Documentation

```
20.26.3.1 INT8 typedef signed char INT8 Signed eight bit.
```

```
20.26.3.2 UINT8 typedef unsigned char UINT8 Unsigned eight bit.
```

```
20.26.3.3 INT16 typedef signed int INT16 Signed sixteen bit.
```

**20.26.3.4 UINT16** typedef unsigned int UINT16 Unsigned sixteen bit.

20.26.3.5 INT32 typedef signed long INT32 Signed 32 bit.

20.26.3.6 UINT32 typedef unsigned long UINT32 Unsigned 32 bit.

 $\textbf{20.26.3.7} \quad \textbf{size\_t} \quad \texttt{typedef unsigned int size\_t}$ 

 $\begin{array}{lll} \textbf{20.26.3.8} & \textbf{clock\_t} & \texttt{typedef unsigned int clock\_t} \\ \textbf{Returned from clock} \end{array}$ 

See also

clock

## 20.27 gbdk-lib/include/asm/types.h File Reference

#include <asm/sm83/types.h>

### **Data Structures**

• union \_fixed

#### Macros

- #define OLDCALL
- #define PRESERVES\_REGS(...)
- #define NAKED
- #define SFR
- #define AT(A)
- #define NORETURN
- #define NONBANKED
- #define BANKED
- #define CRITICAL
- #define INTERRUPT

## **Typedefs**

- typedef INT8 BOOLEAN
- typedef INT8 BYTE
- typedef UINT8 UBYTE
- typedef INT16 WORD
- typedef UINT16 UWORD
- typedef INT32 LWORD
- typedef UINT32 ULWORD
- typedef INT32 DWORD
- typedef UINT32 UDWORD
- typedef union <u>\_fixed fixed</u>

## 20.27.1 Detailed Description

Shared types definitions.

### 20,27.2 Macro Definition Documentation

```
20.27.2.1 OLDCALL #define OLDCALL
```

 $\textbf{20.27.2.2} \quad \textbf{PRESERVES\_REGS} \quad \texttt{\#define PRESERVES\_REGS} \ ($ 

...)

20.27.2.3 NAKED #define NAKED

**20.27.2.4 SFR** #define SFR

```
20.27.2.5 AT #define AT( A )
```

20.27.2.6 NORETURN #define NORETURN

20.27.2.7 NONBANKED #define NONBANKED

20.27.2.8 BANKED #define BANKED

20.27.2.9 CRITICAL #define CRITICAL

20.27.2.10 INTERRUPT #define INTERRUPT

20.27.3 Typedef Documentation

**20.27.3.1 BOOLEAN** typedef INT8 BOOLEAN TRUE or FALSE.

**20.27.3.2 BYTE** typedef INT8 BYTE Signed 8 bit.

**20.27.3.3 UBYTE** typedef UINT8 UBYTE Unsigned 8 bit.

**20.27.3.4 WORD** typedef INT16 WORD Signed 16 bit

**20.27.3.5 UWORD** typedef UINT16 UWORD Unsigned 16 bit

**20.27.3.6 LWORD** typedef INT32 LWORD Signed 32 bit

**20.27.3.7 ULWORD** typedef UINT32 ULWORD Unsigned 32 bit

**20.27.3.8 DWORD** typedef INT32 DWORD Signed 32 bit

**20.27.3.9 UDWORD** typedef UINT32 UDWORD Unsigned 32 bit

**20.27.3.10 fixed** typedef union \_fixed fixed Useful definition for working with 8 bit + 8 bit fixed point values Use . w to access the variable as unsigned 16 bit type.

Use .b.h and .b.1 (or just .h and .1) to directly access it's high and low unsigned 8 bit values.

## 20.28 gbdk-lib/include/asm/z80/types.h File Reference

#### Macros

- #define Z88DK CALLEE
- #define Z88DK FASTCALL
- #define \_\_SIZE\_T\_DEFINED

## **Typedefs**

- typedef signed char INT8
- typedef unsigned char UINT8
- typedef signed int INT16
- typedef unsigned int UINT16
- typedef signed long INT32
- typedef unsigned long UINT32
- typedef unsigned int size\_t
- typedef unsigned int clock\_t

## 20.28.1 Detailed Description

Types definitions for the gb.

#### 20.28.2 Macro Definition Documentation

```
20.28.2.1 Z88DK_CALLEE #define Z88DK_CALLEE
```

20.28.2.2 Z88DK\_FASTCALL #define Z88DK\_FASTCALL

20.28.2.3 \_\_SIZE\_T\_DEFINED #define \_\_SIZE\_T\_DEFINED

## 20.28.3 Typedef Documentation

**20.28.3.1 INT8** typedef signed char INT8 Signed eight bit.

20.28.3.2 **UINT8** typedef unsigned char UINT8 Unsigned eight bit.

**20.28.3.3 INT16** typedef signed int INT16 Signed sixteen bit.

**20.28.3.4 UINT16** typedef unsigned int UINT16 Unsigned sixteen bit.

**20.28.3.5 INT32** typedef signed long INT32 Signed 32 bit.

 ${f 20.28.3.6}$  UINT32 typedef unsigned long UINT32 Unsigned 32 bit.

```
20.28.3.7 size_t typedef unsigned int size_t
20.28.3.8 clock_t typedef unsigned int clock_t
Returned from clock
See also
    clock
```

## 20.29 gbdk-lib/include/types.h File Reference

```
#include <asm/types.h>
```

#### Macros

- #define NULL 0
- #define FALSE 0
- #define TRUE 1

#### **Typedefs**

typedef void \* POINTER

## 20.29.1 Detailed Description

Basic types.

Directly include the port specific file.

## 20.29.2 Macro Definition Documentation

```
20.29.2.1 NULL #define NULL 0 Good 'ol NULL.

20.29.2.2 FALSE #define FALSE 0 A 'false' value.

20.29.2.3 TRUE #define TRUE 1 A 'true' value.
```

## 20.29.3 Typedef Documentation

```
20.29.3.1 POINTER typedef void* POINTER No longer used.
```

## 20.30 gbdk-lib/include/assert.h File Reference

#### **Macros**

```
    #define assert(x) ((x) ? (void)0 : __assert(#x, __func__, __FILE__, __LINE__))
```

#### **Functions**

• void \_\_assert (const char \*expression, const char \*functionname, const char \*filename, unsigned int linenumber)

### 20.30.1 Macro Definition Documentation

#### 20.30.2 Function Documentation

## 20.31 gbdk-lib/include/ctype.h File Reference

```
#include <types.h>
#include <stdbool.h>
```

### **Functions**

- bool isalpha (char c)
- bool isupper (char c)
- bool islower (char c)
- bool isdigit (char c)
- bool isspace (char c)
- char toupper (char c)
- char tolower (char c)

## 20.31.1 Detailed Description

Character type functions.

## 20.31.2 Function Documentation

```
20.31.2.1 isalpha() bool isalpha ( \operatorname{char} c )
```

Returns TRUE if the character **c** is a letter (a-z, A-Z), otherwise FALSE

#### **Parameters**

c Character to test

```
20.31.2.2 isupper() bool isupper ( char c )
```

Returns TRUE if the character  ${\bf c}$  is an uppercase letter (A-Z), otherwise FALSE

## Parameters

c Character to test

```
20.31.2.3 islower() bool islower ( \operatorname{char} c )
```

Returns TRUE if the character **c** is a lowercase letter (a-z), otherwise FALSE

#### **Parameters**

c Character to test

## **20.31.2.4 isdigit()** bool isdigit ( char c )

Returns TRUE if the character c is a digit (0-9), otherwise FALSE

### **Parameters**

c Character to test

## **20.31.2.5 isspace()** bool isspace ( char c )

Returns TRUE if the character c is a space (' '), tab (\t), or newline (\n) character, otherwise FALSE

#### **Parameters**

c Character to test

# **20.31.2.6 toupper()** char toupper ( char c )

Returns uppercase version of character **c** if it is a letter (a-z), otherwise it returns the input value unchanged.

### **Parameters**

c Character to test

## 20.31.2.7 tolower() char tolower (

Returns lowercase version of character **c** if it is a letter (A-Z), otherwise it returns the input value unchanged.

## **Parameters**

c Character to test

## 20.32 gbdk-lib/include/gb/bcd.h File Reference

```
#include <types.h>
#include <stdint.h>
```

#### **Macros**

- #define BCD\_HEX(v) ((BCD)(v))
- #define MAKE\_BCD(v) BCD\_HEX(0x ## v)

## **Typedefs**

typedef uint32\_t BCD

#### **Functions**

- void uint2bcd (uint16\_t i, BCD \*value) OLDCALL
- void bcd\_add (BCD \*sour, const BCD \*value) OLDCALL
- void bcd\_sub (BCD \*sour, const BCD \*value) OLDCALL
- uint8\_t bcd2text (const BCD \*bcd, uint8\_t tile\_offset, uint8\_t \*buffer) OLDCALL

## 20.32.1 Detailed Description

Support for working with BCD (Binary Coded Decimal) See the example BCD project for additional details.

### 20.32.2 Macro Definition Documentation

```
20.32.2.1 BCD_HEX #define BCD_HEX( v ) ((BCD)(v))
```

```
20.32.2.2 MAKE_BCD #define MAKE_BCD( v ) BCD_HEX(0x ## v)
```

Converts an integer value into BCD format A maximum of 8 digits may be used

## 20.32.3 Typedef Documentation

```
20.32.3.1 BCD typedef uint32_t BCD
```

### 20.32.4 Function Documentation

```
20.32.4.1 uint2bcd() void uint2bcd ( uint16_t i, BCD * value )
```

Converts integer i into BCD format (Binary Coded Decimal)

#### **Parameters**

i	Numeric value to convert
value	Pointer to a BCD variable to store the converted result

```
20.32.4.2 bcd_add() void bcd_add ( BCD * sour,
```

```
const BCD * value )
```

Adds two numbers in BCD format: sour += value

#### **Parameters**

sour	Pointer to a BCD value to add to (and where the result is stored)
value	Pointer to the BCD value to add to <b>sour</b>

```
20.32.4.3 bcd_sub() void bcd_sub (

BCD * sour,

const BCD * value )
```

Subtracts two numbers in BCD format: sour -= value

#### **Parameters**

sour	Pointer to a BCD value to subtract from (and where the result is stored)
value	Pointer to the BCD value to subtract from <b>sour</b>

Convert a BCD number into an asciiz (null terminated) string and return the length

## **Parameters**

bcd	Pointer to BCD value to convert
tile_offset	Optional per-character offset value to add (use 0 for none)
buffer	Buffer to store the result in

Returns: Length in characters (always 8)

**buffer** should be large enough to store the converted string (9 bytes: 8 characters + 1 for terminator) There are a couple different ways to use **tile\_offset**. For example:

- It can be the Index of the Font Tile '0' in VRAM to allow the buffer to be used directly with set\_bkg\_tiles.
- It can also be set to the ascii value for character '0' so that the buffer is a normal string that can be passed to printf.

## 20.33 gbdk-lib/include/gbdk/bcd.h File Reference

```
#include <gb/bcd.h>
```

## 20.34 gbdk-lib/include/sms/bcd.h File Reference

```
#include <types.h>
#include <stdint.h>
```

## **Macros**

- #define BCD\_HEX(v) ((BCD)(v))
- #define MAKE\_BCD(v) BCD\_HEX(0x ## v)

## **Typedefs**

• typedef uint32\_t BCD

### **Functions**

- void uint2bcd (uint16\_t i, BCD \*value)
- void bcd\_add (BCD \*sour, const BCD \*value)
- void bcd\_sub (BCD \*sour, const BCD \*value)
- uint8 t bcd2text (const BCD \*bcd, uint8 t tile offset, uint8 t \*buffer)

## 20.34.1 Detailed Description

Support for working with BCD (Binary Coded Decimal) See the example BCD project for additional details.

#### 20.34.2 Macro Definition Documentation

```
20.34.2.2 MAKE_BCD #define MAKE_BCD( v ) BCD_HEX(0x ## v)
```

Converts an integer value into BCD format A maximum of 8 digits may be used

## 20.34.3 Typedef Documentation

```
20.34.3.1 BCD typedef uint32_t BCD
```

## 20.34.4 Function Documentation

Converts integer i into BCD format (Binary Coded Decimal)

### **Parameters**

i	Numeric value to convert
value	Pointer to a BCD variable to store the converted result

```
20.34.4.2 bcd_add() void bcd_add ( BCD * sour, const BCD * value)
```

Adds two numbers in BCD format: sour += value

sour	Pointer to a BCD value to add to (and where the result is stored)
value	Pointer to the BCD value to add to <b>sour</b>

Subtracts two numbers in BCD format: sour -= value

#### **Parameters**

sour	Pointer to a BCD value to subtract from (and where the result is stored)
value	Pointer to the BCD value to subtract from <b>sour</b>

Convert a BCD number into an asciiz (null terminated) string and return the length

#### **Parameters**

bcd	Pointer to BCD value to convert
tile_offset	Optional per-character offset value to add (use 0 for none)
buffer	Buffer to store the result in

Returns: Length in characters (always 8)

**buffer** should be large enough to store the converted string (9 bytes: 8 characters + 1 for terminator) There are a couple different ways to use **tile\_offset**. For example:

- It can be the Index of the Font Tile '0' in VRAM to allow the buffer to be used directly with set\_bkg\_tiles.
- It can also be set to the ascii value for character '0' so that the buffer is a normal string that can be passed to printf.

## 20.35 gbdk-lib/include/gb/bgb emu.h File Reference

```
#include <gbdk/emu_debug.h>
```

## 20.35.1 Detailed Description

Shim for legacy use of bgb\_emu.h which has been migrated to emu\_debug.h See the <code>emu\_debug</code> example project included with gbdk.

## 20.36 gbdk-lib/include/gb/cgb.h File Reference

```
#include <types.h>
#include <stdint.h>
```

#### **Macros**

- #define RGB(r, g, b) ((uint16\_t)((((b) & 0x1f) << 10) | ((uint16\_t)(((g) & 0x1f) << 5)) | ((r) & 0x1f)))</li>
- #define RGB8(r, g, b) (((uint16\_t)((((b) >> 3) & 0x1f) << 10)) | ((uint16\_t)((((g) >> 3) & 0x1f) << 5)) | (((r) >> 3) & 0x1f))
- #define RGBHTML(RGB24bit) (RGB8((((RGB24bit) >> 16) & 0xff), (((RGB24bit) >> 8) & 0xff), ((RGB24bit) 
   & 0xff)))
- #define RGB RED RGB(31, 0, 0)
- #define RGB DARKRED RGB(15, 0, 0)
- #define RGB GREEN RGB( 0, 31, 0)
- #define RGB DARKGREEN RGB( 0, 15, 0)
- #define RGB\_BLUE RGB( 0, 0, 31)
- #define RGB\_DARKBLUE RGB( 0, 0, 15)
- #define RGB YELLOW RGB(31, 31, 0)
- #define RGB DARKYELLOW RGB(21, 21, 0)
- #define RGB\_CYAN RGB( 0, 31, 31)
- #define RGB\_AQUA RGB(28, 5, 22)
- #define RGB PINK RGB(31, 0, 31)
- #define RGB\_PURPLE RGB(21, 0, 21)
- #define RGB BLACK RGB(0,0,0)
- #define RGB DARKGRAY RGB(10, 10, 10)
- #define RGB\_LIGHTGRAY RGB(21, 21, 21)
- #define RGB WHITE RGB(31, 31, 31)
- #define RGB LIGHTFLESH RGB(30, 20, 15)
- #define RGB\_BROWN RGB(10, 10, 0)
- #define RGB ORANGE RGB(30, 20, 0)
- #define RGB\_TEAL RGB(15, 15, 0)

## **Typedefs**

· typedef uint16 t palette color t

### **Functions**

- void set bkg palette (uint8 t first palette, uint8 t nb palettes, const palette color t \*rgb data) OLDCALL
- void set sprite palette (uint8 t first palette, uint8 t nb palettes, const palette color t \*rgb data) OLDCALL
- void set\_bkg\_palette\_entry (uint8\_t palette, uint8\_t entry, uint16\_t rgb\_data) OLDCALL
- void set\_sprite\_palette\_entry (uint8\_t palette, uint8\_t entry, uint16\_t rgb\_data) OLDCALL
- void cpu slow (void)
- void cpu\_fast (void)
- · void set default palette (void)
- · void cgb compatibility (void)

### 20.36.1 Detailed Description

Support for the Color GameBoy (CGB).

## **Enabling CGB features**

To unlock and use CGB features and registers you need to change byte 0143h in the cartridge header. Otherwise, the CGB will operate in monochrome "Non CGB" compatibility mode.

- Use a value of 80h for games that support CGB and monochrome gameboys (with Lcc: -Wm-yc, or makebin directly: -yc)
- Use a value of C0h for CGB only games.
   (with Lcc: -Wm-yC, or makebin directly: -yC)

See the Pan Docs for more information CGB features.

#### 20.36.2 Macro Definition Documentation

Macro to create a CGB palette color entry out of 5-bit color components.

#### **Parameters**

r	5-bit Red Component, range 0 - 31 (31 brightest)
g	5-bit Green Component, range 0 - 31 (31 brightest)
b	5-bit Blue Component, range 0 - 31 (31 brightest)

The resulting format is bitpacked BGR-555 in a uint16\_t.

#### See also

```
set_bkg_palette(), set_sprite_palette(), RGB8(), RGBHTML()
```

Macro to create a CGB palette color entry out of 8-bit color components.

#### **Parameters**

r	8-bit Red Component, range 0 - 255 (255 brightest)
g	8-bit Green Component, range 0 - 255 (255 brightest)
b	8-bit Blue Component, range 0 - 255 (255 brightest)

The resulting format is bitpacked BGR-555 in a uint16\_t.

The lowest 3 bits of each color component are dropped during conversion.

#### See also

```
set_bkg_palette(), set_sprite_palette(), RGB(), RGBHTML()
```

```
20.36.2.3 RGBHTML #define RGBHTML(  RGB24bit \ ) \ (RGB8 (((RGB24bit) >> 16) \& 0xff), (((RGB24bit) >> 8) \& 0xff), ((RGB24bit) & 0xff)))
```

Macro to convert a 24 Bit RGB color to a CGB palette color entry.

### **Parameters**

```
RGB24bit Bit packed RGB-888 color (0-255 for each color component).
```

The resulting format is bitpacked BGR-555 in a uint16 t.

The lowest 3 bits of each color component are dropped during conversion.

```
See also
```

```
set_bkg_palette(), set_sprite_palette(), RGB(), RGB8()
```

```
20.36.2.4 RGB_RED #define RGB_RED RGB(31, 0, 0)
Common colors based on the EGA default palette.
20.36.2.5 RGB_DARKRED #define RGB_DARKRED RGB(15, 0, 0)
20.36.2.6 RGB_GREEN #define RGB_GREEN RGB( 0, 31, 0)
20.36.2.7 RGB_DARKGREEN #define RGB_DARKGREEN RGB( 0, 15, 0)
20.36.2.8 RGB_BLUE #define RGB_BLUE RGB( 0, 0, 31)
20.36.2.9 RGB_DARKBLUE #define RGB_DARKBLUE RGB( 0, 0, 15)
20.36.2.10 RGB_YELLOW #define RGB_YELLOW RGB(31, 31, 0)
20.36.2.11 RGB_DARKYELLOW #define RGB_DARKYELLOW RGB(21, 21, 0)
20.36.2.12 RGB_CYAN #define RGB_CYAN RGB( 0, 31, 31)
20.36.2.13 RGB_AQUA #define RGB_AQUA RGB(28, 5, 22)
20.36.2.14 RGB PINK #define RGB_PINK RGB(31, 0, 31)
20.36.2.15 RGB_PURPLE #define RGB_PURPLE RGB(21, 0, 21)
20.36.2.16 RGB_BLACK #define RGB_BLACK RGB( 0, 0, 0)
20.36.2.17 RGB_DARKGRAY #define RGB_DARKGRAY RGB(10, 10, 10)
20.36.2.18 RGB_LIGHTGRAY #define RGB_LIGHTGRAY RGB(21, 21, 21)
20.36.2.19 RGB_WHITE #define RGB_WHITE RGB(31, 31, 31)
```

```
20.36.2.20 RGB_LIGHTFLESH #define RGB_LIGHTFLESH RGB(30, 20, 15)

20.36.2.21 RGB_BROWN #define RGB_BROWN RGB(10, 10, 0)

20.36.2.22 RGB_ORANGE #define RGB_ORANGE RGB(30, 20, 0)

20.36.2.23 RGB_TEAL #define RGB_TEAL RGB(15, 15, 0)

20.36.3 Typedef Documentation

20.36.3.1 palette_color_t typedef uint16_t palette_color_t
16 bit color entry

20.36.4 Function Documentation
```

first_palette	Index of the first palette to write (0-7)
nb_palettes	Number of palettes to write (1-8, max depends on first_palette)
rgb_data	Pointer to source palette data

Writes nb\_palettes to background palette data starting at first\_palette, Palette data is sourced from rgb\_data.

- Each Palette is 8 bytes in size: 4 colors x 2 bytes per palette color entry.
- Each color (4 per palette) is packed as BGR-555 format (1:5:5:5, MSBit [15] is unused).
- Each component (R, G, B) may have values from 0 31 (5 bits), 31 is brightest.

## See also

```
RGB(), set_bkg_palette_entry()

BKGF_CGB_PAL0, BKGF_CGB_PAL1, BKGF_CGB_PAL2, BKGF_CGB_PAL3

BKGF_CGB_PAL4, BKGF_CGB_PAL5, BKGF_CGB_PAL6, BKGF_CGB_PAL7
```

first_palette	Index of the first palette to write (0-7)
nb_palettes	Number of palettes to write (1-8, max depends on first_palette)
rgb_data	Pointer to source palette data

Writes **nb** palettes to sprite palette data starting at **first** palette, Palette data is sourced from **rgb** data.

- Each Palette is 8 bytes in size: 4 colors x 2 bytes per palette color entry.
- Each color (4 per palette) is packed as BGR-555 format (1:5:5:5, MSBit [15] is unused).
- Each component (R, G, B) may have values from 0 31 (5 bits), 31 is brightest.

#### See also

```
RGB(), set_sprite_palette_entry()

OAMF_CGB_PAL0, OAMF_CGB_PAL1, OAMF_CGB_PAL2, OAMF_CGB_PAL3

OAMF_CGB_PAL4, OAMF_CGB_PAL5, OAMF_CGB_PAL6, OAMF_CGB_PAL7
```

Sets a single color in the specified CGB background palette.

### **Parameters**

palette	Index of the palette to modify (0-7)
entry	Index of color in palette to modify (0-3)
rgb_data	New color data in BGR 15bpp format.

## See also

```
set_bkg_palette(), RGB()

BKGF_CGB_PAL0, BKGF_CGB_PAL1, BKGF_CGB_PAL2, BKGF_CGB_PAL3

BKGF_CGB_PAL4, BKGF_CGB_PAL5, BKGF_CGB_PAL6, BKGF_CGB_PAL7
```

Sets a single color in the specified CGB sprite palette.

#### **Parameters**

palette	Index of the palette to modify (0-7)
entry	Index of color in palette to modify (0-3)
rgb_data	New color data in BGR 15bpp format.

See also

```
set_sprite_palette(), RGB()
OAMF_CGB_PAL0, OAMF_CGB_PAL1, OAMF_CGB_PAL2, OAMF_CGB_PAL3
OAMF_CGB_PAL4, OAMF_CGB_PAL5, OAMF_CGB_PAL6, OAMF_CGB_PAL7
```

```
20.36.4.5 cpu_slow() void cpu_slow (
```

Set CPU speed to slow (Normal Speed) operation.

Interrupts are temporarily disabled and then re-enabled during this call.

In this mode the CGB operates at the same speed as the DMG/Pocket/SGB models.

You can check to see if <u>cpu</u> == <u>CGB\_TYPE</u> before using this function.

See also

cpu fast()

```
20.36.4.6 cpu_fast() void cpu_fast ( void ) [inline]
```

Set CPU speed to fast (CGB Double Speed) operation.

On startup the CGB operates in Normal Speed Mode and can be switched into Double speed mode (faster processing but also higher power consumption). See the Pan Docs for more information about which hardware features operate faster and which remain at Normal Speed.

- · Interrupts are temporarily disabled and then re-enabled during this call.
- You can check to see if \_cpu == CGB\_TYPE before using this function.

See also

```
cpu_slow(), _cpu
```

Sets CGB palette 0 to be compatible with the DMG/GBP.

The default/first CGB palettes for sprites and backgrounds are set to a similar default appearance as on the DMG/← Pocket/SGB models. (White, Light Gray, Dark Gray, Black)

• You can check to see if \_cpu == CGB\_TYPE before using this function.

Obsolete. This function has been replaced by set\_default\_palette(), which has identical behavior.

## 20.37 gbdk-lib/include/gb/crash\_handler.h File Reference

## **Functions**

void <u>HandleCrash</u> (void)

## 20.37.1 Detailed Description

When crash\_handler.h is included, a crash dump screen will be displayed if the CPU executes uninitalized memory (with a value of 0xFF, the opcode for RST 38). A handler is installed for RST 38 that calls \_\_HandleCrash(). #include <gb/>
gb/crash\_handler.h>

Also see the crash example project included with gbdk.

#### 20.37.2 Function Documentation

```
20.37.2.1 __HandleCrash() void __HandleCrash (
```

Display the crash dump screen.

See the intro for this file for more details.

## 20.38 gbdk-lib/include/gb/drawing.h File Reference

```
#include <types.h>
#include <stdint.h>
```

#### **Macros**

- #define GRAPHICS\_WIDTH 160
- #define GRAPHICS HEIGHT 144
- #define SOLID 0x00 /\* Overwrites the existing pixels \*/
- #define OR 0x01 /\* Performs a logical OR \*/
- #define XOR 0x02 /\* Performs a logical XOR \*/
- #define AND 0x03 /\* Performs a logical AND \*/
- #define WHITE 0
- #define LTGREY 1
- #define DKGREY 2
- #define BLACK 3
- #define M NOFILL 0
- #define M FILL 1
- #define SIGNED 1
- #define UNSIGNED 0

## **Functions**

- void gprint (char \*str) NONBANKED
- void gprintln (int16\_t number, int8\_t radix, int8\_t signed\_value) NONBANKED
- void gprintn (int8\_t number, int8\_t radix, int8\_t signed\_value) NONBANKED
- int8 t gprintf (char \*fmt,...) NONBANKED
- · void plot (uint8 t x, uint8 t y, uint8 t colour, uint8 t mode) OLDCALL
- void plot\_point (uint8\_t x, uint8\_t y) OLDCALL
- void switch\_data (uint8\_t x, uint8\_t y, uint8\_t \*src, uint8\_t \*dst) OLDCALL
- void draw\_image (uint8\_t \*data)
- void line (uint8\_t x1, uint8\_t y1, uint8\_t x2, uint8\_t y2) OLDCALL
- void box (uint8 t x1, uint8 t y1, uint8 t x2, uint8 t y2, uint8 t style) OLDCALL
- void circle (uint8\_t x, uint8\_t y, uint8\_t radius, uint8\_t style) OLDCALL
- uint8\_t getpix (uint8\_t x, uint8\_t y) OLDCALL
- · void wrtchr (char chr) OLDCALL
- void gotogxy (uint8\_t x, uint8\_t y) OLDCALL
- void color (uint8\_t forecolor, uint8\_t backcolor, uint8\_t mode) OLDCALL

## 20.38.1 Detailed Description

All Points Addressable (APA) mode drawing library.

Drawing routines originally by Pascal Felber Legendary overhall by Jon Fuge : com/jf1452 Commenting by Michael Hope

Note: The standard text printf() and putchar() cannot be used in APA mode - use gprintf() and wrtchr() instead.

Note: Using drawing.h will cause it's custom VBL and LCD ISRs (drawing\_vbl and drawing\_lcd) to be installed. Changing the mode (mode (M\_TEXT\_OUT);) will cause them to be de-installed.

The valid coordinate ranges are from (x,y) 0,0 to 159,143. There is no built-in clipping, so drawing outside valid coordinates will likely produce undesired results (wrapping/etc). Important note for the drawing API:

The Game Boy graphics hardware is not well suited to frame-buffer style graphics such as the kind provided in drawing.h. Due to that, most drawing functions (rectangles, circles, etc) will be slow. When possible it's much faster and more efficient to work with the tiles and tile maps that the Game Boy hardware is built around.

#### 20.38.2 Macro Definition Documentation

```
20.38.2.1 GRAPHICS_WIDTH #define GRAPHICS_WIDTH 160
Size of the screen in pixels
20.38.2.2 GRAPHICS_HEIGHT #define GRAPHICS_HEIGHT 144
20.38.2.3 SOLID #define SOLID 0x00 / * Overwrites the existing pixels */
20.38.2.4 OR #define OR 0 \times 01 /* Performs a logical OR */
20.38.2.5 XOR #define XOR 0x02 /* Performs a logical XOR */
20.38.2.6 AND #define AND 0x03 /* Performs a logical AND */
20.38.2.7 WHITE #define WHITE 0
Possible drawing colours
20.38.2.8 LTGREY #define LTGREY 1
20.38.2.9 DKGREY #define DKGREY 2
20.38.2.10 BLACK #define BLACK 3
20.38.2.11 M_NOFILL #define M_NOFILL 0
Possible fill styles for box() and circle()
```

**20.38.2.12 M FILL** #define M\_FILL 1

```
20.38.2.13 SIGNED #define SIGNED 1
```

Possible values for signed\_value in <a href="mailto:gprintln">gprintln()</a> and <a href="mailto:gprintln">gprintln()</a> and <a href="mailto:gprintln">gprintln()</a>

```
20.38.2.14 UNSIGNED #define UNSIGNED 0
```

### 20.38.3 Function Documentation

```
20.38.3.1 gprint() void gprint ( char * str)
```

Print the string 'str' with no interpretation

See also

gotogxy()

Print 16 bit number in radix (base) in the default font at the current text position.

#### **Parameters**

number	number to print
radix	radix (base) to print with
signed_value	should be set to SIGNED or UNSIGNED depending on whether the number is signed or not

The current position is advanced by the numer of characters printed.

See also

gotogxy()

Print 8 bit **number** in **radix** (base) in the default font at the current text position.

See also

```
gprintln(), gotogxy()
```

Print the string and arguments given by fmt with arguments \_\_...\_

## **Parameters**

fmt	The format string as per printf
	params

Currently supported:

- · %c (character)
- %u (int)
- %d (int8\_t)
- %o (int8\_t as octal)
- %x (int8\_t as hex)
- · %s (string)

#### Returns

Returns the number of items printed, or -1 if there was an error.

See also

```
gotogxy()
```

Plot a point in the current drawing mode and colour at x,y

Exchanges the tile on screen at x,y with the tile pointed by src, original tile is saved in dst. Both src and dst may be NULL - saving or copying to screen is not performed in this case.

```
20.38.3.8 draw_image() void draw_image ( uint8_t * data)
```

Draw a full screen image at data

Draw a line in the current drawing mode and colour from x1,y1 to x2,y2

Draw a box (rectangle) with corners x1,y1 and x2,y2 using fill mode style (one of NOFILL or FILL)

Draw a circle with centre at x,y and radius using fill mode style (one of NOFILL or FILL)

```
20.38.3.12 getpix() uint8_t getpix ( uint8_t x, uint8_t y)
```

Returns the current colour of the pixel at x,y

```
20.38.3.13 wrtchr() void wrtchr ( char chr)
```

Prints the character **chr** in the default font at the current text position.

The current position is advanced by 1 after the character is printed.

See also

gotogxy()

```
20.38.3.14 gotogxy() void gotogxy ( uint8_t x, uint8_t y )
```

Sets the current text position to **x**,**y**.

Note: x and y have units of tiles (8 pixels per unit)

See also

wrtchr()

Set the current forecolor colour, backcolor colour, and draw mode

#### **Parameters**

forecolor	The primary drawing color (outlines of rectangles with box(), letter color with gprintf(), etc).
backcolor	Secondary or background color where applicable (fill color of rectangles with box() when M_FILL is specifed, background color of text with gprintf(), etc).
mode	Drawing style to use. Several settings are available SOLID, OR, XOR, AND.

In order to completely overwrite existing pixels use SOLID for mode

# 20.39 gbdk-lib/include/gb/emu\_debug.h File Reference

```
#include <gbdk/emu_debug.h>
```

# 20.39.1 Detailed Description

Shim for legacy use of gb/emu\_debug.h which has been migrated to gbdk/emu\_debug.h See the <code>emu\_debug</code> example project included with gbdk.

# 20.40 gbdk-lib/include/gbdk/emu\_debug.h File Reference

#include <types.h>

#### Macros

- #define EMU\_MESSAGE(message\_text) EMU\_MESSAGE1(EMU\_MACRONAME(\_\_LINE\_\_), message\_
   text)
- #define BGB\_MESSAGE(message\_text) EMU\_MESSAGE(message\_text)
- #define EMU PROFILE BEGIN(MSG) EMU MESSAGE SUFFIX(MSG, "%ZEROCLKS%");
- #define BGB PROFILE BEGIN(MSG) EMU PROFILE BEGIN(MSG)
- #define EMU PROFILE END(MSG) EMU MESSAGE SUFFIX(MSG, "%-8+LASTCLKS%");
- #define BGB\_PROFILE\_END(MSG) EMU\_PROFILE\_END(MSG)
- #define EMU\_TEXT(MSG) EMU\_MESSAGE(MSG)
- #define BGB\_TEXT(MSG) EMU\_TEXT(MSG)
- #define BGB\_profiler\_message EMU\_profiler\_message()
- #define BGB\_printf(...) EMU\_printf(\_\_VA\_ARGS\_\_)
- #define EMU BREAKPOINT asm ("ld b, b");
- #define BGB\_BREAKPOINT EMU\_BREAKPOINT

#### **Functions**

- void EMU\_profiler\_message (void)
- void EMU printf (const char \*format,...) PRESERVES REGS(a
- void EMU fmtbuf (const unsigned char \*format, void \*data) PRESERVES REGS(a

#### **Variables**

- void b
- void c

#### 20.40.1 Detailed Description

Debug window logging and profiling support for emulators (BGB, Emulicious, etc).

Also see the emu\_debug example project included with gbdk.

See the BGB Manual for more information ("expressions, breakpoint conditions, and debug messages") http
∴//bgb.bircd.org/manual.html#expressions

#### 20.40.2 Macro Definition Documentation

# ${\bf 20.40.2.1} \quad {\bf EMU\_MESSAGE} \quad {\tt \#define} \ {\tt EMU\_MESSAGE} \ ($

message\_text ) EMU\_MESSAGE1(EMU\_MACRONAME(\_\_LINE\_\_), message\_text)

Macro to display a message in the emulator debug message window

#### **Parameters**

message\_text | Quoted text string to display in the debug message window

The following special parameters can be used when bracketed with "%" characters.

- CPU registers: AF, BC, DE, HL, SP, PC, B, C, D, E, H, L, A, ZERO, ZF, Z, CARRY, CY, IME, ALLREGS
- Other state values: ROMBANK, XRAMBANK, SRAMBANK, WRAMBANK, VRAMBANK, TOTALCLKS, LAST-CLKS, CLKS2VBLANK

Example: print a message along with the currently active ROM bank.

```
EMU_MESSAGE("Current ROM Bank is: %ROMBANK%");
```

See the BGB Manual for more information ("expressions, breakpoint conditions, and debug messages")  $http \leftarrow ://bgb.bircd.org/manual.html#expressions$ 

See also

EMU PROFILE BEGIN(), EMU PROFILE END()

```
20.40.2.3 EMU PROFILE BEGIN #define EMU_PROFILE_BEGIN(
```

MSG ) EMU\_MESSAGE\_SUFFIX(MSG, "%ZEROCLKS%");

Macro to **Start** a profiling block for the emulator (BGB, Emulicious, etc)

**Parameters** 

MSG | Quoted text string to display in the debug message window along with the result

To complete the profiling block and print the result call EMU PROFILE END.

See also

EMU PROFILE END(), EMU MESSAGE()

```
20.40.2.4 BGB_PROFILE_BEGIN #define BGB_PROFILE_BEGIN(

MSG) EMU_PROFILE_BEGIN(MSG)
```

```
20.40.2.5 EMU_PROFILE_END #define EMU_PROFILE_END(

MSG) EMU_MESSAGE_SUFFIX(MSG, "%-8+LASTCLKS%");
```

Macro to End a profiling block and print the results in the emulator debug message window

**Parameters** 

MSG Quoted text string to display in the debug message window along with the result

This should only be called after a previous call to EMU\_PROFILE\_BEGIN()

The results are in Emulator clock units, which are "1 nop in [CGB] doublespeed mode".

So when running in Normal Speed mode (i.e. non-CGB doublespeed) the printed result should be **divided by 2** to get the actual ellapsed cycle count.

If running in CB Double Speed mode use the below call instead, it correctly compensates for the speed difference. In this scenario, the result does **not need to be divided by 2** to get the ellapsed cycle count.

EMU\_MESSAGE("NOP TIME: %-4+LASTCLKS%");

See also

EMU\_PROFILE\_BEGIN(), EMU\_MESSAGE()

```
20.40.2.6 BGB_PROFILE_END #define BGB_PROFILE_END(

MSG) EMU_PROFILE_END(MSG)
```

```
20.40.2.7 EMU_TEXT #define EMU_TEXT(
                MSG ) EMU_MESSAGE(MSG)
20.40.2.8 BGB TEXT #define BGB_TEXT(
                MSG ) EMU_TEXT (MSG)
20.40.2.9 BGB_profiler_message #define BGB_profiler_message EMU_profiler_message()
\textbf{20.40.2.10} \quad \textbf{BGB\_printf} \quad \texttt{\#define BGB\_printf(}
                ... ) EMU_printf(__VA_ARGS__)
\textbf{20.40.2.11} \quad \textbf{EMU\_BREAKPOINT} \quad \texttt{\#define EMU\_BREAKPOINT } \underline{\quad} \texttt{asm\_\_("ld b, b");}
The Emulator will break into debugger when encounters this line
20.40.2.12 BGB_BREAKPOINT #define BGB_BREAKPOINT EMU_BREAKPOINT
20.40.3 Function Documentation
20.40.3.1 EMU_profiler_message() void EMU_profiler_message (
Display preset debug information in the Emulator debug messages window.
This function is equivalent to:
EMU_MESSAGE("PROFILE,%(SP+$0)%,%(SP+$1)%,%A%,%TOTALCLKS%,%ROMBANK%,%WRAMBANK%");
20.40.3.2 EMU_printf() void EMU_printf (
               const char * format,
Print the string and arguments given by format to the emulator debug message window
```

## **Parameters**

	format	The format string as per printf
--	--------	---------------------------------

Does not return the number of characters printed. Currently supported:

- %hx (char as hex)
- · %hu (unsigned char)
- · %hd (signed char)
- · %c (character)
- %u (unsigned int)
- %d (signed int)
- %x (unsigned int as hex)
- · %s (string)

Warning: to correctly pass chars for printing as chars, they must be explicitly re-cast as such when calling the function. See docs\_chars\_varargs for more details.

Currently supported in the Emulicious emulator

Print the string and arguments in the buffer by the pointer given by format to the emulator debug message window

#### **Parameters**

format	The format string as per printf
data	Buffer containing arguments, for example some struct

#### See also

EMU\_printf for the format string description

Currently supported in the Emulicious emulator

#### 20.40.4 Variable Documentation

```
20.40.4.1 b void b
```

**20.40.4.2 c** void c

# 20.41 gbdk-lib/include/gb/gb.h File Reference

```
#include <types.h>
#include <stdint.h>
#include <gbdk/version.h>
#include <gb/hardware.h>
```

# **Data Structures**

- struct joypads\_t
- struct OAM\_item\_t

## Macros

- #define NINTENDO
- #define SYSTEM 60HZ 0x00
- #define SYSTEM\_50HZ 0x01
- #define GAMEBOY
- #define J UP 0x04U
- #define J\_DOWN 0x08U
- #define J\_LEFT 0x02U
- #define J RIGHT 0x01U
- #define J\_A 0x10U
- #define J\_B 0x20U
- #define J\_SELECT 0x40U
- #define J\_START 0x80U
- #define M DRAWING 0x01U
- #define M\_TEXT\_OUT 0x02U
- #define M\_TEXT\_INOUT 0x03U
- #define M\_NO\_SCROLL 0x04U

- #define M\_NO\_INTERP 0x08U
- #define S\_BANK 0x08U
- #define S\_PALETTE 0x10U
- #define S FLIPX 0x20U
- #define S FLIPY 0x40U
- #define S\_PRIORITY 0x80U
- #define S PAL(n) n
- #define EMPTY IFLAG 0x00U
- #define VBL\_IFLAG 0x01U
- #define LCD IFLAG 0x02U
- #define TIM IFLAG 0x04U
- #define SIO IFLAG 0x08U
- #define JOY\_IFLAG 0x10U
- #define DMG BLACK 0x03
- #define DMG\_DARK\_GRAY 0x02
- #define DMG LITE GRAY 0x01
- #define DMG WHITE 0x00
- #define DMG\_PALETTE(C0, C1, C2, C3) ((uint8\_t)(((C3) & 0x03) << 6) | ((C2) & 0x03) << 4) | ((C1) & 0x03) << 2) | ((C0) & 0x03)))</li>
- #define SCREENWIDTH DEVICE\_SCREEN\_PX\_WIDTH
- #define SCREENHEIGHT DEVICE\_SCREEN\_PX\_HEIGHT
- #define MINWNDPOSX DEVICE WINDOW PX OFFSET X
- #define MINWNDPOSY DEVICE\_WINDOW\_PX\_OFFSET\_Y
- #define MAXWNDPOSX (DEVICE\_WINDOW\_PX\_OFFSET\_X + DEVICE\_SCREEN\_PX\_WIDTH 1)
- #define MAXWNDPOSY (DEVICE WINDOW PX OFFSET Y + DEVICE SCREEN PX HEIGHT 1)
- #define DMG\_TYPE 0x01
- #define MGB TYPE 0xFF
- #define CGB TYPE 0x11
- #define GBA NOT DETECTED 0x00
- #define GBA DETECTED 0x01
- #define DEVICE\_SUPPORTS\_COLOR (\_cpu == CGB\_TYPE)
- #define IO\_IDLE 0x00U
- #define IO\_SENDING 0x01U
- #define IO\_RECEIVING 0x02U
- #define IO\_ERROR 0x04U
- #define CURRENT BANK current bank
- #define BANK(VARNAME) ( (uint8\_t) & \_\_bank\_ ## VARNAME )
- #define BANKREF(VARNAME)
- #define BANKREF\_EXTERN(VARNAME) extern const void \_\_bank\_ ## VARNAME;
- #define SWITCH ROM(b) ( current bank = (b), rROMB0 = (b))
- #define SWITCH RAM(b) (rRAMB = (b))
- #define ENABLE\_RAM (rRAMG = 0x0A)
- #define DISABLE\_RAM (rRAMG = 0x00)
- #define SWITCH\_ROM\_MEGADUCK(b) SWITCH\_ROM(b)
- #define SWITCH\_ROM\_MBC1(b) SWITCH\_ROM(b)
- #define SWITCH RAM MBC1(b) SWITCH RAM(b)
- #define ENABLE\_RAM\_MBC1 ENABLE\_RAM
- #define DISABLE\_RAM\_MBC1 DISABLE\_RAM
- #define SWITCH\_16\_8\_MODE\_MBC1 (\*(volatile uint8\_t \*)0x6000 = 0x00)
- #define SWITCH\_4\_32\_MODE\_MBC1 (\*(volatile uint8\_t \*)0x6000 = 0x01)
- #define SWITCH\_ROM\_MBC5(b) (\_current\_bank = (b), rROMB1 = 0, rROMB0 = (b))
- #define SWITCH\_ROM\_MBC5\_8M(b) (rROMB1 = ((uint16\_t)(b) >> 8), rROMB0 = (b))
- #define SWITCH\_RAM\_MBC5(b) SWITCH\_RAM(b)
- #define ENABLE\_RAM\_MBC5 ENABLE\_RAM
- #define DISABLE\_RAM\_MBC5 DISABLE\_RAM

- #define DISPLAY\_ON LCDC\_REG|=LCDCF\_ON
- #define DISPLAY\_OFF display\_off();
- #define HIDE LEFT COLUMN
- #define SHOW LEFT COLUMN
- #define SET BORDER COLOR(C)
- #define SHOW\_BKG\_LCDC\_REG|=LCDCF\_BGON
- #define HIDE\_BKG LCDC\_REG&=~LCDCF\_BGON
- #define SHOW WIN LCDC REG|=LCDCF WINON
- #define HIDE WIN LCDC REG&=~LCDCF WINON
- #define SHOW SPRITES LCDC REG|=LCDCF OBJON
- #define HIDE SPRITES LCDC REG&=~LCDCF OBJON
- #define SPRITES\_8x16 LCDC\_REG|=LCDCF\_OBJ16
- #define SPRITES\_8x8 LCDC\_REG&=~LCDCF\_OBJ16
- #define COMPAT\_PALETTE(C0, C1, C2, C3) ((uint8\_t)(((C3) << 6) | ((C2) << 4) | ((C1) << 2) | (C0)))</li>
- · #define set bkg 2bpp data set bkg data
- · #define set tile map set bkg tiles
- #define set\_tile\_submap set\_bkg\_submap
- #define set\_tile\_xy set\_bkg\_tile\_xy
- #define set\_attribute\_xy set\_bkg\_attribute\_xy
- #define set\_sprite\_2bpp\_data set\_sprite\_data
- #define DISABLE OAM DMA shadow OAM base = 0
- #define DISABLE VBL TRANSFER DISABLE OAM DMA
- #define ENABLE\_OAM\_DMA \_shadow\_OAM\_base = (uint8\_t)((uint16\_t)&shadow\_OAM >> 8)
- #define ENABLE\_VBL\_TRANSFER ENABLE\_OAM\_DMA
- #define MAX\_HARDWARE\_SPRITES 40
- #define HARDWARE SPRITE CAN FLIP X 1
- #define HARDWARE SPRITE CAN FLIP Y 1
- #define fill\_rect fill\_bkg\_rect

## **Typedefs**

- typedef void(\* int\_handler) (void) NONBANKED
- typedef struct OAM\_item\_t OAM\_item\_t

#### **Functions**

- · void remove VBL (int handler h)
- void remove\_LCD (int\_handler h)
- void remove\_TIM (int\_handler h)
- void remove\_SIO (int\_handler h)
- void remove\_JOY (int\_handler h)
- void add VBL (int handler h)
- · void add LCD (int handler h)
- void add TIM (int handler h)
- void add\_low\_priority\_TIM (int\_handler h)
- void add\_SIO (int\_handler h)
- · void add JOY (int handler h)
- · void nowait int handler (void)
- void wait\_int\_handler (void)
- uint8\_t cancel\_pending\_interrupts (void)
- void mode (uint8\_t m)
- uint8\_t get\_mode (void) PRESERVES\_REGS(b
- uint8\_t get\_system (void)
- void send\_byte (void)
- void receive\_byte (void)

- void delay (uint16\_t d) PRESERVES\_REGS(h
- uint8\_t joypad (void) PRESERVES\_REGS(b
- uint8\_t waitpad (uint8\_t mask) PRESERVES\_REGS(b
- · void waitpadup (void) PRESERVES REGS(a
- uint8 t joypad init (uint8 t npads, joypads t \*joypads) OLDCALL
- void joypad ex (joypads t \*joypads) PRESERVES REGS(b
- · void enable interrupts (void) PRESERVES REGS(a
- void disable\_interrupts (void) PRESERVES\_REGS(a
- void set\_interrupts (uint8\_t flags) PRESERVES\_REGS(b
- · void reset (void)
- · void vsync (void) PRESERVES REGS(b
- · void wait vbl done (void) PRESERVES REGS(b
- void display\_off (void) PRESERVES\_REGS(b
- · void refresh\_OAM (void) PRESERVES\_REGS(b
- void hiramcpy (uint8\_t dst, const void \*src, uint8\_t n) OLDCALL PRESERVES\_REGS(b
- void set\_vram\_byte (uint8\_t \*addr, uint8\_t v) PRESERVES\_REGS(b
- uint8 t get vram byte (uint8 t \*addr) PRESERVES REGS(b
- uint8\_t \* get\_bkg\_xy\_addr (uint8\_t x, uint8\_t y) OLDCALL PRESERVES\_REGS(b
- void set\_2bpp\_palette (uint16\_t palette)
- void set\_1bpp\_colors\_ex (uint8\_t fgcolor, uint8\_t bgcolor, uint8\_t mode) OLDCALL
- void set 1bpp colors (uint8 t fgcolor, uint8 t bgcolor)
- void set\_bkg\_data (uint8\_t first\_tile, uint8\_t nb\_tiles, const uint8\_t \*data) OLDCALL PRESERVES\_REGS(b
- void set\_bkg\_1bpp\_data (uint8\_t first\_tile, uint8\_t nb\_tiles, const uint8\_t \*data) OLDCALL PRESERVES\_REGS(b
- void get\_bkg\_data (uint8\_t first\_tile, uint8\_t nb\_tiles, uint8\_t \*data) OLDCALL PRESERVES\_REGS(b
- void set\_bkg\_tiles (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*tiles) OLDCALL PRESERVES\_REGS(b
- void set\_bkg\_based\_tiles (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*tiles, uint8\_t base\_tile)
- void set\_bkg\_attributes (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*tiles)
- void set\_bkg\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w) OLDCALL
- void set\_bkg\_based\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w, uint8\_t base\_tile)
- void set\_bkg\_submap\_attributes (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w)
- void get bkg tiles (uint8 t x, uint8 t y, uint8 t w, uint8 t + tiles) OLDCALL PRESERVES REGS(b
- uint8\_t \* set\_bkg\_tile\_xy (uint8\_t x, uint8\_t y, uint8\_t t)
- uint8\_t \* set\_bkg\_attribute\_xy (uint8\_t x, uint8\_t y, uint8\_t a)
- uint8\_t get\_bkg\_tile\_xy (uint8\_t x, uint8\_t y) OLDCALL PRESERVES\_REGS(b
- void move\_bkg (uint8\_t x, uint8\_t y)
- void scroll\_bkg (int8\_t x, int8\_t y)
- uint8\_t \* get\_win\_xy\_addr (uint8\_t x, uint8\_t y) OLDCALL PRESERVES\_REGS(b
- void set\_win\_data (uint8\_t first\_tile, uint8\_t nb\_tiles, const uint8\_t \*data) OLDCALL PRESERVES\_REGS(b
- void set\_win\_1bpp\_data (uint8\_t first\_tile, uint8\_t nb\_tiles, const uint8\_t \*data) OLDCALL PRESERVES\_REGS(b
- void get win data (uint8 t first tile, uint8 t nb tiles, uint8 t \*data) OLDCALL PRESERVES REGS(b
- void set win tiles (uint8 tx, uint8 ty, uint8 th, const uint8 t\*tiles) OLDCALL PRESERVES REGS(b
- void set\_win\_based\_tiles (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*tiles, uint8\_t base\_tile)
- void set\_win\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w) OLDCALL
- void set\_win\_based\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w, uint8\_t base\_tile)
- void get win tiles (uint8 t x, uint8 t y, uint8 t w, uint8 t \*tiles) OLDCALL PRESERVES REGS(b
- uint8\_t \* set\_win\_tile\_xy (uint8\_t x, uint8\_t y, uint8\_t t)
- uint8\_t get\_win\_tile\_xy (uint8\_t x, uint8\_t y) OLDCALL PRESERVES\_REGS(b
- void move\_win (uint8\_t x, uint8\_t y)
- void scroll\_win (int8\_t x, int8\_t y)
- void set sprite data (uint8 t first tile, uint8 t nb tiles, const uint8 t \*data) OLDCALL PRESERVES REGS(b
- void set sprite 1bpp data (uint8 t first tile, uint8 t nb tiles, const uint8 t \*data) OLDCALL PRESERVES REGS(b
- void get sprite data (uint8 t first tile, uint8 t nb tiles, uint8 t \*data) OLDCALL PRESERVES REGS(b
- void SET\_SHADOW\_OAM\_ADDRESS (void \*address)

- void set\_sprite\_tile (uint8\_t nb, uint8\_t tile)
- uint8\_t get\_sprite\_tile (uint8\_t nb)
- void set sprite prop (uint8 t nb, uint8 t prop)
- uint8 t get sprite prop (uint8 t nb)
- void move\_sprite (uint8\_t nb, uint8\_t x, uint8\_t y)
- void scroll\_sprite (uint8\_t nb, int8\_t x, int8\_t y)
- void hide\_sprite (uint8\_t nb)
- void set data (uint8 t \*vram addr, const uint8 t \*data, uint16 t len)
- void get data (uint8 t \*data, uint8 t \*vram addr, uint16 t len)
- void vmemcpy (uint8 t \*dest, uint8 t \*sour, uint16 t len)
- void set tiles (uint8 t x, uint8 t y, uint8 t w, uint8 t h, uint8 t \*vram addr, const uint8 t \*tiles) OLDCALL
- void set\_tile\_data (uint8\_t first\_tile, uint8\_t nb\_tiles, const uint8\_t \*data, uint8\_t base) OLDCALL PRESERVES\_REGS(b
- void get\_tiles (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, uint8\_t \*vram\_addr, uint8\_t \*tiles) OLDCALL
- void set native tile data (uint16 t first tile, uint8 t nb tiles, const uint8 t \*data)
- void set\_bkg\_native\_data (uint8\_t first\_tile, uint8\_t nb\_tiles, const uint8\_t \*data)
- void set\_sprite\_native\_data (uint8\_t first\_tile, uint8\_t nb\_tiles, const uint8\_t \*data)
- void init\_win (uint8\_t c) OLDCALL PRESERVES\_REGS(b
- void init\_bkg (uint8\_t c) OLDCALL PRESERVES\_REGS(b
- void vmemset (void \*s, uint8\_t c, size\_t n) OLDCALL PRESERVES\_REGS(b
- void fill\_bkg\_rect (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, uint8\_t tile) OLDCALL PRESERVES\_REGS(b
- void fill\_win\_rect (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, uint8\_t tile) OLDCALL PRESERVES\_REGS(b

#### **Variables**

- uint8 t c
- uint8\_t d
- uint8\_t e
- uint8\_t h
- uint8 t1
- uint8\_t \_cpu
- uint8\_t \_is\_GBA
- volatile uint16\_t sys\_time
- volatile uint8\_t \_io\_status
- volatile uint8 t io in
- volatile uint8\_t \_io\_out
- \_\_REG \_current\_bank
- void b
- uint16\_t \_current\_1bpp\_colors
- · uint8\_t \_map\_tile\_offset
- · uint8 t submap tile offset
- volatile struct OAM item t shadow OAM []
- \_\_REG \_shadow\_OAM\_base

#### 20.41.1 Detailed Description

Gameboy specific functions.

#### 20.41.2 Macro Definition Documentation

## 20.41.2.1 NINTENDO #define NINTENDO

```
20.41.2.2 SYSTEM_60HZ #define SYSTEM_60HZ 0x00
20.41.2.3 SYSTEM_50HZ #define SYSTEM_50HZ 0x01
20.41.2.4 GAMEBOY #define GAMEBOY
20.41.2.5 J_UP #define J_UP 0x04U
Joypad bits. A logical OR of these is used in the wait pad and joypad functions. For example, to see if the B button
is pressed try
uint8_t keys; keys = joypad(); if (keys & J_B) { ... }
See also
    joypad
20.41.2.6 J_DOWN #define J_DOWN 0x08U
20.41.2.7 J_LEFT #define J_LEFT 0x02U
20.41.2.8 J_RIGHT #define J_RIGHT 0x01U
20.41.2.9 J_A #define J_A 0x10U
20.41.2.10 J_B #define J_B 0x20U
20.41.2.11 J_SELECT #define J_SELECT 0x40U
20.41.2.12 J_START #define J_START 0x80U
20.41.2.13 M DRAWING #define M_DRAWING 0x01U
Screen modes. Normally used by internal functions only.
See also
     mode()
20.41.2.14 M_TEXT_OUT #define M_TEXT_OUT 0x02U
20.41.2.15 M_TEXT_INOUT #define M_TEXT_INOUT 0x03U
```

```
20.41.2.16 M_NO_SCROLL #define M_NO_SCROLL 0x04U
Set this in addition to the others to disable scrolling
If scrolling is disabled, the cursor returns to (0,0)
See also
     mode()
20.41.2.17 M_NO_INTERP #define M_NO_INTERP 0x08U
Set this to disable interpretation
See also
     mode()
If this bit set clear, the tile from the second VRAM bank is used
See also
     set_sprite_prop()
20.41.2.19 S_PALETTE #define S_PALETTE 0x10U
If this is set, sprite colours come from OBJ1PAL. Else they come from OBJ0PAL
See also
     set_sprite_prop().
20.41.2.20 S_FLIPX #define S_FLIPX 0x20U
If set the sprite will be flipped horizontally.
See also
     set sprite prop()
20.41.2.21 S_FLIPY #define S_FLIPY 0x40U
If set the sprite will be flipped vertically.
See also
     set_sprite_prop()
20.41.2.22 S_PRIORITY #define S_PRIORITY 0x80U
If this bit is clear, then the sprite will be displayed on top of the background and window.
See also
     set_sprite_prop()
```

```
20.41.2.23 S_PAL #define S_PAL(
               n ) n
Defines how palette number is encoded in OAM. Required for the png2asset tool's metasprite output.
20.41.2.24 EMPTY IFLAG #define EMPTY_IFLAG 0x00U
Disable calling of interrupt service routines
20.41.2.25 VBL_IFLAG #define VBL_IFLAG 0x01U
VBlank Interrupt occurs at the start of the vertical blank.
During this period the video ram may be freely accessed.
See also
     set_interrupts(),
     add_VBL
20.41.2.26 LCD IFLAG #define LCD_IFLAG 0x02U
LCD Interrupt when triggered by the STAT register.
See also
     set_interrupts(),
     add LCD
20.41.2.27 TIM_IFLAG #define TIM_IFLAG 0x04U
Timer Interrupt when the timer TIMA_REG overflows.
See also
     set_interrupts(),
     add_TIM
20.41.2.28 SIO_IFLAG #define SIO_IFLAG 0x08U
Serial Link Interrupt occurs when the serial transfer has completed.
See also
     set_interrupts(),
     add SIO
20.41.2.29 JOY_IFLAG #define JOY_IFLAG 0x10U
Joypad Interrupt occurs on a transition of the keypad.
See also
     set_interrupts(),
     add_JOY
```

**20.41.2.30 DMG\_BLACK** #define DMG\_BLACK 0x03

```
20.41.2.31 DMG_DARK_GRAY #define DMG_DARK_GRAY 0x02
20.41.2.32 DMG_LITE_GRAY #define DMG_LITE_GRAY 0x01
20.41.2.33 DMG_WHITE #define DMG_WHITE 0x00
20.41.2.34 DMG_PALETTE #define DMG_PALETTE(
              CO,
              C1,
              C2.
              C3) ((uint8_t)((((C3) \& 0x03) << 6) | (((C2) \& 0x03) << 4) | (((C1) \& 0x03) <<
2) | ((C0) & 0x03)))
Macro to create a DMG palette from 4 colors
Parameters
 C0
      Color for Index 0
 C1
      Color for Index 1
 C2
      Color for Index 2
      Color for Index 3
The resulting format is four greyscale colors packed into a single unsigned byte.
Example:
BGP_REG = DMG_PALETTE(DMG_BLACK, DMG_DARK_GRAY, DMG_LITE_GRAY, DMG_WHITE);
See also
     OBP0_REG, OBP1_REG, BGP_REG
     DMG BLACK, DMG DARK GRAY, DMG LITE GRAY, DMG WHITE
20.41.2.35 SCREENWIDTH #define SCREENWIDTH DEVICE_SCREEN_PX_WIDTH
Width of the visible screen in pixels.
20.41.2.36 SCREENHEIGHT #define SCREENHEIGHT DEVICE_SCREEN_PX_HEIGHT
Height of the visible screen in pixels.
20.41.2.37 MINWNDPOSX #define MINWNDPOSX DEVICE_WINDOW_PX_OFFSET_X
The Minimum X position of the Window Layer (Left edge of screen)
See also
     move win()
20.41.2.38 MINWNDPOSY #define MINWNDPOSY DEVICE_WINDOW_PX_OFFSET_Y
The Minimum Y position of the Window Layer (Top edge of screen)
See also
     move_win()
```

```
20.41.2.39 MAXWNDPOSX #define MAXWNDPOSX (DEVICE_WINDOW_PX_OFFSET_X + DEVICE_SCREEN_PX_WIDTH
The Maximum X position of the Window Layer (Right edge of screen)
See also
     move_win()
20.41.2.40 MAXWNDPOSY #define MAXWNDPOSY (DEVICE_WINDOW_PX_OFFSET_Y + DEVICE_SCREEN_PX_HEIGHT
The Maximum Y position of the Window Layer (Bottom edge of screen)
See also
     move win()
20.41.2.41 DMG_TYPE #define DMG_TYPE 0x01
Hardware Model: Original GB or Super GB.
See also
     _cpu
20.41.2.42 MGB_TYPE #define MGB_TYPE 0xFF
Hardware Model: Pocket GB or Super GB 2.
See also
     _cpu
20.41.2.43 CGB_TYPE #define CGB_TYPE 0x11
Hardware Model: Color GB.
See also
     cpu
\textbf{20.41.2.44} \quad \textbf{GBA\_NOT\_DETECTED} \quad \texttt{\#define GBA\_NOT\_DETECTED 0x00}
Hardware Model: DMG, CGB or MGB.
See also
     _cpu, _is_GBA
20.41.2.45 GBA_DETECTED #define GBA_DETECTED 0x01
Hardware Model: GBA.
See also
     _cpu, _is_GBA
```

**20.41.2.46 DEVICE\_SUPPORTS\_COLOR** #define DEVICE\_SUPPORTS\_COLOR (\_cpu == CGB\_TYPE) Macro returns TRUE if device supports color

20.41.2.47 IO\_IDLE #define IO\_IDLE 0x00U

Serial Link IO is completed

20.41.2.48 IO\_SENDING #define IO\_SENDING 0x01U

Serial Link Sending data

20.41.2.49 IO\_RECEIVING #define IO\_RECEIVING 0x02U

Serial Link Receiving data

20.41.2.50 IO\_ERROR #define IO\_ERROR 0x04U

Serial Link Error

20.41.2.51 CURRENT\_BANK #define CURRENT\_BANK \_current\_bank

```
20.41.2.52 BANK #define BANK(

**VARNAME ) ( (uint8_t) & __bank_ ## VARNAME )
```

Obtains the bank number of VARNAME

#### **Parameters**

VARNAME	Name of the variable which has a	bank_VARNAME companion symbol which is adjusted by
	bankpack	

Use this to obtain the bank number from a bank reference created with BANKREF().

See also

BANKREF\_EXTERN(), BANKREF()

```
20.41.2.53 BANKREF #define BANKREF( VARNAME )
```

# Value:

```
void __func_ ## VARNAME(void) __banked __naked { \
_asm \
    .local b___func_ ## VARNAME \
    __bank_ ## VARNAME = b___func_ ## VARNAME \
    .globl ___bank_ ## VARNAME \
__endasm; \
```

Creates a reference for retrieving the bank number of a variable or function

#### **Parameters**

VARNAME Variable name to use, which may be an existing identifier

See also

BANK() for obtaining the bank number of the included data.

More than one BANKREF () may be created per file, but each call should always use a unique VARNAME. Use BANKREF\_EXTERN() within another source file to make the variable and it's data accesible there.

```
20.41.2.54 BANKREF_EXTERN #define BANKREF_EXTERN(

VARNAME) extern const void __bank_ ## VARNAME;
```

Creates extern references for accessing a BANKREF() generated variable.

#### **Parameters**

VARNAME	Name of the variable used with BANKREF()
---------	------------------------------------------

This makes a BANKREF() reference in another source file accessible in the current file for use with BANK().

See also

BANKREF(), BANK()

Makes default platform MBC switch the active ROM bank

#### **Parameters**

```
b ROM bank to switch to (max 255)
```

- When used with MBC1 the max bank is Bank 31 (512K).
- When used with MBC5 the max bank is Bank 255 (4MB).
- To use the full 8MB size of MBC5 see SWITCH\_ROM\_MBC5\_8M().
- For MBC1 some banks in it's range are unavailable (typically 0x20, 0x40, 0x60).

Note

Using SWITCH\_ROM\_MBC5\_8M() should not be mixed with using SWITCH\_ROM\_MBC5() and SWITCH\_ROM().

See also

SWITCH\_ROM\_MBC1, SWITCH\_ROM\_MBC5, SWITCH\_ROM\_MEGADUCK

```
20.41.2.56 SWITCH_RAM #define SWITCH_RAM(
b) (rRAMB = (b))
```

Switches SRAM bank on MBC1 and other compatible MBCs

**Parameters** 

```
b SRAM bank to switch to
```

Before switching SRAM banks enable it using <a href="ENABLE\_RAM">ENABLE\_RAM</a>

See also

```
SWITCH_RAM_MBC1, SWITCH_RAM_MBC5
```

```
20.41.2.57 ENABLE_RAM #define ENABLE_RAM (rRAMG = 0x0A)
```

Enables SRAM on MBC1 and other compatible MBCs

```
20.41.2.58 DISABLE_RAM #define DISABLE_RAM (rRAMG = 0x00)
```

Disables SRAM on MBC1 and other compatible MBCs

```
20.41.2.59 SWITCH_ROM_MEGADUCK #define SWITCH_ROM_MEGADUCK(
```

b ) SWITCH\_ROM(b)

Makes MEGADUCK MBC switch the active ROM bank

#### **Parameters**

b ROM bank to switch to (max 3 for 64K, or 7 for 128K)

# ${\bf 20.41.2.60 \quad SWITCH\_ROM\_MBC1} \quad {\tt \#define \; SWITCH\_ROM\_MBC1} \ ($

b ) SWITCH\_ROM(b)

Makes MBC1 and other compatible MBCs switch the active ROM bank

## **Parameters**

b ROM bank to switch to

For MBC1 some banks in it's range are unavailable (typically 0x20, 0x40, 0x60). See pandocs for more details <a href="https://gbdev.io/pandocs/MBC1">https://gbdev.io/pandocs/MBC1</a>

# 20.41.2.61 SWITCH\_RAM\_MBC1 #define SWITCH\_RAM\_MBC1(

b ) SWITCH\_RAM(b)

Switches SRAM bank on MBC1 and other compatible MBCs

#### **Parameters**

b SRAM bank to switch to

Before switching SRAM banks enable it using ENABLE\_RAM

See also

SWITCH RAM, SWITCH RAM MBC5

# 20.41.2.62 ENABLE\_RAM\_MBC1 #define ENABLE\_RAM\_MBC1 ENABLE\_RAM

Enables SRAM on MBC1

# 20.41.2.63 DISABLE\_RAM\_MBC1 #define DISABLE\_RAM\_MBC1 DISABLE\_RAM

Disables SRAM on MBC1

**20.41.2.64 SWITCH\_16\_8\_MODE\_MBC1** #define SWITCH\_16\_8\_MODE\_MBC1 (\*(volatile uint8\_t \*)0x6000 = 0x00)

**20.41.2.65 SWITCH\_4\_32\_MODE\_MBC1** #define SWITCH\_4\_32\_MODE\_MBC1 (\*(volatile uint8\_t \*)0x6000 = 0x01)

```
20.41.2.66 SWITCH_ROM_MBC5 #define SWITCH_ROM_MBC5(
```

b ) (\_current\_bank = (b), rROMB1 = 0, rROMB0 = (b))

Makes MBC5 switch to the active ROM bank

#### **Parameters**

b ROM bank to switch to (max 255)

Supports up to ROM bank 255 (4 MB).

SWITCH\_ROM\_MBC5\_8M may be used if the full 8MB size is needed.

Note

Using SWITCH\_ROM\_MBC5\_8M() should not be mixed with using SWITCH\_ROM\_MBC5() and SWITCH\_ROM().

Note the order used here. Writing the other way around on a MBC1 always selects bank 1

```
20.41.2.67 SWITCH_ROM_MBC5_8M #define SWITCH_ROM_MBC5_8M(

b) (rROMB1 = ((uint16_t) (b) >> 8), rROMB0 = (b))
```

Makes MBC5 to switch the active ROM bank using the full 8MB size.

See also

**CURRENT BANK** 

#### **Parameters**

b ROM bank to switch to

This is an alternate to SWITCH\_ROM\_MBC5 which is limited to 4MB. Note:

- Banked SDCC calls are not supported if you use this macro.
- The active bank number is not tracked by CURRENT BANK if you use this macro.
- Using SWITCH\_ROM\_MBC5\_8M() should not be mixed with using SWITCH\_ROM\_MBC5() and SWITCH\_ROM().

Note the order used here. Writing the other way around on a MBC1 always selects bank 1

```
20.41.2.68 SWITCH_RAM_MBC5 #define SWITCH_RAM_MBC5( b ) SWITCH_RAM(b)
```

Switches SRAM bank on MBC5

**Parameters** 

b SRAM bank to switch to

Before switching SRAM banks enable it using <a href="ENABLE\_RAM">ENABLE\_RAM</a>

```
20.41.2.69 ENABLE_RAM_MBC5 #define ENABLE_RAM_MBC5 ENABLE_RAM Enables SRAM on MBC5
```

**20.41.2.70 DISABLE\_RAM\_MBC5** #define DISABLE\_RAM\_MBC5 DISABLE\_RAM Disables SRAM on MBC5

**20.41.2.71 DISPLAY\_ON** #define DISPLAY\_ON LCDC\_REG|=LCDCF\_ON Turns the display back on.

```
See also
```

```
display off, DISPLAY OFF
```

20.41.2.72 DISPLAY\_OFF #define DISPLAY\_OFF display\_off();

Turns the display off

Waits until the VBL before turning the display off.

See also

display\_off, DISPLAY\_ON

20.41.2.73 HIDE\_LEFT\_COLUMN #define HIDE\_LEFT\_COLUMN

Does nothing for GB

 $\textbf{20.41.2.74} \quad \textbf{SHOW\_LEFT\_COLUMN} \quad \texttt{\#define SHOW\_LEFT\_COLUMN}$ 

Does nothing for GB

20.41.2.75 SET\_BORDER\_COLOR #define SET\_BORDER\_COLOR(

C )

Does nothing for GB

20.41.2.76 SHOW BKG #define SHOW\_BKG LCDC\_REG = LCDCF\_BGON

Turns on the background layer. Sets bit 0 of the LCDC register to 1.

20.41.2.77 HIDE\_BKG #define HIDE\_BKG LCDC\_REG&= $\sim$ LCDCF\_BGON

Turns off the background layer. Sets bit 0 of the LCDC register to 0.

20.41.2.78 SHOW\_WIN #define SHOW\_WIN LCDC\_REG = LCDCF\_WINON

Turns on the Window layer Sets bit 5 of the LCDC register to 1.

This only controls Window visibility. If either the Background layer (which the window is part of) or the Display are not turned then the Window contents will not be visible. Those can be turned on using SHOW\_BKG and DISPLAY\_ON.

 $\textbf{20.41.2.79} \quad \textbf{HIDE\_WIN} \quad \texttt{\#define HIDE\_WIN} \quad \texttt{LCDC\_REG\&=} \sim \texttt{LCDCF\_WINON}$ 

Turns off the window layer. Clears bit 5 of the LCDC register to 0.

20.41.2.80 SHOW\_SPRITES #define SHOW\_SPRITES LCDC\_REG|=LCDCF\_OBJON

Turns on the sprites layer. Sets bit 1 of the LCDC register to 1.

20.41.2.81 HIDE\_SPRITES #define HIDE\_SPRITES LCDC\_REG&=~LCDCF\_OBJON

Turns off the sprites layer. Clears bit 1 of the LCDC register to 0.

See also

hide\_sprite, hide\_sprites\_range

20.41.2.82 SPRITES\_8x16 #define SPRITES\_8x16 LCDC\_REG|=LCDCF\_OBJ16

Sets sprite size to 8x16 pixels, two tiles one above the other. Sets bit 2 of the LCDC register to 1.

20.41.2.83 SPRITES 8x8 #define SPRITES\_8x8 LCDC\_REG&=~LCDCF\_OBJ16

Sets sprite size to 8x8 pixels, one tile. Clears bit 2 of the LCDC register to 0.

```
20.41.2.84 COMPAT_PALETTE #define COMPAT_PALETTE(
              CO,
              C1,
              C2,
              C3 ) ((uint8_t)(((C3) << 6) | ((C2) << 4) | ((C1) << 2) | (C0)))
20.41.2.85 set_bkg_2bpp_data #define set_bkg_2bpp_data set_bkg_data
20.41.2.86 set_tile_map #define set_tile_map set_bkg_tiles
20.41.2.87 set_tile_submap #define set_tile_submap set_bkg_submap
20.41.2.88 set_tile_xy #define set_tile_xy set_bkg_tile_xy
20.41.2.89 set_attribute_xy #define set_attribute_xy set_bkg_attribute_xy
20.41.2.90 set_sprite_2bpp_data #define set_sprite_2bpp_data set_sprite_data
20.41.2.91 DISABLE_OAM_DMA #define DISABLE_OAM_DMA _shadow_OAM_base = 0
20.41.2.92 DISABLE VBL TRANSFER #define DISABLE_VBL_TRANSFER DISABLE_OAM_DMA
Disable OAM DMA copy each VBlank
20.41.2.93 ENABLE OAM DMA #define ENABLE_OAM_DMA _shadow_OAM_base = (uint8_t)((uint16_t)&shadow_OAM
>> 8)
20.41.2.94 ENABLE VBL TRANSFER #define ENABLE_VBL_TRANSFER ENABLE_OAM_DMA
Enable OAM DMA copy each VBlank and set it to transfer default shadow_OAM array
20.41.2.95 MAX_HARDWARE_SPRITES #define MAX_HARDWARE_SPRITES 40
Amount of hardware sprites in OAM
20.41.2.96 HARDWARE_SPRITE_CAN_FLIP_X #define HARDWARE_SPRITE_CAN_FLIP_X 1
True if sprite hardware can flip sprites by X (horizontally)
20.41.2.97 HARDWARE_SPRITE_CAN_FLIP_Y #define HARDWARE_SPRITE_CAN_FLIP_Y 1
True if sprite hardware can flip sprites by Y (vertically)
20.41.2.98 fill_rect #define fill_rect fill_bkg_rect
20.41.3 Typedef Documentation
20.41.3.1 int_handler typedef void(* int_handler) (void) NONBANKED
```

Interrupt handlers

# **20.41.3.2 OAM\_item\_t** typedef struct OAM\_item\_t OAM\_item\_t Sprite Attributes structure

#### **Parameters**

X	X Coordinate of the sprite on screen	
У	Y Coordinate of the sprite on screen	
tile	Sprite tile number (see set_sprite_tile)	
prop	OAM Property Flags (see set_sprite_prop)	

## 20.41.4 Function Documentation

```
20.41.4.1 remove_VBL() void remove_VBL (
          int_handler h )
```

The remove functions will remove any interrupt handler.

A handler of NULL will cause bad things to happen if the given interrupt is enabled.

Removes the VBL interrupt handler.

See also

```
add_VBL()
```

Removes the VBL interrupt handler.

See also

add\_VBL()

```
20.41.4.2 remove_LCD() void remove_LCD (
          int_handler h )
```

Removes the LCD interrupt handler.

See also

add\_LCD(), remove\_VBL()

Removes the TIM interrupt handler.

See also

add\_TIM(), remove\_VBL()

```
20.41.4.4 remove_SIO() void remove_SIO (
    int_handler h )
```

Removes the Serial Link / SIO interrupt handler.

See also

```
add_SIO(),
remove_VBL()
```

The default SIO ISR gets installed automatically if any of the standard SIO calls are used (send\_byte(), receive\_byte()).

Once installed the default SIO ISR cannot be removed. Only secondary chained SIO ISRs (added with add\_SIO()) can be removed.

```
20.41.4.5 remove_JOY() void remove_JOY (
          int_handler h )
```

Removes the JOY interrupt handler.

See also

add JOY(), remove VBL()

```
20.41.4.6 add_VBL() void add_VBL (
          int_handler h )
```

Adds a Vertical Blanking interrupt handler.

#### **Parameters**

h The handler to be called whenever a V-blank interrupt occurs.

Up to 4 handlers may be added, with the last added being called last.

**Do not** use the function definition attributes CRITICAL and INTERRUPT when declaring ISR functions added via add\_VBL() (or LCD, etc). Those attributes are only required when constructing a bare jump from the interrupt vector itself (such as with ISR\_VECTOR()).

ISR handlers added using add\_VBL()/etc are instead called via the GBDK ISR dispatcher which makes the extra function attributes unecessary.

Note

The default GBDK VBL is installed automatically.

See also

```
ISR_VECTOR()
```

Adds a V-blank interrupt handler.

```
20.41.4.7 add_LCD() void add_LCD (
    int_handler h )
```

Adds a LCD interrupt handler.

Called when the LCD interrupt occurs.

Up to 3 handlers may be added, with the last added being called last.

There are various sources controlled by the STAT\_REG register (\$FF41) which can trigger this interrupt. Common examples include triggering on specific scanlines using LY\_REG == LYC\_REG. Another is applying graphics effects on a per-scanline basis such as modifying the X and Y scroll registers (SCX\_REG / SCY\_REG registers).

Note

LYC may not trigger with scanline 0 in the same way as other scanlines due to particular behavior with scanlines 153 and 0. Instead, using an add\_VBL() interrupt handler for start of frame behavior may be more suitable.

**Do not** use the function definition attributes CRITICAL and INTERRUPT when declaring ISR functions added via add\_VBL() (or LCD, etc). Those attributes are only required when constructing a bare jump from the interrupt vector itself (such as with ISR\_VECTOR()).

ISR handlers added using add\_VBL/LCD/etc are instead called via the GBDK ISR dispatcher which makes the extra function attributes unecessary.

If this ISR is to be called once per each scanline then make sure that the time it takes to execute is less than the duration of a scanline.

See also

```
add_VBL, nowait_int_handler, ISR_VECTOR()
```

Adds a LCD interrupt handler.

Adds a timer interrupt handler.

Can not be used together with add\_low\_priority\_TIM

This interrupt occurs when the TIMA\_REG register (\$FF05) changes from \$FF to \$00.

Up to 4 handlers may be added, with the last added being called last.

See also

```
add_VBL
set_interrupts() with TIM_IFLAG, ISR_VECTOR()
```

```
20.41.4.9 add_low_priority_TIM() void add_low_priority_TIM (
    int handler h )
```

Adds a timer interrupt handler, that could be interrupted by the other interrupts, as well as itself, if it runs too slow. Can not be used together with add TIM

This interrupt occurs when the TIMA\_REG register (\$FF05) changes from \$FF to \$00.

Up to 4 handlers may be added, with the last added being called last.

See also

```
add_VBL
set_interrupts() with TIM_IFLAG, ISR_VECTOR()
```

```
20.41.4.10 add_SIO() void add_SIO ( int_handler h )
```

Adds a Serial Link transmit complete interrupt handler.

This interrupt occurs when a serial transfer has completed on the game link port.

Up to 4 handlers may be added, with the last added being called last.

The default SIO ISR gets installed automatically if any of the standard SIO calls are used (send\_byte(), receive byte()).

See also

```
send_byte, receive_byte(), add_VBL()
set_interrupts() with SIO_IFLAG
```

```
20.41.4.11 add_JOY() void add_JOY (
          int_handler h )
```

Adds a joypad button change interrupt handler.

This interrupt occurs on a transition of any of the keypad input lines from high to low, if the relevant P1\_REG bits 4 or 5 are set.

```
For details about configuring flags or reading the data see: https://gbdev.io/pandocs/Interrupt

_Sources.html#int-60-joypad-interrupt
Input.html#ff00-p1joyp-joypad
```

Due to the fact that keypad "bounce" is virtually always present, software should expect this interrupt to occur one or more times for every button press and one or more times for every button release.

Up to 4 handlers may be added, with the last added being called last.

An example use of this is allowing the user to trigger an exit from the lower-power STOP cpu state.

See also

```
joypad(), add_VBL(), IEF_HILO, P1F_5, P1F_4, P1F_3, P1F_2, P1F_1, P1F_0, P1F_GET_DPAD, P1F_GET_BTN, P1F_GET_NONE
```

Interrupt handler chain terminator that does **not** wait for .STAT

You must add this handler last in every interrupt handler chain if you want to change the default interrupt handler behaviour that waits for LCD controller mode to become 1 or 0 before return from the interrupt.

Example:

```
CRITICAL {
    add_SIO(nowait_int_handler); // Disable wait on VRAM state before returning from SIO interrupt
}
See also
```

wait int handler()

Default Interrupt handler chain terminator that waits for

See also

STAT\_REG and only returns at the BEGINNING of either Mode 0 or Mode 1.

Used by default at the end of interrupt chains to help prevent graphical glitches. The glitches are caused when an ISR interrupts a graphics operation in one mode but returns in a different mode for which that graphics operation is not allowed.

See also

nowait int handler()

```
20.41.4.14 cancel_pending_interrupts() uint8_t cancel_pending_interrupts (
```

void ) [inline]

Cancel pending interrupts

```
20.41.4.15 mode() void mode ( uint8_t m )
```

Set the current screen mode - one of M\_\* modes

Normally used by internal functions only.

See also

M\_DRAWING, M\_TEXT\_OUT, M\_TEXT\_INOUT, M\_NO\_SCROLL, M\_NO\_INTERP

```
20.41.4.16 get_mode() uint8_t get_mode() void()
```

Returns the current mode

See also

M\_DRAWING, M\_TEXT\_OUT, M\_TEXT\_INOUT, M\_NO\_SCROLL, M\_NO\_INTERP

Returns the system gbdk is running on.

See also

SYSTEM\_50HZ, SYSTEM\_60HZ, SYSTEM\_BITS\_DENDY, SYSTEM\_BITS\_NTSC, SYSTEM\_BITS\_PAL, SYSTEM\_NTSC SYSTEM\_PAL

```
20.41.4.18 send_byte() void send_byte (
```

void )

Serial Link: Send the byte in \_io\_out out through the serial port

Make sure to enable interrupts for the Serial Link before trying to transfer data.

See also

```
add_SIO(), remove_SIO()
set_interrupts() with SIO_IFLAG
```

Serial Link: Receive a byte from the serial port into \_io\_in

Make sure to enable interrupts for the Serial Link before trying to transfer data.

See also

```
add_SIO(), remove_SIO()
set interrupts() with SIO IFLAG
```

```
20.41.4.20 delay() void delay ( uint16_t d)
```

Delays the given number of milliseconds. Uses no timers or interrupts, and can be called with interrupts disabled

```
20.41.4.21 joypad() uint8_t joypad ( void )
```

Reads and returns the current state of the joypad. Follows Nintendo's guidelines for reading the pad. Return value is an OR of J  $\,*$ 

When testing for multiple different buttons, it's best to read the joypad state *once* into a variable and then test using that variable.

See also

```
J START, J SELECT, J A, J B, J UP, J DOWN, J LEFT, J RIGHT
```

```
20.41.4.22 waitpad() uint8_t waitpad ( uint8_t mask )
```

Waits until at least one of the buttons given in mask are pressed.

**Parameters** 

```
mask Bitmask indicating which buttons to wait for
```

Normally only used for checking one key, but it will support many, even J\_LEFT at the same time as J\_RIGHT. :)

Note

Checks in a loop that doesn't HALT at all, so the CPU will be maxed out until this call returns.

See also

```
joypad
J_START, J_SELECT, J_A, J_B, J_UP, J_DOWN, J_LEFT, J_RIGHT
```

```
20.41.4.23 waitpadup() void waitpadup (
```

void )

Waits for the directional pad and all buttons to be released.

Note

Checks in a loop that doesn't HALT at all, so the CPU will be maxed out until this call returns.

Initializes joypads\_t structure for polling multiple joypads (for the GB and ones connected via SGB)

## **Parameters**

npads	number of joypads requested (1, 2 or 4)
joypads	pointer to joypads_t structure to be initialized

Only required for joypad ex, not required for calls to regular joypad()

Returns

number of joypads avaliable

See also

```
joypad_ex(), joypads_t
```

Polls all avaliable joypads (for the GB and ones connected via SGB)

## **Parameters**

joypads	pointer to joypads_t structure to be filled with joypad statuses, must be previously initialized with
	joypad_init()

See also

```
joypad_init(), joypads_t
```

Enables unmasked interrupts

Note

Use CRITICAL {...} instead for creating a block of of code which should execute with interrupts temporarily turned off.

See also

disable\_interrupts, set\_interrupts, CRITICAL

```
{\bf 20.41.4.27} \quad {\bf disable\_interrupts()} \quad {\tt void \ disable\_interrupts} \ \ (
```

void ) [inline]

Disables interrupts

Note

Use CRITICAL {...} instead for creating a block of of code which should execute with interrupts temporarily turned off.

This function may be called as many times as you like; however the first call to enable interrupts will re-enable them.

See also

enable interrupts, set interrupts, CRITICAL

Clears any pending interrupts and sets the interrupt mask register IO to flags.

#### **Parameters**

```
flags A logical OR of *_IFLAGS
```

Note

This disables and then re-enables interrupts so it must be used outside of a critical section.

#### See also

```
enable_interrupts(), disable_interrupts()
VBL IFLAG, LCD IFLAG, TIM IFLAG, SIO IFLAG, JOY IFLAG
```

```
20.41.4.29 reset() void reset (
```

Performs a soft reset.

For the Game Boy and related it does this by jumping to address 0x0150 which is in crt0.s (the c-runtime that executes before main() is called).

This performs various startup steps such as resetting the stack, clearing WRAM and OAM, resetting initialized variables and some display registers (scroll, window, LCDC), etc.

This is not the same a hard power reset.

```
20.41.4.30 vsync() void vsync ( void )
```

HALTs the CPU and waits for the vertical blank interrupt and then returns when all registered VBL ISRs have completed.

This is often used in main loops to idle the CPU at low power until it's time to start the next frame. It's also useful for syncing animation with the screen re-draw.

Warning: If the VBL interrupt is disabled, this function will never return. If the screen is off this function returns immediately.

```
20.41.4.31 wait_vbl_done() void wait_vbl_done (
```

Obsolete. This function has been replaced by vsync(), which has identical behavior.

```
20.41.4.32 display_off() void display_off (
```

Turns the display off.

Waits until the VBL before turning the display off.

See also

DISPLAY ON

```
20.41.4.33 refresh_OAM() void refresh_OAM ( void )
```

Copies data from shadow OAM to OAM

```
20.41.4.34 hiramcpy() void hiramcpy ( uint8\_t \ dst, const \ void * src, uint8\_t \ n)
```

Copies data from somewhere in the lower address space to part of hi-ram.

#### **Parameters**

dst	Offset in high ram (0xFF00 and above) to copy to.
src	Area to copy from
n	Number of bytes to copy.

Set byte in vram at given memory location

#### **Parameters**

addr	address to write to
V	value

Get byte from vram at given memory location

## **Parameters**

addr	address to read from
------	----------------------

Returns

read value

Note

In general **avoid reading from VRAM** since that memory is not accessible at all times. It is also not supported by GBDK on the NES platform. See coding guidelines for more details.

Get address of X,Y tile of background map

Sets palette for 2bpp color translation for GG/SMS, does nothing on GB

Sets the Foreground and Background colors used by the set\_\*\_1bpp\_\*() functions

#### **Parameters**

fgcolor	Foreground color
bgcolor	Background color
mode	Draw Mode

See set\_1bpp\_colors for details.

Sets the Foreground and Background colors used by the set\_\*\_1bpp\_\*() functions

# **Parameters**

fgcolor	Foreground color to use	
bgcolor	Background color to use	

The default colors are:

• Foreground: DMG\_BLACK

• Background: DMG\_WHITE

#### Example:

```
// Use DMG_BLACK as the Foreground color and DMG_LITE_GRAY
// as the Background color when loading lbpp tile data.
set_lbpp_colors(DMG_BLACK, DMG_LITE_GRAY);
```

#### See also

```
DMG_BLACK, DMG_DARK_GRAY, DMG_LITE_GRAY, DMG_WHITE set_bkg_1bpp_data, set_win_1bpp_data, set_sprite_1bpp_data
```

Sets VRAM Tile Pattern data for the Background / Window

#### **Parameters**

first_tile Index of the first tile to write
---------------------------------------------

#### **Parameters**

nb_tiles	Number of tiles to write
data	Pointer to (2 bpp) source tile data

Writes **nb\_tiles** tiles to VRAM starting at **first\_tile**, tile data is sourced from **data**. Each Tile is 16 bytes in size (8x8 pixels, 2 bits-per-pixel).

Note

Sprite Tiles 128-255 share the same memory region as Background Tiles 128-255.

GBC only: VBK\_REG determines which bank of tile patterns are written to.

- VBK\_REG = VBK\_BANK\_0 indicates the first bank
- VBK\_REG = VBK\_BANK\_1 indicates the second

See also

```
set_win_data, set_tile_data
```

Sets VRAM Tile Pattern data for the Background / Window using 1bpp source data

## **Parameters**

first_tile	Index of the first Tile to write
nb_tiles	Number of Tiles to write
data	Pointer to (1bpp) source Tile Pattern data

Similar to set\_bkg\_data, except source data is 1 bit-per-pixel which gets expanded into 2 bits-per-pixel. For a given bit that represent a pixel:

- · 0 will be expanded into the Background color
- 1 will be expanded into the Foreground color

See set\_1bpp\_colors for details about setting the Foreground and Background colors.

See also

```
SHOW_BKG, HIDE_BKG, set_bkg_tiles
set_win_1bpp_data, set_sprite_1bpp_data
```

Copies from Background / Window VRAM Tile Pattern data into a buffer

# **Parameters**

first_tile	Index of the first Tile to read from
nb_tiles	Number of Tiles to read
data	Pointer to destination buffer for Tile Pattern data
uala	1 office to destination baller for the rattern data

Generated on Mon May 13 2024 22:45:24 for GBDK 2020 Docs by Doxygen

#### Note

In general **avoid reading from VRAM** since that memory is not accessible at all times. It is also not supported by GBDK on the NES platform. See coding guidelines for more details.

Copies nb\_tiles tiles from VRAM starting at first\_tile, Tile data is copied into data.

Each Tile is 16 bytes, so the buffer pointed to by data should be at least nb tiles x 16 bytes in size.

#### See also

```
get_win_data, get_data
```

Sets a rectangular region of Background Tile Map.

#### **Parameters**

X	X Start position in Background Map tile coordinates. Range 0 - 31
У	Y Start position in Background Map tile coordinates. Range 0 - 31
W	Width of area to set in tiles. Range 1 - 32
h	Height of area to set in tiles. Range 1 - 32
tiles	Pointer to source tile map data

Entries are copied from map at **tiles** to the Background Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles.

Use set\_bkg\_submap() instead when:

- · Source map is wider than 32 tiles.
- Writing a width that does not match the source map width and more than one row high at a time.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

Note

Patterns 128-255 overlap with patterns 128-255 of the sprite Tile Pattern table.

GBC only: VBK\_REG determines whether Tile Numbers or Tile Attributes get set.

- VBK\_REG = VBK\_TILES Tile Numbers are written
- VBK\_REG = VBK\_ATTRIBUTES Tile Attributes are written

GBC Tile Attributes are defined as:

- Bit 7 Priority flag. When this is set, it puts the tile above the sprites with colour 0 being transparent.
  - 0: Below sprites
  - 1: Above sprites

Note: SHOW\_BKG needs to be set for these priorities to take place.

- Bit 6 Vertical flip. Dictates which way up the tile is drawn vertically.
  - 0: Normal
  - 1: Flipped Vertically
- Bit 5 Horizontal flip. Dictates which way up the tile is drawn horizontally.
  - 0: Normal
  - 1: Flipped Horizontally

- · Bit 4 Not used
- Bit 3 Character Bank specification. Dictates from which bank of Background Tile Patterns the tile is taken.
   0: Bank 0
  - 1: Bank 1
- Bit 2 See bit 0.
- Bit 1 See bit 0.
- Bit 0 Bits 0-2 indicate which of the 7 BKG colour palettes the tile is assigned.

#### See also

```
SHOW_BKG
set_bkg_data, set_bkg_submap, set_win_tiles, set_tiles
```

Sets a rectangular region of Background Tile Map. The offset value in **base\_tile** is added to the tile ID for each map entry.

#### **Parameters**

Х	X Start position in Background Map tile coordinates. Range 0 - 31
У	Y Start position in Background Map tile coordinates. Range 0 - 31
W	Width of area to set in tiles. Range 1 - 32
h	Height of area to set in tiles. Range 1 - 32
tiles	Pointer to source tile map data
base_tile	Offset each tile ID entry of the source map by this value. Range 1 - 255

This is identical to set\_bkg\_tiles() except that it adds the **base\_tile** parameter for when a tile map's tiles don't start at index zero. (For example, the tiles used by the map range from 100 -> 120 in VRAM instead of 0 -> 20).

# See also

set bkg tiles for more details

Sets a rectangular region of Background Tile Map Attributes.

# **Parameters**

Х	X Start position in Background Map tile coordinates. Range 0 - 31
V	Y Start position in Background Map tile coordinates. Range 0 - 31

#### **Parameters**

W	Width of area to set in tiles. Range 1 - 32
h	Height of area to set in tiles. Range 1 - 32
tiles	Pointer to source tile map attribute data

Entries are copied from map at **tiles** to the Background Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles.

Use set bkg submap attributes() instead when:

- · Source map is wider than 32 tiles.
- · Writing a width that does not match the source map width and more than one row high at a time.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

GBC Tile Attributes are defined as:

- Bit 7 Priority flag. When this is set, it puts the tile above the sprites with colour 0 being transparent.
  - 0: Below sprites
  - 1: Above sprites

Note: SHOW BKG needs to be set for these priorities to take place.

- Bit 6 Vertical flip. Dictates which way up the tile is drawn vertically.
  - 0: Normal
  - 1: Flipped Vertically
- Bit 5 Horizontal flip. Dictates which way up the tile is drawn horizontally.
  - 0: Normal
  - 1: Flipped Horizontally
- · Bit 4 Not used
- Bit 3 Character Bank specification. Dictates from which bank of Background Tile Patterns the tile is taken.
  - 0: Bank 0
  - 1: Bank 1
- Bit 2 See bit 0.
- Bit 1 See bit 0.
- Bit 0 Bits 0-2 indicate which of the 7 BKG colour palettes the tile is assigned.

#### See also

```
SHOW_BKG
set_bkg_data, set_bkg_submap_attributes, set_win_tiles, set_tiles
```

## Note

On the Game Boy this is only usable in Game Boy Color mode

Sets a rectangular area of the Background Tile Map using a sub-region from a source tile map. Useful for scrolling implementations of maps larger than  $32 \times 32$  tiles.

#### **Parameters**

X	X Start position in both the Source Tile Map and hardware Background Map tile coordinates. Range 0 - 255
У	Y Start position in both the Source Tile Map and hardware Background Map tile coordinates. Range 0 - 255
W	Width of area to set in tiles. Range 1 - 255
h	Height of area to set in tiles. Range 1 - 255
тар	Pointer to source tile map data
тар⊷	Width of source tile map in tiles. Range 1 - 255
_ <i>w</i>	

Entries are copied from **map** to the Background Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles, using **map\_w** as the rowstride for the source tile map.

The **x** and **y** parameters are in Source Tile Map tile coordinates. The location tiles will be written to on the hardware Background Map is derived from those, but only uses the lower 5 bits of each axis, for range of 0-31 (they are bit-masked:  $x \& 0 \times 1F$  and  $y \& 0 \times 1F$ ). As a result the two coordinate systems are aligned together.

In order to transfer tile map data in a way where the coordinate systems are not aligned, an offset from the Source Tile Map pointer can be passed in:  $(map\_ptr + x + (y * map\_width))$ .

For example, if you want the tile id at 1, 2 from the source map to show up at 0, 0 on the hardware Background Map (instead of at 1, 2) then modify the pointer address that is passed in:  $map\_ptr + 1 + (2 * map\_width)$  Use this instead of  $set\_bkg\_tiles$  when the source map is wider than 32 tiles or when writing a width that does not match the source map width.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

See set bkg tiles for setting CGB attribute maps with VBK REG.

#### See also

```
SHOW_BKG
set bkg data, set bkg tiles, set win submap, set tiles
```

```
20.41.4.48 set_bkg_based_submap() void set_bkg_based_submap (
```

```
uint8_t x,
uint8_t y,
uint8_t w,
uint8_t h,
const uint8_t * map,
uint8_t map_w,
uint8_t base_tile ) [inline]
```

Sets a rectangular area of the Background Tile Map using a sub-region from a source tile map. The offset value in **base\_tile** is added to the tile ID for each map entry.

## **Parameters**

X	X Start position in both the Source Tile Map and hardware Background Map tile coordinates. Range 0 - 255
У	Y Start position in both the Source Tile Map and hardware Background Map tile coordinates. Range 0 - 255
W	Width of area to set in tiles. Range 1 - 255
h	Height of area to set in tiles. Range 1 - 255
тар	Pointer to source tile map data
map_w	Width of source tile map in tiles. Range 1 - 255
base_tile	Offset each tile ID entry of the source map by this value. Range 1 - 255

This is identical to set\_bkg\_submap() except that it adds the **base\_tile** parameter for when a tile map's tiles don't start at index zero. (For example, the tiles used by the map range from 100 -> 120 in VRAM instead of 0 -> 20).

#### See also

set\_bkg\_submap for more details

Sets a rectangular area of the Background Tile Map Attributes using a sub-region from a source tile attribute map. Useful for scrolling implementations of maps larger than 32 x 32 tiles.

#### **Parameters**

X	X Start position in both the Source Tile Map and hardware Background Map tile coordinates. Range
	0 - 255
У	Y Start position in both the Source Tile Map and hardware Background Map tile coordinates. Range
	0 - 255
W	Width of area to set in tiles. Range 1 - 255
h	Height of area to set in tiles. Range 1 - 255
тар	Pointer to source tile map attribute data
тар⊷	Width of source tile map in tiles. Range 1 - 255
_w	

Entries are copied from **map** to the Background Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles, using **map\_w** as the rowstride for the source tile map.

The **x** and **y** parameters are in Source Tile Map tile coordinates. The location tiles will be written to on the hardware Background Map is derived from those, but only uses the lower 5 bits of each axis, for range of 0-31 (they are bit-masked: x & 0x1F and y & 0x1F). As a result the two coordinate systems are aligned together.

In order to transfer tile map data in a way where the coordinate systems are not aligned, an offset from the Source Tile Map pointer can be passed in:  $(map\_ptr + x + (y * map\_width))$ .

For example, if you want the tile id at 1, 2 from the source map to show up at 0, 0 on the hardware Background Map (instead of at 1, 2) then modify the pointer address that is passed in:  $map\_ptr + 1 + (2 * map\_width)$  Use this instead of  $set\_bkg\_tiles$  when the source map is wider than 32 tiles or when writing a width that does not match the source map width.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

See set\_bkg\_tiles for setting CGB attribute maps with VBK\_REG.

## See also

```
SHOW_BKG
set_bkg_data, set_bkg_attributes, set_win_submap, set_tiles
```

## Note

On the Game Boy this is only usable in Game Boy Color mode

```
20.41.4.50 get_bkg_tiles() void get_bkg_tiles ( uint8_t x,
```

```
uint8_t y,
uint8_t w,
uint8_t h,
uint8_t * tiles )
```

Copies a rectangular region of Background Tile Map entries into a buffer.

## **Parameters**

Х	X Start position in Background Map tile coordinates. Range 0 - 31	
У	Y Start position in Background Map tile coordinates. Range 0 - 31	
W	Width of area to copy in tiles. Range 0 - 31	
h	Height of area to copy in tiles. Range 0 - 31	
tiles	Pointer to destination buffer for Tile Map data	

#### Note

In general **avoid reading from VRAM** since that memory is not accessible at all times. It is also not supported by GBDK on the NES platform. See coding guidelines for more details.

Entries are copied into **tiles** from the Background Tile Map starting at **x**, **y** reading across for **w** tiles and down for **h** tiles

One byte per tile.

The buffer pointed to by **tiles** should be at least  $\mathbf{x} \times \mathbf{y}$  bytes in size.

See also

```
get_win_tiles, get_bkg_tile_xy, get_tiles, get_vram_byte
```

Set single tile t on background layer at x,y

#### **Parameters**

Χ	X-coordinate
у	Y-coordinate
t	tile index

## Returns

returns the address of tile, so you may use faster set\_vram\_byte() later

Set single attribute data a on background layer at x,y

X	X-coordinate
у	Y-coordinate
а	tile attributes

#### Returns

returns the address of tile attribute, so you may use faster set\_vram\_byte() later

Note

On the Game Boy this is only usable in Game Boy Color mode

Get single tile t on background layer at x,y

## **Parameters**

Х	X-coordinate
У	Y-coordinate

## Returns

returns tile index

Note

In general **avoid reading from VRAM** since that memory is not accessible at all times. It is also not supported by GBDK on the NES platform. See coding guidelines for more details.

Moves the Background Layer to the position specified in  $\mathbf{x}$  and  $\mathbf{y}$  in pixels.

## **Parameters**

X	X axis screen coordinate for Left edge of the Background
У	Y axis screen coordinate for Top edge of the Background

0,0 is the top left corner of the GB screen. The Background Layer wraps around the screen, so when part of it goes off the screen it appears on the opposite side (factoring in the larger size of the Background Layer versus the screen size).

The background layer is always under the Window Layer.

See also

```
SHOW_BKG, HIDE_BKG
```

Moves the Background relative to it's current position.

#### **Parameters**

X	Number of pixels to move the Background on the <b>X axis</b> Range: -128 - 127
У	Number of pixels to move the Background on the <b>Y axis</b> Range: -128 - 127

#### See also

move\_bkg

Get address of X,Y tile of window map

Sets VRAM Tile Pattern data for the Window / Background

#### **Parameters**

first_tile	Index of the first tile to write
nb_tiles	Number of tiles to write
data	Pointer to (2 bpp) source Tile Pattern data.

This is the same as set\_bkg\_data, since the Window Layer and Background Layer share the same Tile pattern data.

## See also

```
set_bkg_data
set_win_tiles, set_bkg_data, set_data
SHOW_WIN, HIDE_WIN
```

Sets VRAM Tile Pattern data for the Window / Background using 1bpp source data

#### **Parameters**

first_tile	Index of the first tile to write
nb_tiles	Number of tiles to write
data	Pointer to (1bpp) source Tile Pattern data

This is the same as set\_bkg\_1bpp\_data, since the Window Layer and Background Layer share the same Tile pattern data.

For a given bit that represent a pixel:

• 0 will be expanded into the Background color

· 1 will be expanded into the Foreground color

See set 1bpp colors for details about setting the Foreground and Background colors.

#### See also

```
set_bkg_data, set_win_data, set_1bpp_colors
set_bkg_1bpp_data, set_sprite_1bpp_data
```

Copies from Window / Background VRAM Tile Pattern data into a buffer

#### **Parameters**

first_tile	Index of the first Tile to read from
nb_tiles	Number of Tiles to read
data	Pointer to destination buffer for Tile Pattern Data

#### Note

In general **avoid reading from VRAM** since that memory is not accessible at all times. It is also not supported by GBDK on the NES platform. See coding guidelines for more details.

This is the same as get\_bkg\_data, since the Window Layer and Background Layer share the same Tile pattern data.

## See also

```
get bkg data, get data
```

Sets a rectangular region of the Window Tile Map.

#### **Parameters**

X	X Start position in Window Map tile coordinates. Range 0 - 31
У	Y Start position in Window Map tile coordinates. Range 0 - 31
W	Width of area to set in tiles. Range 1 - 32
h	Height of area to set in tiles. Range 1 - 32
tiles	Pointer to source tile map data

Entries are copied from map at **tiles** to the Window Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles.

Use set\_win\_submap() instead when:

- · Source map is wider than 32 tiles.
- Writing a width that does not match the source map width and more than one row high at a time.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

Note

Patterns 128-255 overlap with patterns 128-255 of the sprite Tile Pattern table.

GBC only: VBK REG determines whether Tile Numbers or Tile Attributes get set.

- VBK\_REG = VBK\_TILES Tile Numbers are written
- VBK\_REG = VBK\_ATTRIBUTES Tile Attributes are written

For more details about GBC Tile Attributes see set\_bkg\_tiles.

See also

SHOW\_WIN, HIDE\_WIN, set\_win\_submap, set\_bkg\_tiles, set\_bkg\_data, set\_tiles

Sets a rectangular region of the Window Tile Map. The offset value in **base\_tile** is added to the tile ID for each map entry.

#### **Parameters**

Х	X Start position in Window Map tile coordinates. Range 0 - 31
У	Y Start position in Window Map tile coordinates. Range 0 - 31
W	Width of area to set in tiles. Range 1 - 32
h	Height of area to set in tiles. Range 1 - 32
tiles	Pointer to source tile map data
base_tile	Offset each tile ID entry of the source map by this value. Range 1 - 255

This is identical to set\_win\_tiles() except that it adds the **base\_tile** parameter for when a tile map's tiles don't start at index zero. (For example, the tiles used by the map range from 100 -> 120 in VRAM instead of 0 -> 20).

See also

set win tiles for more details

Sets a rectangular area of the Window Tile Map using a sub-region from a source tile map.

### **Parameters**

x X Start position in both the Source Tile Map and hardware Window Map tile coordinates. Range 0 - 255

#### **Parameters**

У	Y Start position in both the Source Tile Map and hardware Window Map tile coordinates. Range 0 - 255
W	Width of area to set in tiles. Range 1 - 255
h	Height of area to set in tiles. Range 1 - 255
тар	Pointer to source tile map data
тар⊷	Width of source tile map in tiles. Range 1 - 255
_ <i>w</i>	

Entries are copied from **map** to the Window Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles, using **map\_w** as the rowstride for the source tile map.

The **x** and **y** parameters are in Source Tile Map tile coordinates. The location tiles will be written to on the hardware Background Map is derived from those, but only uses the lower 5 bits of each axis, for range of 0-31 (they are bit-masked: x & 0x1F and y & 0x1F). As a result the two coordinate systems are aligned together.

In order to transfer tile map data in a way where the coordinate systems are not aligned, an offset from the Source Tile Map pointer can be passed in:  $(map\_ptr + x + (y * map\_width))$ .

For example, if you want the tile id at 1, 2 from the source map to show up at 0, 0 on the hardware Background Map (instead of at 1, 2) then modify the pointer address that is passed in:  $map\_ptr + 1 + (2 * map\_width)$  Use this instead of  $set\_win\_tiles$  when the source map is wider than 32 tiles or when writing a width that does not match the source map width.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

GBC only: VBK\_REG determines whether Tile Numbers or Tile Attributes get set.

- VBK\_REG = VBK\_TILES Tile Numbers are written
- VBK REG = VBK ATTRIBUTES Tile Attributes are written

See set bkg tiles for details about CGB attribute maps with VBK REG.

## See also

SHOW\_WIN, HIDE\_WIN, set\_win\_tiles, set\_bkg\_submap, set\_bkg\_tiles, set\_bkg\_data, set\_tiles

Sets a rectangular area of the Window Tile Map using a sub-region from a source tile map. The offset value in **base tile** is added to the tile ID for each map entry.

X	X Start position in both the Source Tile Map and hardware Window Map tile coordinates. Range 0 - 255
У	Y Start position in both the Source Tile Map and hardware Window Map tile coordinates. Range 0 - 255
W	Width of area to set in tiles. Range 1 - 255
h	Height of area to set in tiles. Range 1 - 255
тар	Pointer to source tile map data
map_w	Width of source tile map in tiles. Range 1 - 255
base_tile	Offset each tile ID entry of the source map by this value. Range 1 - 255

This is identical to set\_win\_submap() except that it adds the **base\_tile** parameter for when a tile map's tiles don't start at index zero. (For example, the tiles used by the map range from 100 -> 120 in VRAM instead of 0 -> 20).

#### See also

set\_win\_submap for more details

Copies a rectangular region of Window Tile Map entries into a buffer.

#### **Parameters**

X	X Start position in Window Map tile coordinates. Range 0 - 31
У	Y Start position in Window Map tile coordinates. Range 0 - 31
W	Width of area to copy in tiles. Range 0 - 31
h	Height of area to copy in tiles. Range 0 - 31
tiles	Pointer to destination buffer for Tile Map data

## Note

In general **avoid reading from VRAM** since that memory is not accessible at all times. It is also not supported by GBDK on the NES platform. See coding guidelines for more details.

Entries are copied into **tiles** from the Window Tile Map starting at  $\mathbf{x}$ ,  $\mathbf{y}$  reading across for  $\mathbf{w}$  tiles and down for  $\mathbf{h}$  tiles.

One byte per tile.

The buffer pointed to by **tiles** should be at least  $\mathbf{x} \times \mathbf{y}$  bytes in size.

#### See also

```
get_bkg_tiles, get_bkg_tile_xy, get_tiles, get_vram_byte
```

Set single tile t on window layer at x,y

## **Parameters**

Χ	X-coordinate
У	Y-coordinate
t	tile index

#### Returns

returns the address of tile, so you may use faster set\_vram\_byte() later

```
20.41.4.66 get_win_tile_xy() uint8_t get_win_tile_xy ( uint8_t x, uint8_t y)
```

Get single tile t on window layer at x,y

## **Parameters**

X	X-coordinate
У	Y-coordinate

#### Returns

returns the tile index

#### Note

In general **avoid reading from VRAM** since that memory is not accessible at all times. It is also not supported by GBDK on the NES platform. See coding guidelines for more details.

Moves the Window to the **x**, **y** position on the screen.

#### **Parameters**

X	X coordinate for Left edge of the Window (actual displayed location will be X - 7)
У	Y coordinate for Top edge of the Window

7,0 is the top left corner of the screen in Window coordinates. The Window is locked to the bottom right corner. The Window is always over the Background layer.

## See also

```
SHOW_WIN, HIDE_WIN
```

Move the Window relative to its current position.

## **Parameters**

Х	Number of pixels to move the window on the <b>X axis</b> Range: -128 - 127
У	Number of pixels to move the window on the <b>Y axis</b> Range: -128 - 127

## See also

move\_win

Sets VRAM Tile Pattern data for Sprites

## **Parameters**

first_tile	Index of the first tile to write
nb_tiles	Number of tiles to write
data	Pointer to (2 bpp) source Tile Pattern data

Writes **nb\_tiles** tiles to VRAM starting at **first\_tile**, tile data is sourced from **data**. Each Tile is 16 bytes in size (8x8 pixels, 2 bits-per-pixel).

Note

Sprite Tiles 128-255 share the same memory region as Background Tiles 128-255.

GBC only: VBK\_REG determines which bank of tile patterns are written to.

- VBK\_REG = VBK\_BANK\_0 indicates the first bank
- VBK\_REG = VBK\_BANK\_1 indicates the second

Sets VRAM Tile Pattern data for Sprites using 1bpp source data

#### **Parameters**

first_tile	Index of the first tile to write
nb_tiles	Number of tiles to write
data	Pointer to (1bpp) source Tile Pattern data

Similar to set\_sprite\_data, except source data is 1 bit-per-pixel which gets expanded into 2 bits-per-pixel. For a given bit that represent a pixel:

- · 0 will be expanded into the Background color
- · 1 will be expanded into the Foreground color

See set\_1bpp\_colors for details about setting the Foreground and Background colors.

See also

```
SHOW_SPRITES, HIDE_SPRITES, set_sprite_tile set_bkg_1bpp_data, set_win_1bpp_data
```

Copies from Sprite VRAM Tile Pattern data into a buffer

#### **Parameters**

first_tile	Index of the first tile to read from
nb_tiles	Number of tiles to read
data	Pointer to destination buffer for Tile Pattern data

#### Note

In general **avoid reading from VRAM** since that memory is not accessible at all times. It is also not supported by GBDK on the NES platform. See coding guidelines for more details.

Copies **nb\_tiles** tiles from VRAM starting at **first\_tile**, tile data is copied into **data**.

Each Tile is 16 bytes, so the buffer pointed to by data should be at least nb\_tiles x 16 bytes in size.

```
20.41.4.72 SET_SHADOW_OAM_ADDRESS() void SET_SHADOW_OAM_ADDRESS ( void * address ) [inline]
```

Enable OAM DMA copy each VBlank and set it to transfer any 256-byte aligned array

Sets sprite number **nb\_in** the **OAM** to **display** tile number **\_\_tile**.

#### **Parameters**

nb	Sprite number, range 0 - 39
tile	Selects a tile (0 - 255) from memory at 8000h - 8FFFh In CGB Mode this could be either in VRAM Bank 0 or 1, depending on Bit 3 of the OAM Attribute Flag (see set_sprite_prop)

## In 8x16 mode:

- The sprite will also display the next tile (tile + 1) directly below (y + 8) the first tile.
- The lower bit of the tile number is ignored: the upper 8x8 tile is (**tile** & 0xFE), and the lower 8x8 tile is (**tile** | 0x01).
- See: SPRITES\_8x16

Returns the tile number of sprite number **nb** in the OAM.

#### **Parameters**

```
nb Sprite number, range 0 - 39
```

## See also

set\_sprite\_tile for more details

Sets the OAM Property Flags of sprite number **nb** to those defined in **prop**.

### **Parameters**

nb	Sprite number, range 0 - 39
prop	Property setting (see bitfield description)

## The bits in **prop** represent:

- Bit 7 Priority flag. When this is set the sprites appear behind the background and window layer.
  - 0: infront
  - 1: behind
- · Bit 6 Vertical flip. Dictates which way up the sprite is drawn vertically.
  - 0: normal
  - 1:upside down
- Bit 5 Horizontal flip. Dictates which way up the sprite is drawn horizontally.
  - 0: normal
  - 1:back to front
- Bit 4 DMG/Non-CGB Mode Only. Assigns either one of the two b/w palettes to the sprite.
  - 0: OBJ palette 0
  - 1: OBJ palette 1
- Bit 3 GBC only. Dictates from which bank of Sprite Tile Patterns the tile is taken.
  - 0: Bank 0
  - 1: Bank 1
- Bit 2 See bit 0.
- Bit 1 See bit 0.
- Bit 0 GBC only. Bits 0-2 indicate which of the 7 OBJ colour palettes the sprite is assigned.

It's recommended to use GBDK constants (eg: S\_FLIPY) to configure sprite properties as these are crossplatform.

```
// Load palette data into the first palette
set_sprite_palette(4, 1, exampleSprite_palettes)
// Set the OAM value for the sprite
// These flags tell the sprite to flip both vertically and horizontally.
set_sprite_prop(0, S_FLIPY | S_FLIPX);
```

## See also

## S PALETTE, S FLIPX, S FLIPY, S PRIORITY

Returns the OAM Property Flags of sprite number **nb**.

## **Parameters**

```
nb Sprite number, range 0 - 39
```

## See also

set\_sprite\_prop for property bitfield settings

```
uint8_t x,
uint8_t y) [inline]
```

Moves sprite number  $\mathbf{nb}$  to the  $\mathbf{x}$ ,  $\mathbf{y}$  position on the screen.

#### **Parameters**

nb	Sprite number, range 0 - 39
Х	X Position. Specifies the sprites horizontal position on the screen (minus 8).
	An offscreen value ( $X=0$ or $X>=168$ ) hides the sprite, but the sprite still affects the priority ordering - a
	better way to hide a sprite is to set its Y-coordinate offscreen.
У	Y Position. Specifies the sprites vertical position on the screen (minus 16).
	An offscreen value (for example, $Y=0$ or $Y>=160$ ) hides the sprite.

Moving the sprite to 0,0 (or similar off-screen location) will hide it.

Moves sprite number **nb** relative to its current position.

#### **Parameters**

nb	Sprite number, range 0 - 39
Х	Number of pixels to move the sprite on the <b>X axis</b> Range: -128 - 127
У	Number of pixels to move the sprite on the <b>Y axis</b> Range: -128 - 127

## See also

move\_sprite for more details about the X and Y position

Hides sprite number **nb** by moving it to zero position by Y.

### **Parameters**

```
nb Sprite number, range 0 - 39
```

### See also

hide\_sprites\_range, HIDE\_SPRITES

Copies arbitrary data to an address in VRAM without taking into account the state of LCDC bits 3 or 4.

#### **Parameters**

vram_addr	Pointer to destination VRAM Address
data	Pointer to source buffer
len	Number of bytes to copy

Copies len bytes from a buffer at data to VRAM starting at vram\_addr.

GBC only: VBK\_REG determines which bank of tile patterns are written to.

- VBK\_REG = VBK\_BANK\_0 indicates the first bank
- VBK\_REG = VBK\_BANK\_1 indicates the second

#### See also

```
set_bkg_data, set_win_data, set_bkg_tiles, set_win_tiles, set_tile_data, set_tiles
```

Copies arbitrary data from an address in VRAM into a buffer without taking into account the state of LCDC bits 3 or 4.

#### **Parameters**

vram_addr	Pointer to source VRAM Address
data	Pointer to destination buffer
len	Number of bytes to copy

## Note

In general **avoid reading from VRAM** since that memory is not accessible at all times. It is also not supported by GBDK on the NES platform. See coding guidelines for more details.

Copies **len** bytes from VRAM starting at **vram\_addr** into a buffer at **data**. GBC only: VBK REG determines which bank of tile patterns are written to.

- VBK REG = VBK BANK 0 indicates the first bank
- VBK\_REG = VBK\_BANK\_1 indicates the second

#### See also

```
get_bkg_data, get_win_data, get_bkg_tiles, get_win_tiles, get_tiles
```

Copies arbitrary data from an address in VRAM into a buffer

dest	Pointer to destination buffer (may be in VRAM)
sour	Pointer to source buffer (may be in VRAM)
len	Number of bytes to copy

Copies **len** bytes from or to VRAM starting at **sour** into a buffer or to VRAM at **dest**. GBC only: VBK\_REG determines which bank of tile patterns are written to.

- VBK\_REG = VBK\_BANK\_0 indicates the first bank
- VBK\_REG = VBK\_BANK\_1 indicates the second

Sets a rectangular region of Tile Map entries at a given VRAM Address without taking into account the state of LCDC bit 3.

#### **Parameters**

X	X Start position in Map tile coordinates. Range 0 - 31
У	Y Start position in Map tile coordinates. Range 0 - 31
W	Width of area to set in tiles. Range 1 - 32
h	Height of area to set in tiles. Range 1 - 32
vram_addr	Pointer to destination VRAM Address
tiles	Pointer to source Tile Map data

Entries are copied from **tiles** to Tile Map at address vram\_addr starting at **x**, **y** writing across for **w** tiles and down for **h** tiles.

One byte per source tile map entry.

There are two 32x32 Tile Maps in VRAM at addresses 9800h-9BFFh and 9C00h-9FFFh.

GBC only: VBK\_REG determines whether Tile Numbers or Tile Attributes get set.

- VBK\_REG = VBK\_TILES Tile Numbers are written
- VBK\_REG = VBK\_ATTRIBUTES Tile Attributes are written

### See also

```
set_bkg_tiles, set_win_tiles
```

Sets VRAM Tile Pattern data starting from given base address without taking into account the state of LCDC bit 4.

first_tile	Index of the first tile to write
nb_tiles	Number of tiles to write
data	Pointer to (2 bpp) source Tile Pattern data.
base	MSB of the destination address in VRAM (usually 0x80 or 0x90 which gives 0x8000 or 0x9000)

See also

```
set_bkg_data, set_win_data, set_data
```

Copies a rectangular region of Tile Map entries from a given VRAM Address into a buffer without taking into account the state of LCDC bit 3.

#### **Parameters**

X	X Start position in Background Map tile coordinates. Range 0 - 31
У	Y Start position in Background Map tile coordinates. Range 0 - 31
W	Width of area to copy in tiles. Range 0 - 31
h	Height of area to copy in tiles. Range 0 - 31
vram_addr	Pointer to source VRAM Address
tiles	Pointer to destination buffer for Tile Map data

#### Note

In general **avoid reading from VRAM** since that memory is not accessible at all times. It is also not supported by GBDK on the NES platform. See coding guidelines for more details.

Entries are copied into **tiles** from the Background Tile Map starting at **x**, **y** reading across for **w** tiles and down for **h** tiles.

One byte per tile.

There are two 32x32 Tile Maps in VRAM at addresses 9800h - 9BFFh and 9C00h - 9FFFh.

The buffer pointed to by tiles should be at least  $x \times y$  bytes in size.

See also

```
get_bkg_tiles, get_win_tiles
```

Sets VRAM Tile Pattern data in the native format

## **Parameters**

first_tile	Index of the first tile to write (0 - 511)
nb_tiles	Number of tiles to write
data	Pointer to source Tile Pattern data.

When first\_tile is larger than 256 on the GB/AP, it will write to sprite data instead of background data. The bit depth of the source Tile Pattern data depends on which console is being used:

- · Game Boy/Analogue Pocket: loads 2bpp tiles data
- · SMS/GG: loads 4bpp tile data

Sets VRAM Tile Pattern data for the Background / Window in the native format

#### **Parameters**

first_tile	Index of the first tile to write
nb_tiles	Number of tiles to write
data	Pointer to source tile data

Writes **nb\_tiles** tiles to VRAM starting at **first\_tile**, tile data is sourced from **data**. GBC only: VBK\_REG determines which bank of tile patterns are written to.

- VBK\_REG = VBK\_BANK\_0 indicates the first bank
- VBK\_REG = VBK\_BANK\_1 indicates the second

#### See also

```
set_win_data, set_tile_data
```

Sets VRAM Tile Pattern data for Sprites in the native format

### **Parameters**

first_tile	Index of the first tile to write
nb_tiles	Number of tiles to write
data	Pointer to source tile data

Writes **nb\_tiles** tiles to VRAM starting at **first\_tile**, tile data is sourced from **data**. GBC only: VBK\_REG determines which bank of tile patterns are written to.

- VBK\_REG = VBK\_BANK\_0 indicates the first bank
- VBK\_REG = VBK\_BANK\_1 indicates the second

```
20.41.4.89 init_win() void init_win ( uint8_t c)
```

Initializes the entire Window Tile Map with Tile Number c

Note

This function avoids writes during modes 2 & 3

Initializes the entire Background Tile Map with Tile Number c

#### **Parameters**

```
c Tile number to fill with
```

Note

This function avoids writes during modes 2 & 3

Fills the VRAM memory region  ${\boldsymbol s}$  of size  ${\boldsymbol n}$  with Tile Number  ${\boldsymbol c}$ 

#### **Parameters**

s	Start address in VRAM
С	Tile number to fill with
n	Size of memory region (in bytes) to fill

Note

This function avoids writes during modes 2 & 3

Fills a rectangular region of Tile Map entries for the Background layer with tile.

X	X Start position in Background Map tile coordinates. Range 0 - 31
У	Y Start position in Background Map tile coordinates. Range 0 - 31
W	Width of area to set in tiles. Range 0 - 31
h	Height of area to set in tiles. Range 0 - 31
tile	Fill value

```
\textbf{20.41.4.93} \quad \textbf{fill\_win\_rect()} \quad \texttt{void fill\_win\_rect} \ \ (
```

```
uint8_t x,
uint8_t y,
uint8_t w,
uint8_t h,
uint8_t tile )
```

Fills a rectangular region of Tile Map entries for the Window layer with tile.

#### **Parameters**

X	X Start position in Window Map tile coordinates. Range 0 - 31
У	Y Start position in Window Map tile coordinates. Range 0 - 31
W	Width of area to set in tiles. Range 0 - 31
h	Height of area to set in tiles. Range 0 - 31
tile	Fill value

## 20.41.5 Variable Documentation

```
20.41.5.1 c void c
20.41.5.2 d void d
20.41.5.3 e void e
20.41.5.4 h void h
20.41.5.5 I void 1
Initial value:
   __asm__("ei")
20.41.5.6 _cpu uint8_t _cpu [extern]
GB CPU type
See also
    DMG_TYPE, MGB_TYPE, CGB_TYPE, cpu_fast(), cpu_slow(), _is_GBA
20.41.5.7 _is_GBA uint8_t _is_GBA [extern]
GBA detection
See also
     GBA_DETECTED, GBA_NOT_DETECTED, _cpu
20.41.5.8 sys_time volatile uint16_t sys_time [extern]
Global Time Counter in VBL periods (60Hz)
Increments once per Frame
```

Will wrap around every  $\sim$ 18 minutes (unsigned 16 bits = 65535 / 60 / 60 = 18.2)

```
20.41.5.9 _io_status volatile uint8_t _io_status [extern]
Serial Link: Current IO Status. An OR of IO *
20.41.5.10 _io_in volatile uint8_t _io_in [extern]
Serial Link: Byte just read after calling receive byte()
20.41.5.11 _io_out volatile uint8_t _io_out [extern]
Serial Link: Write byte to send here before calling send_byte()
20.41.5.12 _current_bank ___REG _current_bank
Tracks current active ROM bank
In most cases the CURRENT BANK macro for this variable is recommended for use instead of the variable itself.
The active bank number is not tracked by _current_bank when SWITCH_ROM_MBC5_8M is used.
This variable is updated automatically when you call SWITCH_ROM_MBC1 or SWITCH_ROM_MBC5,
SWITCH_ROM(), or call a BANKED function.
See also
     SWITCH ROM MBC1(), SWITCH ROM MBC5(), SWITCH ROM()
20.41.5.13 b void b
20.41.5.14 _current_1bpp_colors uint16_t _current_1bpp_colors [extern]
20.41.5.15 _map_tile_offset uint8_t _map_tile_offset [extern]
20.41.5.16 _submap_tile_offset uint8_t _submap_tile_offset [extern]
20.41.5.17 shadow_OAM volatile struct OAM_item_t shadow_OAM[] [extern]
Shadow OAM array in WRAM, that is DMA-transferred into the real OAM each VBlank
20.41.5.18 _shadow_OAM_base ___REG _shadow_OAM_base
MSB of shadow_OAM address is used by OAM DMA copying routine
```

## 20.42 gbdk-lib/include/gb/gbdecompress.h File Reference

```
#include <types.h>
#include <stdint.h>
```

#### **Functions**

- uint16\_t gb\_decompress (const uint8\_t \*sour, uint8\_t \*dest)
- void gb\_decompress\_bkg\_data (uint8\_t first\_tile, const uint8\_t \*sour)
- void gb\_decompress\_win\_data (uint8\_t first\_tile, const uint8\_t \*sour)
- void gb\_decompress\_sprite\_data (uint8\_t first\_tile, const uint8\_t \*sour)

## 20.42.1 Detailed Description

GB-Compress decompressor Compatible with the compression used in GBTD

See also

utility\_gbcompress "gbcompress"

GB-Compress decompressor Compatible with the compression used in GBTD

#### 20.42.2 Function Documentation

gb-decompress data from sour into dest

### **Parameters**

sour	Pointer to source gb-compressed data
dest	Pointer to destination buffer/address

Will decompress **all** of it's data to destination without stopping until the end of compressed data is reached. It is not possible to set a limit, so ensure the destination buffer has sufficient space to avoid an overflow.

See also

gb\_decompress\_bkg\_data, gb\_decompress\_win\_data, gb\_decompress\_sprite\_data, rle\_decompress

gb-decompress data from sour into dest

## **Parameters**

sour	Pointer to source gb-compressed data
dest	Pointer to destination buffer/address

## Returns

Return value is number of bytes decompressed

See also

gb decompress bkg data, gb decompress win data, gb decompress sprite data

gb-decompress background tiles into VRAM

### **Parameters**

first_tile	Index of the first tile to write
sour	Pointer to (gb-compressed 2 bpp) source Tile Pattern data.

Note: This function avoids writes during modes 2 & 3

Will decompress **all** of it's data to destination without stopping until the end of compressed data is reached. It is not possible to set a limit, so ensure the destination buffer has sufficient space to avoid an overflow.

See also

 $gb\_decompress\_bkg\_data, \\ gb\_decompress\_win\_data, \\ gb\_decompress\_sprite\_data$ 

## 

gb-decompress window tiles into VRAM

#### **Parameters**

first_tile	Index of the first tile to write
sour	Pointer to (gb-compressed 2 bpp) source Tile Pattern data.

This is the same as gb\_decompress\_bkg\_data, since the Window Layer and Background Layer share the same Tile pattern data.

Note: This function avoids writes during modes 2 & 3

Will decompress **all** of it's data to destination without stopping until the end of compressed data is reached. It is not possible to set a limit, so ensure the destination buffer has sufficient space to avoid an overflow.

See also

gb\_decompress, gb\_decompress\_bkg\_data, gb\_decompress\_sprite\_data

gb-decompress sprite tiles into VRAM

#### **Parameters**

first_tile	Index of the first tile to write
sour	Pointer to source compressed data

Note: This function avoids writes during modes 2 & 3

Will decompress **all** of it's data to destination without stopping until the end of compressed data is reached. It is not possible to set a limit, so ensure the destination buffer has sufficient space to avoid an overflow.

See also

gb\_decompress, gb\_decompress\_bkg\_data, gb\_decompress\_win\_data

## 20.43 gbdk-lib/include/gbdk/gbdecompress.h File Reference

```
#include <gb/gbdecompress.h>
```

## 20.44 gbdk-lib/include/sms/gbdecompress.h File Reference

```
#include <types.h>
#include <stdint.h>
```

#### **Functions**

uint16\_t gb\_decompress (const uint8\_t \*sour, uint8\_t \*dest) Z88DK\_CALLEE PRESERVES\_REGS(b

#### **Variables**

• uint16 t c

## 20.44.1 Function Documentation

gb-decompress data from sour into dest

### **Parameters**

sour	Pointer to source gb-compressed data
dest	Pointer to destination buffer/address

## Returns

Return value is number of bytes decompressed

## See also

gb\_decompress\_bkg\_data, gb\_decompress\_win\_data, gb\_decompress\_sprite\_data

## 20.44.2 Variable Documentation

```
20.44.2.1 c uint16_t c
```

## 20.45 gbdk-lib/include/gb/hardware.h File Reference

```
#include <types.h>
```

#### **Macros**

- #define BYTES extern UBYTE
- #define \_\_BYTE\_REG extern volatile UBYTE
- #define \_\_\_REG extern volatile SFR
- #define rP1 P1\_REG
- #define P1F\_5 0b00100000
- #define P1F\_4 0b00010000
- #define P1F 3 0b00001000
- #define P1F\_2 0b00000100
- #define P1F\_1 0b00000010
- #define P1F\_0 0b00000001
- #define P1F\_GET\_DPAD P1F\_5
- #define P1F GET BTN P1F 4
- #define P1F\_GET\_NONE (P1F\_4 | P1F\_5)
- #define rSB SB REG
- #define rSC SC\_REG

- #define SIOF\_XFER\_START 0b10000000
- #define SIOF\_CLOCK\_INT 0b00000001
- #define SIOF\_CLOCK\_EXT 0b00000000
- #define SIOF\_SPEED\_1X 0b00000000
- #define SIOF SPEED 32X 0b00000010
- #define SIOF\_B\_CLOCK 0
- #define SIOF B SPEED 1
- #define SIOF\_B\_XFER\_START 7
- #define SCF\_START SIOF\_XFER\_START
- #define SCF SOURCE SIOF CLOCK INT
- #define SCF SPEED SIOF SPEED 32X
- #define rDIV DIV REG
- #define rTIMA TIMA\_REG
- #define rTMA TMA REG
- #define rTAC TAC\_REG
- #define TACF START 0b00000100
- #define TACF STOP 0b00000000
- #define TACF 4KHZ 0b00000000
- #define TACF 16KHZ 0b00000011
- #define TACF\_65KHZ 0b00000010
- #define TACF\_262KHZ 0b00000001
- #define rIF IF REG
- #define rAUD1SWEEP NR10 REG
- #define AUD1SWEEP\_UP 0b00000000
- #define AUD1SWEEP DOWN 0b00001000
- #define AUD1SWEEP\_TIME(x) ((x) << 4)</li>
- #define AUD1SWEEP\_LENGTH(x) (x)
- #define rAUD1LEN NR11 REG
- #define rAUD1ENV NR12 REG
- #define rAUD1LOW NR13\_REG
- #define rAUD1HIGH NR14 REG
- #define rAUD2LEN NR21 REG
- #define rAUD2ENV NR22\_REG
- #define rAUD2LOW NR23\_REG
- #define rAUD2HIGH NR24\_REG
- #define rAUD3ENA NR30\_REG
- #define rAUD3LEN NR31\_REG
- #define rAUD3LEVEL NR32 REG
- #define rAUD3LOW NR33 REG
- #define rAUD3HIGH NR34 REG
- #define rAUD4LEN NR41 REG
- #define rAUD4ENV NR42\_REG
- #define rAUD4POLY NR43\_REG
- #define AUD4POLY\_WIDTH\_15BIT 0x00
- #define AUD4POLY\_WIDTH\_7BIT 0x08
- #define rAUD4GO NR44\_REG
- #define rAUDVOL NR50 REG
- #define AUDVOL\_VOL\_LEFT(x) ((x) << 4)</li>
- #define AUDVOL\_VOL\_RIGHT(x) ((x))
- #define AUDVOL\_VIN\_LEFT 0b10000000
- #define AUDVOL VIN RIGHT 0b00001000
- #define rAUDTERM NR51\_REG
- #define AUDTERM 4 LEFT 0b10000000
- #define AUDTERM 3 LEFT 0b01000000
- #define AUDTERM\_2\_LEFT 0b00100000

- #define AUDTERM\_1\_LEFT 0b00010000
- #define AUDTERM\_4\_RIGHT 0b00001000
- #define AUDTERM\_3\_RIGHT 0b00000100
- #define AUDTERM\_2\_RIGHT 0b00000010
- #define AUDTERM 1 RIGHT 0b00000001
- #define rAUDENA NR52 REG
- #define AUDENA ON 0b10000000
- #define AUDENA\_OFF 0b00000000
- #define rLCDC LCDC\_REG#define LCDCF\_OFF 0b00000000
- #define LCDCF ON 0b10000000
- #define LCDCF WIN9800 0b00000000
- #define LCDCF\_WIN9C00 0b01000000
- #define LCDCF WINOFF 0b00000000
- #define LCDCF\_WINON 0b00100000
- #define LCDCF BG8800 0b00000000
- #define LCDCF BG8000 0b00010000
- #define LCDCF BG9800 0b00000000
- #define LCDCF\_BG9C00 0b00001000
- #define LCDCF\_OBJ8 0b00000000
- #define LCDCF\_OBJ16 0b00000100
- #define LCDCF OBJOFF 0b00000000
- #define LCDCF OBJON 0b00000010
- #define LCDCF\_BGOFF 0b00000000
- #define LCDCF BGON 0b00000001
- #define LCDCF\_B\_ON 7
- #define LCDCF\_B\_WIN9C00 6
- #define LCDCF\_B\_WINON 5
- #define LCDCF\_B\_BG8000 4
- #define LCDCF\_B\_BG9C00 3
- #define LCDCF\_B\_OBJ16 2
- #define LCDCF\_B\_OBJON 1
- #define LCDCF\_B\_BGON 0
- #define rSTAT STAT\_REG
- #define STATF\_LYC 0b01000000
- #define STATF\_MODE10 0b00100000
- #define STATF\_MODE01 0b00010000
- #define STATF\_MODE00 0b00001000
- #define STATF\_LYCF 0b00000100
- #define STATF\_HBL 0b00000000
- #define STATF VBL 0b00000001
- #define STATF\_OAM 0b00000010
- #define STATF\_LCD 0b00000011
- #define STATF\_BUSY 0b00000010
- #define STATF\_B\_LYC 6
- #define STATF B MODE10 5
- #define STATF\_B\_MODE01 4
- #define STATF\_B\_MODE00 3
- #define STATF\_B\_LYCF 2
- #define STATF\_B\_VBL 0
- #define STATF B OAM 1
- #define STATF\_B\_BUSY 1
- #define rSCY
- #define rSCX SCX REG
- #define rLY LY\_REG

- #define rLYC LYC\_REG
- #define rDMA DMA\_REG
- #define rBGP BGP\_REG
- #define rOBP0 OBP0 REG
- #define rOBP1 OBP1 REG
- #define rWY WY\_REG
- #define rWX WX REG
- #define rKEY1 KEY1\_REG
- #define rSPD KEY1\_REG
- #define KEY1F DBLSPEED 0b10000000
- #define KEY1F PREPARE 0b00000001
- #define rVBK VBK REG
- #define VBK\_BANK\_0 0
- #define VBK TILES 0
- #define VBK\_BANK\_1 1
- #define VBK ATTRIBUTES 1
- #define BKGF\_PRI 0b10000000
- #define BKGF\_YFLIP 0b01000000
- #define BKGF XFLIP 0b00100000
- #define BKGF\_BANK0 0b00000000
- #define BKGF\_BANK1 0b00001000
- #define BKGF CGB PAL0 0b00000000
- #define BKGF\_CGB\_PAL1 0b00000001
- #define BKGF\_CGB\_PAL2 0b00000010
- #define BKGF CGB PAL3 0b00000011
- #define BKGF\_CGB\_PAL4 0b00000100
- #define BKGF\_CGB\_PAL5 0b00000101
- #define BKGF\_CGB\_PAL6 0b00000110
- #define BKGF\_CGB\_PAL7 0b00000111
- #define rHDMA1\_REG
- #define rHDMA2 HDMA2 REG
- #define rHDMA3 HDMA3 REG
- #define rHDMA4 HDMA4\_REG
- #define rHDMA5 HDMA5\_REG
- #define HDMA5F MODE GP 0b00000000
- #define HDMA5F MODE HBL 0b10000000
- #define HDMA5F BUSY 0b10000000
- #define rRP RP\_REG
- #define RPF ENREAD 0b11000000
- #define RPF DATAIN 0b00000010
- #define RPF WRITE HI 0b00000001
- #define RPF\_WRITE\_LO 0b00000000
- #define rBCPS BCPS\_REG
- #define BCPSF\_AUTOINC 0b10000000
- #define rBCPD BCPD REG
- #define rOCPS OCPS REG
- #define OCPSF AUTOINC 0b10000000
- #define rOCPD OCPD\_REG
- #define rSVBK SVBK\_REG
- #define rSMBK SVBK\_REG
- #define rPCM12 PCM12 REG
- #define rPCM34 PCM34\_REG
- #define rIE IE\_REG
- #define IEF\_HILO 0b00010000
- #define IEF\_SERIAL 0b00001000

- #define IEF\_TIMER 0b00000100
- #define IEF\_STAT 0b00000010
- #define IEF\_VBLANK 0b00000001
- #define AUDLEN DUTY 12 5 0b00000000
- #define AUDLEN DUTY 25 0b01000000
- #define AUDLEN DUTY 50 0b10000000
- #define AUDLEN\_DUTY\_75 0b11000000
- #define AUDLEN\_LENGTH(x) (x)
- #define AUDENV VOL(x) ((x) << 4)</li>
- #define AUDENV UP 0b00001000
- #define AUDENV DOWN 0b00000000
- #define AUDENV\_LENGTH(x) (x)
- #define AUDHIGH\_RESTART 0b10000000
- #define AUDHIGH\_LENGTH\_ON 0b01000000
- #define AUDHIGH LENGTH OFF 0b00000000
- #define OAMF PRI 0b10000000
- #define OAMF\_YFLIP 0b01000000
- #define OAMF\_XFLIP 0b00100000
- #define OAMF\_PAL0 0b00000000
- #define OAMF PAL1 0b00010000
- #define OAMF BANKO 0b00000000
- #define OAMF BANK1 0b00001000
- #define OAMF\_CGB\_PAL0 0b00000000
- #define OAMF\_CGB\_PAL1 0b00000001
- #define OAMF\_CGB\_PAL2 0b00000010
- #define OAMF CGB PAL3 0b00000011
- #define OAMF CGB PAL4 0b00000100
- #define OAMF\_CGB\_PAL5 0b00000101
- #define OAMF\_CGB\_PAL6 0b00000110
- #define OAMF\_CGB\_PAL7 0b00000111
- #define OAMF\_PALMASK 0b00000111
- #define DEVICE SCREEN X OFFSET 0
- #define DEVICE\_SCREEN\_Y\_OFFSET 0
- #define DEVICE\_SCREEN\_WIDTH 20
- #define DEVICE\_SCREEN\_HEIGHT 18
- #define DEVICE\_SCREEN\_BUFFER\_WIDTH 32
- #define DEVICE\_SCREEN\_BUFFER\_HEIGHT 32
- #define DEVICE SCREEN MAP ENTRY SIZE 1
- #define DEVICE\_SPRITE\_PX\_OFFSET\_X 8
- #define DEVICE\_SPRITE\_PX\_OFFSET\_Y 16
- #define DEVICE\_WINDOW\_PX\_OFFSET\_X 7
- #define DEVICE WINDOW PX OFFSET Y 0
- #define DEVICE SCREEN PX WIDTH (DEVICE SCREEN WIDTH \* 8)
- #define DEVICE SCREEN PX HEIGHT (DEVICE SCREEN HEIGHT \* 8)

### **Variables**

- \_\_BYTES \_VRAM []
- \_\_BYTES \_VRAM8000 []
- \_\_BYTES \_VRAM8800 []
- \_\_BYTES \_VRAM9000 []
- \_\_BYTES \_SCRN0 []
- \_\_BYTES \_SCRN1 []
- \_\_BYTES \_SRAM []
- \_\_BYTES \_RAM []

- \_\_BYTES \_RAMBANK []
- \_\_BYTES \_OAMRAM []
- \_\_BYTE\_REG\_IO[]
- \_BYTE\_REG \_AUD3WAVERAM []
- \_\_BYTE\_REG \_HRAM []
- \_\_BYTE\_REG rRAMG
- \_\_BYTE\_REG rROMB0
- \_\_BYTE\_REG rROMB1
- \_\_BYTE\_REG rRAMB
- REG P1 REG
- \_\_REG SB\_REG
- \_\_REG SC\_REG
- \_\_REG DIV\_REG
- \_\_REG TIMA\_REG
- \_\_REG TMA\_REG
- \_\_REG TAC\_REG
- \_\_REG IF\_REG
- \_\_REG NR10\_REG
- \_\_REG NR11\_REG
- \_\_REG NR12\_REG
- \_\_REG NR13\_REG
- \_\_REG NR14\_REG
- \_\_REG NR21\_REG
- \_\_REG NR22\_REG
- \_\_REG NR23\_ REG
- \_\_REG NR24\_REG
- \_\_REG NR30\_REG
- \_\_REG NR31\_REG
- REG NR32 REG
- \_\_REG NR33\_REG
- \_\_REG NR34\_REG
- \_\_REG NR41\_REG
- \_\_REG NR42\_REG • \_\_REG NR43\_REG
- \_\_REG NR44\_REG
- \_\_REG NR50\_REG
- \_\_REG NR51\_REG
- \_\_REG NR52\_REG
- \_\_BYTE\_REG AUD3WAVE [16]
- \_\_BYTE\_REG PCM\_SAMPLE [16]
- \_\_REG LCDC\_ REG
- \_\_REG STAT\_REG
- \_\_REG SCY\_REG
- \_\_REG SCX\_REG
- \_\_REG LY\_REG
- \_\_REG LYC\_REG
- \_\_REG DMA\_REG
- \_\_REG BGP\_REG
- \_\_REG OBP0\_REG
- \_\_REG OBP1\_REG
- \_\_REG WY\_REG
- \_\_REG WX\_REG
- \_\_REG KEY1\_REG
- \_\_REG VBK\_REG
- \_\_REG HDMA1\_REG

- \_\_REG HDMA2\_REG
- \_\_REG HDMA3\_REG
- \_\_REG HDMA4\_REG
- \_\_REG HDMA5\_REG
- \_\_REG RP\_REG
- \_\_REG BCPS\_REG
- \_\_REG BCPD\_REG
- \_\_REG OCPS\_REG
- \_\_REG OCPD\_REG
- \_\_REG SVBK\_REG
- \_\_REG PCM12\_REG
- \_\_REG PCM34\_REG
- \_\_REG IE\_REG

## 20.45.1 Detailed Description

Defines that let the GB's hardware registers be accessed from C. See the Pandocs for more details on each register.

#### 20.45.2 Macro Definition Documentation

```
20.45.2.1 _BYTES #define _BYTES extern UBYTE

20.45.2.2 _BYTE_REG #define _BYTE_REG extern volatile UBYTE

20.45.2.3 _REG #define _REG extern volatile SFR

20.45.2.4 rP1 #define rP1 P1_REG

20.45.2.5 P1F_5 #define P1F_5 0b00100000

20.45.2.6 P1F_4 #define P1F_4 0b00010000

20.45.2.7 P1F_3 #define P1F_3 0b00001000

20.45.2.8 P1F_2 #define P1F_2 0b00000100

20.45.2.9 P1F_1 #define P1F_1 0b00000010
```

20.45.2.11 P1F\_GET\_DPAD #define P1F\_GET\_DPAD P1F\_5

```
20.45.2.12 P1F_GET_BTN #define P1F_GET_BTN P1F_4
20.45.2.13 P1F_GET_NONE #define P1F_GET_NONE (P1F_4 | P1F_5)
20.45.2.14 rSB #define rSB SB_REG
20.45.2.15 rSC #define rSC SC_REG
20.45.2.16 SIOF_XFER_START #define SIOF_XFER_START 0b10000000
Serial IO: Start Transfer. Automatically cleared at the end of transfer
20.45.2.17 SIOF_CLOCK_INT #define SIOF_CLOCK_INT 0b00000001
Serial IO: Use Internal clock
20.45.2.18 SIOF_CLOCK_EXT #define SIOF_CLOCK_EXT 0b00000000
Serial IO: Use External clock
20.45.2.19 SIOF_SPEED_1X #define SIOF_SPEED_1X 0b00000000
Serial IO: If internal clock then 8KHz mode, 1KB/s (16Khz in CGB high-speed mode, 2KB/s)
20.45.2.20 SIOF_SPEED_32X #define SIOF_SPEED_32X 0b00000010
Serial IO: CGB-Mode ONLY If internal clock then 256KHz mode, 32KB/s (512KHz in CGB high-speed mode,
64KB/s)
20.45.2.21 SIOF_B_CLOCK #define SIOF_B_CLOCK 0
20.45.2.22 SIOF_B_SPEED #define SIOF_B_SPEED 1
20.45.2.23 SIOF_B_XFER_START #define SIOF_B_XFER_START 7
20.45.2.24 SCF_START #define SCF_START SIOF_XFER_START
20.45.2.25 SCF_SOURCE #define SCF_SOURCE SIOF_CLOCK_INT
20.45.2.26 SCF_SPEED #define SCF_SPEED_32X
20.45.2.27 rDIV #define rDIV DIV_REG
20.45.2.28 rTIMA #define rTIMA TIMA_REG
20.45.2.29 rTMA #define rTMA TMA_REG
```

```
20.45.2.30 rTAC #define rTAC TAC_REG
20.45.2.31 TACF_START #define TACF_START 0b00000100
20.45.2.32 TACF_STOP #define TACF_STOP 0b00000000
\textbf{20.45.2.33} \quad \textbf{TACF\_4KHZ} \quad \texttt{\#define} \quad \texttt{TACF\_4KHZ} \quad \texttt{0b000000000}
20.45.2.34 TACF_16KHZ #define TACF_16KHZ 0b00000011
20.45.2.35 TACF_65KHZ #define TACF_65KHZ 0b00000010
20.45.2.36 TACF_262KHZ #define TACF_262KHZ 0b00000001
20.45.2.37 rlF #define rIF IF_REG
20.45.2.38 rAUD1SWEEP #define rAUD1SWEEP NR10_REG
Sound Channel 1, NR10: Sweep
20.45.2.39 AUD1SWEEP_UP #define AUD1SWEEP_UP 0b00000000
For Sound Channel 1, NR10: Sweep Addition, period increases
20.45.2.40 AUDISWEEP DOWN #define AUDISWEEP_DOWN 0b00001000
For Sound Channel 1, NR10: Sweep Subtraction, period decreases
20.45.2.41 AUD1SWEEP_TIME #define AUD1SWEEP_TIME(
              x ) ((x) << 4)
For Sound Channel 1, NR10: Sweep Time/Pace, Range: 0-7
20.45.2.42 AUD1SWEEP_LENGTH #define AUD1SWEEP_LENGTH(
For Sound Channel 1, NR10: Sweep Length/Individual step, Range: 0-7
20.45.2.43 rAUD1LEN #define rAUD1LEN NR11_REG
Sound Channel 1, NR11: Sound length/Wave pattern duty
20.45.2.44 rAUD1ENV #define rAUD1ENV NR12_REG
Sound Channel 1, NR12: Volume Envelope
20.45.2.45 rAUD1LOW #define rAUD1LOW NR13_REG
Sound Channel 1, NR13: Frequency Low
20.45.2.46 rAUD1HIGH #define rAUD1HIGH NR14_REG
Sound Channel 1, NR14: Frequency High
```

20.45.2.47 rAUD2LEN #define rAUD2LEN NR21\_REG Sound Channel 2, NR21\_REG: Tone

**20.45.2.48 rAUD2ENV** #define rAUD2ENV NR22\_REG Sound Channel 2, NR22 REG: Volume Envelope

**20.45.2.49 rAUD2LOW** #define rAUD2LOW NR23\_REG Sound Channel 2, NR23\_REG: Frequency data Low

**20.45.2.50 rAUD2HIGH** #define rAUD2HIGH NR24\_REG Sound Channel 2, NR24 REG: Frequency data High

**20.45.2.51 rAUD3ENA** #define rAUD3ENA NR30\_REG Sound Channel 3, NR30\_REG: Sound on/off

**20.45.2.52 rAUD3LEN** #define rAUD3LEN NR31\_REG Sound Channel 3, NR31\_REG: Sound Length

**20.45.2.53 rAUD3LEVEL** #define rAUD3LEVEL NR32\_REG Sound Channel 3, NR32\_REG: Select output level

**20.45.2.54 rAUD3LOW** #define rAUD3LOW NR33\_REG Sound Channel 3, NR33\_REG: Frequency data Low

**20.45.2.55 rAUD3HIGH** #define rAUD3HIGH NR34\_REG Sound Channel 3, NR34\_REG: Frequency data High

20.45.2.56 rAUD4LEN #define rAUD4LEN NR41\_REG Sound Channel 4, NR41\_REG: Sound Length

**20.45.2.57 rAUD4ENV** #define rAUD4ENV NR42\_REG Sound Channel 4, NR42\_REG: Volume Envelope

**20.45.2.58 rAUD4POLY** #define rAUD4POLY NR43\_REG Sound Channel 4, NR43\_REG: Polynomial Counter

**20.45.2.59 AUD4POLY\_WIDTH\_15BIT** #define AUD4POLY\_WIDTH\_15BIT  $0 \times 00$  For Sound Channel 4, NR43\_REG: Polynomial counter use 15 steps

**20.45.2.60 AUD4POLY\_WIDTH\_7BIT** #define AUD4POLY\_WIDTH\_7BIT 0x08 For Sound Channel 4, NR43\_REG: Polynomial counter use 7 steps

**20.45.2.61 rAUD4GO** #define rAUD4GO NR44\_REG Sound Channel 4, NR44\_REG: Counter / Consecutive and Initial

**20.45.2.62 rAUDVOL** #define rAUDVOL NR50\_REG Sound Master Volume, NR50: Volume and Cart external sound input (VIN)

20.45.2.63 AUDVOL\_VOL\_LEFT #define AUDVOL\_VOL\_LEFT(  $\times$  ) ((x) << 4)

For Sound Master Volume, NR50: Left Volume, Range: 0-7

## 20.45.2.64 AUDVOL\_VOL\_RIGHT #define AUDVOL\_VOL\_RIGHT(

x ) ((x)

For Sound Master Volume, NR50: Right Volume, Range: 0-7

### 20.45.2.65 AUDVOL\_VIN\_LEFT #define AUDVOL\_VIN\_LEFT 0b10000000

For Sound Master Volume, NR50: Cart external sound input (VIN) Left bit, 1 = ON, 0 = OFF

## 20.45.2.66 AUDVOL\_VIN\_RIGHT #define AUDVOL\_VIN\_RIGHT 0b00001000

For Sound Master Volume, NR50: Cart external sound input (VIN) Right bit, 1 = ON, 0 = OFF

#### 20.45.2.67 rAUDTERM #define rAUDTERM NR51\_REG

Sound Panning, NR51: Enable/disable left and right output for sound channels

## **20.45.2.68 AUDTERM\_4\_LEFT** #define AUDTERM\_4\_LEFT 0b10000000

For Sound Panning, NR51: Channel 4 Left bit, 1 = ON, 0 = OFF

## **20.45.2.69 AUDTERM\_3\_LEFT** #define AUDTERM\_3\_LEFT 0b01000000

For Sound Panning, NR51: Channel 3 Left bit, 1 = ON, 0 = OFF

## **20.45.2.70 AUDTERM\_2\_LEFT** #define AUDTERM\_2\_LEFT 0b00100000

For Sound Panning, NR51: Channel 2 Left bit, 1 = ON, 0 = OFF

## **20.45.2.71 AUDTERM\_1\_LEFT** #define AUDTERM\_1\_LEFT 0b00010000

For Sound Panning, NR51: Channel 1 Left bit, 1 = ON, 0 = OFF

## 20.45.2.72 AUDTERM\_4 RIGHT #define AUDTERM\_4\_RIGHT 0b00001000

For Sound Panning, NR51: Channel 4 Right bit, 1 = ON, 0 = OFF

## 20.45.2.73 AUDTERM\_3\_RIGHT #define AUDTERM\_3\_RIGHT 0b00000100

For Sound Panning, NR51: Channel 4 Right bit, 1 = ON, 0 = OFF

# $\textbf{20.45.2.74} \quad \textbf{AUDTERM\_2\_RIGHT} \quad \texttt{\#define AUDTERM\_2\_RIGHT 0b00000010}$

For Sound Panning, NR51: Channel 4 Right bit, 1 = ON, 0 = OFF

# $\textbf{20.45.2.75} \quad \textbf{AUDTERM\_1\_RIGHT} \quad \texttt{\#define AUDTERM\_1\_RIGHT 0b00000001}$

For Sound Panning, NR51: Channel 4 Right bit, 1 = ON, 0 = OFF

## 20.45.2.76 rAUDENA #define rAUDENA NR52\_REG

Sound Master Control, NR52: ON / OFF

# **20.45.2.77 AUDENA\_ON** #define AUDENA\_ON 0b10000000

For Sound Master Control, NR52: Sound ON

## 20.45.2.78 AUDENA\_OFF #define AUDENA\_OFF 0b00000000

For Sound Master Control, NR52: Sound OFF

20.45.2.79 rLCDC #define rLCDC LCDC\_REG

## **20.45.2.80 LCDCF\_OFF** #define LCDCF\_OFF 0b00000000

LCD Control: Off

# $\textbf{20.45.2.81} \quad \textbf{LCDCF\_ON} \quad \texttt{\#define LCDCF\_ON 0b10000000}$

LCD Control: On

**20.45.2.82 LCDCF\_WIN9800** #define LCDCF\_WIN9800 0b00000000 Window Tile Map: Use 9800 Region

**20.45.2.83 LCDCF\_WIN9C00** #define LCDCF\_WIN9C00 0b01000000 Window Tile Map: Use 9C00 Region

**20.45.2.84 LCDCF\_WINOFF** #define LCDCF\_WINOFF 0b00000000 Window Display: Hidden

**20.45.2.85 LCDCF\_WINON** #define LCDCF\_WINON 0b00100000 Window Display: Visible

**20.45.2.86 LCDCF\_BG8800** #define LCDCF\_BG8800 0b00000000 BG & Window Tile Data: Use 8800 Region

**20.45.2.87 LCDCF\_BG8000** #define LCDCF\_BG8000 0b00010000 BG & Window Tile Data: Use 8000 Region

**20.45.2.88 LCDCF\_BG9800** #define LCDCF\_BG9800 0b00000000 BG Tile Map: use 9800 Region

**20.45.2.89 LCDCF\_BG9C00** #define LCDCF\_BG9C00 0b00001000 BG Tile Map: use 9C00 Region

**20.45.2.90 LCDCF\_OBJ8** #define LCDCF\_OBJ8 0b00000000 Sprites Size: 8x8 pixels

**20.45.2.91 LCDCF\_OBJ16** #define LCDCF\_OBJ16 0b00000100 Sprites Size: 8x16 pixels

**20.45.2.93 LCDCF\_OBJON** #define LCDCF\_OBJON 0b00000010 Sprites Display: Visible

**20.45.2.96 LCDCF\_B\_ON** #define LCDCF\_B\_ON 7 Bit for LCD On/Off Select

**20.45.2.97 LCDCF\_B\_WIN9C00** #define LCDCF\_B\_WIN9C00 6 Bit for Window Tile Map Region Select

**20.45.2.98 LCDCF\_B\_WINON** #define LCDCF\_B\_WINON 5 Bit for Window Display On/Off Control

**20.45.2.99 LCDCF\_B\_BG8000** #define LCDCF\_B\_BG8000 4 Bit for BG & Window Tile Data Region Select

20.45.2.100 LCDCF\_B\_BG9C00 #define LCDCF\_B\_BG9C00 3

Bit for BG Tile Map Region Select

**20.45.2.101 LCDCF\_B\_OBJ16** #define LCDCF\_B\_OBJ16 2

Bit for Sprites Size Select

20.45.2.102 LCDCF\_B\_OBJON #define LCDCF\_B\_OBJON 1

Bit for Sprites Display Visible/Hidden Select

20.45.2.103 LCDCF\_B\_BGON #define LCDCF\_B\_BGON 0

Bit for Background Display Visible/Hidden Select

20.45.2.104 rSTAT #define rSTAT STAT\_REG

**20.45.2.105 STATF\_LYC** #define STATF\_LYC 0b01000000

STAT Interrupt: LYC=LY Coincidence Source Enable

**20.45.2.106 STATF MODE10** #define STATF\_MODE10 0b00100000

STAT Interrupt: Mode 2 OAM Source Enable

**20.45.2.107 STATF\_MODE01** #define STATF\_MODE01 0b00010000

STAT Interrupt: Mode 1 VBlank Source Enable

**20.45.2.108 STATF\_MODE00** #define STATF\_MODE00 0b00001000

STAT Interrupt: Mode 0 HBlank Source Enable

 $\textbf{20.45.2.109} \quad \textbf{STATF\_LYCF} \quad \texttt{\#define STATF\_LYCF 0b00000100}$ 

LYC=LY Coincidence Status Flag, Set when LY contains the same value as LYC

20.45.2.110 STATF\_HBL #define STATF\_HBL 0b00000000

Current LCD Mode is: 0, in H-Blank

**20.45.2.111 STATF\_VBL** #define STATF\_VBL 0b00000001

Current LCD Mode is: 1, in V-Blank

**20.45.2.112 STATF\_OAM** #define STATF\_OAM 0b00000010

Current LCD Mode is: 2, in OAM-RAM is used by system (Searching OAM)

**20.45.2.113 STATF\_LCD** #define STATF\_LCD 0b00000011

Current LCD Mode is: 3, both OAM and VRAM used by system (Transferring Data to LCD Controller)

**20.45.2.114 STATF\_BUSY** #define STATF\_BUSY 0b00000010

When set, VRAM access is unsafe

20.45.2.115 STATF\_B\_LYC #define STATF\_B\_LYC 6

Bit for STAT Interrupt: LYC=LY Coincidence Source Enable

20.45.2.116 STATF\_B\_MODE10 #define STATF\_B\_MODE10 5

Bit for STAT Interrupt: Mode 2 OAM Source Enable

20.45.2.117 STATF\_B\_MODE01 #define STATF\_B\_MODE01 4

Bit for STAT Interrupt: Mode 1 VBlank Source Enable

```
20.45.2.118 STATF_B_MODE00 #define STATF_B_MODE00 3
Bit for STAT Interrupt: Mode 0 HBlank Source Enable
20.45.2.119 STATF B LYCF #define STATF_B_LYCF 2
Bit for LYC=LY Coincidence Status Flag
20.45.2.120 STATF_B_VBL #define STATF_B_VBL 0
20.45.2.121 STATF_B_OAM #define STATF_B_OAM 1
20.45.2.122 STATF_B_BUSY #define STATF_B_BUSY 1
Bit for when VRAM access is unsafe
20.45.2.123 rSCY #define rSCY
20.45.2.124 rSCX #define rSCX SCX_REG
20.45.2.125 rLY #define rLY LY_REG
20.45.2.126 rLYC #define rLYC LYC_REG
\textbf{20.45.2.127} \quad \textbf{rDMA} \quad \texttt{\#define rDMA DMA\_REG}
20.45.2.128 rBGP #define rBGP BGP_REG
20.45.2.129 rOBP0 #define rOBP0 OBP0_REG
20.45.2.130 rOBP1 #define rOBP1 OBP1_REG
20.45.2.131 rWY #define rWY WY_REG
20.45.2.132 rWX #define rWX WX_REG
20.45.2.133 rKEY1 #define rKEY1 KEY1_REG
20.45.2.134 rSPD #define rSPD KEY1_REG
```

20.45.2.135 KEY1F\_DBLSPEED #define KEY1F\_DBLSPEED 0b10000000

20.45.2.136 KEY1F\_PREPARE #define KEY1F\_PREPARE 0b00000001

20.45.2.137 rVBK #define rVBK VBK\_REG

**20.45.2.138 VBK\_BANK\_0** #define VBK\_BANK\_0 0 Select Regular Map and Normal Tiles (CGB Mode Only)

**20.45.2.139 VBK\_TILES** #define VBK\_TILES 0 Select Regular Map and Normal Tiles (CGB Mode Only)

**20.45.2.140 VBK\_BANK\_1** #define VBK\_BANK\_1 1 Select Map Attributes and Extra Tile Bank (CGB Mode Only)

**20.45.2.141 VBK\_ATTRIBUTES** #define VBK\_ATTRIBUTES 1 Select Map Attributes and Extra Tile Bank (CGB Mode Only)

**20.45.2.142 BKGF\_PRI** #define BKGF\_PRI 0b10000000 Background CGB BG and Window over Sprite priority Enabled

**20.45.2.143 BKGF\_YFLIP** #define BKGF\_YFLIP 0b01000000 Background CGB Y axis flip: Vertically mirrored

**20.45.2.144 BKGF\_XFLIP** #define BKGF\_XFLIP 0b00100000 Background CGB X axis flip: Horizontally mirrored

**20.45.2.145 BKGF\_BANK0** #define BKGF\_BANK0 0b00000000 Background CGB Tile VRAM-Bank: Use Bank 0 (CGB Mode Only)

**20.45.2.146 BKGF\_BANK1** #define BKGF\_BANK1 0b00001000 Background CGB Tile VRAM-Bank: Use Bank 1 (CGB Mode Only)

**20.45.2.148 BKGF\_CGB\_PAL1** #define BKGF\_CGB\_PAL1 0b00000001 Background CGB Palette number (CGB Mode Only)

**20.45.2.149 BKGF\_CGB\_PAL2** #define BKGF\_CGB\_PAL2 0b00000010 Background CGB Palette number (CGB Mode Only)

**20.45.2.150 BKGF\_CGB\_PAL3** #define BKGF\_CGB\_PAL3 0b00000011 Background CGB Palette number (CGB Mode Only)

**20.45.2.151 BKGF\_CGB\_PAL4** #define BKGF\_CGB\_PAL4 0b00000100 Background CGB Palette number (CGB Mode Only)

**20.45.2.152 BKGF\_CGB\_PAL5** #define BKGF\_CGB\_PAL5 0b00000101 Background CGB Palette number (CGB Mode Only)

**20.45.2.153 BKGF\_CGB\_PAL6** #define BKGF\_CGB\_PAL6 0b00000110 Background CGB Palette number (CGB Mode Only)

```
20.45.2.154 BKGF_CGB_PAL7 #define BKGF_CGB_PAL7 0b00000111
Background CGB Palette number (CGB Mode Only)
20.45.2.155 rHDMA1 #define rHDMA1 HDMA1_REG
20.45.2.156 rHDMA2 #define rHDMA2 HDMA2_REG
20.45.2.157 rHDMA3 #define rHDMA3 HDMA3_REG
20.45.2.158 rHDMA4 #define rHDMA4 HDMA4_REG
20.45.2.159 rHDMA5 #define rHDMA5 HDMA5_REG
20.45.2.160 HDMA5F_MODE_GP #define HDMA5F_MODE_GP 0b00000000
20.45.2.161 HDMA5F_MODE_HBL #define HDMA5F_MODE_HBL 0b10000000
```

20.45.2.163 rRP #define rRP RP\_REG

**20.45.2.164 RPF\_ENREAD** #define RPF\_ENREAD 0b11000000

**20.45.2.165 RPF\_DATAIN** #define RPF\_DATAIN 0b00000010

20.45.2.166 RPF\_WRITE\_HI #define RPF\_WRITE\_HI 0b00000001

20.45.2.167 RPF\_WRITE\_LO #define RPF\_WRITE\_LO 0b00000000

20.45.2.168 rBCPS #define rBCPS BCPS\_REG

20.45.2.169 BCPSF AUTOINC #define BCPSF\_AUTOINC 0b10000000

20.45.2.170 rBCPD #define rBCPD BCPD\_REG

20.45.2.171 rOCPS #define rOCPS OCPS\_REG

```
20.45.2.172 OCPSF_AUTOINC #define OCPSF_AUTOINC Ob10000000
20.45.2.173 rOCPD #define rOCPD OCPD_REG
20.45.2.174 rSVBK #define rSVBK SVBK_REG
20.45.2.175 rSMBK #define rSMBK SVBK_REG
20.45.2.176 rPCM12 #define rPCM12 PCM12_REG
20.45.2.177 rPCM34 #define rPCM34 PCM34_REG
20.45.2.178 rIE #define rIE IE_REG
20.45.2.179 IEF_HILO #define IEF_HILO 0b00010000
Joypad interrupt enable flag
20.45.2.180 IEF_SERIAL #define IEF_SERIAL 0b00001000
Serial interrupt enable flag
20.45.2.181 IEF_TIMER #define IEF_TIMER 0b00000100
Timer interrupt enable flag
20.45.2.182 IEF_STAT #define IEF_STAT 0b00000010
Stat interrupt enable flag
20.45.2.183 IEF_VBLANK #define IEF_VBLANK 0b00000001
VBlank interrupt enable flag
20.45.2.184 AUDLEN_DUTY_12_5 #define AUDLEN_DUTY_12_5 0b00000000
20.45.2.185 AUDLEN_DUTY_25 #define AUDLEN_DUTY_25 0b01000000
20.45.2.186 AUDLEN_DUTY_50 #define AUDLEN_DUTY_50 0b10000000
20.45.2.187 AUDLEN_DUTY_75 #define AUDLEN_DUTY_75 0b11000000
20.45.2.188 AUDLEN_LENGTH #define AUDLEN_LENGTH(
             x ) (x)
```

**20.45.2.190 AUDENV\_UP** #define AUDENV\_UP 0b00001000

**20.45.2.191 AUDENV\_DOWN** #define AUDENV\_DOWN 0b00000000

20.45.2.192 AUDENV\_LENGTH #define AUDENV\_LENGTH(
x ) (x)

20.45.2.193 AUDHIGH RESTART #define AUDHIGH\_RESTART 0b10000000

20.45.2.194 AUDHIGH\_LENGTH\_ON #define AUDHIGH\_LENGTH\_ON 0b01000000

20.45.2.195 AUDHIGH\_LENGTH\_OFF #define AUDHIGH\_LENGTH\_OFF Ob00000000

**20.45.2.196 OAMF\_PRI** #define OAMF\_PRI Ob10000000 BG and Window over Sprite Enabled

**20.45.2.197 OAMF\_YFLIP** #define OAMF\_YFLIP 0b01000000 Sprite Y axis flip: Vertically mirrored

**20.45.2.198 OAMF\_XFLIP** #define OAMF\_XFLIP 0b00100000 Sprite X axis flip: Horizontally mirrored

**20.45.2.199 OAMF\_PALO** #define OAMF\_PALO 0b00000000 Sprite Palette number: use OBPO (Non-CGB Mode Only)

**20.45.2.200 OAMF\_PAL1** #define OAMF\_PAL1 0b00010000 Sprite Palette number: use OBP1 (Non-CGB Mode Only)

**20.45.2.201 OAMF\_BANKO** #define OAMF\_BANKO 0b00000000 Sprite Tile VRAM-Bank: Use Bank 0 (CGB Mode Only)

**20.45.2.202 OAMF\_BANK1** #define OAMF\_BANK1 0b00001000 Sprite Tile VRAM-Bank: Use Bank 1 (CGB Mode Only)

**20.45.2.203 OAMF\_CGB\_PALO** #define OAMF\_CGB\_PALO 0b0000000000 Sprite CGB Palette number: use OCP0 (CGB Mode Only)

**20.45.2.204 OAMF\_CGB\_PAL1** #define OAMF\_CGB\_PAL1 0b00000001 Sprite CGB Palette number: use OCP1 (CGB Mode Only)

**20.45.2.205 OAMF\_CGB\_PAL2** #define OAMF\_CGB\_PAL2 0b00000010 Sprite CGB Palette number: use OCP2 (CGB Mode Only)

**20.45.2.206 OAMF\_CGB\_PAL3** #define OAMF\_CGB\_PAL3 0b00000011

Sprite CGB Palette number: use OCP3 (CGB Mode Only)

**20.45.2.207 OAMF\_CGB\_PAL4** #define OAMF\_CGB\_PAL4 0b00000100

Sprite CGB Palette number: use OCP4 (CGB Mode Only)

**20.45.2.208 OAMF\_CGB\_PAL5** #define OAMF\_CGB\_PAL5 0b00000101

Sprite CGB Palette number: use OCP5 (CGB Mode Only)

**20.45.2.209 OAMF\_CGB\_PAL6** #define OAMF\_CGB\_PAL6 0b00000110

Sprite CGB Palette number: use OCP6 (CGB Mode Only)

**20.45.2.210 OAMF\_CGB\_PAL7** #define OAMF\_CGB\_PAL7 0b00000111

Sprite CGB Palette number: use OCP7 (CGB Mode Only)

20.45.2.211 OAMF\_PALMASK #define OAMF\_PALMASK 0b00000111

Mask for Sprite CGB Palette number (CGB Mode Only)

20.45.2.212 DEVICE SCREEN X OFFSET #define DEVICE\_SCREEN\_X\_OFFSET 0

Offset of visible screen (in tile units) from left edge of hardware map

**20.45.2.213 DEVICE\_SCREEN\_Y\_OFFSET** #define DEVICE\_SCREEN\_Y\_OFFSET 0

Offset of visible screen (in tile units) from top edge of hardware map

20.45.2.214 DEVICE\_SCREEN\_WIDTH #define DEVICE\_SCREEN\_WIDTH 20

Width of visible screen in tile units

20.45.2.215 DEVICE\_SCREEN\_HEIGHT #define DEVICE\_SCREEN\_HEIGHT 18

Height of visible screen in tile units

20.45.2.216 DEVICE\_SCREEN\_BUFFER\_WIDTH #define DEVICE\_SCREEN\_BUFFER\_WIDTH 32

Width of hardware map buffer in tile units

20.45.2.217 DEVICE\_SCREEN\_BUFFER\_HEIGHT #define DEVICE\_SCREEN\_BUFFER\_HEIGHT 32

Height of hardware map buffer in tile units

20.45.2.218 DEVICE SCREEN MAP ENTRY SIZE #define DEVICE\_SCREEN\_MAP\_ENTRY\_SIZE 1

Number of bytes per hardware map entry

20.45.2.219 DEVICE SPRITE PX OFFSET X #define DEVICE SPRITE PX OFFSET X 8

Offset of sprite X coordinate origin (in pixels) from left edge of visible screen

**20.45.2.220 DEVICE\_SPRITE\_PX\_OFFSET\_Y** #define DEVICE\_SPRITE\_PX\_OFFSET\_Y 16

Offset of sprite Y coordinate origin (in pixels) from top edge of visible screen

20.45.2.221 DEVICE WINDOW PX OFFSET X #define DEVICE\_WINDOW\_PX\_OFFSET\_X 7

Minimal X coordinate of the window layer

20.45.2.222 DEVICE WINDOW PX OFFSET Y #define DEVICE\_WINDOW\_PX\_OFFSET\_Y 0

Minimal Y coordinate of the window layer

20.45.2.223 DEVICE SCREEN PX\_WIDTH #define DEVICE\_SCREEN\_PX\_WIDTH (DEVICE\_SCREEN\_WIDTH \*

8)

Width of visible screen in pixels

```
20.45.2.224 DEVICE_SCREEN_PX_HEIGHT #define DEVICE_SCREEN_PX_HEIGHT (DEVICE_SCREEN_HEIGHT * 8)
```

Height of visible screen in pixels

# 20.45.3 Variable Documentation

```
20.45.3.1 _VRAM __BYTES _VRAM[]
Memory map
20.45.3.2 _VRAM8000 __BYTES _VRAM8000[]
20.45.3.3 _VRAM8800 __BYTES _VRAM8800[]
20.45.3.4 _VRAM9000 __BYTES _VRAM9000[]
20.45.3.5 _SCRN0 __BYTES _SCRN0[]
20.45.3.6 _SCRN1 __BYTES _SCRN1[]
20.45.3.7 _SRAM __BYTES _SRAM[]
20.45.3.8 _RAM __BYTES _RAM[]
20.45.3.9 _RAMBANK __BYTES _RAMBANK[]
20.45.3.10 _OAMRAM __BYTES _OAMRAM[]
20.45.3.11 _IO __BYTE_REG _IO[]
20.45.3.12 _AUD3WAVERAM __BYTE_REG _AUD3WAVERAM[]
20.45.3.13 _HRAM __BYTE_REG _HRAM[]
20.45.3.14 rRAMG __BYTE_REG rRAMG
MBC5 registers
20.45.3.15 rROMB0 __BYTE_REG rROMB0
20.45.3.16 rROMB1 __BYTE_REG rROMB1
```

```
20.45.3.17 rRAMB __BYTE_REG rRAMB
20.45.3.18 P1_REG __REG P1_REG
IO Registers Joystick register
See also
    joypad(), add_JOY(), IEF_HILO, P1F_5, P1F_4, P1F_3, P1F_2, P1F_1, P1F_0, P1F_GET_DPAD,
    P1F_GET_BTN, P1F_GET_NONE
20.45.3.19 SB_REG ___REG SB_REG
Serial IO data buffer
20.45.3.20 SC_REG __REG SC_REG
Serial IO control register
20.45.3.21 DIV_REG __REG DIV_REG
Divider register
20.45.3.22 TIMA_REG __REG TIMA_REG
Timer counter
20.45.3.23 TMA_REG ___REG TMA_REG
Timer modulo
20.45.3.24 TAC_REG __REG TAC_REG
Timer control
20.45.3.25 IF_REG ___REG IF_REG
Interrupt flags: IEF_HILO, IEF_SERIAL, IEF_TIMER, IEF_STAT, IEF_VBLANK
20.45.3.26 NR10_REG __REG NR10_REG
Sound Channel 1, NR10: Sweep
20.45.3.27 NR11_REG __REG NR11_REG
Sound Channel 1, NR11: Sound length/Wave pattern duty
20.45.3.28 NR12_REG __REG NR12_REG
Sound Channel 1, NR12: Volume Envelope
20.45.3.29 NR13_REG ___REG NR13_REG
Sound Channel 1, NR13: Frequency Low
20.45.3.30 NR14_REG ___REG NR14_REG
Sound Channel 1, NR14: Frequency High
20.45.3.31 NR21_REG __REG NR21_REG
Sound Channel 2, NR21_REG: Tone
20.45.3.32 NR22_REG __REG NR22_REG
```

Sound Channel 2, NR22\_REG: Volume Envelope

```
20.45.3.33 NR23_REG __REG NR23_REG
Sound Channel 2, NR23_REG: Frequency data Low
20.45.3.34 NR24 REG __REG NR24_REG
Sound Channel 2, NR24 REG: Frequency data High
20.45.3.35 NR30_REG __REG NR30_REG
Sound Channel 3, NR30_REG: Sound on/off
20.45.3.36 NR31_REG __REG NR31_REG
Sound Channel 3, NR31 REG: Sound Length
20.45.3.37 NR32_REG __REG NR32_REG
Sound Channel 3, NR32_REG: Select output level
20.45.3.38 NR33_REG __REG NR33_REG
Sound Channel 3, NR33_REG: Frequency data Low
20.45.3.39 NR34 REG __REG NR34_REG
Sound Channel 3, NR34_REG: Frequency data High
20.45.3.40 NR41_REG __REG NR41_REG
Sound Channel 4, NR41_REG: Sound Length
20.45.3.41 NR42 REG REG NR42 REG
Sound Channel 4, NR42_REG: Volume Envelope
20.45.3.42 NR43_REG __REG NR43_REG
Sound Channel 4, NR43_REG: Polynomial Counter
20.45.3.43 NR44 REG __REG NR44_REG
Sound Channel 4, NR44_REG: Counter / Consecutive and Initial
20.45.3.44 NR50_REG __REG NR50_REG
Sound Master Volume, NR50: Volume and Cart external sound input (VIN)
20.45.3.45 NR51_REG __REG NR51_REG
Sound Panning, NR51: Enable/disable left and right output for sound channels
20.45.3.46 NR52_REG __REG NR52_REG
Sound Master Control, NR52: ON / OFF
20.45.3.47 AUD3WAVE __BYTE_REG AUD3WAVE[16]
20.45.3.48 PCM_SAMPLE __BYTE_REG PCM_SAMPLE[16]
20.45.3.49 LCDC_REG __REG LCDC_REG
LCD control
20.45.3.50 STAT_REG __REG STAT_REG
```

LCD status

```
20.45.3.51 SCY_REG __REG SCY_REG
Scroll Y
20.45.3.52 SCX_REG __REG SCX_REG
Scroll X
20.45.3.53 LY_REG __REG LY_REG
LCDC Y-coordinate
20.45.3.54 LYC_REG __REG LYC_REG
LY compare
20.45.3.55 DMA_REG __REG DMA_REG
DMA transfer
20.45.3.56 BGP REG __REG BGP_REG
Set and Read the Background palette.
Example with the DMG_PALETTE() helper function and constants:
BGP_REG = DMG_PALETTE(DMG_BLACK, DMG_DARK_GRAY, DMG_LITE_GRAY, DMG_WHITE);
20.45.3.57 OBPO_REG __REG OBPO_REG
Set and Read the OBJ (Sprite) palette 0.
The first color entry is always transparent.
Example with the DMG PALETTE() helper function and constants:
OBPO REG = DMG PALETTE(DMG BLACK, DMG DARK GRAY, DMG LITE GRAY, DMG WHITE);
20.45.3.58 OBP1_REG ___REG OBP1_REG
Set and Read the OBJ (Sprite) palette 1.
The first color entry is always transparent.
Example with the DMG PALETTE() helper function and constants:
OBP1_REG = DMG_PALETTE(DMG_BLACK, DMG_DARK_GRAY, DMG_LITE_GRAY, DMG_WHITE);
20.45.3.59 WY_REG ___REG WY_REG
Window Y coordinate
20.45.3.60 WX_REG ___REG WX_REG
Window X coordinate
20.45.3.61 KEY1_REG ___REG KEY1_REG
CPU speed
20.45.3.62 VBK_REG __REG VBK_REG
VRAM bank select (CGB only)
See also
     VBK_BANK_0, VBK_TILES, VBK_BANK_1, VBK_ATTRIBUTES
```

20.45.3.63 HDMA1\_REG \_\_REG HDMA1\_REG

DMA control 1

```
20.45.3.64 HDMA2_REG ___REG HDMA2_REG
DMA control 2
20.45.3.65 HDMA3_REG __REG HDMA3_REG
DMA control 3
20.45.3.66 HDMA4_REG __REG HDMA4_REG
DMA control 4
20.45.3.67 HDMA5_REG __REG HDMA5_REG
DMA control 5
20.45.3.68 RP_REG __REG RP_REG
IR port
20.45.3.69 BCPS_REG __REG BCPS_REG
BG color palette specification
20.45.3.70 BCPD_REG __REG BCPD_REG
BG color palette data
20.45.3.71 OCPS_REG __REG OCPS_REG
OBJ color palette specification
20.45.3.72 OCPD_REG __REG OCPD_REG
OBJ color palette data
20.45.3.73 SVBK_REG __REG SVBK_REG
Selects the WRAM upper region bank (CGB Only). WRAM Banking is NOT officially supported in GBDK and SDCC.
```

The stack must be moved and other special care taken.

**20.45.3.74 PCM12\_REG** \_\_\_REG PCM12\_REG Sound channel 1&2 PCM amplitude (R)

**20.45.3.75 PCM34\_REG** \_\_\_REG PCM34\_REG Sound channel 3&4 PCM amplitude (R)

**20.45.3.76 IE\_REG** \_\_REG IE\_REG Interrupt enable

### 20.46 gbdk-lib/include/msx/hardware.h File Reference

#include <types.h>

#### **Macros**

- #define \_\_BYTES extern UBYTE
- #define \_\_BYTE\_REG extern volatile UBYTE
- #define PSG\_LATCH 0x80
- #define PSG\_CH0 0b00000000
- #define PSG\_CH1 0b00100000
- #define PSG CH2 0b01000000
- #define PSG CH3 0b01100000
- #define PSG\_VOLUME 0b00010000

- #define STATF\_INT\_VBL 0b10000000
- #define STATF\_9\_SPR 0b01000000
- #define STATF\_SPR\_COLL 0b00100000
- #define VDP REG MASK 0b10000000
- #define VDP R0 0b10000000
- #define R0 DEFAULT 0b00000000
- #define R0 CB OUTPUT 0b00000000
- #define R0\_CB\_INPUT 0b01000000
- #define R0\_IE2\_OFF 0b00000000
- #define R0 IE2 0b00100000
- #define R0 IE1 OFF 0b00000000
- #define R0 IE1 0b00010000
- #define R0\_SCR\_MODE1 0b00000000
- #define R0 SCR MODE2 0b00000010
- #define R0\_SCR\_MODE3 0b00000100
- #define R0 ES OFF 0b00000000
- #define R0 ES 0b00000001
- #define VDP R1 0b10000001
- #define R1 DEFAULT 0b10000000
- #define R1\_DISP\_OFF 0b00000000
- #define R1\_DISP\_ON 0b01000000
- #define R1 IE OFF 0b00000000
- #define R1 IE 0b00100000
- #define R1\_SCR\_MODE1 0b00010000
- #define R1\_SCR\_MODE2 0b00000000
- #define R1\_SCR\_MODE3 0b00000000
- #define R1\_SPR\_8X8 0b00000000
- #define R1\_SPR\_16X16 0b00000010
- #define R1\_SPR\_MAG 0b00000001
- #define R1\_SPR\_MAG\_OFF 0b00000000
- #define VDP\_R2 0b10000010
- #define R2 MAP 0x3800 0xFF
- #define R2\_MAP\_0x3000 0xFD
- #define R2\_MAP\_0x2800 0xFB
- #define R2\_MAP\_0x2000 0xF9
- #define R2\_MAP\_0x1800 0xF7
- #define R2\_MAP\_0x1000 0xF5#define R2\_MAP\_0x0800 0xF3
- #define R2\_MAP\_0x0000 0xF1
- #define VDP R3 0b10000011
- #define VDP R4 0b10000100
- #define VDP\_R5 0b10000101
- #define R5\_SAT\_0x3F00 0xFF
- #define R5\_SAT\_MASK 0b10000001
- #define VDP\_R6 0b10000110
- #define R6\_BANK0 0xFB
- #define R6 DATA 0x0000 0xFB
- #define R6\_BANK1 0xFF
- #define R6\_DATA\_0x2000 0xFF
- #define VDP\_R7 0b10000111
- #define VDP RBORDER 0b10000111
- #define R7\_COLOR\_MASK 0b11110000
- #define VDP R8 0b10001000
- #define VDP RSCX 0b10001000
- #define VDP\_R9 0b10001001

- #define VDP\_RSCY 0b10001001
- #define VDP\_R10 0b10001010
- #define R10\_INT\_OFF 0xFF
- #define R10\_INT\_EVERY 0x00
- #define SYSTEM PAL 0x00
- #define SYSTEM\_NTSC 0x01
- #define VBK TILES 0
- #define VBK\_ATTRIBUTES 1
- #define VDP\_SAT\_TERM 0xD0
- #define DEVICE\_SCREEN\_PX\_WIDTH (DEVICE\_SCREEN\_WIDTH \* 8)
- #define DEVICE\_SCREEN\_PX\_HEIGHT (DEVICE\_SCREEN\_HEIGHT \* 8)

#### **Variables**

- UBYTE shadow\_VDP\_R0
- UBYTE shadow VDP R1
- UBYTE shadow\_VDP\_R2
- UBYTE shadow\_VDP R3
- UBYTE shadow\_VDP\_R4
- UBYTE shadow\_VDP\_R5
- UBYTE shadow\_VDP\_R6
- UBYTE shadow\_VDP\_R7
- UBYTE shadow\_VDP\_RBORDER
- UBYTE shadow\_VDP\_R8
- UBYTE shadow VDP RSCX
- UBYTE shadow\_VDP\_R9
- UBYTE shadow VDP RSCY
- UBYTE shadow\_VDP\_R10
- const UBYTE SYSTEM
- volatile UBYTE VDP\_ATTR\_SHIFT

# 20.46.1 Detailed Description

Defines that let the MSX hardware registers be accessed from C.

# 20.46.2 Macro Definition Documentation

```
20.46.2.1 __BYTES #define __BYTES extern UBYTE
```

20.46.2.2 \_\_BYTE\_REG #define \_\_BYTE\_REG extern volatile UBYTE

20.46.2.3 PSG\_LATCH #define PSG\_LATCH 0x80

**20.46.2.4 PSG\_CHO** #define PSG\_CHO 0b00000000

20.46.2.5 PSG\_CH1 #define PSG\_CH1 0b00100000

**20.46.2.6 PSG\_CH2** #define PSG\_CH2 0b01000000

- **20.46.2.7 PSG\_CH3** #define PSG\_CH3 0b01100000
- 20.46.2.8 PSG\_VOLUME #define PSG\_VOLUME 0b00010000
- 20.46.2.9 STATF\_INT\_VBL #define STATF\_INT\_VBL 0b10000000
- **20.46.2.10 STATF\_9\_SPR** #define STATF\_9\_SPR 0b01000000
- 20.46.2.11 STATF\_SPR\_COLL #define STATF\_SPR\_COLL 0b00100000
- 20.46.2.12 VDP\_REG\_MASK #define VDP\_REG\_MASK 0b10000000
- **20.46.2.13 VDP\_R0** #define VDP\_R0 0b10000000
- **20.46.2.14 R0\_DEFAULT** #define R0\_DEFAULT 0b00000000
- **20.46.2.15 RO\_CB\_OUTPUT** #define RO\_CB\_OUTPUT 0b00000000
- **20.46.2.16 R0\_CB\_INPUT** #define R0\_CB\_INPUT 0b01000000
- **20.46.2.17 R0\_IE2\_OFF** #define R0\_IE2\_OFF 0b00000000
- **20.46.2.18 R0\_IE2** #define R0\_IE2 0b00100000
- $\textbf{20.46.2.19} \quad \textbf{R0\_IE1\_OFF} \quad \texttt{\#define} \quad \texttt{R0\_IE1\_OFF} \quad \texttt{0b000000000}$
- **20.46.2.20 R0\_IE1** #define R0\_IE1 0b00010000
- **20.46.2.21 R0\_SCR\_MODE1** #define R0\_SCR\_MODE1 0b00000000
- **20.46.2.22 R0\_SCR\_MODE2** #define R0\_SCR\_MODE2 0b00000010
- **20.46.2.23 R0\_SCR\_MODE3** #define R0\_SCR\_MODE3 0b00000100
- **20.46.2.24 R0\_ES\_OFF** #define R0\_ES\_OFF 0b00000000

- 20.46.2.25 R0\_ES #define R0\_ES 0b00000001
- **20.46.2.26 VDP\_R1** #define VDP\_R1 0b10000001
- **20.46.2.27 R1\_DEFAULT** #define R1\_DEFAULT 0b10000000
- **20.46.2.28 R1\_DISP\_OFF** #define R1\_DISP\_OFF 0b00000000
- **20.46.2.29 R1\_DISP\_ON** #define R1\_DISP\_ON 0b01000000
- **20.46.2.30 R1\_IE\_OFF** #define R1\_IE\_OFF 0b00000000
- **20.46.2.31 R1\_IE** #define R1\_IE 0b00100000
- **20.46.2.32** R1\_SCR\_MODE1 #define R1\_SCR\_MODE1 0b00010000
- **20.46.2.33** R1\_SCR\_MODE2 #define R1\_SCR\_MODE2 0b00000000
- **20.46.2.34** R1\_SCR\_MODE3 #define R1\_SCR\_MODE3 0b00000000
- **20.46.2.35** R1\_SPR\_8X8 #define R1\_SPR\_8X8 0b00000000
- **20.46.2.36** R1\_SPR\_16X16 #define R1\_SPR\_16X16 0b00000010
- **20.46.2.37** R1\_SPR\_MAG #define R1\_SPR\_MAG 0b00000001
- **20.46.2.38 R1 SPR MAG OFF** #define R1\_SPR\_MAG\_OFF 0b00000000
- **20.46.2.39 VDP\_R2** #define VDP\_R2 0b10000010
- $\textbf{20.46.2.40} \quad \textbf{R2\_MAP\_0x3800} \quad \texttt{\#define} \ \, \texttt{R2\_MAP\_0x3800} \quad \texttt{0xff}$
- **20.46.2.41 R2\_MAP\_0x3000** #define R2\_MAP\_0x3000 0xFD
- **20.46.2.42 R2\_MAP\_0x2800** #define R2\_MAP\_0x2800 0xFB

20.46.2.43 R2\_MAP\_0x2000 #define R2\_MAP\_0x2000 0xF9 **20.46.2.44 R2\_MAP\_0x1800** #define R2\_MAP\_0x1800 0xF7 **20.46.2.45 R2\_MAP\_0x1000** #define R2\_MAP\_0x1000 0xF5 **20.46.2.46 R2\_MAP\_0x0800** #define R2\_MAP\_0x0800 0xF3 **20.46.2.47 R2\_MAP\_0x0000** #define R2\_MAP\_0x0000 0xF1 **20.46.2.48 VDP\_R3** #define VDP\_R3 0b10000011 **20.46.2.49 VDP\_R4** #define VDP\_R4 0b10000100 **20.46.2.50 VDP\_R5** #define VDP\_R5 0b10000101 **20.46.2.51 R5\_SAT\_0x3F00** #define R5\_SAT\_0x3F00 0xFF **20.46.2.52 R5\_SAT\_MASK** #define R5\_SAT\_MASK 0b10000001 **20.46.2.53 VDP\_R6** #define VDP\_R6 0b10000110 **20.46.2.54 R6\_BANK0** #define R6\_BANK0 0xFB **20.46.2.55 R6\_DATA\_0x0000** #define R6\_DATA\_0x0000 0xFB **20.46.2.56 R6 BANK1** #define R6\_BANK1 0xFF **20.46.2.57 R6\_DATA\_0x2000** #define R6\_DATA\_0x2000 0xFF **20.46.2.58 VDP\_R7** #define VDP\_R7 0b10000111 20.46.2.59 VDP\_RBORDER #define VDP\_RBORDER 0b10000111

**20.46.2.60 R7\_COLOR\_MASK** #define R7\_COLOR\_MASK 0b11110000

```
20.46.2.61 VDP_R8 #define VDP_R8 0b10001000
20.46.2.62 VDP_RSCX #define VDP_RSCX 0b10001000
20.46.2.63 VDP_R9 #define VDP_R9 0b10001001
20.46.2.64 VDP_RSCY #define VDP_RSCY 0b10001001
20.46.2.65 VDP_R10 #define VDP_R10 0b10001010
20.46.2.66 R10 INT OFF #define R10_INT_OFF 0xFF
20.46.2.67 R10_INT_EVERY #define R10_INT_EVERY 0x00
20.46.2.68 SYSTEM_PAL #define SYSTEM_PAL 0x00
20.46.2.69 SYSTEM_NTSC #define SYSTEM_NTSC 0x01
20.46.2.70 VBK_TILES #define VBK_TILES 0
20.46.2.71 VBK_ATTRIBUTES #define VBK_ATTRIBUTES 1
20.46.2.72 VDP_SAT_TERM #define VDP_SAT_TERM 0xD0
20.46.2.73 DEVICE_SCREEN_PX_WIDTH #define DEVICE_SCREEN_PX_WIDTH (DEVICE_SCREEN_WIDTH *
20.46.2.74 DEVICE_SCREEN_PX_HEIGHT #define DEVICE_SCREEN_PX_HEIGHT *
20.46.3 Variable Documentation
20.46.3.1 shadow_VDP_R0 UBYTE shadow_VDP_R0 [extern]
20.46.3.2 shadow_VDP_R1 UBYTE shadow_VDP_R1 [extern]
20.46.3.3 shadow_VDP_R2 UBYTE shadow_VDP_R2 [extern]
```

```
20.46.3.4 shadow_VDP_R3 UBYTE shadow_VDP_R3 [extern]
20.46.3.5 shadow_VDP_R4 UBYTE shadow_VDP_R4 [extern]
20.46.3.6 shadow_VDP_R5 UBYTE shadow_VDP_R5 [extern]
20.46.3.7 shadow_VDP_R6 UBYTE shadow_VDP_R6 [extern]
20.46.3.8 shadow_VDP_R7 UBYTE shadow_VDP_R7 [extern]
20.46.3.9 shadow_VDP_RBORDER UBYTE shadow_VDP_RBORDER [extern]
20.46.3.10 shadow_VDP_R8 UBYTE shadow_VDP_R8 [extern]
20.46.3.11 shadow_VDP_RSCX UBYTE shadow_VDP_RSCX [extern]
20.46.3.12 shadow_VDP_R9 UBYTE shadow_VDP_R9 [extern]
20.46.3.13 shadow_VDP_RSCY UBYTE shadow_VDP_RSCY [extern]
20.46.3.14 shadow VDP_R10 UBYTE shadow_VDP_R10 [extern]
20.46.3.15 _SYSTEM const UBYTE _SYSTEM [extern]
20.46.3.16 VDP_ATTR_SHIFT volatile UBYTE VDP_ATTR_SHIFT [extern]
20.47 gbdk-lib/include/nes/hardware.h File Reference
```

#include <types.h>

# **Macros**

- #define SHADOW REG extern volatile uint8 t
- #define REG(addr) volatile at (addr) uint8 t
- #define PPUCTRL\_NMI 0b10000000
- #define PPUCTRL\_SPR\_8X8 0b00000000
- #define PPUCTRL\_SPR\_8X16 0b00100000
- #define PPUCTRL\_BG\_CHR 0b00010000
- #define PPUCTRL SPR CHR 0b00001000
- #define PPUCTRL\_INC32 0b00000100
- #define PPUMASK BLUE 0b10000000
- #define PPUMASK\_RED 0b01000000

- #define PPUMASK GREEN 0b00100000
- #define PPUMASK\_SHOW\_SPR 0b00010000
- #define PPUMASK SHOW BG 0b00001000
- #define PPUMASK SHOW SPR LC 0b00000100
- #define PPUMASK SHOW BG LC 0b00000010
- #define PPUMASK\_MONOCHROME 0b00000001
- #define DEVICE\_SCREEN\_X\_OFFSET 0
- #define DEVICE\_SCREEN\_Y\_OFFSET 0
- #define DEVICE SCREEN WIDTH 32
- #define DEVICE\_SCREEN\_HEIGHT 30
- #define DEVICE SCREEN BUFFER WIDTH 32
- #define DEVICE\_SCREEN\_BUFFER\_HEIGHT 30
- #define DEVICE\_SCREEN\_MAP\_ENTRY\_SIZE 1
- #define DEVICE\_SPRITE\_PX\_OFFSET\_X 0
- #define DEVICE\_SPRITE\_PX\_OFFSET\_Y -1
- #define DEVICE WINDOW PX OFFSET X 0
- #define DEVICE\_WINDOW\_PX\_OFFSET\_Y 0
- #define DEVICE\_SCREEN\_PX\_WIDTH (DEVICE\_SCREEN\_WIDTH \* 8)
- #define DEVICE\_SCREEN\_PX\_HEIGHT (DEVICE\_SCREEN\_HEIGHT \* 8)

#### **Functions**

- REG (0x2000) PPUCTRL
- \_\_REG (0x2001) PPUMASK
- \_\_REG (0x2002) PPUSTATUS
- \_\_REG (0x2003) OAMADDR
- \_\_REG (0x2004) OAMDATA
- REG (0x2005) PPUSCROLL
- REG (0x2006) PPUADDR
- REG (0x2007) PPUDATA
- REG (0x4014) OAMDMA

#### **Variables**

- \_SHADOW\_REG shadow\_PPUCTRL
- \_SHADOW\_REG shadow\_PPUMASK
- SHADOW REG bkg scroll x
- \_\_SHADOW\_REG bkg\_scroll\_y

#### 20.47.1 Detailed Description

Defines that let the NES hardware registers be accessed from C.

#### 20.47.2 Macro Definition Documentation

```
20.47.2.1 __SHADOW_REG #define __SHADOW_REG extern volatile uint8_t
```

20.47.2.3 PPUCTRL\_NMI #define PPUCTRL\_NMI 0b10000000

20.47.2.4 PPUCTRL\_SPR\_8X8 #define PPUCTRL\_SPR\_8X8 0b00000000 **20.47.2.5 PPUCTRL\_SPR\_8X16** #define PPUCTRL\_SPR\_8X16 0b00100000 20.47.2.6 PPUCTRL\_BG\_CHR #define PPUCTRL\_BG\_CHR 0b00010000 20.47.2.7 PPUCTRL SPR CHR #define PPUCTRL\_SPR\_CHR 0b00001000 20.47.2.8 PPUCTRL\_INC32 #define PPUCTRL\_INC32 0b00000100 20.47.2.9 PPUMASK\_BLUE #define PPUMASK\_BLUE 0b10000000 20.47.2.10 PPUMASK RED #define PPUMASK\_RED 0b01000000 20.47.2.11 PPUMASK\_GREEN #define PPUMASK\_GREEN 0b00100000 20.47.2.12 PPUMASK SHOW SPR #define PPUMASK\_SHOW\_SPR 0b00010000 20.47.2.13 PPUMASK\_SHOW\_BG #define PPUMASK\_SHOW\_BG 0b00001000 20.47.2.14 PPUMASK\_SHOW\_SPR\_LC #define PPUMASK\_SHOW\_SPR\_LC 0b00000100 20.47.2.15 PPUMASK\_SHOW\_BG\_LC #define PPUMASK\_SHOW\_BG\_LC 0b00000010 20.47.2.16 PPUMASK MONOCHROME #define PPUMASK\_MONOCHROME 0b00000001 20.47.2.17 DEVICE SCREEN X OFFSET #define DEVICE\_SCREEN\_X\_OFFSET 0 20.47.2.18 DEVICE\_SCREEN\_Y\_OFFSET #define DEVICE\_SCREEN\_Y\_OFFSET 0 20.47.2.19 DEVICE SCREEN WIDTH #define DEVICE\_SCREEN\_WIDTH 32 20.47.2.20 DEVICE\_SCREEN\_HEIGHT #define DEVICE\_SCREEN\_HEIGHT 30

20.47.2.21 DEVICE\_SCREEN\_BUFFER\_WIDTH #define DEVICE\_SCREEN\_BUFFER\_WIDTH 32

```
20.47.2.22 DEVICE_SCREEN_BUFFER_HEIGHT #define DEVICE_SCREEN_BUFFER_HEIGHT 30
20.47.2.23 DEVICE_SCREEN_MAP_ENTRY_SIZE #define DEVICE_SCREEN_MAP_ENTRY_SIZE 1
20.47.2.24 DEVICE_SPRITE_PX_OFFSET_X #define DEVICE_SPRITE_PX_OFFSET_X 0
20.47.2.25 DEVICE_SPRITE_PX_OFFSET_Y #define DEVICE_SPRITE_PX_OFFSET_Y -1
20.47.2.26 DEVICE_WINDOW_PX_OFFSET_X #define DEVICE_WINDOW_PX_OFFSET_X 0
20.47.2.27 DEVICE_WINDOW_PX_OFFSET_Y #define DEVICE_WINDOW_PX_OFFSET_Y 0
20.47.2.28 DEVICE_SCREEN_PX_WIDTH #define DEVICE_SCREEN_PX_WIDTH (DEVICE_SCREEN_WIDTH *
20.47.2.29 DEVICE_SCREEN_PX_HEIGHT #define DEVICE_SCREEN_PX_HEIGHT *
20.47.3 Function Documentation
20.47.3.1 __REG() [1/9] __REG (
           0x2000 )
20.47.3.2 __REG() [2/9] __REG (
           0x2001 )
20.47.3.3 __REG() [3/9] __REG (
           0x2002 )
20.47.3.4 __REG() [4/9] __REG (
           0x2003 )
20.47.3.5 __REG() [5/9] __REG (
           0x2004 )
20.47.3.6 __REG() [6/9] __REG (
           0x2005 )
```

```
20.47.3.7 __REG() [7/9] __REG (
             0x2006 )
20.47.3.8 __REG() [8/9] __REG (
             0x2007 )
20.47.3.9 __REG() [9/9] __REG (
             0x4014 )
20.47.4 Variable Documentation
20.47.4.1 shadow_PPUCTRL __SHADOW_REG shadow_PPUCTRL
20.47.4.2 shadow_PPUMASK ___SHADOW_REG shadow_PPUMASK
20.47.4.3 bkg_scroll_x __SHADOW_REG bkg_scroll_x
20.47.4.4 bkg_scroll_y __SHADOW_REG bkg_scroll_y
20.48 gbdk-lib/include/sms/hardware.h File Reference
#include <types.h>
Macros
   • #define BYTES extern UBYTE

    #define BYTE REG extern volatile UBYTE

   • #define GGSTATE_STT 0b10000000

    #define GGSTATE NJAP 0b01000000

   • #define GGSTATE_NNTS 0b00100000
   • #define GGEXT_NINIT 0b10000000

    #define SIOCTL TXFL 0b00000001

    #define SIOCTL RXRD 0b00000010

   • #define SIOCTL FRER 0b00000100

    #define SIOCTL_INT 0b00001000

   • #define SIOCTL_TON 0b00010000
   • #define SIOCTL RON 0b00100000
   • #define SIOCTL_BS0 0b01000000

    #define SIOCTL_BS1 0b10000000

    #define SOUNDPAN TN1R 0b00000001

   • #define SOUNDPAN_TN2R 0b00000010
   • #define SOUNDPAN TN3R 0b00000100

    #define SOUNDPAN_NOSR 0b00001000

   • #define SOUNDPAN_TN1L 0b00010000

    #define SOUNDPAN TN2L 0b00100000
```

#define SOUNDPAN\_TN3L 0b01000000#define SOUNDPAN NOSL 0b10000000

- #define MEMCTL JOYON 0b00000000
- #define MEMCTL\_JOYOFF 0b00000100
- #define MEMCTL\_BASEON 0b00000000
- #define MEMCTL BASEOFF 0b00001000
- #define MEMCTL RAMON 0b00000000
- #define MEMCTL RAMOFF 0b00010000
- #define MEMCTL CROMON 0b00000000
- #define MEMCTL CROMOFF 0b00100000
- #define MEMCTL\_ROMON 0b00000000
- #define MEMCTL ROMOFF 0b01000000
- #define MEMCTL EXTON 0b00000000
- #define MEMCTL EXTOFF 0b10000000
- #define JOY\_P1\_TR\_DIR\_IN 0b00000001
- #define JOY P1 TR DIR OUT 0b00000000
- #define JOY\_P1\_TH\_DIR\_IN 0b00000010
- #define GUN P1 LATCH JOY P1 TH DIR IN
- #define JOY P1 TH DIR OUT 0b00000000
- #define JOY\_P2\_TR\_DIR\_IN 0b00000100
- #define JOY P2 TR DIR OUT 0b00000000
- #define JOY\_P2\_TH\_DIR\_IN 0b00001000
- #define GUN P2 LATCH JOY P2 TH DIR IN
- #define JOY P2 TH DIR OUT 0b00000000
- #define JOY\_P1\_TR\_OUT\_HI 0b00010000
- #define JOY\_P1\_TR\_OUT\_LO 0b00000000
- #define JOY\_P1\_TH\_OUT\_HI 0b00100000
- #define JOY\_P1\_TH\_OUT\_LO 0b00000000
- #define JOY\_P2\_TR\_OUT\_HI 0b01000000
- #define JOY P2 TR OUT LO 0b00000000
- #define JOY P2 TH OUT HI 0b10000000
- #define JOY P2 TH OUT LO 0b00000000
- #define JOY\_TH\_HI (JOY\_P1\_TR\_DIR\_IN | JOY\_P1\_TH\_DIR\_OUT | JOY\_P2\_TR\_DIR\_IN | JOY\_P2\_TH\_DIR\_OUT | JOY\_P1\_TR\_OUT\_HI | JOY\_P1\_TR\_OUT\_HI | JOY\_P2\_TR\_OUT\_HI | JOY\_P2\_TH\_OUT\_HI | JOY\_P1\_TR\_OUT\_HI | JOY\_P1\_TR\_OUT\_HI
- #define JOY\_TH\_LO (JOY\_P1\_TR\_DIR\_IN | JOY\_P1\_TH\_DIR\_OUT | JOY\_P2\_TR\_DIR\_IN | JOY\_P2\_TH\_DIR\_OUT | JOY\_P1\_TR\_OUT\_HI | JOY\_P1\_TH\_OUT\_LO | JOY\_P2\_TR\_OUT\_HI | JOY\_P2\_TH\_OUT\_LO)
- #define PSG LATCH 0b10000000
- #define PSG CH0 0b00000000
- #define PSG\_CH1 0b00100000
- #define PSG CH2 0b01000000
- #define PSG\_CH3 0b01100000
- #define PSG VOLUME 0b00010000
- #define STATF\_INT\_VBL 0b10000000
- #define STATF\_9\_SPR 0b01000000
- #define STATF\_SPR\_COLL 0b00100000
- #define VDP\_REG\_MASK 0b10000000
- #define VDP R0 0b10000000
- #define R0 VSCRL 0b00000000
- #define R0 VSCRL INH 0b10000000
- #define R0 HSCRL 0b00000000
- #define R0\_HSCRL\_INH 0b01000000
- #define R0\_NO\_LCB 0b00000000
- #define R0\_LCB 0b00100000
- #define R0\_IE1\_OFF 0b00000000
- #define R0 IE1 0b00010000
- #define R0\_SS\_OFF 0b00000000
- #define R0\_SS 0b00001000

- #define R0 DEFAULT 0b00000110
- #define R0 ES OFF 0b00000000
- #define R0\_ES 0b00000001
- #define VDP R1 0b10000001
- #define R1 DEFAULT 0b10000000
- #define R1\_DISP\_OFF 0b00000000
- #define R1 DISP ON 0b01000000
- #define R1\_IE\_OFF 0b00000000
- #define R1\_IE 0b00100000
- #define R1 SPR 8X8 0b00000000
- #define R1 SPR 8X16 0b00000010
- #define VDP R2 0b10000010
- #define R2\_MAP\_0x3800 0xFF
- #define R2 MAP 0x3000 0xFD
- #define R2\_MAP\_0x2800 0xFB
- #define R2 MAP 0x2000 0xF9
- #define R2\_MAP\_0x1800 0xF7
- #define R2 MAP 0x1000 0xF5
- #define R2\_MAP\_0x0800 0xF3
- #define R2\_MAP\_0x0000 0xF1
- #define VDP\_R3 0b10000011
- #define VDP\_R4 0b10000100
- #define VDP\_R5 0b10000101
- #define R5\_SAT\_0x3F00 0xFF
- #define R5 SAT 0x1F00 0xBF
- #define R5\_SAT\_MASK 0b10000001
- #define VDP\_R6 0b10000110
- #define R6 BANK0 0xFB
- #define R6 DATA 0x0000 0xFB
- #define R6\_BANK1 0xFF
- #define R6 DATA 0x2000 0xFF
- #define VDP R7 0b10000111
- #define VDP\_RBORDER 0b10000111
- #define R7\_COLOR\_MASK 0b11110000
- #define VDP\_R8 0b10001000
- #define VDP\_RSCX 0b10001000
- #define VDP\_R9 0b10001001
- #define VDP\_RSCY 0b10001001
- #define VDP\_R10 0b10001010
- #define R10 INT OFF 0xFF
- #define R10\_INT\_EVERY 0x00
- #define JOY\_P1\_UP 0b00000001
- #define JOY\_P1\_MD\_Z JOY\_P1\_UP
- #define JOY\_P1\_DOWN 0b00000010
- #define JOY\_P1\_MD\_Y JOY\_P1\_DOWN
- #define JOY P1 LEFT 0b00000100
- #define JOY\_P1\_MD\_X JOY\_P1\_LEFT
- #define JOY\_P1\_RIGHT 0b00001000
- #define JOY\_P1\_MD\_MODE JOY\_P1\_RIGHT
- #define JOY\_P1\_SW1 0b00010000
- #define JOY P1 TRIGGER JOY P1 SW1
- #define JOY\_P1\_MD\_A JOY\_P1\_SW1
- #define JOY P1 SW2 0b00100000
- #define JOY\_P1\_MD\_START JOY\_P1\_SW2
- #define JOY\_P2\_UP 0b01000000

- #define JOY\_P2\_MD\_Z JOY\_P2\_UP
- #define JOY\_P2\_DOWN 0b10000000
- #define JOY P2 MD Y JOY P2 DOWN
- #define JOY P2 LEFT 0b00000001
- #define JOY\_P2\_MD\_X JOY\_P2\_LEFT
- #define JOY\_P2\_RIGHT 0b00000010
- #define JOY\_P2\_MD\_MODE JOY\_P2\_RIGHT
- #define JOY P2 SW1 0b00000100
- #define JOY P2 TRIGGER JOY P2 SW1
- #define JOY P2 MD A JOY P2 SW1
- #define JOY P2 SW2 0b00001000
- #define JOY\_P2\_MD\_START JOY\_P2\_SW2
- #define JOY RESET 0b00010000
- #define JOY\_P1\_LIGHT 0b01000000
- #define JOY P2 LIGHT 0b10000000
- #define RAMCTL\_BANK 0b00000100
- #define RAMCTL\_ROM 0b00000000
- #define RAMCTL\_RAM 0b00001000
- #define RAMCTL\_RO 0b00010000
- #define RAMCTL\_PROT 0b10000000
- #define VBK TILES 0
- #define VBK ATTRIBUTES 1
- #define VDP\_SAT\_TERM 0xD0
- #define DEVICE\_SCREEN\_PX\_WIDTH (DEVICE\_SCREEN\_WIDTH \* 8)
- #define DEVICE\_SCREEN\_PX\_HEIGHT (DEVICE\_SCREEN\_HEIGHT \* 8)

#### **Variables**

- UBYTE shadow VDP R0
- UBYTE shadow VDP R1
- UBYTE shadow VDP R2
- UBYTE shadow\_VDP\_R3
- UBYTE shadow\_VDP\_R4
- UBYTE shadow\_VDP\_R5
- UBYTE shadow\_VDP\_R6
- UBYTE shadow\_VDP\_R7UBYTE shadow VDP RBORDER
- UBYTE shadow\_VDP\_R8
- UBYTE shadow VDP RSCX
- UBYTE shadow\_VDP\_R9
- UBYTE shadow\_VDP\_RSCY
- UBYTE shadow VDP R10
- volatile UBYTE VDP\_ATTR\_SHIFT

### 20.48.1 Detailed Description

Defines that let the SMS/GG hardware registers be accessed from C.

# 20.48.2 Macro Definition Documentation

20.48.2.1 \_\_BYTES #define \_\_BYTES extern UBYTE

20.48.2.2 \_\_BYTE\_REG #define \_\_BYTE\_REG extern volatile UBYTE 20.48.2.3 GGSTATE\_STT #define GGSTATE\_STT 0b10000000 20.48.2.4 GGSTATE\_NJAP #define GGSTATE\_NJAP 0b01000000 20.48.2.5 GGSTATE\_NNTS #define GGSTATE\_NNTS 0b00100000 20.48.2.6 GGEXT\_NINIT #define GGEXT\_NINIT 0b10000000 20.48.2.7 SIOCTL\_TXFL #define SIOCTL\_TXFL 0b00000001 20.48.2.8 SIOCTL\_RXRD #define SIOCTL\_RXRD 0b00000010 20.48.2.9 SIOCTL\_FRER #define SIOCTL\_FRER 0b00000100 20.48.2.10 SIOCTL INT #define SIOCTL\_INT 0b00001000 20.48.2.11 SIOCTL\_TON #define SIOCTL\_TON 0b00010000 20.48.2.12 SIOCTL\_RON #define SIOCTL\_RON 0b00100000 **20.48.2.13 SIOCTL\_BS0** #define SIOCTL\_BS0 0b01000000 **20.48.2.14 SIOCTL\_BS1** #define SIOCTL\_BS1 0b10000000 20.48.2.15 SOUNDPAN\_TN1R #define SOUNDPAN\_TN1R 0b00000001 20.48.2.16 SOUNDPAN\_TN2R #define SOUNDPAN\_TN2R 0b00000010 20.48.2.17 SOUNDPAN\_TN3R #define SOUNDPAN\_TN3R 0b00000100 20.48.2.18 SOUNDPAN\_NOSR #define SOUNDPAN\_NOSR 0b00001000 20.48.2.19 SOUNDPAN\_TN1L #define SOUNDPAN\_TN1L 0b00010000

- $\textbf{20.48.2.20} \quad \textbf{SOUNDPAN\_TN2L} \quad \texttt{\#define SOUNDPAN\_TN2L 0b001000000}$
- 20.48.2.21 SOUNDPAN\_TN3L #define SOUNDPAN\_TN3L 0b01000000
- 20.48.2.22 SOUNDPAN\_NOSL #define SOUNDPAN\_NOSL 0b10000000
- 20.48.2.23 MEMCTL\_JOYON #define MEMCTL\_JOYON 0b00000000
- 20.48.2.24 MEMCTL\_JOYOFF #define MEMCTL\_JOYOFF 0b00000100
- 20.48.2.25 MEMCTL\_BASEON #define MEMCTL\_BASEON 0b00000000
- 20.48.2.26 MEMCTL\_BASEOFF #define MEMCTL\_BASEOFF 0b00001000
- 20.48.2.27 MEMCTL\_RAMON #define MEMCTL\_RAMON 0b00000000
- 20.48.2.28 MEMCTL\_RAMOFF #define MEMCTL\_RAMOFF 0b00010000
- 20.48.2.29 MEMCTL\_CROMON #define MEMCTL\_CROMON 0b00000000
- 20.48.2.30 MEMCTL\_CROMOFF #define MEMCTL\_CROMOFF 0b00100000
- 20.48.2.31 MEMCTL\_ROMON #define MEMCTL\_ROMON 0b00000000
- $\textbf{20.48.2.32} \quad \textbf{MEMCTL\_ROMOFF} \quad \texttt{\#define} \quad \texttt{MEMCTL\_ROMOFF} \quad \texttt{0b010000000}$
- $\textbf{20.48.2.33} \quad \textbf{MEMCTL\_EXTON} \quad \texttt{\#define} \quad \texttt{MEMCTL\_EXTON} \quad \texttt{0b000000000}$
- 20.48.2.34 MEMCTL\_EXTOFF #define MEMCTL\_EXTOFF 0b10000000
- **20.48.2.35 JOY\_P1\_TR\_DIR\_IN** #define JOY\_P1\_TR\_DIR\_IN 0b00000001
- **20.48.2.36 JOY\_P1\_TR\_DIR\_OUT** #define JOY\_P1\_TR\_DIR\_OUT 0b00000000
- $\textbf{20.48.2.37} \quad \textbf{JOY\_P1\_TH\_DIR\_IN} \quad \texttt{\#define JOY\_P1\_TH\_DIR\_IN 0b000000010}$

```
20.48.2.38 GUN_P1_LATCH #define GUN_P1_LATCH JOY_P1_TH_DIR_IN
20.48.2.39 JOY_P1_TH_DIR_OUT #define JOY_P1_TH_DIR_OUT 0b00000000
20.48.2.40 JOY_P2_TR_DIR_IN #define JOY_P2_TR_DIR_IN 0b00000100
20.48.2.41 JOY_P2_TR_DIR_OUT #define JOY_P2_TR_DIR_OUT 0b000000000
20.48.2.42 JOY_P2_TH_DIR_IN #define JOY_P2_TH_DIR_IN 0b00001000
20.48.2.43 GUN_P2_LATCH #define GUN_P2_LATCH JOY_P2_TH_DIR_IN
20.48.2.44 JOY_P2_TH_DIR_OUT #define JOY_P2_TH_DIR_OUT 0b00000000
20.48.2.45 JOY_P1_TR_OUT_HI #define JOY_P1_TR_OUT_HI 0b00010000
20.48.2.46 JOY_P1_TR_OUT_LO #define JOY_P1_TR_OUT_LO 0b00000000
20.48.2.47 JOY_P1_TH_OUT_HI #define JOY_P1_TH_OUT_HI 0b00100000
20.48.2.48 JOY_P1_TH_OUT_LO #define JOY_P1_TH_OUT_LO 0b00000000
20.48.2.49 JOY_P2_TR_OUT_HI #define JOY_P2_TR_OUT_HI 0b01000000
20.48.2.50 JOY_P2_TR_OUT_LO #define JOY_P2_TR_OUT_LO 0b00000000
20.48.2.51 JOY_P2_TH_OUT_HI #define JOY_P2_TH_OUT_HI 0b10000000
20.48.2.52 JOY_P2_TH_OUT_LO #define JOY_P2_TH_OUT_LO 0b00000000
20.48.2.53 JOY_TH_HI #define JOY_TH_HI (JOY_P1_TR_DIR_IN | JOY_P1_TH_DIR_OUT | JOY_P2_TR_DIR_IN
| JOY_P2_TH_DIR_OUT | JOY_P1_TR_OUT_HI | JOY_P1_TH_OUT_HI | JOY_P2_TR_OUT_HI | JOY_P2_TH_OUT_HI)
```

**20.48.2.54 JOY\_TH\_LO** #define JOY\_TH\_LO (JOY\_P1\_TR\_DIR\_IN | JOY\_P1\_TH\_DIR\_OUT | JOY\_P2\_TR\_DIR\_IN | JOY\_P2\_TH\_DIR\_OUT | JOY\_P2\_TH\_OUT\_LO | JOY\_P2\_TR\_OUT\_HI | JOY\_P2\_TH\_OUT\_LO)

- **20.48.2.55 PSG\_LATCH** #define PSG\_LATCH 0b10000000
- **20.48.2.56 PSG\_CH0** #define PSG\_CH0 0b00000000
- **20.48.2.57 PSG\_CH1** #define PSG\_CH1 0b00100000
- **20.48.2.58 PSG\_CH2** #define PSG\_CH2 0b01000000
- **20.48.2.59 PSG\_CH3** #define PSG\_CH3 0b01100000
- **20.48.2.60 PSG\_VOLUME** #define PSG\_VOLUME 0b00010000
- 20.48.2.61 STATF\_INT\_VBL #define STATF\_INT\_VBL 0b10000000
- **20.48.2.62 STATF\_9\_SPR** #define STATF\_9\_SPR 0b01000000
- 20.48.2.63 STATF\_SPR\_COLL #define STATF\_SPR\_COLL 0b00100000
- 20.48.2.64 VDP\_REG\_MASK #define VDP\_REG\_MASK 0b10000000
- **20.48.2.65 VDP\_R0** #define VDP\_R0 0b10000000
- **20.48.2.66 R0\_VSCRL** #define R0\_VSCRL 0b00000000
- **20.48.2.67 R0\_VSCRL\_INH** #define R0\_VSCRL\_INH 0b10000000
- **20.48.2.68 R0\_HSCRL** #define R0\_HSCRL 0b00000000
- **20.48.2.69 RO\_HSCRL\_INH** #define RO\_HSCRL\_INH 0b01000000
- **20.48.2.70 R0\_NO\_LCB** #define R0\_NO\_LCB 0b00000000
- **20.48.2.71 R0\_LCB** #define R0\_LCB 0b00100000
- **20.48.2.72 R0\_IE1\_OFF** #define R0\_IE1\_OFF 0b00000000

- **20.48.2.73 R0\_IE1** #define R0\_IE1 0b00010000
- **20.48.2.74 R0\_SS\_OFF** #define R0\_SS\_OFF 0b00000000
- **20.48.2.75 R0\_SS** #define R0\_SS 0b00001000
- **20.48.2.76 R0\_DEFAULT** #define R0\_DEFAULT 0b00000110
- **20.48.2.77 R0\_ES\_OFF** #define R0\_ES\_OFF 0b00000000
- **20.48.2.78 R0\_ES** #define R0\_ES 0b00000001
- **20.48.2.79 VDP\_R1** #define VDP\_R1 0b10000001
- **20.48.2.80 R1\_DEFAULT** #define R1\_DEFAULT 0b10000000
- **20.48.2.81 R1\_DISP\_OFF** #define R1\_DISP\_OFF 0b00000000
- **20.48.2.82 R1\_DISP\_ON** #define R1\_DISP\_ON 0b01000000
- **20.48.2.83 R1\_IE\_OFF** #define R1\_IE\_OFF 0b00000000
- **20.48.2.84 R1\_IE** #define R1\_IE 0b00100000
- **20.48.2.85** R1\_SPR\_8X8 #define R1\_SPR\_8X8 0b000000000
- **20.48.2.86 R1\_SPR\_8X16** #define R1\_SPR\_8X16 0b00000010
- **20.48.2.87 VDP\_R2** #define VDP\_R2 0b10000010
- **20.48.2.88 R2\_MAP\_0x3800** #define R2\_MAP\_0x3800 0xFF
- **20.48.2.89 R2\_MAP\_0x3000** #define R2\_MAP\_0x3000 0xFD
- **20.48.2.90 R2\_MAP\_0x2800** #define R2\_MAP\_0x2800 0xFB

- **20.48.2.91 R2\_MAP\_0x2000** #define R2\_MAP\_0x2000 0xF9
- **20.48.2.92 R2\_MAP\_0x1800** #define R2\_MAP\_0x1800 0xF7
- 20.48.2.93 R2\_MAP\_0x1000 #define R2\_MAP\_0x1000 0xF5
- **20.48.2.94 R2\_MAP\_0x0800** #define R2\_MAP\_0x0800 0xF3
- **20.48.2.95 R2\_MAP\_0x0000** #define R2\_MAP\_0x0000 0xF1
- **20.48.2.96 VDP\_R3** #define VDP\_R3 0b10000011
- **20.48.2.97 VDP\_R4** #define VDP\_R4 0b10000100
- **20.48.2.98 VDP\_R5** #define VDP\_R5 0b10000101
- **20.48.2.99 R5\_SAT\_0x3F00** #define R5\_SAT\_0x3F00 0xFF
- **20.48.2.100 R5\_SAT\_0x1F00** #define R5\_SAT\_0x1F00 0xBF
- **20.48.2.101 R5\_SAT\_MASK** #define R5\_SAT\_MASK 0b10000001
- **20.48.2.102 VDP\_R6** #define VDP\_R6 0b10000110
- $\textbf{20.48.2.103} \quad \textbf{R6\_BANK0} \quad \texttt{\#define} \;\; \texttt{R6\_BANK0} \;\; \texttt{0xFB}$
- $\textbf{20.48.2.104} \quad \textbf{R6\_DATA\_0x0000} \quad \texttt{\#define R6\_DATA\_0x0000 0xFB}$
- **20.48.2.105 R6\_BANK1** #define R6\_BANK1 0xFF
- **20.48.2.106 R6\_DATA\_0x2000** #define R6\_DATA\_0x2000 0xFF
- **20.48.2.107 VDP\_R7** #define VDP\_R7 0b10000111
- 20.48.2.108 VDP\_RBORDER #define VDP\_RBORDER 0b10000111

```
20.48.2.109 R7_COLOR_MASK #define R7_COLOR_MASK 0b11110000
20.48.2.110 VDP_R8 #define VDP_R8 0b10001000
20.48.2.111 VDP_RSCX #define VDP_RSCX 0b10001000
20.48.2.112 VDP_R9 #define VDP_R9 0b10001001
20.48.2.113 VDP_RSCY #define VDP_RSCY 0b10001001
20.48.2.114 VDP_R10 #define VDP_R10 0b10001010
20.48.2.115 R10_INT_OFF #define R10_INT_OFF 0xFF
20.48.2.116 R10_INT_EVERY #define R10_INT_EVERY 0x00
20.48.2.117 JOY_P1_UP #define JOY_P1_UP 0b00000001
\textbf{20.48.2.118} \quad \textbf{JOY\_P1\_MD\_Z} \quad \texttt{\#define JOY\_P1\_MD\_Z JOY\_P1\_UP}
20.48.2.119 JOY_P1_DOWN #define JOY_P1_DOWN 0b00000010
\textbf{20.48.2.120} \quad \textbf{JOY\_P1\_MD\_Y} \quad \texttt{\#define JOY\_P1\_MD\_Y JOY\_P1\_DOWN}
20.48.2.121 JOY_P1_LEFT #define JOY_P1_LEFT 0b00000100
\textbf{20.48.2.122} \quad \textbf{JOY\_P1\_MD\_X} \quad \texttt{\#define JOY\_P1\_MD\_X JOY\_P1\_LEFT}
20.48.2.123 JOY_P1_RIGHT #define JOY_P1_RIGHT 0b00001000
20.48.2.124 JOY_P1_MD_MODE #define JOY_P1_MD_MODE JOY_P1_RIGHT
20.48.2.125 JOY_P1_SW1 #define JOY_P1_SW1 0b00010000
20.48.2.126 JOY_P1_TRIGGER #define JOY_P1_TRIGGER JOY_P1_SW1
```

```
20.48.2.128 JOY_P1_SW2 #define JOY_P1_SW2 0b00100000
20.48.2.129 JOY_P1_MD_START #define JOY_P1_MD_START JOY_P1_SW2
20.48.2.130 JOY_P2_UP #define JOY_P2_UP 0b01000000
 \textbf{20.48.2.131} \quad \textbf{JOY\_P2\_MD\_Z} \quad \texttt{\#define JOY\_P2\_MD\_Z JOY\_P2\_UP} 
20.48.2.132 JOY_P2_DOWN #define JOY_P2_DOWN 0b10000000
20.48.2.133 JOY_P2_MD_Y #define JOY_P2_MD_Y JOY_P2_DOWN
20.48.2.134 JOY_P2_LEFT #define JOY_P2_LEFT 0b00000001
20.48.2.135 JOY_P2_MD_X #define JOY_P2_MD_X JOY_P2_LEFT
20.48.2.136 JOY_P2_RIGHT #define JOY_P2_RIGHT 0b00000010
20.48.2.137 JOY_P2_MD_MODE #define JOY_P2_MD_MODE JOY_P2_RIGHT
20.48.2.138 JOY_P2_SW1 #define JOY_P2_SW1 0b00000100
20.48.2.139 JOY_P2_TRIGGER #define JOY_P2_TRIGGER JOY_P2_SW1
20.48.2.140 JOY_P2_MD_A #define JOY_P2_MD_A JOY_P2_SW1
20.48.2.141 JOY_P2_SW2 #define JOY_P2_SW2 0b00001000
20.48.2.142 JOY_P2_MD_START #define JOY_P2_MD_START JOY_P2_SW2
20.48.2.143 JOY_RESET #define JOY_RESET 0b00010000
20.48.2.144 JOY_P1_LIGHT #define JOY_P1_LIGHT 0b01000000
```

```
20.48.2.145 JOY_P2_LIGHT #define JOY_P2_LIGHT 0b10000000
20.48.2.146 RAMCTL BANK #define RAMCTL_BANK 0b00000100
20.48.2.147 RAMCTL_ROM #define RAMCTL_ROM 0b00000000
20.48.2.148 RAMCTL RAM #define RAMCTL_RAM 0b00001000
20.48.2.149 RAMCTL_RO #define RAMCTL_RO 0b00010000
20.48.2.150 RAMCTL PROT #define RAMCTL_PROT 0b10000000
\textbf{20.48.2.151} \quad \textbf{VBK\_TILES} \quad \texttt{\#define VBK\_TILES 0}
20.48.2.152 VBK_ATTRIBUTES #define VBK_ATTRIBUTES 1
20.48.2.153 VDP_SAT_TERM #define VDP_SAT_TERM 0xD0
20.48.2.154 DEVICE_SCREEN_PX_WIDTH #define DEVICE_SCREEN_PX_WIDTH (DEVICE_SCREEN_WIDTH *
20.48.2.155 DEVICE_SCREEN_PX_HEIGHT #define DEVICE_SCREEN_PX_HEIGHT (DEVICE_SCREEN_HEIGHT
* 8)
20.48.3 Variable Documentation
20.48.3.1 shadow_VDP_R0 UBYTE shadow_VDP_R0 [extern]
20.48.3.2 shadow_VDP_R1 UBYTE shadow_VDP_R1 [extern]
20.48.3.3 shadow_VDP_R2 UBYTE shadow_VDP_R2 [extern]
20.48.3.4 shadow_VDP_R3 UBYTE shadow_VDP_R3 [extern]
20.48.3.5 shadow_VDP_R4 UBYTE shadow_VDP_R4 [extern]
20.48.3.6 shadow_VDP_R5 UBYTE shadow_VDP_R5 [extern]
```

```
20.48.3.7 shadow_VDP_R6 UBYTE shadow_VDP_R6 [extern]

20.48.3.8 shadow_VDP_R7 UBYTE shadow_VDP_R7 [extern]

20.48.3.9 shadow_VDP_RBORDER UBYTE shadow_VDP_RBORDER [extern]

20.48.3.10 shadow_VDP_R8 UBYTE shadow_VDP_R8 [extern]

20.48.3.11 shadow_VDP_RSCX UBYTE shadow_VDP_RSCX [extern]

20.48.3.12 shadow_VDP_R9 UBYTE shadow_VDP_R9 [extern]

20.48.3.13 shadow_VDP_RSCY UBYTE shadow_VDP_RSCY [extern]

20.48.3.14 shadow_VDP_R10 UBYTE shadow_VDP_R10 [extern]

20.48.3.15 VDP_ATTR_SHIFT volatile UBYTE VDP_ATTR_SHIFT [extern]
```

# 20.49 gbdk-lib/include/gb/hblankcpy.h File Reference

```
#include <stdint.h>
```

#### **Functions**

- void hblank\_copy\_vram (const uint8\_t \*sour, uint8\_t count)
- void hblank cpy vram (const uint8 t \*sour, uint8 t count)
- void hblank\_copy (uint8\_t \*dest, const uint8\_t \*sour, uint16\_t size)

#### **Variables**

• uint8 t \* hblank copy destination

#### 20.49.1 Function Documentation

#### **Parameters**

sour	Source address to copy from
count	Number of 16 byte chunks to copy

Performs the required STAT\_REG, IE\_REG, IF\_REG manipulation when called and restores STAT\_REG and IE\_←

REG on exit (unlike hblank\_cpy\_vram()). Before calling:

- Set the destination using hblank\_copy\_destination
- · Interrupts must be disabled

#### See also

hblank\_cpy\_vram, hblank\_copy\_destination, hblank\_copy

ribianik olasik oopy roalink

#### **Parameters**

sour	Source address to copy from
count	Number of 16 byte chunks to copy

Unlike hblank\_copy\_vram() does not perform the required STAT\_REG, IE\_REG, IF\_REG manipulation, nor does it restore STAT\_REG and IE\_REG on exit.

Before calling:

- Set the destination using hblank\_copy\_destination
- · Interrupts must be properly configured
- · Interrupts must be disabled

#### See also

hblank\_copy\_vram, hblank\_copy\_destination, hblank\_copy

HBlank stack copy routine (must be called with interrupts disabled!)

#### **Parameters**

dest	destination pointer
sour	source pointer
size	number of bytes to copy (rounded to 16-byte chunks)

Performs a fast vram safe copy of data during HBlank.

#### 20.49.2 Variable Documentation

```
20.49.2.1 hblank_copy_destination uint8_t* hblank_copy_destination [extern] Destination address for hblank copy routine
```

# 20.50 gbdk-lib/include/gb/isr.h File Reference

```
#include <stdint.h>
#include <types.h>
```

#### **Data Structures**

- · struct isr\_vector\_t
- · struct isr\_nested\_vector\_t

#### **Macros**

- #define VECTOR STAT 0x48
- #define VECTOR TIMER 0x50
- #define VECTOR\_SERIAL 0x58
- #define VECTOR\_JOYPAD 0x60
- #define ISR\_VECTOR(ADDR, FUNC) static const isr\_vector\_t AT((ADDR)) \_\_ISR\_ ## ADDR = {0xc3, (void \*)&(FUNC)};
- #define ISR\_NESTED\_VECTOR(ADDR, FUNC) static const isr\_nested\_vector\_t AT((ADDR)) \_\_ISR\_ ##
  ADDR = {{0xfb, 0xc3}, (void \*)&(FUNC)};

### **Typedefs**

- typedef struct isr\_vector\_t isr\_vector\_t
- typedef struct isr\_nested\_vector\_t isr\_nested\_vector\_t

#### 20.50.1 Detailed Description

Macros for creating raw interrupt service routines (ISRs) which do not use the default GBDK ISR dispatcher. Handlers installed this way will have less overhead than ones which use the GBDK ISR dispatcher.

### 20.50.2 Macro Definition Documentation

```
20.50.2.1 VECTOR_STAT #define VECTOR_STAT 0x48 Address for the STAT interrupt vector
```

```
20.50.2.2 VECTOR_TIMER \#define\ VECTOR\_TIMER\ 0x50 Address for the TIMER interrupt vector
```

```
20.50.2.3 VECTOR_SERIAL #define VECTOR_SERIAL 0x58 Address for the SERIAL interrupt vector
```

```
20.50.2.4 VECTOR_JOYPAD #define VECTOR_JOYPAD 0x60 Address for the JOYPAD interrupt vector
```

Creates an interrupt vector at the given address for a raw interrupt service routine (which does not use the GBDK ISR dispatcher)

# **Parameters**

ADDR	Address of the interrupt vector, any of: VECTOR_STAT, VECTOR_TIMER, VECTOR_SERIAL, VECTOR_JOYPAD
FUNC	ISR function supplied by the user

This cannot be used with the VBLANK interrupt.

Do not use this in combination with interrupt installers that rely on the default GBDK ISR dispatcher such as add\_TIM(), remove\_TIM() (and the same for all other interrupts).

#### Example:

```
#include <gb/isr.h>
void TimerISR() __critical __interrupt {
// some ISR code here
}
ISR_VECTOR(VECTOR_TIMER, TimerISR)
```

#### See also

ISR\_NESTED\_VECTOR, set\_interrupts

Creates an interrupt vector at the given address for a raw interrupt service routine allowing nested interrupts

#### **Parameters**

ADDR	Address of the interrupt vector, any of: VECTOR_STAT, VECTOR_TIMER, VECTOR_SERIAL, VECTOR_JOYPAD	
FUNC	1 1 41	-

This cannot be used with the VBLANK interrupt

The LCD STAT vector (VECTOR\_STAT) cannot be used in the same program as stdio.h since they install an ISR vector to the same location.

#### See also

```
ISR_VECTOR
```

### 20.50.3 Typedef Documentation

```
20.50.3.1 isr_vector_t typedef struct isr_vector_t isr_vector_t
```

 $\textbf{20.50.3.2} \quad \textbf{isr\_nested\_vector\_t} \quad \textbf{typedef struct isr\_nested\_vector\_t} \quad \textbf{isr\_nested\_vector\_t}$ 

### 20.51 gbdk-lib/include/gb/metasprites.h File Reference

```
#include <gb/hardware.h>
#include <types.h>
#include <stdint.h>
```

#### **Data Structures**

struct metasprite\_t

#### **Macros**

- #define metasprite\_end -128
- #define METASPR\_ITEM(dy, dx, dt, a) {(dy),(dx),(dt),(a)}
- #define METASPR\_TERM {metasprite\_end}

#### **Typedefs**

typedef struct metasprite\_t metasprite\_t

#### **Functions**

- void hide sprites range (uint8 t from, uint8 t to)
- uint8\_t move\_metasprite\_ex (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_prop, uint8\_t base\_sprite, uint8\_t x, uint8\_t y)
- uint8\_t move\_metasprite (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_sprite, uint8\_t x, uint8\_t y)
- uint8\_t move\_metasprite\_flipx (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_prop, uint8\_t base sprite, uint8 t x, uint8 t y)
- uint8\_t move\_metasprite\_vflip (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_sprite, uint8\_t x, uint8\_t y)
- uint8\_t move\_metasprite\_flipy (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_prop, uint8\_t base\_sprite, uint8\_t x, uint8\_t y)
- uint8\_t move\_metasprite\_hflip (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_sprite, uint8\_t x, uint8\_t y)
- uint8\_t move\_metasprite\_flipxy (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_prop, uint8\_t base sprite, uint8 t x, uint8 t y)
- uint8\_t move\_metasprite\_hvflip (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_sprite, uint8 t x, uint8 t y)
- void hide\_metasprite (const metasprite\_t \*metasprite, uint8\_t base\_sprite)

#### **Variables**

- const void \* current metasprite
- uint8 t current base tile
- uint8\_t \_\_current\_base\_prop
- uint8\_t \_\_render\_shadow\_OAM

#### 20.51.1 Detailed Description

## 20.51.2 Metasprite support

A metasprite is a larger sprite made up from a collection of smaller individual hardware sprites. Different frames of the same metasprites can share tile data.

The api supports metasprites in both SPRITES\_8x8 and SPRITES\_8x16 mode. If 8x16 mode is used then the height of the metasprite must be a multiple of 16.

The origin (pivot) for the metasprite is not required to be in the upper left-hand corner as with regular hardware sprites.

Use the utility\_png2asset tool to convert single or multiple frames of graphics into metasprite structured data for use with the ...metasprite...() functions.

## 20.51.3 Metasprites composed of variable numbers of sprites

When using png2asset, it's common for the output of different frames to be composed of different numbers of hardware sprites (since it's trying to create each frame as efficiently as possible). Due to that, it's good practice to clear out (hide) unused sprites in the shadow\_OAM that have been set by previous frames.

```
// Example:
// Hide rest of the hardware sprites, because amount
// of sprites differ between animation frames.
// (where hiwater == last hardware sprite used + 1)
hide_sprites_range(hiwater, MAX_HARDWARE_SPRITES);
```

## 20.51.4 Metasprites and sprite properties (including cgb palette)

When the move\_metasprite\_\*() functions are called they update all properties for the affected sprites in the Shadow OAM. This means any existing property flags set for a sprite (CGB palette, BG/WIN priority, Tile VRAM Bank) will get overwritten.

How to use sprite property flags with metasprites:

- Primary method: Use the base\_prop parameter for the move\_metasprite\_\*() functions.
  - For more details about the properties on the Game Boy see: https://gbdev.io/pandocs/← OAM.html#byte-3-attributesflags
  - This can be left at zero for defaults
  - Various OAMF \* flags can be used depending on the platform:
    - \* OAMF\_BANK0, OAMF\_BANK1
    - \* OAMF\_CGB\_PAL0, OAMF\_CGB\_PAL1, OAMF\_CGB\_PAL2, OAMF\_CGB\_PAL3, OAMF\_CGB\_PAL4, OAMF\_CGB\_PAL5, OAMF\_CGB\_PAL6, OAMF\_CGB\_PAL7,
    - \* OAMF PALO, OAMF PAL1,
    - \* OAMF\_PALMASK, OAMF\_PRI, OAMF\_XFLIP, OAMF\_YFLIP
- Alternate method: The metasprite structures can have the property flags modified before compilation (such as with -sp props> in the png2asset tool).

The following functions only support hardware sprite flipping on the Game Boy / Mega Duck and NES. For other consoles which do not have hardware sprite flipping see the cross-platform metasprite example for a workaround (with some performance penalty).

- move\_metasprite\_flipx()
- move metasprite flipy()
- move\_metasprite\_flipxy()

To test for hardware support see HARDWARE\_SPRITE\_CAN\_FLIP\_X and HARDWARE\_SPRITE\_CAN\_FLIP\_Y. Also see docs consoles supported list for a brief summary of console capabilities.

#### 20.51.5 Macro Definition Documentation

```
20.51.5.1 metasprite_end #define metasprite_end -128
```

```
20.51.5.3 METASPR_TERM #define METASPR_TERM {metasprite_end}
```

## 20.51.6 Typedef Documentation

```
20.51.6.1 metasprite_t typedef struct metasprite_t metasprite_t Metasprite sub-item structure
```

#### **Parameters**

dy	(int8_t) Y coordinate of the sprite relative to the metasprite origin (pivot)
dx	(int8_t) X coordinate of the sprite relative to the metasprite origin (pivot)
dtile	(uint8_t) Start tile relative to the metasprites own set of tiles
props	(uint8_t) Property Flags

Metasprites are built from multiple metasprite\_t items (one for each sub-sprite) and a pool of tiles they reference. If a metasprite has multiple frames then each frame will be built from some number of metasprite\_t items (which may vary based on how many sprites are required for that particular frame).

A metasprite frame is terminated with a {metasprite\_end} entry.

## 20.51.7 Function Documentation

Hides all hardware sprites in range from  $\leq$ = X  $\leq$  to

#### **Parameters**

from	start OAM index
to	finish OAM index (must be <= MAX_HARDWARE_SPRITES)

## See also

# hide\_sprite, MAX\_HARDWARE\_SPRITES

Hides all hardware sprites in range from <= X < to

## **Parameters**

from	start OAM index
to	finish OAM index

Moves metasprite to the absolute position x and y

# **Parameters**

metasprite	Pointer to the first struct of the metasprite (for the desired frame)
base_tile	Number of the first tile where the metasprite's tiles start
base_prop	Base sprite property flags (can be used to set palette, etc)
base_sprite	Number of the first hardware sprite to be used by the metasprite
X	Absolute x coordinate of the sprite
У	Absolute y coordinate of the sprite

Moves **metasprite** to the absolute position **x** and **y** (with **no flip** on the X or Y axis). Hardware sprites are allocated starting from **base\_sprite**, using tiles starting from **base\_tile**. Sets:

- \_\_current\_metasprite = metasprite;
- \_\_current\_base\_tile = base\_tile;

Note: Overwrites OAM sprite properties (such as CGB Palette), see Metasprites and sprite properties.

#### Returns

Number of hardware sprites used to draw this metasprite

Obsolete. This function has been replaced by move metasprite ex()

Moves metasprite to the absolute position x and y, flipped by X (horizontally)

## **Parameters**

metasprite	Pointer to the first struct of the metasprite (for the desired frame)
base_tile	Number of the first tile where the metasprite's tiles start
base_prop	Base sprite property flags (can be used to set palette, etc)
base_sprite	Number of the first hardware sprite to be used by the metasprite
X	Absolute x coordinate of the sprite
У	Absolute y coordinate of the sprite

Same as move\_metasprite(), but with the metasprite flipped by X (horizontally). Sets:

```
__current_metasprite = metasprite;
```

```
__current_base_tile = base_tile;
```

Note: Overwrites OAM sprite properties (such as CGB palette), see Metasprites and sprite properties. This function is only available on Game Boy and related clone consoles.

#### Returns

Number of hardware sprites used to draw this metasprite

#### See also

move\_metasprite()

Obsolete. This function has been replaced by move\_metasprite\_flipx()

Moves metasprite to the absolute position x and y, flipped by Y (vertically)

#### **Parameters**

metasprite	Pointer to the first struct of the metasprite (for the desired frame)
base_tile	Number of the first tile where the metasprite's tiles start
base_prop	Base sprite property flags (can be used to set palette, etc)
base_sprite	Number of the first hardware sprite to be used by the metasprite
X	Absolute x coordinate of the sprite
У	Absolute y coordinate of the sprite

Same as move\_metasprite(), but with the metasprite flipped by Y (vertically). Sets:

- \_\_current\_metasprite = metasprite;
- \_\_current\_base\_tile = base\_tile;

Note: Overwrites OAM sprite properties (such as CGB palette), see Metasprites and sprite properties. This function is only available on Game Boy and related clone consoles.

# Returns

Number of hardware sprites used to draw this metasprite

## See also

move\_metasprite()

Obsolete. This function has been replaced by move\_metasprite\_flipy()

```
uint8_t x,
uint8_t y ) [inline]
```

Moves metasprite to the absolute position x and y, flipped by X and Y (horizontally and vertically)

#### **Parameters**

metasprite	Pointer to the first struct of the metasprite (for the desired frame)
base_tile	Number of the first tile where the metasprite's tiles start
base_prop	Base sprite property flags (can be used to set palette, etc)
base_sprite	Number of the first hardware sprite to be used by the metasprite
X	Absolute x coordinate of the sprite
У	Absolute y coordinate of the sprite

Same as move\_metasprite(), but with the metasprite flipped by X and Y (horizontally and vertically). Sets:

```
__current_metasprite = metasprite;
```

```
__current_base_tile = base_tile;
```

Note: Overwrites OAM sprite properties (such as CGB palette), see Metasprites and sprite properties. This function is only available on Game Boy and related clone consoles.

#### Returns

Number of hardware sprites used to draw this metasprite

#### See also

move\_metasprite()

Obsolete. This function has been replaced by move\_metasprite\_flipxy()

Hides a metasprite from the screen

#### **Parameters**

metasprite	Pointer to first struct of the desired metasprite frame
base_sprite	Number of hardware sprite to start with

# Sets:

\_\_current\_metasprite = metasprite;

## 20.51.8 Variable Documentation

```
20.51.8.1 __current_metasprite const void* __current_metasprite [extern]

20.51.8.2 __current_base_tile uint8_t __current_base_tile [extern]

20.51.8.3 __current_base_prop uint8_t __current_base_prop [extern]

20.51.8.4 __render_shadow_OAM uint8_t __render_shadow_OAM [extern]

20.52 gbdk-lib/include/gbdk/metasprites.h File Reference
```

# 20.53 gbdk-lib/include/msx/metasprites.h File Reference

```
#include <msx/hardware.h>
#include <types.h>
#include <stdint.h>
```

#include <gb/metasprites.h>

## **Data Structures**

· struct metasprite\_t

#### **Macros**

- #define metasprite\_end -128
- #define METASPR\_ITEM(dy, dx, dt, a) {(dy),(dx),(dt),(a)}
- #define METASPR\_TERM {metasprite\_end}

## **Typedefs**

typedef struct metasprite\_t metasprite\_t

## **Functions**

- void hide\_sprites\_range (uint8\_t from, uint8\_t to) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- uint8\_t move\_metasprite\_ex (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_prop, uint8\_t base sprite, uint8 t x, uint8 t y)
- uint8\_t move\_metasprite (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_sprite, uint8\_t x, uint8\_t y)
- void hide\_metasprite (const metasprite\_t \*metasprite, uint8\_t base\_sprite)

## **Variables**

- const void \* \_\_current\_metasprite
- uint8\_t \_\_current\_base\_tile
- uint8\_t \_\_render\_shadow\_OAM
- static uint8\_t iyl

#### 20.53.1 Macro Definition Documentation

## 20.53.1.1 metasprite\_end #define metasprite\_end -128

# 20.53.1.3 METASPR\_TERM #define METASPR\_TERM {metasprite\_end}

## 20.53.2 Typedef Documentation

# 20.53.2.1 metasprite\_t typedef struct metasprite\_t metasprite\_t Metasprite sub-item structure

#### **Parameters**

dy	(int8_t) Y coordinate of the sprite relative to the metasprite origin (pivot)
dx	(int8_t) X coordinate of the sprite relative to the metasprite origin (pivot)
dtile	(uint8_t) Start tile relative to the metasprites own set of tiles
props	(uint8_t) Property Flags

Metasprites are built from multiple metasprite\_t items (one for each sub-sprite) and a pool of tiles they reference. If a metasprite has multiple frames then each frame will be built from some number of metasprite\_t items (which may vary based on how many sprites are required for that particular frame).

A metasprite frame is terminated with a {metasprite\_end} entry.

## 20.53.3 Function Documentation

Hides all hardware sprites in range from  $\leq$ = X  $\leq$  to

## **Parameters**

from	start OAM index
to	finish OAM index

Moves metasprite to the absolute position x and y

#### **Parameters**

metasprite	Pointer to the first struct of the metasprite (for the desired frame)
base_tile	Number of the first tile where the metasprite's tiles start
base_prop	Base sprite property flags (unused on this platform)
base_sprite	Number of the first hardware sprite to be used by the metasprite
X	Absolute x coordinate of the sprite
У	Absolute y coordinate of the sprite

Moves **metasprite** to the absolute position **x** and **y** (with **no flip** on the X or Y axis). Hardware sprites are allocated starting from **base\_sprite**, using tiles starting from **base\_tile**. Sets:

```
    current metasprite = metasprite;
```

```
__current_base_tile = base_tile;
```

#### Returns

Number of hardware sprites used to draw this metasprite

# Obsolete

Hides a metasprite from the screen

## **Parameters**

metasprite	Pointer to first struct of the desired metasprite frame
base_sprite	Number of hardware sprite to start with

## Sets:

\_\_current\_metasprite = metasprite;

## 20.53.4 Variable Documentation

```
20.53.4.1 __current_metasprite const void* __current_metasprite [extern]
20.53.4.2 __current_base_tile uint8_t __current_base_tile [extern]
20.53.4.3 __render_shadow_OAM uint8_t __render_shadow_OAM [extern]
```

```
20.53.4.4 iyl uint8_t iyl
Initial value:
{
    _asm__("ei")
```

# 20.54 gbdk-lib/include/nes/metasprites.h File Reference

```
#include <nes/hardware.h>
#include <types.h>
#include <stdint.h>
```

#### **Data Structures**

· struct metasprite\_t

#### **Macros**

- #define metasprite\_end -128
- #define METASPR ITEM(dy, dx, dt, a) {(dy),(dx),(dt),(a)}
- #define METASPR TERM {metasprite end}

## **Typedefs**

· typedef struct metasprite\_t metasprite\_t

## **Functions**

- void hide\_sprites\_range (uint8\_t from, uint8\_t to) OLDCALL
- uint8\_t move\_metasprite\_ex (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_prop, uint8\_t base\_sprite, int16\_t x, int16\_t y)
- uint8\_t move\_metasprite (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_sprite, int16\_t x, int16\_t y)
- uint8\_t move\_metasprite\_flipx (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_prop, uint8\_t base\_sprite, int16\_t x, int16\_t y)
- uint8\_t move\_metasprite\_vflip (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_sprite, int16\_t x, int16\_t y)
- uint8\_t move\_metasprite\_flipy (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_prop, uint8\_t base\_sprite, int16\_t x, int16\_t y)
- uint8\_t move\_metasprite\_hflip (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_sprite, int16\_t x, int16\_t y)
- uint8\_t move\_metasprite\_flipxy (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_prop, uint8\_t base\_sprite, int16\_t x, int16\_t y)
- uint8\_t move\_metasprite\_hvflip (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_sprite, int16\_t x, int16\_t y)
- void hide\_metasprite (const metasprite\_t \*metasprite, uint8\_t base\_sprite)

#### **Variables**

- const void \* current metasprite
- uint8\_t \_\_current\_base\_tile
- uint8\_t \_\_current\_base\_prop
- uint8\_t \_\_render\_shadow\_OAM

## 20.54.1 Detailed Description

# 20.54.2 Metasprite support

A metasprite is a larger sprite made up from a collection of smaller individual hardware sprites. Different frames of the same metasprites can share tile data.

See the main metasprite docs under the game Boy platform for additional details.

#### 20.54.3 Macro Definition Documentation

## **20.54.3.1 metasprite\_end** #define metasprite\_end -128

# 20.54.3.3 METASPR\_TERM #define METASPR\_TERM {metasprite\_end}

## 20.54.4 Typedef Documentation

```
20.54.4.1 metasprite_t typedef struct metasprite_t metasprite_t Metasprite sub-item structure
```

## **Parameters**

dy	(int8_t) Y coordinate of the sprite relative to the metasprite origin (pivot)
dx	(int8_t) X coordinate of the sprite relative to the metasprite origin (pivot)
dtile	(uint8_t) Start tile relative to the metasprites own set of tiles
props	(uint8_t) Property Flags

Metasprites are built from multiple metasprite\_t items (one for each sub-sprite) and a pool of tiles they reference. If a metasprite has multiple frames then each frame will be built from some number of metasprite\_t items (which may vary based on how many sprites are required for that particular frame).

A metasprite frame is terminated with a {metasprite\_end} entry.

## 20.54.5 Function Documentation

Hides all hardware sprites in range from  $\leq$ = X  $\leq$  to

## **Parameters**

from	start OAM index
to	finish OAM index

```
int16_t x,
int16_t y) [inline]
```

Moves metasprite to the absolute position x and y

#### **Parameters**

metasprite	Pointer to the first struct of the metasprite (for the desired frame)
base_tile	Number of the first tile where the metasprite's tiles start
base_prop	Base sprite property flags
base_sprite	Number of the first hardware sprite to be used by the metasprite
X	Absolute x coordinate of the sprite
У	Absolute y coordinate of the sprite

Moves **metasprite** to the absolute position **x** and **y** (with **no flip** on the X or Y axis). Hardware sprites are allocated starting from **base\_sprite**, using tiles starting from **base\_tile**.

Sets:

```
__current_metasprite = metasprite;
```

```
    current base tile = base tile;
```

Note: Overwrites OAM sprite properties (such as palette), see Metasprites and sprite properties.

#### Returns

Number of hardware sprites used to draw this metasprite

Obsolete. Replaced by move\_metasprite\_ex()

Moves metasprite to the absolute position x and y, flipped by X (horizontally)

#### **Parameters**

metasprite	Pointer to the first struct of the metasprite (for the desired frame)
base_tile	Number of the first tile where the metasprite's tiles start
base_prop	Base sprite property flags
base_sprite	Number of the first hardware sprite to be used by the metasprite
X	Absolute x coordinate of the sprite
У	Absolute y coordinate of the sprite

Same as move\_metasprite(), but with the metasprite flipped by X (horizontally). Sets:

```
__current_metasprite = metasprite;
```

```
    current base tile = base tile;
```

Note: Overwrites OAM sprite properties (such as palette), see Metasprites and sprite properties.

Returns

Number of hardware sprites used to draw this metasprite

See also

move\_metasprite()

Obsolete. Replaced by move\_metasprite\_flipx()

Moves metasprite to the absolute position x and y, flipped by Y (vertically)

## **Parameters**

metasprite	Pointer to the first struct of the metasprite (for the desired frame)
base_tile	Number of the first tile where the metasprite's tiles start
base_prop	Base sprite property flags
base_sprite	Number of the first hardware sprite to be used by the metasprite
X	Absolute x coordinate of the sprite
У	Absolute y coordinate of the sprite

Same as move\_metasprite(), but with the metasprite flipped by Y (vertically). Sets:

```
__current_metasprite = metasprite;
```

```
__current_base_tile = base_tile;
```

Note: Overwrites OAM sprite properties (such as palette), see Metasprites and sprite properties.

Returns

Number of hardware sprites used to draw this metasprite

See also

```
move_metasprite()
```

Moves metasprite to the absolute position x and y, flipped by X and Y (horizontally and vertically)

#### **Parameters**

metasprite	Pointer to the first struct of the metasprite (for the desired frame)
base_tile	Number of the first tile where the metasprite's tiles start
base_prop	Base sprite property flags
base_sprite	Number of the first hardware sprite to be used by the metasprite
X	Absolute x coordinate of the sprite
У	Absolute y coordinate of the sprite

Same as move\_metasprite(), but with the metasprite flipped by X and Y (horizontally and vertically). Sets:

```
__current_metasprite = metasprite;
```

```
• __current_base_tile = base_tile;
```

Note: Overwrites OAM sprite properties (such as palette), see Metasprites and sprite properties.

## Returns

Number of hardware sprites used to draw this metasprite

## See also

move\_metasprite()

Obsolete. Replaced by move\_metasprite\_flipxy()

Hides a metasprite from the screen

#### **Parameters**

metasprite	Pointer to first struct of the desired metasprite frame
base_sprite	Number of hardware sprite to start with

## Sets:

\_\_current\_metasprite = metasprite;

## 20.54.6 Variable Documentation

```
20.54.6.1 __current_metasprite const void* __current_metasprite [extern]
20.54.6.2 __current_base_tile uint8_t __current_base_tile [extern]
20.54.6.3 __current_base_prop uint8_t __current_base_prop [extern]
20.54.6.4 __render_shadow_OAM uint8_t __render_shadow_OAM [extern]
```

# 20.55 gbdk-lib/include/sms/metasprites.h File Reference

```
#include <sms/sms.h>
#include <sms/hardware.h>
#include <types.h>
#include <stdint.h>
```

## **Data Structures**

• struct metasprite\_t

#### Macros

- #define metasprite end -128
- #define METASPR\_ITEM(dy, dx, dt, a) {(dy),(dx),(dt)}
- #define METASPR\_TERM {metasprite\_end}

## **Typedefs**

typedef struct metasprite\_t metasprite\_t

### **Functions**

- void hide\_sprites\_range (uint8\_t from, uint8\_t to) PRESERVES\_REGS(iyh
- uint8\_t move\_metasprite\_ex (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_prop, uint8\_t base sprite, uint16 t x, uint16 t y)
- uint8\_t move\_metasprite (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_sprite, uint16\_t x, uint16\_t y)
- uint8\_t move\_metasprite\_flipx (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_prop, uint8\_t base\_sprite, uint16\_t x, uint16\_t y)
- uint8\_t move\_metasprite\_flipy (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_prop, uint8\_t base\_sprite, uint16\_t x, uint16\_t y)

- uint8\_t move\_metasprite\_flipxy (const metasprite\_t \*metasprite, uint8\_t base\_tile, uint8\_t base\_prop, uint8\_t base\_sprite, uint16\_t x, uint16\_t y)
- void hide\_metasprite (const metasprite\_t \*metasprite, uint8\_t base\_sprite)

#### **Variables**

- const void \* current metasprite
- uint8\_t \_\_current\_base\_tile
- uint8\_t \_\_render\_shadow\_OAM
- static void iyl

## 20.55.1 Detailed Description

## 20.55.2 Metasprite support

A metasprite is a larger sprite made up from a collection of smaller individual hardware sprites. Different frames of the same metasprites can share tile data.

See the main metasprite docs under the game Boy platform for additional details.

## 20.55.3 Metasprite support

A metasprite is a larger sprite made up from a collection of smaller individual hardware sprites. Different frames of the same metasprites can share tile data.

See the main metasprite docs under the game Boy platform for additional details.

#### 20.55.4 Macro Definition Documentation

```
20.55.4.1 metasprite_end #define metasprite_end -128
```

```
20.55.4.3 METASPR_TERM #define METASPR_TERM {metasprite_end}
```

## 20.55.5 Typedef Documentation

```
20.55.5.1 metasprite_t typedef struct metasprite_t metasprite_t Metasprite sub-item structure
```

## **Parameters**

dy	(int8_t) Y coordinate of the sprite relative to the metasprite origin (pivot)
dx	(int8_t) X coordinate of the sprite relative to the metasprite origin (pivot)
dtile	(uint8_t) Start tile relative to the metasprites own set of tiles

Metasprites are built from multiple metasprite\_t items (one for each sub-sprite) and a pool of tiles they reference. If a metasprite has multiple frames then each frame will be built from some number of metasprite\_t items (which may vary based on how many sprites are required for that particular frame).

A metasprite frame is terminated with a {metasprite\_end} entry.

## 20.55.6 Function Documentation

Hides all hardware sprites in range from  $\leq$ = X  $\leq$  to

#### **Parameters**

from	start OAM index
to	finish OAM index

Moves metasprite to the absolute position x and y

### **Parameters**

metasprite	Pointer to the first struct of the metasprite (for the desired frame)
base_tile	Number of the first tile where the metasprite's tiles start
base_prop	Base sprite property flags (unused on this platform)
base_sprite	Number of the first hardware sprite to be used by the metasprite
X	Absolute x coordinate of the sprite
У	Absolute y coordinate of the sprite

Moves **metasprite** to the absolute position **x** and **y** (with **no flip** on the X or Y axis). Hardware sprites are allocated starting from **base\_sprite**, using tiles starting from **base\_tile**.

Sets:

```
• __current_metasprite = metasprite;
```

```
__current_base_tile = base_tile;
```

#### Returns

Number of hardware sprites used to draw this metasprite

Obsolete. This function has been replaced by move\_metasprite\_ex()

Moves metasprite to the absolute position x and y, flipped by X (horizontally)

#### **Parameters**

metasprite	Pointer to the first struct of the metasprite (for the desired frame)
base_tile	Number of the first tile where the metasprite's tiles start
base_prop	Base sprite property flags (unused on this platform)
base_sprite	Number of the first hardware sprite to be used by the metasprite
X	Absolute x coordinate of the sprite
У	Absolute y coordinate of the sprite

Same as move\_metasprite(), but with the metasprite flipped by X (horizontally). Sets:

```
__current_metasprite = metasprite;
```

```
• __current_base_tile = base_tile;
```

Note: Overwrites OAM sprite properties (such as palette), see Metasprites and sprite properties.

#### Returns

Number of hardware sprites used to draw this metasprite

## See also

move\_metasprite()

Moves metasprite to the absolute position x and y, flipped by Y (vertically)

#### **Parameters**

metasprite	Pointer to the first struct of the metasprite (for the desired frame)
base_tile	Number of the first tile where the metasprite's tiles start
base_prop	Base sprite property flags (unused on this platform)
base_sprite	Number of the first hardware sprite to be used by the metasprite
X	Absolute x coordinate of the sprite
У	Absolute y coordinate of the sprite

Same as move\_metasprite(), but with the metasprite flipped by Y (vertically). Sets:

- \_\_current\_metasprite = metasprite;
- current base tile = base tile;

Note: Overwrites OAM sprite properties (such as palette), see Metasprites and sprite properties.

Returns

Number of hardware sprites used to draw this metasprite

See also

move\_metasprite()

Moves metasprite to the absolute position x and y, flipped by X and Y (horizontally and vertically)

#### **Parameters**

metasprite	Pointer to the first struct of the metasprite (for the desired frame)
base_tile	Number of the first tile where the metasprite's tiles start
base_prop	Base sprite property flags (unused on this platform)
base_sprite	Number of the first hardware sprite to be used by the metasprite
X	Absolute x coordinate of the sprite
У	Absolute y coordinate of the sprite

Same as move\_metasprite(), but with the metasprite flipped by X and Y (horizontally and vertically). Sets:

- \_\_current\_metasprite = metasprite;
- \_\_current\_base\_tile = base\_tile;

Note: Overwrites OAM sprite properties (such as palette), see Metasprites and sprite properties.

Returns

Number of hardware sprites used to draw this metasprite

See also

move\_metasprite()

Hides a metasprite from the screen

## **Parameters**

metasprite	Pointer to first struct of the desired metasprite frame
base_sprite	Number of hardware sprite to start with

#### Sets:

\_\_current\_metasprite = metasprite;

#### 20.55.7 Variable Documentation

```
20.55.7.1 __current_metasprite const void* __current_metasprite [extern]
20.55.7.2 __current_base_tile uint8_t __current_base_tile [extern]
20.55.7.3 __render_shadow_OAM uint8_t __render_shadow_OAM [extern]
20.55.7.4 iyl void iyl
```

# 20.56 gbdk-lib/include/gb/sgb.h File Reference

```
#include <types.h>
#include <stdint.h>
```

#### Macros

- #define SGB PAL 01 0x00U
- #define SGB\_PAL\_23 0x01U
- #define SGB\_PAL\_03 0x02U
- #define SGB\_PAL\_12 0x03U
- #define SGB\_ATTR\_BLK 0x04U
- #define SGB\_ATTR\_LIN 0x05U
- #define SGB\_ATTR\_DIV 0x06U
- #define SGB\_ATTR\_CHR 0x07U
- #define SGB\_SOUND 0x08U
- #define SGB\_SOU\_TRN 0x09U
- #define SGB\_PAL\_SET 0x0AU
- #define SGB\_PAL\_TRN 0x0BU
- #define SGB\_ATRC\_EN 0x0CU
- #define SGB\_TEST\_EN 0x0DU
- #define SGB\_ICON\_EN 0x0EU
- #define SGB\_DATA\_SND 0x0FU#define SGB\_DATA\_TRN 0x10U
- #define SGB MLT REQ 0x11U
- #define SGB\_JUMP 0x12U
- #define SGB\_CHR\_TRN 0x13U
- #define SGB\_PCT\_TRN 0x14U
- #define SGB\_ATTR\_TRN 0x15U
- #define SGB ATTR SET 0x16U
- #define SGB MASK EN 0x17U
- #define SGB\_OBJ\_TRN 0x18U

## **Functions**

- uint8\_t sgb\_check (void) OLDCALL PRESERVES\_REGS(b
- void sgb\_transfer (uint8\_t \*packet) OLDCALL PRESERVES\_REGS(b

#### **Variables**

• uint8 t c

## 20.56.1 Detailed Description

Super Gameboy definitions.

See the example SGB project for additional details.

#### 20.56.2 Macro Definition Documentation

**20.56.2.1 SGB\_PAL\_01** #define SGB\_PAL\_01 0x00U

SGB Command: Set SGB Palettes 0 & 1

**20.56.2.2 SGB\_PAL\_23** #define SGB\_PAL\_23 0x01U

SGB Command: Set SGB Palettes 2 & 3

20.56.2.3 SGB\_PAL\_03 #define SGB\_PAL\_03 0x02U

SGB Command: Set SGB Palettes 0 & 3

20.56.2.4 SGB PAL 12 #define SGB PAL 12 0x03U

SGB Command: Set SGB Palettes 1 & 2

20.56.2.5 SGB\_ATTR\_BLK #define SGB\_ATTR\_BLK 0x04U

SGB Command: Set color attributes for rectangular regions

20.56.2.6 SGB\_ATTR\_LIN #define SGB\_ATTR\_LIN 0x05U

SGB Command: Set color attributes for horizontal or vertical character lines

20.56.2.7 SGB\_ATTR\_DIV #define SGB\_ATTR\_DIV 0x06U

SGB Command: Split screen in half and assign separate color attribes to each side and the divider

20.56.2.8 SGB\_ATTR\_CHR #define SGB\_ATTR\_CHR 0x07U

SGB Command: Set color attributes for separate charactersSet SGB Palette 0,1 Data

20.56.2.9 SGB\_SOUND #define SGB\_SOUND 0x08U

SGB Command: Start and stop a internal sound effect, and sounds using internal tone data

20.56.2.10 SGB\_SOU\_TRN #define SGB\_SOU\_TRN 0x09U

SGB Command: Transfer sound code or data to the SNES APU RAM

20.56.2.11 SGB PAL SET #define SGB\_PAL\_SET 0x0AU

SGB Command: Apply (previously transferred) SGB system color palettes to actual SNES palettes

20.56.2.12 SGB\_PAL\_TRN #define SGB\_PAL\_TRN 0x0BU

SGB Command: Transfer palette data into SGB system color palettes

20.56.2.13 SGB ATRC EN #define SGB\_ATRC\_EN 0x0CU

SGB Command: Enable/disable Attraction mode. It is enabled by default

20.56.2.14 SGB\_TEST\_EN #define SGB\_TEST\_EN 0x0DU

SGB Command: Enable/disable test mode for "SGB-CPU variable clock speed function"

20.56.2.15 SGB\_ICON\_EN #define SGB\_ICON\_EN 0x0EU

SGB Command: Enable/disable ICON functionality

20.56.2.16 SGB\_DATA\_SND #define SGB\_DATA\_SND 0x0FU

SGB Command: Write one or more bytes into SNES Work RAM

20.56.2.17 SGB\_DATA\_TRN #define SGB\_DATA\_TRN 0x10U

SGB Command: Transfer code or data into SNES RAM

20.56.2.18 SGB\_MLT\_REQ #define SGB\_MLT\_REQ 0x11U

SGB Command: Request multiplayer mode (input from more than one joypad)

20.56.2.19 SGB\_JUMP #define SGB\_JUMP 0x12U

SGB Command: Set the SNES program counter and NMI (vblank interrupt) handler to specific addresses

20.56.2.20 SGB\_CHR\_TRN #define SGB\_CHR\_TRN 0x13U

SGB Command: Transfer tile data (characters) to SNES Tile memory

20.56.2.21 SGB\_PCT\_TRN #define SGB\_PCT\_TRN 0x14U

SGB Command: Transfer tile map and palette data to SNES BG Map memory

20.56.2.22 SGB\_ATTR\_TRN #define SGB\_ATTR\_TRN 0x15U

SGB Command: Transfer data to (color) Attribute Files (ATFs) in SNES RAM

20.56.2.23 SGB\_ATTR\_SET #define SGB\_ATTR\_SET 0x16U

SGB Command: Transfer attributes from (color) Attribute Files (ATF) to the Game Boy window

20.56.2.24 SGB\_MASK\_EN #define SGB\_MASK\_EN 0x17U

SGB Command: Modify Game Boy window mask settings

20.56.2.25 SGB\_OBJ\_TRN #define SGB\_OBJ\_TRN 0x18U

SGB Command: Transfer OBJ attributes to SNES OAM memory

20.56.3 Function Documentation

**20.56.3.1 sgb\_check() uint**8\_t **sgb\_check** ( **void** )

Returns a non-zero value if running on a Super GameBoy

Since sgb\_check() uses sgb\_transfer(), the same delay at startup requirement applies to ensure correct operation on PAL SNES. See sgb\_transfer() for details.

 ${\bf 20.56.3.2 \quad sgb\_transfer() \quad {\tt void \; sgb\_transfer \; (} \\$ 

uint8\_t \* packet )
Transfer a SGB packet

**Parameters** 

packet Pointer to buffer with SGB packet data.

The first byte of **packet** should be a SGB command, then up to 15 bytes of command parameter data.

See the sqb\_border GBDK example project for a demo of how to use these the sqb functions.

When using the SGB with a PAL SNES, a delay should be added just after program startup such as:

// Wait 4 frames

 $\ensuremath{//}$  For PAL SNES this delay is required on startup

```
for (uint8_t i = 4; i != 0; i--) wait_vbl_done();
See also
    sgb_check()
```

## 20.56.4 Variable Documentation

```
20.56.4.1 c void c
```

# 20.57 gbdk-lib/include/gbdk/console.h File Reference

```
#include <types.h>
#include <stdint.h>
```

## **Functions**

- void gotoxy (uint8\_t x, uint8\_t y) OLDCALL
- uint8\_t posx (void) OLDCALL
- uint8\_t posy (void) OLDCALL
- void setchar (char c) OLDCALL
- void cls (void)

## 20.57.1 Detailed Description

Console functions that work like Turbo C's. The font is 8x8, making the screen 20x18 characters.

# 20.57.2 Function Documentation

```
20.57.2.1 gotoxy() void gotoxy ( uint8_t x, uint8_t y)
```

Move the cursor to an absolute position at **x**, **y**. **x** and **y** have units of tiles (8 pixels per unit)

See also

setchar()

```
20.57.2.2 posx() uint8_t posx ( void )
```

Returns the current X position of the cursor.

See also

gotoxy()

# **20.57.2.5** cls() void cls ( void )

Clears the screen

# 20.58 gbdk-lib/include/gbdk/far\_ptr.h File Reference

```
#include <types.h>
#include <stdint.h>
```

# **Data Structures**

• union \_\_far\_ptr

## **Macros**

- #define TO\_FAR\_PTR(ofs, seg) (((FAR\_PTR)seg << 16) | (FAR\_PTR)ofs)
- #define FAR\_SEG(ptr) (((union \_\_far\_ptr \*)&ptr)->segofs.seg)
- #define FAR\_OFS(ptr) (((union \_\_far\_ptr \*)&ptr)->segofs.ofs)
- #define FAR\_FUNC(ptr, typ) ((typ)(((union \_\_far\_ptr \*)&ptr)->segfn.fn))
- #define FAR\_CALL(ptr, typ, ...) (\_\_call\_banked\_ptr=ptr,((typ)(&\_\_call\_banked))(\_\_VA\_ARGS\_\_))

## **Typedefs**

typedef uint32\_t FAR\_PTR

# **Functions**

- void call banked (void)
- uint32\_t to\_far\_ptr (void \*ofs, uint16\_t seg)

## Variables

- volatile FAR\_PTR \_\_call\_banked\_ptr
- volatile void \* \_\_call\_banked\_addr
- volatile uint8\_t \_\_call\_banked\_bank

## 20.58.1 Detailed Description

Far pointers include a segment (bank) selector so they are able to point to addresses (functions or data) outside of the current bank (unlike normal pointers which are not bank-aware).

See the banks\_farptr example project included with gbdk.

Todo Add link to a discussion about banking (such as, how to assign code and variables to banks)

## 20.58.2 Macro Definition Documentation

Macro to obtain a far pointer at compile-time

#### **Parameters**

ofs	Memory address within the given Segment (Bank)
seg	Segment (Bank) number

#### Returns

A far pointer (type FAR\_PTR)

Macro to get the Segment (Bank) number of a far pointer

## **Parameters**

```
ptr A far pointer (type FAR_PTR)
```

## Returns

Segment (Bank) of the far pointer (type uint16\_t)

Macro to get the Offset (address) of a far pointer

## **Parameters**

```
ptr A far pointer (type FAR_PTR)
```

## Returns

Offset (address) of the far pointer (type void \*)

```
20.58.2.4 FAR_FUNC #define FAR_FUNC(

ptr,
```

```
typ ) ((typ)(((union __far_ptr *)&ptr)->segfn.fn))
```

Macro to call a function at far pointer ptr of type typ

#### **Parameters**

ptr	Far pointer of a function to call (type FAR_PTR)
typ	Type to cast the function far pointer to.
	VA Args list of parameters for the function

## **type** should match the definition of the function being called. For example:

```
// A function in bank 2
#pragma bank 2
uint16_t some_function(uint16_t param1, uint16_t param2) __banked { return 1; };
...
// Code elsewhere, such as unbanked main()
// This type declaration should match the above function
typedef uint16_t (*some_function_t)(uint16_t, uint16_t) __banked;
// Using FAR_CALL() with the above as *ptr*, *typ*, and two parameters.
result = FAR_CALL(some_function, some_function_t, 100, 50);
```

#### Returns

Value returned by the function (if present)

## 20.58.3 Typedef Documentation

```
20.58.3.1 FAR_PTR typedef uint32_t FAR_PTR Type for storing a FAR_PTR
```

## 20.58.4 Function Documentation

```
20.58.4.1 __call__banked() void __call__banked ( void )
```

Obtain a far pointer at runtime

## **Parameters**

ofs	Memory address within the given Segment (Bank)
seg	Segment (Bank) number

#### Returns

A far pointer (type FAR\_PTR)

## 20.58.5 Variable Documentation

```
20.58.5.1 __call_banked_ptr volatile FAR_PTR __call_banked_ptr [extern]
20.58.5.2 __call_banked_addr volatile void* __call_banked_addr [extern]
20.58.5.3 __call_banked_bank volatile uint8_t __call_banked_bank [extern]
```

# 20.59 gbdk-lib/include/gbdk/font.h File Reference

```
#include <types.h>
#include <stdint.h>
```

#### **Data Structures**

· struct sfont handle

## **Macros**

- #define FONT\_256ENCODING 0
- #define FONT\_128ENCODING 1
- #define FONT NOENCODING 2
- #define FONT\_COMPRESSED 4

## **Typedefs**

- typedef uint16\_t font\_t
- typedef struct sfont\_handle mfont\_handle
- typedef struct sfont\_handle \* pmfont\_handle

## **Functions**

- void font\_init (void)
- font\_t font\_load (void \*font) OLDCALL
- font\_t font\_set (font\_t font\_handle) OLDCALL
- void font\_color (uint8\_t forecolor, uint8\_t backcolor) OLDCALL

# Variables

- uint8\_t font\_spect []
- uint8\_t font\_italic []
- uint8\_t font\_ibm []
- uint8\_t font\_min []
- uint8\_t font\_ibm\_fixed []

## 20.59.1 Detailed Description

Multiple font support for the GameBoy Michael Hope, 1999 michaelh@earthling.net

Set the current font.

#### 20.59.2 Macro Definition Documentation

```
20.59.2.1 FONT_256ENCODING #define FONT_256ENCODING 0
Various flags in the font header.
20.59.2.2 FONT_128ENCODING #define FONT_128ENCODING 1
20.59.2.3 FONT_NOENCODING #define FONT_NOENCODING 2
20.59.2.4 FONT_COMPRESSED #define FONT_COMPRESSED 4
20.59.3 Typedef Documentation
20.59.3.1 font_t typedef uint16_t font_t
font_t is a handle to a font loaded by font_load(). It can be used with font_set()
20.59.3.2 mfont_handle typedef struct sfont_handle mfont_handle
Internal representation of a font. What a font_t really is
\textbf{20.59.3.3} \quad \textbf{pmfont\_handle} \quad \texttt{typedef struct sfont\_handle* pmfont\_handle}
20.59.4 Function Documentation
20.59.4.1 font_init() void font_init (
               void )
Initializes the font system. Should be called before other font functions.
 20.59.4.2 \quad font\_load() \quad \texttt{font\_t font\_load} \ (
               void * font )
Load a font and set it as the current font.
Parameters
        Pointer to a font to load (usually a gbdk font)
Returns
     Handle to the loaded font, which can be used with font_set()
See also
     font init(), font set(), List of gbdk fonts
20.59.4.3 font_set() font_t font_set (
               font_t font_handle )
```

#### **Parameters**

font_handle	handle of a font returned by font_load()
-------------	------------------------------------------

#### Returns

The previously used font handle.

#### See also

```
font_init(), font_load()
```

Set the current foreground colour (for pixels), background colour

## 20.60 gbdk-lib/include/gbdk/gbdk-lib.h File Reference

```
#include <asm/sm83/provides.h>
```

## 20.60.1 Detailed Description

Settings for the greater library system.

# 20.61 gbdk-lib/include/gbdk/incbin.h File Reference

```
#include <stdint.h>
```

## Macros

- #define INCBIN\_EXTERN(VARNAME)
- #define INCBIN\_SIZE(VARNAME) ( (uint16\_t) & \_\_size\_ ## VARNAME )
- #define BANK(VARNAME) ( (uint8 t) & bank ## VARNAME )
- #define INCBIN(VARNAME, FILEPATH)

# 20.61.1 Detailed Description

Allows binary data from other files to be included into a C source file.

It is implemented using asm .incbin and macros.

See the incbin example project for a demo of how to use it.

## 20.61.2 Macro Definition Documentation

# 

Creates extern entries for accessing a INCBIN() generated variable and it's size in another source file.

#### **Parameters**

<i>VARNAME</i>	Name of the variable used with INCBIN	
----------------	---------------------------------------	--

An entry is created for the variable and it's size variable. INCBIN(), INCBIN\_SIZE()

```
20.61.2.2 INCBIN_SIZE #define INCBIN_SIZE(

VARNAME) ((uint16_t) & __size_ ## VARNAME)
```

Obtains the size in bytes of the INCBIN() generated data

#### **Parameters**

VARNAME	Name of the variable used with INCBIN
---------	---------------------------------------

Requires INCBIN\_EXTERN() to have been called earlier in the source file INCBIN(), INCBIN\_EXTERN()

```
20.61.2.3 BANK #define BANK(

**VARNAME ) ( (uint8_t) & __bank_ ## VARNAME )
```

Obtains the **bank number** of the INCBIN() generated data

#### **Parameters**

VARNAME   Name of the variable used with INCBIN
-------------------------------------------------

Requires INCBIN\_EXTERN() to have been called earlier in the source file INCBIN(), INCBIN\_EXTERN()

```
20.61.2.4 INCBIN #define INCBIN(

VARNAME,

FILEPATH)

Value:

void __func_ ## VARNAME(void) __banked __naked { \
_asm \
_ ## VARNAME:: \
1$: \
.incbin FILEPATH \
2$: \
__size_ ## VARNAME = (2$-1$) \
.globl __size_ ## VARNAME \
.local b__func_ ## VARNAME \
__bank_ ## VARNAME = b__func_ ## VARNAME \
.globl __bank_ ## VARNAME \
.endasm; \
}
```

Includes binary data into a C source file

## **Parameters**

VARNAME	Variable name to use
FILEPATH	Path to the file which will be binary included into the C source file

**filepath** is relative to the working directory of the tool that is calling it (often a makefile's working directory), **NOT** to the file it's being included into.

The variable name is not modified and can be used as-is.

The INCBIN() macro will declare the BANK() and INCBIN\_SIZE() helper symbols. Then if INCBIN\_EXTERN() is used in the header then those helper macros can be used in the application code.

- INCBIN\_SIZE() for obtaining the size of the included data.
- BANK() for obtaining the bank number of the included data.

Use INCBIN\_EXTERN() within another source file to make the variable and it's data accessible there.

# 20.62 gbdk-lib/include/gbdk/platform.h File Reference

```
#include <gb/gb.h>
#include <gb/cgb.h>
#include <gb/sgb.h>
```

# 20.63 gbdk-lib/include/gbdk/rledecompress.h File Reference

```
#include <types.h>
#include <stdint.h>
```

## **Macros**

• #define RLE\_STOP 0

#### **Functions**

- uint8\_t rle\_init (void \*data)
- uint8\_t rle\_decompress (void \*dest, uint8\_t len)

## 20.63.1 Detailed Description

Decompressor for RLE encoded data

Decompresses data which has been compressed with gbcompress using the --alg=rle argument.

## 20.63.2 Macro Definition Documentation

```
20.63.2.1 RLE_STOP #define RLE_STOP 0
```

#### 20.63.3 Function Documentation

Initialize the RLE decompressor with RLE data at address data

# **Parameters**

```
data Pointer to start of RLE compressed data
```

#### See also

rle\_decompress

Decompress RLE compressed data into dest for length len bytes

#### **Parameters**

dest	Pointer to destination buffer/address
len	Number of bytes to decompress

## Returns

Returns 0 if compression is complete, 1 if there is more data to decompress

Before calling this function rle\_init must be called one time to initialize the RLE decompressor. Decompresses data which has been compressed with gbcompress using the --alg=rle argument.

See also

rle init

# 20.64 gbdk-lib/include/gbdk/version.h File Reference

#### **Macros**

• #define GBDK VERSION 430

## 20.64.1 Macro Definition Documentation

20.64.1.1 \_\_GBDK\_VERSION #define \_\_GBDK\_VERSION 430

# 20.65 gbdk-lib/include/limits.h File Reference

## **Macros**

- #define CHAR BIT 8 /\* bits in a char \*/
- #define SCHAR\_MAX 127
- #define SCHAR MIN -128
- #define UCHAR\_MAX 0xff
- #define CHAR\_MAX SCHAR\_MAX
- #define CHAR MIN SCHAR MIN
- #define INT\_MIN (-32767 1)
- #define INT\_MAX 32767
- #define SHRT MAX INT MAX
- #define SHRT\_MIN INT\_MIN
- #define UINT MAX 0xffff
- #define UINT\_MIN 0
- #define USHRT\_MAX UINT\_MAX
- #define USHRT\_MIN UINT\_MIN
- #define LONG\_MIN (-2147483647L-1)
- #define LONG\_MAX 2147483647L
- #define ULONG\_MAX 0xffffffff
- #define ULONG\_MIN 0

# 20.65.1 Macro Definition Documentation

**20.65.1.1 CHAR\_BIT** #define CHAR\_BIT 8 /\* bits in a char \*/

- 20.65.1.2 SCHAR\_MAX #define SCHAR\_MAX 127
- 20.65.1.3 SCHAR\_MIN #define SCHAR\_MIN -128
- 20.65.1.4 UCHAR\_MAX #define UCHAR\_MAX 0xff
- 20.65.1.5 CHAR\_MAX #define CHAR\_MAX SCHAR\_MAX
- 20.65.1.6 CHAR\_MIN #define CHAR\_MIN SCHAR\_MIN
- **20.65.1.7 INT\_MIN** #define INT\_MIN (-32767 1)
- **20.65.1.8 INT\_MAX** #define INT\_MAX 32767
- 20.65.1.9 SHRT\_MAX #define SHRT\_MAX INT\_MAX
- 20.65.1.10 SHRT\_MIN #define SHRT\_MIN INT\_MIN
- 20.65.1.11 UINT\_MAX #define UINT\_MAX 0xfffff
- 20.65.1.12 UINT\_MIN #define UINT\_MIN 0
- 20.65.1.13 USHRT\_MAX #define USHRT\_MAX UINT\_MAX
- $\textbf{20.65.1.14} \quad \textbf{USHRT\_MIN} \quad \texttt{\#define USHRT\_MIN UINT\_MIN}$
- $\textbf{20.65.1.15} \quad \textbf{LONG\_MIN} \quad \texttt{\#define LONG\_MIN} \quad (-2147483647L-1)$
- **20.65.1.16 LONG\_MAX** #define LONG\_MAX 2147483647L
- 20.65.1.17 ULONG\_MAX #define ULONG\_MAX Oxffffffff
- 20.65.1.18 ULONG\_MIN #define ULONG\_MIN 0

# 20.66 gbdk-lib/include/msx/msx.h File Reference

```
#include <types.h>
#include <stdint.h>
#include <gbdk/version.h>
#include <msx/hardware.h>
```

#### **Data Structures**

- · struct joypads t
- struct OAM\_item\_t

#### **Macros**

- #define MSX
- #define SYSTEM 60HZ 0x00
- #define SYSTEM\_50HZ 0x01
- · #define VBK REG VDP ATTR SHIFT
- #define J UP 0b00100000
- #define J DOWN 0b01000000
- #define J\_LEFT 0b00010000
- #define J\_RIGHT 0b10000000
- #define J A 0b00000001
- #define J\_B 0b00000100
- #define J SELECT 0b00001000
- #define J START 0b00000010
- #define M\_TEXT\_OUT 0x02U
- #define M\_TEXT\_INOUT 0x03U
- #define M\_NO\_SCROLL 0x04U
- #define M NO INTERP 0x08U
- #define S BANK 0x01U
- #define S\_FLIPX 0x02U
- #define S\_FLIPY 0x04U
- #define S\_PALETTE 0x08U
- #define S\_PRIORITY 0x10U
- #define S\_PAL(n) (((n) & 0x01U) << 3)</li>
- #define \_\_WRITE\_VDP\_REG\_UNSAFE(REG, v) shadow\_##REG=(v), VDP\_CMD=(shadow\_##REG), VDP ←
   \_\_CMD=REG
- #define \_\_WRITE\_VDP\_REG(REG, v) shadow\_##REG=(v);\_asm\_\_("di");VDP\_CMD=(shadow\_
  ##REG);VDP\_CMD=REG;\_asm\_\_("ei")
- #define \_\_READ\_VDP\_REG(REG) shadow\_##REG
- #define EMPTY\_IFLAG 0x00U
- #define VBL\_IFLAG 0x01U
- #define LCD IFLAG 0x02U
- #define TIM\_IFLAG 0x04U
- #define SIO\_IFLAG 0x08U
- #define JOY IFLAG 0x10U
- #define SCREENWIDTH DEVICE SCREEN PX WIDTH
- #define SCREENHEIGHT DEVICE\_SCREEN\_PX\_HEIGHT
- #define MINWNDPOSX 0x00U
- #define MINWNDPOSY 0x00U
- #define MAXWNDPOSX 0x00U
- #define MAXWNDPOSY 0x00U
- #define DISPLAY\_ON \_\_WRITE\_VDP\_REG(VDP\_R1, \_\_READ\_VDP\_REG(VDP\_R1) |= R1\_DISP\_ON)
- #define DISPLAY\_OFF display\_off();

- #define HIDE\_LEFT\_COLUMN \_\_WRITE\_VDP\_REG(VDP\_R0, \_\_READ\_VDP\_REG(VDP\_R0) |= R0\_LCB)
- #define SHOW\_LEFT\_COLUMN \_\_WRITE\_VDP\_REG(VDP\_R0, \_\_READ\_VDP\_REG(VDP\_R0) &= (~R0\_LCB))
- #define SET\_BORDER\_COLOR(C) \_\_WRITE\_VDP\_REG(VDP\_R7, ((C) | 0xf0u))
- #define SHOW BKG
- #define HIDE BKG
- #define SHOW WIN
- #define HIDE WIN
- #define SHOW\_SPRITES
- #define HIDE SPRITES
- #define SPRITES\_16x16 \_\_WRITE\_VDP\_REG(VDP\_R1, \_\_READ\_VDP\_REG(VDP\_R1) |= R1\_SPR\_16X16)
- #define SPRITES\_8x8 \_\_WRITE\_VDP\_REG(VDP\_R1, \_\_READ\_VDP\_REG(VDP\_R1) &= (~R1\_SPR\_16X16))
- #define DEVICE\_SUPPORTS\_COLOR (TRUE)
- #define DIV\_REG get\_r\_reg()
- #define CURRENT BANK current bank
- #define BANK(VARNAME) ( (uint8\_t) & \_\_bank\_ ## VARNAME )
- #define BANKREF(VARNAME)
- #define BANKREF\_EXTERN(VARNAME) extern const void \_\_bank\_ ## VARNAME;
- #define SWITCH\_ROM1 SWITCH\_ROM
- #define SWITCH ROM2(b) MAP FRAME2=(b)
- #define SWITCH\_RAM(b) RAM\_CONTROL=((b)&1)?RAM\_CONTROL|RAMCTL\_BANK:RAM\_CONTROL&(~RAMCTL\_BANI
- #define ENABLE RAM RAM CONTROL = RAMCTL RAM
- #define DISABLE\_RAM RAM\_CONTROL&=(~RAMCTL\_RAM)
- #define set\_bkg\_palette\_entry set\_palette\_entry
- #define set\_sprite\_palette\_entry(palette, entry, rgb\_data) set\_palette\_entry(1,entry,rgb\_data)
- #define set\_bkg\_palette set\_palette
- #define set\_sprite\_palette(first\_palette, nb\_palettes, rgb\_data) set\_palette(1,1,rgb\_data)
- #define COMPAT\_PALETTE(C0, C1, C2, C3) (((uint16\_t)(C3) << 12) | ((uint16\_t)(C2) << 8) | ((uint16\_t)(C1) << 4) | (uint16\_t)(C0))
- #define set\_bkg\_tiles set\_tile\_map
- #define set\_win\_tiles set\_tile\_map
- #define fill bkg rect fill rect
- · #define fill win rect fill rect
- #define DISABLE\_VBL\_TRANSFER \_shadow\_OAM\_base = 0
- #define ENABLE\_VBL\_TRANSFER \_shadow\_OAM\_base = (uint8\_t)((uint16\_t)&shadow\_OAM >> 8)
- #define MAX\_HARDWARE\_SPRITES 32
- #define HARDWARE\_SPRITE\_CAN\_FLIP\_X 0
- #define HARDWARE\_SPRITE\_CAN\_FLIP\_Y 0
- #define set\_bkg\_tile\_xy set\_tile\_xy
- #define set win tile xy set tile xy
- #define get\_win\_xy\_addr get\_bkg\_xy\_addr

## **Typedefs**

- typedef void(\* int\_handler) (void) NONBANKED
- typedef struct OAM\_item\_t OAM\_item\_t

## **Functions**

- void WRITE\_VDP\_CMD (uint16\_t cmd) Z88DK\_FASTCALL PRESERVES\_REGS(b
- void WRITE\_VDP\_DATA (uint16\_t data) Z88DK\_FASTCALL PRESERVES\_REGS(b
- void mode (uint8\_t m) OLDCALL
- uint8\_t get\_mode (void) OLDCALL
- uint8 t get system (void)
- void set\_interrupts (uint8\_t flags) Z88DK\_FASTCALL

- · void remove VBL (int handler h) Z88DK FASTCALL PRESERVES REGS(iyh
- void remove\_LCD (int\_handler h) Z88DK\_FASTCALL PRESERVES\_REGS(b
- · void remove TIM (int handler h) Z88DK FASTCALL
- void remove\_SIO (int\_handler h) Z88DK\_FASTCALL
- void remove JOY (int handler h) Z88DK FASTCALL
- void add\_VBL (int\_handler h) Z88DK\_FASTCALL PRESERVES\_REGS(d
- · void add LCD (int handler h) Z88DK FASTCALL PRESERVES REGS(b
- · void add TIM (int handler h) Z88DK FASTCALL
- · void add SIO (int handler h) Z88DK FASTCALL
- · void add JOY (int handler h) Z88DK FASTCALL
- uint8 t cancel pending interrupts (void)
- void move\_bkg (uint8\_t x, uint8\_t y)
- void scroll\_bkg (int8\_t x, int8\_t y)
- · void vsync (void) PRESERVES REGS(b
- · void wait vbl done (void) PRESERVES REGS(b
- void display off (void)
- void refresh\_OAM (void)
- uint8 t get r reg (void) PRESERVES REGS(b
- void SWITCH\_ROM (uint8\_t bank) Z88DK\_FASTCALL PRESERVES\_REGS(b
- void delay (uint16\_t d) Z88DK\_FASTCALL
- uint8\_t joypad (void) OLDCALL PRESERVES\_REGS(b
- uint8 t waitpad (uint8 t mask) Z88DK FASTCALL PRESERVES REGS(b
- void waitpadup (void) PRESERVES\_REGS(b
- uint8\_t joypad\_init (uint8\_t npads, joypads\_t \*joypads) Z88DK\_CALLEE
- void joypad\_ex (joypads\_t \*joypads) Z88DK\_FASTCALL PRESERVES\_REGS(iyh
- · void enable interrupts (void) PRESERVES REGS(a
- · void disable\_interrupts (void) PRESERVES\_REGS(a
- · void set default palette (void)
- void cpu\_fast (void)
- void set\_palette\_entry (uint8\_t palette, uint8\_t entry, uint16\_t rgb\_data) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- void set\_palette (uint8\_t first\_palette, uint8\_t nb\_palettes, const palette\_color\_t \*rgb\_data) Z88DK\_CALLEE
- void set\_native\_tile\_data (uint16\_t start, uint16\_t ntiles, const void \*src) Z88DK\_CALLEE
- void set\_bkg\_4bpp\_data (uint16\_t start, uint16\_t ntiles, const void \*src)
- void set\_sprite\_1bpp\_data (uint16\_t start, uint16\_t ntiles, const void \*src) Z88DK\_CALLEE
- void set\_native\_sprite\_data (uint16\_t start, uint16\_t ntiles, const void \*src)
- void set\_2bpp\_palette (uint16\_t palette)
- void set bkg data (uint16 t start, uint16 t ntiles, const void \*src)
- void set\_sprite\_data (uint16\_t start, uint16\_t ntiles, const void \*src)
- void set 1bpp colors (uint8 t fgcolor, uint8 t bgcolor)
- void set\_tile\_1bpp\_data (uint16\_t start, uint16\_t ntiles, const void \*src, uint16\_t colors) Z88DK\_CALLEE PRESERVES REGS(iyh
- void set\_bkg\_1bpp\_data (uint16\_t start, uint16\_t ntiles, const void \*src)
- void set\_data (uint16\_t dst, const void \*src, uint16\_t size) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- void vmemcpy (uint16\_t dst, const void \*src, uint16\_t size) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- void set\_tile\_map (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*tiles) Z88DK\_CALLEE PRESERVES REGS(iyh
- void set\_bkg\_based\_tiles (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*tiles, uint8\_t base\_tile)
- void set win based tiles (uint8 t x, uint8 t y, uint8 t w, uint8 t h, const uint8 t \*tiles, uint8 t base tile)
- void set\_tile\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, uint8\_t map\_w, const uint8\_t \*map) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- void set\_tile\_submap\_compat (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, uint8\_t map\_w, const uint8\_t \*map) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- void set\_bkg\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w)
- void set\_win\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w)

- void set\_bkg\_based\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w, uint8 t base tile)
- void set\_win\_based\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w, uint8\_t base\_tile)
- void fill\_rect (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint16\_t tile) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- void SET\_SHADOW\_OAM\_ADDRESS (void \*address)
- void set\_sprite\_tile (uint8\_t nb, uint8\_t tile)
- uint8\_t get\_sprite\_tile (uint8\_t nb)
- void set\_sprite\_prop (uint8\_t nb, uint8\_t prop)
- uint8 t get sprite prop (uint8 t nb)
- void move\_sprite (uint8\_t nb, uint8\_t x, uint8\_t y)
- void scroll\_sprite (uint8\_t nb, int8\_t x, int8\_t y)
- void hide\_sprite (uint8\_t nb)
- void set\_vram\_byte (uint8\_t \*addr, uint8\_t v) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- uint8\_t \* set\_attributed\_tile\_xy (uint8\_t x, uint8\_t y, uint16\_t t) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- uint8 t \* set tile xy (uint8 t x, uint8 t y, uint8 t t) Z88DK CALLEE PRESERVES REGS(iyh
- uint8 t \* get bkg xy addr (uint8 t x, uint8 t y) Z88DK CALLEE PRESERVES REGS(iyh

#### **Variables**

- const uint8\_t \_SYSTEM
- void c
- void d
- void e
- · void iyh
- void iyl
- void h
- void
- volatile uint16 t sys time
- · volatile uint8 t current bank
- void b
- uint16\_t \_current\_2bpp\_palette
- uint16\_t \_current\_1bpp\_colors
- uint8\_t \_map\_tile\_offset
- · uint8 t submap tile offset
- volatile struct OAM\_item\_t shadow\_OAM []
- volatile uint8 t shadow OAM base
- volatile uint8\_t \_shadow\_OAM\_OFF

## 20.66.1 Detailed Description

MSX specific functions.

## 20.66.2 Macro Definition Documentation

**20.66.2.1 MSX** #define MSX

20.66.2.2 SYSTEM\_60HZ #define SYSTEM\_60HZ 0x00

20.66.2.3 SYSTEM\_50HZ #define SYSTEM\_50HZ 0x01

```
20.66.2.4 VBK_REG #define VBK_REG VDP_ATTR_SHIFT
20.66.2.5 J_UP #define J_UP 0b00100000
Joypad bits. A logical OR of these is used in the wait_pad and joypad functions. For example, to see if the B button
is pressed try
uint8_t keys; keys = joypad(); if (keys & J_B) { ... }
See also
     joypad
20.66.2.6 J_DOWN #define J_DOWN 0b01000000
20.66.2.7 J_LEFT #define J_LEFT 0b00010000
20.66.2.8 J_RIGHT #define J_RIGHT 0b10000000
20.66.2.9 J_A #define J_A 0b00000001
20.66.2.10 J_B #define J_B 0b00000100
20.66.2.11 J_SELECT #define J_SELECT 0b00001000
20.66.2.12 J_START #define J_START 0b00000010
20.66.2.13 M_TEXT_OUT #define M_TEXT_OUT 0x02U
Screen modes. Normally used by internal functions only.
See also
      mode()
\textbf{20.66.2.14} \quad \textbf{M\_TEXT\_INOUT} \quad \texttt{\#define M\_TEXT\_INOUT 0x03U}
\textbf{20.66.2.15} \quad \textbf{M\_NO\_SCROLL} \quad \texttt{\#define} \quad \texttt{M\_NO\_SCROLL} \quad \texttt{0x04U}
Set this in addition to the others to disable scrolling
If scrolling is disabled, the cursor returns to (0,0)
See also
     mode()
```

```
20.66.2.16 M_NO_INTERP #define M_NO_INTERP 0x08U Set this to disable interpretation
```

See also

mode()

## **20.66.2.17 S\_BANK** #define S\_BANK 0x01U

The nineth bit of the tile id

## **20.66.2.18 S\_FLIPX** #define S\_FLIPX 0x02U

If set the background tile will be flipped horizontally.

## **20.66.2.19 S\_FLIPY** #define S\_FLIPY 0x04U

If set the background tile will be flipped vertically.

## 20.66.2.20 S\_PALETTE #define S\_PALETTE 0x08U

If set the background tile palette.

## 20.66.2.21 S\_PRIORITY #define S\_PRIORITY 0x10U

If set the background tile priority.

```
20.66.2.22 S_PAL #define S_PAL(
```

n ) (((n) & 0x01U) << 3)

Defines how palette number is encoded in OAM. Required for the png2asset tool's metasprite output.

## 20.66.2.23 \_\_WRITE\_VDP\_REG\_UNSAFE #define \_\_WRITE\_VDP\_REG\_UNSAFE(

REG,

v ) shadow\_##REG=(v), VDP\_CMD=(shadow\_##REG), VDP\_CMD=REG

# 20.66.2.24 \_\_WRITE\_VDP\_REG #define \_\_WRITE\_VDP\_REG(

REG,

v ) shadow\_##REG=(v);\_\_asm\_\_("di");VDP\_CMD=(shadow\_##REG);VDP\_CMD=REG;\_\_asm\_\_↔

("ei")

# 20.66.2.25 \_\_READ\_VDP\_REG #define \_\_READ\_VDP\_REG(

REG ) shadow\_##REG

# 20.66.2.26 EMPTY\_IFLAG #define EMPTY\_IFLAG 0x00U

Disable calling of interrupt service routines

## 20.66.2.27 VBL\_IFLAG #define VBL\_IFLAG 0x01U

VBlank Interrupt occurs at the start of the vertical blank.

During this period the video ram may be freely accessed.

See also

```
set_interrupts(),
```

add VBL

move\_win()

```
20.66.2.28 LCD_IFLAG #define LCD_IFLAG 0x02U
LCD Interrupt when triggered by the STAT register.
See also
     set_interrupts(),
     add LCD
20.66.2.29 TIM IFLAG #define TIM_IFLAG 0x04U
Does nothing on MSX
20.66.2.30 SIO_IFLAG #define SIO_IFLAG 0x08U
Does nothing on MSX
20.66.2.31 JOY_IFLAG #define JOY_IFLAG 0x10U
Does nothing on MSX
20.66.2.32 SCREENWIDTH #define SCREENWIDTH DEVICE_SCREEN_PX_WIDTH
Width of the visible screen in pixels.
20.66.2.33 SCREENHEIGHT #define SCREENHEIGHT DEVICE_SCREEN_PX_HEIGHT
Height of the visible screen in pixels.
20.66.2.34 MINWNDPOSX #define MINWNDPOSX 0x00U
The Minimum X position of the Window Layer (Left edge of screen)
See also
     move_win()
20.66.2.35 MINWNDPOSY #define MINWNDPOSY 0x00U
The Minimum Y position of the Window Layer (Top edge of screen)
See also
     move_win()
20.66.2.36 MAXWNDPOSX #define MAXWNDPOSX 0x00U
The Maximum X position of the Window Layer (Right edge of screen)
See also
     move_win()
20.66.2.37 MAXWNDPOSY #define MAXWNDPOSY 0x00U
The Maximum Y position of the Window Layer (Bottom edge of screen)
See also
```

```
20.66.2.38 DISPLAY_ON #define DISPLAY_ON __WRITE_VDP_REG(VDP_R1, __READ_VDP_REG(VDP_R1) |=
R1_DISP_ON)
Turns the display back on.
See also
     display off, DISPLAY OFF
20.66.2.39 DISPLAY_OFF #define DISPLAY_OFF display_off();
Turns the display off immediately.
See also
     display_off, DISPLAY_ON
20.66.2.40 HIDE_LEFT_COLUMN #define HIDE_LEFT_COLUMN __WRITE_VDP_REG(VDP_R0, __READ_VDP_REG(VDP_R0)
= R0_LCB)
Blanks leftmost column, so it is not garbaged when you use horizontal scroll
See also
     SHOW LEFT COLUMN
20.66.2.41 SHOW_LEFT_COLUMN #define SHOW_LEFT_COLUMN __WRITE_VDP_REG(VDP_R0, __READ_VDP_REG(VDP_R0)
\&= (\sim R0\_LCB))
Shows leftmost column
See also
     HIDE LEFT COLUMN
20.66.2.42 SET_BORDER_COLOR #define SET_BORDER_COLOR(
              C ) __WRITE_VDP_REG(VDP_R7, ((C) | 0xf0u))
Sets border color
20.66.2.43 SHOW_BKG #define SHOW_BKG
Turns on the background layer. Not yet implemented
20.66.2.44 HIDE_BKG #define HIDE_BKG
Turns off the background layer. Not yet implemented
20.66.2.45 SHOW_WIN #define SHOW_WIN
Turns on the window layer Not yet implemented
20.66.2.46 HIDE_WIN #define HIDE_WIN
Turns off the window layer. Not yet implemented
20.66.2.47 SHOW_SPRITES #define SHOW_SPRITES
Turns on the sprites layer. Not yet implemented
20.66.2.48 HIDE_SPRITES #define HIDE_SPRITES
Turns off the sprites layer. Not yet implemented
```

```
20.66.2.49 SPRITES_16x16 #define SPRITES_16x16 __WRITE_VDP_REG(VDP_R1, __READ_VDP_REG(VDP_R1) |= R1_SPR_16x16)
```

Sets sprite size to 8x16 pixels, two tiles one above the other.

```
20.66.2.50 SPRITES_8x8 #define SPRITES_8x8 __WRITE_VDP_REG(VDP_R1, __READ_VDP_REG(VDP_R1) &= (~R1_SPR_16X16))
```

Sets sprite size to 8x8 pixels, one tile.

```
{\bf 20.66.2.51} \quad {\bf DEVICE\_SUPPORTS\_COLOR} \quad {\tt \#define\ DEVICE\_SUPPORTS\_COLOR} \quad ({\tt TRUE})
```

Macro returns TRUE if device supports color (it always does on MSX)

```
20.66.2.52 DIV_REG #define DIV_REG get_r_reg()
```

20.66.2.53 CURRENT\_BANK #define CURRENT\_BANK \_current\_bank

Obtains the bank number of VARNAME

#### **Parameters**

VARNAME	Name of the variable which has abank_VARNAME companion symbol which is adjusted by
	bankpack

Use this to obtain the bank number from a bank reference created with BANKREF().

See also

BANKREF\_EXTERN(), BANKREF()

```
20.66.2.55 BANKREF #define BANKREF( VARNAME)
```

## Value:

Creates a reference for retrieving the bank number of a variable or function

### **Parameters**

VARNAME | Variable name to use, which may be an existing identifier

See also

BANK() for obtaining the bank number of the included data.

More than one BANKREF () may be created per file, but each call should always use a unique VARNAME. Use BANKREF EXTERN() within another source file to make the variable and it's data accesible there.

```
20.66.2.56 BANKREF_EXTERN #define BANKREF_EXTERN(
```

VARNAME ) extern const void \_\_bank\_ ## VARNAME;

Creates extern references for accessing a BANKREF() generated variable.

```
Parameters
```

VARNAME Name of the variable used with BANKREF()

This makes a BANKREF() reference in another source file accessible in the current file for use with BANK().

See also

BANKREF(), BANK()

20.66.2.57 SWITCH\_ROM1 #define SWITCH\_ROM1 SWITCH\_ROM

```
20.66.2.58 SWITCH_ROM2 #define SWITCH_ROM2( b ) MAP_FRAME2=(b)
```

Makes switch the active ROM bank in frame 2

**Parameters** 

b ROM bank to switch to

```
20.66.2.59 SWITCH_RAM #define SWITCH_RAM(
```

b) RAM\_CONTROL=((b)&1)?RAM\_CONTROL|RAMCTL\_BANK:RAM\_CONTROL&(~RAMCTL\_BANK)

Switches RAM bank

**Parameters** 

b SRAM bank to switch to

```
20.66.2.60 ENABLE_RAM #define ENABLE_RAM RAM_CONTROL = RAMCTL_RAM
```

**Enables RAM** 

20.66.2.61 DISABLE\_RAM #define DISABLE\_RAM RAM\_CONTROL&=(~RAMCTL\_RAM)

Disables RAM

20.66.2.62 set\_bkg\_palette\_entry #define set\_bkg\_palette\_entry set\_palette\_entry

```
20.66.2.63 set_sprite_palette_entry #define set_sprite_palette_entry(
```

```
palette,
entry,
rgb_data ) set_palette_entry(1,entry,rgb_data)
```

20.66.2.64 set\_bkg\_palette #define set\_bkg\_palette set\_palette

```
20.66.2.65 set_sprite_palette #define set_sprite_palette(
```

```
first_palette,

nb_palettes,

rgb_data ) set_palette(1,1,rgb_data)
```

Sprite Attributes structure

```
20.66.2.66 COMPAT_PALETTE #define COMPAT_PALETTE(
              CO,
              C1,
              C3 ) (((uint16_t)(C3) << 12) | ((uint16_t)(C2) << 8) | ((uint16_t)(C1) << 4) |
(uint16_t)(C0))
20.66.2.67 set_bkg_tiles #define set_bkg_tiles set_tile_map
20.66.2.68 set_win_tiles #define set_win_tiles set_tile_map
20.66.2.69 fill_bkg_rect #define fill_bkg_rect fill_rect
20.66.2.70 fill_win_rect #define fill_win_rect fill_rect
20.66.2.71 DISABLE_VBL_TRANSFER #define DISABLE_VBL_TRANSFER __shadow_OAM_base = 0
Disable shadow OAM to VRAM copy on each VBlank
20.66.2.72 ENABLE_VBL_TRANSFER #define ENABLE_VBL_TRANSFER __shadow_OAM_base = (uint8_t)((uint16_t)&shado
>> 8)
Enable shadow OAM to VRAM copy on each VBlank
20.66.2.73 MAX_HARDWARE_SPRITES #define MAX_HARDWARE_SPRITES 32
Amount of hardware sprites in OAM
20.66.2.74 HARDWARE SPRITE CAN FLIP X #define HARDWARE_SPRITE_CAN_FLIP_X 0
True if sprite hardware can flip sprites by X (horizontally)
20.66.2.75 HARDWARE SPRITE CAN FLIP Y #define HARDWARE_SPRITE_CAN_FLIP_Y 0
True if sprite hardware can flip sprites by Y (vertically)
20.66.2.76 set_bkg_tile_xy #define set_bkg_tile_xy set_tile_xy
20.66.2.77 set win tile xy #define set_win_tile_xy set_tile_xy
20.66.2.78 get_win_xy_addr #define get_win_xy_addr get_bkg_xy_addr
20.66.3 Typedef Documentation
20.66.3.1 int handler typedef void(* int_handler) (void) NONBANKED
Interrupt handlers
20.66.3.2 OAM_item_t typedef struct OAM_item_t OAM_item_t
```

#### **Parameters**

X	X Coordinate of the sprite on screen
У	Y Coordinate of the sprite on screen
tile	Sprite tile number (see set_sprite_tile)
prop	OAM Property Flags (see set_sprite_prop)

## 20.66.4 Function Documentation

Set the current screen mode - one of M\_\* modes Normally used by internal functions only.

See also

M\_TEXT\_OUT, M\_TEXT\_INOUT, M\_NO\_SCROLL, M\_NO\_INTERP

```
20.66.4.4 get_mode() uint8_t get_mode ( void )
```

Returns the current mode

See also

```
M_TEXT_OUT, M_TEXT_INOUT, M_NO_SCROLL, M_NO_INTERP
```

Returns the current mode

See also

M\_DRAWING, M\_TEXT\_OUT, M\_TEXT\_INOUT, M\_NO\_SCROLL, M\_NO\_INTERP

```
20.66.4.5 get_system() uint8_t get_system ( void ) [inline]
```

Returns the system gbdk is running on.

```
20.66.4.6 set_interrupts() void set_interrupts ( uint8\_t\ flags )
```

Clears any pending interrupts and sets the interrupt mask register IO to flags.

**Parameters** 

```
flags A logical OR of *_IFLAGS
```

Note

This disables and then re-enables interrupts so it must be used outside of a critical section.

```
See also
     enable interrupts(), disable interrupts()
     VBL_IFLAG, LCD_IFLAG, TIM_IFLAG, SIO_IFLAG, JOY_IFLAG
20.66.4.7 remove_VBL() void remove_VBL (
             int_handler h )
Removes the VBL interrupt handler.
See also
     add_VBL()
20.66.4.8 remove_LCD() void remove_LCD (
             int_handler h )
Removes the LCD interrupt handler.
See also
     add_LCD(), remove_VBL()
20.66.4.9 remove_TIM() void remove_TIM (
             int_handler h )
20.66.4.10 remove_SIO() void remove_SIO (
             int_handler h )
20.66.4.11 remove_JOY() void remove_JOY (
             int_handler h )
20.66.4.12 add_VBL() void add_VBL (
             int_handler h )
Adds a V-blank interrupt handler.
20.66.4.13 add_LCD() void add_LCD (
             int_handler h )
Adds a LCD interrupt handler.
20.66.4.14 add_TIM() void add_TIM (
             int_handler h )
Does nothing on MSX
20.66.4.15 add SIO() void add_SIO (
```

int\_handler h )

Does nothing on MSX

```
20.66.4.16 add_JOY() void add_JOY (
             int_handler h )
Does nothing on MSX
20.66.4.17 cancel_pending_interrupts() uint8_t cancel_pending_interrupts (
             void ) [inline]
Cancel pending interrupts
20.66.4.18 move_bkg() void move_bkg (
             uint8_t x,
             uint8_t y ) [inline]
20.66.4.19 scroll_bkg() void scroll_bkg (
             int8_t x,
             int8_t y ) [inline]
20.66.4.20 vsync() void vsync (
             void )
```

HALTs the CPU and waits for the vertical blank interrupt.

This is often used in main loops to idle the CPU at low power until it's time to start the next frame. It's also useful for syncing animation with the screen re-draw.

Warning: If the VBL interrupt is disabled, this function will never return. If the screen is off this function returns immediately.

```
{\bf 20.66.4.21} \quad {\bf wait\_vbl\_done()} \quad {\tt void\ wait\_vbl\_done\ (}
```

Obsolete. This function has been replaced by vsync(), which has identical behavior.

```
20.66.4.22 display_off() void display_off (
              void ) [inline]
Turns the display off.
```

See also

**DISPLAY\_ON** 

```
20.66.4.23 refresh_OAM() void refresh_OAM (
            void )
```

Copies data from shadow OAM to OAM

```
\textbf{20.66.4.24} \quad \textbf{get\_r\_reg()} \quad \texttt{uint8\_t} \;\; \texttt{get\_r\_reg} \;\; \texttt{(}
                                void )
```

Return R register for the DIV\_REG emulation

Increments once per CPU instruction (fetches the Z80 CPU R register)

```
20.66.4.25 SWITCH_ROM() void SWITCH_ROM (
            uint8_t bank )
```

Makes switch the active ROM bank in frame 1

**Parameters** 

bank ROM bank to switch to

```
20.66.4.26 delay() void delay ( uint16_t d )
```

Delays the given number of milliseconds. Uses no timers or interrupts, and can be called with interrupts disabled

```
20.66.4.27 joypad() uint8_t joypad ( void )
```

Reads and returns the current state of the joypad.

```
20.66.4.28 waitpad() uint8_t waitpad ( uint8_t mask )
```

Waits until at least one of the buttons given in mask are pressed.

```
20.66.4.29 waitpadup() void waitpadup ( void )
```

Waits for the directional pad and all buttons to be released.

Note: Checks in a loop that doesn't HALT at all, so the CPU will be maxed out until this call returns.

Initializes joypads\_t structure for polling multiple joypads

#### **Parameters**

npads	number of joypads requested (1, 2 or 4)
joypads	pointer to joypads_t structure to be initialized

Only required for joypad\_ex, not required for calls to regular joypad()

Returns

number of joypads avaliable

See also

```
joypad_ex(), joypads_t
```

Polls all avaliable joypads

## **Parameters**

joypads	pointer to joypads_t structure to be filled with joypad statuses, must be previously initialized with
	joypad_init()

See also

```
joypad_init(), joypads_t
```

Enables unmasked interrupts

Note

Use CRITICAL {...} instead for creating a block of of code which should execute with interrupts temporarily turned off.

See also

disable\_interrupts, set\_interrupts, CRITICAL

Note

Use CRITICAL {...} instead for creating a block of of code which should execute with interrupts temporarily turned off.

This function may be called as many times as you like; however the first call to enable\_interrupts will re-enable them.

See also

enable\_interrupts, set\_interrupts, CRITICAL

Set CPU speed to fast (CGB Double Speed) operation.

On startup the CGB operates in Normal Speed Mode and can be switched into Double speed mode (faster processing but also higher power consumption). See the Pan Docs for more information about which hardware features operate faster and which remain at Normal Speed.

- · Interrupts are temporarily disabled and then re-enabled during this call.
- You can check to see if \_cpu == CGB\_TYPE before using this function.

See also

```
cpu_slow(), _cpu
```

```
20.66.4.38 set_native_tile_data() void set_native_tile_data (
              uint16_t start,
              uint16_t ntiles,
              const void * src )
\textbf{20.66.4.39} \quad \textbf{set\_bkg\_4bpp\_data()} \quad \texttt{void set\_bkg\_4bpp\_data ()}
              uint16_t start,
              uint16_t ntiles,
              const void * src ) [inline]
{\bf 20.66.4.40} \quad {\bf set\_sprite\_1bpp\_data()} \quad {\tt void set\_sprite\_1bpp\_data} \ \ (
              uint16_t start,
              uint16_t ntiles,
              const void * src ) [inline]
20.66.4.41 set_native_sprite_data() void set_native_sprite_data (
              uint16_t start,
              uint16_t ntiles,
              const void * src ) [inline]
20.66.4.42 set_2bpp_palette() void set_2bpp_palette (
              uint16_t palette ) [inline]
20.66.4.43 set_bkg_data() void set_bkg_data (
              uint16_t start,
              uint16_t ntiles,
              const void * src ) [inline]
20.66.4.44 set_sprite_data() void set_sprite_data (
              uint16_t start,
              uint16_t ntiles,
              const void * src ) [inline]
20.66.4.45 set_1bpp_colors() void set_1bpp_colors (
              uint8_t fgcolor,
              uint8_t bgcolor ) [inline]
20.66.4.46 set tile 1bpp data() void set_tile_1bpp_data (
              uint16_t start,
              uint16_t ntiles,
              const void * src,
              uint16_t colors )
20.66.4.47 set_bkg_1bpp_data() void set_bkg_1bpp_data (
              uint16_t start,
              uint16_t ntiles,
              const void * src ) [inline]
```

Copies arbitrary data to an address in VRAM

#### **Parameters**

dst	destination VRAM Address
src	Pointer to source buffer
size	Number of bytes to copy

Copies **size** bytes from a buffer at \_src\_\_ to VRAM starting at **dst**.

```
20.66.4.49 vmemcpy() void vmemcpy (
             uint16_t dst,
             const void * src,
             uint16_t size )
20.66.4.50 set_tile_map() void set_tile_map (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint8_t * tiles )
20.66.4.51 set_bkg_based_tiles() void set_bkg_based_tiles (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint8_t * tiles,
             uint8_t base_tile ) [inline]
20.66.4.52 set_win_based_tiles() void set_win_based_tiles (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint8_t * tiles,
             uint8_t base_tile ) [inline]
20.66.4.53 set_tile_submap() void set_tile_submap (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             uint8_t map_w,
             const uint8_t * map )
```

Sets a rectangular area of the Background Tile Map using a sub-region from a source tile map. Useful for scrolling implementations of maps larger than  $32 \times 32$  tiles.

#### **Parameters**

X	X Start position in both the Source Tile Map and hardware Background Map tile coordinates. Range 0 - 255
У	Y Start position in both the Source Tile Map and hardware Background Map tile coordinates. Range 0 - 255
W	Width of area to set in tiles. Range 1 - 255
h	Height of area to set in tiles. Range 1 - 255
тар	Pointer to source tile map data
тар⊷	Width of source tile map in tiles. Range 1 - 255
_ <i>w</i>	

Entries are copied from **map** to the Background Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles, using **map w** as the rowstride for the source tile map.

The **x** and **y** parameters are in Source Tile Map tile coordinates. The location tiles will be written to on the hardware Background Map is derived from those, but only uses the lower 5 bits of each axis, for range of 0-31 (they are bit-masked: x & 0x1F and y & 0x1F). As a result the two coordinate systems are aligned together.

In order to transfer tile map data in a way where the coordinate systems are not aligned, an offset from the Source Tile Map pointer can be passed in:  $(map\_ptr + x + (y * map\_width))$ .

For example, if you want the tile id at 1, 2 from the source map to show up at 0, 0 on the hardware Background Map (instead of at 1, 2) then modify the pointer address that is passed in:  $map\_ptr + 1 + (2 * map\_width)$  Use this instead of  $set\_bkg\_tiles$  when the source map is wider than 32 tiles or when writing a width that does not match the source map width.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

See set bkg tiles for setting CGB attribute maps with VBK REG.

## See also

```
SHOW_BKG
```

set\_bkg\_data, set\_bkg\_tiles, set\_win\_submap, set\_tiles

```
const uint8_t * map,
uint8 t map w ) [inline]
```

Sets a rectangular area of the Window Tile Map using a sub-region from a source tile map.

#### **Parameters**

X	X Start position in both the Source Tile Map and hardware Window Map tile coordinates. Range 0 - 255
У	Y Start position in both the Source Tile Map and hardware Window Map tile coordinates. Range 0 - 255
W	Width of area to set in tiles. Range 1 - 255
h	Height of area to set in tiles. Range 1 - 255
тар	Pointer to source tile map data
map⇔	Width of source tile map in tiles. Range 1 - 255
_ <i>W</i>	

Entries are copied from **map** to the Window Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles, using **map\_w** as the rowstride for the source tile map.

The **x** and **y** parameters are in Source Tile Map tile coordinates. The location tiles will be written to on the hardware Background Map is derived from those, but only uses the lower 5 bits of each axis, for range of 0-31 (they are bit-masked:  $x \& 0 \times 1F$  and  $y \& 0 \times 1F$ ). As a result the two coordinate systems are aligned together.

In order to transfer tile map data in a way where the coordinate systems are not aligned, an offset from the Source Tile Map pointer can be passed in:  $(map\_ptr + x + (y * map\_width))$ .

For example, if you want the tile id at 1, 2 from the source map to show up at 0, 0 on the hardware Background Map (instead of at 1, 2) then modify the pointer address that is passed in:  $map\_ptr + 1 + (2 * map\_width)$  Use this instead of  $set\_win\_tiles$  when the source map is wider than 32 tiles or when writing a width that does not match the source map width.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

GBC only: VBK REG determines whether Tile Numbers or Tile Attributes get set.

- VBK\_REG = VBK\_TILES Tile Numbers are written
- VBK REG = VBK ATTRIBUTES Tile Attributes are written

See set\_bkg\_tiles for details about CGB attribute maps with VBK\_REG.

See also

SHOW\_WIN, HIDE\_WIN, set\_win\_tiles, set\_bkg\_submap, set\_bkg\_tiles, set\_bkg\_data, set\_tiles

```
20.66.4.60 SET_SHADOW_OAM_ADDRESS() void SET_SHADOW_OAM_ADDRESS ( void * address ) [inline]
```

Sets address of 256-byte aligned array of shadow OAM to be transferred on each VBlank

Sets sprite number nb\_in the OAM to display tile number \_\_tile.

#### **Parameters**

nb	Sprite number, range 0 - 39
tile	Selects a tile (0 - 255) from memory at 8000h - 8FFFh In CGB Mode this could be either in VRAM Bank
	0 or 1, depending on Bit 3 of the OAM Attribute Flag
	(see set_sprite_prop)

#### In 8x16 mode:

- The sprite will also display the next tile (tile + 1) directly below (y + 8) the first tile.
- The lower bit of the tile number is ignored: the upper 8x8 tile is (**tile** & 0xFE), and the lower 8x8 tile is (**tile** | 0x01).
- See: SPRITES\_8x16

Returns the tile number of sprite number **nb** in the OAM.

### **Parameters**

```
nb Sprite number, range 0 - 39
```

## See also

set\_sprite\_tile for more details

Sets the OAM Property Flags of sprite number **nb** to those defined in **prop**.

#### **Parameters**

nb	Sprite number, range 0 - 39
prop	Property setting (see bitfield description)

## The bits in **prop** represent:

- Bit 7 Vertical flip. Dictates which way up the sprite is drawn vertically.
  - 0: normal
  - 1: upside down
- · Bit 6 Horizontal flip. Dictates which way up the sprite is drawn horizontally.
  - 0: normal
  - 1: back to front
- Bit 5 Priority flag. When this is set, the sprites appear behind the background and window layer.
  - 0: infront
  - 1: behind
- · Bit 4 Unimplemented
- · Bit 3 Unimplemented
- · Bit 2 Unimplemented
- Bit 1 See bit 0.
- Bit 0 Bits 0-1 indicate which color palette the sprite should use. Note: only palettes 4 to 7 will be available
  for NES sprites.

It's recommended to use GBDK constants (eg: S\_FLIPY) to configure sprite properties as these are crossplatform.

```
// Load palette data into the first palette
set_sprite_palette(4, 1, exampleSprite_palettes)
// Set the OAM value for the sprite
// These flags tell the sprite to use the first sprite palette (palette 4) and to flip the sprite both
    vertically and horizontally.
set_sprite_prop(0, S_FLIPY | S_FLIPX);
```

### See also

## S\_PALETTE, S\_FLIPX, S\_FLIPY, S\_PRIORITY

Sets the OAM Property Flags of sprite number **nb** to those defined in **prop**.

#### **Parameters**

nb	Sprite number, range 0 - 39
prop	Property setting (see bitfield description)

## The bits in **prop** represent:

- Bit 7 Priority flag. When this is set the sprites appear behind the background and window layer.
  - 0: infront
  - 1: behind
- Bit 6 Vertical flip. Dictates which way up the sprite is drawn vertically.
  - 0: normal
  - 1:upside down
- Bit 5 Horizontal flip. Dictates which way up the sprite is drawn horizontally.
  - 0: normal
  - 1:back to front
- Bit 4 DMG/Non-CGB Mode Only. Assigns either one of the two b/w palettes to the sprite.
  - 0: OBJ palette 0
  - 1: OBJ palette 1
- Bit 3 GBC only. Dictates from which bank of Sprite Tile Patterns the tile is taken.
  - 0: Bank 0
  - 1: Bank 1

- Bit 2 See bit 0.
- Bit 1 See bit 0.
- Bit 0 GBC only. Bits 0-2 indicate which of the 7 OBJ colour palettes the sprite is assigned.

It's recommended to use GBDK constants (eg: S FLIPY) to configure sprite properties as these are crossplatform.

```
// Load palette data into the first palette
set_sprite_palette(4, 1, exampleSprite_palettes)
// Set the OAM value for the sprite
// These flags tell the sprite to flip both vertically and horizontally.
set_sprite_prop(0, S_FLIPY | S_FLIPX);
```

#### See also

```
S PALETTE, S FLIPX, S FLIPY, S PRIORITY
```

Returns the OAM Property Flags of sprite number  ${\bf nb}$ .

## **Parameters**

```
nb Sprite number, range 0 - 39
```

#### See also

set\_sprite\_prop for property bitfield settings

Moves sprite number  $\mathbf{nb}$  to the  $\mathbf{x}$ ,  $\mathbf{y}$  position on the screen.

### **Parameters**

nb	Sprite number, range 0 - 39
Х	X Position. Specifies the sprites horizontal position on the screen (minus 8).
	An offscreen value ( $X=0$ or $X>=168$ ) hides the sprite, but the sprite still affects the priority ordering - a
	better way to hide a sprite is to set its Y-coordinate offscreen.
У	Y Position. Specifies the sprites vertical position on the screen (minus 16).
	An offscreen value (for example, $Y=0$ or $Y>=160$ ) hides the sprite.

Moving the sprite to 0,0 (or similar off-screen location) will hide it.

Moves sprite number **nb** relative to its current position.

#### **Parameters**

nb	Sprite number, range 0 - 39
X	Number of pixels to move the sprite on the X axis
	Range: -128 - 127

#### **Parameters**

У	Number of pixels to move the sprite on the Y axis
	Range: -128 - 127

## See also

move\_sprite for more details about the X and Y position

Hides sprite number **nb** by moving it to zero position by Y.

#### **Parameters**

```
nb Sprite number, range 0 - 39
```

Set byte in vram at given memory location

#### **Parameters**

addr	address to write to
V	value

```
20.66.4.69 set_attributed_tile_xy() uint8_t* set_attributed_tile_xy ( uint8_t x, uint8_t y, uint16_t t)
```

Set single tile t with attributes on background layer at x,y

## **Parameters**

Χ	X-coordinate
У	Y-coordinate
t	tile index

# Returns

returns the address of tile, so you may use faster set vram byte() later

Set single tile t on background layer at x,y

#### **Parameters**

X	X-coordinate
У	Y-coordinate
t	tile index

## Returns

returns the address of tile, so you may use faster set\_vram\_byte() later

```
20.66.4.71 get_bkg_xy_addr() uint8_t* get_bkg_xy_addr ( uint8_t x, uint8_t y)
```

Get address of X,Y tile of background map

## 20.66.5 Variable Documentation

```
20.66.5.1 _SYSTEM const uint8_t _SYSTEM [extern]

20.66.5.2 c void c

20.66.5.3 d void d

20.66.5.4 e void e

20.66.5.5 iyh void iyh

20.66.5.6 iyl uint8_t iyl
Initial value:
{ __asm__("ei")}

20.66.5.7 h void h

20.66.5.8 l void l

20.66.5.9 sys_time volatile uint16_t sys_time [extern]
Global Time Counter in VBL periods (60Hz)
Increments once per Frame
Will wrap around every ~18 minutes (unsigned 16 bits = 65535 / 60 / 60 = 18.2)
```

```
20.66.5.10 _current_bank volatile uint8_t _current_bank [extern]
```

Tracks current active ROM bank in frame 1

Tracks current active ROM bank

In most cases the CURRENT\_BANK macro for this variable is recommended for use instead of the variable itself. The active bank number is not tracked by \_current\_bank when SWITCH\_ROM\_MBC5\_8M is used.

This variable is updated automatically when you call SWITCH\_ROM\_MBC1 or SWITCH\_ROM\_MBC5, SWITCH\_ROM(), or call a BANKED function.

See also

SWITCH\_ROM\_MBC1(), SWITCH\_ROM\_MBC5(), SWITCH\_ROM()

```
20.66.5.12 _current_2bpp_palette uint16_t _current_2bpp_palette [extern]

20.66.5.13 _current_1bpp_colors uint16_t _current_1bpp_colors [extern]

20.66.5.14 _map_tile_offset uint8_t _map_tile_offset [extern]

20.66.5.15 _submap_tile_offset uint8_t _submap_tile_offset [extern]

20.66.5.16 shadow_OAM volatile struct OAM_item_t shadow_OAM[] [extern]

Shadow OAM array in WRAM, that is DMA-transferred into the real OAM each VBlank

20.66.5.17 _shadow_OAM_base volatile uint8_t _shadow_OAM_base [extern]

MSB of shadow_OAM address is used by OAM copying routine

MSB of shadow_OAM address is used by OAM DMA copying routine
```

- 1: OAM copy routine is disabled (non-isr VDP operation may be in progress)
- · 0: OAM copy routine is enabled

Flag for disabling of OAM copying routine

This flag is modified by all MSX GBDK API calls that write to the VDP. It is set to DISABLED when they start and ENABLED when they complete.

Note

Values:

It is recommended to avoid writing to the Video Display Processor (VDP) during an interrupt service routine (ISR) since it can corrupt the VDP pointer of an VDP operation already in progress.

If it is necessary, this flag can be used during an ISR to determine whether a VDP operation is already in progress. If the value is 1 then avoid writing to the VDP (tiles, map, scrolling, colors, etc).

```
// at the beginning of and ISR that would write to the VDP
if (_shadow_OAM_OFF) return;
```

See also

docs\_consoles\_safe\_display\_controller\_access

## 20.67 gbdk-lib/include/nes/nes.h File Reference

```
#include <types.h>
#include <stdint.h>
#include <gbdk/version.h>
#include <nes/hardware.h>
#include <nes/rgb_to_nes_macro.h>
```

#### **Data Structures**

- · struct joypads\_t
- struct OAM item t

#### **Macros**

- #define NINTENDO\_NES
- #define SYSTEM BITS NTSC 0x00
- #define SYSTEM\_BITS\_PAL 0x40
- #define SYSTEM\_BITS\_DENDY 0x80
- #define SYSTEM 60HZ 0x00
- #define SYSTEM 50HZ 0x01
- #define RGB(r, g, b) RGB\_TO\_NES(((r)  $\mid$  ((g) << 2)  $\mid$  ((b) << 4)))
- #define RGB8(r, g, b) RGB\_TO\_NES((((r)  $>> 6) \mid (((g) >> 6) << 2) \mid (((b) >> 6) << 4)))$
- #define RGBHTML(RGB24bit) RGB\_TO\_NES((((RGB24bit) >> 22) | ((((RGB24bit) & 0xFFF) >> 14) <<</li>
   2) | ((((RGB24bit) & 0xFF) >> 6) << 4)))</li>
- #define RGB RED 0x16
- #define RGB\_DARKRED 0x06
- #define RGB GREEN 0x2A
- #define RGB\_DARKGREEN 0x1A
- #define RGB\_BLUE 0x12
- #define RGB DARKBLUE 0x02
- #define RGB YELLOW 0x28
- #define RGB\_DARKYELLOW 0x18
- #define RGB CYAN 0x2C
- #define RGB\_AQUA 0x1C
- #define RGB\_PINK 0x24
- #define RGB PURPLE 0x14
- #define RGB\_BLACK 0x0F
- #define RGB\_DARKGRAY 0x00
- #define RGB\_LIGHTGRAY 0x10
- #define RGB\_WHITE 0x30
- #define J UP 0x08U
- #define J DOWN 0x04U
- #define J LEFT 0x02U
- #define J\_RIGHT 0x01U
- #define J\_A 0x80U
- #define J B 0x40U
- #define J SELECT 0x20U
- #define J\_START 0x10U
- #define M DRAWING 0x01U
- #define M\_TEXT\_OUT 0x02U
- #define M\_TEXT\_INOUT 0x03U
- #define M NO SCROLL 0x04U
- #define M\_NO\_INTERP 0x08U
- #define S\_PALETTE 0x10U

- #define S FLIPX 0x40U #define S\_FLIPY 0x80U • #define S PRIORITY 0x20U • #define S PAL(n) n • #define DMG BLACK 0x03 #define DMG DARK GRAY 0x02 #define DMG\_LITE\_GRAY 0x01 • #define DMG WHITE 0x00 #define DMG PALETTE(C0, C1, C2, C3) ((uint8 t)((((C3) & 0x03) << 6) | (((C2) & 0x03) << 4) | (((C1) &</li> 0x03) << 2) | ((C0) & 0x03))) • #define SCREENWIDTH DEVICE\_SCREEN\_PX\_WIDTH #define SCREENHEIGHT DEVICE SCREEN PX HEIGHT #define CURRENT BANK current bank #define BANK(VARNAME) ( (uint8\_t) & \_\_bank\_ ## VARNAME ) #define BANKREF(VARNAME) #define BANKREF\_EXTERN(VARNAME) extern const void \_\_bank\_ ## VARNAME; #define SWITCH ROM DUMMY(b) #define SWITCH ROM UNROM(b) switch prg0(b) #define SWITCH\_ROM SWITCH\_ROM\_UNROM • #define SWITCH\_RAM(b) 0 • #define ENABLE RAM #define DISABLE RAM #define DISPLAY ON display on(); #define DISPLAY\_OFF display\_off(); #define HIDE\_LEFT\_COLUMN shadow\_PPUMASK &= ~(PPUMASK\_SHOW\_BG\_LC | PPUMASK\_SHOW\_SPR\_LC); #define SHOW LEFT COLUMN shadow PPUMASK |= (PPUMASK SHOW BG LC | PPUMASK SHOW SPR LC); #define SET BORDER COLOR(C) #define SHOW BKG shadow PPUMASK |= PPUMASK SHOW BG; #define HIDE\_BKG shadow\_PPUMASK &= ~PPUMASK\_SHOW\_BG; #define SHOW\_SPRITES shadow\_PPUMASK |= PPUMASK\_SHOW\_SPR; #define HIDE SPRITES shadow PPUMASK &= ~PPUMASK SHOW SPR; • #define SPRITES 8x16 shadow PPUCTRL |= PPUCTRL SPR 8X16; #define SPRITES 8x8 shadow PPUCTRL &= ~PPUCTRL SPR 8X16; #define COMPAT\_PALETTE(C0, C1, C2, C3) ((uint8\_t)(((C3) << 6) | ((C2) << 4) | ((C1) << 2) | (C0)))</li> #define set\_bkg\_2bpp\_data set\_bkg\_data #define set\_tile\_map set\_bkg\_tiles #define set\_tile\_submap set\_bkg\_submap #define set\_tile\_xy set\_bkg\_tile\_xy #define set\_attribute\_xy set\_bkg\_attribute\_xy #define set\_sprite\_2bpp\_data set\_sprite\_data #define DISABLE\_OAM\_DMA \_shadow\_OAM\_base = 0
- #define DISABLE\_VBL\_TRANSFER DISABLE\_OAM\_DMA
- #define ENABLE OAM DMA shadow OAM base = (uint8 t)((uint16 t)&shadow OAM >> 8)
- #define ENABLE VBL TRANSFER ENABLE OAM DMA
- #define MAX\_HARDWARE\_SPRITES 64
- #define HARDWARE\_SPRITE\_CAN\_FLIP\_X 1
- #define HARDWARE\_SPRITE\_CAN\_FLIP\_Y 1
- · #define fill rect fill bkg rect

## **Typedefs**

- typedef uint8\_t palette\_color\_t
- typedef void(\* int handler) (void) NONBANKED
- typedef struct OAM\_item\_t OAM\_item\_t

#### **Functions**

- void set\_bkg\_palette (uint8\_t first\_palette, uint8\_t nb\_palettes, const palette\_color\_t \*rgb\_data) NO\_←
   OVERLAY LOCALS
- void set\_sprite\_palette (uint8\_t first\_palette, uint8\_t nb\_palettes, const palette\_color\_t \*rgb\_data) NO\_←
   OVERLAY\_LOCALS
- void set\_bkg\_palette\_entry (uint8\_t palette, uint8\_t entry, palette\_color\_t rgb\_data) NO\_OVERLAY\_LOCALS
- void set\_sprite\_palette\_entry (uint8\_t palette, uint8\_t entry, palette\_color\_t rgb\_data) NO\_OVERLAY\_←
  LOCALS
- void remove\_VBL (int\_handler h) NO\_OVERLAY\_LOCALS
- · void remove LCD (int handler h) NO OVERLAY LOCALS
- · void add VBL (int handler h) NO OVERLAY LOCALS
- void add LCD (int handler h) NO OVERLAY LOCALS
- void mode (uint8\_t m) NO\_OVERLAY\_LOCALS
- uint8\_t get\_mode (void) NO\_OVERLAY\_LOCALS
- uint8\_t get\_system (void)
- void delay (uint16 t d) NO OVERLAY LOCALS
- uint8\_t joypad (void) NO\_OVERLAY\_LOCALS
- uint8\_t waitpad (uint8\_t mask) NO\_OVERLAY\_LOCALS
- void waitpadup (void) NO\_OVERLAY\_LOCALS
- uint8 t joypad init (uint8 t npads, joypads t \*joypads) NO OVERLAY LOCALS
- void joypad ex (joypads t \*joypads) NO OVERLAY LOCALS
- void enable\_interrupts (void)
- void disable\_interrupts (void)
- void vsync (void) NO\_OVERLAY\_LOCALS
- void wait\_vbl\_done (void) NO\_OVERLAY\_LOCALS
- · void display on (void) NO OVERLAY LOCALS
- void display\_off (void) NO\_OVERLAY\_LOCALS
- void refresh\_OAM (void) NO\_OVERLAY\_LOCALS
- void set\_vram\_byte (uint8\_t \*addr, uint8\_t v) NO\_OVERLAY\_LOCALS
- uint8\_t \* get\_bkg\_xy\_addr (uint8\_t x, uint8\_t y) NO\_OVERLAY\_LOCALS
- void set\_2bpp\_palette (uint16\_t palette)
- void set 1bpp colors ex (uint8 t fgcolor, uint8 t bgcolor, uint8 t mode) NO OVERLAY LOCALS
- void set 1bpp colors (uint8 t fgcolor, uint8 t bgcolor)
- void set\_bkg\_data (uint8\_t first\_tile, uint8\_t nb\_tiles, const uint8\_t \*data) NO\_OVERLAY\_LOCALS
- void set bkg 1bpp data (uint8 t first tile, uint8 t nb tiles, const uint8 t \*data) NO OVERLAY LOCALS
- void set\_bkg\_tiles (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*tiles) NO\_OVERLAY\_LOCALS
- void set\_bkg\_attributes\_nes16x16 (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*attributes) NO\_←
   OVERLAY\_LOCALS
- void set bkg attributes (uint8 t x, uint8 t y, uint8 t w, uint8 t h, const uint8 t \*attributes)
- void set\_bkg\_submap\_attributes\_nes16x16 (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w) NO\_OVERLAY\_LOCALS
- void set\_bkg\_submap\_attributes (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*attributes, uint8\_t map\_w)
- void set\_bkg\_based\_tiles (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*tiles, uint8\_t base\_tile)
- void set\_bkg\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w) NO\_←
   OVERLAY LOCALS
- void set\_bkg\_based\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w, uint8\_t base\_tile)
- void get\_bkg\_tiles (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, uint8\_t \*tiles) NO\_OVERLAY\_LOCALS
- uint8\_t \* set\_bkg\_tile\_xy (uint8\_t x, uint8\_t y, uint8\_t t) NO\_OVERLAY\_LOCALS
- void set\_bkg\_attribute\_xy\_nes16x16 (uint8\_t x, uint8\_t y, uint8\_t a) NO\_OVERLAY\_LOCALS
- void set\_bkg\_attribute\_xy (uint8\_t x, uint8\_t y, uint8\_t a)
- uint8 t get bkg tile xy (uint8 t x, uint8 t y) NO OVERLAY LOCALS
- void move bkg (uint8 t x, uint8 t y)
- void scroll\_bkg (int8\_t x, int8\_t y)

- void set\_sprite\_data (uint8\_t first\_tile, uint8\_t nb\_tiles, const uint8\_t \*data) NO\_OVERLAY\_LOCALS
- void set\_sprite\_1bpp\_data (uint8\_t first\_tile, uint8\_t nb\_tiles, const uint8\_t \*data) NO\_OVERLAY\_LOCALS
- void SET\_SHADOW\_OAM\_ADDRESS (void \*address)
- void set\_sprite\_tile (uint8\_t nb, uint8\_t tile) NO\_OVERLAY\_LOCALS
- uint8\_t get\_sprite\_tile (uint8\_t nb) NO\_OVERLAY\_LOCALS
- void set\_sprite\_prop (uint8\_t nb, uint8\_t prop) NO\_OVERLAY\_LOCALS
- uint8\_t get\_sprite\_prop (uint8\_t nb) NO\_OVERLAY\_LOCALS
- void move\_sprite (uint8\_t nb, uint8\_t x, uint8\_t y) NO\_OVERLAY\_LOCALS
- void scroll\_sprite (uint8\_t nb, int8\_t x, int8\_t y) NO\_OVERLAY\_LOCALS
- void hide sprite (uint8 t nb) NO OVERLAY LOCALS
- void set data (uint8 t \*vram addr, const uint8 t \*data, uint16 t len) NO OVERLAY LOCALS
- void set\_tiles (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, uint8\_t \*vram\_addr, const uint8\_t \*tiles) NO\_←
   OVERLAY\_LOCALS
- void set\_tile\_data (uint16\_t first\_tile, uint8\_t nb\_tiles, const uint8\_t \*data)
- void set\_bkg\_native\_data (uint8\_t first\_tile, uint8\_t nb\_tiles, const uint8\_t \*data) NO\_OVERLAY\_LOCALS
- void set sprite native data (uint8 t first tile, uint8 t nb tiles, const uint8 t \*data) NO OVERLAY LOCALS
- void set native tile data (uint16 t first tile, uint8 t nb tiles, const uint8 t \*data)
- void init\_bkg (uint8\_t c) NO\_OVERLAY\_LOCALS
- void vmemset (void \*s, uint8\_t c, size\_t n) NO\_OVERLAY\_LOCALS
- void fill\_bkg\_rect (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, uint8\_t tile) NO\_OVERLAY\_LOCALS
- void flush\_shadow\_attributes (void) NO\_OVERLAY\_LOCALS
- uint8\_t \_switch\_prg0 (uint8\_t bank) NO\_OVERLAY\_LOCALS

#### **Variables**

- const uint8\_t \_SYSTEM
- volatile uint16\_t sys\_time
- volatile uint8\_t \_current\_bank
- uint16\_t \_current\_1bpp\_colors
- uint8\_t \_map\_tile\_offset
- uint8\_t \_submap\_tile\_offset
- volatile struct OAM item t shadow OAM []
- uint8\_t \_shadow\_OAM\_base

## 20.67.1 Detailed Description

NES specific functions.

#### 20.67.2 Macro Definition Documentation

- 20.67.2.1 NINTENDO\_NES #define NINTENDO\_NES
- 20.67.2.2 SYSTEM\_BITS\_NTSC #define SYSTEM\_BITS\_NTSC 0x00
- 20.67.2.3 SYSTEM\_BITS\_PAL #define SYSTEM\_BITS\_PAL 0x40
- 20.67.2.4 SYSTEM BITS DENDY #define SYSTEM\_BITS\_DENDY 0x80
- 20.67.2.5 SYSTEM\_60HZ #define SYSTEM\_60HZ 0x00

```
20.67.2.6 SYSTEM_50HZ #define SYSTEM_50HZ 0x01
20.67.2.7 RGB #define RGB(
              r.
              b ) RGB_TO_NES(((r) | ((g) << 2) | ((b) << 4)))
20.67.2.8 RGB8 #define RGB8(
              r,
              g,
              b ) RGB_TO_NES((((r) >> 6) | (((g) >> 6) << 2) | (((b) >> 6) << 4)))
20.67.2.9 RGBHTML #define RGBHTML(
              RGB24bit ) RGB_{TO\_NES}(((RGB24bit) >> 22) | (((RGB24bit) & 0xFFFF) >> 14) << 
2) | ((((RGB24bit) & 0xFF) >> 6) << 4)))
20.67.2.10 RGB_RED #define RGB_RED 0x16
Common colors based on the EGA default palette.
Manually entered from https://www.nesdev.org/wiki/PPU_palettes#RGBI
20.67.2.11 RGB_DARKRED #define RGB_DARKRED 0x06
20.67.2.12 RGB_GREEN #define RGB_GREEN 0x2A
20.67.2.13 RGB_DARKGREEN #define RGB_DARKGREEN 0x1A
20.67.2.14 RGB_BLUE #define RGB_BLUE 0x12
20.67.2.15 RGB_DARKBLUE #define RGB_DARKBLUE 0x02
\textbf{20.67.2.16} \quad \textbf{RGB\_YELLOW} \quad \texttt{\#define} \ \texttt{RGB\_YELLOW} \ \texttt{0x28}
20.67.2.17 RGB_DARKYELLOW #define RGB_DARKYELLOW 0x18
20.67.2.18 RGB_CYAN #define RGB_CYAN 0x2C
20.67.2.19 RGB_AQUA #define RGB_AQUA 0x1C
20.67.2.20 RGB_PINK #define RGB_PINK 0x24
```

```
20.67.2.21 RGB_PURPLE #define RGB_PURPLE 0x14
\textbf{20.67.2.22} \quad \textbf{RGB\_BLACK} \quad \texttt{\#define} \;\; \texttt{RGB\_BLACK} \;\; \texttt{0x0F}
20.67.2.23 RGB_DARKGRAY #define RGB_DARKGRAY 0x00
20.67.2.24 RGB_LIGHTGRAY #define RGB_LIGHTGRAY 0x10
20.67.2.25 RGB_WHITE #define RGB_WHITE 0x30
20.67.2.26 J_UP #define J_UP 0x08U
Joypad bits. A logical OR of these is used in the wait_pad and joypad functions. For example, to see if the B button
is pressed try
uint8_t keys; keys = joypad(); if (keys & J_B) { ... }
See also
     joypad
20.67.2.28 J_LEFT #define J_LEFT 0x02U
20.67.2.29 J_RIGHT #define J_RIGHT 0x01U
20.67.2.30 J_A #define J_A 0x80U
20.67.2.31 J_B #define J_B 0x40U
20.67.2.32 J_SELECT #define J_SELECT 0x20U
20.67.2.33 J_START #define J_START 0x10U
20.67.2.34 M_DRAWING #define M_DRAWING 0x01U
Screen modes. Normally used by internal functions only.
See also
     mode()
```

20.67.2.35 M\_TEXT\_OUT #define M\_TEXT\_OUT 0x02U

```
20.67.2.36 M_TEXT_INOUT #define M_TEXT_INOUT 0x03U
20.67.2.37 M_NO_SCROLL #define M_NO_SCROLL 0x04U
Set this in addition to the others to disable scrolling
If scrolling is disabled, the cursor returns to (0,0)
See also
     mode()
20.67.2.38 M_NO_INTERP #define M_NO_INTERP 0x08U
Set this to disable interpretation
See also
     mode()
20.67.2.39 S_PALETTE #define S_PALETTE 0x10U
If this is set, sprite colours come from OBJ1PAL. Else they come from OBJ0PAL
See also
     set_sprite_prop().
20.67.2.40 S_FLIPX #define S_FLIPX 0x40U
If set the sprite will be flipped horizontally.
See also
     set_sprite_prop()
20.67.2.41 S_FLIPY #define S_FLIPY 0x80U
If set the sprite will be flipped vertically.
See also
     set_sprite_prop()
20.67.2.42 S_PRIORITY #define S_PRIORITY 0x20U
If this bit is clear, then the sprite will be displayed on top of the background and window.
See also
     set_sprite_prop()
20.67.2.43 S_PAL #define S_PAL(
Defines how palette number is encoded in OAM. Required for the png2asset tool's metasprite output.
20.67.2.44 DMG_BLACK #define DMG_BLACK 0x03
```

#### **Parameters**

C0	Color for Index 0
C1	Color for Index 1
C2	Color for Index 2
СЗ	Color for Index 3

Macro to create a DMG palette from 4 colors

The resulting format is four greyscale colors packed into a single unsigned byte.

## Example:

```
REG_BGP = DMG_PALETTE(DMG_BLACK, DMG_DARK_GRAY, DMG_LITE_GRAY, DMG_WHITE);
```

## See also

```
OBP0_REG, OBP1_REG, BGP_REG

DMG_BLACK, DMG_DARK_GRAY, DMG_LITE_GRAY, DMG_WHITE
```

**20.67.2.49 SCREENWIDTH** #define SCREENWIDTH DEVICE\_SCREEN\_PX\_WIDTH Width of the visible screen in pixels.

**20.67.2.50 SCREENHEIGHT** #define SCREENHEIGHT DEVICE\_SCREEN\_PX\_HEIGHT Height of the visible screen in pixels.

20.67.2.51 CURRENT\_BANK #define CURRENT\_BANK \_current\_bank

Obtains the bank number of VARNAME

# **Parameters**

VARNAME	Name of the variable which has abank_VARNAME companion symbol which is adjusted by
	bankpack

Use this to obtain the bank number from a bank reference created with BANKREF().

#### See also

## BANKREF\_EXTERN(), BANKREF()

Creates a reference for retrieving the bank number of a variable or function

#### **Parameters**

VADNIANE	Variable name to use, which may be an existing identifier
VARIVAIVIE	Variable name to use, which may be an existing identifier

#### See also

BANK() for obtaining the bank number of the included data.

More than one BANKREF () may be created per file, but each call should always use a unique VARNAME. Use BANKREF EXTERN() within another source file to make the variable and it's data accesible there.

```
20.67.2.54 BANKREF_EXTERN #define BANKREF_EXTERN(

VARNAME) extern const void __bank_ ## VARNAME;
```

Creates extern references for accessing a BANKREF() generated variable.

#### **Parameters**

VARNAME	Name of the variable used with BANKREF()

This makes a BANKREF() reference in another source file accessible in the current file for use with BANK().

### See also

BANKREF(), BANK()

```
20.67.2.55 SWITCH_ROM_DUMMY #define SWITCH_ROM_DUMMY(
```

Dummy macro for no-bank-switching WIP prototype

# Parameters

b ROM bank to switch to

Macro for simple UNROM-like switching (write bank# to single 8-bit register)

### **Parameters**

b ROM bank to switch to

 $\textbf{20.67.2.57} \quad \textbf{SWITCH\_ROM} \quad \texttt{\#define} \quad \texttt{SWITCH\_ROM\_UNROM}$ 

Makes default mapper switch the active ROM bank

**Parameters** 

b ROM bank to switch to (max 255)

See also

SWITCH ROM UNROM

```
20.67.2.58 SWITCH_RAM #define SWITCH_RAM(
```

**b** ) 0

No-op at the moment. Placeholder for future mappers / test compatibility.

**Parameters** 

b SRAM bank to switch to

20.67.2.59 ENABLE\_RAM #define ENABLE\_RAM

No-op at the moment. Placeholder for future mappers / test compatibility.

20.67.2.60 DISABLE\_RAM #define DISABLE\_RAM

No-op at the moment. Placeholder for future mappers / test compatibility.

20.67.2.61 DISPLAY\_ON #define DISPLAY\_ON display\_on();

Turns the display back on.

See also

display\_off, DISPLAY\_OFF

20.67.2.62 DISPLAY\_OFF #define DISPLAY\_OFF display\_off();

Turns the display off immediately.

See also

display\_off, DISPLAY\_ON

**20.67.2.63 HIDE\_LEFT\_COLUMN** #define HIDE\_LEFT\_COLUMN shadow\_PPUMASK &= ~(PPUMASK\_SHOW\_BG\_LC | PPUMASK\_SHOW\_SPR\_LC); \

Blanks leftmost column, so it is not garbaged when you use horizontal scroll

See also

SHOW\_LEFT\_COLUMN

```
20.67.2.64 SHOW_LEFT_COLUMN #define SHOW_LEFT_COLUMN shadow_PPUMASK |= (PPUMASK_SHOW_BG_LC
| PPUMASK_SHOW_SPR_LC);
Shows leftmost column
See also
     HIDE LEFT COLUMN
20.67.2.65 SET_BORDER_COLOR #define SET_BORDER_COLOR(
Does nothing for NES not implemented yet
20.67.2.66 SHOW_BKG #define SHOW_BKG shadow_PPUMASK |= PPUMASK_SHOW_BG;
Turns on the background layer. Sets bit 0 of the LCDC register to 1.
20.67.2.67 HIDE_BKG #define HIDE_BKG shadow_PPUMASK &= ~PPUMASK_SHOW_BG;
Turns off the background layer. Sets bit 0 of the LCDC register to 0.
20.67.2.68 SHOW_SPRITES #define SHOW_SPRITES shadow_PPUMASK |= PPUMASK_SHOW_SPR;
Turns on the sprites layer. Sets bit 1 of the LCDC register to 1.
20.67.2.69 HIDE_SPRITES #define HIDE_SPRITES shadow_PPUMASK &= ~PPUMASK_SHOW_SPR;
Turns off the sprites layer. Clears bit 1 of the LCDC register to 0.
20.67.2.70 SPRITES_8x16 #define SPRITES_8x16 shadow_PPUCTRL |= PPUCTRL_SPR_8X16;
Sets sprite size to 8x16 pixels, two tiles one above the other. Sets bit 2 of the LCDC register to 1.
20.67.2.71 SPRITES_8x8 #define SPRITES_8x8 shadow_PPUCTRL &= ~PPUCTRL_SPR_8X16;
Sets sprite size to 8x8 pixels, one tile. Clears bit 2 of the LCDC register to 0.
20.67.2.72 COMPAT_PALETTE #define COMPAT_PALETTE(
              CO,
              C1,
              C2,
              C3 ) ((uint8_t)(((C3) << 6) | ((C2) << 4) | ((C1) << 2) | (C0)))
20.67.2.73 set_bkg_2bpp_data #define set_bkg_2bpp_data set_bkg_data
20.67.2.74 set_tile_map #define set_tile_map set_bkg_tiles
20.67.2.75 set_tile_submap #define set_tile_submap set_bkg_submap
20.67.2.76 set_tile_xy #define set_tile_xy set_bkg_tile_xy
20.67.2.77 set_attribute_xy #define set_attribute_xy set_bkg_attribute_xy
20.67.2.78 set_sprite_2bpp_data #define set_sprite_2bpp_data set_sprite_data
```

```
20.67.2.79 DISABLE_OAM_DMA #define DISABLE_OAM_DMA _shadow_OAM_base = 0
```

**20.67.2.80 DISABLE\_VBL\_TRANSFER** #define DISABLE\_VBL\_TRANSFER DISABLE\_OAM\_DMA Disable OAM DMA copy each VBlank

20.67.2.81 ENABLE\_OAM\_DMA #define ENABLE\_OAM\_DMA \_shadow\_OAM\_base = (uint8\_t)((uint16\_t)&shadow\_OAM >> 8)

**20.67.2.82 ENABLE\_VBL\_TRANSFER** #define ENABLE\_VBL\_TRANSFER ENABLE\_OAM\_DMA Enable OAM DMA copy each VBlank and set it to transfer default shadow\_OAM array

**20.67.2.83 MAX\_HARDWARE\_SPRITES** #define MAX\_HARDWARE\_SPRITES 64 Amount of hardware sprites in OAM

**20.67.2.84 HARDWARE\_SPRITE\_CAN\_FLIP\_X** #define HARDWARE\_SPRITE\_CAN\_FLIP\_X 1 True if sprite hardware can flip sprites by X (horizontally)

**20.67.2.85 HARDWARE\_SPRITE\_CAN\_FLIP\_Y** #define HARDWARE\_SPRITE\_CAN\_FLIP\_Y 1 True if sprite hardware can flip sprites by Y (vertically)

20.67.2.86 fill\_rect #define fill\_rect fill\_bkg\_rect

## 20.67.3 Typedef Documentation

20.67.3.1 palette\_color\_t typedef uint8\_t palette\_color\_t

 $\textbf{20.67.3.2} \quad \textbf{int\_handler} \quad \texttt{typedef void(* int\_handler)} \quad \texttt{(void)} \quad \textbf{NONBANKED} \\ \textbf{Interrupt handlers}$ 

**20.67.3.3 OAM\_item\_t** typedef struct OAM\_item\_t OAM\_item\_t Sprite Attributes structure

### **Parameters**

X	X Coordinate of the sprite on screen
У	Y Coordinate of the sprite on screen - 1
tile	Sprite tile number (see set_sprite_tile)
prop	OAM Property Flags (see set_sprite_prop)

## 20.67.4 Function Documentation

```
20.67.4.2 set_sprite_palette() void set_sprite_palette (
             uint8_t first_palette,
             uint8_t nb_palettes,
             const palette_color_t * rgb_data )
20.67.4.3 set_bkg_palette_entry() void set_bkg_palette_entry (
             uint8_t palette,
             uint8_t entry,
             palette_color_t rgb_data )
20.67.4.4 set_sprite_palette_entry() void set_sprite_palette_entry (
             uint8_t palette,
             uint8_t entry,
             palette_color_t rgb_data )
20.67.4.5 remove_VBL() void remove_VBL (
              int_handler h )
The remove functions will remove any interrupt handler.
A handler of NULL will cause bad things to happen if the given interrupt is enabled.
Removes the VBL interrupt handler.
See also
     add_VBL()
Removes the VBL interrupt handler.
See also
     add_VBL()
20.67.4.6 remove_LCD() void remove_LCD (
              int_handler h )
Removes the LCD interrupt handler.
See also
     add_LCD(), remove_VBL()
20.67.4.7 add_VBL() void add_VBL (
              int_handler h )
Adds a Vertical Blanking interrupt handler.
```

Only a single handler is currently supported for NES.

The handler to be called whenever a V-blank interrupt occurs.

**Parameters** 

**Do not** use the function definition attributes CRITICAL and INTERRUPT when declaring ISR functions added via add\_VBL() (or LCD, etc). Those attributes are only required when constructing a bare jump from the interrupt vector itself (such as with ISR\_VECTOR()).

ISR handlers added using add\_VBL()/etc are instead called via the GBDK ISR dispatcher which makes the extra function attributes unecessary.

Note

The default GBDK VBL is installed automatically.

On the current NES implementation, this handler is actually faked, and called before vblank occurs, by vsync(). Writes to PPU registers should be done to the shadow\_ versions, so they are updated by the default VBL handler only when vblank actually occurs.

See also

```
ISR VECTOR()
```

Adds a V-blank interrupt handler.

```
20.67.4.8 add_LCD() void add_LCD (
          int_handler h )
```

Adds a LCD interrupt handler.

Called when the scanline matches the lcd scanline variables.

Only a single handler is currently supported for NES.

The use-case is to indicate to the user when the video hardware is about to redraw a given LCD line. This can be useful for dynamically controlling the scrolling registers to perform special video effects.

**Do not** use the function definition attributes CRITICAL and INTERRUPT when declaring ISR functions added via add\_VBL() (or LCD, etc). Those attributes are only required when constructing a bare jump from the interrupt vector itself (such as with ISR\_VECTOR()).

ISR handlers added using add\_VBL()/etc are instead called via the GBDK ISR dispatcher which makes the extra function attributes unecessary.

Note

On the current NES implementation, this handler is actually faked, and called by the default VBL handler after a manual delay loop. Only one such faked "interrupt" is possible per frame. This means the CPU cycles wasted in the delay loop increase with higher values of \_lcd\_scanline. In practice, it makes this functionality mostly suited for a top status bar.

See also

```
add_VBL, nowait_int_handler, ISR_VECTOR()
```

Adds a LCD interrupt handler.

```
20.67.4.9 mode() void mode ( uint8_t m )
```

Set the current screen mode - one of M \* modes

Normally used by internal functions only.

See also

M\_DRAWING, M\_TEXT\_OUT, M\_TEXT\_INOUT, M\_NO\_SCROLL, M\_NO\_INTERP

```
20.67.4.10 get_mode() uint8_t get_mode ( void )
```

Returns the current mode

See also

M\_DRAWING, M\_TEXT\_OUT, M\_TEXT\_INOUT, M\_NO\_SCROLL, M\_NO\_INTERP

Returns the system gbdk is running on.

```
20.67.4.12 delay() void delay ( uint16_t d )
```

Delays the given number of milliseconds. Uses no timers or interrupts, and can be called with interrupts disabled

```
20.67.4.13 joypad() uint8_t joypad ( void )
```

Reads and returns the current state of the joypad. Return value is an OR of J\_\*

When testing for multiple different buttons, it's best to read the joypad state *once* into a variable and then test using that variable.

See also

```
J_START, J_SELECT, J_A, J_B, J_UP, J_DOWN, J_LEFT, J_RIGHT
```

Reads and returns the current state of the joypad. Follows Nintendo's guidelines for reading the pad. Return value is an OR of J  $\,*$ 

When testing for multiple different buttons, it's best to read the joypad state *once* into a variable and then test using that variable.

See also

```
J START, J SELECT, J A, J B, J UP, J DOWN, J LEFT, J RIGHT
```

Reads and returns the current state of the joypad.

```
20.67.4.14 waitpad() uint8_t waitpad (
uint8_t mask)
```

Waits until at least one of the buttons given in mask are pressed.

Normally only used for checking one key, but it will support many, even J LEFT at the same time as J RIGHT. :)

See also

```
joypad
```

```
J START, J SELECT, J A, J B, J UP, J DOWN, J LEFT, J RIGHT
```

Waits until at least one of the buttons given in mask are pressed.

**Parameters** 

```
mask Bitmask indicating which buttons to wait for
```

Normally only used for checking one key, but it will support many, even J\_LEFT at the same time as J\_RIGHT. :)

Note

Checks in a loop that doesn't HALT at all, so the CPU will be maxed out until this call returns.

See also

```
joypad
```

```
J_START, J_SELECT, J_A, J_B, J_UP, J_DOWN, J_LEFT, J_RIGHT
```

Waits until at least one of the buttons given in mask are pressed.

```
20.67.4.15 waitpadup() void waitpadup (
```

Waits for the directional pad and all buttons to be released.

Waits for the directional pad and all buttons to be released.

Note

Checks in a loop that doesn't HALT at all, so the CPU will be maxed out until this call returns.

Waits for the directional pad and all buttons to be released.

Note: Checks in a loop that doesn't HALT at all, so the CPU will be maxed out until this call returns.

Initializes joypads\_t structure for polling multiple joypads

## **Parameters**

npads	number of joypads requested (1, 2 or 4)
joypads	pointer to joypads_t structure to be initialized

Only required for joypad\_ex, not required for calls to regular joypad()

Returns

number of joypads avaliable

See also

```
joypad_ex(), joypads_t
```

Polls all avaliable joypads

See also

joypad\_init(), joypads\_t

Polls all avaliable joypads (for the GB and ones connected via SGB)

## **Parameters**

joypads	pointer to joypads_t structure to be filled with joypad statuses, must be previously initialized with
	joypad_init()

See also

```
joypad_init(), joypads_t
```

Polls all avaliable joypads

# **Parameters**

joypads	pointer to joypads_t structure to be filled with joypad statuses, must be previously initialized with
	joypad_init()

See also

```
joypad_init(), joypads_t
```

Enables unmasked interrupts

Note

Use CRITICAL {...} instead for creating a block of of code which should execute with interrupts temporarily turned off

See also

disable\_interrupts, set\_interrupts, CRITICAL

Note

Use CRITICAL {...} instead for creating a block of of code which should execute with interrupts temporarily turned off.

This function may be called as many times as you like; however the first call to enable\_interrupts will re-enable them.

See also

enable\_interrupts, set\_interrupts, CRITICAL

```
20.67.4.20 vsync() void vsync ( void )
```

Waits for the vertical blank interrupt.

This is often used in main loops to idle the CPU until it's time to start the next frame. It's also useful for syncing animation with the screen re-draw.

Warning: If the VBL interrupt is disabled, this function will never return.

HALTs the CPU and waits for the vertical blank interrupt and then returns when all registered VBL ISRs have completed.

This is often used in main loops to idle the CPU at low power until it's time to start the next frame. It's also useful for syncing animation with the screen re-draw.

Warning: If the VBL interrupt is disabled, this function will never return. If the screen is off this function returns immediately.

HALTs the CPU and waits for the vertical blank interrupt.

This is often used in main loops to idle the CPU at low power until it's time to start the next frame. It's also useful for syncing animation with the screen re-draw.

Warning: If the VBL interrupt is disabled, this function will never return. If the screen is off this function returns immediately.

```
20.67.4.21 wait_vbl_done() void wait_vbl_done (
```

Obsolete. This function has been replaced by vsync(), which has identical behavior.

```
20.67.4.22 display_on() void display_on ( void ) Turns the display on.
```

ranno uno anopia,

See also

**DISPLAY\_ON** 

Turns the display off immediately.

See also

```
DISPLAY_ON
```

Turns the display off.

Waits until the VBL before turning the display off.

See also

```
DISPLAY_ON
```

Turns the display off.

See also

**DISPLAY ON** 

```
20.67.4.24 refresh_OAM() void refresh_OAM ( void )
```

Copies data from shadow OAM to OAM

Set byte in vram at given memory location

# **Parameters**

addr	address to write to
V	value

Get address of X,Y tile of background map

Sets palette for 2bpp color translation for GG/SMS, does nothing on GB

Sets VRAM Tile Pattern data for the Background

Writes **nb\_tiles** tiles to VRAM starting at **first\_tile**, tile data is sourced from **data**. Each Tile is 16 bytes in size (8x8 pixels, 2 bits-per-pixel).

Note: Sprite Tiles 128-255 share the same memory region as Background Tiles 128-255.

See also

```
set tile data
```

Sets VRAM Tile Pattern data for the Background / Window

## **Parameters**

first_tile	Index of the first tile to write
nb_tiles	Number of tiles to write
data	Pointer to (2 bpp) source tile data

Writes **nb\_tiles** tiles to VRAM starting at **first\_tile**, tile data is sourced from **data**. Each Tile is 16 bytes in size (8x8 pixels, 2 bits-per-pixel).

Note

Sprite Tiles 128-255 share the same memory region as Background Tiles 128-255.

GBC only: VBK\_REG determines which bank of tile patterns are written to.

- VBK\_REG = VBK\_BANK\_0 indicates the first bank
- VBK\_REG = VBK\_BANK\_1 indicates the second

See also

```
set_win_data, set_tile_data
```

Sets VRAM Tile Pattern data for the Background using 1bpp source data

Similar to set\_bkg\_data, except source data is 1 bit-per-pixel which gets expanded into 2 bits-per-pixel.

For a given bit that represent a pixel:

- · 0 will be expanded into color 0
- 1 will be expanded into color 1, 2 or 3 depending on color argument

See also

```
SHOW_BKG, HIDE_BKG, set_bkg_tiles
```

Sets VRAM Tile Pattern data for the Background / Window using 1bpp source data

## **Parameters**

first_tile	Index of the first Tile to write
nb_tiles	Number of Tiles to write
data	Pointer to (1bpp) source Tile Pattern data

Similar to set\_bkg\_data, except source data is 1 bit-per-pixel which gets expanded into 2 bits-per-pixel. For a given bit that represent a pixel:

- · 0 will be expanded into the Background color
- 1 will be expanded into the Foreground color

See set\_1bpp\_colors for details about setting the Foreground and Background colors.

See also

```
SHOW_BKG, HIDE_BKG, set_bkg_tiles
set_win_1bpp_data, set_sprite_1bpp_data
```

Sets a rectangular region of Background Tile Map.

Entries are copied from map at **tiles** to the Background Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles.

Use set\_bkg\_submap() instead when:

- · Source map is wider than 32 tiles.
- Writing a width that does not match the source map width and more than one row high at a time.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

See also

```
SHOW_BKG
set_bkg_data, set_bkg_submap, set_win_tiles, set_tiles
```

Sets a rectangular region of Background Tile Map.

## **Parameters**

X	X Start position in Background Map tile coordinates. Range 0 - 31
У	Y Start position in Background Map tile coordinates. Range 0 - 31
W	Width of area to set in tiles. Range 1 - 32
h	Height of area to set in tiles. Range 1 - 32
tiles	Pointer to source tile map data

Entries are copied from map at **tiles** to the Background Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles.

Use set bkg submap() instead when:

- · Source map is wider than 32 tiles.
- Writing a width that does not match the source map width and more than one row high at a time.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

Note

Patterns 128-255 overlap with patterns 128-255 of the sprite Tile Pattern table.

GBC only: VBK\_REG determines whether Tile Numbers or Tile Attributes get set.

- VBK\_REG = VBK\_TILES Tile Numbers are written
- VBK REG = VBK ATTRIBUTES Tile Attributes are written

GBC Tile Attributes are defined as:

- Bit 7 Priority flag. When this is set, it puts the tile above the sprites with colour 0 being transparent.
  - 0: Below sprites
  - 1: Above sprites

Note: SHOW\_BKG needs to be set for these priorities to take place.

- Bit 6 Vertical flip. Dictates which way up the tile is drawn vertically.
  - 0: Normal
  - 1: Flipped Vertically
- Bit 5 Horizontal flip. Dictates which way up the tile is drawn horizontally.
  - 0. Normal
  - 1: Flipped Horizontally
- · Bit 4 Not used
- Bit 3 Character Bank specification. Dictates from which bank of Background Tile Patterns the tile is taken.
  - 0: Bank 0
  - 1: Bank 1
- Bit 2 See bit 0.
- Bit 1 See bit 0.
- Bit 0 Bits 0-2 indicate which of the 7 BKG colour palettes the tile is assigned.

## See also

```
SHOW_BKG
set_bkg_data, set_bkg_submap, set_win_tiles, set_tiles
```

Sets a rectangular region of Background Tile Map Attributes.

# **Parameters**

X	X Start position in Background Map tile coordinates. Range 0 - 15
У	Y Start position in Background Map tile coordinates. Range 0 - 14
W	Width of area to set in tiles. Range 1 - 16
h	Height of area to set in tiles. Range 1 - 15
attributes	Pointer to source tile map attribute data

Entries are copied from map at **tiles** to the Background Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles.

NES 16x16 Tile Attributes are tightly packed into 4 attributes per byte, with each 16x16 area of a 32x32 pixel block using the bits as follows: D1-D0: Top-left 16x16 pixels D3-D2: Top-right 16x16 pixels D5-D4: Bottom-left 16x16 pixels D7-D6: Bottom-right 16x16 pixels

```
https://www.nesdev.org/wiki/PPU_attribute_tables
```

See also

```
SHOW_BKG
set_bkg_data, set_bkg_submap_attributes, set_win_tiles, set_tiles
```

Sets a rectangular region of Background Tile Map Attributes.

Entries are copied from map at **tiles** to the Background Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles

Use set\_bkg\_submap\_attributes() instead when:

- · Source map is wider than 32 tiles.
- · Writing a width that does not match the source map width and more than one row high at a time.

One byte per source tile map attribute entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

Please note that this is just a wrapper function for set\_bkg\_attributes\_nes16x16() and divides the coordinates and dimensions by 2 to achieve this. It is intended to make code more portable by using the same coordinate system that systems with the much more common 8x8 attribute resolution would use.

See also

```
SHOW_BKG set_bkg_submap_attributes, set_win_tiles, set_tiles
```

Sets a rectangular area of the Background Tile Map using a sub-region from a source tile map. Useful for scrolling implementations of maps larger than 32 x 30 tiles / 16x15 attributes.

## **Parameters**

X	X Start position in both the Source Attribute Map and hardware Background Map attribute coordinates. Range 0 - 255
У	Y Start position in both the Source Attribute Map and hardware Background Map attribute coordinates. Range 0 - 255
W	Width of area to set in Attributes. Range 1 - 127
h	Height of area to set in Attributes. Range 1 - 127
тар	Pointer to source tile map data
map⇔	Width of source tile map in tiles. Range 1 - 127
_ <i>w</i>	

Entries are copied from **map** to the Background Attribute Map starting at **x**, **y** writing across for **w** tiles and down for **h** attributes, using **map\_w** as the rowstride for the source attribute map.

The **x** and **y** parameters are in Source Attribute Map Attribute coordinates. The location tiles will be written to on the hardware Background Map is derived from those, but only uses the lower 5 bits of each axis, for range of 0-15 (they are bit-masked:  $\times$  &  $0 \times F$  and y &  $0 \times F$ ). As a result the two coordinate systems are aligned together.

In order to transfer tile map data in a way where the coordinate systems are not aligned, an offset from the Source Attribute Map pointer can be passed in:  $(map\_ptr + x + (y * map\_width))$ . For example, if you want the tile id at 1, 2 from the source map to show up at 0, 0 on the hardware Background Map

(instead of at 1, 2) then modify the pointer address that is passed in:  $map\_ptr + 1 + (2 * map\_width)$  Use this instead of set\_bkg\_tiles when the source map is wider than 32 tiles or when writing a width that does not match the source map width.

One byte per source attribute map entry.

Writes that exceed coordinate 15/14 on the x / y axis will wrap around to the Left and Top edges. See set\_bkg\_tiles for setting CGB attribute maps with VBK\_REG.

#### See also

```
SHOW_BKG
set_bkg_data, set_bkg_tiles, set_win_submap, set_tiles
```

Sets a rectangular area of the Background Tile Map attributes using a sub-region from a source tile map. Useful for scrolling implementations of maps larger than 32 x 30 tiles.

Please note that this is just a wrapper function for <a href="set\_bkg\_submap\_attributes\_nes16x16">set\_bkg\_submap\_attributes\_nes16x16</a>() and divides the coordinates and dimensions by 2 to achieve this. It is intended to make code more portable by using the same coordinate system that systems with the much more common 8x8 attribute resolution would use.

## See also

```
SHOW_BKG
set bkg data, set bkg tiles, set win submap, set tiles
```

Sets a rectangular region of Background Tile Map. The offset value in **base\_tile** is added to the tile ID for each map entry.

## **Parameters**

X	X Start position in Background Map tile coordinates. Range 0 - 31
У	Y Start position in Background Map tile coordinates. Range 0 - 31
W	Width of area to set in tiles. Range 1 - 32
h	Height of area to set in tiles. Range 1 - 32
tiles	Pointer to source tile map data
base_tile	Offset each tile ID entry of the source map by this value. Range 1 - 255

This is identical to set\_bkg\_tiles() except that it adds the **base\_tile** parameter for when a tile map's tiles don't start at index zero. (For example, the tiles used by the map range from 100 -> 120 in VRAM instead of 0 -> 20).

#### See also

set bkg tiles for more details

Sets a rectangular area of the Background Tile Map using a sub-region from a source tile map. Useful for scrolling implementations of maps larger than 32 x 32 tiles.

@ param x X Start position in Background Map tile coordinates. Range 0 - 31 @ param y Y Start position in Background Map tile coordinates. Range 0 - 31 @ param w Width of area to set in tiles. Range 1 - 255 @ param h Height of area to set in tiles. Range 1 - 255 @ param map Pointer to source tile map data @ param map\_w Width of source tile map in tiles. Range 1 - 255

Entries are copied from **map** to the Background Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles, using **map\_w** as the rowstride for the source tile map.

Use this instead of set\_bkg\_tiles when the source map is wider than 32 tiles or when writing a width that does not match the source map width.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

See set bkg tiles for setting CGB attribute maps with VBK REG.

# See also

```
SHOW_BKG
set bkg data, set bkg tiles, set win submap, set tiles
```

Sets a rectangular area of the Background Tile Map using a sub-region from a source tile map. Useful for scrolling implementations of maps larger than 32 x 32 tiles.

## **Parameters**

X	X Start position in both the Source Tile Map and hardware Background Map tile coordinates. Range 0 - 255
У	Y Start position in both the Source Tile Map and hardware Background Map tile coordinates. Range 0 - 255
W	Width of area to set in tiles. Range 1 - 255
h	Height of area to set in tiles. Range 1 - 255
тар	Pointer to source tile map data
тар⊷	Width of source tile map in tiles. Range 1 - 255
_W	

Entries are copied from **map** to the Background Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles, using **map\_w** as the rowstride for the source tile map.

The x and y parameters are in Source Tile Map tile coordinates. The location tiles will be written to on the hardware Background Map is derived from those, but only uses the lower 5 bits of each axis, for range of 0-31 (they are bit-masked: x & 0x1F and y & 0x1F). As a result the two coordinate systems are aligned together.

In order to transfer tile map data in a way where the coordinate systems are not aligned, an offset from the Source Tile Map pointer can be passed in:  $(map\_ptr + x + (y * map\_width))$ .

For example, if you want the tile id at 1, 2 from the source map to show up at 0, 0 on the hardware Background Map (instead of at 1, 2) then modify the pointer address that is passed in:  $map\_ptr + 1 + (2 * map\_width)$ 

Use this instead of set\_bkg\_tiles when the source map is wider than 32 tiles or when writing a width that does not match the source map width.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

See set\_bkg\_tiles for setting CGB attribute maps with VBK\_REG.

## See also

```
SHOW_BKG
set_bkg_data, set_bkg_tiles, set_win_submap, set_tiles
```

Sets a rectangular area of the Background Tile Map using a sub-region from a source tile map. The offset value in **base\_tile** is added to the tile ID for each map entry.

#### **Parameters**

X	X Start position in Background Map tile coordinates. Range 0 - 31
У	Y Start position in Background Map tile coordinates. Range 0 - 31
W	Width of area to set in tiles. Range 1 - 255
h	Height of area to set in tiles. Range 1 - 255
тар	Pointer to source tile map data
map_w	Width of source tile map in tiles. Range 1 - 255
base_tile	Offset each tile ID entry of the source map by this value. Range 1 - 255

This is identical to set\_bkg\_submap() except that it adds the **base\_tile** parameter for when a tile map's tiles don't start at index zero. (For example, the tiles used by the map range from 100 -> 120 in VRAM instead of 0 -> 20). See also

set\_bkg\_submap for more details

Copies a rectangular region of Background Tile Map entries into a buffer.

Entries are copied into **tiles** from the Background Tile Map starting at **x**, **y** reading across for **w** tiles and down for **h** tiles

One byte per tile.

The buffer pointed to by **tiles** should be at least **x** x **y** bytes in size.

See also

```
get_bkg_tile_xy, get_tiles
```

Copies a rectangular region of Background Tile Map entries into a buffer.

#### **Parameters**

X	X Start position in Background Map tile coordinates. Range 0 - 31
У	Y Start position in Background Map tile coordinates. Range 0 - 31
W	Width of area to copy in tiles. Range 0 - 31
h	Height of area to copy in tiles. Range 0 - 31
tiles	Pointer to destination buffer for Tile Map data

## Note

In general **avoid reading from VRAM** since that memory is not accessible at all times. It is also not supported by GBDK on the NES platform. See coding guidelines for more details.

Entries are copied into **tiles** from the Background Tile Map starting at **x**, **y** reading across for **w** tiles and down for **h** tiles

One byte per tile.

The buffer pointed to by **tiles** should be at least **x** x **y** bytes in size.

## See also

```
get_win_tiles, get_bkg_tile_xy, get_tiles, get_vram_byte
```

Set single tile t on background layer at x,y

## **Parameters**

Х	X-coordinate
У	Y-coordinate
t	tile index

## Returns

returns the address of tile, so you may use faster set\_vram\_byte() later

Set single attribute data a on background layer at x,y

## **Parameters**

X	X-coordinate
У	Y-coordinate
а	tile attributes

# 20.67.4.43 set\_bkg\_attribute\_xy() void set\_bkg\_attribute\_xy (

```
uint8_t x,
uint8_t y,
uint8_t a) [inline]
```

Set single attribute data a on background layer at x,y

Please note that this is just a wrapper function for set\_bkg\_submap\_attributes\_nes16x16() and divides the coordinates and dimensions by 2 to achieve this. It is intended to make code more portable by using the same coordinate system that systems with the much more common 8x8 attribute resolution would use.

## **Parameters**

Χ	X-coordinate
у	Y-coordinate
а	tile attributes

Get single tile t on background layer at x,y

## **Parameters**

Χ	X-coordinate
У	Y-coordinate

## Returns

returns tile index

Get single tile t on background layer at x,y

# **Parameters**

Χ	X-coordinate
У	Y-coordinate

## Returns

returns tile index

## Note

In general **avoid reading from VRAM** since that memory is not accessible at all times. It is also not supported by GBDK on the NES platform. See coding guidelines for more details.

Moves the Background Layer to the position specified in  ${\bf x}$  and  ${\bf y}$  in pixels.

# **Parameters**

	X axis screen coordinate for Left edge of the Background
У	Y axis screen coordinate for Top edge of the Background

0,0 is the top left corner of the GB screen. The Background Layer wraps around the screen, so when part of it goes off the screen it appears on the opposite side (factoring in the larger size of the Background Layer versus the screen size).

The background layer is always under the Window Layer.

#### See also

```
SHOW BKG, HIDE BKG
```

```
20.67.4.46 scroll_bkg() void scroll_bkg ( int8\_t x, int8\_t y ) [inline]
```

Moves the Background relative to it's current position.

## **Parameters**

Х	Number of pixels to move the Background on the <b>X axis</b> Range: -128 - 127
У	Number of pixels to move the Background on the <b>Y axis</b> Range: -128 - 127

## See also

move\_bkg

Sets VRAM Tile Pattern data for Sprites

Writes **nb\_tiles** tiles to VRAM starting at **first\_tile**, tile data is sourced from **data**. Each Tile is 16 bytes in size (8x8 pixels, 2 bits-per-pixel).

Note: Sprite Tiles 128-255 share the same memory region as Background Tiles 128-255.

GBC only: VBK\_REG determines which bank of tile patterns are written to.

- VBK\_REG=0 indicates the first bank
- · VBK\_REG=1 indicates the second

Sets VRAM Tile Pattern data for Sprites

## **Parameters**

first_tile	Index of the first tile to write
nb_tiles	Number of tiles to write
data	Pointer to (2 bpp) source Tile Pattern data

Writes **nb\_tiles** tiles to VRAM starting at **first\_tile**, tile data is sourced from **data**. Each Tile is 16 bytes in size (8x8 pixels, 2 bits-per-pixel).

Note

Sprite Tiles 128-255 share the same memory region as Background Tiles 128-255.

GBC only: VBK\_REG determines which bank of tile patterns are written to.

• VBK\_REG = VBK\_BANK\_0 indicates the first bank

VBK\_REG = VBK\_BANK\_1 indicates the second

Sets VRAM Tile Pattern data for Sprites using 1bpp source data

Similar to set\_sprite\_data, except source data is 1 bit-per-pixel which gets expanded into 2 bits-per-pixel. For a given bit that represent a pixel:

- · 0 will be expanded into color 0
- 1 will be expanded into color 3

## See also

```
SHOW_SPRITES, HIDE_SPRITES, set_sprite_tile
```

Sets VRAM Tile Pattern data for Sprites using 1bpp source data

#### **Parameters**

first_tile	Index of the first tile to write
nb_tiles	Number of tiles to write
data	Pointer to (1bpp) source Tile Pattern data

Similar to set\_sprite\_data, except source data is 1 bit-per-pixel which gets expanded into 2 bits-per-pixel. For a given bit that represent a pixel:

- · 0 will be expanded into the Background color
- 1 will be expanded into the Foreground color

See set\_1bpp\_colors for details about setting the Foreground and Background colors.

# See also

```
SHOW_SPRITES, HIDE_SPRITES, set_sprite_tile set_bkg_1bpp_data, set_win_1bpp_data
```

```
20.67.4.49 SET_SHADOW_OAM_ADDRESS() void SET_SHADOW_OAM_ADDRESS ( void * address ) [inline]
```

Enable OAM DMA copy each VBlank and set it to transfer any 256-byte aligned array

Sets sprite number nb\_in the OAM to display tile number \_\_tile.

## **Parameters**

nb	Sprite number, range 0 - 63
tile	Selects a tile (0 - 255) from PPU memory at 0000h - 0FFFh / 1000h - 1FFFh

In 8x16 mode:

- The sprite will also display the next tile (tile + 1) directly below (y + 8) the first tile.
- The lower bit of the tile number is ignored: the upper 8x8 tile is (**tile** & 0xFE), and the lower 8x8 tile is (**tile** | 0x01).
- See: SPRITES\_8x16

Sets sprite number **nb\_in** the **OAM** to **display** tile number **\_\_tile**.

## **Parameters**

nb	Sprite number, range 0 - 39
tile	Selects a tile (0 - 255) from memory at 8000h - 8FFFh In CGB Mode this could be either in VRAM Bank 0 or 1, depending on Bit 3 of the OAM Attribute Flag (see set_sprite_prop)

## In 8x16 mode:

- The sprite will also display the next tile (tile + 1) directly below (y + 8) the first tile.
- The lower bit of the tile number is ignored: the upper 8x8 tile is (**tile** & 0xFE), and the lower 8x8 tile is (**tile** | 0x01).
- See: SPRITES 8x16

Returns the tile number of sprite number **nb** in the OAM.

## **Parameters**

```
nb Sprite number, range 0 - 63
```

## See also

set\_sprite\_tile for more details

Returns the tile number of sprite number **nb** in the OAM.

# **Parameters**

```
nb Sprite number, range 0 - 39
```

## See also

set\_sprite\_tile for more details

Sets the OAM Property Flags of sprite number **nb** to those defined in **prop**.

# **Parameters**

nb	Sprite number, range 0 - 39
prop	Property setting (see bitfield description)

# The bits in **prop** represent:

- Bit 7 Vertical flip. Dictates which way up the sprite is drawn vertically.
  - 0: normal
  - 1: upside down
- · Bit 6 Horizontal flip. Dictates which way up the sprite is drawn horizontally.
  - 0: normal
  - 1: back to front
- Bit 5 Priority flag. When this is set, the sprites appear behind the background and window layer.
  - 0: infront
  - 1: behind
- · Bit 4 Unimplemented
- · Bit 3 Unimplemented
- · Bit 2 Unimplemented
- Bit 1 See bit 0.
- Bit 0 Bits 0-1 indicate which color palette the sprite should use. Note: only palettes 4 to 7 will be available
  for NES sprites.

It's recommended to use GBDK constants (eg: S\_FLIPY) to configure sprite properties as these are crossplatform.

```
// Load palette data into the first palette
set_sprite_palette(4, 1, exampleSprite_palettes)
// Set the OAM value for the sprite
// These flags tell the sprite to use the first sprite palette (palette 4) and to flip the sprite both
    vertically and horizontally.
set_sprite_prop(0, S_FLIPY | S_FLIPX);
```

## See also

# S\_PALETTE, S\_FLIPX, S\_FLIPY, S\_PRIORITY

Sets the OAM Property Flags of sprite number **nb** to those defined in **prop**.

## **Parameters**

nb	Sprite number, range 0 - 39	
prop	Property setting (see bitfield description)	

# The bits in **prop** represent:

- Bit 7 Priority flag. When this is set the sprites appear behind the background and window layer.
  - 0: infront
  - 1: behind
- Bit 6 Vertical flip. Dictates which way up the sprite is drawn vertically.
  - 0: normal
  - 1:upside down
- Bit 5 Horizontal flip. Dictates which way up the sprite is drawn horizontally.
  - 0: normal
  - 1:back to front
- Bit 4 DMG/Non-CGB Mode Only. Assigns either one of the two b/w palettes to the sprite.
  - 0: OBJ palette 0
  - 1: OBJ palette 1
- Bit 3 GBC only. Dictates from which bank of Sprite Tile Patterns the tile is taken.
  - 0: Bank 0
  - 1: Bank 1

- Bit 2 See bit 0.
- Bit 1 See bit 0.
- Bit 0 GBC only. Bits 0-2 indicate which of the 7 OBJ colour palettes the sprite is assigned.

It's recommended to use GBDK constants (eg: S FLIPY) to configure sprite properties as these are crossplatform.

```
// Load palette data into the first palette
set_sprite_palette(4, 1, exampleSprite_palettes)
// Set the OAM value for the sprite
// These flags tell the sprite to flip both vertically and horizontally.
set_sprite_prop(0, S_FLIPY | S_FLIPX);
```

#### See also

```
S PALETTE, S FLIPX, S FLIPY, S PRIORITY
```

Function has no affect on sms.

This function is only here to enable game portability

Returns the OAM Property Flags of sprite number **nb**.

## **Parameters**

```
nb | Sprite number, range 0 - 39
```

## See also

set\_sprite\_prop for property bitfield settings

Moves sprite number  $\mathbf{nb}$  to the  $\mathbf{x}$ ,  $\mathbf{y}$  position on the screen.

# **Parameters**

nb	Sprite number, range 0 - 63	
X	X Position. Specifies the sprites horizontal position on the screen (minus 8).	
У	Y Position. Specifies the sprites vertical position on the screen (minus 16).	
	An offscreen value (Y>=240) hides the sprite.	

Moving the sprite to 0,0 (or similar off-screen location) will hide it.

Moves sprite number  $\mathbf{nb}$  to the  $\mathbf{x}$ ,  $\mathbf{y}$  position on the screen.

## **Parameters**

nb	Sprite number, range 0 - 39
X	X Position. Specifies the sprites horizontal position on the screen (minus 8).
	An offscreen value ( $X=0$ or $X>=168$ ) hides the sprite, but the sprite still affects the priority ordering - a
	better way to hide a sprite is to set its Y-coordinate offscreen.
У	Y Position. Specifies the sprites vertical position on the screen (minus 16).
	An offscreen value (for example, Y=0 or Y>=160) hides the sprite.

Moving the sprite to 0,0 (or similar off-screen location) will hide it.

Moves sprite number **nb** relative to its current position.

# **Parameters**

nb	Sprite number, range 0 - 63
Х	Number of pixels to move the sprite on the <b>X axis</b> Range: -128 - 127
У	Number of pixels to move the sprite on the <b>Y axis</b> Range: -128 - 127

## See also

move\_sprite for more details about the X and Y position

Moves sprite number **nb** relative to its current position.

## **Parameters**

nb	Sprite number, range 0 - 39
Х	Number of pixels to move the sprite on the X axis
	Range: -128 - 127
У	Number of pixels to move the sprite on the Y axis
	Range: -128 - 127

## See also

move\_sprite for more details about the X and Y position

# 

Hides sprite number **nb** by moving it to Y position 240.

## **Parameters**

nb	Sprite number, range 0 - 63
----	-----------------------------

Hides sprite number  ${f nb}$  by moving it to zero position by Y.

## **Parameters**

nb	Sprite number, range 0 - 39
----	-----------------------------

## See also

```
hide_sprites_range, HIDE_SPRITES
```

Hides sprite number **nb** by moving it to zero position by Y.

# **Parameters**

nb	Sprite number, range 0 - 39
----	-----------------------------

Copies arbitrary data to an address in VRAM without taking into account the state of LCDC bits 3 or 4. Copies **len** bytes from a buffer at **data** to VRAM starting at **vram\_addr**.

See also

```
set_bkg_data, set_win_data, set_bkg_tiles, set_win_tiles, set_tile_data, set_tiles
```

Sets a rectangular region of Tile Map entries at a given VRAM Address.

#### **Parameters**

X	X Start position in Map tile coordinates. Range 0 - 31
У	Y Start position in Map tile coordinates. Range 0 - 31
W	Width of area to set in tiles. Range 1 - 32
h	Height of area to set in tiles. Range 1 - 32
vram_addr	Pointer to destination VRAM Address
tiles	Pointer to source Tile Map data

Entries are copied from **tiles** to Tile Map at address vram\_addr starting at **x**, **y** writing across for **w** tiles and down for **h** tiles.

One byte per source tile map entry.

There are two 32x30 Tile Maps in VRAM at addresses 2000h-23FFh and 2400h-27FFh.

See also

```
set_bkg_tiles
```

Sets VRAM Tile Pattern data starting from given base address without taking into account the state of PPUMASK.

See also

```
set bkg data, set data
```

Sets VRAM Tile Pattern data for the Background in the native format			

#### **Parameters**

first_tile	Index of the first tile to write
nb_tiles	Number of tiles to write
data	Pointer to source tile data

Writes **nb\_tiles** tiles to VRAM starting at **first\_tile**, tile data is sourced from **data**.

## See also

```
set tile data
```

Sets VRAM Tile Pattern data for the Background / Window in the native format

## **Parameters**

first_tile	irst_tile Index of the first tile to writ	
nb_tiles	Number of tiles to write	
data	Pointer to source tile data	

Writes **nb\_tiles** tiles to VRAM starting at **first\_tile**, tile data is sourced from **data**. GBC only: VBK\_REG determines which bank of tile patterns are written to.

- VBK\_REG = VBK\_BANK\_0 indicates the first bank
- VBK\_REG = VBK\_BANK\_1 indicates the second

## See also

```
set_win_data, set_tile_data
```

Sets VRAM Tile Pattern data for Sprites in the native format

## **Parameters**

first_tile	Index of the first tile to write
nb_tiles	Number of tiles to write
data	Pointer to source tile data

Writes **nb\_tiles** tiles to VRAM starting at **first\_tile**, tile data is sourced from **data**. Sets VRAM Tile Pattern data for Sprites in the native format

## **Parameters**

first_tile	Index of the first tile to write
nb_tiles	Number of tiles to write
data	Pointer to source tile data

Writes **nb\_tiles** tiles to VRAM starting at **first\_tile**, tile data is sourced from **data**. GBC only: VBK\_REG determines which bank of tile patterns are written to.

• VBK\_REG = VBK\_BANK\_0 indicates the first bank

VBK\_REG = VBK\_BANK\_1 indicates the second

Sets VRAM Tile Pattern data in the native format

## **Parameters**

first_tile	Index of the first tile to write (0 - 511)
nb_tiles	Number of tiles to write
data	Pointer to source Tile Pattern data.

When first\_tile is larger than 256 on the GB/AP, it will write to sprite data instead of background data. The bit depth of the source Tile Pattern data depends on which console is being used:

· NES: loads 2bpp tiles data

Initializes the entire Background Tile Map with Tile Number  ${\bf c}$ 

## **Parameters**

```
c Tile number to fill with
```

Note: This function avoids writes during modes 2 & 3 Initializes the entire Background Tile Map with Tile Number **c** 

## **Parameters**

```
c Tile number to fill with
```

## Note

This function avoids writes during modes 2 & 3

Fills the VRAM memory region  ${\boldsymbol s}$  of size  ${\boldsymbol n}$  with Tile Number  ${\boldsymbol c}$ 

## **Parameters**

s	Start address in VRAM
С	Tile number to fill with
n	Size of memory region (in bytes) to fill

Note: This function avoids writes during modes 2 & 3

Fills the VRAM memory region **s** of size **n** with Tile Number **c** 

## **Parameters**

s	Start address in VRAM
С	Tile number to fill with
n	Size of memory region (in bytes) to fill

## Note

This function avoids writes during modes 2 & 3

Fills a rectangular region of Tile Map entries for the Background layer with tile.

## **Parameters**

Х	X Start position in Background Map tile coordinates. Range 0 - 31
У	Y Start position in Background Map tile coordinates. Range 0 - 31
W	Width of area to set in tiles. Range 0 - 31
h	Height of area to set in tiles. Range 0 - 31
tile	Fill value

```
20.67.4.66 flush_shadow_attributes() void flush_shadow_attributes ( void )
```

"Flushes" the updates to the shadow attributes so they are written to the transfer buffer, and then written to PPU memory on next vblank.

This function must be called to see visible changes to attributes on the NES target. But it will automatically be called by vsync(), so the use-cases for calling it manually are rare in practice.

## 20.67.5 Variable Documentation

```
20.67.5.1 _SYSTEM const uint8_t _SYSTEM [extern]
```

```
20.67.5.2 sys_time volatile uint16_t sys_time [extern] Global Time Counter in VBL periods (60Hz) Increments once per Frame
```

Will wrap around every  $\sim$ 18 minutes (unsigned 16 bits = 65535 / 60 / 60 = 18.2)

```
20.67.5.3 _current_bank volatile uint8_t _current_bank [extern]
```

Tracks current active ROM bank

The active bank number is not tracked by \_current\_bank when SWITCH\_ROM\_MBC5\_8M is used.

This variable is updated automatically when you call SWITCH\_ROM\_MBC1 or SWITCH\_ROM\_MBC5, SWITCH\_ROM(), or call a BANKED function.

See also

```
SWITCH ROM MBC1(), SWITCH ROM MBC5(), SWITCH ROM()
```

Tracks current active ROM bank

In most cases the CURRENT\_BANK macro for this variable is recommended for use instead of the variable itself. The active bank number is not tracked by \_current\_bank when SWITCH\_ROM\_MBC5\_8M is used.

This variable is updated automatically when you call SWITCH\_ROM\_MBC1 or SWITCH\_ROM\_MBC5, SWITCH\_ROM(), or call a BANKED function.

See also

```
SWITCH_ROM_MBC1(), SWITCH_ROM_MBC5(), SWITCH_ROM()
```

```
\textbf{20.67.5.4} \quad \underline{\textbf{_current\_1bpp\_colors}} \quad \underline{\textbf{uint16\_t}} \quad \underline{\textbf{_current\_1bpp\_colors}} \quad [\texttt{extern}]
```

```
20.67.5.5 _map_tile_offset uint8_t _map_tile_offset [extern]
```

```
20.67.5.6 _submap_tile_offset uint8_t _submap_tile_offset [extern]
```

**20.67.5.7 shadow\_OAM** volatile struct OAM\_item\_t shadow\_OAM[] [extern] Shadow OAM array in WRAM, that is DMA-transferred into the real OAM each VBlank

```
20.67.5.8 _shadow_OAM_base uint8_t _shadow_OAM_base [extern] MSB of shadow_OAM address is used by OAM DMA copying routine
```

## 20.68 gbdk-lib/include/nes/rgb to nes macro.h File Reference

## **Macros**

• #define RGB\_TO\_NES(c)

# 20.68.1 Macro Definition Documentation

```
20.68.1.1 RGB_TO_NES #define RGB_TO_NES(
```

## 20.69 gbdk-lib/include/rand.h File Reference

```
#include <types.h>
#include <stdint.h>
```

# Macros

- #define RAND MAX 255
- #define RANDW\_MAX 65535

## **Functions**

- void initrand (uint16\_t seed) OLDCALL
- uint8 t rand (void) OLDCALL
- uint16\_t randw (void) OLDCALL
- void initarand (uint16\_t seed) OLDCALL
- · uint8 t arand (void) OLDCALL

## **Variables**

• uint16\_t \_\_rand\_seed

## 20.69.1 Detailed Description

Random generator using the linear congruential method

Author

Luc Van den Borre

## 20.69.2 Macro Definition Documentation

```
20.69.2.1 RAND_MAX #define RAND_MAX 255
```

```
20.69.2.2 RANDW_MAX #define RANDW_MAX 65535
```

## 20.69.3 Function Documentation

```
20.69.3.1 initrand() void initrand ( uint16\_t \ seed )
```

Initalise the pseudo-random number generator.

## **Parameters**

seed The value for initializing the random number generator.

The seed should be different each time, otherwise the same pseudo-random sequence will be generated. One way to do this is sampling (DIV\_REG) up to 2 times (high byte of seed value then the low byte) at variable, non-deterministic points in time (such as when the player presses buttons on the title screen or in a menu). It only needs to be called once to be initialized.

See also

rand(), randw()

```
20.69.3.2 rand() uint8_t rand ( void )
```

Returns a random byte (8 bit) value.

initrand() should be used to initialize the random number generator before using rand()

```
20.69.3.3 randw() uint16_t randw ( void )
```

Returns a random word (16 bit) value.

initrand() should be used to initialize the random number generator before using rand()

Random generator using the linear lagged additive method

#### **Parameters**

```
seed The value for initializing the random number generator.
```

Note: initarand() calls initrand() with the same seed value, and uses rand() to initialize the random generator.

## See also

initrand() for suggestions about seed values, arand()

```
20.69.3.5 arand() uint8_t arand ( void )
```

Returns a random number generated with the linear lagged additive method. initarand() should be used to initialize the random number generator before using arand()

## 20.69.4 Variable Documentation

```
20.69.4.1 __rand_seed uint16_t __rand_seed [extern]
The random number seed is stored in __rand_seed and can be saved and restored if needed.
// Save
some_uint16 = __rand_seed;
...
// Restore
__rand_seed = some_uint16;
```

# 20.70 gbdk-lib/include/setjmp.h File Reference

## **Macros**

- #define SP SIZE 1
- #define BP\_SIZE 0
- #define SPX SIZE 0
- #define BPX\_SIZE SPX\_SIZE
- #define RET SIZE 2
- #define setjmp(jump\_buf) \_\_setjmp(jump\_buf)

# **Typedefs**

• typedef unsigned char jmp\_buf[RET\_SIZE+SP\_SIZE+BP\_SIZE+SPX\_SIZE+BPX\_SIZE]

# **Functions**

- int \_\_setjmp (jmp\_buf) OLDCALL
- \_Noreturn void longjmp (jmp\_buf, int) OLDCALL

# 20.70.1 Macro Definition Documentation

```
20.70.1.1 SP_SIZE #define SP_SIZE 1
20.70.1.2 BP_SIZE #define BP_SIZE 0
20.70.1.3 SPX_SIZE #define SPX_SIZE 0
20.70.1.4 BPX_SIZE #define BPX_SIZE SPX_SIZE
20.70.1.5 RET_SIZE #define RET_SIZE 2
\textbf{20.70.1.6} \quad \textbf{setjmp} \quad \texttt{\#define setjmp} \, (
              jump_buf ) __setjmp(jump_buf)
20.70.2 Typedef Documentation
20.70.2.1 jmp_buf typedef unsigned char jmp_buf[RET_SIZE+SP_SIZE+BP_SIZE+SPX_SIZE+BPX_SIZE]
20.70.3 Function Documentation
20.70.3.1 __setjmp() int __setjmp (
             jmp_buf )
20.70.3.2 longjmp() _Noreturn void longjmp (
             jmp_buf ,
             int )
20.71 gbdk-lib/include/sms/sms.h File Reference
#include <types.h>
#include <stdint.h>
#include <gbdk/version.h>
#include <sms/hardware.h>
Data Structures

    struct joypads_t

Macros
   • #define SEGA
   • #define SYSTEM_60HZ 0x00
   • #define SYSTEM 50HZ 0x01

    #define VBK_REG VDP_ATTR_SHIFT

    #define J_UP 0b00000001
```

• #define J DOWN 0b00000010

- #define J LEFT 0b00000100
- #define J RIGHT 0b00001000
- #define J\_B 0b00010000
- #define J A 0b00100000
- #define J START 0b01000000
- #define J SELECT 0b10000000
- #define M TEXT OUT 0x02U
- #define M\_TEXT\_INOUT 0x03U
- #define M\_NO\_SCROLL 0x04U
- #define M NO INTERP 0x08U
- #define S\_BANK 0x01U
- #define S FLIPX 0x02U
- #define S\_FLIPY 0x04U
- #define S PALETTE 0x08U
- #define S\_PRIORITY 0x10U
- #define S PAL(n) (((n) & 0x01U) << 3)
- #define \_\_WRITE\_VDP\_REG\_UNSAFE(REG, v) shadow\_##REG=(v),VDP\_CMD=(shadow\_##REG),VDP
   CMD=REG
- #define \_\_WRITE\_VDP\_REG(REG, v) shadow\_##REG=(v);\_asm\_\_("di");VDP\_CMD=(shadow\_\(\infty\) ##REG);VDP\_CMD=REG;\_asm\_\_("ei")
- #define \_\_READ\_VDP\_REG(REG) shadow\_##REG
- #define EMPTY IFLAG 0x00U
- #define VBL IFLAG 0x01U
- #define LCD IFLAG 0x02U
- #define TIM\_IFLAG 0x04U
- #define SIO\_IFLAG 0x08U
- #define JOY IFLAG 0x10U
- #define SCREENWIDTH DEVICE SCREEN PX WIDTH
- #define SCREENHEIGHT DEVICE SCREEN PX HEIGHT
- #define MINWNDPOSX 0x00U
- #define MINWNDPOSY 0x00U
- #define MAXWNDPOSX 0x00U
- #define MAXWNDPOSY 0x00U
- #define DISPLAY\_ON \_\_WRITE\_VDP\_REG(VDP\_R1, \_\_READ\_VDP\_REG(VDP\_R1) |= R1\_DISP\_ON)
- #define DISPLAY\_OFF display\_off();
- #define HIDE LEFT COLUMN WRITE VDP REG(VDP R0, READ VDP REG(VDP R0) |= R0 LCB)
- #define SHOW\_LEFT\_COLUMN \_\_WRITE\_VDP\_REG(VDP\_R0, \_\_READ\_VDP\_REG(VDP\_R0) &= (~R0 LCB))
- #define SET\_BORDER\_COLOR(C) \_\_WRITE\_VDP\_REG(VDP\_R7, ((C) | 0xf0u))
- #define SHOW BKG
- #define HIDE\_BKG
- #define SHOW WIN
- #define HIDE WIN
- #define SHOW\_SPRITES (\_sprites\_OFF = 0)
- #define HIDE\_SPRITES (\_sprites\_OFF = 1)
- #define SPRITES\_8x16 \_\_WRITE\_VDP\_REG(VDP\_R1, \_\_READ\_VDP\_REG(VDP\_R1) |= R1\_SPR\_8X16)
- #define SPRITES\_8x8 \_\_WRITE\_VDP\_REG(VDP\_R1, \_\_READ\_VDP\_REG(VDP\_R1) &= (~R1\_SPR\_8X16))
- #define DEVICE SUPPORTS COLOR (TRUE)
- #define DIV\_REG get\_r\_reg()
- #define \_current\_bank MAP\_FRAME1
- #define CURRENT\_BANK MAP\_FRAME1
- #define BANK(VARNAME) ( (uint8\_t) & \_\_bank\_ ## VARNAME )
- #define BANKREF(VARNAME)
- #define BANKREF\_EXTERN(VARNAME) extern const void \_\_bank\_ ## VARNAME;
- #define SWITCH\_ROM(b) MAP\_FRAME1=(b)

- #define SWITCH ROM1 SWITCH ROM
- #define SWITCH\_ROM2(b) MAP\_FRAME2=(b)
- #define SWITCH RAM(b) RAM CONTROL=((b)&1)?RAM CONTROL|RAMCTL BANK:RAM CONTROL&(~RAMCTL BANK)
- #define ENABLE RAM RAM CONTROL = RAMCTL RAM
- #define DISABLE\_RAM RAM\_CONTROL&=(~RAMCTL\_RAM)
- #define set\_bkg\_palette\_entry set\_palette\_entry
- #define set\_sprite\_palette\_entry(palette, entry, rgb\_data) set\_palette\_entry(1,entry,rgb\_data)
- · #define set bkg palette set palette
- #define set sprite palette(first palette, nb palettes, rgb data) set palette(1,1,rgb data)
- #define COMPAT\_PALETTE(C0, C1, C2, C3) (((uint16\_t)(C3) << 12) | ((uint16\_t)(C2) << 8) | ((uint16\_t)(C1) << 4) | (uint16\_t)(C0))
- #define set\_bkg\_tiles set\_tile\_map\_compat
- · #define set\_win\_tiles set\_tile\_map\_compat
- #define fill\_bkg\_rect fill\_rect\_compat
- · #define fill win rect fill rect compat
- #define DISABLE\_VBL\_TRANSFER \_shadow\_OAM\_base = 0
- #define ENABLE\_VBL\_TRANSFER \_shadow\_OAM\_base = (uint8\_t)((uint16\_t)&shadow\_OAM >> 8)
- #define MAX\_HARDWARE\_SPRITES 64
- #define HARDWARE\_SPRITE\_CAN\_FLIP\_X 0
- #define HARDWARE SPRITE CAN FLIP Y 0
- #define set\_bkg\_tile\_xy set\_tile\_xy
- #define set\_win\_tile\_xy set\_tile\_xy
- #define set\_bkg\_attribute\_xy set\_attribute\_xy
- #define set\_win\_attribute\_xy set\_attribute\_xy
- #define get\_win\_xy\_addr get\_bkg\_xy\_addr

## **Typedefs**

typedef void(\* int\_handler) (void) NONBANKED

## **Functions**

- void WRITE VDP CMD (uint16 t cmd) Z88DK FASTCALL PRESERVES REGS(b
- void WRITE\_VDP\_DATA (uint16\_t data) Z88DK\_FASTCALL PRESERVES\_REGS(b
- void mode (uint8\_t m) OLDCALL
- uint8\_t get\_mode (void) OLDCALL
- uint8\_t get\_system (void)
- void set\_interrupts (uint8\_t flags) Z88DK\_FASTCALL
- void remove\_VBL (int\_handler h) Z88DK\_FASTCALL PRESERVES\_REGS(iyh
- void remove\_LCD (int\_handler h) Z88DK\_FASTCALL PRESERVES\_REGS(b
- · void remove TIM (int handler h) Z88DK FASTCALL
- void remove\_SIO (int\_handler h) Z88DK\_FASTCALL
- void remove\_JOY (int\_handler h) Z88DK\_FASTCALL
- · void add VBL (int handler h) Z88DK FASTCALL PRESERVES REGS(d
- void add\_LCD (int\_handler h) Z88DK\_FASTCALL PRESERVES\_REGS(b)
- void add TIM (int handler h) Z88DK FASTCALL
- void add\_SIO (int\_handler h) Z88DK\_FASTCALL
- · void add JOY (int handler h) Z88DK FASTCALL
- uint8\_t cancel\_pending\_interrupts (void)
- void move\_bkg (uint8\_t x, uint8\_t y)
- void scroll bkg (int8 t x, int8 t y)
- void vsync (void) PRESERVES\_REGS(b
- void wait\_vbl\_done (void) PRESERVES\_REGS(b
- void display off (void)
- void refresh\_OAM (void)

- uint8\_t get\_r\_reg (void) PRESERVES\_REGS(b
- void delay (uint16\_t d) Z88DK\_FASTCALL
- uint8\_t joypad (void) OLDCALL PRESERVES\_REGS(b
- uint8 t waitpad (uint8 t mask) Z88DK FASTCALL PRESERVES REGS(d
- · void waitpadup (void) PRESERVES REGS(d
- uint8\_t joypad\_init (uint8\_t npads, joypads\_t \*joypads) Z88DK\_CALLEE
- void joypad\_ex (joypads\_t \*joypads) Z88DK\_FASTCALL PRESERVES\_REGS(iyh
- void enable\_interrupts (void) PRESERVES\_REGS(a
- · void disable interrupts (void) PRESERVES REGS(a
- void set default palette (void)
- void cgb compatibility (void)
- void cpu\_fast (void)
- void set\_palette\_entry (uint8\_t palette, uint8\_t entry, uint16\_t rgb\_data) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- void set\_palette (uint8\_t first\_palette, uint8\_t nb\_palettes, const palette\_color\_t \*rgb\_data) Z88DK\_CALLEE
- void set native tile data (uint16 t start, uint16 t ntiles, const void \*src) PRESERVES REGS(iyh
- void set\_bkg\_4bpp\_data (uint16\_t start, uint16\_t ntiles, const void \*src) PRESERVES\_REGS(iyh
- void set\_bkg\_native\_data (uint16\_t start, uint16\_t ntiles, const void \*src) PRESERVES\_REGS(iyh
- void set\_sprite\_4bpp\_data (uint8\_t start, uint16\_t ntiles, const void \*src) PRESERVES\_REGS(iyh
- void set\_sprite\_native\_data (uint8\_t start, uint16\_t ntiles, const void \*src) PRESERVES\_REGS(iyh
- void set 2bpp palette (uint16 t palette)
- void set\_tile\_2bpp\_data (uint16\_t start, uint16\_t ntiles, const void \*src, uint16\_t palette) Z88DK\_CALLEE PRESERVES REGS(iyh
- void set\_bkg\_data (uint16\_t start, uint16\_t ntiles, const void \*src)
- void set sprite data (uint16 t start, uint16 t ntiles, const void \*src)
- void set\_bkg\_2bpp\_data (uint16\_t start, uint16\_t ntiles, const void \*src)
- void set sprite 2bpp data (uint16 t start, uint16 t ntiles, const void \*src)
- void set 1bpp colors (uint8 t fgcolor, uint8 t bgcolor)
- void set\_tile\_1bpp\_data (uint16\_t start, uint16\_t ntiles, const void \*src, uint16\_t colors) Z88DK\_CALLEE PRESERVES REGS(iyh
- void set\_bkg\_1bpp\_data (uint16\_t start, uint16\_t ntiles, const void \*src)
- void set\_sprite\_1bpp\_data (uint16\_t start, uint16\_t ntiles, const void \*src)
- void set\_data (uint16\_t dst, const void \*src, uint16\_t size) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- void vmemcpy (uint16 t dst, const void \*src, uint16 t size) Z88DK CALLEE PRESERVES REGS(iyh
- void set tile map (uint8 t x, uint8 t y, uint8 t w, uint8 t h, const uint8 t \*tiles) Z88DK CALLEE
- void set tile map compat (uint8 t x, uint8 t y, uint8 t w, uint8 t h, const uint8 t \*tiles) Z88DK CALLEE
- void set\_bkg\_based\_tiles (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*tiles, uint8\_t base\_tile)
- void set\_win\_based\_tiles (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*tiles, uint8\_t base\_tile)
- void set bkg attributes (uint8 t x, uint8 t y, uint8 t w, uint8 t h, const uint8 t \*tiles)
- void set\_tile\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, uint8\_t map\_w, const uint8\_t \*map) Z88DK CALLEE
- void set\_tile\_submap\_compat (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, uint8\_t map\_w, const uint8\_t \*map)
   Z88DK CALLEE
- void set\_bkg\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w)
- void set\_win\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w)
- void set\_bkg\_based\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w, uint8\_t base\_tile)
- void set\_win\_based\_submap (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint8\_t \*map, uint8\_t map\_w, uint8\_t base\_tile)
- void set bkg submap attributes (uint8 t x, uint8 t y, uint8 t w, uint8 t h, const uint8 t \*map, uint8 t map w)
- void fill\_rect (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint16\_t tile) Z88DK\_CALLEE
- void fill\_rect\_compat (uint8\_t x, uint8\_t y, uint8\_t w, uint8\_t h, const uint16\_t tile) Z88DK\_CALLEE
- void SET SHADOW OAM ADDRESS (void \*address)
- void set\_sprite\_tile (uint8\_t nb, uint8\_t tile)
- uint8 t get sprite tile (uint8 t nb)
- void set\_sprite\_prop (uint8\_t nb, uint8\_t prop)

- uint8\_t get\_sprite\_prop (uint8\_t nb)
- void move\_sprite (uint8\_t nb, uint8\_t x, uint8\_t y)
- void scroll\_sprite (uint8\_t nb, int8\_t x, int8\_t y)
- void hide\_sprite (uint8\_t nb)
- void set\_vram\_byte (uint8\_t \*addr, uint8\_t v) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- uint8\_t \* set\_attributed\_tile\_xy (uint8\_t x, uint8\_t y, uint16\_t t) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- uint8\_t \* set\_tile\_xy (uint8\_t x, uint8\_t y, uint8\_t t) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- uint8\_t \* set\_attribute\_xy (uint8\_t x, uint8\_t y, uint8\_t a) Z88DK\_CALLEE PRESERVES\_REGS(iyh
- uint8\_t \* get\_bkg\_xy\_addr (uint8\_t x, uint8\_t y) Z88DK\_CALLEE PRESERVES\_REGS(iyh

#### **Variables**

- const UBYTE BIOS
- const uint8\_t \_SYSTEM
- void c
- void d
- void e
- void iyh
- void iyl
- void h
- void I
- volatile uint16\_t sys\_time
- void b
- · uint16 t current 2bpp palette
- uint16\_t \_current\_1bpp\_colors
- · uint8\_t \_map\_tile\_offset
- uint8\_t \_submap\_tile\_offset
- volatile uint8\_t shadow\_OAM []
- · volatile uint8 t shadow OAM base
- volatile uint8\_t \_shadow\_OAM\_OFF
- volatile uint8\_t \_sprites\_OFF

## 20.71.1 Detailed Description

SMS/GG specific functions.

## 20.71.2 Macro Definition Documentation

```
20.71.2.1 SEGA #define SEGA
```

20.71.2.2 SYSTEM 60HZ #define SYSTEM\_60HZ 0x00

20.71.2.3 SYSTEM\_50HZ #define SYSTEM\_50HZ 0x01

20.71.2.4 VBK\_REG #define VBK\_REG VDP\_ATTR\_SHIFT

mode()

```
20.71.2.5 J_UP #define J_UP 0b00000001
Joypad bits. A logical OR of these is used in the wait_pad and joypad functions. For example, to see if the B button
is pressed try
uint8_t keys; keys = joypad(); if (keys & J_B) { ... }
See also
     joypad
20.71.2.6 J_DOWN #define J_DOWN 0b00000010
20.71.2.7 J_LEFT #define J_LEFT 0b00000100
20.71.2.8 J_RIGHT #define J_RIGHT 0b00001000
20.71.2.9 J_B #define J_B 0b00010000
20.71.2.10 J_A #define J_A 0b00100000
20.71.2.11 J_START #define J_START 0b01000000
20.71.2.12 J_SELECT #define J_SELECT 0b10000000
20.71.2.13 M_TEXT_OUT #define M_TEXT_OUT 0x02U
Screen modes. Normally used by internal functions only.
See also
     mode()
\textbf{20.71.2.14} \quad \textbf{M\_TEXT\_INOUT} \quad \texttt{\#define} \quad \texttt{M\_TEXT\_INOUT} \quad \texttt{0x03U}
20.71.2.15 M_NO_SCROLL #define M_NO_SCROLL 0x04U
Set this in addition to the others to disable scrolling
If scrolling is disabled, the cursor returns to (0,0)
See also
     mode()
20.71.2.16 M_NO_INTERP #define M_NO_INTERP 0x08U
Set this to disable interpretation
See also
```

```
20.71.2.17 S_BANK #define S_BANK 0x01U The nineth bit of the tile id
```

**20.71.2.18 S\_FLIPX** #define S\_FLIPX 0x02U If set the background tile will be flipped horizontally.

**20.71.2.19 S\_FLIPY** #define S\_FLIPY 0x04U If set the background tile will be flipped vertically.

**20.71.2.20 S\_PALETTE** #define S\_PALETTE 0x08U If set the background tile palette.

**20.71.2.21 S\_PRIORITY** #define S\_PRIORITY 0x10U If set the background tile priority.

Dummy function used by other platforms. Required for the png2asset tool's metasprite output.

```
20.71.2.25 __READ_VDP_REG #define __READ_VDP_REG(

REG ) shadow_##REG
```

20.71.2.26 EMPTY\_IFLAG #define EMPTY\_IFLAG 0x00U Disable calling of interrupt service routines

**20.71.2.27 VBL\_IFLAG** #define VBL\_IFLAG 0x01U VBlank Interrupt occurs at the start of the vertical blank. During this period the video ram may be freely accessed.

See also

```
set_interrupts(),
add_VBL
```

**20.71.2.28 LCD\_IFLAG** #define LCD\_IFLAG 0x02U LCD Interrupt when triggered by the STAT register.

See also

```
set_interrupts(),
add_LCD
```

```
20.71.2.29 TIM_IFLAG #define TIM_IFLAG 0x04U
Does nothing on SMS/GG
20.71.2.30 SIO_IFLAG #define SIO_IFLAG 0x08U
Does nothing on SMS/GG
20.71.2.31 JOY_IFLAG #define JOY_IFLAG 0x10U
Does nothing on SMS/GG
20.71.2.32 SCREENWIDTH #define SCREENWIDTH DEVICE_SCREEN_PX_WIDTH
Width of the visible screen in pixels.
20.71.2.33 SCREENHEIGHT #define SCREENHEIGHT DEVICE_SCREEN_PX_HEIGHT
Height of the visible screen in pixels.
20.71.2.34 MINWNDPOSX #define MINWNDPOSX 0x00U
The Minimum X position of the Window Layer (Left edge of screen)
See also
     move_win()
20.71.2.35 MINWNDPOSY #define MINWNDPOSY 0x00U
The Minimum Y position of the Window Layer (Top edge of screen)
See also
     move_win()
20.71.2.36 MAXWNDPOSX #define MAXWNDPOSX 0x00U
The Maximum X position of the Window Layer (Right edge of screen)
See also
     move_win()
20.71.2.37 MAXWNDPOSY #define MAXWNDPOSY 0x00U
The Maximum Y position of the Window Layer (Bottom edge of screen)
See also
     move_win()
20.71.2.38 DISPLAY_ON #define DISPLAY_ON ___WRITE_VDP_REG(VDP_R1, ___READ_VDP_REG(VDP_R1) |=
R1_DISP_ON)
Turns the display back on.
See also
     display_off, DISPLAY_OFF
```

```
20.71.2.39 DISPLAY_OFF #define DISPLAY_OFF display_off();
Turns the display off immediately.
See also
     display off, DISPLAY ON
20.71.2.40 HIDE_LEFT_COLUMN #define HIDE_LEFT_COLUMN __WRITE_VDP_REG(VDP_R0, __READ_VDP_REG(VDP_R0)
|= R0_LCB)
Blanks leftmost column, so it is not garbaged when you use horizontal scroll
See also
     SHOW_LEFT_COLUMN
20.71.2.41 SHOW_LEFT_COLUMN #define SHOW_LEFT_COLUMN __WRITE_VDP_REG(VDP_R0, __READ_VDP_REG(VDP_R0)
&= (\sim R0\_LCB))
Shows leftmost column
See also
     HIDE_LEFT_COLUMN
20.71.2.42 SET_BORDER_COLOR #define SET_BORDER_COLOR(
              C) __WRITE_VDP_REG(VDP_R7, ((C) | 0xf0u))
Sets border color
20.71.2.43 SHOW BKG #define SHOW_BKG
Turns on the background layer. Not yet implemented
20.71.2.44 HIDE_BKG #define HIDE_BKG
Turns off the background layer. Not yet implemented
20.71.2.45 SHOW_WIN #define SHOW_WIN
Turns on the window layer Not yet implemented
20.71.2.46 HIDE_WIN #define HIDE_WIN
Turns off the window layer. Not yet implemented
20.71.2.47 SHOW_SPRITES #define SHOW_SPRITES (_sprites_OFF = 0)
Turns on the sprites layer.
20.71.2.48 HIDE SPRITES #define HIDE_SPRITES (_sprites_OFF = 1)
Turns off the sprites layer.
20.71.2.49 SPRITES_8x16 #define SPRITES_8x16 __WRITE_VDP_REG(VDP_R1, __READ_VDP_REG(VDP_R1)
|= R1_SPR_8X16)
Sets sprite size to 8x16 pixels, two tiles one above the other.
20.71.2.50 SPRITES_8x8 #define SPRITES_8x8 __WRITE_VDP_REG(VDP_R1, __READ_VDP_REG(VDP_R1) &=
(∼R1_SPR_8X16))
Sets sprite size to 8x8 pixels, one tile.
```

20.71.2.51 DEVICE\_SUPPORTS\_COLOR #define DEVICE\_SUPPORTS\_COLOR (TRUE)

Macro returns TRUE if device supports color (it always does on SMS/GG)

```
20.71.2.52 DIV_REG #define DIV_REG get_r_reg()
```

20.71.2.53 \_current\_bank #define \_current\_bank MAP\_FRAME1

Tracks current active ROM bank in frame 1

20.71.2.54 CURRENT\_BANK #define CURRENT\_BANK MAP\_FRAME1

```
20.71.2.55 BANK #define BANK(
```

```
VARNAME ) ( (uint8_t) & __bank_ ## VARNAME )
```

Obtains the bank number of VARNAME

#### **Parameters**

VARNAME	Name of the variable which has ab	ank_VARNAME companion symbol which is adjusted by
	bankpack	

Use this to obtain the bank number from a bank reference created with BANKREF().

See also

BANKREF\_EXTERN(), BANKREF()

```
20.71.2.56 BANKREF #define BANKREF(
```

VARNAME )

#### Value:

```
void __func_ ## VARNAME(void) __banked __naked { \
   _asm \
        .local b___func_ ## VARNAME \
        __bank_ ## VARNAME = b___func_ ## VARNAME \
        .globl ___bank_ ## VARNAME \
   __endasm; \
}
```

Creates a reference for retrieving the bank number of a variable or function

#### **Parameters**

VARNAME Variable name to use, which may be an existing identifier

See also

BANK() for obtaining the bank number of the included data.

More than one BANKREF () may be created per file, but each call should always use a unique VARNAME. Use BANKREF\_EXTERN() within another source file to make the variable and it's data accesible there.

```
20.71.2.57 BANKREF_EXTERN #define BANKREF_EXTERN(
```

```
VARNAME ) extern const void __bank_ ## VARNAME;
```

Creates extern references for accessing a BANKREF() generated variable.

#### **Parameters**

<i>VARNAME</i>	Name of the variable used with BANKREF()
----------------	------------------------------------------

This makes a BANKREF() reference in another source file accessible in the current file for use with BANK().

See also

BANKREF(), BANK()

```
\textbf{20.71.2.58} \quad \textbf{SWITCH\_ROM} \quad \texttt{\#define SWITCH\_ROM()}
```

b ) MAP\_FRAME1=(b)

Makes switch the active ROM bank in frame 1

**Parameters** 

b ROM bank to switch to

```
20.71.2.59 SWITCH_ROM1 #define SWITCH_ROM1 SWITCH_ROM
```

```
\textbf{20.71.2.60} \quad \textbf{SWITCH\_ROM2} \quad \texttt{\#define SWITCH\_ROM2} \, (
```

b ) MAP\_FRAME2=(b)

Makes switch the active ROM bank in frame 2

**Parameters** 

b ROM bank to switch to

```
20.71.2.61 SWITCH_RAM #define SWITCH_RAM(
```

b ) RAM\_CONTROL=((b)&1)?RAM\_CONTROL|RAMCTL\_BANK:RAM\_CONTROL&( $\sim$ RAMCTL\_BANK)

Switches RAM bank

**Parameters** 

b | SRAM bank to switch to

```
20.71.2.62 ENABLE_RAM #define ENABLE_RAM RAM_CONTROL|=RAMCTL_RAM
```

**Enables RAM** 

```
\textbf{20.71.2.63} \quad \textbf{DISABLE\_RAM} \quad \texttt{\#define DISABLE\_RAM RAM\_CONTROL} \&= (\sim \texttt{RAMCTL\_RAM})
```

Disables RAM

```
20.71.2.64 set_bkg_palette_entry #define set_bkg_palette_entry set_palette_entry
```

```
20.71.2.65 set_sprite_palette_entry #define set_sprite_palette_entry(
```

```
palette,
entry,
rgb_data ) set_palette_entry(1,entry,rgb_data)
```

```
20.71.2.66 set_bkg_palette #define set_bkg_palette set_palette
20.71.2.67 set_sprite_palette #define set_sprite_palette(
              first_palette,
              nb_palettes,
              rgb_data ) set_palette(1,1,rgb_data)
20.71.2.68 COMPAT_PALETTE #define COMPAT_PALETTE(
              CO,
              C1,
              C2.
              C3) (((uint16_t)(C3) << 12) | ((uint16_t)(C2) << 8) | ((uint16_t)(C1) << 4) |
(uint16_t)(C0))
20.71.2.69 set_bkg_tiles #define set_bkg_tiles set_tile_map_compat
20.71.2.70 set_win_tiles #define set_win_tiles set_tile_map_compat
20.71.2.71 fill_bkg_rect #define fill_bkg_rect fill_rect_compat
20.71.2.72 fill_win_rect #define fill_win_rect fill_rect_compat
20.71.2.73 DISABLE_VBL_TRANSFER #define DISABLE_VBL_TRANSFER __shadow_OAM_base = 0
Disable shadow OAM to VRAM copy on each VBlank
20.71.2.74 ENABLE_VBL_TRANSFER #define ENABLE_VBL_TRANSFER _shadow_OAM_base = (uint8_t)((uint16_t)&shadow_OAM_base = (uint8_t)((uint16_t)&shadow_OAM_base)
>> 8)
Enable shadow OAM to VRAM copy on each VBlank
20.71.2.75 MAX_HARDWARE_SPRITES #define MAX_HARDWARE_SPRITES 64
Amount of hardware sprites in OAM
20.71.2.76 HARDWARE_SPRITE_CAN_FLIP_X #define HARDWARE_SPRITE_CAN_FLIP_X 0
True if sprite hardware can flip sprites by X (horizontally)
20.71.2.77 HARDWARE_SPRITE_CAN_FLIP_Y #define HARDWARE_SPRITE_CAN_FLIP_Y 0
True if sprite hardware can flip sprites by Y (vertically)
20.71.2.78 set_bkg_tile_xy #define set_bkg_tile_xy set_tile_xy
20.71.2.79 set_win_tile_xy #define set_win_tile_xy set_tile_xy
20.71.2.80 set_bkg_attribute_xy #define set_bkg_attribute_xy set_attribute_xy
```

```
20.71.2.81 set_win_attribute_xy #define set_win_attribute_xy set_attribute_xy
20.71.2.82 get_win_xy_addr #define get_win_xy_addr get_bkg_xy_addr
20.71.3 Typedef Documentation
20.71.3.1 int_handler typedef void(* int_handler) (void) NONBANKED
Interrupt handlers
20.71.4 Function Documentation
20.71.4.1 WRITE_VDP_CMD() void WRITE_VDP_CMD (
              uint16_t cmd )
20.71.4.2 WRITE_VDP_DATA() void WRITE_VDP_DATA (
              uint16_t data )
20.71.4.3 \quad mode() \quad void \; mode \; (
              uint8_t m )
Set the current screen mode - one of M_* modes
Normally used by internal functions only.
See also
     M_TEXT_OUT, M_TEXT_INOUT, M_NO_SCROLL, M_NO_INTERP
20.71.4.4 get_mode() uint8_t get_mode (
              void )
Returns the current mode
See also
     M_TEXT_OUT, M_TEXT_INOUT, M_NO_SCROLL, M_NO_INTERP
Returns the current mode
See also
     M_DRAWING, M_TEXT_OUT, M_TEXT_INOUT, M_NO_SCROLL, M_NO_INTERP
\textbf{20.71.4.5} \quad \textbf{get\_system()} \quad \texttt{uint8\_t} \;\; \texttt{get\_system ()}
              void ) [inline]
Returns the system gbdk is running on.
20.71.4.6 set_interrupts() void set_interrupts (
              uint8_t flags )
Clears any pending interrupts and sets the interrupt mask register IO to flags.
```

```
Parameters
```

```
flags A logical OR of *_IFLAGS
```

Note

This disables and then re-enables interrupts so it must be used outside of a critical section.

```
See also
```

```
enable_interrupts(), disable_interrupts()
VBL_IFLAG, LCD_IFLAG, TIM_IFLAG, SIO_IFLAG, JOY_IFLAG
```

```
20.71.4.7 remove_VBL() void remove_VBL (
          int_handler h )
```

Removes the VBL interrupt handler.

See also

add\_VBL()

```
20.71.4.8 remove_LCD() void remove_LCD (
          int_handler h )
```

Removes the LCD interrupt handler.

See also

```
add_LCD(), remove_VBL()
```

**20.71.4.11** remove\_JOY() void remove\_JOY ( 
$$int_handler h$$
 )

Adds a V-blank interrupt handler.

Adds a LCD interrupt handler.

Does nothing on SMS/GG

```
20.71.4.15 add_SIO() void add_SIO (
              int_handler h )
Does nothing on SMS/GG
20.71.4.16 add JOY() void add_JOY (
              int_handler h )
Does nothing on SMS/GG
20.71.4.17 cancel_pending_interrupts() uint8_t cancel_pending_interrupts (
              void ) [inline]
Cancel pending interrupts
\textbf{20.71.4.18} \quad \textbf{move\_bkg()} \quad \texttt{void move\_bkg ()}
              uint8_t x,
              uint8_t y ) [inline]
20.71.4.19 scroll_bkg() void scroll_bkg (
              int8_t x,
              int8_t y ) [inline]
20.71.4.20 vsync() void vsync (
              void )
HALTs the CPU and waits for the vertical blank interrupt.
```

This is often used in main loops to idle the CPU at low power until it's time to start the next frame. It's also useful for syncing animation with the screen re-draw.

Warning: If the VBL interrupt is disabled, this function will never return. If the screen is off this function returns immediately.

```
20.71.4.21 wait_vbl_done() void wait_vbl_done (
```

Obsolete. This function has been replaced by vsync(), which has identical behavior.

```
20.71.4.22 display_off() void display_off (
              void ) [inline]
Turns the display off.
```

See also

**DISPLAY ON** 

```
20.71.4.23 refresh_OAM() void refresh_OAM (
             void )
```

Copies data from shadow OAM to OAM

```
\textbf{20.71.4.24} \quad \textbf{get\_r\_reg()} \quad \texttt{uint8\_t} \quad \texttt{get\_r\_reg} \ (
                             void )
```

Return R register for the DIV\_REG emulation

Increments once per CPU instruction (fetches the Z80 CPU R register)

```
20.71.4.25 delay() void delay (
             uint16_t d )
```

Delays the given number of milliseconds. Uses no timers or interrupts, and can be called with interrupts disabled

```
20.71.4.26 joypad() uint8_t joypad ( void )
```

Reads and returns the current state of the joypad.

Waits until at least one of the buttons given in mask are pressed.

```
20.71.4.28 waitpadup() void waitpadup ( void )
```

Waits for the directional pad and all buttons to be released.

Note: Checks in a loop that doesn't HALT at all, so the CPU will be maxed out until this call returns.

Initializes joypads\_t structure for polling multiple joypads

## **Parameters**

npads	number of joypads requested (1, 2 or 4)
joypads	pointer to joypads_t structure to be initialized

Only required for joypad\_ex, not required for calls to regular joypad()

### Returns

number of joypads avaliable

#### See also

```
joypad_ex(), joypads_t
```

Polls all avaliable joypads

#### **Parameters**

joypads	pointer to joypads_t structure to be filled with joypad statuses, must be previously initialized with
	joypad_init()

#### See also

```
joypad_init(), joypads_t
```

Enables unmasked interrupts

### Note

Use CRITICAL {...} instead for creating a block of of code which should execute with interrupts temporarily turned off.

See also

disable\_interrupts, set\_interrupts, CRITICAL

Disables interrupts

Note

Use CRITICAL {...} instead for creating a block of of code which should execute with interrupts temporarily turned off.

This function may be called as many times as you like; however the first call to enable\_interrupts will re-enable them.

See also

enable\_interrupts, set\_interrupts, CRITICAL

Obsolete. This function has been replaced by set\_default\_palette(), which has identical behavior.

```
20.71.4.35 cpu_fast() void cpu_fast ( void ) [inline]
```

Set CPU speed to fast (CGB Double Speed) operation.

On startup the CGB operates in Normal Speed Mode and can be switched into Double speed mode (faster processing but also higher power consumption). See the Pan Docs for more information about which hardware features operate faster and which remain at Normal Speed.

- · Interrupts are temporarily disabled and then re-enabled during this call.
- You can check to see if <u>cpu</u> == CGB\_TYPE before using this function.

See also

```
cpu_slow(), _cpu
```

Set color palette(s)

const palette\_color\_t \* rgb\_data )

#### **Parameters**

first_palette	Index of the first 16 color palette to write (0-1)
nb_palettes	Number of palettes to write (1-2, max depends on first_palette)
rgb_data	Pointer to source palette data

Writes nb palettes to palette data starting at first palette, Palette data is sourced from rgb data.

- · Palette 0 can be used for the Background.
- · Palette 1 is shared between Background and Sprites.

#### On the Game Gear

- Each Palette is 32 bytes in size: 16 colors x 2 bytes per palette color entry.
- Each color (16 per palette) is packed as BGR-444 format (x:4:4:4, MSBits [15..12] are unused).
- Each component (R, G, B) may have values from 0 15 (4 bits), 15 is brightest.

### On the SMS

- On SMS each Palette is 16 bytes in size: 16 colors x 1 byte per palette color entry.
- Each color (16 per palette) is packed as BGR-222 format (x:2:2:2, MSBits [7..6] are unused).
- Each component (R, G, B) may have values from 0 3 (2 bits), 3 is brightest.

### See also

RGB(), set\_sprite\_palette(), set\_bkg\_palette(), set\_palette\_entry(), set\_sprite\_palette\_entry(), set\_bkg\_palette\_entry(), set\_sprite\_palette()

```
20.71.4.38 set_native_tile_data() void set_native_tile_data (
             uint16_t start,
             uint16_t ntiles,
             const void * src )
20.71.4.39 set_bkg_4bpp_data() void set_bkg_4bpp_data (
             uint16_t start,
             uint16_t ntiles,
             const void * src )
20.71.4.40 set_bkg_native_data() void set_bkg_native_data (
             uint16_t start,
             uint16_t ntiles,
             const void * src )
20.71.4.41 set_sprite_4bpp_data() void set_sprite_4bpp_data (
             uint8_t start,
             uint16_t ntiles,
             const void * src )
```

```
20.71.4.42 set_sprite_native_data() void set_sprite_native_data (
              uint8_t start,
              uint16_t ntiles,
              const void * src )
\textbf{20.71.4.43} \quad \textbf{set\_2bpp\_palette()} \quad \texttt{void set\_2bpp\_palette} \ \ (
              uint16_t palette ) [inline]
20.71.4.44 set_tile_2bpp_data() void set_tile_2bpp_data (
              uint16_t start,
              uint16_t ntiles,
              const void * src,
              uint16_t palette )
20.71.4.45 set_bkg_data() void set_bkg_data (
              uint16_t start,
              uint16_t ntiles,
              const void * src ) [inline]
20.71.4.46 set_sprite_data() void set_sprite_data (
              uint16_t start,
              uint16_t ntiles,
              const void * src ) [inline]
20.71.4.47 set_bkg_2bpp_data() void set_bkg_2bpp_data (
              uint16_t start,
              uint16_t ntiles,
              const void * src ) [inline]
20.71.4.48 set_sprite_2bpp_data() void set_sprite_2bpp_data (
              uint16_t start,
              uint16_t ntiles,
              const void * src ) [inline]
20.71.4.49 set_1bpp_colors() void set_1bpp_colors (
              uint8_t fgcolor,
              uint8_t bgcolor ) [inline]
{\bf 20.71.4.50} \quad {\bf set\_tile\_1bpp\_data()} \quad {\tt void set\_tile\_1bpp\_data} \ \ (
              uint16_t start,
              uint16_t ntiles,
              const void * src,
              uint16_t colors )
```

# Parameters

dst	destination VRAM Address
src	Pointer to source buffer
size	Number of bytes to copy

Copies size bytes from a buffer at src to VRAM starting at dst.

```
20.71.4.54 vmemcpy() void vmemcpy (
             uint16_t dst,
             const void * src,
             uint16_t size )
20.71.4.55 set_tile_map() void set_tile_map (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint8_t * tiles )
20.71.4.56 set_tile_map_compat() void set_tile_map_compat (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint8_t * tiles )
20.71.4.57 set_bkg_based_tiles() void set_bkg_based_tiles (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint8_t * tiles,
             uint8_t base_tile ) [inline]
```

```
20.71.4.58 set_win_based_tiles() void set_win_based_tiles (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint8_t * tiles,
             uint8_t base_tile ) [inline]
20.71.4.59 set_bkg_attributes() void set_bkg_attributes (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint8_t * tiles ) [inline]
20.71.4.60 set_tile_submap() void set_tile_submap (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             uint8_t map_w,
             const uint8_t * map )
20.71.4.61 set_tile_submap_compat() void set_tile_submap_compat (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             uint8_t map_w,
             const uint8_t * map )
20.71.4.62 set_bkg_submap() void set_bkg_submap (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint8_t * map,
             uint8_t map_w ) [inline]
```

Sets a rectangular area of the Background Tile Map using a sub-region from a source tile map. Useful for scrolling implementations of maps larger than 32 x 32 tiles.

## **Parameters**

Х	X Start position in both the Source Tile Map and hardware Background Map tile coordinates. Range 0 - 255
У	Y Start position in both the Source Tile Map and hardware Background Map tile coordinates. Range 0 - 255
W	Width of area to set in tiles. Range 1 - 255
h	Height of area to set in tiles. Range 1 - 255
тар	Pointer to source tile map data
map← _w	Width of source tile map in tiles. Range 1 - 255

Entries are copied from **map** to the Background Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles, using **map\_w** as the rowstride for the source tile map.

The x and y parameters are in Source Tile Map tile coordinates. The location tiles will be written to on the hardware Background Map is derived from those, but only uses the lower 5 bits of each axis, for range of 0-31 (they are bit-masked: x & 0x1F and y & 0x1F). As a result the two coordinate systems are aligned together.

In order to transfer tile map data in a way where the coordinate systems are not aligned, an offset from the Source Tile Map pointer can be passed in:  $(map\_ptr + x + (y * map\_width))$ .

For example, if you want the tile id at 1, 2 from the source map to show up at 0, 0 on the hardware Background Map (instead of at 1, 2) then modify the pointer address that is passed in:  $map\_ptr + 1 + (2 * map\_width)$  Use this instead of  $set\_bkg\_tiles$  when the source map is wider than 32 tiles or when writing a width that does not match the source map width.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

See set\_bkg\_tiles for setting CGB attribute maps with VBK\_REG.

#### See also

```
SHOW_BKG
set_bkg_data, set_bkg_tiles, set_win_submap, set_tiles
```

Sets a rectangular area of the Window Tile Map using a sub-region from a source tile map.

#### **Parameters**

X	X Start position in both the Source Tile Map and hardware Window Map tile coordinates. Range 0 - 255
У	Y Start position in both the Source Tile Map and hardware Window Map tile coordinates. Range 0 - 255
W	Width of area to set in tiles. Range 1 - 255
h	Height of area to set in tiles. Range 1 - 255
тар	Pointer to source tile map data
тар⊷	Width of source tile map in tiles. Range 1 - 255
_ <i>w</i>	

Entries are copied from **map** to the Window Tile Map starting at **x**, **y** writing across for **w** tiles and down for **h** tiles, using **map w** as the rowstride for the source tile map.

The **x** and **y** parameters are in Source Tile Map tile coordinates. The location tiles will be written to on the hardware Background Map is derived from those, but only uses the lower 5 bits of each axis, for range of 0-31 (they are bit-masked:  $x \& 0 \times 1F$  and  $y \& 0 \times 1F$ ). As a result the two coordinate systems are aligned together.

In order to transfer tile map data in a way where the coordinate systems are not aligned, an offset from the Source Tile Map pointer can be passed in:  $(map\_ptr + x + (y * map\_width))$ .

For example, if you want the tile id at 1, 2 from the source map to show up at 0, 0 on the hardware Background Map (instead of at 1, 2) then modify the pointer address that is passed in:  $map\_ptr + 1 + (2 * map\_width)$  Use this instead of  $set\_win\_tiles$  when the source map is wider than 32 tiles or when writing a width that does not match the source map width.

One byte per source tile map entry.

Writes that exceed coordinate 31 on the x or y axis will wrap around to the Left and Top edges.

GBC only: VBK\_REG determines whether Tile Numbers or Tile Attributes get set.

- VBK\_REG = VBK\_TILES Tile Numbers are written
- VBK REG = VBK ATTRIBUTES Tile Attributes are written

See set\_bkg\_tiles for details about CGB attribute maps with VBK\_REG.

See also

SHOW\_WIN, HIDE\_WIN, set\_win\_tiles, set\_bkg\_submap, set\_bkg\_tiles, set\_bkg\_data, set\_tiles

```
20.71.4.64 set_bkg_based_submap() void set_bkg_based_submap (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint8_t * map,
             uint8_t map_w,
             uint8_t base_tile ) [inline]
20.71.4.65 set_win_based_submap() void set_win_based_submap (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint8_t * map,
             uint8_t map_w,
             uint8_t base_tile ) [inline]
20.71.4.66 set_bkg_submap_attributes() void set_bkg_submap_attributes (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint8_t * map,
             uint8_t map_w ) [inline]
20.71.4.67 fill_rect() void fill_rect (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint16_t tile )
20.71.4.68 fill rect compat() void fill_rect_compat (
             uint8_t x,
             uint8_t y,
             uint8_t w,
             uint8_t h,
             const uint16_t tile )
20.71.4.69 SET_SHADOW_OAM_ADDRESS() void SET_SHADOW_OAM_ADDRESS (
             void * address ) [inline]
Sets address of 256-byte aligned array of shadow OAM to be transferred on each VBlank
```

Sets sprite number **nb\_in the OAM to display tile number \_\_tile**.

### **Parameters**

nb	Sprite number, range 0 - 39
tile	Selects a tile (0 - 255) from memory at 8000h - 8FFFh In CGB Mode this could be either in VRAM Bank 0 or 1, depending on Bit 3 of the OAM Attribute Flag (see set_sprite_prop)

## In 8x16 mode:

- The sprite will also display the next tile (tile + 1) directly below (y + 8) the first tile.
- The lower bit of the tile number is ignored: the upper 8x8 tile is (**tile** & 0xFE), and the lower 8x8 tile is (**tile** | 0x01).
- See: SPRITES\_8x16

Returns the tile number of sprite number **nb** in the OAM.

#### **Parameters**

```
nb Sprite number, range 0 - 39
```

### See also

set\_sprite\_tile for more details

Function has no affect on sms.

This function is only here to enable game portability

Returns the OAM Property Flags of sprite number **nb**.

## **Parameters**

nb Sprite number, range 0 - 39

## See also

set\_sprite\_prop for property bitfield settings

Moves sprite number **nb** to the **x**, **y** position on the screen.

### **Parameters**

nb	Sprite number, range 0 - 39
Х	X Position. Specifies the sprites horizontal position on the screen (minus 8).
	An offscreen value (X=0 or X>=168) hides the sprite, but the sprite still affects the priority ordering - a
	better way to hide a sprite is to set its Y-coordinate offscreen.
У	Y Position. Specifies the sprites vertical position on the screen (minus 16).
	An offscreen value (for example, $Y=0$ or $Y>=160$ ) hides the sprite.

Moving the sprite to 0,0 (or similar off-screen location) will hide it.

Moves sprite number **nb** relative to its current position.

#### **Parameters**

nb	Sprite number, range 0 - 39
Х	Number of pixels to move the sprite on the <b>X axis</b> Range: -128 - 127
У	Number of pixels to move the sprite on the <b>Y axis</b> Range: -128 - 127

## See also

move\_sprite for more details about the X and Y position

Hides sprite number **nb** by moving it to zero position by Y.

## **Parameters**

nb	Sprite number, range 0 - 39
	, ,

```
20.71.4.77 set_vram_byte() void set_vram_byte ( uint8_t * addr, uint8_t v)
```

Set byte in vram at given memory location

### **Parameters**

addr address to write to	
V	value

Set single tile t with attributes on background layer at x,y

### **Parameters**

Х	X-coordinate
У	Y-coordinate
t	tile index

### Returns

returns the address of tile, so you may use faster set\_vram\_byte() later

Set single tile t on background layer at x,y

### **Parameters**

X	X-coordinate
У	Y-coordinate
t	tile index

## Returns

returns the address of tile, so you may use faster set\_vram\_byte() later

Set single attribute data a on background layer at x,y

## **Parameters**

Х	X-coordinate
у	Y-coordinate
а	tile attributes

## Returns

returns the address of tile attribute, so you may use faster set\_vram\_byte() later

```
\textbf{20.71.4.81} \quad \textbf{get\_bkg\_xy\_addr()} \quad \texttt{uint8\_t*} \; \texttt{get\_bkg\_xy\_addr} \; \; (
```

uint8\_t x,
uint8\_t y)

```
Get address of X,Y tile of background map
20.71.5 Variable Documentation
20.71.5.1 _BIOS const UBYTE _BIOS [extern]
20.71.5.2 _SYSTEM const uint8_t _SYSTEM [extern]
20.71.5.3 c void c
20.71.5.4 d void d
20.71.5.5 e void e
20.71.5.6 iyh void iyh
20.71.5.7 iyl uint8_t iyl
Initial value:
   __asm__("ei")
20.71.5.8 h void h
20.71.5.9 I void 1
20.71.5.10 sys_time volatile uint16_t sys_time [extern]
Global Time Counter in VBL periods (60Hz)
Increments once per Frame
Will wrap around every \sim18 minutes (unsigned 16 bits = 65535 / 60 / 60 = 18.2)
20.71.5.11 b void b
20.71.5.12 _current_2bpp_palette uint16_t _current_2bpp_palette [extern]
20.71.5.13 _current_1bpp_colors uint16_t _current_1bpp_colors [extern]
20.71.5.14 _map_tile_offset uint8_t _map_tile_offset [extern]
```

```
20.71.5.15 _submap_tile_offset uint8_t _submap_tile_offset [extern]
```

```
20.71.5.16 shadow_OAM volatile uint8_t shadow_OAM[] [extern]
```

Shadow OAM array in WRAM, that is transferred into the real OAM each VBlank

```
20.71.5.17 _shadow_OAM_base volatile uint8_t _shadow_OAM_base [extern]
```

MSB of shadow\_OAM address is used by OAM copying routine

MSB of shadow\_OAM address is used by OAM DMA copying routine

### 20.71.5.18 shadow OAM OFF volatile uint8\_t \_shadow\_OAM\_OFF [extern]

Flag for disabling of OAM copying routine

Values:

- 1: OAM copy routine is disabled (non-isr VDP operation may be in progress)
- 0: OAM copy routine is enabled

This flag is modified by all sms/gg GBDK API calls that write to the VDP. It is set to DISABLED when they start and ENABLED when they complete.

Note

It is recommended to avoid writing to the Video Display Processor (VDP) during an interrupt service routine (ISR) since it can corrupt the VDP pointer of an VDP operation already in progress.

If it is necessary, this flag can be used during an ISR to determine whether a VDP operation is already in progress. If the value is 1 then avoid writing to the VDP (tiles, map, scrolling, colors, etc).

```
// at the beginning of and ISR that would write to the VDP
if (_shadow_OAM_OFF) return;
```

See also

docs consoles safe display controller access

```
20.71.5.19 _sprites_OFF volatile uint8_t _sprites_OFF [extern]
```

## 20.72 gbdk-lib/include/stdatomic.h File Reference

```
#include <types.h>
```

## **Data Structures**

· struct atomic\_flag

## **Functions**

- \_Bool atomic\_flag\_test\_and\_set (volatile atomic\_flag \*object) OLDCALL
- void atomic\_flag\_clear (volatile atomic\_flag \*object)

## 20.72.1 Function Documentation

## 20.73 gbdk-lib/include/stdbool.h File Reference

### **Macros**

- #define true ((\_Bool)+1)
- #define false ((\_Bool)+0)
- #define bool Bool
- #define \_\_bool\_true\_false\_are\_defined 1

#### 20.73.1 Macro Definition Documentation

```
20.73.1.1 true #define true ((_Bool)+1)
20.73.1.2 false #define false ((_Bool)+0)
20.73.1.3 bool #define bool _Bool
20.73.1.4 __bool_true_false_are_defined #define __bool_true_false_are_defined 1
```

## 20.74 gbdk-lib/include/stddef.h File Reference

#### **Macros**

- #define NULL (void \*)0
- #define \_\_PTRDIFF\_T\_DEFINED
- #define SIZE T DEFINED
- #define \_\_WCHAR\_T\_DEFINED
- #define offsetof(s, m) \_\_builtin\_offsetof (s, m)

### **Typedefs**

- typedef int ptrdiff\_t
- typedef unsigned int size\_t
- typedef unsigned long int wchar\_t

## 20.74.1 Macro Definition Documentation

```
20.74.1.1 NULL #define NULL (void *) 0
20.74.1.2 __PTRDIFF_T_DEFINED #define __PTRDIFF_T_DEFINED
20.74.1.3 __SIZE_T_DEFINED #define __SIZE_T_DEFINED
```

```
368
20.74.1.4 __WCHAR_T_DEFINED #define __WCHAR_T_DEFINED
20.74.1.5 offsetof #define offsetof(
               m ) __builtin_offsetof (s, m)
20.74.2 Typedef Documentation
20.74.2.1 ptrdiff_t typedef int ptrdiff_t
20.74.2.2 size_t typedef unsigned int size_t
20.74.2.3 wchar t typedef unsigned long int wchar_t
20.75 gbdk-lib/include/stdint.h File Reference
Macros

    #define INT8 MIN (-128)

    #define INT16_MIN (-32767-1)

    #define INT32 MIN (-2147483647L-1)

    #define INT8_MAX (127)

    #define INT16_MAX (32767)

    #define INT32 MAX (2147483647L)

    #define UINT8_MAX (255)

    #define UINT16_MAX (65535)

    #define UINT32_MAX (4294967295UL)

    #define INT_LEAST8_MIN INT8_MIN

    #define INT_LEAST16_MIN INT16_MIN

    • #define INT LEAST32 MIN INT32 MIN

    #define INT LEAST8 MAX INT8 MAX

    #define INT LEAST16 MAX INT16 MAX

    #define INT_LEAST32_MAX INT32_MAX

    #define UINT_LEAST8_MAX UINT8_MAX

    #define UINT_LEAST16_MAX UINT16_MAX

    #define UINT_LEAST32_MAX UINT32_MAX

    #define INT FAST8 MIN INT8 MIN
```

- #define INT\_FAST16\_MIN INT16\_MIN #define INT FAST32 MIN INT32 MIN #define INT\_FAST8\_MAX INT8\_MAX
- #define INT\_FAST16\_MAX INT16\_MAX
- #define INT\_FAST32\_MAX INT32\_MAX
- #define UINT\_FAST8\_MAX UINT8\_MAX
- #define UINT\_FAST16\_MAX UINT16\_MAX
- #define UINT\_FAST32\_MAX UINT32\_MAX
- #define INTPTR\_MIN (-32767-1)
- #define INTPTR\_MAX (32767)
- #define UINTPTR\_MAX (65535)
- #define INTMAX\_MIN (-2147483647L-1)
- #define INTMAX MAX (2147483647L)
- #define UINTMAX\_MAX (4294967295UL)

- #define PTRDIFF\_MIN (-32767-1)
- #define PTRDIFF\_MAX (32767)
- #define SIG ATOMIC MIN (0)
- #define SIG ATOMIC MAX (255)
- #define SIZE\_MAX (65535u)
- #define INT8\_C(c) c
- #define INT16\_C(c) c
- #define INT32\_C(c) c ## L
- #define UINT8\_C(c) c ## U
- #define UINT16\_C(c) c ## U
- #define UINT32 C(c) c ## UL
- #define WCHAR\_MIN 0
- #define WCHAR MAX 0xffffffff
- #define WINT\_MIN 0
- #define WINT MAX 0xffffffff
- #define INTMAX\_C(c) c ## L
- #define UINTMAX\_C(c) c ## UL

### **Typedefs**

- typedef signed char int8\_t
- typedef short int int16\_t
- typedef long int int32 t
- typedef unsigned char uint8\_t
- · typedef unsigned short int uint16\_t
- · typedef unsigned long int uint32\_t
- typedef signed char int\_least8\_t
- typedef short int int\_least16\_t
- typedef long int int least32 t
- typedef unsigned char uint least8 t
- typedef unsigned short int uint\_least16\_t
- typedef unsigned long int uint\_least32\_t
- typedef signed char int\_fast8\_t
- typedef int int\_fast16\_t
- typedef long int int\_fast32\_t
- typedef unsigned char uint\_fast8\_t
- typedef unsigned int uint\_fast16\_t
- typedef unsigned long int uint\_fast32\_t
- typedef int intptr t
- typedef unsigned int uintptr\_t
- typedef long int intmax\_t
- typedef unsigned long int uintmax\_t

### 20.75.1 Macro Definition Documentation

```
20.75.1.1 INT8_MIN #define INT8_MIN (-128)
```

**20.75.1.2 INT16\_MIN** #define INT16\_MIN (-32767-1)

**20.75.1.3 INT32 MIN** #define INT32\_MIN (-2147483647L-1)

```
20.75.1.4 INT8_MAX #define INT8_MAX (127)
20.75.1.5 INT16_MAX #define INT16_MAX (32767)
20.75.1.6 INT32_MAX #define INT32_MAX (2147483647L)
20.75.1.7 UINT8_MAX #define UINT8_MAX (255)
20.75.1.8 UINT16_MAX #define UINT16_MAX (65535)
20.75.1.9 UINT32_MAX #define UINT32_MAX (4294967295UL)
20.75.1.10 INT_LEAST8_MIN #define INT_LEAST8_MIN INT8_MIN
20.75.1.11 INT_LEAST16_MIN #define INT_LEAST16_MIN INT16_MIN
20.75.1.12 INT_LEAST32_MIN #define INT_LEAST32_MIN INT32_MIN
20.75.1.13 INT_LEAST8_MAX #define INT_LEAST8_MAX INT8_MAX
20.75.1.14 INT_LEAST16_MAX #define INT_LEAST16_MAX INT16_MAX
20.75.1.15 INT_LEAST32_MAX #define INT_LEAST32_MAX INT32_MAX
20.75.1.16 UINT_LEAST8_MAX #define UINT_LEAST8_MAX UINT8_MAX
20.75.1.17 UINT_LEAST16_MAX #define UINT_LEAST16_MAX UINT16_MAX
20.75.1.18 UINT_LEAST32_MAX #define UINT_LEAST32_MAX UINT32_MAX
20.75.1.19 INT_FAST8_MIN #define INT_FAST8_MIN INT8_MIN
20.75.1.20 INT_FAST16_MIN #define INT_FAST16_MIN INT16_MIN
20.75.1.21 INT_FAST32_MIN #define INT_FAST32_MIN INT32_MIN
```

```
20.75.1.22 INT_FAST8_MAX #define INT_FAST8_MAX INT8_MAX
20.75.1.23 INT_FAST16_MAX #define INT_FAST16_MAX INT16_MAX
20.75.1.24 INT_FAST32_MAX #define INT_FAST32_MAX INT32_MAX
20.75.1.25 UINT_FAST8_MAX #define UINT_FAST8_MAX UINT8_MAX
20.75.1.26 UINT_FAST16_MAX #define UINT_FAST16_MAX UINT16_MAX
20.75.1.27 UINT_FAST32_MAX #define UINT_FAST32_MAX UINT32_MAX
20.75.1.28 INTPTR_MIN #define INTPTR_MIN (-32767-1)
20.75.1.29 INTPTR_MAX #define INTPTR_MAX (32767)
20.75.1.30 UINTPTR_MAX #define UINTPTR_MAX (65535)
20.75.1.31 INTMAX_MIN #define INTMAX_MIN (-2147483647L-1)
20.75.1.32 INTMAX_MAX #define INTMAX_MAX (2147483647L)
20.75.1.33 UINTMAX_MAX #define UINTMAX_MAX (4294967295UL)
20.75.1.34 PTRDIFF_MIN #define PTRDIFF_MIN (-32767-1)
20.75.1.35 PTRDIFF_MAX #define PTRDIFF_MAX (32767)
20.75.1.36 SIG_ATOMIC_MIN #define SIG_ATOMIC_MIN (0)
20.75.1.37 SIG_ATOMIC_MAX #define SIG_ATOMIC_MAX (255)
20.75.1.38 SIZE_MAX #define SIZE_MAX (65535u)
20.75.1.39 INT8_C #define INT8_C(
             c ) c
```

```
20.75.1.40 INT16_C #define INT16_C(
              c ) c
20.75.1.41 INT32 C #define INT32_C(
              c) c ## L
20.75.1.42 UINT8_C #define UINT8_C(
              c ) c ## U
20.75.1.43 UINT16_C #define UINT16_C(
              c ) c ## U
20.75.1.44 UINT32_C #define UINT32_C(
              c ) c ## UL
20.75.1.45 WCHAR_MIN #define WCHAR_MIN 0
20.75.1.46 WCHAR_MAX #define WCHAR_MAX 0xffffffff
20.75.1.47 WINT_MIN #define WINT_MIN 0
20.75.1.48 WINT_MAX #define WINT_MAX 0xffffffff
20.75.1.49 INTMAX_C #define INTMAX_C(
              c) c ## L
20.75.1.50 UINTMAX_C #define UINTMAX_C(
              c ) c ## UL
20.75.2 Typedef Documentation
\textbf{20.75.2.1} \quad \textbf{int8\_t} \quad \texttt{typedef signed char int8\_t}
\textbf{20.75.2.2} \quad \textbf{int16\_t} \quad \texttt{typedef short int int16\_t}
20.75.2.3 int32_t typedef long int int32_t
20.75.2.4 uint8_t typedef unsigned char uint8_t
```

```
20.75.2.5 uint16_t typedef unsigned short int uint16_t
20.75.2.6 uint32_t typedef unsigned long int uint32_t
20.75.2.7 int_least8_t typedef signed char int_least8_t
20.75.2.8 int_least16_t typedef short int int_least16_t
\textbf{20.75.2.9} \quad \textbf{int\_least32\_t} \quad \texttt{typedef long int int\_least32\_t}
\pmb{20.75.2.10} \quad \pmb{uint\_least8\_t} \quad \text{typedef unsigned char uint\_least8\_t}
20.75.2.11 uint_least16_t typedef unsigned short int uint_least16_t
\textbf{20.75.2.12} \quad \textbf{uint\_least32\_t} \quad \texttt{typedef unsigned long int uint\_least32\_t}
20.75.2.13 int_fast8_t typedef signed char int_fast8_t
20.75.2.14 int_fast16_t typedef int int_fast16_t
20.75.2.15 int_fast32_t typedef long int int_fast32_t
20.75.2.16 uint_fast8_t typedef unsigned char uint_fast8_t
20.75.2.17 uint_fast16_t typedef unsigned int uint_fast16_t
20.75.2.18 uint_fast32_t typedef unsigned long int uint_fast32_t
20.75.2.19 intptr_t typedef int intptr_t
20.75.2.20 uintptr_t typedef unsigned int uintptr_t
20.75.2.21 intmax_t typedef long int intmax_t
20.75.2.22 uintmax_t typedef unsigned long int uintmax_t
```

## 20.76 gbdk-lib/include/stdio.h File Reference

```
#include <types.h>
```

### **Functions**

- void putchar (char c) OLDCALL REENTRANT
- void printf (const char \*format,...)
- void sprintf (char \*str, const char \*format,...)
- void puts (const char \*s)
- char \* gets (char \*s) OLDCALL
- char getchar (void) OLDCALL

### 20.76.1 Detailed Description

Basic file/console input output functions.

Including stdio.h will use a large number of the background tiles for font characters. If stdio.h is not included then that space will be available for use with other tiles instead.

#### 20.76.2 Function Documentation

```
20.76.2.1 putchar() void putchar ( char c)
```

Print char to stdout.

#### **Parameters**

c Character to print

Print the string and arguments given by format to stdout.

#### **Parameters**

format The format string as per printf

Does not return the number of characters printed. Currently supported:

- · %hx (char as hex)
- · %hu (unsigned char)
- · %hd (signed char)
- %c (character)
- %u (unsigned int)
- %d (signed int)
- %x (unsigned int as hex)
- %s (string)

Warning: to correctly pass parameters (such as chars, ints, etc) all of them should always be explicitly cast as when calling the function. See docs\_chars\_varargs for more details.

Print the string and arguments given by format to a buffer.

#### **Parameters**

str	The buffer to print into
format	The format string as per printf

Does not return the number of characters printed.

Warning: to correctly pass parameters (such as chars, ints, etc) **all of them should always be explicitly cast** as when calling the function. See docs\_chars\_varargs for more details.

```
20.76.2.4 puts() void puts ( const char *s )
```

puts() writes the string **s** and a trailing newline to stdout.

```
20.76.2.5 gets() char* gets ( char *s)
```

gets() Reads a line from stdin into a buffer pointed to by s.

#### **Parameters**

s Buffer to store string in

Reads until either a terminating newline or an EOF, which it replaces with '\0'. No check for buffer overrun is performed.

Returns: Buffer pointed to by s

```
20.76.2.6 getchar() char getchar ( void )
```

getchar() Reads and returns a single character from stdin.

## 20.77 gbdk-lib/include/stdlib.h File Reference

```
#include <types.h>
```

#### **Functions**

- · void exit (int status) OLDCALL
- int abs (int i)
- long labs (long num) OLDCALL
- int atoi (const char \*s)
- long atol (const char \*s)
- char \* itoa (int n, char \*s, unsigned char radix) OLDCALL
- char \* uitoa (unsigned int n, char \*s, unsigned char radix) OLDCALL
- char \* Itoa (long n, char \*s, unsigned char radix) OLDCALL
- char \* ultoa (unsigned long n, char \*s, unsigned char radix) OLDCALL
- void \* calloc (size\_t nmemb, size\_t size)
- void \* malloc (size\_t size)

- void \* realloc (void \*ptr, size\_t size)
- void free (void \*ptr)
- void \* bsearch (const void \*key, const void \*base, size\_t nmemb, size\_t size, int(\*compar)(const void \*, const void \*) REENTRANT)
- void qsort (void \*base, size t nmemb, size t size, int(\*compar)(const void \*, const void \*) REENTRANT)

### 20.77.1 Function Documentation

```
20.77.1.1 exit() void exit ( int status )
```

file stdlib.h 'Standard library' functions, for whatever that means. Causes normal program termination and the value of status is returned to the parent. All open streams are flushed and closed.

```
20.77.1.2 abs() int abs ( int i)
```

Returns the absolute value of int i

#### **Parameters**

i Int to obtain absolute value of

If i is negative, returns -i; else returns i.

```
20.77.1.3 labs() long labs ( long num )
```

Returns the absolute value of long int num

### **Parameters**

num | Long integer to obtain absolute value of

```
20.77.1.4 atoi() int atoi ( const char *s)
```

Converts an ASCII string to an int

### **Parameters**

s String to convert to an int

## The string may be of the format

[\s]\*[+-][\d]+[\D]\*

i.e. any number of spaces, an optional + or -, then an arbitrary number of digits.

The result is undefined if the number doesnt fit in an int.

Returns: Int value of string

```
20.77.1.5 atol() long atol ( const char *s)
```

Converts an ASCII string to a long.

### **Parameters**

s String to convert to an long int

#### See also

atoi()

Returns: Long int value of string

Converts an int into a base 10 ASCII string.

### **Parameters**

n	Int to convert to a string	
s	String to store the converted number	
radix	Numerical base for converted number, ex: 10 is decimal base (parameter is required but not utilized on	
	Game Boy and Analogue Pocket)	

Can be used with <a href="mailto:set\_bkg\_based\_tiles">set\_bkg\_based\_tiles</a>() for printing if the digit character tiles are not ascii-mapped.

Returns: Pointer to converted string

```
20.77.1.7 uitoa() char* uitoa (
          unsigned int n,
          char * s,
          unsigned char radix )
```

Converts an unsigned int into a base 10 ASCII string.

#### **Parameters**

n	Unsigned Int to convert to a string	
s	String to store the converted number	
radix	Numerical base for converted number, ex: 10 is decimal base (parameter is required but not utilized on	
	Game Boy and Analogue Pocket)	

Can be used with <a href="mailto:set\_bkg\_based\_tiles">set\_bkg\_based\_tiles</a>() for printing if the digit character tiles are not ascii-mapped.

Returns: Pointer to converted string

```
20.77.1.8 Itoa() char* ltoa ( long n, char * s, unsigned char radix )
```

Converts a long into a base 10 ASCII string.

## **Parameters**

n	Long int to convert to a string	
s	String to store the converted number	
radix	Numerical base for converted number, ex: 10 is decimal base (parameter is required but not utilized on	
	Game Boy and Analogue Pocket)	

Can be used with <a href="mailto:set\_bkg\_based\_tiles">set\_bkg\_based\_tiles</a>() for printing if the digit character tiles are not ascii-mapped. Returns: Pointer to converted string

```
·
```

```
20.77.1.9 ultoa() char* ultoa ( unsigned long n,
```

```
char * s,
unsigned char radix )
```

Converts an unsigned long into a base 10 ASCII string.

#### **Parameters**

n	Unsigned Long Int to convert to a string	
s	String to store the converted number	
radix	Numerical base for converted number, ex: 10 is decimal base (parameter is required but not utilized on Game Boy and Analogue Pocket)	

Can be used with <a href="mailto:set\_bkg\_based\_tiles">set\_bkg\_based\_tiles</a>() for printing if the digit character tiles are not ascii-mapped. Returns: Pointer to converted string

```
20.77.1.10 calloc() void* calloc (
             size_t nmemb,
             size_t size )
Memory allocation functions
20.77.1.11 malloc() void* malloc (
             size_t size )
20.77.1.12 realloc() void* realloc (
             void * ptr,
             size_t size )
20.77.1.13 free() void free (
             void * ptr )
20.77.1.14 bsearch() void* bsearch (
             const void * key,
             const void * base,
             size_t nmemb,
             size_t size,
             int(*)(const void *, const void *) REENTRANT compar )
```

## **Parameters**

search a sorted array of nmemb items

key	Pointer to object that is the key for the search
base	Pointer to first object in the array to search
nmemb	Number of elements in the array
size	Size in bytes of each element in the array
compar	Function used to compare two elements of the array

Returns: Pointer to array entry that matches the search key. If key is not found, NULL is returned.

### Sort an array of nmemb items

#### **Parameters**

base	Pointer to first object in the array to sort
nmemb	Number of elements in the array
size	Size in bytes of each element in the array
compar	Function used to compare and sort two elements of the array

## 20.78 gbdk-lib/include/stdnoreturn.h File Reference

### **Macros**

• #define noreturn \_Noreturn

## 20.78.1 Macro Definition Documentation

 $\textbf{20.78.1.1} \quad \textbf{noreturn} \quad \texttt{\#define noreturn \_Noreturn}$ 

## 20.79 gbdk-lib/include/time.h File Reference

```
#include <types.h>
#include <stdint.h>
```

#### **Macros**

• #define CLOCKS\_PER\_SEC 60

### **Typedefs**

• typedef uint16\_t time\_t

### **Functions**

- clock\_t clock (void) OLDCALL
- time\_t time (time\_t \*t)

## 20.79.1 Detailed Description

Sort of ANSI compliant time functions.

### 20.79.2 Macro Definition Documentation

```
20.79.2.1 CLOCKS_PER_SEC #define CLOCKS_PER_SEC 60
```

## 20.79.3 Typedef Documentation

```
20.79.3.1 time_t typedef uint16_t time_t
```

#### 20.79.4 Function Documentation

```
20.79.4.1 \operatorname{clock}() \operatorname{clock\_t} \operatorname{clock} (
```

Returns an approximation of processor time used by the program in Clocks

The value returned is the CPU time (ticks) used so far as a clock t.

To get the number of seconds used, divide by CLOCKS\_PER\_SEC.

This is based on sys\_time, which will wrap around every  $\sim$ 18 minutes. (unsigned 16 bits = 65535 / 60 / 60 = 18.2)

See also

sys\_time, time()

```
20.79.4.2 time() time_t time ( time_t * t )
```

Converts clock() time to Seconds

#### **Parameters**

t If pointer t is not NULL, it's value will be set to the same seconds calculation as returned by the function.

The calculation is clock() / CLOCKS PER SEC

Returns: time in seconds

See also

sys time, clock()

## 20.80 gbdk-lib/include/typeof.h File Reference

## **Macros**

- #define TYPEOF INT 1
- #define TYPEOF SHORT 2
- #define TYPEOF\_CHAR 3
- #define TYPEOF\_LONG 4
- #define TYPEOF\_FLOAT 5
- #define TYPEOF FIXED16X16 6
- #define TYPEOF\_BIT 7
- #define TYPEOF BITFIELD 8
- #define TYPEOF SBIT 9
- #define TYPEOF\_SFR 10
- #define TYPEOF\_VOID 11
- #define TYPEOF\_STRUCT 12
- #define TYPEOF\_ARRAY 13
- #define TYPEOF FUNCTION 14
- #define TYPEOF\_POINTER 15
- #define TYPEOF\_FPOINTER 16
- #define TYPEOF\_CPOINTER 17
- #define TYPEOF\_GPOINTER 18
- #define TYPEOF PPOINTER 19
- #define TYPEOF\_IPOINTER 20
- #define TYPEOF\_EEPPOINTER 21

### 20.80.1 Macro Definition Documentation

- 20.80.1.1 TYPEOF\_INT #define TYPEOF\_INT 1
- 20.80.1.2 TYPEOF\_SHORT #define TYPEOF\_SHORT 2
- 20.80.1.3 TYPEOF\_CHAR #define TYPEOF\_CHAR 3
- 20.80.1.4 TYPEOF\_LONG #define TYPEOF\_LONG 4
- 20.80.1.5 TYPEOF\_FLOAT #define TYPEOF\_FLOAT 5
- 20.80.1.6 TYPEOF\_FIXED16X16 #define TYPEOF\_FIXED16X16 6
- 20.80.1.7 TYPEOF\_BIT #define TYPEOF\_BIT 7
- 20.80.1.8 TYPEOF\_BITFIELD #define TYPEOF\_BITFIELD 8
- 20.80.1.9 TYPEOF\_SBIT #define TYPEOF\_SBIT 9
- 20.80.1.10 TYPEOF\_SFR #define TYPEOF\_SFR 10
- 20.80.1.11 TYPEOF\_VOID #define TYPEOF\_VOID 11
- 20.80.1.12 TYPEOF\_STRUCT #define TYPEOF\_STRUCT 12
- 20.80.1.13 TYPEOF\_ARRAY #define TYPEOF\_ARRAY 13
- 20.80.1.14 TYPEOF\_FUNCTION #define TYPEOF\_FUNCTION 14
- 20.80.1.15 TYPEOF\_POINTER #define TYPEOF\_POINTER 15
- $\textbf{20.80.1.16} \quad \textbf{TYPEOF\_FPOINTER} \quad \texttt{\#define} \quad \texttt{TYPEOF\_FPOINTER} \quad \texttt{16}$
- 20.80.1.17 TYPEOF\_CPOINTER #define TYPEOF\_CPOINTER 17

- 20.80.1.18 TYPEOF\_GPOINTER #define TYPEOF\_GPOINTER 18
- 20.80.1.19 TYPEOF\_PPOINTER #define TYPEOF\_PPOINTER 19
- 20.80.1.20 TYPEOF\_IPOINTER #define TYPEOF\_IPOINTER 20
- 20.80.1.21 TYPEOF\_EEPPOINTER #define TYPEOF\_EEPPOINTER 21

## Index

_AUD3WAVERAM	WRITE_VDP_REG
hardware.h, 207	msx.h, 277
_BIOS	sms.h, 345
sms.h, 365	WRITE_VDP_REG_UNSAFE
HRAM	msx.h, 277
hardware.h, 207	sms.h, 345
IO	assert
hardware.h, 207	assert.h, 116
OAMRAM	bool true false are defined
hardware.h, 207	stdbool.h, 367
RAM	call banked
hardware.h, 207	far_ptr.h, 264
RAMBANK	call_banked_addr
hardware.h, 207	far_ptr.h, 265
SCRN0	call_banked_bank
hardware.h, 207	far_ptr.h, 265
SCRN1	call_banked_ptr
hardware.h, 207	far ptr.h, 265
SRAM	current_base_prop
<del>_</del>	
hardware.h, 207	metasprites.h, 245, 253
_SYSTEM	current_base_tile
hardware.h, 218	metasprites.h, 245, 247, 253, 258
msx.h, 296	current_metasprite
nes.h, 335	metasprites.h, 244, 247, 253, 258
sms.h, 365	far_ptr, 87
_VRAM	fn, 88
hardware.h, 207	ofs, 88
_VRAM8000	ptr, 88
hardware.h, 207	seg, 88
_VRAM8800	segfn, 88
hardware.h, 207	segofs, 88
_VRAM9000	memcpy
hardware.h, 207	string.h, 99
BYTES	rand_seed
hardware.h, 194, 213, 225	rand.h, 338
BYTE_REG	render_shadow_OAM
hardware.h, 194, 213, 225	metasprites.h, 245, 247, 253, 258
GBDK_VERSION	setjmp
version.h, 270	setjmp.h, 339
HandleCrash	_cpu
crash_handler.h, 128	gb.h, 184
PTRDIFF T DEFINED	_current_1bpp_colors
stddef.h, 367	gb.h, 185
READ_VDP_REG	msx.h, 297
msx.h, 277	nes.h, 336
sms.h, 345	sms.h, 365
REG	_current_2bpp_palette
hardware.h, 194, 219, 221, 222	msx.h, 297
SHADOW_REG	sms.h, 365
hardware.h, 219	_current_bank
SIZE T DEFINED	
<del></del>	gb.h, 185
stddef.h, 367	msx.h, 296
types.h, 110, 111, 114	nes.h, 335
WCHAR_T_DEFINED	sms.h, 348
stddef.h, 367	_fixed, 88

b, 89	nes.h, 310
h, 88	sms.h, 352
I, 88	AND
w, 89	drawing.h, 129
_io_in	arand
gb.h, 185	rand.h, 338
_io_out	assert
gb.h, 185	assert.h, 116
_io_status	assert.h
gb.h, 184	assert, 116
_is_GBA	assert, 116
gb.h, 184	AT
_map_tile_offset	types.h, 112
gb.h, 185	atoi
msx.h, 297	stdlib.h, 376
nes.h, 336	atol
sms.h, 365	stdlib.h, 376
_shadow_OAM_OFF	atomic_flag, 89
msx.h, 297	flag, 89
sms.h, 366	atomic_flag_clear
_shadow_OAM_base	stdatomic.h, 366
gb.h, 185	atomic_flag_test_and_set
msx.h, 297	stdatomic.h, 366
nes.h, 336	AUD1SWEEP_DOWN
sms.h, 366	hardware.h, 196
_sprites_OFF	AUD1SWEEP_LENGTH
sms.h, 366	hardware.h, 196
_submap_tile_offset	AUD1SWEEP_TIME
gb.h, 185	hardware.h, 196
msx.h, 297	AUD1SWEEP_UP
nes.h, 336	hardware.h, 196 AUD3WAVE
sms.h, 365 switch prg0	
	hardware.h, 209 AUD4POLY_WIDTH_15BIT
nes.h, 335	hardware.h, 197
abs	AUD4POLY_WIDTH_7BIT
stdlib.h, 376	hardware.h, 197
add_JOY	AUDENA OFF
gb.h, 154	hardware.h, 198
msx.h, 284	AUDENA ON
sms.h, 353	hardware.h, 198
add_LCD	AUDENV_DOWN
gb.h, 153	hardware.h, 205
msx.h, 284	AUDENV LENGTH
nes.h, 311	hardware.h, 205
sms.h, 352	AUDENV UP
add_low_priority_TIM	hardware.h, 205
gb.h, 154	AUDENV VOL
add_SIO	hardware.h, 204
gb.h, 154	AUDHIGH_LENGTH_OFF
msx.h, 284	hardware.h, 205
sms.h, 352	AUDHIGH_LENGTH_ON
add_TIM	hardware.h, 205
gb.h, 153	AUDHIGH_RESTART
msx.h, 284	hardware.h, 205
sms.h, 352	AUDLEN_DUTY_12_5
add_VBL	hardware.h, 204
gb.h, 153	AUDLEN_DUTY_25
msx.h, 284	

hardware.h, 204	BCD, 118, 120
AUDLEN_DUTY_50	bcd2text, 119, 121
hardware.h, 204	bcd_add, 118, 120
AUDLEN_DUTY_75	BCD_HEX, 118, 120
hardware.h, 204	bcd_sub, 119, 121
AUDLEN_LENGTH	MAKE_BCD, 118, 120
hardware.h, 204	uint2bcd, 118, 120
AUDTERM_1_LEFT	bcd2text
hardware.h, 198	bcd.h, 119, 121
AUDTERM_1_RIGHT	bcd_add
hardware.h, 198	bcd.h, 118, 120
AUDTERM_2_LEFT	BCD_HEX
hardware.h, 198	bcd.h, 118, 120
AUDTERM 2 RIGHT	bcd sub
hardware.h, 198	bcd.h, 119, 121
AUDTERM 3 LEFT	BCPD REG
hardware.h, 198	hardware.h, 211
AUDTERM 3 RIGHT	BCPS_REG
hardware.h, 198	hardware.h, 211
AUDTERM 4 LEFT	BCPSF AUTOINC
hardware.h, 198	hardware.h, 203
AUDTERM 4 RIGHT	BGB BREAKPOINT
hardware.h, 198	emu_debug.h, 135
AUDVOL VIN LEFT	BGB MESSAGE
— — —	<del>_</del>
hardware.h, 198	emu_debug.h, 134
AUDVOL_VIN_RIGHT	BGB_printf
hardware.h, 198	emu_debug.h, 135
AUDVOL_VOL_LEFT	BGB_PROFILE_BEGIN
hardware.h, 197	emu_debug.h, 134
AUDVOL_VOL_RIGHT	BGB_PROFILE_END
hardware.h, 197	emu_debug.h, 134
b	BGB_profiler_message
	emu_debug.h, 135
_fixed, 89	BGB_TEXT
emu_debug.h, 136	emu_debug.h, 135
gb.h, 185	BGP_REG
msx.h, 297	
	hardware.h, 210
sms.h, 365	hardware.h, 210 bkg_scroll_x
BANK	•
BANK gb.h, 146	bkg_scroll_x
BANK gb.h, 146 incbin.h, 268	bkg_scroll_x hardware.h, 222
BANK gb.h, 146 incbin.h, 268 msx.h, 280	bkg_scroll_x hardware.h, 222 bkg_scroll_y
BANK gb.h, 146 incbin.h, 268 msx.h, 280 nes.h, 305	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222
BANK gb.h, 146 incbin.h, 268 msx.h, 280 nes.h, 305 sms.h, 348	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0
BANK gb.h, 146 incbin.h, 268 msx.h, 280 nes.h, 305 sms.h, 348 BANKED	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202
BANK     gb.h, 146     incbin.h, 268     msx.h, 280     nes.h, 305     sms.h, 348 BANKED     types.h, 113	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1
BANK     gb.h, 146     incbin.h, 268     msx.h, 280     nes.h, 305     sms.h, 348 BANKED     types.h, 113 BANKREF	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1 hardware.h, 202 BKGF_CGB_PAL0
BANK     gb.h, 146     incbin.h, 268     msx.h, 280     nes.h, 305     sms.h, 348 BANKED     types.h, 113	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1 hardware.h, 202 BKGF_CGB_PAL0 hardware.h, 202
BANK     gb.h, 146     incbin.h, 268     msx.h, 280     nes.h, 305     sms.h, 348 BANKED     types.h, 113 BANKREF	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1 hardware.h, 202 BKGF_CGB_PAL0 hardware.h, 202 BKGF_CGB_PAL1
BANK     gb.h, 146     incbin.h, 268     msx.h, 280     nes.h, 305     sms.h, 348 BANKED     types.h, 113 BANKREF     gb.h, 146	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1 hardware.h, 202 BKGF_CGB_PAL0 hardware.h, 202 BKGF_CGB_PAL1 hardware.h, 202
BANK  gb.h, 146 incbin.h, 268 msx.h, 280 nes.h, 305 sms.h, 348 BANKED types.h, 113 BANKREF gb.h, 146 msx.h, 280	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1 hardware.h, 202 BKGF_CGB_PAL0 hardware.h, 202 BKGF_CGB_PAL1 hardware.h, 202 BKGF_CGB_PAL1
BANK  gb.h, 146 incbin.h, 268 msx.h, 280 nes.h, 305 sms.h, 348  BANKED types.h, 113  BANKREF gb.h, 146 msx.h, 280 nes.h, 306	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1 hardware.h, 202 BKGF_CGB_PAL0 hardware.h, 202 BKGF_CGB_PAL1 hardware.h, 202 BKGF_CGB_PAL1 hardware.h, 202 BKGF_CGB_PAL2 hardware.h, 202
BANK  gb.h, 146 incbin.h, 268 msx.h, 280 nes.h, 305 sms.h, 348  BANKED types.h, 113  BANKREF gb.h, 146 msx.h, 280 nes.h, 306 sms.h, 348	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1 hardware.h, 202 BKGF_CGB_PAL0 hardware.h, 202 BKGF_CGB_PAL1 hardware.h, 202 BKGF_CGB_PAL2 hardware.h, 202 BKGF_CGB_PAL2 BKGF_CGB_PAL3
BANK  gb.h, 146 incbin.h, 268 msx.h, 280 nes.h, 305 sms.h, 348  BANKED types.h, 113  BANKREF gb.h, 146 msx.h, 280 nes.h, 306 sms.h, 348  BANKREF_EXTERN	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1 hardware.h, 202 BKGF_CGB_PAL0 hardware.h, 202 BKGF_CGB_PAL1 hardware.h, 202 BKGF_CGB_PAL2 hardware.h, 202 BKGF_CGB_PAL3 hardware.h, 202
BANK  gb.h, 146 incbin.h, 268 msx.h, 280 nes.h, 305 sms.h, 348  BANKED types.h, 113  BANKREF gb.h, 146 msx.h, 280 nes.h, 306 sms.h, 348  BANKREF_EXTERN gb.h, 146	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1 hardware.h, 202 BKGF_CGB_PAL0 hardware.h, 202 BKGF_CGB_PAL1 hardware.h, 202 BKGF_CGB_PAL2 hardware.h, 202 BKGF_CGB_PAL2 bardware.h, 202 BKGF_CGB_PAL3 hardware.h, 202 BKGF_CGB_PAL4
BANK	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1 hardware.h, 202 BKGF_CGB_PAL0 hardware.h, 202 BKGF_CGB_PAL1 hardware.h, 202 BKGF_CGB_PAL2 hardware.h, 202 BKGF_CGB_PAL2 hardware.h, 202 BKGF_CGB_PAL3 hardware.h, 202 BKGF_CGB_PAL4 hardware.h, 202
BANK  gb.h, 146 incbin.h, 268 msx.h, 280 nes.h, 305 sms.h, 348  BANKED types.h, 113  BANKREF gb.h, 146 msx.h, 280 nes.h, 306 sms.h, 348  BANKREF_EXTERN gb.h, 146 msx.h, 280 nes.h, 306	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1 hardware.h, 202 BKGF_CGB_PAL0 hardware.h, 202 BKGF_CGB_PAL1 hardware.h, 202 BKGF_CGB_PAL2 hardware.h, 202 BKGF_CGB_PAL3 hardware.h, 202 BKGF_CGB_PAL3 hardware.h, 202 BKGF_CGB_PAL4 hardware.h, 202 BKGF_CGB_PAL4 BKGF_CGB_PAL5
BANK  gb.h, 146 incbin.h, 268 msx.h, 280 nes.h, 305 sms.h, 348  BANKED types.h, 113  BANKREF gb.h, 146 msx.h, 280 nes.h, 306 sms.h, 348  BANKREF_EXTERN gb.h, 146 msx.h, 280 nes.h, 306 sms.h, 348  BANKREF_EXTERN gb.h, 146 msx.h, 280 nes.h, 306 sms.h, 348  BCD	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1 hardware.h, 202 BKGF_CGB_PAL0 hardware.h, 202 BKGF_CGB_PAL1 hardware.h, 202 BKGF_CGB_PAL2 hardware.h, 202 BKGF_CGB_PAL3 hardware.h, 202 BKGF_CGB_PAL3 hardware.h, 202 BKGF_CGB_PAL4 hardware.h, 202 BKGF_CGB_PAL5 hardware.h, 202
BANK  gb.h, 146 incbin.h, 268 msx.h, 280 nes.h, 305 sms.h, 348  BANKED types.h, 113  BANKREF gb.h, 146 msx.h, 280 nes.h, 306 sms.h, 348  BANKREF_EXTERN gb.h, 146 msx.h, 280 nes.h, 306 sms.h, 348	bkg_scroll_x hardware.h, 222 bkg_scroll_y hardware.h, 222 BKGF_BANK0 hardware.h, 202 BKGF_BANK1 hardware.h, 202 BKGF_CGB_PAL0 hardware.h, 202 BKGF_CGB_PAL1 hardware.h, 202 BKGF_CGB_PAL2 hardware.h, 202 BKGF_CGB_PAL3 hardware.h, 202 BKGF_CGB_PAL3 hardware.h, 202 BKGF_CGB_PAL4 hardware.h, 202 BKGF_CGB_PAL4 BKGF_CGB_PAL5

hardware.h, 202	RGB_LIGHTGRAY, 124
BKGF_CGB_PAL7	RGB_ORANGE, 125
hardware.h, 202	RGB_PINK, 124
BKGF_PRI	RGB_PURPLE, 124
hardware.h, 202	RGB_RED, 124
BKGF_XFLIP	RGB_TEAL, 125
hardware.h, 202	RGB_WHITE, 124
BKGF_YFLIP	RGB_YELLOW, 124
hardware.h, 202	RGBHTML, 123
BLACK	set_bkg_palette, 125
drawing.h, 129	set_bkg_palette_entry, 126
bool	set_default_palette, 127
stdbool.h, 367	set_sprite_palette, 125
BOOLEAN	set_sprite_palette_entry, 126
types.h, 113	cgb_compatibility
box	cgb.h, 127
drawing.h, 131	sms.h, 355
BP_SIZE	CGB_TYPE
setjmp.h, 339	gb.h, 145
BPX_SIZE	CHAR_BIT
setjmp.h, 339	limits.h, 270
bsearch	CHAR_MAX
stdlib.h, 378	limits.h, 271
BYTE	CHAR_MIN
types.h, 113	limits.h, 271
	circle
C amu dahua h. 126	drawing.h, 131
emu_debug.h, 136	clock
gb.h, 184	time.h, 380
gbdecompress.h, 188	clock_t
msx.h, 296	types.h, 110, 111, 115
sgb.h, 261	CLOCKS_PER_SEC
sms.h, 365	time.h, 379
string.h, 106	cls
calloc	console.h, 262
stdlib.h, 378	color
cancel_pending_interrupts	drawing.h, 132
gb.h, 155	COMPAT_PALETTE
msx.h, 285	gb.h, 150
sms.h, 353	msx.h, 282
cgb.h	nes.h, 308
cgb_compatibility, 127	sms.h, 350
cpu_fast, 127	console.h
cpu_slow, 127	cls, 262
palette_color_t, 125	gotoxy, 261
RGB, 123	posx, 261
RGB8, 123	posy, 261
RGB_AQUA, 124	setchar, 262
RGB_BLACK, 124	cpu_fast
RGB_BLUE, 124	cgb.h, 127
RGB_BROWN, 125	msx.h, 287
RGB_CYAN, 124	sms.h, 355
RGB_DARKBLUE, 124	cpu_slow
RGB_DARKGRAY, 124	cgb.h, 127
RGB_DARKGREEN, 124	crash_handler.h
RGB_DARKRED, 124	HandleCrash, 128
RGB_DARKYELLOW, 124	CRITICAL
RGB_GREEN, 124	types.h, 113
RGB_LIGHTFLESH, 124	

ctype.h	gb.h, 151
isalpha, 116	nes.h, 308
isdigit, 117	DISABLE_RAM
islower, 117	gb.h, 147
isspace, 117	msx.h, 281
isupper, 116	nes.h, 307
tolower, 117	sms.h, 349
toupper, 117	DISABLE RAM MBC1
CURRENT_BANK	gb.h, 148
gb.h, 146	DISABLE RAM MBC5
msx.h, 280	gb.h, 149
nes.h, 305	DISABLE_VBL_TRANSFER
sms.h, 348	gb.h, 151
3113.11, 040	msx.h, 282
d	
gb.h, 184	nes.h, 309
msx.h, 296	sms.h, 350
sms.h, 365	DISPLAY_OFF
delay	gb.h, 150
gb.h, 156	msx.h, 279
msx.h, 286	nes.h, 307
	sms.h, 346
nes.h, 311	display_off
sms.h, 353	gb.h, 158
DEVICE_SCREEN_BUFFER_HEIGHT	msx.h, 285
hardware.h, 206, 220	nes.h, 314
DEVICE_SCREEN_BUFFER_WIDTH	sms.h, <mark>353</mark>
hardware.h, 206, 220	DISPLAY_ON
DEVICE_SCREEN_HEIGHT	gb.h, 149
hardware.h, 206, 220	msx.h, 278
DEVICE_SCREEN_MAP_ENTRY_SIZE	nes.h, 307
hardware.h, 206, 221	sms.h, 346
DEVICE_SCREEN_PX_HEIGHT	display_on
hardware.h, 206, 217, 221, 234	nes.h, 314
DEVICE_SCREEN_PX_WIDTH	DIV REG
hardware.h, 206, 217, 221, 234	hardware.h, 208
DEVICE_SCREEN_WIDTH	msx.h, 280
hardware.h, 206, 220	sms.h, 348
DEVICE_SCREEN_X_OFFSET	DKGREY
hardware.h, 206, 220	drawing.h, 129
DEVICE SCREEN Y OFFSET	DMA_REG
hardware.h, 206, 220	hardware.h, 210
DEVICE SPRITE PX OFFSET X	DMG_BLACK
hardware.h, 206, 221	
DEVICE SPRITE PX OFFSET Y	gb.h, 143
hardware.h, 206, 221	nes.h, 304
DEVICE_SUPPORTS_COLOR	DMG_DARK_GRAY
gb.h, 145	gb.h, 143
msx.h, 280	nes.h, 304
sms.h, 347	DMG_LITE_GRAY
DEVICE_WINDOW_PX_OFFSET_X	gb.h, 144
hardware.h, 206, 221	nes.h, 305
	DMG_PALETTE
DEVICE_WINDOW_PX_OFFSET_Y	gb.h, 144
hardware.h, 206, 221	nes.h, 305
disable_interrupts	DMG_TYPE
gb.h, 157	gb.h, 145
msx.h, 287	DMG_WHITE
nes.h, 314	gb.h, 144
sms.h, 355	nes.h, 305
DISABLE_OAM_DMA	

docs/pages/01_getting_started.md, 95	gb.h, 143
docs/pages/02_links_and_tools.md, 95	msx.h, 277
docs/pages/03_using_gbdk.md, 95	sms.h, 345
docs/pages/04_coding_guidelines.md, 95	EMU_BREAKPOINT
docs/pages/05 banking mbcs.md, 95	emu_debug.h, 135
docs/pages/06_toolchain.md, 95	emu_debug.h
docs/pages/06b_supported_consoles.md, 95	b, 136
docs/pages/07_sample_programs.md, 95	BGB_BREAKPOINT, 135
docs/pages/08_faq.md, 95	BGB_MESSAGE, 134
docs/pages/09_migrating_new_versions.md, 95	BGB_printf, 135
docs/pages/10_release_notes.md, 95	BGB_PROFILE_BEGIN, 134
docs/pages/20_toolchain_settings.md, 95	BGB PROFILE END, 134
docs/pages/docs_index.md, 95	BGB_profiler_message, 135
draw_image	BGB TEXT, 135
drawing.h, 131	c, 136
drawing.h	EMU BREAKPOINT, 135
_	
AND, 129	EMU_fmtbuf, 135
BLACK, 129	EMU_MESSAGE, 133
box, 131	EMU_printf, 135
circle, 131	EMU_PROFILE_BEGIN, 134
color, 132	EMU_PROFILE_END, 134
DKGREY, 129	EMU_profiler_message, 135
draw_image, 131	EMU_TEXT, 134
getpix, 132	EMU fmtbuf
gotogxy, 132	emu_debug.h, 135
gprint, 130	EMU MESSAGE
	emu_debug.h, 133
gprintf, 130	
gprintln, 130	EMU_printf
gprintn, 130	emu_debug.h, 135
GRAPHICS_HEIGHT, 129	EMU_PROFILE_BEGIN
GRAPHICS_WIDTH, 129	emu_debug.h, 134
line, 131	EMU_PROFILE_END
LTGREY, 129	emu_debug.h, 134
M_FILL, 129	EMU_profiler_message
M NOFILL, 129	emu_debug.h, 135
OR, 129	EMU TEXT
plot, 131	emu debug.h, 134
plot point, 131	enable_interrupts
SIGNED, 129	gb.h, 157
SOLID, 129	<del>-</del>
•	msx.h, 286
switch_data, 131	nes.h, 313
UNSIGNED, 130	sms.h, 354
WHITE, 129	ENABLE_OAM_DMA
wrtchr, 132	gb.h, 151
XOR, 129	nes.h, 309
dtile	ENABLE_RAM
metasprite_t, 93	gb.h, 147
DWORD	msx.h, 281
types.h, 113	nes.h, 307
dx	sms.h, 349
metasprite_t, 93	ENABLE_RAM_MBC1
• —	
dy	gb.h, 148
metasprite_t, 93	ENABLE_RAM_MBC5
0	gb.h, 149
e ab b 104	ENABLE_VBL_TRANSFER
gb.h, 184	gb.h, 151
msx.h, 296	msx.h, 282
sms.h, 365	nes.h, 309
EMPTY_IFLAG	

sms.h, 350	FONT_128ENCODING, 266
exit	FONT 256ENCODING, 266
stdlib.h, 376	font_color, 267
Stalls.11, 07 0	FONT_COMPRESSED, 266
FALSE	
_	font_init, 266
types.h, 115	font_load, 266
false	FONT_NOENCODING, 266
stdbool.h, 367	font_set, 266
FAR_CALL	font_t, 266
far_ptr.h, 264	mfont_handle, 266
FAR FUNC	pmfont handle, 266
far ptr.h, 263	• –
FAR OFS	FONT_128ENCODING
far_ptr.h, 263	font.h, 266
<b>-</b>	FONT_256ENCODING
FAR_PTR	font.h, 266
far_ptr.h, 264	font_color
far_ptr.h	font.h, 267
callbanked, 264	FONT_COMPRESSED
call_banked_addr, 265	font.h, 266
_call_banked_bank, 265	
call_banked_ptr, 265	font_ibm
FAR_CALL, 264	List of gbdk fonts, 87
	font_ibm_fixed
FAR_FUNC, 263	List of gbdk fonts, 87
FAR_OFS, 263	font_init
FAR_PTR, 264	font.h, 266
FAR_SEG, 263	font italic
TO_FAR_PTR, 263	List of gbdk fonts, 87
to_far_ptr, 264	_
FAR SEG	font_load
<del>_</del>	font.h, 266
far_ptr.h, 263	font_min
fill_bkg_rect	List of gbdk fonts, 87
gb.h, 183	FONT_NOENCODING
msx.h, 282	font.h, 266
nes.h, 335	font_set
sms.h, 350	font.h, 266
fill_rect	
gb.h, 151	font_spect
msx.h, 291	List of gbdk fonts, 87
	font_t
nes.h, 309	font.h, 266
sms.h, 361	free
fill_rect_compat	stdlib.h, 378
sms.h, 361	func
fill_win_rect	isr_nested_vector_t, 89
gb.h, 183	isr vector t, 90
msx.h, 282	isi_vector_t, 90
sms.h, 350	GAMEBOY
first_tile	gb.h, 141
sfont_handle, 94	gb.h
fixed	_cpu, 184
types.h, 113	_current_1bpp_colors, 185
flag	_current_bank, 185
atomic_flag, 89	_io_in, 185
flush_shadow_attributes	_io_out, 185
nes.h, 335	_io_status, 184
fn	_is_GBA, 184
far_ptr, 88	
	_map_tile_offset, 185
font	_map_tile_offset, 185 _shadow_OAM_base, 185
font	_shadow_OAM_base, 185

add_LCD, 153	get_win_data, 170
add_low_priority_TIM, 154	get_win_tile_xy, 173
add_SIO, 154	get_win_tiles, 173
add_TIM, 153	get_win_xy_addr, 169
add VBL, 153	h, 184
b, 185	HARDWARE SPRITE CAN FLIP X, 151
BANK, 146	HARDWARE SPRITE CAN FLIP Y, 151
•	
BANKREF, 146	HIDE_BKG, 150
BANKREF_EXTERN, 146	HIDE_LEFT_COLUMN, 150
c, 184	hide_sprite, 178
cancel_pending_interrupts, 155	HIDE_SPRITES, 150
CGB_TYPE, 145	HIDE_WIN, 150
COMPAT_PALETTE, 150	hiramcpy, 159
CURRENT_BANK, 146	init_bkg, 183
d, 184	init_win, 182
delay, 156	int_handler, 151
DEVICE_SUPPORTS_COLOR, 145	IO_ERROR, 146
disable interrupts, 157	IO IDLE, 146
DISABLE_OAM_DMA, 151	IO_RECEIVING, 146
DISABLE RAM, 147	IO SENDING, 146
DISABLE_RAM_MBC1, 148	J_A, 141
DISABLE_RAM_MBC5, 149	J_B, 141
DISABLE_VBL_TRANSFER, 151	J_DOWN, 141
DISPLAY_OFF, 150	J_LEFT, 141
display_off, 158	J_RIGHT, 141
DISPLAY_ON, 149	J_SELECT, 141
DMG_BLACK, 143	J_START, 141
DMG_DARK_GRAY, 143	J_UP, 141
DMG_LITE_GRAY, 144	JOY_IFLAG, 143
DMG PALETTE, 144	joypad, 156
DMG TYPE, 145	joypad_ex, 157
DMG WHITE, 144	joypad_init, 157
e, 184	I, 184
EMPTY_IFLAG, 143	LCD IFLAG, 143
enable_interrupts, 157	M DRAWING, 141
ENABLE_OAM_DMA, 151	M_NO_INTERP, 142
ENABLE_RAM, 147	M NO SCROLL, 141
ENABLE_RAM_MBC1, 148	M_TEXT_INOUT, 141
ENABLE_RAM_MBC5, 149	M_TEXT_OUT, 141
ENABLE_VBL_TRANSFER, 151	MAX_HARDWARE_SPRITES, 151
fill_bkg_rect, 183	MAXWNDPOSX, 144
fill_rect, 151	MAXWNDPOSY, 145
fill_win_rect, 183	MGB_TYPE, 145
GAMEBOY, 141	MINWNDPOSX, 144
GBA_DETECTED, 145	MINWNDPOSY, 144
GBA_NOT_DETECTED, 145	mode, 155
get_bkg_data, 161	move_bkg, 168
get_bkg_tile_xy, 168	move_sprite, 177
get_bkg_tiles, 166	move_win, 174
get_bkg_xy_addr, 159	NINTENDO, 140
get_data, 179	nowait_int_handler, 154
get_mode, 155	OAM_item_t, 151
<del>-</del> -	
get_sprite_data, 175	receive_byte, 156
get_sprite_prop, 177	refresh_OAM, 159
get_sprite_tile, 176	remove_JOY, 152
get_system, 155	remove_LCD, 152
get_tiles, 181	remove_SIO, 152
get_vram_byte, 159	remove_TIM, 152

remove_VBL, 152	SHOW_WIN, 150
reset, 158	SIO_IFLAG, 143
S_BANK, 142	SPRITES_8x16, 150
S_FLIPX, 142	SPRITES_8x8, 150
S_FLIPY, 142	SWITCH_16_8_MODE_MBC1, 148
S_PAL, 142	SWITCH_4_32_MODE_MBC1, 148
S_PALETTE, 142	SWITCH_RAM, 147
S_PRIORITY, 142	SWITCH_RAM_MBC1, 148
SCREENHEIGHT, 144	SWITCH_RAM_MBC5, 149
SCREENWIDTH, 144	SWITCH_ROM, 147
scroll bkg, 168	SWITCH ROM MBC1, 148
scroll_sprite, 178	SWITCH_ROM_MBC5, 148
scroll win, 174	SWITCH_ROM_MBC5_8M, 149
send_byte, 155	SWITCH ROM MEGADUCK, 148
set_1bpp_colors, 160	sys_time, 184
set_1bpp_colors_ex, 160	SYSTEM_50HZ, 141
set_2bpp_palette, 160	SYSTEM_60HZ, 140
set attribute xy, 151	TIM IFLAG, 143
set bkg 1bpp data, 161	VBL_IFLAG, 143
set_bkg_2bpp_data, 151	vmemcpy, 179
set_bkg_attribute_xy, 167	vmemset, 183
set_bkg_attributes, 163	vsync, 158
set bkg based submap, 165	•
set bkg based tiles, 163	wait_int_handler, 155 wait vbl done, 158
	— — ·
set_bkg_data, 160	waitpad, 156
set_bkg_native_data, 182	waitpadup, 156
set_bkg_submap, 164	gb_decompress
set_bkg_submap_attributes, 166	gbdecompress.h, 186, 188
set_bkg_tile_xy, 167	gb_decompress_bkg_data
set_bkg_tiles, 162	gbdecompress.h, 186
SET_BORDER_COLOR, 150	gb_decompress_sprite_data
set_data, 178	gbdecompress.h, 187
set_interrupts, 158	gb_decompress_win_data
set_native_tile_data, 181	gbdecompress.h, 187
SET_SHADOW_OAM_ADDRESS, 176	GBA_DETECTED
set_sprite_1bpp_data, 175	gb.h, 145
set_sprite_2bpp_data, 151	GBA_NOT_DETECTED
set_sprite_data, 174	gb.h, 145
set_sprite_native_data, 182	gbdecompress.h
set_sprite_prop, 176	c, 188
set_sprite_tile, 176	gb_decompress, 186, 188
set_tile_data, 180	gb_decompress_bkg_data, 186
set_tile_map, 151	gb_decompress_sprite_data, 187
set_tile_submap, 151	gb_decompress_win_data, 187
set_tile_xy, 151	gbdk-lib/include/asm/mos6502/provides.h, 95
set_tiles, 180	gbdk-lib/include/asm/mos6502/stdarg.h, 96
set_vram_byte, 159	gbdk-lib/include/asm/mos6502/string.h, 98
set_win_1bpp_data, 169	gbdk-lib/include/asm/mos6502/types.h, 110
set_win_based_submap, 172	gbdk-lib/include/asm/sm83/provides.h, 95
set_win_based_tiles, 171	gbdk-lib/include/asm/sm83/stdarg.h, 97
set_win_data, 169	gbdk-lib/include/asm/sm83/string.h, 102
set_win_submap, 171	gbdk-lib/include/asm/sm83/types.h, 111
set_win_tile_xy, 173	gbdk-lib/include/asm/types.h, 112
set_win_tiles, 170	gbdk-lib/include/asm/z80/provides.h, 96
shadow_OAM, 185	gbdk-lib/include/asm/z80/stdarg.h, 97
SHOW_BKG, 150	gbdk-lib/include/asm/z80/string.h, 106
SHOW_LEFT_COLUMN, 150	gbdk-lib/include/asm/z80/types.h, 114
SHOW_SPRITES, 150	gbdk-lib/include/assert.h, 115

gbdk-lib/include/ctype.h, 116	get_bkg_tiles
gbdk-lib/include/gb/bcd.h, 117	gb.h, 166
gbdk-lib/include/gb/bgb_emu.h, 121	nes.h, 322
gbdk-lib/include/gb/cgb.h, 121	get_bkg_xy_addr
gbdk-lib/include/gb/crash_handler.h, 127	gb.h, 159
gbdk-lib/include/gb/drawing.h, 128	msx.h, 296
gbdk-lib/include/gb/emu_debug.h, 132	nes.h, 315
gbdk-lib/include/gb/gb.h, 136	sms.h, 364
gbdk-lib/include/gb/gbdecompress.h, 185	get_data
gbdk-lib/include/gb/hardware.h, 188	gb.h, 179
gbdk-lib/include/gb/hblankcpy.h, 235	get_mode
gbdk-lib/include/gb/isr.h, 237	gb.h, 155
gbdk-lib/include/gb/metasprites.h, 238	msx.h, 283
gbdk-lib/include/gb/sgb.h, 258	nes.h, 311
gbdk-lib/include/gbdk/bcd.h, 119	sms.h, 351
gbdk-lib/include/gbdk/console.h, 261	get_r_reg
gbdk-lib/include/gbdk/emu_debug.h, 133	msx.h, 285
gbdk-lib/include/gbdk/far_ptr.h, 262	sms.h, 353
gbdk-lib/include/gbdk/font.h, 265	get_sprite_data
gbdk-lib/include/gbdk/gbdecompress.h, 187	gb.h, 175
gbdk-lib/include/gbdk/gbdk-lib.h, 267	get_sprite_prop
gbdk-lib/include/gbdk/incbin.h, 267	gb.h, 177
gbdk-lib/include/gbdk/metasprites.h, 245	msx.h, 294
gbdk-lib/include/gbdk/platform.h, 269	nes.h, 329
gbdk-lib/include/gbdk/rledecompress.h, 269	sms.h, 362
gbdk-lib/include/gbdk/version.h, 270	get_sprite_tile
gbdk-lib/include/limits.h, 270	gb.h, 176
gbdk-lib/include/msx/hardware.h, 211	msx.h, 292
gbdk-lib/include/msx/metasprites.h, 245	nes.h, 327
gbdk-lib/include/msx/metasphtes.n, 243	sms.h, 362
gbdk-lib/include/msx/msx.m, 272	get_system
	get_system gb.h, 155
gbdk-lib/include/nes/metasprites.h, 248 gbdk-lib/include/nes/nes.h, 298	_
	msx.h, 283 nes.h, 311
gbdk-lib/include/nes/rgb_to_nes_macro.h, 336	
gbdk-lib/include/rand.h, 336	sms.h, 351
gbdk-lib/include/setjmp.h, 338	get_tiles
gbdk-lib/include/sms/bcd.h, 119	gb.h, 181
gbdk-lib/include/sms/gbdecompress.h, 187	get_vram_byte
gbdk-lib/include/sms/hardware.h, 222	gb.h, 159
gbdk-lib/include/sms/metasprites.h, 253	get_win_data
gbdk-lib/include/sms/sms.h, 339	gb.h, 170
gbdk-lib/include/stdarg.h, 98	get_win_tile_xy
gbdk-lib/include/stdatomic.h, 366	gb.h, 173
gbdk-lib/include/stdbool.h, 367	get_win_tiles
gbdk-lib/include/stddef.h, 367	gb.h, 173
gbdk-lib/include/stdint.h, 368	get_win_xy_addr
gbdk-lib/include/stdio.h, 374	gb.h, 169
gbdk-lib/include/stdlib.h, 375	msx.h, 282
gbdk-lib/include/stdnoreturn.h, 379	sms.h, 351
gbdk-lib/include/string.h, 109	getchar
gbdk-lib/include/time.h, 379	stdio.h, 375
gbdk-lib/include/typeof.h, 380	getpix
gbdk-lib/include/types.h, 115	drawing.h, 132
get_bkg_data	gets
gb.h, 161	stdio.h, 375
get_bkg_tile_xy	GGEXT_NINIT
gb.h, 168	hardware.h, 226
nes.h. 324	GGSTATE NJAP

	ALIDENIA DOMAL COE
hardware.h, 226	AUDENV_DOWN, 205
GGSTATE_NNTS	AUDENV_LENGTH, 205
hardware.h, 226	AUDENV_UP, 205
GGSTATE_STT	AUDENV_VOL, 204
hardware.h, 226	AUDHIGH_LENGTH_OFF, 205
gotogxy	AUDHIGH_LENGTH_ON, 205
drawing.h, 132	AUDHIGH_RESTART, 205
gotoxy	AUDLEN_DUTY_12_5, 204
console.h, 261	AUDLEN DUTY 25, 204
gprint	AUDLEN DUTY 50, 204
drawing.h, 130	AUDLEN DUTY 75, 204
gprintf	AUDLEN_LENGTH, 204
<u> </u>	
drawing.h, 130	AUDTERM_1_LEFT, 198
gprintln	AUDTERM_1_RIGHT, 198
drawing.h, 130	AUDTERM_2_LEFT, 198
gprintn	AUDTERM_2_RIGHT, 198
drawing.h, 130	AUDTERM_3_LEFT, 198
GRAPHICS_HEIGHT	AUDTERM_3_RIGHT, 198
drawing.h, 129	AUDTERM_4_LEFT, 198
GRAPHICS_WIDTH	AUDTERM_4_RIGHT, 198
drawing.h, 129	AUDVOL_VIN_LEFT, 198
GUN_P1_LATCH	AUDVOL_VIN_RIGHT, 198
hardware.h, 227	AUDVOL VOL LEFT, 197
GUN_P2_LATCH	AUDVOL_VOL_RIGHT, 197
hardware.h, 228	BCPD REG, 211
Transfer and Trans	BCPS REG, 211
h	BCPSF_AUTOINC, 203
_fixed, 88	BGP_REG, 210
gb.h, 184	
msx.h, 296	bkg_scroll_x, 222
sms.h, 365	bkg_scroll_y, 222
hardware.h	BKGF_BANKO, 202
_AUD3WAVERAM, 207	BKGF_BANK1, 202
	BKGF_CGB_PAL0, 202
_HRAM, 207	BKGF_CGB_PAL1, 202
_IO, 207	BKGF_CGB_PAL2, 202
_OAMRAM, 207	BKGF_CGB_PAL3, 202
_RAM, 207	BKGF_CGB_PAL4, 202
_RAMBANK, 207	BKGF_CGB_PAL5, 202
_SCRN0, 207	BKGF_CGB_PAL6, 202
_SCRN1, 207	BKGF_CGB_PAL7, 202
_SRAM, 207	BKGF_PRI, 202
_SYSTEM, 218	BKGF_XFLIP, 202
_VRAM, 207	BKGF_YFLIP, 202
_VRAM8000, 207	DEVICE_SCREEN_BUFFER_HEIGHT, 206, 220
_VRAM8800, 207	DEVICE_SCREEN_BUFFER_WIDTH, 206, 220
_VRAM9000, 207	DEVICE_SCREEN_HEIGHT, 206, 220
BYTES, 194, 213, 225	DEVICE SCREEN MAP ENTRY SIZE, 206, 221
BYTE_REG, 194, 213, 225	DEVICE_SCREEN_PX_HEIGHT, 206, 217, 221,
REG, 194, 219, 221, 222	
SHADOW_REG, 219	234 DEVICE SCREEN BY WIDTH 206 217 221
AUD1SWEEP_DOWN, 196	DEVICE_SCREEN_PX_WIDTH, 206, 217, 221,
AUD1SWEEP_LENGTH, 196	234
AUD1SWEEP_TIME, 196	DEVICE_SCREEN_WIDTH, 206, 220
	DEVICE_SCREEN_X_OFFSET, 206, 220
AUD1SWEEP_UP, 196	DEVICE_SCREEN_Y_OFFSET, 206, 220
AUD3WAVE, 209	DEVICE_SPRITE_PX_OFFSET_X, 206, 221
AUD4POLY_WIDTH_15BIT, 197	DEVICE_SPRITE_PX_OFFSET_Y, 206, 221
AUD4POLY_WIDTH_7BIT, 197	DEVICE_WINDOW_PX_OFFSET_X, 206, 221
AUDENA_OFF, 198	DEVICE_WINDOW_PX_OFFSET_Y, 206, 221
AUDENA_ON, 198	<del>_</del> · ·

DIV_REG, 208	JOY_P2_TH_DIR_OUT, 228
DMA REG, 210	JOY P2 TH OUT HI, 228
GGEXT_NINIT, 226	JOY P2 TH OUT LO, 228
GGSTATE_NJAP, 226	JOY_P2_TR_DIR_IN, 228
GGSTATE_NNTS, 226	JOY_P2_TR_DIR_OUT, 228
GGSTATE_STT, 226	JOY_P2_TR_OUT_HI, 228
GUN_P1_LATCH, 227	JOY_P2_TR_OUT_LO, 228
GUN_P2_LATCH, 228	JOY_P2_TRIGGER, 233
HDMA1 REG, 210	JOY P2 UP, 233
HDMA2 REG, 210	JOY_RESET, 233
HDMA3 REG, 211	
_ ·	JOY_TH_HI, 228
HDMA4_REG, 211	JOY_TH_LO, 228
HDMA5_REG, 211	KEY1_REG, 210
HDMA5F_BUSY, 203	KEY1F_DBLSPEED, 201
HDMA5F_MODE_GP, 203	KEY1F PREPARE, 201
HDMA5F_MODE_HBL, 203	LCDC REG, 209
IE REG, 211	LCDCF_B_BG8000, 199
IEF HILO, 204	LCDCF B BG9C00, 199
<del>-</del>	
IEF_SERIAL, 204	LCDCF_B_BGON, 200
IEF_STAT, 204	LCDCF_B_OBJ16, 200
IEF_TIMER, 204	LCDCF_B_OBJON, 200
IEF_VBLANK, 204	LCDCF_B_ON, 199
IF_REG, 208	LCDCF_B_WIN9C00, 199
JOY_P1_DOWN, 232	LCDCF_B_WINON, 199
JOY_P1_LEFT, 232	LCDCF_BG8000, 199
JOY_P1_LIGHT, 233	LCDCF_BG8800, 199
JOY_P1_MD_A, 232	LCDCF_BG9800, 199
JOY_P1_MD_MODE, 232	LCDCF_BG9C00, 199
JOY_P1_MD_START, 233	LCDCF_BGOFF, 199
JOY_P1_MD_X, 232	LCDCF_BGON, 199
JOY_P1_MD_Y, 232	LCDCF_OBJ16, 199
JOY_P1_MD_Z, 232	LCDCF_OBJ8, 199
JOY_P1_RIGHT, 232	LCDCF_OBJOFF, 199
JOY_P1_SW1, 232	LCDCF OBJON, 199
JOY_P1_SW2, 233	LCDCF_OFF, 198
JOY_P1_TH_DIR_IN, 227	LCDCF_ON, 198
JOY_P1_TH_DIR_OUT, 228	LCDCF_WIN9800, 198
JOY_P1_TH_OUT_HI, 228	LCDCF_WIN9C00, 199
JOY_P1_TH_OUT_LO, 228	LCDCF_WINOFF, 199
JOY_P1_TR_DIR_IN, 227	LCDCF_WINON, 199
JOY_P1_TR_DIR_OUT, 227	LY_REG, 210
JOY_P1_TR_OUT_HI, 228	LYC_REG, 210
JOY P1 TR OUT LO, 228	MEMCTL BASEOFF, 227
JOY P1 TRIGGER, 232	MEMCTL BASEON, 227
JOY_P1_UP, 232	MEMOTE_BROZON, 227
	<del>_</del>
JOY_P2_DOWN, 233	MEMCTL_CROMON, 227
JOY_P2_LEFT, 233	MEMCTL_EXTOFF, 227
JOY_P2_LIGHT, 233	MEMCTL_EXTON, 227
JOY_P2_MD_A, 233	MEMCTL_JOYOFF, 227
JOY_P2_MD_MODE, 233	MEMCTL_JOYON, 227
JOY_P2_MD_START, 233	MEMCTL_RAMOFF, 227
JOY_P2_MD_X, 233	MEMCTL RAMON, 227
JOY P2 MD Y, 233	MEMCTL ROMOFF, 227
JOY_P2_MD_Z, 233	MEMCTL_ROMON, 227
	<del>-</del>
JOY_P2_RIGHT, 233	NR10_REG, 208
JOY_P2_SW1, 233	NR11_REG, 208
JOY_P2_SW2, 233	NR12_REG, 208
JOY_P2_TH_DIR_IN, 228	NR13_REG, 208

NR14_REG, 208	PPUMASK GREEN, 220
NR21 REG, 208	PPUMASK MONOCHROME, 220
NR22 REG, 208	PPUMASK RED, 220
<del>-</del>	<u> </u>
NR23_REG, 208	PPUMASK_SHOW_BG, 220
NR24_REG, 209	PPUMASK_SHOW_BG_LC, 220
NR30_REG, 209	PPUMASK_SHOW_SPR, 220
NR31 REG, 209	PPUMASK SHOW SPR LC, 220
NR32 REG, 209	PSG_CH0, 213, 229
_ <i>,</i>	
NR33_REG, 209	PSG_CH1, 213, 229
NR34_REG, 209	PSG_CH2, 213, 229
NR41_REG, 209	PSG_CH3, 213, 229
NR42_REG, 209	PSG_LATCH, 213, 228
NR43_REG, 209	PSG_VOLUME, 214, 229
NR44 REG, 209	R0 CB INPUT, 214
NR50 REG, 209	R0 CB OUTPUT, 214
NR51_REG, 209	R0_DEFAULT, 214, 230
NR52_REG, 209	R0_ES, 214, 230
OAMF_BANK0, 205	R0_ES_OFF, 214, 230
OAMF_BANK1, 205	R0_HSCRL, 229
OAMF CGB PALO, 205	R0_HSCRL_INH, 229
OAMF CGB PAL1, 205	R0 IE1, 214, 229
:	R0_IE1_OFF, 214, 229
OAMF_CGB_PAL2, 205	
OAMF_CGB_PAL3, 205	R0_IE2, 214
OAMF_CGB_PAL4, 206	R0_IE2_OFF, 214
OAMF_CGB_PAL5, 206	R0_LCB, 229
OAMF_CGB_PAL6, 206	R0_NO_LCB, 229
OAMF_CGB_PAL7, 206	R0_SCR_MODE1, 214
OAMF_PAL0, 205	R0_SCR_MODE2, 214
OAMF PAL1, 205	R0_SCR_MODE3, 214
OAMF PALMASK, 206	R0_SS, 230
OAMF_PRI, 205	R0_SS_OFF, 230
OAMF_XFLIP, 205	R0_VSCRL, 229
OAMF_YFLIP, 205	R0_VSCRL_INH, 229
OBP0_REG, 210	R10_INT_EVERY, 217, 232
OBP1_REG, 210	R10_INT_OFF, 217, 232
OCPD_REG, 211	R1_DEFAULT, 215, 230
OCPS_REG, 211	R1 DISP OFF, 215, 230
OCPSF_AUTOINC, 203	R1_DISP_ON, 215, 230
P1_REG, 208	R1 IE, 215, 230
	<del>-</del>
P1F_0, 194	R1_IE_OFF, 215, 230
P1F_1, 194	R1_SCR_MODE1, 215
P1F_2, 194	R1_SCR_MODE2, 215
P1F_3, 194	R1_SCR_MODE3, 215
P1F_4, 194	R1_SPR_16X16, 215
P1F 5, 194	R1 SPR 8X16, 230
P1F_GET_BTN, 194	R1 SPR 8X8, 215, 230
P1F GET DPAD, 194	R1 SPR MAG, 215
P1F GET NONE, 195	R1_SPR_MAG_OFF, 215
PCM12_REG, 211	R2_MAP_0x0000, 216, 231
PCM34_REG, 211	R2_MAP_0x0800, 216, 231
PCM_SAMPLE, 209	R2_MAP_0x1000, 216, 231
PPUCTRL_BG_CHR, 220	R2_MAP_0x1800, 216, 231
PPUCTRL_INC32, 220	R2_MAP_0x2000, 215, 230
PPUCTRL NMI, 219	R2_MAP_0x2800, 215, 230
PPUCTRL SPR 8X16, 220	R2_MAP_0x3000, 215, 230
PPUCTRL SPR 8X8, 219	R2_MAP_0x3800, 215, 230
PPUCTRL SPR CHR, 220	
	R5_SAT_0x1F00, 231
PPUMASK_BLUE, 220	R5_SAT_0x3F00, 216, 231

R5_SAT_MASK, 216, 231	RPF_WRITE_HI, 203
R6 BANK0, 216, 231	RPF WRITE LO, 203
R6_BANK1, 216, 231	rRAMB, 207
R6_DATA_0x0000, 216, 231	rRAMG, 207
R6_DATA_0x2000, 216, 231	rROMB0, 207
R7_COLOR_MASK, 216, 231	rROMB1, 207
RAMCTL_BANK, 234	rRP, 203
RAMCTL_PROT, 234	rSB, 195
RAMCTL_RAM, 234	rSC, 195
RAMCTL_RO, 234	rSCX, 201
RAMCTL ROM, 234	rSCY, 201
rAUD1ENV, 196	rSMBK, 204
rAUD1HIGH, 196	rSPD, 201
rAUD1LEN, 196	rSTAT, 200
rAUD1LOW, 196	rSVBK, 204
rAUD1SWEEP, 196	rTAC, 195
rAUD2ENV, 197	rTIMA, 195
rAUD2HIGH, 197	rTMA, 195
rAUD2LEN, 196	rVBK, 202
rAUD2LOW, 197	rWX, 201
rAUD3ENA, 197	rWY, 201
•	
rAUD3HIGH, 197	SB_REG, 208
rAUD3LEN, 197	SC_REG, 208
rAUD3LEVEL, 197	SCF_SOURCE, 195
rAUD3LOW, 197	SCF_SPEED, 195
rAUD4ENV, 197	SCF_START, 195
rAUD4GO, 197	SCX_REG, 210
rAUD4LEN, 197	SCY_REG, 209
rAUD4POLY, 197	shadow PPUCTRL, 222
rAUDENA, 198	shadow PPUMASK, 222
•	<del>-</del>
rAUDTERM, 198	shadow_VDP_R0, 217, 234
rAUDVOL, 197	shadow_VDP_R1, 217, 234
rBCPD, 203	shadow_VDP_R10, 218, 235
rBCPS, 203	shadow_VDP_R2, 217, 234
DOD 004	
rBGP, 201	shadow_VDP_R3, 217, 234
rBGP, 201 rDIV, 195	shadow_VDP_R3, 217, 234 shadow_VDP_R4, 218, 234
rDIV, 195	shadow_VDP_R4, 218, 234
rDIV, 195 rDMA, 201	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234
rDIV, 195 rDMA, 201 rHDMA1, 203	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA4, 203	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA4, 203 rHDMA5, 203	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA4, 203 rHDMA5, 203 rIE, 204	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA4, 203 rHDMA5, 203 rIE, 204 rIF, 196	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA4, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA4, 203 rHDMA5, 203 rIE, 204 rIF, 196	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA4, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235 SHOCTL_BSO, 226
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA4, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201 rLCDC, 198 rLY, 201	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235 SIOCTL_BS0, 226 SIOCTL_BS1, 226 SIOCTL_FRER, 226
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA4, 203 rHDMA5, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201 rLCDC, 198 rLY, 201 rLYC, 201	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235 shadow_VDP_RSCY, 218, 235 SIOCTL_BS0, 226 SIOCTL_BS1, 226 SIOCTL_FRER, 226 SIOCTL_INT, 226
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA4, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201 rLCDC, 198 rLY, 201 rLYC, 201 rOBP0, 201	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235 shadow_VDP_RSCY, 218, 235 SIOCTL_BS0, 226 SIOCTL_BS1, 226 SIOCTL_FRER, 226 SIOCTL_INT, 226 SIOCTL_RON, 226
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA4, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201 rLCDC, 198 rLY, 201 rLYC, 201 rOBP0, 201 rOBP1, 201	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235 shadow_VDP_RSCY, 218, 235 SIOCTL_BS0, 226 SIOCTL_BS1, 226 SIOCTL_FRER, 226 SIOCTL_INT, 226 SIOCTL_RON, 226 SIOCTL_RXRD, 226
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA4, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201 rLCDC, 198 rLY, 201 rLYC, 201 rOBP0, 201 rOBP1, 201 rOCPD, 204	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235 shadow_VDP_RSCY, 218, 235 SIOCTL_BS0, 226 SIOCTL_BS1, 226 SIOCTL_FRER, 226 SIOCTL_INT, 226 SIOCTL_RON, 226 SIOCTL_RXRD, 226 SIOCTL_TON, 226
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA4, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201 rLCDC, 198 rLY, 201 rLYC, 201 rOBP0, 201 rOBP1, 201 rOCPD, 204 rOCPS, 203	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R6, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235 sloCTL_BS0, 226 SIOCTL_BS1, 226 SIOCTL_FRER, 226 SIOCTL_FRER, 226 SIOCTL_RON, 226 SIOCTL_RXRD, 226 SIOCTL_TON, 226 SIOCTL_TXFL, 226
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA5, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201 rLCDC, 198 rLY, 201 rLYC, 201 rOBP0, 201 rOBP1, 201 rOCPD, 204 rOCPS, 203 rP1, 194	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R6, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235 shadow_VDP_RSCY, 218, 235 SIOCTL_BS0, 226 SIOCTL_BS1, 226 SIOCTL_FRER, 226 SIOCTL_INT, 226 SIOCTL_RON, 226 SIOCTL_RXRD, 226 SIOCTL_TXFL, 226 SIOCTL_TXFL, 226 SIOF_B_CLOCK, 195
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA5, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201 rLCDC, 198 rLY, 201 rLYC, 201 rOBP0, 201 rOBP1, 201 rOCPD, 204 rOCPS, 203 rP1, 194 RP_REG, 211	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R6, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235 shadow_VDP_RSCY, 218, 235 SIOCTL_BS0, 226 SIOCTL_BS1, 226 SIOCTL_FRER, 226 SIOCTL_INT, 226 SIOCTL_RXRD, 226 SIOCTL_TON, 226 SIOCTL_TON, 226 SIOCTL_TXFL, 226 SIOCTL_TXFL, 226 SIOF_B_CLOCK, 195 SIOF_B_SPEED, 195
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA5, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201 rLCDC, 198 rLY, 201 rLYC, 201 rOBP0, 201 rOBP1, 201 rOCPD, 204 rOCPS, 203 rP1, 194 RP_REG, 211 rPCM12, 204	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235 shadow_VDP_RSCY, 218, 235 SIOCTL_BS0, 226 SIOCTL_BS1, 226 SIOCTL_FRER, 226 SIOCTL_INT, 226 SIOCTL_RXRD, 226 SIOCTL_TON, 226 SIOCTL_TXFL, 226 SIOCTL_TXFL, 226 SIOF_B_CLOCK, 195 SIOF_B_SPEED, 195 SIOF_B_XFER_START, 195
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA5, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201 rLCDC, 198 rLY, 201 rLYC, 201 rOBP0, 201 rOBP1, 201 rOCPD, 204 rOCPS, 203 rP1, 194 RP_REG, 211	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R6, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235 shadow_VDP_RSCY, 218, 235 SIOCTL_BS0, 226 SIOCTL_BS1, 226 SIOCTL_FRER, 226 SIOCTL_INT, 226 SIOCTL_RXRD, 226 SIOCTL_TON, 226 SIOCTL_TON, 226 SIOCTL_TXFL, 226 SIOCTL_TXFL, 226 SIOF_B_CLOCK, 195 SIOF_B_SPEED, 195
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA5, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201 rLCDC, 198 rLY, 201 rLYC, 201 rOBP0, 201 rOBP1, 201 rOCPD, 204 rOCPS, 203 rP1, 194 RP_REG, 211 rPCM12, 204	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235 shadow_VDP_RSCY, 218, 235 SIOCTL_BS0, 226 SIOCTL_BS1, 226 SIOCTL_FRER, 226 SIOCTL_INT, 226 SIOCTL_RXRD, 226 SIOCTL_TON, 226 SIOCTL_TXFL, 226 SIOCTL_TXFL, 226 SIOF_B_CLOCK, 195 SIOF_B_SPEED, 195 SIOF_B_XFER_START, 195
rDIV, 195 rDMA, 201 rHDMA1, 203 rHDMA2, 203 rHDMA3, 203 rHDMA5, 203 rHDMA5, 203 rIE, 204 rIF, 196 rKEY1, 201 rLCDC, 198 rLY, 201 rLYC, 201 rOBP0, 201 rOBP1, 201 rOCPD, 204 rOCPS, 203 rP1, 194 RP_REG, 211 rPCM12, 204 rPCM34, 204	shadow_VDP_R4, 218, 234 shadow_VDP_R5, 218, 234 shadow_VDP_R6, 218, 234 shadow_VDP_R7, 218, 235 shadow_VDP_R8, 218, 235 shadow_VDP_R9, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RBORDER, 218, 235 shadow_VDP_RSCX, 218, 235 shadow_VDP_RSCY, 218, 235 shadow_VDP_RSCY, 218, 235 SIOCTL_BS0, 226 SIOCTL_BS1, 226 SIOCTL_FRER, 226 SIOCTL_INT, 226 SIOCTL_RXRD, 226 SIOCTL_TXFL, 226 SIOCTL_TXFL, 226 SIOCTL_TXFL, 226 SIOF_B_CLOCK, 195 SIOF_B_SPEED, 195 SIOF_B_XFER_START, 195 SIOF_CLOCK_EXT, 195

SIOF_SPEED_32X, 195	VDP_R7, 216, 231
SIOF_XFER_START, 195	VDP_R8, 216, 232
SOUNDPAN_NOSL, 227	VDP_R9, 217, 232
SOUNDPAN_NOSR, 226	VDP_RBORDER, 216, 231
SOUNDPAN TN1L, 226	VDP REG MASK, 214, 229
SOUNDPAN TN1R, 226	VDP RSCX, 217, 232
SOUNDPAN TN2L, 226	VDP RSCY, 217, 232
SOUNDPAN TN2R, 226	VDP SAT TERM, 217, 234
SOUNDPAN TN3L, 227	WX REG, 210
SOUNDPAN_TN3R, 226	WY_REG, 210
STAT REG, 209	HARDWARE_SPRITE_CAN_FLIP_X
STATE 9 SPR, 214, 229	
' '	gb.h, 151
STATE BLVC 200	msx.h, 282
STATE B LYCE 200	nes.h, 309
STATF_B_LYCF, 201	sms.h, 350
STATF_B_MODE00, 200	HARDWARE_SPRITE_CAN_FLIP_Y
STATF_B_MODE01, 200	gb.h, 151
STATF_B_MODE10, 200	msx.h, 282
STATF_B_OAM, 201	nes.h, 309
STATF_B_VBL, 201	sms.h, 350
STATF_BUSY, 200	hblank_copy
STATF_HBL, 200	hblankcpy.h, 236
STATF_INT_VBL, 214, 229	hblank_copy_destination
STATE LCD, 200	hblankcpy.h, 236
STATE LYC, 200	hblank_copy_vram
STATE LYCE, 200	hblankcpy.h, 235
STATE MODE00, 200	hblank_cpy_vram
STATE MODE01, 200	hblankcpy.h, 236
STATE MODE10, 200	hblankcpy.h
STATE OAM, 200	hblank_copy, 236
STATF_SPR_COLL, 214, 229	hblank_copy_destination, 236
STATE VBL, 200	hblank_copy_vram, 235
SVBK REG, 211	hblank cpy vram, 236
SYSTEM_NTSC, 217	HDMA1_REG
SYSTEM_PAL, 217	hardware.h, 210
TAC_REG, 208	HDMA2_REG
TACF_16KHZ, 196	hardware.h, 210
TACF_262KHZ, 196	HDMA3_REG
TACF_4KHZ, 196	hardware.h, 211
TACF_65KHZ, 196	HDMA4_REG
TACF_START, 196	hardware.h, 211
TACF_STOP, 196	HDMA5_REG
TIMA_REG, 208	hardware.h, 211
TMA_REG, 208	HDMA5F_BUSY
VBK_ATTRIBUTES, 202, 217, 234	hardware.h, 203
VBK_BANK_0, 202	HDMA5F_MODE_GP
VBK BANK 1, 202	hardware.h, 203
VBK REG, 210	HDMA5F_MODE_HBL
VBK TILES, 202, 217, 234	hardware.h, 203
VDP_ATTR_SHIFT, 218, 235	HIDE_BKG
VDP_R0, 214, 229	gb.h, 150
VDP_R1, 215, 230	msx.h, 279
VDP_R10, 217, 232	nes.h, 308
VDP_R10, 217, 232 VDP_R2, 215, 230	
	sms.h, 347
VDP_R3, 216, 231	HIDE_LEFT_COLUMN
VDP_R4, 216, 231	gb.h, 150
VDP_R5, 216, 231	msx.h, 279
VDP_R6, 216, 231	nes.h, 307

sms.h, 347	stdint.h, 371
hide_metasprite	INT16_MAX
metasprites.h, 244, 247, 252, 257	stdint.h, 370
hide_sprite	INT16_MIN
gb.h, 178	stdint.h, 369
msx.h, 295	int16 t
nes.h, 330	stdint.h, 372
sms.h, 363	INT32
HIDE_SPRITES	types.h, 110, 111, 114
gb.h, 150	INT32_C
msx.h, 279	stdint.h, 372
nes.h, 308	INT32_MAX
sms.h, 347	stdint.h, 370
hide_sprites_range	INT32_MIN
metasprites.h, 241, 246, 249, 255	stdint.h, 369
HIDE WIN	int32 t
 gb.h, 150	stdint.h, 372
msx.h, 279	INT8
sms.h, 347	types.h, 110, 111, 114
hiramcpy	INT8_C
gb.h, 159	stdint.h, 371
IE DEC	INT8_MAX
IE_REG	stdint.h, 369
hardware.h, 211	INT8_MIN
IEF_HILO	stdint.h, 369
hardware.h, 204	int8 t
IEF_SERIAL	stdint.h, 372
hardware.h, 204	INT FAST16 MAX
IEF STAT	
hardware.h, 204	stdint.h, 371
IEF TIMER	INT_FAST16_MIN
<del>-</del>	stdint.h, 370
hardware.h, 204	int_fast16_t
IEF_VBLANK	stdint.h, 373
hardware.h, 204	INT_FAST32_MAX
IF_REG	stdint.h, 371
hardware.h, 208	INT FAST32 MIN
INCBIN	stdint.h, 370
incbin.h, 268	int_fast32_t
incbin.h	stdint.h, 373
BANK, 268	•
INCBIN, 268	INT_FAST8_MAX
INCBIN EXTERN, 267	stdint.h, 370
INCBIN SIZE, 268	INT_FAST8_MIN
_ <i>′</i>	stdint.h, 370
INCBIN_EXTERN	int_fast8_t
incbin.h, 267	stdint.h, 373
INCBIN_SIZE	int_handler
incbin.h, 268	gb.h, 151
init_bkg	msx.h, 282
gb.h, 183	nes.h, 309
nes.h, 334	sms.h, 351
init win	INT_LEAST16_MAX
gb.h, 182	stdint.h, 370
initarand	
rand.h, 338	INT_LEAST16_MIN
	stdint.h, 370
initrand	int_least16_t
rand.h, 337	stdint.h, 373
INT16	INT_LEAST32_MAX
types.h, 110, 111, 114	stdint.h, 370
INT16_C	•

INT_LEAST32_MIN	opcode, 89
stdint.h, 370	ISR_VECTOR
int_least32_t	isr.h, 237
stdint.h, 373	isr_vector_t, 89
INT_LEAST8_MAX	func, 90
stdint.h, 370	isr.h, 238
INT LEAST8 MIN	opcode, 90
stdint.h, 370	isspace
int_least8_t	ctype.h, 117
stdint.h, 373	isupper
INT MAX	ctype.h, 116
limits.h, 271	itoa
INT MIN	
<del>_</del>	stdlib.h, 377
limits.h, 271	iyh
INTERRUPT	msx.h, 296
types.h, 113	sms.h, 365
INTMAX_C	iyl
stdint.h, 372	metasprites.h, 247, 258
INTMAX_MAX	msx.h, 296
stdint.h, 371	sms.h, 365
INTMAX_MIN	
stdint.h, 371	J_A
intmax_t	gb.h, 141
stdint.h, 373	msx.h, 276
INTPTR_MAX	nes.h, 303
stdint.h, 371	sms.h, 344
INTPTR MIN	J_B
stdint.h, 371	gb.h, 141
intptr_t	msx.h, 276
stdint.h, 373	nes.h, 303
IO ERROR	sms.h, 344
gb.h, 146	J_DOWN
IO IDLE	gb.h, 141
gb.h, 146	msx.h, 276
IO RECEIVING	nes.h, 303
<del>-</del>	sms.h, 344
gb.h, 146 IO_SENDING	J LEFT
	gb.h, 141
gb.h, 146	msx.h, 276
isalpha	nes.h, 303
ctype.h, 116	sms.h, 344
isdigit	J_RIGHT
ctype.h, 117	gb.h, 141
islower	_
ctype.h, 117	msx.h, 276
isr.h	nes.h, 303
ISR_NESTED_VECTOR, 238	sms.h, 344
isr_nested_vector_t, 238	J_SELECT
ISR_VECTOR, 237	gb.h, 141
isr_vector_t, 238	msx.h, 276
VECTOR JOYPAD, 237	nes.h, <mark>303</mark>
VECTOR SERIAL, 237	sms.h, 344
VECTOR STAT, 237	J_START
VECTOR TIMER, 237	gb.h, 141
ISR_NESTED_VECTOR	msx.h, 276
isr.h, 238	nes.h, 303
isr_nested_vector_t, 89	sms.h, 344
func, 89	J_UP
	gb.h, 141
isr.h, 238	msx.h, 276
	, =

nes.h, 303	JOY P1 UP
sms.h, 343	hardware.h, 232
jmp_buf	JOY P2 DOWN
setjmp.h, 339	hardware.h, 233
joy0	JOY P2 LEFT
joypads t, 91	hardware.h, 233
joy1	JOY P2 LIGHT
joypads t, 91	hardware.h, 233
joy2	JOY P2 MD A
joypads_t, 91	 hardware.h, 233
joy3	JOY P2 MD MODE
joypads_t, 91	hardware.h, 233
JOY_IFLAG	JOY_P2_MD_START
gb.h, 143	hardware.h, 233
msx.h, 278	JOY_P2_MD_X
sms.h, 346	hardware.h, 233
JOY_P1_DOWN	JOY_P2_MD_Y
hardware.h, 232	hardware.h, 233
JOY_P1_LEFT	JOY_P2_MD_Z
hardware.h, 232	hardware.h, 233
JOY_P1_LIGHT	JOY_P2_RIGHT
hardware.h, 233	hardware.h, 233
JOY_P1_MD_A	JOY_P2_SW1
hardware.h, 232	hardware.h, 233
JOY_P1_MD_MODE	JOY_P2_SW2
hardware.h, 232	hardware.h, 233
JOY_P1_MD_START	JOY_P2_TH_DIR_IN
hardware.h, 233	hardware.h, 228
JOY_P1_MD_X	JOY_P2_TH_DIR_OUT
hardware.h, 232	hardware.h, 228
JOY_P1_MD_Y	JOY_P2_TH_OUT_HI
hardware.h, 232	hardware.h, 228
JOY_P1_MD_Z	JOY_P2_TH_OUT_LO
hardware.h, 232	hardware.h, 228
JOY_P1_RIGHT	JOY_P2_TR_DIR_IN
hardware.h, 232	hardware.h, 228
JOY_P1_SW1	JOY_P2_TR_DIR_OUT
hardware.h, 232	hardware.h, 228
JOY_P1_SW2	JOY_P2_TR_OUT_HI
hardware.h, 233	hardware.h, 228
JOY_P1_TH_DIR_IN hardware.h, 227	JOY_P2_TR_OUT_LO hardware.h, 228
JOY P1 TH DIR OUT	JOY P2 TRIGGER
hardware.h, 228	hardware.h, 233
JOY P1 TH OUT HI	JOY P2 UP
hardware.h, 228	hardware.h, 233
JOY P1 TH OUT LO	JOY RESET
hardware.h, 228	hardware.h, 233
JOY P1 TR DIR IN	JOY TH HI
hardware.h, 227	hardware.h, 228
JOY_P1_TR_DIR_OUT	JOY TH LO
hardware.h, 227	hardware.h, 228
JOY P1 TR OUT HI	joypad
hardware.h, 228	gb.h, 156
JOY P1 TR OUT LO	msx.h, 286
hardware.h, 228	nes.h, 312
JOY_P1_TRIGGER	sms.h, 353
hardware.h, 232	joypad_ex
	<del>-</del>

gb.h, 157	LCDCF_BG9800
msx.h, 286	hardware.h, 199
nes.h, 313	LCDCF BG9C00
sms.h, 354	hardware.h, 199
joypad init	LCDCF BGOFF
gb.h, 157	hardware.h, 199
msx.h, 286	LCDCF BGON
	<del>-</del>
nes.h, 312	hardware.h, 199
sms.h, 354	LCDCF_OBJ16
joypads	hardware.h, 199
joypads_t, 91	LCDCF_OBJ8
joypads_t, 90	hardware.h, 199
joy0, <mark>91</mark>	LCDCF_OBJOFF
joy1, 91	hardware.h, 199
joy2, 91	LCDCF OBJON
joy3, 91	hardware.h, 199
	LCDCF OFF
joypads, 91	<del>-</del>
npads, 91	hardware.h, 198
KEVA DEO	LCDCF_ON
KEY1_REG	hardware.h, 198
hardware.h, 210	LCDCF_WIN9800
KEY1F_DBLSPEED	hardware.h, 198
hardware.h, 201	LCDCF WIN9C00
KEY1F_PREPARE	hardware.h, 199
hardware.h, 201	LCDCF WINOFF
	hardware.h, 199
_fixed, 88	LCDCF_WINON
gb.h, 184	hardware.h, 199
<del>-</del>	limits.h
msx.h, 296	CHAR_BIT, 270
sms.h, 365	CHAR_MAX, 271
labs	CHAR MIN, 271
stdlib.h, 376	INT MAX, 271
LCD_IFLAG	INT MIN, 271
gb.h, 143	LONG MAX, 271
msx.h, 277	<del>-</del> '
	I ONG MINI 971
sms.h. 345	LONG_MIN, 271
sms.h, 345	SCHAR_MAX, 270
LCDC_REG	SCHAR_MAX, 270 SCHAR_MIN, 271
LCDC_REG hardware.h, 209	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271
LCDC_REG hardware.h, 209 LCDCF_B_BG8000	SCHAR_MAX, 270 SCHAR_MIN, 271
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MAX, 271
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MAX, 271 UINT_MIN, 271
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00 hardware.h, 199	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00 hardware.h, 199 LCDCF_B_BGON hardware.h, 200	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00 hardware.h, 199 LCDCF_B_BGON hardware.h, 200 LCDCF_B_OBJ16	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 USHRT_MAX, 271
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00 hardware.h, 199 LCDCF_B_BGON hardware.h, 200 LCDCF_B_OBJ16 hardware.h, 200	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 USHRT_MAX, 271 USHRT_MIN, 271
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00 hardware.h, 199 LCDCF_B_BGON hardware.h, 200 LCDCF_B_OBJ16 hardware.h, 200 LCDCF_B_OBJON	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 USHRT_MAX, 271 USHRT_MIN, 271
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00 hardware.h, 199 LCDCF_B_BGON hardware.h, 200 LCDCF_B_OBJ16 hardware.h, 200 LCDCF_B_OBJON hardware.h, 200	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 USHRT_MAX, 271 USHRT_MIN, 271 line drawing.h, 131
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00 hardware.h, 199 LCDCF_B_BGON hardware.h, 200 LCDCF_B_OBJ16 hardware.h, 200 LCDCF_B_OBJON hardware.h, 200 LCDCF_B_OBJON LCDCF_B_OBJON LCDCF_B_OBJON LCDCF_B_ON	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 USHRT_MAX, 271 USHRT_MIN, 271 line drawing.h, 131 List of gbdk fonts, 87
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00 hardware.h, 199 LCDCF_B_BGON hardware.h, 200 LCDCF_B_OBJ16 hardware.h, 200 LCDCF_B_OBJON hardware.h, 200 LCDCF_B_OBJON hardware.h, 200 LCDCF_B_OBJON hardware.h, 199	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 USHRT_MAX, 271 USHRT_MIN, 271 line drawing.h, 131
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00 hardware.h, 199 LCDCF_B_BGON hardware.h, 200 LCDCF_B_OBJ16 hardware.h, 200 LCDCF_B_OBJON hardware.h, 200 LCDCF_B_OBJON hardware.h, 199 LCDCF_B_ON hardware.h, 199 LCDCF_B_WIN9C00	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 USHRT_MAX, 271 USHRT_MIN, 271 line drawing.h, 131 List of gbdk fonts, 87
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00 hardware.h, 199 LCDCF_B_BGON hardware.h, 200 LCDCF_B_OBJ16 hardware.h, 200 LCDCF_B_OBJON hardware.h, 200 LCDCF_B_OBJON hardware.h, 200 LCDCF_B_OBJON hardware.h, 199	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 ULONG_MIN, 271 USHRT_MAX, 271 USHRT_MIN, 271 line drawing.h, 131 List of gbdk fonts, 87 font_ibm, 87 font_ibm_fixed, 87
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00 hardware.h, 199 LCDCF_B_BGON hardware.h, 200 LCDCF_B_OBJ16 hardware.h, 200 LCDCF_B_OBJON hardware.h, 200 LCDCF_B_OBJON hardware.h, 199 LCDCF_B_ON hardware.h, 199 LCDCF_B_WIN9C00	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 ULONG_MIN, 271 USHRT_MAX, 271 USHRT_MIN, 271 line drawing.h, 131 List of gbdk fonts, 87 font_ibm, 87 font_ibm_fixed, 87 font_italic, 87
LCDC_REG hardware.h, 209  LCDCF_B_BG8000 hardware.h, 199  LCDCF_B_BG9C00 hardware.h, 199  LCDCF_B_BGON hardware.h, 200  LCDCF_B_OBJ16 hardware.h, 200  LCDCF_B_OBJON hardware.h, 200  LCDCF_B_OBJON hardware.h, 199  LCDCF_B_ON hardware.h, 199  LCDCF_B_WIN9C00 hardware.h, 199	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 ULONG_MIN, 271 USHRT_MAX, 271 USHRT_MIN, 271 line drawing.h, 131 List of gbdk fonts, 87 font_ibm_fixed, 87 font_italic, 87 font_min, 87
LCDC_REG hardware.h, 209  LCDCF_B_BG8000 hardware.h, 199  LCDCF_B_BG9C00 hardware.h, 199  LCDCF_B_BGON hardware.h, 200  LCDCF_B_OBJ16 hardware.h, 200  LCDCF_B_OBJON hardware.h, 200  LCDCF_B_OBJON hardware.h, 199  LCDCF_B_WIN9C00 hardware.h, 199  LCDCF_B_WINON hardware.h, 199	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 ULONG_MIN, 271 USHRT_MAX, 271 USHRT_MIN, 271 line drawing.h, 131 List of gbdk fonts, 87 font_ibm_fixed, 87 font_ibm_fixed, 87 font_min, 87 font_spect, 87
LCDC_REG hardware.h, 209  LCDCF_B_BG8000 hardware.h, 199  LCDCF_B_BG9C00 hardware.h, 199  LCDCF_B_BGON hardware.h, 200  LCDCF_B_OBJ16 hardware.h, 200  LCDCF_B_OBJON hardware.h, 200  LCDCF_B_OBJON hardware.h, 199  LCDCF_B_WIN9C00 hardware.h, 199  LCDCF_B_WINON hardware.h, 199  LCDCF_B_WINON hardware.h, 199  LCDCF_BG8000	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MIN, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 USHRT_MIN, 271 USHRT_MIN, 271 line drawing.h, 131 List of gbdk fonts, 87 font_ibm_fixed, 87 font_ibm_fixed, 87 font_min, 87 font_spect, 87 LONG_MAX
LCDC_REG hardware.h, 209 LCDCF_B_BG8000 hardware.h, 199 LCDCF_B_BG9C00 hardware.h, 199 LCDCF_B_BGON hardware.h, 200 LCDCF_B_OBJ16 hardware.h, 200 LCDCF_B_OBJON hardware.h, 200 LCDCF_B_OBJON hardware.h, 199 LCDCF_B_NON hardware.h, 199 LCDCF_B_WIN9C00 hardware.h, 199 LCDCF_B_WINON hardware.h, 199 LCDCF_B_BO8000 hardware.h, 199	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 USHRT_MIN, 271 USHRT_MIN, 271 Iine drawing.h, 131 List of gbdk fonts, 87 font_ibm, 87 font_ibm_fixed, 87 font_min, 87 font_spect, 87 LONG_MAX limits.h, 271
LCDC_REG hardware.h, 209  LCDCF_B_BG8000 hardware.h, 199  LCDCF_B_BG9C00 hardware.h, 199  LCDCF_B_BGON hardware.h, 200  LCDCF_B_OBJ16 hardware.h, 200  LCDCF_B_OBJON hardware.h, 200  LCDCF_B_OBJON hardware.h, 199  LCDCF_B_WIN9C00 hardware.h, 199  LCDCF_B_WINON hardware.h, 199  LCDCF_B_WINON hardware.h, 199  LCDCF_BG8000	SCHAR_MAX, 270 SCHAR_MIN, 271 SHRT_MAX, 271 SHRT_MIN, 271 UCHAR_MAX, 271 UINT_MIN, 271 UINT_MIN, 271 ULONG_MAX, 271 ULONG_MIN, 271 USHRT_MIN, 271 USHRT_MIN, 271 line drawing.h, 131 List of gbdk fonts, 87 font_ibm_fixed, 87 font_ibm_fixed, 87 font_min, 87 font_spect, 87 LONG_MAX

limita h. 071	otring b 101 105 100
limits.h, 271 longjmp	string.h, 101, 105, 109
setjmp.h, 339	memcpy string.h, 98, 103, 107
LTGREY	MEMCTL_BASEOFF
drawing.h, 129	hardware.h, 227
Itoa	MEMCTL_BASEON
stdlib.h, 377	hardware.h, 227
LWORD	MEMCTL_CROMOFF
types.h, 113	hardware.h, 227
LY_REG	MEMCTL_CROMON
hardware.h, 210	hardware.h, 227
LYC_REG	MEMCTL_EXTOFF
hardware.h, 210	hardware.h, 227
M DRAWING	MEMCTL_EXTON
M_DRAWING gb.h, 141	hardware.h, 227
nes.h, 303	MEMCTL_JOYOFF
M FILL	hardware.h, 227
drawing.h, 129	MEMCTL_JOYON
M_NO_INTERP	hardware.h, 227
gb.h, 142	MEMCTL_RAMOFF hardware.h, 227
msx.h, 276	MEMCTL_RAMON
nes.h, 304	hardware.h, 227
sms.h, 344	MEMCTL_ROMOFF
M_NO_SCROLL	hardware.h, 227
gb.h, 141	MEMCTL ROMON
msx.h, 276	hardware.h, 227
nes.h, 304	memmove
sms.h, 344	string.h, 100, 103, 107
M_NOFILL	memset
drawing.h, 129	string.h, 100, 103, 107
M_TEXT_INOUT	METASPR_ITEM
gb.h, 141	metasprites.h, 240, 246, 249, 254
msx.h, 276 nes.h, 303	METASPR_TERM
sms.h, 344	metasprites.h, 240, 246, 249, 254
M_TEXT_OUT	metasprite_end
gb.h, 141	metasprites.h, 240, 245, 249, 254
msx.h, 276	metasprite_t, 91
nes.h, 303	dtile, 93
sms.h, 344	dx, 93 dy, 93
MAKE BCD	metasprites.h, 240, 246, 249, 254
bcd.h, 118, 120	props, 93
malloc	metasprites.h
stdlib.h, 378	current_base_prop, 245, 253
MAX_HARDWARE_SPRITES	current_base_tile, 245, 247, 253, 258
gb.h, 151	current_metasprite, 244, 247, 253, 258
msx.h, 282	render_shadow_OAM, 245, 247, 253, 258
nes.h, 309	hide_metasprite, 244, 247, 252, 257
sms.h, 350	hide_sprites_range, 241, 246, 249, 255
MAXWNDPOSX	iyl, 247, 258
gb.h, 144	METASPR_ITEM, 240, 246, 249, 254
msx.h, 278	METASPR_TERM, 240, 246, 249, 254
sms.h, 346	metasprite_end, 240, 245, 249, 254
MAXWNDPOSY	metasprite_t, 240, 246, 249, 254
gb.h, 145 msx.h, 278	move_metasprite, 242, 247, 250, 255
sms.h, 346	move_metasprite_ex, 241, 246, 249, 255
memcmp	move_metasprite_flipx, 242, 250, 255
momority	

move_metasprite_flipxy, 243, 252, 257	_current_2bpp_palette, 297
move_metasprite_flipy, 243, 251, 256	_current_bank, 296
move_metasprite_hflip, 243, 251	_map_tile_offset, 297
move_metasprite_hvflip, 244, 252	_shadow_OAM_OFF, 297
move_metasprite_vflip, 242, 251	_shadow_OAM_base, 297
mfont_handle	_submap_tile_offset, 297
font.h, 266	add_JOY, 284
MGB TYPE	add_LCD, 284
gb.h, 145	add_SIO, 284
_	
MINWNDPOSX	add_TIM, 284
gb.h, 144	add_VBL, 284
msx.h, 278	b, 297
sms.h, 346	BANK, 280
MINWNDPOSY	BANKREF, 280
gb.h, 144	BANKREF_EXTERN, 280
msx.h, 278	c, 296
sms.h, 346	cancel_pending_interrupts, 285
mode	COMPAT_PALETTE, 282
gb.h, 155	cpu_fast, 287
msx.h, 283	CURRENT BANK, 280
nes.h, 311	d, 296
sms.h, 351	delay, 286
	• •
move_bkg	DEVICE_SUPPORTS_COLOR, 280
gb.h, 168	disable_interrupts, 287
msx.h, 285	DISABLE_RAM, 281
nes.h, 324	DISABLE_VBL_TRANSFER, 282
sms.h, 353	DISPLAY_OFF, 279
move_metasprite	display_off, 285
metasprites.h, 242, 247, 250, 255	DISPLAY_ON, 278
move_metasprite_ex	DIV_REG, 280
metasprites.h, 241, 246, 249, 255	e, 296
move_metasprite_flipx	EMPTY_IFLAG, 277
metasprites.h, 242, 250, 255	enable_interrupts, 286
move metasprite flipxy	ENABLE RAM, 281
metasprites.h, 243, 252, 257	ENABLE_VBL_TRANSFER, 282
move_metasprite_flipy	fill_bkg_rect, 282
	— <del>-</del>
metasprites.h, 243, 251, 256	fill_rect, 291
move_metasprite_hflip	fill_win_rect, 282
metasprites.h, 243, 251	get_bkg_xy_addr, 296
move_metasprite_hvflip	get_mode, 283
metasprites.h, 244, 252	get_r_reg, 285
move_metasprite_vflip	get_sprite_prop, 294
metasprites.h, 242, 251	get_sprite_tile, 292
move_sprite	get_system, 283
gb.h, 177	get_win_xy_addr, 282
msx.h, 294	h, 296
nes.h, 329	HARDWARE_SPRITE_CAN_FLIP_X, 282
sms.h, 362	HARDWARE_SPRITE_CAN_FLIP_Y, 282
move_win	HIDE BKG, 279
gb.h, 174	HIDE_ERG, 279
MSX	hide_sprite, 295
msx.h, 275	HIDE_SPRITES, 279
msx.h	HIDE_WIN, 279
_SYSTEM, 296	int_handler, 282
READ_VDP_REG, 277	iyh, 296
WRITE_VDP_REG, 277	iyl, 296
WRITE_VDP_REG_UNSAFE, 277	J_A, 276
_current_1bpp_colors, 297	J_B, 276

J_DOWN, 276	set_interrupts, 283
J_LEFT, 276	set_native_sprite_data, 288
J_RIGHT, 276	set_native_tile_data, 287
J_SELECT, 276	set_palette, 287
J_START, 276	set_palette_entry, 287
J_UP, 276	SET_SHADOW_OAM_ADDRESS, 292
JOY_IFLAG, 278	set_sprite_1bpp_data, 288
joypad, 286	set_sprite_data, 288
joypad_ex, 286	set_sprite_palette, 281
joypad_init, 286	set_sprite_palette_entry, 281
I, 296	set_sprite_prop, 292
LCD_IFLAG, 277	set_sprite_tile, 292
M_NO_INTERP, 276	set_tile_1bpp_data, 288
M_NO_SCROLL, 276	set_tile_map, 289
M_TEXT_INOUT, 276	set_tile_submap, 289
M TEXT OUT, 276	set_tile_submap_compat, 289
MAX HARDWARE SPRITES, 282	set_tile_xy, 295
MAXWNDPOSX, 278	set_vram_byte, 295
MAXWNDPOSY, 278	set_win_based_submap, 291
MINWNDPOSX, 278	set_win_based_tiles, 289
MINWNDPOSY, 278	set win submap, 290
mode, 283	set_win_tile_xy, 282
move bkg, 285	set_win_tiles, 282
move_sprite, 294	shadow OAM, 297
MSX, 275	SHOW BKG, 279
OAM_item_t, 282	SHOW_LEFT_COLUMN, 279
refresh_OAM, 285	SHOW SPRITES, 279
remove_JOY, 284	SHOW WIN, 279
remove LCD, 284	SIO_IFLAG, 278
remove_SIO, 284	SPRITES 16x16, 279
remove_TIM, 284	SPRITES_8x8, 280
remove_VBL, 284	SWITCH RAM, 281
S BANK, 277	SWITCH ROM, 285
S FLIPX, 277	SWITCH ROM1, 281
S FLIPY, 277	SWITCH ROM2, 281
S PAL, 277	sys_time, 296
S_PALETTE, 277	• —
S PRIORITY, 277	SYSTEM_50HZ, 275 SYSTEM 60HZ, 275
SCREENHEIGHT, 278	TIM_IFLAG, 278
SCREENWIDTH, 278	VBK REG, 275
scroll bkg, 285	VBK_REG, 275 VBL_IFLAG, 277
scroll_sprite, 294	vmemcpy, 289
set_1bpp_colors, 288	vsync, 285
set_2bpp_palette, 288	wait_vbl_done, 285
set_attributed_tile_xy, 295	waitpad, 286
set_bkg_1bpp_data, 288	waitpadup, 286
set_bkg_4bpp_data, 288	WRITE_VDP_CMD, 283
set_bkg_based_submap, 291	WRITE_VDP_DATA, 283
set_bkg_based_tiles, 289	NAKED
set_bkg_data, 288	types.h, 112
set_bkg_palette, 281	nes.h
set_bkg_palette_entry, 281	_SYSTEM, 335
set_bkg_submap, 290	_current_1bpp_colors, 336
set_bkg_tile_xy, 282	_current_bank, 335
set_bkg_tiles, 282	_map_tile_offset, 336
SET_BORDER_COLOR, 279	_shadow_OAM_base, 336
set_data, 289	_submap_tile_offset, 336
set_default_palette, 287	_switch_prg0, 335

11.100.044	M TEVT OUT 000
add_LCD, 311	M_TEXT_OUT, 303
add_VBL, 310	MAX_HARDWARE_SPRITES, 309
BANK, 305	mode, 311
BANKREF, 306	move_bkg, 324
BANKREF_EXTERN, 306	move_sprite, 329
COMPAT_PALETTE, 308	NINTENDO_NES, 301
CURRENT_BANK, 305	OAM_item_t, 309
delay, 311	palette_color_t, 309
disable_interrupts, 314	refresh_OAM, 315
DISABLE_OAM_DMA, 308	remove_LCD, 310
DISABLE_RAM, 307	remove_VBL, 310
DISABLE_VBL_TRANSFER, 309	RGB, 302
DISPLAY_OFF, 307	RGB8, 302
display_off, 314	RGB_AQUA, 302
DISPLAY_ON, 307	RGB_BLACK, 303
display_on, 314	RGB_BLUE, 302
DMG_BLACK, 304	RGB_CYAN, 302
DMG_DARK_GRAY, 304	RGB_DARKBLUE, 302
DMG_LITE_GRAY, 305	RGB_DARKGRAY, 303
DMG_PALETTE, 305	RGB_DARKGREEN, 302
DMG_WHITE, 305	RGB_DARKRED, 302
enable_interrupts, 313	RGB_DARKYELLOW, 302
ENABLE_OAM_DMA, 309	RGB_GREEN, 302
ENABLE RAM, 307	RGB LIGHTGRAY, 303
ENABLE_VBL_TRANSFER, 309	RGB PINK, 302
fill_bkg_rect, 335	RGB PURPLE, 302
fill_rect, 309	RGB RED, 302
flush_shadow_attributes, 335	RGB WHITE, 303
get_bkg_tile_xy, 324	RGB_YELLOW, 302
get_bkg_tiles, 322	RGBHTML, 302
get_bkg_xy_addr, 315	S_FLIPX, 304
get_mode, 311	S_FLIPY, 304
get_sprite_prop, 329	S_PAL, 304
get_sprite_tile, 327	S_PALETTE, 304
get_system, 311	S_PRIORITY, 304
HARDWARE_SPRITE_CAN_FLIP_X, 309	SCREENHEIGHT, 305
HARDWARE_SPRITE_CAN_FLIP_Y, 309	SCREENWIDTH, 305
HIDE_BKG, 308	scroll_bkg, 325
HIDE_LEFT_COLUMN, 307	scroll_sprite, 329
hide_sprite, 330	set_1bpp_colors, 315
HIDE_SPRITES, 308	set_1bpp_colors_ex, 315
init_bkg, 334	set_2bpp_palette, 315
int_handler, 309	set_attribute_xy, 308
J_A, 303	set_bkg_1bpp_data, 316
J_B, 303	set_bkg_2bpp_data, 308
J_DOWN, 303	set_bkg_attribute_xy, 323
J_LEFT, 303	set_bkg_attribute_xy_nes16x16, 323
J_RIGHT, 303	set_bkg_attributes, 319
J_SELECT, 303	set_bkg_attributes_nes16x16, 318
J_START, 303	set_bkg_based_submap, 322
J_UP, 303	set_bkg_based_tiles, 320
joypad, 312	set_bkg_data, 315
joypad_ex, 313	set_bkg_native_data, 331
joypad_init, 312	set_bkg_palette, 309
M_DRAWING, 303	set_bkg_palette_entry, 310
M_NO_INTERP, 304	set_bkg_submap, 321
M_NO_SCROLL, 304	set_bkg_submap_attributes, 320
M_TEXT_INOUT, 303	set_bkg_submap_attributes_nes16x16, 319

set_bkg_tile_xy, 323	hardware.h, 208
set_bkg_tiles, 317	NR12_REG
SET_BORDER_COLOR, 308	hardware.h, 208
set_data, 331	NR13_REG
set_native_tile_data, 334	hardware.h, 208
SET_SHADOW_OAM_ADDRESS, 326	NR14_REG
set_sprite_1bpp_data, 326	hardware.h, 208
set_sprite_2bpp_data, 308	NR21_REG
set_sprite_data, 325	hardware.h, 208
set_sprite_native_data, 333	NR22_REG
set_sprite_palette, 309	hardware.h, 208
set_sprite_palette_entry, 310	NR23_REG
set_sprite_prop, 327	hardware.h, 208
set_sprite_tile, 326	NR24_REG
set_tile_data, 331	hardware.h, 209
set_tile_map, 308 set_tile_submap, 308	NR30_REG
	hardware.h, 209 NR31 REG
set_tile_xy, 308 set_tiles, 331	hardware.h, 209
set_vram_byte, 315	NR32 REG
shadow OAM, 336	hardware.h, 209
SHOW BKG, 308	NR33 REG
SHOW LEFT COLUMN, 307	hardware.h, 209
SHOW SPRITES, 308	NR34 REG
SPRITES 8x16, 308	hardware.h, 209
SPRITES 8x8, 308	NR41 REG
SWITCH RAM, 307	hardware.h, 209
SWITCH ROM, 307	NR42 REG
SWITCH ROM DUMMY, 306	hardware.h, 209
SWITCH ROM UNROM, 306	NR43 REG
sys_time, 335	hardware.h, 209
SYSTEM_50HZ, 301	NR44 REG
SYSTEM 60HZ, 301	hardware.h, 209
SYSTEM BITS DENDY, 301	NR50 REG
SYSTEM BITS NTSC, 301	hardware.h, 209
SYSTEM_BITS_PAL, 301	NR51 REG
vmemset, 334	hardware.h, 209
vsync, 314	NR52_REG
wait_vbl_done, 314	hardware.h, 209
waitpad, 312	NULL
waitpadup, 312	stddef.h, 367
NINTENDO	types.h, 115
gb.h, 140	
NINTENDO_NES	OAM_item_t, 93
nes.h, 301	gb.h, 151
NONBANKED	msx.h, 282
types.h, 113	nes.h, 309
NORETURN	prop, 94
types.h, 113	tile, 94
noreturn	x, 94
stdnoreturn.h, 379	y, 94
nowait_int_handler	OAMF_BANK0
gb.h, 154	hardware.h, 205
npads	OAMF_BANK1
joypads_t, 91	hardware.h, 205
NR10_REG	OAMF_CGB_PAL0
hardware.h, 208	hardware.h, 205
NR11_REG	OAMF_CGB_PAL1
	hardware.h, 205

OAMF_CGB_PAL2	hardware.h, 194
hardware.h, 205	P1F_GET_BTN
OAMF_CGB_PAL3	hardware.h, 194
hardware.h, 205	P1F_GET_DPAD
OAMF_CGB_PAL4	hardware.h, 194
hardware.h, 206	P1F_GET_NONE
OAMF_CGB_PAL5	hardware.h, 195
hardware.h, 206	palette_color_t
OAMF_CGB_PAL6 hardware.h, 206	cgb.h, 125 nes.h, 309
OAMF CGB PAL7	PCM12 REG
hardware.h, 206	hardware.h, 211
OAMF_PAL0	PCM34 REG
hardware.h, 205	hardware.h, 211
OAMF_PAL1	PCM SAMPLE
hardware.h, 205	hardware.h, 209
OAMF_PALMASK	plot
hardware.h, 206	drawing.h, 131
OAMF_PRI	plot_point
hardware.h, 205	drawing.h, 131
OAMF_XFLIP	pmfont_handle
hardware.h, 205	font.h, 266
OAMF_YFLIP	POINTER
hardware.h, 205	types.h, 115
OBPO_REG	posx
hardware.h, 210 OBP1 REG	console.h, 261
hardware.h, 210	console.h, 261
OCPD REG	PPUCTRL BG CHR
hardware.h, 211	hardware.h, 220
OCPS_REG	PPUCTRL_INC32
hardware.h, 211	hardware.h, 220
OCPSF_AUTOINC	PPUCTRL_NMI
hardware.h, 203	hardware.h, 219
offsetof	PPUCTRL_SPR_8X16
stddef.h, 368	hardware.h, 220
ofs	PPUCTRL_SPR_8X8
far_ptr, 88	hardware.h, 219
OLDCALL	PPUCTRL_SPR_CHR
types.h, 112	hardware.h, 220
opcode	PPUMASK_BLUE
isr_nested_vector_t, 89 isr_vector_t, 90	hardware.h, 220 PPUMASK GREEN
OR	hardware.h, 220
drawing.h, 129	PPUMASK MONOCHROME
diaming.ii, 125	hardware.h, 220
P1_REG	PPUMASK RED
hardware.h, 208	hardware.h, 220
P1F_0	PPUMASK_SHOW_BG
hardware.h, 194	hardware.h, 220
P1F_1	PPUMASK_SHOW_BG_LC
hardware.h, 194	hardware.h, 220
P1F_2	PPUMASK_SHOW_SPR
hardware.h, 194	hardware.h, 220
P1F_3 hardware.h, 194	PPUMASK_SHOW_SPR_LC
P1F 4	hardware.h, 220
hardware.h, 194	PRESERVES_REGS
P1F 5	types.h, 112
_	

printf	hardware.h, 214
stdio.h, 374	R0 LCB
prop	hardware.h, 229
OAM_item_t, 94	R0_NO_LCB
props	hardware.h, 229
metasprite_t, 93	R0_SCR_MODE1
provides.h	hardware.h, 214
USE_C_MEMCPY, 95, 96	R0_SCR_MODE2
USE_C_STRCMP, 95, 96	hardware.h, 214
USE_C_STRCPY, 95, 96	R0_SCR_MODE3
PSG_CH0	hardware.h, 214
hardware.h, 213, 229	R0_SS
PSG_CH1	hardware.h, 230
hardware.h, 213, 229 PSG CH2	R0_SS_OFF hardware.h, 230
hardware.h, 213, 229	R0_VSCRL
PSG CH3	hardware.h, 229
hardware.h, 213, 229	R0_VSCRL_INH
PSG LATCH	hardware.h, 229
hardware.h, 213, 228	R10 INT EVERY
PSG_VOLUME	hardware.h, 217, 232
hardware.h, 214, 229	R10_INT_OFF
ptr	hardware.h, 217, 232
far_ptr, 88	R1_DEFAULT
PTRDIFF_MAX	hardware.h, 215, 230
stdint.h, 371	R1_DISP_OFF
PTRDIFF_MIN	hardware.h, 215, 230
stdint.h, 371	R1_DISP_ON
ptrdiff_t	hardware.h, 215, 230
stddef.h, 368 putchar	R1_IE hardware.h, 215, 230
stdio.h, 374	R1 IE OFF
puts	hardware.h, 215, 230
stdio.h, 375	R1_SCR_MODE1
,	hardware.h, 215
qsort	R1 SCR MODE2
stdlib.h, 378	hardware.h, 215
DO OR INDUT	R1_SCR_MODE3
RO_CB_INPUT	hardware.h, 215
hardware.h, 214 R0 CB OUTPUT	R1_SPR_16X16
hardware.h, 214	hardware.h, 215
R0 DEFAULT	R1_SPR_8X16
hardware.h, 214, 230	hardware.h, 230
R0_ES	R1_SPR_8X8 hardware.h, 215, 230
hardware.h, 214, 230	R1 SPR MAG
R0_ES_OFF	hardware.h, 215
hardware.h, 214, 230	R1_SPR_MAG_OFF
R0_HSCRL	hardware.h, 215
hardware.h, 229	R2_MAP_0x0000
R0_HSCRL_INH	hardware.h, 216, 231
hardware.h, 229	R2_MAP_0x0800
R0_IE1	hardware.h, 216, 231
hardware.h, 214, 229	R2_MAP_0x1000
R0_IE1_OFF hardware.h, 214, 229	hardware.h, 216, 231
R0 IE2	R2_MAP_0x1800
hardware.h, 214	hardware.h, 216, 231
R0 IE2 OFF	R2_MAP_0x2000
<del></del>	

hardware.h, 215, 230	rAUD1SWEEP
R2_MAP_0x2800	hardware.h, 196
hardware.h, 215, 230	rAUD2ENV
R2_MAP_0x3000	hardware.h, 197
hardware.h, 215, 230	rAUD2HIGH
R2_MAP_0x3800	hardware.h, 197
hardware.h, 215, 230	rAUD2LEN
R5_SAT_0x1F00	hardware.h, 196
hardware.h, 231	rAUD2LOW
R5_SAT_0x3F00	hardware.h, 197
hardware.h, 216, 231	rAUD3ENA
R5_SAT_MASK	hardware.h, 197
hardware.h, 216, 231	rAUD3HIGH
R6_BANK0	hardware.h, 197
hardware.h, 216, 231	rAUD3LEN
R6_BANK1	hardware.h, 197
hardware.h, 216, 231	rAUD3LEVEL
R6_DATA_0x0000	hardware.h, 197
hardware.h, 216, 231	rAUD3LOW
R6_DATA_0x2000	hardware.h, 197
hardware.h, 216, 231	rAUD4ENV
R7_COLOR_MASK	hardware.h, 197
hardware.h, 216, 231	rAUD4GO
RAMCTL_BANK	hardware.h, 197
hardware.h, 234	rAUD4LEN
RAMCTL_PROT	hardware.h, 197
hardware.h, 234	rAUD4POLY
RAMCTL RAM	hardware.h, 197
hardware.h, 234	rAUDENA
RAMCTL RO	hardware.h, 198
hardware.h, 234	rAUDTERM
RAMCTL ROM	hardware.h, 198
hardware.h, 234	rAUDVOL
rand	hardware.h, 197
rand.h, 337	rBCPD
rand.h	hardware.h, 203
rand_seed, 338	rBCPS
arand, 338	hardware.h, 203
initarand, 338	rBGP
initrand, 337	hardware.h, 201
rand, 337	rDIV
RAND MAX, 337	hardware.h, 195
randw, 337	rDMA
RANDW_MAX, 337	hardware.h, 201
RAND MAX	realloc
rand.h, 337	stdlib.h, 378
randw	receive_byte
rand.h, 337	gb.h, 156
RANDW MAX	refresh_OAM
rand.h, 337	gb.h, 159
rAUD1ENV	msx.h, 285
hardware.h, 196 rAUD1HIGH	nes.h, 315
	sms.h, 353
hardware.h, 196	remove_JOY
rAUD1LEN	gb.h, 152
hardware.h, 196	msx.h, 284
rAUD1LOW	sms.h, 352
hardware.h, 196	remove_LCD

gb.h, 152	RGB_GREEN
msx.h, 284	cgb.h, 124
nes.h, 310	nes.h, 302
sms.h, 352	RGB_LIGHTFLESH
remove_SIO	cgb.h, 124
gb.h, 152	RGB_LIGHTGRAY
msx.h, 284	cgb.h, 124
sms.h, 352	nes.h, 303
remove TIM	RGB ORANGE
gb.h, 152	cgb.h, 125
msx.h, 284	RGB PINK
sms.h, 352	cgb.h, 124
remove VBL	nes.h, 302
gb.h, 152	RGB PURPLE
-	<del>_</del>
msx.h, 284	cgb.h, 124
nes.h, 310	nes.h, 302
sms.h, 352	RGB_RED
reset	cgb.h, 124
gb.h, 158	nes.h, 302
RET_SIZE	RGB_TEAL
setjmp.h, 339	cgb.h, 125
reverse	RGB_TO_NES
string.h, 100, 104, 107	rgb_to_nes_macro.h, 336
RGB	rgb_to_nes_macro.h
cgb.h, 123	RGB_TO_NES, 336
nes.h, 302	RGB WHITE
RGB8	_ cgb.h, 124
cgb.h, 123	nes.h, 303
nes.h, 302	RGB YELLOW
RGB AQUA	cgb.h, 124
cgb.h, 124	nes.h, 302
nes.h, 302	RGBHTML
	<del>-</del> '
RGB_BLACK	cgb.h, 123
cgb.h, 124	nes.h, 302
nes.h, 303	rHDMA1
RGB_BLUE	hardware.h, 203
cgb.h, 124	rHDMA2
nes.h, 302	hardware.h, 203
RGB_BROWN	rHDMA3
cgb.h, 125	hardware.h, 203
RGB_CYAN	rHDMA4
cgb.h, 124	hardware.h, 203
nes.h, 302	rHDMA5
RGB DARKBLUE	hardware.h, 203
cgb.h, 124	rIE
nes.h, 302	hardware.h, 204
RGB_DARKGRAY	rIF
cgb.h, 124	hardware.h, 196
nes.h, 303	rKEY1
RGB_DARKGREEN	hardware.h, 201
cgb.h, 124	rLCDC
nes.h, 302	hardware.h, 198
RGB_DARKRED	rle_decompress
cgb.h, 124	rledecompress.h, 269
nes.h, 302	rle_init
RGB_DARKYELLOW	rledecompress.h, 269
cgb.h, 124	RLE_STOP
nes.h, 302	rledecompress.h, 269

rledecompress.h	rTAC
rle_decompress, 269	hardware.h, 195 rTIMA
rle_init, 269	
RLE_STOP, 269	hardware.h, 195 rTMA
hardware.h, 201	hardware.h, 195
rLYC	rVBK
hardware.h, 201	hardware.h, 202
rOBP0	rWX
hardware.h, 201	hardware.h, 201
rOBP1	rWY
hardware.h, 201	hardware.h, 201
rOCPD	O DANIK
hardware.h, 204	S_BANK
rOCPS	gb.h, 142 msx.h, 277
hardware.h, 203	sms.h, 344
rP1	S FLIPX
hardware.h, 194	gb.h, 142
RP_REG	msx.h, 277
hardware.h, 211 rPCM12	nes.h, 304
hardware.h, 204	sms.h, 345
rPCM34	S_FLIPY
hardware.h, 204	gb.h, 142
RPF DATAIN	msx.h, 277
hardware.h, 203	nes.h, 304
RPF_ENREAD	sms.h, 345
hardware.h, 203	S_PAL
RPF_WRITE_HI	gb.h, 142
hardware.h, 203	msx.h, 277
RPF_WRITE_LO	nes.h, 304
hardware.h, 203	sms.h, 345 S PALETTE
rRAMB	gb.h, 142
hardware.h, 207	msx.h, 277
rRAMG	nes.h, 304
hardware.h, 207 rROMB0	sms.h, 345
hardware.h, 207	S_PRIORITY
rROMB1	gb.h, 142
hardware.h, 207	msx.h, 277
rRP	nes.h, 304
hardware.h, 203	sms.h, 345
rSB	SB_REG
hardware.h, 195	hardware.h, 208
rSC	SC_REG
hardware.h, 195	hardware.h, 208 SCF SOURCE
rSCX	hardware.h, 195
hardware.h, 201	SCF SPEED
rSCY	hardware.h, 195
hardware.h, 201 rSMBK	SCF START
hardware.h, 204	hardware.h, 195
rSPD	SCHAR_MAX
hardware.h, 201	limits.h, 270
rSTAT	SCHAR_MIN
hardware.h, 200	limits.h, 271
rSVBK	SCREENHEIGHT
hardware.h, 204	gb.h, 144
	msx.h, 278

nes.h, 305	set_bkg_2bpp_data
sms.h, 346	gb.h, 151
SCREENWIDTH	nes.h, 308
gb.h, 144	sms.h, 357
msx.h, 278	set bkg 4bpp data
nes.h, 305	msx.h, 288
sms.h, 346	sms.h, 356
scroll bkg	set_bkg_attribute_xy
_ ·	
gb.h, 168	gb.h, 167
msx.h, 285	nes.h, 323
nes.h, 325	sms.h, 350
sms.h, 353	set_bkg_attribute_xy_nes16x16
scroll_sprite	nes.h, 323
gb.h, 178	set_bkg_attributes
msx.h, 294	gb.h, 163
nes.h, 329	nes.h, 319
sms.h, 363	sms.h, 359
scroll win	set bkg attributes nes16x16
gb.h, 174	nes.h, 318
SCX REG	set bkg based submap
hardware.h, 210	gb.h, 165
SCY REG	msx.h, 291
<del>-</del>	
hardware.h, 209	nes.h, 322
seg	sms.h, 361
far_ptr, 88	set_bkg_based_tiles
SEGA	gb.h, 163
sms.h, 343	msx.h, 289
segfn	nes.h, <mark>320</mark>
far_ptr, 88	sms.h, 358
segofs	set_bkg_data
	ala la 100
far_ptr, 88	gb.h, 160
	_
send_byte	msx.h, 288
send_byte gb.h, 155	msx.h, 288 nes.h, 315
send_byte gb.h, 155 set_1bpp_colors	msx.h, 288 nes.h, 315 sms.h, 357
send_byte gb.h, 155 set_1bpp_colors gb.h, 160	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126 msx.h, 281
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315 set_h, 315 sms.h, 357 set_attribute_xy	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126 msx.h, 281 nes.h, 309
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315 set_sms.h, 357 set_attribute_xy gb.h, 151	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126 msx.h, 281 nes.h, 310 sms.h, 349
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315 set_sms.h, 357 set_attribute_xy gb.h, 151 nes.h, 308	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126 msx.h, 281 nes.h, 310 sms.h, 349 set_bkg_submap
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_attribute_xy gb.h, 151 nes.h, 308 sms.h, 364	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126 msx.h, 281 nes.h, 310 sms.h, 349 set_bkg_submap gb.h, 164
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_attribute_xy gb.h, 151 nes.h, 308 sms.h, 364 set_attributed_tile_xy	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126 msx.h, 281 nes.h, 310 sms.h, 349 set_bkg_submap gb.h, 164 msx.h, 290
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_attribute_xy gb.h, 151 nes.h, 308 sms.h, 364 set_attributed_tile_xy msx.h, 295	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126 msx.h, 281 nes.h, 310 sms.h, 349 set_bkg_submap gb.h, 164 msx.h, 290 nes.h, 321
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_attribute_xy gb.h, 151 nes.h, 308 sms.h, 364 set_attributed_tile_xy msx.h, 295 sms.h, 364	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126 msx.h, 281 nes.h, 310 sms.h, 349 set_bkg_submap gb.h, 164 msx.h, 290 nes.h, 321 sms.h, 359
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_attribute_xy gb.h, 151 nes.h, 308 sms.h, 364 set_attributed_tile_xy msx.h, 295 sms.h, 364 set_bkg_1bpp_data	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126 msx.h, 281 nes.h, 310 sms.h, 349 set_bkg_submap gb.h, 164 msx.h, 290 nes.h, 321 sms.h, 359 set_bkg_submap_attributes
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_attribute_xy gb.h, 151 nes.h, 308 sms.h, 364 set_attributed_tile_xy msx.h, 295 sms.h, 364 set_bkg_1bpp_data gb.h, 161	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126 msx.h, 281 nes.h, 310 sms.h, 349 set_bkg_submap gb.h, 164 msx.h, 290 nes.h, 321 sms.h, 359 set_bkg_submap_attributes gb.h, 166
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_attribute_xy gb.h, 151 nes.h, 308 sms.h, 364 set_attributed_tile_xy msx.h, 295 sms.h, 364 set_bkg_1bpp_data	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126 msx.h, 281 nes.h, 310 sms.h, 349 set_bkg_submap gb.h, 164 msx.h, 290 nes.h, 321 sms.h, 359 set_bkg_submap_attributes
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_attribute_xy gb.h, 151 nes.h, 308 sms.h, 364 set_attributed_tile_xy msx.h, 295 sms.h, 364 set_bkg_1bpp_data gb.h, 161	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126 msx.h, 281 nes.h, 310 sms.h, 349 set_bkg_submap gb.h, 164 msx.h, 290 nes.h, 321 sms.h, 359 set_bkg_submap_attributes gb.h, 166
send_byte gb.h, 155 set_1bpp_colors gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_1bpp_colors_ex gb.h, 160 nes.h, 315 set_2bpp_palette gb.h, 160 msx.h, 288 nes.h, 315 sms.h, 357 set_attribute_xy gb.h, 151 nes.h, 308 sms.h, 364 set_attributed_tile_xy msx.h, 295 sms.h, 364 set_bkg_1bpp_data gb.h, 161 msx.h, 288	msx.h, 288 nes.h, 315 sms.h, 357 set_bkg_native_data gb.h, 182 nes.h, 331 sms.h, 356 set_bkg_palette cgb.h, 125 msx.h, 281 nes.h, 309 sms.h, 349 set_bkg_palette_entry cgb.h, 126 msx.h, 281 nes.h, 310 sms.h, 349 set_bkg_submap gb.h, 164 msx.h, 290 nes.h, 321 sms.h, 359 set_bkg_submap_attributes gb.h, 166 nes.h, 320

nes.h, 319	set_sprite_data
set_bkg_tile_xy	gb.h, 174
gb.h, 167	msx.h, 288
msx.h, 282	nes.h, <mark>325</mark>
nes.h, <mark>323</mark>	sms.h, 357
sms.h, 350	set_sprite_native_data
set_bkg_tiles	gb.h, 182
gb.h, 162	nes.h, 333
msx.h, 282	sms.h, 356
nes.h, 317	set sprite palette
sms.h, 350	cgb.h, 125
SET_BORDER_COLOR	msx.h, 281
gb.h, 150	nes.h, 309
msx.h, 279	sms.h, 350
nes.h, 308	set_sprite_palette_entry
sms.h, 347	cgb.h, 126
set data	msx.h, 281
<del>_</del>	
gb.h, 178	nes.h, 310
msx.h, 289	sms.h, 349
nes.h, 331	set_sprite_prop
sms.h, 358	gb.h, 176
set_default_palette	msx.h, 292
cgb.h, 127	nes.h, <mark>327</mark>
msx.h, 287	sms.h, 362
sms.h, 355	set_sprite_tile
set_interrupts	gb.h, 176
gb.h, 158	msx.h, 292
msx.h, 283	nes.h, <mark>326</mark>
sms.h, 351	sms.h, 361
set_native_sprite_data	set_tile_1bpp_data
msx.h, 288	msx.h, 288
	•
set native tile data	sms.h. 357
set_native_tile_data ab.h. 181	sms.h, 357 set tile 2bpp data
gb.h, 181	set_tile_2bpp_data
gb.h, 181 msx.h, 287	set_tile_2bpp_data sms.h, 357
gb.h, 181 msx.h, 287 nes.h, 334	set_tile_2bpp_data sms.h, 357 set_tile_data
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette msx.h, 287	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette msx.h, 287 sms.h, 355	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette msx.h, 287 sms.h, 355 set_palette_entry	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette msx.h, 287 sms.h, 355 set_palette_entry msx.h, 287	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette msx.h, 287 sms.h, 355 set_palette_entry msx.h, 287 sms.h, 355	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette msx.h, 287 sms.h, 355 set_palette_entry msx.h, 287 sms.h, 355 SET_SHADOW_OAM_ADDRESS	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette msx.h, 287 sms.h, 355 set_palette_entry msx.h, 287 sms.h, 355 SET_SHADOW_OAM_ADDRESS gb.h, 176	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette msx.h, 287 sms.h, 355 set_palette_entry msx.h, 287 sms.h, 355 SET_SHADOW_OAM_ADDRESS gb.h, 176 msx.h, 292	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette msx.h, 287 sms.h, 355 set_palette_entry msx.h, 287 sms.h, 355 SET_SHADOW_OAM_ADDRESS gb.h, 176 msx.h, 292 nes.h, 326	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap gb.h, 151
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette msx.h, 287 sms.h, 355 set_palette_entry msx.h, 287 sms.h, 355 SET_SHADOW_OAM_ADDRESS gb.h, 176 msx.h, 292 nes.h, 326 sms.h, 361	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap gb.h, 151 msx.h, 289
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette msx.h, 287 sms.h, 355 set_palette_entry msx.h, 287 sms.h, 355 SET_SHADOW_OAM_ADDRESS gb.h, 176 msx.h, 292 nes.h, 326	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap gb.h, 151
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette msx.h, 287 sms.h, 355 set_palette_entry msx.h, 287 sms.h, 355 SET_SHADOW_OAM_ADDRESS gb.h, 176 msx.h, 292 nes.h, 326 sms.h, 361	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap gb.h, 151 msx.h, 289
gb.h, 181     msx.h, 287     nes.h, 334     sms.h, 356  set_palette     msx.h, 287     sms.h, 355  set_palette_entry     msx.h, 287     sms.h, 355  SET_SHADOW_OAM_ADDRESS     gb.h, 176     msx.h, 292     nes.h, 326     sms.h, 361  set_sprite_1bpp_data	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap gb.h, 151 msx.h, 289 nes.h, 308
gb.h, 181     msx.h, 287     nes.h, 334     sms.h, 356  set_palette     msx.h, 287     sms.h, 355  set_palette_entry     msx.h, 287     sms.h, 355  SET_SHADOW_OAM_ADDRESS     gb.h, 176     msx.h, 292     nes.h, 326     sms.h, 361  set_sprite_1bpp_data     gb.h, 175	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 308 sms.h, 359
gb.h, 181     msx.h, 287     nes.h, 334     sms.h, 356  set_palette     msx.h, 287     sms.h, 355  set_palette_entry     msx.h, 287     sms.h, 355  SET_SHADOW_OAM_ADDRESS     gb.h, 176     msx.h, 292     nes.h, 326     sms.h, 361  set_sprite_1bpp_data     gb.h, 175     msx.h, 288	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap gb.h, 151 msx.h, 289 nes.h, 308 set_tile_submap gb.h, 151 smsx.h, 289 nes.h, 308 sms.h, 359 set_tile_submap_compat
gb.h, 181     msx.h, 287     nes.h, 334     sms.h, 356  set_palette     msx.h, 287     sms.h, 355  set_palette_entry     msx.h, 287     sms.h, 355  SET_SHADOW_OAM_ADDRESS     gb.h, 176     msx.h, 292     nes.h, 326     sms.h, 361  set_sprite_1bpp_data     gb.h, 175     msx.h, 288     nes.h, 326	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap gb.h, 151 msx.h, 289 nes.h, 308 set_tile_submap gb.h, 151 msx.h, 289 set_tile_submap_compat msx.h, 359
gb.h, 181 msx.h, 287 nes.h, 334 sms.h, 356 set_palette msx.h, 287 sms.h, 355 set_palette_entry msx.h, 287 sms.h, 355 SET_SHADOW_OAM_ADDRESS gb.h, 176 msx.h, 292 nes.h, 326 sms.h, 361 set_sprite_1bpp_data gb.h, 175 msx.h, 288 nes.h, 326 sms.h, 326 sms.h, 326 sms.h, 358	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 359 set_tile_submap_compat msx.h, 289 nes.h, 308 sms.h, 359
gb.h, 181     msx.h, 287     nes.h, 334     sms.h, 356  set_palette     msx.h, 287     sms.h, 355  set_palette_entry     msx.h, 287     sms.h, 355  SET_SHADOW_OAM_ADDRESS     gb.h, 176     msx.h, 292     nes.h, 326     sms.h, 361  set_sprite_1bpp_data     gb.h, 175     msx.h, 288     nes.h, 326     sms.h, 358  set_sprite_2bpp_data     gb.h, 151	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 359 set_tile_submap_compat msx.h, 289 sms.h, 359 set_tile_submap_compat msx.h, 289 sms.h, 359 set_tile_xy gb.h, 151
gb.h, 181     msx.h, 287     nes.h, 334     sms.h, 356  set_palette     msx.h, 287     sms.h, 355  set_palette_entry     msx.h, 287     sms.h, 355  SET_SHADOW_OAM_ADDRESS     gb.h, 176     msx.h, 292     nes.h, 326     sms.h, 361  set_sprite_1bpp_data     gb.h, 175     msx.h, 288     nes.h, 326     sms.h, 358  set_sprite_2bpp_data     gb.h, 151     nes.h, 308	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 359 set_tile_submap_compat msx.h, 289 sms.h, 359 set_tile_submap_compat msx.h, 289 sms.h, 359 set_tile_submap_compat msx.h, 289 sms.h, 359 set_tile_xy gb.h, 151 msx.h, 295
gb.h, 181     msx.h, 287     nes.h, 334     sms.h, 356  set_palette     msx.h, 287     sms.h, 355  set_palette_entry     msx.h, 287     sms.h, 355  SET_SHADOW_OAM_ADDRESS     gb.h, 176     msx.h, 292     nes.h, 326     sms.h, 361  set_sprite_1bpp_data     gb.h, 175     msx.h, 288     nes.h, 326     sms.h, 358  set_sprite_2bpp_data     gb.h, 151     nes.h, 308     sms.h, 357	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 359 set_tile_submap_compat msx.h, 289 sms.h, 359 set_tile_xy gb.h, 151 msx.h, 295 nes.h, 308
gb.h, 181     msx.h, 287     nes.h, 334     sms.h, 356  set_palette     msx.h, 287     sms.h, 355  set_palette_entry     msx.h, 287     sms.h, 355  SET_SHADOW_OAM_ADDRESS     gb.h, 176     msx.h, 292     nes.h, 326     sms.h, 361  set_sprite_1bpp_data     gb.h, 175     msx.h, 288     nes.h, 326     sms.h, 358  set_sprite_2bpp_data     gb.h, 151     nes.h, 308	set_tile_2bpp_data sms.h, 357 set_tile_data gb.h, 180 nes.h, 331 set_tile_map gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 358 set_tile_map_compat sms.h, 358 set_tile_submap gb.h, 151 msx.h, 289 nes.h, 308 sms.h, 359 set_tile_submap_compat msx.h, 289 sms.h, 359 set_tile_submap_compat msx.h, 289 sms.h, 359 set_tile_submap_compat msx.h, 289 sms.h, 359 set_tile_xy gb.h, 151 msx.h, 295

gb.h, 180	SGB_ATTR_LIN, 259
nes.h, <mark>331</mark>	SGB_ATTR_SET, 260
set_vram_byte	SGB_ATTR_TRN, 260
gb.h, 159	sgb_check, 260
msx.h, 295	SGB_CHR_TRN, 260
nes.h, 315	SGB_DATA_SND, 260
sms.h, 363	SGB_DATA_TRN, 260
set_win_1bpp_data	SGB_ICON_EN, 259
gb.h, 169	SGB_JUMP, 260
set_win_attribute_xy	SGB MASK EN, 260
sms.h, 350	SGB MLT REQ, 260
set_win_based_submap	SGB_OBJ_TRN, 260
gb.h, 172	SGB_PAL_01, 259
msx.h, 291	SGB_PAL_03, 259
sms.h, 361	SGB_PAL_12, 259
set_win_based_tiles	SGB_PAL_23, 259
gb.h, 171	SGB_PAL_SET, 259
msx.h, 289	SGB_PAL_TRN, 259
sms.h, 358	SGB_PCT_TRN, 260
set_win_data	SGB_SOU_TRN, 259
gb.h, 169	SGB_SOUND, 259
set_win_submap	SGB_TEST_EN, 259
gb.h, 171	sgb_transfer, 260
msx.h, 290	SGB_ATRC_EN
sms.h, 360	sgb.h, 259
set_win_tile_xy	SGB_ATTR_BLK
gb.h, 173	 sgb.h, <mark>259</mark>
msx.h, 282	SGB ATTR CHR
sms.h, 350	sgb.h, 259
set_win_tiles	SGB ATTR DIV
gb.h, 170	sgb.h, 259
msx.h, 282	SGB_ATTR_LIN
sms.h, 350	sgb.h, 259
setchar	SGB_ATTR_SET
console.h, 262	sgb.h, 260
setjmp	SGB_ATTR_TRN
setjmp.h, 339	sgb.h, 260
setjmp.h	sgb_check
setjmp, 339	sgb.h, 260
BP_SIZE, 339	SGB_CHR_TRN
BPX_SIZE, 339	sgb.h, <mark>260</mark>
jmp_buf, 339	SGB_DATA_SND
longjmp, 339	sgb.h, <mark>260</mark>
RET_SIZE, 339	SGB_DATA_TRN
setjmp, 339	sgb.h, 260
SP_SIZE, 338	SGB_ICON_EN
SPX_SIZE, 339	sgb.h, 259
sfont_handle, 94	SGB_JUMP
first tile, 94	sgb.h, 260
font, 94	SGB MASK EN
SFR	sgb.h, 260
types.h, 112	SGB MLT REQ
sgb.h	sgb.h, 260
c, 261	SGB OBJ TRN
SGB ATRC EN, 259	sgb.h, 260
SGB_ATRO_EN, 259 SGB_ATTR_BLK, 259	SGB PAL 01
SGB_ATTR_CHR, 259	sgb.h, 259
SGB_ATTR_DIV, 259	SGB_PAL_03

sgb.h, 259	msx.h, 279
SGB_PAL_12	nes.h, 308
sgb.h, 259	sms.h, 347
SGB_PAL_23	SHOW_LEFT_COLUMN
sgb.h, 259	gb.h, 150
SGB_PAL_SET	msx.h, 279
sgb.h, 259	nes.h, 307
SGB_PAL_TRN	sms.h, 347
sgb.h, 259	SHOW_SPRITES
SGB_PCT_TRN	gb.h, 150
sgb.h, 260	msx.h, 279
SGB_SOU_TRN	nes.h, 308
sgb.h, 259	sms.h, 347
SGB_SOUND	SHOW_WIN
sgb.h, 259	gb.h, 150
SGB_TEST_EN	msx.h, 279
sgb.h, 259	sms.h, 347
sgb transfer	SHRT MAX
sgb.h, 260	 limits.h, 271
shadow OAM	SHRT MIN
gb.h, 185	_ limits.h, 271
msx.h, 297	SIG_ATOMIC_MAX
nes.h, 336	 stdint.h, <mark>37</mark> 1
sms.h, 366	SIG ATOMIC MIN
shadow PPUCTRL	stdint.h, 371
hardware.h, 222	SIGNED
shadow PPUMASK	drawing.h, 129
hardware.h, 222	SIO IFLAG
shadow VDP R0	gb.h, 143
hardware.h, 217, 234	msx.h, 278
shadow_VDP_R1	sms.h, 346
hardware.h, 217, 234	SIOCTL_BS0
shadow VDP R10	hardware.h, 226
hardware.h, 218, 235	SIOCTL BS1
shadow VDP R2	hardware.h, 226
hardware.h, 217, 234	SIOCTL FRER
shadow VDP R3	hardware.h, 226
hardware.h, 217, 234	SIOCTL_INT
shadow VDP R4	hardware.h, 226
hardware.h, 218, 234	SIOCTL_RON
shadow_VDP_R5	hardware.h, 226
hardware.h, 218, 234	SIOCTL_RXRD
shadow_VDP_R6	hardware.h, 226
hardware.h, 218, 234	SIOCTL_TON
shadow_VDP_R7	hardware.h, 226
hardware.h, 218, 235	SIOCTL_TXFL
shadow_VDP_R8	
hardware.h, 218, 235	hardware.h, 226 SIOF_B_CLOCK
shadow_VDP_R9	hardware.h, 195
hardware.h, 218, 235	SIOF_B_SPEED
shadow_VDP_RBORDER	hardware.h, 195
hardware.h, 218, 235	SIOF_B_XFER_START
shadow_VDP_RSCX	hardware.h, 195
hardware.h, 218, 235	SIOF_CLOCK_EXT
shadow_VDP_RSCY	hardware.h, 195
hardware.h, 218, 235	SIOF_CLOCK_INT
SHOW_BKG	hardware.h, 195
gb.h, 150	SIOF_SPEED_1X

hardware.h, 195	get_bkg_xy_addr, 364
SIOF_SPEED_32X	get_mode, 351
hardware.h, 195	get_r_reg, 353
SIOF_XFER_START	get_sprite_prop, 362
hardware.h, 195	get_sprite_tile, 362
SIZE MAX	get_system, 351
stdint.h, 371	get_win_xy_addr, 351
size t	h, 365
stddef.h, 368	HARDWARE SPRITE CAN FLIP X, 350
•	
types.h, 110, 111, 114	HARDWARE_SPRITE_CAN_FLIP_Y, 350
sms.h	HIDE_BKG, 347
_BIOS, 365	HIDE_LEFT_COLUMN, 347
_SYSTEM, 365	hide_sprite, 363
READ_VDP_REG, 345	HIDE_SPRITES, 347
WRITE_VDP_REG, 345	HIDE_WIN, 347
WRITE_VDP_REG_UNSAFE, 345	int_handler, 351
_current_1bpp_colors, 365	iyh, 365
_current_2bpp_palette, 365	iyl, 365
_current_bank, 348	J_A, 344
_map_tile_offset, 365	J_B, 344
_shadow_OAM_OFF, 366	J_DOWN, 344
_shadow_OAM_base, 366	J_LEFT, 344
sprites OFF, 366	J RIGHT, 344
submap tile offset, 365	J_SELECT, 344
add_JOY, 353	J START, 344
add_LCD, 352	J_UP, 343
add_SIO, 352	JOY_IFLAG, 346
add_5i3, 552 add_TIM, 352	joypad, 353
add_TiM, 002	joypad_ex, 354
b, 365	
	joypad_init, 354
BANK, 348	I, 365
BANKREF, 348	LCD_IFLAG, 345
BANKREF_EXTERN, 348	M_NO_INTERP, 344
c, 365	M_NO_SCROLL, 344
cancel_pending_interrupts, 353	M_TEXT_INOUT, 344
cgb_compatibility, 355	M_TEXT_OUT, 344
COMPAT_PALETTE, 350	MAX_HARDWARE_SPRITES, 350
cpu_fast, 355	MAXWNDPOSX, 346
CURRENT_BANK, 348	MAXWNDPOSY, 346
d, 365	MINWNDPOSX, 346
delay, 353	MINWNDPOSY, 346
DEVICE_SUPPORTS_COLOR, 347	mode, 351
disable_interrupts, 355	move_bkg, 353
DISABLE_RAM, 349	move_sprite, 362
DISABLE_VBL_TRANSFER, 350	refresh_OAM, 353
DISPLAY_OFF, 346	remove JOY, 352
display_off, 353	remove LCD, 352
DISPLAY_ON, 346	remove SIO, 352
DIV REG, 348	remove TIM, 352
e, 365	remove_VBL, 352
EMPTY_IFLAG, 345	S BANK, 344
enable_interrupts, 354	S FLIPX, 345
ENABLE RAM, 349	S FLIPY, 345
<del>-</del> · · ·	<del>-</del>
ENABLE_VBL_TRANSFER, 350	S_PAL, 345
fill_bkg_rect, 350	S_PALETTE, 345
fill_rect, 361	S_PRIORITY, 345
fill_rect_compat, 361	SCREENHEIGHT, 346
fill_win_rect, 350	SCREENWIDTH, 346

scroll_bkg, 353	SIO_IFLAG, 346
scroll_sprite, 363	SPRITES_8x16, 347
SEGA, 343	SPRITES_8x8, 347
set_1bpp_colors, 357	SWITCH_RAM, 349
set_2bpp_palette, 357	SWITCH_ROM, 349
set_attribute_xy, 364	SWITCH_ROM1, 349
set_attributed_tile_xy, 364	SWITCH_ROM2, 349
set_bkg_1bpp_data, 357	sys_time, 365
set_bkg_2bpp_data, 357	SYSTEM 50HZ, 343
set_bkg_4bpp_data, 356	SYSTEM 60HZ, 343
set_bkg_attribute_xy, 350	TIM IFLAG, 345
set_bkg_attributes, 359	VBK REG, 343
set_bkg_based_submap, 361	VBL_IFLAG, 345
set_bkg_based_tiles, 358	vmemcpy, 358
set_bkg_data, 357	vsync, 353
set_bkg_native_data, 356	wait_vbl_done, 353
set_bkg_palette, 349	waitpad, 354
set_bkg_palette_entry, 349	waitpadup, 354
set_bkg_submap, 359	WRITE VDP CMD, 351
set_bkg_submap_attributes, 361	WRITE VDP DATA, 351
set_bkg_tile_xy, 350	SOLID
set_bkg_tiles, 350	drawing.h, 129
SET_BORDER_COLOR, 347	SOUNDPAN NOSL
set_data, 358	hardware.h, 227
set_data, 350 set_default_palette, 355	SOUNDPAN NOSR
set_interrupts, 351	hardware.h, 226
set_native_tile_data, 356	SOUNDPAN TN1L
set_palette, 355	hardware.h, 226
set_palette_entry, 355	SOUNDPAN TN1R
SET_SHADOW_OAM_ADDRESS, 361	hardware.h, 226
set_sprite_1bpp_data, 358	SOUNDPAN_TN2L
set_sprite_2bpp_data, 357	hardware.h, 226
set sprite 4bpp data, 356	SOUNDPAN TN2R
set_sprite_data, 357	hardware.h, 226
set_sprite_native_data, 356	SOUNDPAN TN3L
set sprite palette, 350	hardware.h, 227
set_sprite_palette_entry, 349	SOUNDPAN_TN3R
set_sprite_prop, 362	hardware.h, 226
set_sprite_tile, 361	SP_SIZE
set_tile_1bpp_data, 357	setjmp.h, 338
set_tile_2bpp_data, 357	sprintf
set_tile_map, 358	stdio.h, 375
set_tile_map_compat, 358	SPRITES_16x16
set_tile_submap, 359	msx.h, 279
set_tile_submap_compat, 359	SPRITES_8x16
set_tile_xy, 364	gb.h, 150
set vram byte, 363	nes.h, 308
set_win_attribute_xy, 350	
oct_wiii_attiibate_xy, 000	eme h 347
set win hased subman 361	sms.h, 347
set_win_based_submap, 361	SPRITES_8x8
set_win_based_tiles, 358	SPRITES_8x8 gb.h, 150
set_win_based_tiles, 358 set_win_submap, 360	SPRITES_8x8 gb.h, 150 msx.h, 280
set_win_based_tiles, 358 set_win_submap, 360 set_win_tile_xy, 350	SPRITES_8x8 gb.h, 150 msx.h, 280 nes.h, 308
set_win_based_tiles, 358 set_win_submap, 360 set_win_tile_xy, 350 set_win_tiles, 350	SPRITES_8x8 gb.h, 150 msx.h, 280 nes.h, 308 sms.h, 347
set_win_based_tiles, 358 set_win_submap, 360 set_win_tile_xy, 350 set_win_tiles, 350 shadow_OAM, 366	SPRITES_8x8 gb.h, 150 msx.h, 280 nes.h, 308 sms.h, 347 SPX_SIZE
set_win_based_tiles, 358 set_win_submap, 360 set_win_tile_xy, 350 set_win_tiles, 350 shadow_OAM, 366 SHOW_BKG, 347	SPRITES_8x8 gb.h, 150 msx.h, 280 nes.h, 308 sms.h, 347 SPX_SIZE setjmp.h, 339
set_win_based_tiles, 358 set_win_submap, 360 set_win_tile_xy, 350 set_win_tiles, 350 shadow_OAM, 366 SHOW_BKG, 347 SHOW_LEFT_COLUMN, 347	SPRITES_8x8 gb.h, 150 msx.h, 280 nes.h, 308 sms.h, 347 SPX_SIZE setjmp.h, 339 STAT_REG
set_win_based_tiles, 358 set_win_submap, 360 set_win_tile_xy, 350 set_win_tiles, 350 shadow_OAM, 366 SHOW_BKG, 347	SPRITES_8x8 gb.h, 150 msx.h, 280 nes.h, 308 sms.h, 347 SPX_SIZE setjmp.h, 339

	NUUL 007
hardware.h, 214, 229	NULL, 367
STATF_B_BUSY	offsetof, 368
hardware.h, 201	ptrdiff_t, 368
STATF_B_LYC	size_t, 368
hardware.h, 200	wchar_t, 368
STATF_B_LYCF	stdint.h
hardware.h, 201	INT16_C, 371
STATF_B_MODE00	INT16_MAX, 370
hardware.h, 200	INT16 MIN, 369
STATF B MODE01	int16_t, 372
hardware.h, 200	INT32 C, 372
STATF_B_MODE10	INT32 MAX, 370
hardware.h, 200	INT32_MIN, 369
STATF_B_OAM	int32_t, 372
hardware.h, 201	INT8_C, 371
STATE B VBL	INT8 MAX, 369
hardware.h, 201	INT8 MIN, 369
STATE BUSY	_ :
<del>_</del>	int8_t, 372
hardware.h, 200	INT_FAST16_MAX, 371
STATF_HBL	INT_FAST16_MIN, 370
hardware.h, 200	int_fast16_t, 373
STATF_INT_VBL	INT_FAST32_MAX, 371
hardware.h, 214, 229	INT_FAST32_MIN, 370
STATF_LCD	int_fast32_t, <mark>373</mark>
hardware.h, 200	INT_FAST8_MAX, 370
STATF_LYC	INT_FAST8_MIN, 370
hardware.h, 200	int_fast8_t, 373
STATF_LYCF	INT_LEAST16_MAX, 370
hardware.h, 200	INT LEAST16 MIN, 370
STATF MODE00	int least16 t, 373
hardware.h, 200	INT_LEAST32_MAX, 370
STATF_MODE01	INT_LEAST32_MIN, 370
hardware.h, 200	int_least32_t, 373
STATF MODE10	INT_LEAST8_MAX, 370
hardware.h, 200	INT LEASTS MIN, 370
STATE OAM	int_least8_t, 373
hardware.h, 200	INTMAX C, 372
STATF_SPR_COLL	INTMAX_0, 372
	<del>_</del>
hardware.h, 214, 229	INTMAX_MIN, 371
STATF_VBL	intmax_t, 373
hardware.h, 200	INTPTR_MAX, 371
stdarg.h	INTPTR_MIN, 371
va_arg, 96–98	intptr_t, 373
va_end, 96–98	PTRDIFF_MAX, 371
va_list, 97, 98	PTRDIFF_MIN, 371
va_start, 96, 97	SIG_ATOMIC_MAX, 371
stdatomic.h	SIG_ATOMIC_MIN, 371
atomic_flag_clear, 366	SIZE_MAX, 371
atomic_flag_test_and_set, 366	UINT16_C, 372
stdbool.h	UINT16_MAX, 370
bool_true_false_are_defined, 367	uint16_t, 372
bool, 367	UINT32_C, 372
false, 367	UINT32 MAX, 370
true, 367	uint32 t, 373
stddef.h	UINT8 C, 372
PTRDIFF T DEFINED, 367	UINT8 MAX, 370
SIZE T DEFINED, 367	uint8 t, 372
WCHAR T DEFINED, 367	UINT FAST16 MAX, 371
	51141_175110_WAX, 3/1

uint_fast16_t, 373	reverse, 100, 104, 107
UINT_FAST32_MAX, 371	strcat, 100, 104, 108
uint_fast32_t, 373	strcmp, 99, 103, 106
UINT_FAST8_MAX, 371	strcpy, 99, 102, 106
uint fast8 t, 373	strlen, 100, 104, 108
UINT_LEAST16_MAX, 370	strncat, 101, 104, 108
uint least16 t, 373	strncmp, 101, 105, 108
UINT LEAST32 MAX, 370	strncpy, 101, 105, 109
uint least32 t, 373	strlen
— — ·	
UINT_LEAST8_MAX, 370	string.h, 100, 104, 108
uint_least8_t, 373	strncat
UINTMAX_C, 372	string.h, 101, 104, 108
UINTMAX_MAX, 371	strncmp
uintmax_t, 373	string.h, 101, 105, 108
UINTPTR_MAX, 371	strncpy
uintptr_t, 373	string.h, 101, 105, 109
WCHAR_MAX, 372	SVBK_REG
WCHAR_MIN, 372	hardware.h, 211
WINT_MAX, 372	SWITCH_16_8_MODE_MBC1
WINT_MIN, 372	gb.h, 148
stdio.h	SWITCH_4_32_MODE_MBC1
getchar, 375	gb.h, 148
gets, 375	switch data
printf, 374	drawing.h, 131
putchar, 374	SWITCH RAM
puts, 375	gb.h, 147
sprintf, 375	msx.h, 281
stdlib.h	nes.h, 307
abs, 376	sms.h, 349
atoi, 376	SWITCH_RAM_MBC1
atoi, 376 atol, 376	SWITCH_RAM_MBC1 gb.h, 148
atoi, 376 atol, 376 bsearch, 378	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5
atoi, 376 atol, 376 bsearch, 378 calloc, 378	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 Itoa, 377	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 Itoa, 377 malloc, 378	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 stdnoreturn.h	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM2 SWITCH_ROM2 SWITCH_ROM2 DUMMY
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379 strcat	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM_DUMMY nes.h, 306
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379 streat string.h, 100, 104, 108	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_MBC1
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379 strcat string.h, 100, 104, 108	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_MBC1 gb.h, 148
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379 strcat string.h, 100, 104, 108 strcmp string.h, 99, 103, 106	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_MBC1 gb.h, 148 SWITCH_ROM_MBC5
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379 strcat string.h, 100, 104, 108 strcmp string.h, 99, 103, 106 strcpy	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_MBC1 gb.h, 148 SWITCH_ROM_MBC5 gb.h, 148
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379 strcat string.h, 100, 104, 108 strcmp string.h, 99, 103, 106 strcpy string.h, 99, 102, 106	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_MBC1 gb.h, 148 SWITCH_ROM_MBC5 gb.h, 148 SWITCH_ROM_MBC5_8M
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379 strcat string.h, 100, 104, 108 strcmp string.h, 99, 103, 106 strcpy string.h, 99, 102, 106 string.h	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_MBC1 gb.h, 148 SWITCH_ROM_MBC5 gb.h, 148 SWITCH_ROM_MBC5_8M gb.h, 149
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379 strcat string.h, 100, 104, 108 strcmp string.h, 99, 103, 106 strcpy string.hmemcpy, 99	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_MBC1 gb.h, 148 SWITCH_ROM_MBC5 gb.h, 148 SWITCH_ROM_MBC5_8M gb.h, 149 SWITCH_ROM_MEGADUCK
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379 strcat string.h, 100, 104, 108 strcmp string.h, 99, 103, 106 string.hmemcpy, 99 c, 106	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_MBC1 gb.h, 148 SWITCH_ROM_MBC5 gb.h, 148 SWITCH_ROM_MBC5_8M gb.h, 149 SWITCH_ROM_MEGADUCK gb.h, 148
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379 strcat string.h, 100, 104, 108 strcmp string.h, 99, 103, 106 strcpy string.hmemcpy, 99 c, 106 memcmp, 101, 105, 109	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_MBC1 gb.h, 148 SWITCH_ROM_MBC5 gb.h, 148 SWITCH_ROM_MBC5_8M gb.h, 149 SWITCH_ROM_MEGADUCK
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379 strcat string.h, 100, 104, 108 strcmp string.h, 99, 103, 106 string.hmemcpy, 99 c, 106	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_MBC1 gb.h, 148 SWITCH_ROM_MBC5 gb.h, 148 SWITCH_ROM_MBC5_8M gb.h, 149 SWITCH_ROM_MEGADUCK gb.h, 148
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379 strcat string.h, 100, 104, 108 strcmp string.h, 99, 103, 106 strcpy string.hmemcpy, 99 c, 106 memcmp, 101, 105, 109	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_MBC1 gb.h, 148 SWITCH_ROM_MBC5 gb.h, 148 SWITCH_ROM_MBC5_8M gb.h, 149 SWITCH_ROM_MEGADUCK gb.h, 148 SWITCH_ROM_MEGADUCK gb.h, 148 SWITCH_ROM_UNROM
atoi, 376 atol, 376 bsearch, 378 calloc, 378 exit, 376 free, 378 itoa, 377 labs, 376 ltoa, 377 malloc, 378 qsort, 378 realloc, 378 uitoa, 377 ultoa, 377 stdnoreturn.h noreturn, 379 strcat string.h, 100, 104, 108 strcmp string.h, 99, 103, 106 strcpy string.hmemcpy, 99 c, 106 memcmp, 101, 105, 109 memcpy, 98, 103, 107	SWITCH_RAM_MBC1 gb.h, 148 SWITCH_RAM_MBC5 gb.h, 149 SWITCH_ROM gb.h, 147 msx.h, 285 nes.h, 307 sms.h, 349 SWITCH_ROM1 msx.h, 281 sms.h, 349 SWITCH_ROM2 msx.h, 281 sms.h, 349 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_DUMMY nes.h, 306 SWITCH_ROM_MBC1 gb.h, 148 SWITCH_ROM_MBC5 gb.h, 148 SWITCH_ROM_MBC5_8M gb.h, 149 SWITCH_ROM_MEGADUCK gb.h, 148 SWITCH_ROM_UNROM nes.h, 306

msx.h, 296	to_far_ptr
nes.h, 335	far_ptr.h, 264
sms.h, 365	tolower
SYSTEM_50HZ	ctype.h, 117
gb.h, 141	toupper
msx.h, 275	ctype.h, 117
nes.h, 301	TRUE
sms.h, 343	types.h, 115
SYSTEM_60HZ	true
gb.h, 140	stdbool.h, 367
msx.h, 275	typeof.h
nes.h, 301	TYPEOF_ARRAY, 381
sms.h, 343	TYPEOF_BIT, 381
SYSTEM BITS DENDY	TYPEOF_BITFIELD, 381
nes.h, 301	TYPEOF_CHAR, 381
SYSTEM BITS NTSC	TYPEOF_CPOINTER, 381
nes.h, 301	TYPEOF_EEPPOINTER, 382
SYSTEM BITS PAL	TYPEOF FIXED16X16, 381
nes.h, 301	TYPEOF FLOAT, 381
SYSTEM NTSC	TYPEOF FPOINTER, 381
hardware.h, 217	TYPEOF FUNCTION, 381
SYSTEM PAL	TYPEOF_GPOINTER, 381
hardware.h, 217	TYPEOF_INT, 381
	TYPEOF IPOINTER, 382
TAC_REG	TYPEOF LONG, 381
hardware.h, 208	TYPEOF POINTER, 381
TACF_16KHZ	TYPEOF PPOINTER, 382
hardware.h, 196	TYPEOF SBIT, 381
TACF_262KHZ	TYPEOF SFR, 381
hardware.h, 196	TYPEOF SHORT, 381
TACF 4KHZ	TYPEOF_STRUCT, 381
hardware.h, 196	TYPEOF_VOID, 381
TACF 65KHZ	TYPEOF ARRAY
hardware.h, 196	typeof.h, 381
TACF_START	TYPEOF BIT
hardware.h, 196	typeof.h, 381
TACF_STOP	TYPEOF_BITFIELD
hardware.h, 196	typeof.h, 381
tile	TYPEOF CHAR
OAM_item_t, 94	typeof.h, 381
TIM IFLAG	TYPEOF CPOINTER
 gb.h, 143	typeof.h, 381
msx.h, 278	TYPEOF EEPPOINTER
sms.h, 345	typeof.h, 382
TIMA_REG	TYPEOF FIXED16X16
hardware.h, 208	typeof.h, 381
time	TYPEOF FLOAT
time.h, 380	typeof.h, 381
time.h	TYPEOF FPOINTER
clock, 380	typeof.h, 381
CLOCKS_PER_SEC, 379	TYPEOF FUNCTION
time, 380	typeof.h, 381
time_t, 379	
time t	TYPEOF_GPOINTER
time.h, 379	typeof.h, 381
TMA_REG	TYPEOF_INT
hardware.h, 208	typeof.h, 381
TO FAR PTR	TYPEOF_IPOINTER
far_ptr.h, 263	typeof.h, 382
.ap, 200	

TYPEOF_LONG	UINT16
typeof.h, 381	types.h, 110, 111, 114
TYPEOF_POINTER	UINT16_C
typeof.h, 381	stdint.h, 372
TYPEOF_PPOINTER	UINT16_MAX
typeof.h, 382	stdint.h, 370
TYPEOF SBIT	uint16 t
typeof.h, 381	stdint.h, 372
TYPEOF SFR	uint2bcd
typeof.h, 381	bcd.h, 118, 120
TYPEOF_SHORT	UINT32
typeof.h, 381	types.h, 110, 111, 114
TYPEOF STRUCT	UINT32 C
typeof.h, 381	stdint.h, 372
TYPEOF VOID	UINT32_MAX
typeof.h, 381	stdint.h, 370
types.h	uint32 t
	<del>-</del>
SIZE_T_DEFINED, 110, 111, 114	stdint.h, 373
AT, 112	UINT8
BANKED, 113	types.h, 110, 111, 114
BOOLEAN, 113	UINT8_C
BYTE, 113	stdint.h, 372
clock_t, 110, 111, 115	UINT8_MAX
CRITICAL, 113	stdint.h, 370
DWORD, 113	uint8_t
FALSE, 115	stdint.h, 372
fixed, 113	UINT_FAST16_MAX
INT16, 110, 111, 114	stdint.h, 371
INT32, 110, 111, 114	uint_fast16_t
INT8, 110, 111, 114	stdint.h, 373
INTERRUPT, 113	UINT_FAST32_MAX
LWORD, 113	stdint.h, 371
NAKED, 112	uint fast32 t
NONBANKED, 113	stdint.h, 373
NORETURN, 113	UINT_FAST8_MAX
NULL, 115	stdint.h, 371
OLDCALL, 112	uint_fast8_t
POINTER, 115	
	stdint.h, 373 UINT_LEAST16_MAX
PRESERVES_REGS, 112	
SFR, 112	stdint.h, 370
size_t, 110, 111, 114	uint_least16_t
TRUE, 115	stdint.h, 373
UBYTE, 113	UINT_LEAST32_MAX
UDWORD, 113	stdint.h, 370
UINT16, 110, 111, 114	uint_least32_t
UINT32, 110, 111, 114	stdint.h, 373
UINT8, 110, 111, 114	UINT_LEAST8_MAX
ULWORD, 113	stdint.h, 370
UWORD, 113	uint_least8_t
WORD, 113	stdint.h, 373
Z88DK_CALLEE, 114	UINT_MAX
Z88DK_FASTCALL, 114	limits.h, 271
	UINT_MIN
UBYTE	limits.h, 271
types.h, 113	UINTMAX_C
UCHAR_MAX	stdint.h, 372
limits.h, 271	UINTMAX MAX
UDWORD	stdint.h, 371
types.h, 113	

uintmax_t	VDP_R1
stdint.h, 373	hardware.h, 215, 230
UINTPTR_MAX	VDP_R10
stdint.h, 371	hardware.h, 217, 232
uintptr_t	VDP_R2
stdint.h, 373	hardware.h, 215, 230
uitoa	VDP_R3
stdlib.h, 377	hardware.h, 216, 231
ULONG_MAX	VDP_R4
limits.h, 271	hardware.h, 216, 231
ULONG MIN	VDP R5
limits.h, 271	hardware.h, 216, 231
ultoa	VDP R6
stdlib.h, 377	hardware.h, 216, 231
ULWORD	VDP R7
types.h, 113	hardware.h, 216, 231
UNSIGNED	VDP R8
drawing.h, 130	hardware.h, 216, 232
USE C MEMCPY	VDP R9
provides.h, 95, 96	hardware.h, 217, 232
USE C STRCMP	VDP RBORDER
provides.h, 95, 96	hardware.h, 216, 231
USE C STRCPY	VDP REG MASK
<del></del>	
provides.h, 95, 96	hardware.h, 214, 229
USHRT_MAX	VDP_RSCX
limits.h, 271	hardware.h, 217, 232
USHRT_MIN	VDP_RSCY
limits.h, 271	hardware.h, 217, 232
UWORD	VDP_SAT_TERM
types.h, 113	hardware.h, 217, 234
VO. OVO	VECTOR_JOYPAD
va_arg	isr.h, 237
stdarg.h, 96–98	VECTOR_SERIAL
va_end	isr.h, 237
stdarg.h, 96–98	VECTOR_STAT
va_list	isr.h, 237
stdarg.h, 97, 98	VECTOR_TIMER
va_start	isr.h, 237
stdarg.h, 96, 97	version.h
VBK_ATTRIBUTES	GBDK_VERSION, 270
hardware.h, 202, 217, 234	vmemcpy
VBK_BANK_0	gb.h, 179
hardware.h, 202	msx.h, 289
VBK_BANK_1	sms.h, 358
hardware.h, 202	vmemset
VBK_REG	gb.h, 183
hardware.h, 210	nes.h, 334
msx.h, 275	vsync
sms.h, 343	gb.h, 158
VBK_TILES	msx.h, 285
hardware.h, 202, 217, 234	nes.h, 314
VBL_IFLAG	sms.h, 353
gb.h, 143	22, 3.33
msx.h, 277	W
sms.h, 345	_fixed, 89
VDP_ATTR_SHIFT	wait_int_handler
hardware.h, 218, 235	 gb.h, 155
VDP R0	wait_vbl_done
hardware.h, 214, 229	gb.h, 158
······································	g···, · • •

```
msx.h, 285
    nes.h, 314
    sms.h, 353
waitpad
    gb.h, 156
    msx.h, 286
    nes.h, 312
    sms.h, 354
waitpadup
    gb.h, 156
    msx.h, 286
    nes.h, 312
    sms.h, 354
WCHAR_MAX
    stdint.h, 372
WCHAR_MIN
    stdint.h, 372
wchar_t
    stddef.h, 368
\mathsf{WHITE}
    drawing.h, 129
WINT_MAX
    stdint.h, 372
WINT_MIN
    stdint.h, 372
WORD
    types.h, 113
WRITE VDP CMD
    msx.h, 283
    sms.h, 351
WRITE_VDP_DATA
    msx.h, 283
    sms.h, 351
wrtchr
    drawing.h, 132
WX_REG
    hardware.h, 210
WY_REG
    hardware.h, 210
    OAM_item_t, 94
XOR
    drawing.h, 129
у
    OAM_item_t, 94
Z88DK_CALLEE
    types.h, 114
Z88DK_FASTCALL
    types.h, 114
```