### **AMD64 SYSTEM V ABI CALLING CONVENTION**

• First 6 integer/pointer parameters: RDI, RSI, RDX, RCX, R8, R9

• First 8 floating point parameters: XMM0...XMM7

• Further parameters: through the stack, in reversed order

• Function has to preserve: RBX, RBP, RSP, R12...R15

Integer/pointer return value: RAXFloating point return value: XMM0

• Variadic functions: number of floating point parameters in AL

• Before calling a function, RSP has to be 16-byte aligned

### **SYSTEM CALLS**

0	sys_read	Reads from a file_descriptor. Number of bytes read is returned (ENTER included). Parameters: file_descriptor, buffer_pointer, buffer_size
1	sys_write	Writes into a file_descriptor. Number of bytes written is returned. Parameters: file_descriptor, buffer_pointer, buffer_size
60	sys_exit	Terminates the process. Parameters: error_code

#### **INTEGER ARITHMETIC INSTRUCTIONS**

MUL	ор	op: reg8, mem8, reg16, mem16, reg32, mem32, reg64, mem64		
	8 bit	AX = AL * op		
	16 bit	DX:AX = AX * op		
	32 bit	EDX:EAX = EAX * op		
	64 bit	RDX:RAX = RAX * op		
IMUL	ор	See MUL above op1 = op1 * op2 op1 = op2 * op3		
IMUL	op1, op2			
IMUL	op1, op2, op3			
DIV	ор	op: reg8, mem8, reg16, mem16, reg32, mem32, reg64, mem64		
	8 bit	AL = AX / op	AH = remainder	
	16 bit	AX = DX:AX / op	DX = remainder	
	32 bit	EAX = EDX:EAX / op	EDX = remainder	
	64 bit	RAX = RDX:RAX / op	RDX = remainder	
IDIV	ор	See DIV above		

# FLOAT DATA MOVEMENT INSTRUCTIONS

op1, op2: xmm, mem64	op2 = op1	op1, op2	movsd
op1, op2: xmm, reg32, mem32	op2 = op1	op1, op2	movd
op1, op2: xmm, reg64, mem64	op2 = op1	op1, op2	movq

## FLOAT ARITHMETIC INSTRUCTIONS

op1, op2: xmm, mer	op1 = op1 + op2	op1, op2	addsd
op1, op2: xmm, mer	op1 = op1 - op2	op1, op2	subsd
op1, op2: xmm, mer	op1 = op1 * op2	op1, op2	mulsd
op1, op2: xmm, mer	op1 = op1 / op2	op1, op2	divsd

# SSE CONVERSION INSTRUCTIONS

cvtsi2sd op1, op2 op1: xmm op2: reg32/64, mem32/64

Converts 32/64 bit integer to double