# Modeling Thermal Transport and Viscosity with Molecular Dynamics

Steve Plimpton Sandia National Labs sjplimp@sandia.gov

LAMMPS Users and Developers Workshop International Centre for Theoretical Physics (ICTP) March 2014 - Trieste, Italy

Sandia National Laboratories is a multi-program laboratory managed and operated by Sandia Corporation, a wholly owned subsidiary of Lockheed Martin Corporation, for the U.S. Department of Energy's National Nuclear Security Administration under contract DE-AC04-94AL85000. Presentation: SAND2014-2225C



### Tackling a new problem with LAMMPS

- Features: lammps.sandia.gov/features.html
- Commands page: doc/Section\_Commands.html
- Papers: lammps.sandia.gov/papers.html
- Mail list: lammps.sandia.gov/mail.html
- Adding new features: doc/Section\_modify.html
- Howto explanations in manual:
  - doc/Section\_howto.html
  - 6.20 Calculating thermal conductivity
  - 6.21 Calculating viscosity

### What is thermal conductivity?

- Propensity of a material to transmit heat (thermal energy)
- Solids or liquids or gases
- Temperature and density dependent
- ullet High  $\kappa=$  good heat sink, low  $\kappa=$  good insulator

### What is thermal conductivity?

- Propensity of a material to transmit heat (thermal energy)
- Solids or liquids or gases
- Temperature and density dependent
- High  $\kappa = \operatorname{good}$  heat sink, low  $\kappa = \operatorname{good}$  insulator
- Fundamental equation:

$$J = -\kappa \nabla T$$

$$J = {\sf heat\ flux} = \frac{\Delta {\it KE}}{{\sf Area\ time}}$$

$$\nabla T$$
 = temperature gradient =  $dT/dz$ 

$$\kappa = \text{thermal conductivity} = W / m K$$

### What is viscosity?

- Propensity of a fluid to transmit momentum perpendicular to direction of momentum flow (shear direction)
- Fluid "friction" or resistance to flow
- Fluid = Liquids and gases
- High  $\eta =$  honey, low  $\eta =$  water

### What is viscosity?

- Propensity of a fluid to transmit momentum perpendicular to direction of momentum flow (shear direction)
- Fluid "friction" or resistance to flow
- Fluid = Liquids and gases
- High  $\eta =$  honey, low  $\eta =$  water
- Fundamental equation:

$$J_z(p_x) = -\eta \frac{\partial V_x}{\partial z}$$

 $J_z(p_x) =$  momentum flux in perpendicular direction

$$\frac{\partial V_x}{\partial z}$$
 = transverse velocity gradient

$$\eta = \text{shear viscosity}$$

### 4 methods for computing thermal conductivity

- Non-equilibrium methods:
  - basic idea: induce a temperature gradient or heat flux and monitor the other quantity
  - direct thermostatting method of Ikeshoji and Hafskjold
  - reverse perturbation method of Muller-Plathe
  - aggregate variant of Muller-Plathe method
- Equilibrium method:
  - Green-Kubo formalism

# 4 methods for computing thermal conductivity

- Non-equilibrium methods:
  - basic idea: induce a temperature gradient or heat flux and monitor the other quantity
  - direct thermostatting method of Ikeshoji and Hafskjold
  - reverse perturbation method of Muller-Plathe
  - aggregate variant of Muller-Plathe method
- Equilibrium method:
  - Green-Kubo formalism
- See examples/KAPPA for 4 sample scripts
- 3d LJ fluid, but adaptable to other systems (e.g. solids)

### 4 methods for computing shear viscosity

- Non-equilibrium methods:
  - basic idea: induce a flow gradient or momentum flux and monitor the other quantity
  - drag wall over fluid to induce shear
  - NEMD shear deformation with SLLOD thermostatting
  - Muller-Plathe reverse perturbation method
- Equilibrium method:
  - Green-Kubo formalism
  - auto-correlation of pressure tensor component

### 4 methods for computing shear viscosity

- Non-equilibrium methods:
  - basic idea: induce a flow gradient or momentum flux and monitor the other quantity
  - drag wall over fluid to induce shear
  - NEMD shear deformation with SLLOD thermostatting
  - Muller-Plathe reverse perturbation method
- Equilibrium method:
  - Green-Kubo formalism
  - auto-correlation of pressure tensor component
- See examples/VISCOSITY for 4 sample scripts
- 2d LJ fluid, but adaptable to other systems


#### Caveats for atomistic MD

- **1** Missing electronic effects for  $\kappa$ 
  - empirical atomistic simulations ⇒ heat is transported by phonons
  - electronic effects included only indirectly in potential
  - ullet if electrons make large contribution to  $\kappa$ , won't see it
- 2 Homogeneous vs heterogeneous systems
  - formulas are for homogeneous bulk
  - ullet in graphene sheets is 2d, possibly asymmetric
  - $\bullet$   $\eta$  for fluid flowing thru CNTs is radial BC
- Mis-match to experiment
  - MD has severe length- and time-scale constraints
  - temperature gradients & shear rates are typically orders of magnitude larger than expt

### (1) Direct thermostatting method

Ikeshoji and Hafskjold, Molecular Physics, 81, 251-261 (1994)

- 2 thermostats for 2 regions of simulation box
- One hot, one cold
- ullet Monitor flux of energy needed to maintain abla T



### Direct thermostatting method

- LAMMPS implementation:
  - fix langevin using compute temp/region as "bias"
  - fix langevin can tally energy each thermostat adds/subtracts
  - fix ave/spatial monitors resulting temperature gradient

$$\kappa = \frac{\Delta Q}{2Area\Delta t} \frac{\Delta z}{\Delta T}$$


# Script for direct thermostatting method

```
lattice fcc ${rho}
region box block 0 $x 0 $y 0 $z
# heat layers
region hot block INF INF INF O 1
region cold block INF INF INF INF 10 11
compute Thot all temp/region hot
compute Tcold all temp/region cold
# 1st equilibration run
fix 1 all nvt temp $t $t 0.5
run 1000
unfix 1
```

# More script for direct thermostatting method

```
# thermal conductivity calculation
compute ke all ke/atom
variable temp atom c_ke/1.5
fix hot all langevin ${thi} ${thi} 1.0 59804 tally yes
fix cold all langevin ${tlo} ${tlo} 1.0 287859 ...
fix_modify hot temp Thot
fix_modify cold temp Tcold
fix 2 all ave/spatial 10 100 1000 z lower 0.05 v_temp &
  file tmp.profile units reduced
thermo_style custom step temp c_Thot c_Tcold f_hot f_cold
run 20000
```

### Output for direct thermostatting method



#### Step Temp Thot Tcold hot cold


. . .

30000 1.3011151 1.7275961 1.06067 -0.84589474 0.8965726 31000 1.3002026 1.5313418 1.0526131 -0.8964083 0.93984929 Loop time of 25.7381 on 8 procs for 20000 steps with 8000 atoms

### (2) Muller-Plathe reverse perturbation method

#### Muller-Plathe, J Chem Phys, 106, 6082 (1997)

- Define hot and cold regions of simulation box
- Find hottest atom in cold region, coldest atom in hot region
- Swap velocity vector of these 2 atoms (energy)
- Tally heat flux due to KE exchanges
- Monitor the induced temperature profile
- Reverse of previous method



### Muller-Plathe reverse perturbation method


- LAMMPS implementation:
  - fix thermal/conductivity swaps KE and tallies heat flux
  - fix ave/spatial monitors induced temperature gradient

$$\kappa = \frac{\Delta Q}{2Area\Delta t} \frac{\Delta z}{\Delta T}$$

### Script for Muller-Plathe reverse method

```
# thermal conductivity calculation
compute ke all ke/atom
variable temp atom c_ke/1.5
fix 1 all nve
fix 2 all ave/spatial 10 100 1000 z lower 0.05 &
 v_temp file tmp.profile units reduced
fix 3 all thermal/conductivity 10 z 20
variable tdiff equal f_2[11][3]-f_2[1][3]
thermo_style custom step temp epair etotal &
  f 3 v tdiff
run 20000
```

### Output for Muller-Plathe reverse method




Step Temp E\_pair TotEng 3 tdiff

...

 $40000\ 1.4071151\ -3.8068479\ -1.6964391\ 14307.339\ 1.1772366$   $41000\ 1.4126121\ -3.8153948\ -1.6967416\ 15087.11\ 1.1408062$  Loop time of 23.9599 on 8 procs for 20000 steps with 8000 atoms

### (3) Variant of Muller-Plathe reverse perturbation method

- Define hot and cold regions of simulation box
- Add/subtract energy continuously to all atoms in these regions
- Equal and opposite heat flux
- Monitor the induced temperature profile



#### Variant of Muller-Plathe method


- LAMMPS implementation:
  - fix heat adds/subtracts KE in a region
  - fix ave/spatial monitors induced temperature gradient

$$\kappa = \frac{\Delta Q}{2Area\Delta t} \frac{\Delta z}{\Delta T}$$

### Script for variant of Muller-Plathe method

```
# thermal conductivity calculation
fix hot all heat 1 100.0 region hot
fix cold all heat 1 -100.0 region cold
compute ke all ke/atom
variable temp atom c_ke/1.5
fix 2 all ave/spatial 10 100 1000 z lower 0.05 &
  v_temp file tmp.heat.profile units reduced
variable tdiff equal f_2[11][3]-f_2[1][3]
run 20000
```

### Output for variant of Muller-Plathe method



#### Step Temp Thot Tcold tdiff

. . .

30000 1.382101 1.9337034 1.0679145 -0.79821576 31000 1.3779178 1.8832819 1.0837774 -0.80611097 Loop time of 24.3193 on 8 procs for 20000 steps with 8000 atoms

# (4) Green-Kubo equilibrium method

- Relate ensemble average of auto-correlation of J to  $\kappa$
- Equilibrium J computable from per-atom KE, PE, virial

$$\kappa = \frac{V}{k_B T^2} \int_0^\infty \langle J_x(0) J_x(t) \rangle dt = \frac{V}{3k_B T^2} \int_0^\infty \langle \mathbf{J}(0) \cdot \mathbf{J}(t) \rangle dt$$

$$\mathbf{J} = \frac{1}{V} \left[ \sum_{i} e_{i} \mathbf{v}_{i} - \sum_{i} \mathbf{S}_{i} \mathbf{v}_{i} \right]$$

$$= \frac{1}{V} \left[ \sum_{i} e_{i} \mathbf{v}_{i} + \sum_{i < j} (\mathbf{f}_{ij} \cdot \mathbf{v}_{j}) \mathbf{x}_{ij} \right]$$

$$= \frac{1}{V} \left[ \sum_{i} e_{i} \mathbf{v}_{i} + \frac{1}{2} \sum_{i < i} (\mathbf{f}_{ij} \cdot (\mathbf{v}_{i} + \mathbf{v}_{j})) \mathbf{x}_{ij} \right]$$

#### Green-Kubo method

- LAMMPS implementation:
  - compute heat/flux calculates J tensor
  - fix ave/correlate performs auto-correlation
  - variable trap() function performs time integration

### Script for Green-Kubo method

```
compute myKE all ke/atom
compute myPE all pe/atom
compute myStress all stress/atom virial
compute flux all heat/flux myKE myPE myStress
fix JJ all ave/correlate $s $p $d &
  c_flux[1] c_flux[2] c_flux[3] type auto &
  file tmp.heatflux ave running
variable k11 equal trap(f_JJ[3])*${scale}
variable k22 equal trap(f_JJ[4])*${scale}
variable k33 equal trap(f_JJ[5])*${scale}
run 100000
```

### Output for Green-Kubo method

```
Step Temp k11 k22 k33
```

. . .

98000 1.3477904 3.2534428 2.8638625 3.8437754 100000 1.3583776 3.3351133 2.859474 3.7715301 Loop time of 52.1737 on 8 procs for 100000 steps with 4000 atoms

```
variable kappa equal (v_k11+v_k22+v_k33)/3.0
print "thermal conductivity: ${kappa}"
```

### Comparing the 4 methods for thermal conductivity

Liquid Argon at state point:  $\rho^*=0.6$ ,  $T^*=1.35$ ,  $R_c=2.5~\sigma$  D Evans, Phys Rev A, 34, 1449 (1986)

Method	$\kappa$
Direct thermostat	3.41
Muller-Plathe	3.45
M-P with fix heat	3.39
Green-Kubo	3.78
Evans paper	~3.3
Experiment	agrees with Evans

# Comparing the 4 methods for thermal conductivity

Liquid Argon at state point:  $\rho^*=0.6$ ,  $T^*=1.35$ ,  $R_c=2.5~\sigma$  D Evans, Phys Rev A, 34, 1449 (1986)


Method	$\kappa$
Direct thermostat	3.41
Muller-Plathe	3.45
M-P with fix heat	3.39
Green-Kubo	3.78
Evans paper	~3.3
Experiment	agrees with Evans

- Small systems have boundary effects
- Need to monitor equilibration and statistical noise
- Factors of 2 are easy to miss!

# (1) Shearing via moving wall

#### LAMMPS methodology:


- Rigid, moving wall
- Fix addforce can apply load if desired
- Important to thermostat flow since adding energy
  - fix langevin on non-sheared dimensions
  - compute temp/profile to subtract flow profile
- Monitor P<sub>xz</sub> and velocity profile of flow



# (2) Shearing via deforming box

#### LAMMPS methodology:


- Fix deform for box deformation
- Important to thermostat flow since adding energy
  - fix nvt/sllod for SLLOD equations of motion
  - Evans and Morriss,
     Phys Rev A, 30, 1528 (1984)
- Monitor P<sub>xz</sub> and velocity profile of flow
  - insure flow profile agrees with box deformation



### (3) Muller-Plathe reverse perturbation method

Muller-Plathe, Phys Rev E, 59, 4894 (1999)

- Define two slabs within simulation box
- Find max V<sub>x</sub> in one region, max - V<sub>x</sub> in other region
- Fix viscosity swaps momenta of these 2 atoms (or molecules)
- Tally momentum flux due to exchanges
- Monitor the induced velocity profile
- Reverse of previous methods



### (4) Green-Kubo equilibrium method

ullet Relate ensemble average of auto-correlation of  $P_{xz}$  to  $\eta$ 

$$\eta = rac{V}{k_B T} \int_0^\infty \langle P_{xz}(0) P_{xz}(t) \rangle dt$$

- $P_{xz}$  computable from virial
- Fix ave/correlate performs auto-correlation
- Variable trap() function performs time integration

# Comparing the 4 methods for viscosity

LJ at state point:  $\rho^* = 0.6$ ,  $T^* = 1.0$ ,  $R_c = 2.5 \sigma$  Woodcock, AIChE Journal, 52, 438 (2006)

Method	$\eta$
Moving wall	0.946
Deforming box	1.18
Muller-Plathe	0.997
Green-Kubo	1.07
literature value	$\sim$ 1.0


# Comparing the 4 methods for viscosity

LJ at state point:  $\rho^* = 0.6$ ,  $T^* = 1.0$ ,  $R_c = 2.5 \sigma$  Woodcock, AIChE Journal, 52, 438 (2006)


Method	$\eta$
Moving wall	0.946
Deforming box	1.18
Muller-Plathe	0.997
Green-Kubo	1.07
literature value	$\sim$ 1.0

- Small systems have boundary effects
- Need to monitor equilibration and statistical noise
- Factors of 2 are easy to miss!


# Shear viscosity for rigid-bodies in SRD fluid



# Shear viscosity for aspherical bodies in SRD fluid



### Shear viscosity for aspherical bodies in SRD fluid



Any of these examples could use short-chain polymer solvents

#### Trade-offs between methods

- NEMD methods pros:
  - intuitive to understand
  - quick to converge
- NEMD methods cons:
  - unphysically large temperature gradients and heat fluxes
  - bigger systems to allow for gradient

#### Trade-offs between methods

- NEMD methods pros:
  - intuitive to understand
  - quick to converge
- NEMD methods cons:
  - unphysically large temperature gradients and heat fluxes
  - bigger systems to allow for gradient
- Green-Kubo method pros:
  - equilibrium simulation
  - can use smaller system
- Green-Kubo method cons:
  - slow to converge
  - hard to tell when correlation integral has converged

- Focus on viscosity (or thermal conductivity) (or both!)
  - viscosity simulations are more visual to animate
- Study scripts in examples/VISCOSITY (or examples/KAPPA)
  - 4 scripts, for each of 4 methods
  - understand what each command and parameter represents
- Figure out how to analyze output to get  $\eta$  (or  $\kappa$ )

- Focus on viscosity (or thermal conductivity) (or both!)
  - viscosity simulations are more visual to animate
- Study scripts in examples/VISCOSITY (or examples/KAPPA)
  - 4 scripts, for each of 4 methods
  - understand what each command and parameter represents
- Figure out how to analyze output to get  $\eta$  (or  $\kappa$ )

- Reproduce 4 values in examples/VISCOSITY/README
- Do scripts run faster in parallel?
- Do they produce the same answers in parallel?

- Change parameters in input scripts:
  - size of system, density, temperature
  - shear rate, cutoff of potential
- IMPORTANT When you change script and do a new run:
  - visualize to insure system dynamics are normal
  - monitor velocity (or temperature) profile
  - check convergence of G-K integrations
  - are you running long enough?
- Otherwise your  $\eta$  or  $\kappa$  values may be bogus

- Change parameters in input scripts:
  - size of system, density, temperature
  - shear rate, cutoff of potential
- IMPORTANT When you change script and do a new run:
  - visualize to insure system dynamics are normal
  - monitor velocity (or temperature) profile
  - check convergence of G-K integrations
  - are you running long enough?
- ullet Otherwise your  $\eta$  or  $\kappa$  values may be bogus
- Choose one larger/smaller value of a parameter
  - how much larger or smaller?
- Does  $\eta$  (or  $\kappa$ ) change with that parameter?
- Do all methods still agree?
- Does variation make physical sense?

- Make a plot as vary a parameter over a wide range
  - size of system, density, temperature
  - shear rate, cutoff of potential
- E.g.  $\eta$  versus shear-rate for shear-thinning
- What other parameters should remain constant?
  - e.g. temperature, pressure
- How much can parameter vary before dynamics break down?
  - e.g. liquid crystallizes at too high a density

- Make a plot as vary a parameter over a wide range
  - size of system, density, temperature
  - shear rate, cutoff of potential
- E.g.  $\eta$  versus shear-rate for shear-thinning
- What other parameters should remain constant?
  - e.g. temperature, pressure
- How much can parameter vary before dynamics break down?
  - e.g. liquid crystallizes at too high a density
- Bonus: modify script to run series of simulations as parameter varies
  - see Section\_howto.html 6.4 and variable command
- Bonus: run/viz M-P viscosity scripts in examples/ASPHERICAL