CSE 3320 Operating Systems I/O Devices

Jia Rao

Department of Computer Science and Engineering

http://ranger.uta.edu/~jrao

Recap of Previous Classes

- CPU scheduling
- Memory management
- File Systems
- This chapter → I/O devices (e.g., hard disks)

I/O of an OS

Main Function: Control all the computer's I/O devices

- Issue commands to the devices, catch interrupts, and handle errors
- Provide interface between the devices and the rest of system that is simple and easy to use

What we care I/O devices most as software designers and programmers?

The interface presented to us:

- (1) The commands the hardware accepts
- (2) The functions it carries out
- (3) The errors that can be reported back

Principles of I/O Hardware: I/O Devices

- Block devices
- Character devices
- Others

Device	Data rate
Keyboard	10 bytes/sec
Mouse	100 bytes/sec
56K modem	7 KB/sec
Telephone channel	8 KB/sec
Dual ISDN lines	16 KB/sec
Laser printer	100 KB/sec
Scanner	400 KB/sec
Classic Ethernet	1.25 MB/sec
USB (Universal Serial Bus)	1.5 MB/sec
Digital camcorder	4 MB/sec
IDE disk	5 MB/sec
40x CD-ROM	6 MB/sec
Fast Ethernet	12.5 MB/sec
ISA bus	16.7 MB/sec
EIDE (ATA-2) disk	16.7 MB/sec
FireWire (IEEE 1394)	50 MB/sec
XGA Monitor	60 MB/sec
SONET OC-12 network	78 MB/sec
SCSI Ultra 2 disk	80 MB/sec
Gigabit Ethernet	125 MB/sec
Ultrium tape	320 MB/sec
PCI bus	528 MB/sec
Sun Gigaplane XB backplane	20 GB/sec

Some typical device, network, and data base rates

Device Controllers

- I/O devices have two components:
 - mechanical component
 - electronic component
- The electronic component is the *device controller*
 - may be able to handle multiple but identical devices
- Controller's tasks
 - convert serial bit stream to block of bytes
 - perform error correction as necessary
 - make blocks available to main memory

buffer/cache register Device controller I/O Device

Standard interface: IDE, SCSI

CPU→I/O: Special I/O Instructions

- How does the CPU communicate with the control registers and the device data buffers? Two methods are available.
- Method I: Special (assembly) I/O Instructions (IBM 360)
 - Each control register is assigned an I/O port number (device #)


```
IN REG, PORT
OUT PORT, REG
```

The memory address space and I/O address space are different

```
IN R0, 4 ; port 4
MOV R0, 4 ; memory word 4
```


CPU→I/O: Memory-mapped I/O

- ° Method II: Memory-mapped I/O (Pentium)
 - Each register is assigned a unique memory address to which no memory is assigned; read/write to addresses are I/O operations
 - How it works?



$CPU \rightarrow I/O$: Memory-mapped I/O (2)


- Advantages of Memory-mapped I/O
 - An I/O device driver can be written in C, instead of assembly
 - Protection is easy (by address translation); user programs are prevented from issuing I/O operations directly



(a) Separate I/O and memory space; (b) Memory-mapped I/O; (c) Hybrid (PDP-11) (Pentium)

$CPU \rightarrow I/O$: Memory-mapped I/O (3)

- ° Disadvantages of Memory-mapped I/O
 - Caching a device control register would be disastrous
 - Both memory and all I/O devices must examine all memory references to see which ones to respond to, not easy if bus hierarchy




(a) A single-bus architecture;

(b) A dual-bus memory architecture

CPU→I/O: Memory-mapped I/O (4)

PCI bridge chip filters addresses to different buses




I/O CPU: Device Notifying the CPU

- The OS needs to know when:
 - The I/O device has completed an operation
 - The I/O operation has encountered an error
- This can be accomplished in two different ways:
 - Polling (Busy Waiting):
 - ▶ The I/O device put information in a status register
 - The CPU periodically or continuously check the status register
 - o I/O Interrupt:
 - Whenever an I/O device needs attention from the processor, it interrupts the processor from what it is currently doing.

In real-time systems, a hybrid approach is often used

Use a clock to periodically interrupt the CPU, at which time the CPU polls all I/O devices


Data Transfer: Programmed I/O (Busy Waiting)



busy wait loop not an efficient way to use the CPU unless the device is very fast!

- Advantage:
- Disadvantage:
 - Polling overhead can consume a lot of CPU time


Data Transfer: Interrupt Driven



- Disadvantage, special hardware is needed to:
 - Cause an interrupt (I/O device)
 - Detect an interrupt (processor)
 - Save the proper states to resume after the interrupt (processor)


Direct Memory Access (DMA)

- DMA controller has access to system bus independent of CPU
 - A memory address register
 - A byte count register
 - A control register (direction, transfer unit, and transfer mode)




DMA Transfer Modes

- Cycle stealing mode: word-at-a-time, sneaks in and steals an occasional bus cycle from the CPU once in a while
- Burst mode: asks I/O device to acquire the bus, issue a series of transfers, then release the bus
- Tradeoff: I/O efficiency and CPU blocked
 Why need an internal buffer at the disk controller?



Interrupts Revisited

- One way of how I/O notifies CPU
 - Interrupt vector and interrupt service procedures
 - Priority if multiple simultaneous interrupts
 - CPU delays ACK until it is ready to handle the next interrupt is a way to avoid race conditions involving multiple almost simultaneous interrupts



Goals of I/O Software


- Device independence
 - Write programs that can access any I/O device without specifying device in advance
 - (floppy, hard drive, or CD-ROM)
- Uniform naming
 - name of a file or device a string or an integer (e.g., path name)
 - not depending on which machine / device
 - UNIX Mount System
- Error handling
 - handle as close to the hardware as possible, i.e., controller first then device driver next

Goals of I/O Software (2)

- Synchronous vs. asynchronous transfers
 - blocked transfers vs. interrupt-driven
 - Logically synchronous to programmers and physically asynchronous
- Buffering
 - data coming off a device cannot be stored *directly* in final destination, e.g.,
 network-I/O operations
 - For checksum and timing constraints
- Sharable vs. dedicated devices
 - disks are sharable
 - tape drives would not be
 - dedication introduces deadlock
 What are three fundamental different ways of performing I/O?

Programmed I/O

- Polling (busy waiting)
 - CPU continuously polls the device (register) to see if it is ready
 - Simple but CPU time wasteful



Steps in printing a string

Programmed I/O (2)

Writing a string to the printer using programmed I/O

What if the printer can print 100 character/sec?

CPU would be idle for 10ms each loop iteration! Why not switching to another process?



Interrupt-Driven I/O

 A way to allow the CPU to do something else while waiting for the printer to become ready

Still, an interrupt occurs every character, what to do?

```
copy_from_user(buffer, p, count);
enable_interrupts();
while (*printer_status_reg != READY);
*printer_data_register = p[0];
scheduler();

(a)

if (count == 0) {
    unblock_user();
} else {
    *printer_data_register = p[i];
    count = count - 1;
    i = i + 1;
}
acknowledge_interrupt();
return_from_interrupt();
```

Writing a string to the printer using interrupt-driven I/O

- (a) Code executed when print system call is made
- (b) Interrupt service procedure


I/O Using DMA

- A way to reduce the number of interrupts from one per character to one per buffer printed
 - Transfers a block of data directly to or from memory
 - An interrupt is sent when the task is complete
 - The processor is only involved at the beginning and end of the transfer

- Printing a string using DMA
 - code executed when the print system call is made
 - interrupt service procedure

I/O Software Hierarchy

One objective: as little of OS as possible knows about the interrupts



Layers of the I/O Software System

How about the following jobs:

- (1) Check if the user is permitted to use the device
- (2) Writing commands to the device registers
- (3) Formatting the output data for printing

OS Interrupt Handling

Interrupt vector

- contains the address of the interrupt service procedures
- Jump table
 - 1. Hardware stacks program counter, etc.
 - 2. Hardware loads new program counter from interrupt vector.
 - 3. Assembly language procedure saves registers.
 - 4. Assembly language procedure sets up new stack.
 - 5. C interrupt service runs (typically reads and buffers input).
 - 6. Scheduler decides which process is to run next.
 - 7. C procedure returns to the assembly code.
 - 8. Assembly language procedure starts up new current process.

Skeleton of what lowest level of OS does when an interrupt occurs when a process is running




Interrupt Handlers

- Interrupt handlers are best hidden
 - have driver starting an I/O operation block until interrupt notifies of completion
- Interrupt procedure does its task, handling interrupts
 - then unblocks driver that started it
- But actually, many OS steps must be performed in software after hardware interrupt has completed
 - Save regs not already saved by interrupt hardware
 - 2. Set up context for interrupt service procedure
 - 3.

Device Drivers

Device drivers: provided by device's manufacturer, device-specific code for controlling the device (via device controller registers)



- Logical position of device drivers is shown here
- Communications between drivers and device controllers go over the bus

Device Drivers Installation

How to install device drivers to OS kernel?

- Static installation and recompiling (Unix)
 - Recompile the kernel with the new driver
- Static registration and rebooting (early Windows)
 - Make an entry in an OS file and reboot the system
- Dynamic installation (Windows & Unix)
 - On-the-fly loading into the system during the execution

Device-Independent I/O Software

The basic function is to perform the I/O functions that are common to all devices and to provide a uniform interface to the user-level software

Uniform interfacing for device drivers

Buffering


Error reporting

Allocating and releasing dedicate devices

Providing a device-independent block size


Functions of the device-independent I/O software

An Example of Device-independent I/O Software




Buffering

- ° (a) Unbuffered input: doesn't it have too many interrupts?
- ° (b) Buffering in user space: What happens if the buffer is *paged out* (to disk) when a character arrives? Go pinning?
- ° (c) Buffering in the kernel followed by copying to user space
 - What happens to characters that arrive while the page with the user buffer is being brought (in memory) from the disk?
- ° (d) *Double buffering* in the kernel; two buffers take turns.



Disadvantages of Buffering


- ° Why the process does not copy the data to the wire directly from kernel memory?
 - But how about the performance?
 - Why not bit-by-bit from the kernel buffer to the network?



Networking may involve many copies of a packet, and all steps must happen sequentially


User-Space I/O Software

- Some of I/O software consists of user-space libraries
 - The standard I/O library contains a number of procedures that involve with I/O and all run as part of user programs
 - E.g., scanf(), printf() for I/O formatting, Intel DPDK for high-speed NICs



Layers of the I/O system and the main functions of each layer

Hard Disks



- The conventional sector-track-cylinder model
 - A stack of platters, a surface with a magnetic coating
 - Magnetic disks are organized into cylinders, for S/R/W
- Overlapped seeks: one disk controller seeks 2+ drives simultaneously
 - Transfer between the disk and the controller can be simultaneous
 - But one transfer between the controller and the main memory

Three-Stage Disk R/W Process

- Three-stage Disk R/W process: time required to read or write a disk block determined mainly by 3 factors
 - Seek time
 - 2. Rotational delay
 - 3. Actual transfer time
- Seek time dominates


```
Disk Access Time = Seek time + Rotational Latency + Transfer time + Controller Time + Queuing Delay
```

How to optimize seek time?

Disk arm scheduling algorithms

SSF Disk Arm Scheduling Algorithm

- * How to optimize seek time if a table available, indexed by cylinder number, with all the *pending disk requests* for each cylinder chained in a linked list headed by the table entries?
 - Example: 11 (c), 1, 36, 16, 34, 9, 12 by FCFS and SSF
 - SSF cuts average seek time of FCFS almost in half (111→61)





Shortest Seek First (SSF) disk scheduling algorithm

What is the key problem with SSF? How would you deal with it?

The Elevator Disk Arm Scheduling Algorithm

- Elevator algorithm: keep moving in the same direction until there are no more *outstanding* requests in that direction
 - One current direction bit: UP and Down
 - Property: given any collection of requests, the upper bound on the total motion is fixed: twice the number of cylinders
 - Example: 11 (c), 1, 36, 16, 34, 9, 12 by the elevator






The elevator algorithm for scheduling disk requests

Error Handling

- Two general approaches to deal with bad blocks/sectors
 - disk controller based vs. OS based




Controller does sector substitution

OS does step (c)

- A disk track with a bad sector.
- Substituting a spare for the bad sector
- Shifting all the sectors to bypass the bad one

Clocks (Timers)

- Clock hardware: generate interrupts at known intervals
 - A programmable clock: its interrupt frequency can be controlled by software
 - A 500 MHz crystal with a 32-bit register can generate interrupt every 2ns to 8.6s




Clock Software

- ° Clock Software (clock driver):
 - Maintaining the time of day
 - support time-shared scheduling
 - Accounting CPU usage
 - Handling the *alarm* system call
 - •

Maintaining the Time of Day

- ° How about incrementing a counter at each clock tick?
 - Given a clock rate of 60 Hz, a 32-bit counter last about 2 years



- (a) Using 64-bits counter
- (b) Recording time in terms of seconds with a second counter in ticks
- (c) Relative to system boot time, instead of a fixed external moment

Soft Timers

- There is a need of a second hardware clock to cause timer interrupts at whatever rate a program needs
 - specified by applications
 - no problems if interrupt frequency is low
- Two ways of managing I/O
 - Polling has an average latency of half the polling interval
 - Interrupt can be costly, say 4.45μs on a 300 MHz PII
 - A Giga-bit Ethernet asks for a packet every 12 μs
- Soft timers avoid costly interrupts
 - kernel checks for soft timer expiration before it exits to user mode
 - how well this works depends on rate of kernel entries!
 The combination of soft timers and a low-frequency hardware timer may be better than pure interrupt-driven I/O or pure polling

Power Management


- Power consumption is important to desktops and battery-powered computer
- Two General approaches to battery conservation
 - Turn off (down) some parts, top 3 power eaters: display, hard disk, and CPU
 - Application uses less power, multiple states: on/off, sleep, hibernating

Device	Li et al. (1994)	Lorch and Smith (1998)
Display	68%	39%
CPU	12%	18%
Hard disk	20%	12%
Modem		6%
Sound		2%
Memory	0.5%	1%
Other		22%

Power consumption of various parts of a laptop computer

Power-aware computing in mobile and sensor networks, many tradeoffs!

OS Issues: The Display




- ° On-off switching
 - Display consist of some zones that can be independently powered up or down


OS Issues: The Hard Disk

- It takes substantial energy to keep it spinning at high speed, even if there are no disk accesses
- But Restarting a hard disk consumes considerable energy
 - What is the break-even point?
 - Td [5s, 15s]
 - If the next disk access is expected some time t in the future, compare t to Td
 determines the appropriate disk action
- Alternative: have a substantial disk cache in RAM
- Alternative: OS keeps running programs informed about the disk states, so that some accesses can be delayed (and clustered)

Something can be done to CPU too!

OS Issues: The CPU





- Running at full clock speed (full voltage)
- Cutting voltage by two
 - cuts clock speed by two
 - cuts power by four (power consumption ~ voltage^2)

Summary

- OS responsibilities in I/O operations
 - Protection and Scheduling
 - CPU communicates with I/O devices
 - I/O devices notify OS/CPU
- I/O software hierarchy
 - Interrupt handlers
 - Device drivers
 - Buffering
- Storage Systems
 - Disk head scheduling algorithms
- Power Management

Thank you all!