TASSEL 5.0 Pipeline Command Line Interface: Guide to using Tassel Pipeline

Terry Casstevens (tmc46@cornell.edu)

Institute for Genomic Diversity, Cornell University, Ithaca, NY 14853-2703 *August 8, 2014*

Prerequisites

Source Code

Install

Execute

Increasing Heap Size

Setting Logging to Debug

Examples

Examples (XML Configuration Files)

<u>Usage</u>

Pipeline Controls

Data

Filter

Analysis

Results

Prerequisites

Java JDK 8.0 or later (http://java.sun.com/javase/downloads/index.jsp).

Source Code

```
git clone https://bitbucket.org/tasseladmin/tassel-5-source.git
```

Install

```
git clone <a href="https://bitbucket.org/tasseladmin/tassel-5-standalone.git">https://bitbucket.org/tasseladmin/tassel-5-standalone.git</a>
```

OR

https://bitbucket.org/tasseladmin/tassel-5-standalone/downloads (Click on "Tags")

Execute

On Windows, use run pipeline. bat to execute the pipeline.

In UNIX, use run_pipeline.pl to execute the pipeline. If you are using a Bash Shell on Windows, you may need to change the following line to use a; instead of a:.

```
my $CP = join(":", @fl);
```

To launch the Tassel GUI that automatically executes a pipeline, use start_tassel.bat or start_tassel.pl instead of run_pipeline.bat or run_pipeline.pl respectively.

These scripts have a \$top variable that can be changed to the absolute path of your installation. That way, you can execute them any directory.

Increasing Heap Size

To modify the initial or maximum heap size available to the Tassel Pipeline, either edit run_pipeline.pl or specify values via the command line.

```
./run pipeline.pl -Xms512m -Xmx10g -fork1...
```

Setting Logging to Debug

```
./run pipeline.pl -debug ...
```

Examples

```
./run_pipeline.pl -fork1 -h chr1_5000sites.txt -ld -ldd png -o
chr1_5000sites_ld.png -runfork1
./run_pipeline.pl -fork1 -h chr1_5000sites.txt -ld -ldd png -o
chr1_5000sites_ld.png -runfork1
./run_pipeline.pl -fork1 ... -fork2 ... -combine3 -input1 -input2 ... -fork4
-<flag> -input3 -runfork1 -runfork2
```

Examples (XML Configuration Files)

This command runs the Tassel Pipeline according to the specified configuration file... Configuration files are standard XML notation. The tags are the same as the below documented flags although no beginning dash is used. See the example pipelines directory for some common XML configurations.

```
./run pipeline.pl -configFile config.xml
```

This command creates the XML configuration file from the original command line flags. Simply insert the -createXML and filename at the beginning. Only the XML is created. It does not run the pipeline...

```
./run pipeline.pl -createXML config.xml -fork1 ...
```

This command translates the specified XML configuration file back into the original command line flags... It does not run the pipeline...

```
./run pipeline.pl -translateXML config.xml
```

Usage

Pipeline Controls	
-fork <id></id>	This flag identifies the start of a pipeline segment that should be executed sequentially. <id> can be numbers or characters (no spaces). No space between -fork and <id> either. Other flags can reference the <id>.</id></id></id>
-runfork <id></id>	This flag identifies a pipeline segment to execute. This will usually be the last argument. This explicitly executes the identified pipeline segment. This should not be used to execute pipeline segments that receive input from other pipeline segments. Those will start automatically when it receives the input.
-input <id></id>	This specifies a pipeline segment as input to the plugin prior to this flag. That plugin must be in the current pipeline segment. Multiple of these can be specified after plugins that accept multiple inputs. ./run_pipeline.pl -fork1 -h genotype.hmp.txt -fork2 -r phenotype.txt -combine3 -input1 -input2 -intersect -runfork1 -runfork2
	./run_pipeline.pl -fork1 -h genotype.hmp.txt -fork2 -includeTaxaInFile taxaList1.txt -input1 -export file1 -fork3 -includeTaxaInFile taxaList2.txt -input1 -export file2 -runfork1
-inputOnce <id></id>	This specifies a pipeline segment as a one-time input to a -combine. As such, this flag should follow -combine. After the -combine has received data from this input, it will use it for every iteration. Whereas -combine waits for data specified by -input each iteration. Multiple of these can be specified.
-combine <id></id>	This flag starts a new pipeline segment with a CombineDataSetsPlugin at the beginning. The CombineDataSetsPlugin is used to combine data sets from multiple pipeline segments. Follow this flag with -input <id> and/or -inputOnce<id> flags to specify which pipeline segments should be combined.</id></id>

-separate	This separates an input into its components if
<pre><chromosomes></chromosomes></pre>	possible. For example, alignments separated by chromosome (locus). For alignments, optionally specify list of chromosomes (separated by commas and no spaces) to separate. Specifying nothing returns all chromosomes. Example: run_pipeline.pl -fork1 -h file.hmp.txt -separate 3,6 -export -runfork1
-homozygous	This converts any heterozygous values to
	<pre>unknown/run_pipeline.pl -h file.hmp.txt -homozygous -export</pre>
-mergeGenotypeTabless	Merges multiple Alignments regardless of taxa or site name overlap. Undefined taxa / sites are set to UNKNOWN. Duplicate taxon / site set to last Alignment processed. Example: run_pipeline.pl -fork1 -h file1.hmp.txt -fork2 -h file2.hmp.txt -combine3 -input1 -input2 -mergeGenotypeTables -export files_merged.hmp.txt -runfork1 -runfork2
-mergeAlignmentsSameSite s -input <files> -output <filename></filename></files>	Merges Alignments assuming all sites are the same in all Hapmap files. Input files separated by commas without spaces. The resulting file may have incorrect major/minor alleles, strand, center, etc. It uses values from first specified input file. Checks that Site Name, Chromosome, and Physical Position match for each site. Example: run_pipeline.pl -fork1 -mergeAlignmentsSameSites -input file1.hmp.txt,file2.hmp.txt -output temp -runfork1
<pre>-export <filename1, filename2,=""></filename1,></pre>	Exports input dataset to specified filename(s). If no -exportType follows this parameter, the exported format will be determined by the type of input (i.e. Alignments will default to Hapmap format). Exportable datasets, other that Alignment, only have one format option. Therefore, there is no need to specify -exportType. Specify none, one, or multiple filenames matching the number of input data sets. If no filenames, the files will be named the same as the input data sets. If only one specified for multiple data sets, a count starting with 1 will be added to each resulting file. If multiple filenames (separated with commas but no spaces), there should be one for each input. When exporting Hapmap files, if the

	extension is .hmp.txt.gz, the file will be gzipped.
-exportType <type></type>	Defines format that previously specified -export should use. Type can be Hapmap, HapmapDiploid, HDF5, VCF, Plink, zipBLOB (only Tassel 3), gzipBLOB (only Tassel 3), Flapjack, Phylip Seq, Phylip Inter, Text.
' 1 1 m	
-includeTaxa <taxon1,taxon2,></taxon1,taxon2,>	Filters input alignment to only include specified taxa. The taxa should be separated with commas and no spaces.
<pre>-includeTaxaInFile <filename></filename></pre>	Filters input alignment to only include taxa specified in file. The taxa cannot have spaces. Individual taxa should be separated by white space.
-excludeTaxa <taxon1,taxon2,></taxon1,taxon2,>	Filters input alignment to exclude specified taxa. The taxa should be separated with commas and no spaces.
-excludeTaxaInFile <filename></filename>	Filters input alignment to exclude taxa specified in file. The taxa cannot have spaces. Individual taxa should be separated by white space.
<pre>-includeSiteNames <sitename1,sitename2,></sitename1,sitename2,></pre>	Filters input alignment to only include specified site names. The site names should be separated with commas and no spaces.
-includeSiteNamesInFil e <filename></filename>	Filters input alignment to only include site names specified in file. The site names cannot have spaces. Individual site names should be separated by white space.
-excludeSiteNames <taxon1,taxon2,></taxon1,taxon2,>	Filters input alignment to exclude specified site names. The site names should be separated with commas and no spaces.
-excludeSiteNamesInFil e <filename></filename>	Filters input alignment to exclude site names specified in file. The site names cannot have spaces. Individual site names should be separated by white space.
-excludeLastTrait	This removes last column of Phenotype data. For example Can be used to remove last column of population structure for use with MLM or GLM.
-subsetSites <num></num>	This filters an alignment to include a random subset of sites. If <num> is >=1, it specifies the total number of sites to keep. If it is a decimal, it specifies the fraction of sites to keep. Adding the flag "-step" immediately after</num>

	<pre><num> tells the plugin to space the selected sites evenly instead of randomly.</num></pre>
-subsetTaxa <num></num>	This filters an alignment to include a random subset of taxa. If <num> is >=1, it specifies the total number of taxa to keep. If it is a decimal, it specifies the fraction of taxa to keep. Adding flag "-step" immediately after <num> tells the plugin to space the selected taxa evenly instead of randomly.</num></num>
-step	This tells the previously specified -subsetTaxa or -subsetSites plugin to select sites/taxa evenly across the alignment instead of randomly.
<pre>-numericalGenoTransfor m <type></type></pre>	Performs genotype to numerical transform. <type> can be collapse or separated.</type>
-newCoordinates <map< td=""><td>This converts alignment to new coordinates</td></map<>	This converts alignment to new coordinates
filename>	specified in given map file.
-synonymizer	Runs the Synonymizer using the input dataset.
Filter	
Filter	
-filterAlign	Filters an alignment by sites.
-filterAlign -filterAlignMinCount	Filters an alignment by sites. Specifies the minimum count (default: 1) for
-filterAlignMinCount	Specifies the minimum count (default: 1) for
-filterAlignMinCount <num> -filterAlignMinFreq <num></num></num>	Specifies the minimum count (default: 1) for the previously specified -filterAlign. Specifies the minimum frequency (default: 0.0) for the previously specified -filterAlign.
-filterAlignMinCount <num> -filterAlignMinFreq</num>	Specifies the minimum count (default: 1) for the previously specified -filterAlign. Specifies the minimum frequency (default: 0.0)
-filterAlignMinCount <num> -filterAlignMinFreq <num></num></num>	Specifies the minimum count (default: 1) for the previously specified -filterAlign. Specifies the minimum frequency (default: 0.0) for the previously specified -filterAlign. Specifies the maximum frequency (default 1.0)
-filterAlignMinCount <num> -filterAlignMinFreq <num> -filterAlignMaxFreq</num></num>	Specifies the minimum count (default: 1) for the previously specified -filterAlign. Specifies the minimum frequency (default: 0.0) for the previously specified -filterAlign. Specifies the maximum frequency (default 1.0) for the previously specified -filterAlign.
-filterAlignMinCount <num> -filterAlignMinFreq <num> -filterAlignMaxFreq -filterAlignStart</num></num>	Specifies the minimum count (default: 1) for the previously specified -filterAlign. Specifies the minimum frequency (default: 0.0) for the previously specified -filterAlign. Specifies the maximum frequency (default 1.0) for the previously specified -filterAlign. Specifies the starting site index (default value: 0) for the previously specified
-filterAlignMinCount <num> -filterAlignMinFreq <num> -filterAlignMaxFreq -filterAlignStart <num></num></num></num>	Specifies the minimum count (default: 1) for the previously specified -filterAlign. Specifies the minimum frequency (default: 0.0) for the previously specified -filterAlign. Specifies the maximum frequency (default 1.0) for the previously specified -filterAlign. Specifies the starting site index (default value: 0) for the previously specified -filterAlign. Specifies the end site index (default value: last site in alignment) for the previously
-filterAlignMinCount <num> -filterAlignMinFreq <num> -filterAlignMaxFreq -filterAlignStart <num> -filterAlignEnd <num></num></num></num></num>	Specifies the minimum count (default: 1) for the previously specified -filterAlign. Specifies the minimum frequency (default: 0.0) for the previously specified -filterAlign. Specifies the maximum frequency (default 1.0) for the previously specified -filterAlign. Specifies the starting site index (default value: 0) for the previously specified -filterAlign. Specifies the end site index (default value: last site in alignment) for the previously specified -filterAlign. Specifies the Locus to be used with the starting and ending physical positions if
-filterAlignMinCount <num> -filterAlignMinFreq <num> -filterAlignMaxFreq -filterAlignStart <num> -filterAlignEnd <num> -filterAlignLocus</num></num></num></num>	Specifies the minimum count (default: 1) for the previously specified -filterAlign. Specifies the minimum frequency (default: 0.0) for the previously specified -filterAlign. Specifies the maximum frequency (default 1.0) for the previously specified -filterAlign. Specifies the starting site index (default value: 0) for the previously specified -filterAlign. Specifies the end site index (default value: last site in alignment) for the previously specified -filterAlign. Specifies the Locus to be used with the starting and ending physical positions if defined. Defaults to first Locus in the
-filterAlignMinCount <num> -filterAlignMinFreq <num> -filterAlignMaxFreq -filterAlignStart <num> -filterAlignEnd <num> -filterAlignLocus <name></name></num></num></num></num>	Specifies the minimum count (default: 1) for the previously specified -filterAlign. Specifies the minimum frequency (default: 0.0) for the previously specified -filterAlign. Specifies the maximum frequency (default 1.0) for the previously specified -filterAlign. Specifies the starting site index (default value: 0) for the previously specified -filterAlign. Specifies the end site index (default value: last site in alignment) for the previously specified -filterAlign. Specifies the Locus to be used with the starting and ending physical positions if defined. Defaults to first Locus in the Alignment.
-filterAlignMinCount <num> -filterAlignMinFreq <num> -filterAlignMaxFreq -filterAlignStart <num> -filterAlignEnd <num> -filterAlignLocus <name> -filterAlignStartPos</name></num></num></num></num>	Specifies the minimum count (default: 1) for the previously specified -filterAlign. Specifies the minimum frequency (default: 0.0) for the previously specified -filterAlign. Specifies the maximum frequency (default 1.0) for the previously specified -filterAlign. Specifies the starting site index (default value: 0) for the previously specified -filterAlign. Specifies the end site index (default value: last site in alignment) for the previously specified -filterAlign. Specifies the Locus to be used with the starting and ending physical positions if defined. Defaults to first Locus in the Alignment. Specifies the starting physical position
-filterAlignMinCount <num> -filterAlignMinFreq <num> -filterAlignMaxFreq -filterAlignStart <num> -filterAlignEnd <num> -filterAlignLocus <name></name></num></num></num></num>	Specifies the minimum count (default: 1) for the previously specified -filterAlign. Specifies the minimum frequency (default: 0.0) for the previously specified -filterAlign. Specifies the maximum frequency (default 1.0) for the previously specified -filterAlign. Specifies the starting site index (default value: 0) for the previously specified -filterAlign. Specifies the end site index (default value: last site in alignment) for the previously specified -filterAlign. Specifies the Locus to be used with the starting and ending physical positions if defined. Defaults to first Locus in the Alignment.
-filterAlignMinCount <num> -filterAlignMinFreq <num> -filterAlignMaxFreq -filterAlignStart <num> -filterAlignEnd <num> -filterAlignLocus <name> -filterAlignStartPos</name></num></num></num></num>	Specifies the minimum count (default: 1) for the previously specified -filterAlign. Specifies the minimum frequency (default: 0.0) for the previously specified -filterAlign. Specifies the maximum frequency (default 1.0) for the previously specified -filterAlign. Specifies the starting site index (default value: 0) for the previously specified -filterAlign. Specifies the end site index (default value: last site in alignment) for the previously specified -filterAlign. Specifies the Locus to be used with the starting and ending physical positions if defined. Defaults to first Locus in the Alignment. Specifies the starting physical position (default is first site) for the previously
-filterAlignMinCount <num> -filterAlignMinFreq <num> -filterAlignMaxFreq -filterAlignStart <num> -filterAlignEnd <num> -filterAlignLocus <name> -filterAlignStartPos <num></num></name></num></num></num></num>	Specifies the minimum count (default: 1) for the previously specified -filterAlign. Specifies the minimum frequency (default: 0.0) for the previously specified -filterAlign. Specifies the maximum frequency (default 1.0) for the previously specified -filterAlign. Specifies the starting site index (default value: 0) for the previously specified -filterAlign. Specifies the end site index (default value: last site in alignment) for the previously specified -filterAlign. Specified -filterAlign. Specifies the Locus to be used with the starting and ending physical positions if defined. Defaults to first Locus in the Alignment. Specifies the starting physical position (default is first site) for the previously specified -filterAlign.

-filterAlignExtInd	Indicates that the last specified -filterAlign should extract indels. This is not done by default.
-filterAlignRemMinor	Indicates that the last specified -filterAlign should remove minor SNP states. This is not done by default.
-filterAlignSliding	Indicates that the last specified -filterAlign should use sliding windows. This in not done by default.
-filterAlignHapLen	Specifies the haplotype length (default value: 3) if using sliding windows.
-filterAlignStepLen <num></num>	Specifies the step length (default value: 3) if using sliding windows.
Analysis	
-glm	This takes a Phenotype dataset as input that is usually the intersection of sequence data, trait data, and population structure (optional).
-glmOutputFile <filename></filename>	This sends GLM results to specified filename.
-glmMaxP <number></number>	This restricts the output file to entries with P values no larger than number specified.
-glmPermutations <number></number>	This sets the number of permutations. Default is to not do run permutations.
-mlm	This takes a Phenotype dataset as input (usually the intersection of sequence data, trait data, and population structure (optional)) and a Kinship matrix.
-mlmVarCompEst <method></method>	Defines the Variance Component Estimation for the previously specified -mlm. Method can be P3D (default) or EachMarker.
-mlmCompressionLevel <level></level>	Defines the Compression Level for the previously specified -mlm. Level can be Optimum (default), Custom, or None.
-mlmCustomCompression <number></number>	This specifies the compression when compression level is Custom. Default value is 1.0.
-mlmOutputFile <filename></filename>	This sends MLM results to specified filename.
-mlmMaxP <number></number>	This restricts the output file to entries with P values no larger than number specified.
-diversity	Creates a Diversity Analysis step that uses an Alignment as input

-diversityStartBase	This sets start base for the previously
<number></number>	specified -diversity. Default is 0.
-diversityEndBase	This sets end base for the previously specified
<pre><number></number></pre>	-diversity. Default is last site.
-diversitySlidingWin	This uses sliding window analysis for the
-diversitysitatingwin	1
	previously specified -diversity.
-diversitySlidingWinStep	This sets the sliding window step size for the
<number></number>	previously specified -diversity. Default is
	100.
-diversitySlidingWinSize	This sets the sliding window size for the
<number></number>	previously specified -diversity. Default is
	500.
	300.
-ld	Creates LinkageDisequilibriumPlugin. Uses
	Alignment from previous step to analysis
	linkage disequilibrium.
-ldPermNum <number></number>	This sets permutation number for the previously
	specified -ld. Default is 1000.
-ldRapidAnalysis true	Sets whether to use rapid analysis for the
false	
	previously specified -ld. Default is true.
-ldWinSize <number></number>	Sets the window size for the previously
	specified -ld. Default is 50.
-ldType <type></type>	Sets the LD type for the previously specified
	-ld. Options are All, SlidingWindow (Default),
	and SiteByAll.
-ldTestSite <number></number>	Sets the test site for when LD type is set to
idiosesiee (namber)	
7 77 1 77 1 77	SiteByAll.
-ldHetTreatment <type></type>	Sets the LD Heterzygous Treatment Method. Type
	can be Haplotype (Default - For Inbred Lines),
	Homozygous (Uses only homozygous site -
	heterozygotes set to missing), or Genotype (Not
	Implemented Yet).
-ck	Calculates Kinship from Marker Data.
	calculated named from named baca.
+ 200 (2) 25 25 25	mbia amortos o trop maine sissen altestanias
-tree <clustering< td=""><td>This creates a tree using given clustering</td></clustering<>	This creates a tree using given clustering
method>	method: Neighbor (default) or UPGMA. When
	exporting, use -exportType Text to get text
	version.
-treeSaveDistance true	This saves the distance matrix of a tree.
false	Default is true.
-distanceMatrix	Calculate the distance matrix of given
discancenactia	
	Alignment.
-distMatrixRanges	Calculates genetic distances for given taxon in
	specified physical position ranges.

-distMatrixRangesLocus	Locus that specified physical positions
<locus></locus>	corresponds.
<pre>-distMatrixRangesTaxon <taxon></taxon></pre>	Taxon of interest.
-distMatrixRangesPos	Specified physical positions that define
<pos1, pos2,="" pos3,=""></pos1,>	ranges. A comma should separate each one with
	no spaces.
-distMatrixRangesPosFile	File with list of physical positions that
<filename></filename>	define ranges. Individual positions should be
	separated by white space.
-gs	Predicts phenotypes using ridge regression for
	genomic selection.
-genotypeSummary	This generates summaries for alignment
<types></types>	datasets. Types should be a comma-separated
	list (with no spaces) of the following
	(overall, site, taxa, all). Example
	-genotypeSummary overall,site
Results	
-td_csv <filename></filename>	Writes (comma delimited) TableReport from
	previous plugin in current pipeline to
	specified filename.
-td_tab <filename></filename>	Writes (tab delimited) TableReport from
	previous plugin in current pipeline to
	specified filename.
-td_gui	Displays TableReport from previous plugin in
	current pipeline in GUI.
-ldd <output type=""></output>	Creates LinkageDiseqDisplayPlugin. If output
	type is gui, this graphically displays results
	from a LinkageDisequilibriumPlugin. If output
	type is png, gif, bmp, jpg, or svg, then an
	image of that type is written to the output
	file specified with -o.
-ldplotsize <num></num>	Optionally specify LD plot size. Example: 1000
	will produce a 1000 x 1000 plot. Default: 500.
	This should follow the -ldd flag within the
	current pipeline segment.
-ldplotlabels true	Optionally specify whether to show the LD
false	Plot labels. DEFAULT: true. This should follow
	the -ldd flag within the current pipeline
0 (0)+5:+ 5:1->	segment.
-o <output file=""></output>	This should follow the -ldd flag within the
	current pipeline segment.