### assertz/1

### **Description**

```
assertz(Head)
assertz((Head:-Body))
```

Asserts a clause as the last one for an object's dynamic predicate. If the predicate is not already declared, then a dynamic predicate declaration is added to the object.

## Template and modes

```
assertz(+clause)
```

# **Errors**

```
Head is a variable:
```

```
instantiation_error
```

Head is a neither a variable nor a callable term:

```
type_error(callable, Head)
```

Body cannot be converted to a goal:

```
type_error(callable, Body)
```

The predicate indicator of Head is that of a private predicate:

```
permission_error(modify, private_predicate, Head)
```

The predicate indicator of Head is that of a protected predicate:

```
permission_error(modify, protected_predicate, Head)
```

The predicate indicator of Head is that of a static predicate:

```
permission_error(modify, static_predicate, Head)
```

## **Examples**

To assert a clause as the last one for any dynamic predicate in this:

```
assertz(Clause)
```

To assert a clause as the last one for any public or protected dynamic predicate in self:

```
::assertz(Clause)
```

To assert a clause as the last one for any public dynamic predicate in an object:

```
Object::assertz(Clause)
```

Copyright © Paulo Moura — Logtalk.org Last updated on: October 26, 2005

