## Radiation Physics

## A. Basics of Radiation

#### A.1. Cross section

→ The number of interactions detected can be calculated as:

$$N_{\text{detector}} = I \cdot n \cdot x \cdot \epsilon \cdot \sigma_{\text{total}},$$
 (1)

-  $I = \frac{dN_{\text{incident}}}{dt}$  is the incident particle flux (rate of incident particles). -  $n = \frac{dN_{\text{scatter}}}{dV} = \frac{NAV}{\Lambda} \rho$  is the number density of scatterers, with:

 $\rho =$  Material density,  $N_{AV} =$  Avogadro's number

A = atomic weight of the material

-  $\epsilon = \epsilon_{\text{intrinsic}} \cdot \epsilon_{\text{geo}}$  is the detection efficiency, consisting of:

$$\epsilon_{\text{geo}} = \frac{S}{d^2}$$
,

where S is the sensitive area of the detector and d is the distance between the detector and the interaction point. -  $\sigma_{\text{total}}$  is the total cross section, which can be expressed as an integral over the solid

$$\sigma_{\mathrm{total}} = \int \frac{d\sigma(\theta, E)}{d\Omega} d\Omega,$$

where  $\frac{d\sigma(\theta,E)}{d\Omega}$  represents the differential cross section as a function of angle  $\theta$  and energy E.

- → Assume an interaction: A(a, b)B
- $\rightarrow \rightarrow I_a$  = current of incident particles a; number of particles per unit
- $\rightarrow$   $N_T$  = number of target nuclei per unit area
- $\Rightarrow$   $R_b$  = number of detected particles b per unit time (reaction rate)

$$R_h \propto I_a N_T$$

Define the cross section  $\sigma$ :

$$\sigma = \frac{R_b}{I_a N_T}$$

The cross section  $\sigma$  has the dimension of area. The standard unit for cross section is the barn:

1 barn = 
$$10^{-24}$$
 cm<sup>2</sup> =  $100$  fm<sup>2</sup>

$$I = I_0 e^{-\sigma nx} = I_0 e^{-\mu x}$$
, (2)

where  $I_0$  is the initial intensity of the incident radiation, x is the thickness of the material, and  $\mu$  is the linear attenuation coefficient, defined as  $\mu = \sigma n$ .

 For a mixture or compound, the mass attenuation coefficient (μ/2) can be expressed as:

$$\left(\frac{\mu}{\rho}\right) = \sum w_i \left(\frac{\mu}{\rho}\right)_i,\tag{3}$$

## A.2. Lab coordinate and Center-Of-Mass coordinate

→ Angle Transformation:

$$\tan(\theta_{\mathsf{lab}}) = \frac{\sin(\theta_{\mathsf{cm}})}{\gamma + \cos(\theta_{\mathsf{cm}})}$$

→ Solid Angle Transformation:

$$d\Omega_{\text{lab}} = \frac{|1 + \gamma \cos(\theta_{\text{cm}})|}{(1 + \gamma^2 + 2\gamma \cos(\theta_{\text{cm}}))^{3/2}} d\Omega_{\text{cm}}$$

→ Energy Transformation:

$$E_{\rm cm} = \frac{M_a}{M_a + M_A} E_{\rm lab}$$

→ Definition of γ:

$$\gamma = \sqrt{\frac{M_a M_b}{M_A M_B} \cdot \frac{E_{cm}}{E_{cm} + Q}} \approx \frac{M_a}{M_A}$$

## B. Interaction of Photon and matter

## B.1. Photoelectric effect

→ Moseley's Law:

$$E_n = Rhc \frac{(Z - s_n)^2}{n^2}$$

where:

- → R is the Rydberg constant,
- → Z is the atomic number of the element,
- $\rightarrow \rightarrow s_n$  is the screening constant that accounts for the shielding effect of inner electrons.
- → Cross-Section Dependence:

$$_{a} au_{\mathsf{K}}=lpha^{4}\left( _{\mathsf{e}}\sigma_{\mathsf{Th}}
ight) Z^{n}\sqrt{rac{32m_{e}c^{2}}{E^{7}}},$$

 $n \approx 4$ (low energies),  $n \approx 4.6 - 4.8$ (high energies)

## → Rayleigh Scattering

- → Type: Elastic scattering, Coherent
- → Interaction Mechanism: Interaction of photons with bound electrons in an atom without energy transfer. It occurs when the incident photon's wavelength is much larger than the size of the particle.
- → → Differential Cross Section:

$$\frac{d\sigma}{d\Omega} \propto r_0^2 \left(\frac{1+\cos^2\theta}{2}\right) \cdot \left[F\left(\frac{\sin\left(\theta/2\right)}{\lambda},Z\right)\right]^2 \cdot 2\pi \sin\theta$$

where  $F\left(\frac{\sin(\theta/2)}{\lambda},Z\right)$  is the atomic form factor that depends on the scattering angle and atomic number Z. This factor accounts for the constructive interference of scattered waves, leading to coherent scattering

## → Thomson Scattering

- → Type: Elastic scattering, Coherent
- → Interaction Mechanism: Scattering of low-energy photons by free or loosely bound electrons. It occurs in the limit of low photon energy, where the electron remains non-relativistic.
- → → Differential Cross Section:

$$\frac{d\sigma}{d\Omega} = r_0^2 \left( \frac{1 + \cos^2 \theta}{2} \right)$$

This describes the scattering of electromagnetic waves off free electrons, assuming no change in photon energy.

#### → Compton Scattering

- → Type: Inelastic scattering, Incoherent
- → Interaction Mechanism: Photon-electron interaction causing an energy transfer from the photon to the electron, resulting in a lower-energy scattered photon and a recoiling electron. It is significant at higher photon energies where energy transfer cannot
- → Differential Cross Section: The differential cross-section for Compton scattering is given by the Klein-Nishina formula:

$$\frac{d\sigma}{d\Omega} = r_0^2 \cdot \frac{1 + \cos^2 \theta}{2} \cdot \left[ \frac{1}{1 + \alpha(1 - \cos \theta)} \right]^2.$$

$$\left[1 + \frac{\alpha^2(1-\cos\theta)^2}{(1+\cos^2\theta)(1+\alpha(1-\cos\theta))}\right]$$

where  $\alpha = \frac{E\gamma}{mec^2}$  is the normalized photon energy. This formula reflects the dependence of the cross-section on the scattering angle  $\theta$  and the photon's initial energy  $E_{\gamma}$ . The energy of the scattered photon  $E'_{\alpha}$  is given by:

$$E_{\gamma}' = \frac{E_{\gamma}}{1 + \frac{E_{\gamma}}{m_{e}c^{2}}(1 - \cos \theta)}$$

The Compton shift, which represents the wavelength change due to scattering, is expressed as:

$$\Delta \lambda = \lambda' - \lambda = \frac{h}{m_0 c} (1 - \cos \theta)$$

#### B.3. Pair/Triple production

- → Threshold Energy:
- For Pair Production, the photon energy must exceed the combined rest mass energy of an electron-positron pair:

$$h\nu_{\rm threshold} = 2m_e c^2 \approx 1.022 \, {\rm MeV}$$

For Triple Production, involving an additional electron, the threshold energy is:

$$h\nu_{\rm threshold} = 4m_e c^2 \approx 2.044 \, {\rm MeV}$$

ightharpoonup Cross-Section Approximation: The cross-section  $\sigma$  for pair and triple production processes is approximately proportional to the square of the atomic number Z and the logarithm of the incident photon energy  $E_{\sim}$ :

$$\sigma \approx Z^2 \ln(E_{\gamma} + C)$$

where C is a constant that depends on the material properties and interaction parameters. This logarithmic dependence indicates that the cross-section increases with increasing photon energy but at a decreasing rate

## B.4. Photon-Nuclear Interaction


- → Description: Photon-nuclear interactions occur when high-energy photons (typically above a few MeV) interact with a nucleus, causing nuclear reactions. These interactions can result in the emission of particles such as neutrons, protons, or even alpha particles. The most common photon-nuclear processes include the photo-neutron and photo-proton reactions.
- → Photonuclear Reactions: The general form of photonuclear reactions can be represented as:

$$\gamma +_Z^A X \to_Z^{A-1} X + n$$

$$\gamma +_Z^A X \rightarrow_{Z-1}^{A-1} Y + p$$

or

- → γ represents the incident high-energy photon,
- $\rightarrow$   $\stackrel{A}{\sim} X$  is the target nucleus with atomic number Z and mass number
- → n denotes the emitted neutron, and p denotes the emitted proton,
- $\rightarrow$   $\stackrel{A-1}{Z}X$  and  $\stackrel{A-1}{Z}Y$  are the resulting daughter nuclei



# C. Interaction of charged particle and matter

## C.1. Stopping Power and Collision Types → Stopping Power:

- → Collision Stopping Power: This represents the energy loss due to inelastic collisions with atomic electrons. These collisions lead to ionization and excitation of atoms within the material.
- → Radiation Stopping Power: This accounts for energy loss due to the emission of bremsstrahlung radiation, which occurs when a charged particle is decelerated by the electric field of a nucleus.

$$S = \frac{dE}{dx} = S_{rad} + S_{col}$$

- → Collision Types:
- $\rightarrow \rightarrow$  Close/Hard Collisions:  $b \approx a$
- $\rightarrow \rightarrow$  Far/Soft Collisions:  $b \gg a$
- → Radiation/Bremsstrahlung Collisions: b ≪ a

#### C.2. Stopping Power Concepts

- Bohr Classical Formula: A model describing the energy loss of charged particles due to Coulomb interactions with atomic electrons. The formula gives an approximation for the stopping power at lower

$$\begin{split} S_{\text{col}} &= 4\pi \frac{ZN_{\text{A}}}{A} \left(\frac{e^2}{4\pi\varepsilon_0}\right)^2 \frac{z^2}{m_{\text{e}}v^2} \ln \frac{b_{\text{max}}}{b_{\text{min}}} \\ S_{\text{col}} &= 2\pi \frac{ZN_{\text{A}}}{A} \left(\frac{e^2}{4\pi\varepsilon_0}\right)^2 \frac{z^2}{m_{\text{e}}v^2} \ln \frac{2mv^2}{I} \end{split}$$

→ Bethe Equation: The Bethe formula describes the stopping power of charged particles moving through matter. It is given by:


$$S_{col} = S^{hard} + S^{soft}$$

$$=4\pi\frac{ZN_{\rm A}}{A}\left(\frac{e^2}{4\pi\varepsilon_0}\right)^2\frac{z^2}{m_{\rm e}c^2\beta^2}\left\{\ln\frac{2m_{\rm e}c^2}{I}+\ln\frac{\beta^2}{1-\beta^2}-\beta^2\right\}$$

where I is the mean excitation potential.

→ Fano Correction: A correction term applied to the Bethe equation to account for deviations from the classical assumptions in the stopping power calculation, particularly for electrons and positrons.

$$4\pi \frac{N_{\mathsf{A}}}{A} \left(\frac{e^2}{4\pi\varepsilon_0}\right)^2 \frac{z^2 Z}{m_{\mathsf{e}} c^2 \beta^2} \left\{ \ln \frac{2m_{\mathsf{e}} c^2}{I} + \ln \frac{\beta^2}{1-\beta^2} - \beta^2 - \frac{\mathsf{C}}{\mathsf{Z}} - \delta \right\}$$



→ Mass Stopping Power: The stopping power normalized by the density of the absorbing material, for compounds:

$$\frac{1}{\rho} \frac{dE}{dx} = \sum_{i} w_{i} \frac{1}{\rho_{i}} \left( \frac{dE}{dx} \right)_{i}$$
$$w_{i} = (\alpha_{i} A_{i}) / \sum_{i} \alpha_{i} A_{i}$$

→ CSDA Range: The Continuous Slowing Down Approximation (CSDA) range is the total distance a charged particle travels in a material as it loses energy continuously. It is calculated by integrating the reciprocal

$$R_{\rm CSDA} = \int_0^{(E_{\rm K})_0} \frac{dE}{S_{\rm tot}(E)} = \int_{E_0}^0 \frac{dx}{dE} dE = \int_{E_0}^0 \frac{1}{(dE/dx)} dE [{\rm cm}]$$

$$R_{m\_CSDA} = \int_{E_0}^0 \frac{d\xi}{dE} dE = \int_{E_0}^0 \frac{1}{(dE/d\xi)} dE \quad \left[ \mathrm{g/cm^2} \right]$$

Substitution Rule: For two different materials with charges  $Z_1$ ,  $Z_2$ , and masses  $m_1$ ,  $m_2$ , the range can be related as:

$$\left(\frac{dE}{d\xi}\right)|_{(E_2)} = \frac{z_2^2}{z_1^2} \left(\frac{dE}{d\xi}\right)|_{(E_1)}$$

$$R_2(E_2) = \frac{m_2 Z_1^2}{m_1 Z_2^2} R_1(E_1), \quad \text{where} \quad E_1 = E_2 \frac{m_1}{m_2}$$

→ Bragg-Kleeman Rule:

$$\frac{(R_1/\rho_1)}{(R_2/\rho_2)} = \frac{\sqrt{A_1}}{\sqrt{A_2}}$$

→ Critical Energy (E<sub>c</sub>): The critical energy is the energy at which the energy loss due to radiation (bremsstrahlung) becomes equal to the energy loss due to collisions. It is given by:

$$\frac{(dE/dx)_{\text{rad}}}{(dE/dx)_{\text{col}}} \approx \frac{E_k Z}{800}$$
,  $(E_k)_{\text{critical}} = \frac{800}{Z}$ 

→ Radiation Yield (Y): The fraction of the total energy loss due to radiation as opposed to collisions. For electrons, the yield is approximated by:

$$Y = \frac{E_{\text{rad}}}{E_{\text{total}}} \approx \frac{6 \times 10^{-4} ZT}{1 + 6 \times 10^{-4} ZT}$$

where Z is the atomic number of the material and T is the kinetic energy of the particle.

## D. Neutron physics

## D.1. Energy Classifications of Neutrons

Neutrons can be classified based on their energy levels into several

- → Slow (Cold) Neutrons: Energy Range: 0 0.005 eV
- → Thermal Neutrons: Energy Range: 0.005 0.5 eV
- ⇒ Epithermal Neutrons: Energy Range: 0.5 1000 eV
- → Intermediate Neutrons: Energy Range: 1 100 keV

→ Fast Neutrons: Energy Range: 0.1 - 10 MeV

Neutrons also interact differently with target nuclei based on their mass

- → Light Nuclei: Mass Number: A < 25
- → Medium Nuclei: Mass Number: 25 < A < 80</p>
- → Heavy Nuclei: Mass Number: A > 80

## D.2. Neutron Sources

Neutrons can be sourced from various processes, including:

- Fission: Neutrons are produced during the fission of heavy nuclei.
- → Particle Accelerators: High-energy particle collisions can produce
- $\rightarrow$  ( $\alpha$ ,n) Reactions: Neutrons are emitted when alpha particles interact with certain materials
- → (γ,n) Reactions: Neutrons are produced when gamma rays interact with certain nuclei.

## D.3. Neutron Reactions

Neutrons can undergo various reactions, primarily classified into scattering and absorption:

- → Scattering:
- →→ Elastic Scattering (n, n):

$$\Delta E_{K \max} = (E_K)_i \frac{4m_n M}{(m_n + M)^2}$$

Kinetic energy of the scattered neutron

$$(E_K)_f = (E_K)_i - \Delta E_{K \text{max}} = (E_K)_i (\frac{M - m_n}{M + m_n})^2$$

For certain angle  $:\Delta E_K = (E_K)_i \frac{4m_n M}{(m_n + M)^2} \cos^2 \theta$ . The average energy transfer is given by:

$$\langle \Delta E \rangle = \frac{\Delta E_{K \text{max}}}{2}$$

The average kinetic energy attained by the scattered neutron is

$$(E_K)_f = (E_K)_i - \langle \Delta E \rangle = (E_K)_i \frac{m_n^2 + M^2}{(m_n + M)^2}$$

 $\rightarrow$  Inelastic Scattering (n, n'  $\gamma$ ): In this reaction, a neutron is scattered and energy is transferred to the nucleus, resulting in gamma radiation

#### → Absorption:

- Fission: Absorption of a neutron can lead to the fission of heavy nuclei
- $\rightarrow$  Radiative Capture  $(n,\gamma)$ : A neutron is captured by a nucleus, emitting gamma radiation.
- $\rightarrow$  Other reactions include:(n, p); (n, d); (n,  $\alpha$ ); (n, np); (n, 2n); (n, 3n): (n. f)
- $\rightarrow$  Compound nucleus formation  $a + A \rightarrow C^* \rightarrow B + b$

$$mc^2 + Mc^2 + T = M_{CN}c^2 + E_{k=4}$$

→ Partial decay lifetimes of compound nucleus states

$$\Gamma = \Gamma_{n,n} + \Gamma_{n,n/\alpha} + \Gamma_{n,\gamma} + \Gamma_{n,p} + \cdots$$

Relative probability of radiative capture is therefore  $\frac{\Gamma_{n,\gamma}}{\Gamma}$ 

- For light nuclei,  $\Gamma_{n,n} \gg \Gamma_{n,n}$
- For heavy nuclei,  $\Gamma_{n,\gamma} \gg \Gamma_{n,n}$

Neutron width increases with energy of resonance:  $\Gamma_{n,n} = \Gamma_{n,0} \sqrt{E}$ 

→ The formula for the Breit-Wigner cross section

$$\sigma_{CN} = \pi \lambda^2 (2\ell - 1) \frac{\Gamma_a \Gamma}{(E - E_R)^2 + \left(\frac{\Gamma}{2}\right)^2}$$

The decay in to entity b is expressed

$$\sigma_{ab} = \sigma_{CN} \frac{\Gamma_b}{\Gamma}$$

The energy-dependent cross-sections for compound elastic scattering is given by:

$$\sigma_{n,n} = \pi \lambda^2 \frac{\Gamma_{n,n}^2}{(E - E_R)^2 + \left(\frac{\Gamma}{2}\right)^2}$$

Cross sections for radiative capture

$$\sigma_{n,\gamma} = \pi \lambda^2 \frac{\Gamma_{n,n} \Gamma_{n,\gamma}}{(E - E_R)^2 + \left(\frac{\Gamma}{2}\right)^2}$$

# E. X-ray production

Energy Range	X-ray Type	Typical Application			
0.1 - 20 kV	Soft X-rays	Microscopy, surface analysis			
20 - 150 kV	Diagnostic X-rays	Medical imaging, diagnostic			
150 - 300 kV	Orthovoltage X-rays	Superficial cancer treatment			
300 kV - 1 MV	Intermediate Energy X-rays	Therapeutic, deeper tissue treatment			
> 1 MV	Megavoltage X-rays	s High-energy cancer treatment			

→ Bremsstrahlung Radiation Power

$$P = \frac{\mu_0 q^2 a^2}{6\pi c}$$

→ Cross-section of Bremsstrahlung

$$\frac{d\sigma}{dE} \propto \frac{Z^2}{m^2} \frac{In^2 E}{E}$$

→ Kramer's law

$$I(E_{\gamma}) = KZ(T_e - E_{\gamma})$$

→ Efficiency Estimation

$$\frac{S_{\rm rad}}{S_{\rm col}} pprox \frac{E_k Z}{820}$$
 ( $E_k$  in MeV)

$$P_{\text{deposited}} = IV, P_{\text{radiated}} = 0.9 \times 10^{-9} ZV^2 I$$
  
 $\varepsilon = 0.9 \times 10^{-9} ZV$ 

## F. Nuclear radiation and radioactive decay

## F.1. Nuclear Binding Energy and Q-value

→ Nuclear Binding Energy:

$$\frac{B}{A} = -[M(A, Z) - (A - Z)m_n - Z(m_p + m_e)]$$

$$= -(-a_1 A + a_2 A^{\frac{2}{3}} + a_3 \frac{\left(\frac{A}{2} - Z\right)^2}{A} + a_4 \frac{Z^2}{A^{\frac{1}{3}}} + a_5 \frac{\delta}{A^{\frac{3}{4}}})/A$$

$$M(A, Z) = (A - Z)m_n + Z(m_p + m_e) - B$$

→ Q-value:

$$Q = \sum_{i,before} M_i c^2 - \sum_{i,after} M_i c^2 = \sum_{i,after} B_i - \sum_{i,before} B_i$$
$$= \sum_{i,before} \Delta_i - \sum_{i,after} \Delta_i$$

- where  $\Delta [\text{MeV}] = M(A,Z)c^2 Am_{amu}c^2$ . If Q>0, it indicates an exothermic reaction (energy release).
- If Q < 0, it indicates an endothermic reaction (energy absorption).
- F.2. Decay Type
- → Alpha Decay (α decay):

$$P \rightarrow D + He$$
,  $Q = \Delta_P - \Delta_D - \Delta_{Ho}$ 

- → Beta Decay (β decay)
- $\rightarrow \rightarrow$  For  $\beta^-$  decay:

$$P \rightarrow D + e^- + \overline{\nu}, \quad Q = \Delta_P - \Delta_D$$

 $\rightarrow \rightarrow$  For  $\beta^+$  decay

$$P \rightarrow D + e^+ + \nu$$
,  $Q = \Delta_P - \Delta_D - 2m_ec^2$ 

→→ For electron capture:

$$P + e^- \rightarrow D + \nu$$
,  $Q = \Delta_B - \Delta_D - BE(e^-)$ 

→ Gamma Decay (γ decay):

$$X^m \rightarrow X + \gamma$$

F.3. Radioactivity

→ Activity:

$$A = \lambda N$$

→ Exponential Decay:

$$N(t) = N_0 e^{-\lambda t}$$

→ Mean Life

$$\tau = \frac{1}{\lambda} = \frac{T}{\ln 2}$$

→ Special Activity

$$SA = \frac{6.02 \times 10^{23} \lambda}{M} = \frac{4.17 \times 10^{23}}{MT}.$$

# F.4. Serial Radioactive Decay

- Decay Chain: A radioactive nuclide decays into another nuclide, forming a decay chain, represented as:

$$N_1 \xrightarrow{\lambda_1} N_2 \xrightarrow{\lambda_2} N_3$$

→ Equilibrium States:

 $\rightarrow \rightarrow$  Secular Equilibrium:  $T_1 \gg T_2$ .

$$A_2 = A_1(1 - e^{-\lambda_2 t}) + A_{20}e^{-\lambda_2 t}$$

 $\rightarrow$  → Transient Equilibrium:  $T_1 > T_2$ .

$$N_2 = \frac{\lambda_1 N_{10}}{\lambda_2 - \lambda_1} (e^{-\lambda_1 t} - e^{-\lambda_2 t}), A_2 = \frac{\lambda_2 A_1}{\lambda_2 - \lambda_1}$$

 $\rightarrow \rightarrow$  No Equilibrium:  $T_1 < T_2$ ,

$$N_2 = \frac{\lambda_1 N_{10}}{\lambda_1 - \lambda_2} (e^{-\lambda_2 t} - e^{-\lambda_1 t})$$

## G. Counting Statistics and Error Analysis

- G.1. General Aspects on Radiation Measurement and Data → Fundamental Data: The core data in radiation measurement are
  - counts, which serve as indicators of radiation events.
- → Types of Errors:
- → Systematic Errors (Bias): These impact accuracy due to fixed biases, e.g., calibration errors.
- → Random Errors (Precision): Variability arising from factors like electronic noise, minimized by large samples.
- → Accuracy vs Precision: Accuracy reflects closeness to the true value while precision indicates measurement repeatability.

## G.2. Statistical Methodology

- → Descriptive Statistics: Central tendency measures (mean, median, mode) and variability (variance, standard deviation).
- → Inferential Statistics: Used to draw conclusions about population parameters, employing sample data.

## G.3. Statistical Models for Counting Statistics

- → Binomial Distribution: Suitable for processes with two outcomes, defined by the probability of success p and number of trials n.
- → Poisson Distribution: Used when the event probability is low and trials are numerous, approximates binomial for rare events, e.g., radiation
- → Gaussian (Normal) Distribution: Approximates distribution with a large sample size or high event mean.

## G.4. Error Estimation and Propagation

- → Single Measurement Error: Variance for a Poisson-distributed process is  $\sigma^2 = \mu$ .
- → Multiple Measurements:

$$SE = \frac{\sigma}{\sqrt{N}}$$

→ Error Propagation Formula

$$\sigma_{u} = \sqrt{\left(\frac{\partial u}{\partial x}\sigma_{x}\right)^{2} + \left(\frac{\partial u}{\partial x}\sigma_{y}\right)^{2} + \cdots}$$

- → Chi-Square Test: Used to test the "goodness of fit" of observed data to expected distributions
- G.5. Applications of Counting Statistics
- → Limits of Detectability:
- ROC Curves: Analyzes binary decision accuracy using true positive/negative rates.
- → Minimum Detectable Amount (MDA): Defines the smallest reliably detectable signal.
- → Pulse Time Interval Statistics: Examines the intervals between pulses to interpret random decay event distributions.

	Time intervals	Counts		
Distribution Function	Erlang: $I_n(t) = \frac{(rt)^{(n-1)}e^{-rt}}{(n-1)!}$	Poisson: $P(n; rt) = \frac{(rt)^n e^{-rt}}{n!}$		
Туре	Continuous	Discrete Count number (n)		
Variable	Time (t)			
Mean	$\tau_n = \frac{n}{r}$	$\bar{n} = rt$		
Variance	$\sigma_E^2 = \frac{\tau_n^2}{n} = \frac{n}{r^2}$	$\sigma_P^2 = \bar{n} = rt$		

# H. General Properties of detector

# H.1. Detector working mode

→ Pulse Mode

 $\rightarrow \rightarrow$  Case 1: Small RC Time Constant  $(t \ll \tau_c)$ 

$$V(t) = R \times i(t)$$

Here, i(t) represents the instantaneous current at time t, and R is the resistance. This is the fast response case, capturing rapid changes in current.

 $\rightarrow$  Case 2: Large RC Time Constant  $(t \gg \tau_c)$ 

$$V_{\text{max}} = \frac{Q}{G}$$

where Q is the charge collected during the pulse and C is the capacitance. In this case, the circuit integrates the current over

## → Current Mode

The total current can be expressed as:

$$I(t) = I_0 \pm \sigma_I(t), \quad I_0 = rQ = r \frac{E}{wq_e}$$

The mean squared value of the current fluctuations is given by:

$$\overline{\sigma_I^2(t)} = \frac{1}{T} \int_{t-T}^t \left[ I(t') - I_0 \right]^2 dt' = \frac{1}{T} \int_{t-T}^t \sigma_i^2(t') dt'$$

where T is the measurement time interval. This equation represents the time-averaged variance in current fluctuations.

From Poisson statistics, the standard deviation in the number of events n over time T is:

$$\sigma_n = \sqrt{n} = \sqrt{rT}$$

where n = rT is the mean number of events in the time interval T. Thus, the fractional standard deviation in current is:

$$\frac{\overline{\sigma_I(t)}}{I_0} = \frac{\sigma_n}{n} = \frac{1}{\sqrt{rT}}$$

→ Mean Square Voltage (MSV) Mode

$$\overline{\sigma_I^2(t)} = \frac{I_0^2}{rT} = \frac{(rQ)^2}{rT} = \frac{rQ^2}{T}$$

## H.2. Key concepts on detector properties

- → Pulse height spectra
- →→ Differential PHS:

$$N = \int_{H_1}^{H_2} \frac{dN}{dH} dH$$

→→ Integral PHS:

$$N(H*) = \int_{H*}^{\infty} \frac{dN}{dH} dH$$

→ Energy resolution:

FWHM = 2.35
$$\sigma$$
,  $R = \frac{\text{FWHM}}{N} = \frac{2.35}{\sqrt{N}}$ 

→ The Fano factor. F

$$F \equiv \frac{\text{observed variance in } N}{\text{Poisson predicted variance}(=N)}$$

Statistical resolution:

$$R|_{\text{statistical limit}} = 2.35\sqrt{\frac{F}{N}}$$

→ Detector efficiency:

$$N_{obs} = N_{abs} \cdot \varepsilon_{tot} = N_{abs} \cdot W(\Theta, \Phi) \cdot \varepsilon_{geo} \cdot \varepsilon_{intrinsic} \cdot \varepsilon_{electronic}$$

- → Dead time Assume: n = true event rate, m = measured events rate, T = average period between true events (=1/n),  $\tau$  = system dead time
- → Nonparalyzable Model: fixed dead time

$$m=rac{n}{1+n au}$$
,  $n=rac{m}{1-m au}$ 

--- Paralyzable Model: extendable dead time

$$m = ne^{-n\tau}$$
,  $n = -\frac{W(-m\tau)}{\tau}$ 

Dead Time Measurement: two source method

$$n_{12} + n_b = n_1 + n_2$$


→ → Nonparalyzable Model:

$$\tau = \frac{m_1 m_2 - \sqrt{m_1 m_2 (m_{12} - m_1)(m_{12} - m_2)}}{m_1 m_2 m_{12}}$$

→→ Paralyzable Model:

$$\tau = \frac{2m_{12}}{(m_1 + m_2)^2} \ln \left( \frac{m_1 + m_2}{m_{12}} \right)$$

## I. Gas-filled Detector



- Ionization region: ionization chambers
- Proportional region: proportional counters
- Geiger-Mueller region: Geiger counters

#### I.1. Ionization Chambers

→ Average number of ion pairs:

$$\langle n_T \rangle = \frac{L \cdot \left\langle \frac{dE}{dx} \right\rangle_i}{W_i}$$

→ The drift velocity of charge in a gas

$$v = \mu \frac{\mathcal{E}}{p}$$

- → No internal gain (gain ~ 1).
- Slow drift velocity ( $\nu_e \sim 10^3 m/s$ ,  $\nu_{ion} \sim 1 m/s$ ).
- Charge collection time is too slow to count individual pulses.
- Poor timing properties.
- → Exposure: defined as the amount of ionization charge per unit mass

$$X \equiv \frac{Q}{M}$$


Convert exposure to dose  $D = X \times 33.7[Gv]$ 

## I.2. Proportional Counters

$$\mathcal{E} = \frac{V}{r \ln(b/a)}$$

a = anode wire radius, b = cathode inner radius.

→ nobel gas (such as Ar) + "quench gas" (such as CH4)



## I.3. Geiger-Mueller Tubes(G-M counters)

- → Chain avalanche leads to Geiger discharge
- Primary Geiger discharge
- Secondary Geiger discharge(UV photons)
- → A cloud of positive ions surrounds the anode, with the effect of reducing the electric field intensity, leads the Geiger discharge termination - called Quenching effect.

Detector Type	Avalanche amplification	Good timing?	Energy information	Use as monitor	
Ion chamber	none	no, ~10-2 s	none	yes	
Prop. counter	10 <sup>3</sup> - 10 <sup>5</sup>	yes, ~10-6 s	yes	no	
G-M tube	~1010	yes, ~10⁻6 s	none	yes	

## J. Semi-conductor Detector

## J.1. Advantages of semiconductor detectors

- → Semiconductor with moderate bandgap (1-2 eV)
- → Thermal energy = 1/40 eV
- → Energy to create e/h pair (signal quanta) w 3.6 eV ( c.f gas: w = 35 eV)
- → High charge carrier yield
- → Better energy resolution and large signal
- → High density and Z (comparing to gas)
- → High carrier mobility: Fast (< 30 ns )

#### J.2. Basic properties of semiconductor

Majority of charge carriers provided by donors (impurities; doping)

- n-type:majority carriers are electrons(pentavalent dopants)
- p-type:majority carriers are positive holes(trivalent dopants)
- Pentavalent dopants (electron donors); P. As. Sb. .
- [5th electron only weakly bound; easily excited into conduction band]
- Trivalent dopants (electron acceptors): Al, B, Ga, In, ...
- [One unsaturated binding: easily excepts valence electron leaving hole]
- → PN Junction: depletion depth

$$d \approx \sqrt{\frac{2\varepsilon V}{eN}} = \sqrt{2\varepsilon V \mu \rho}, \quad V_{\text{bias}} = \frac{eNd^2}{2\epsilon}, \quad \rho = \frac{1}{e(\mu_n n + \mu_p p)}$$

$$C = \frac{\epsilon A}{d} = A \sqrt{\frac{e\epsilon N}{2V}}$$

→ Noise sources: ( ENC= Equivalent Noise Charge)

Capacitance: ENC  $\propto C_d$ Leakage Current: ENC  $\propto \sqrt{I}$ 

Thermal Noise: ENC  $\propto \sqrt{K_BT/R}$ 

## J.3. Photodiode (PD)

- Cut-off wavelength vs Energy bandgap

$$\lambda_g[\mu m] = \frac{1.24}{E_{gap}[eV]}$$

→ Photon attenuation

$$I(x) = I_0 e^{-\alpha x}$$

→ Photocurrent and responsivity

$$I_{Ph} = q \left(\frac{P_0}{h\nu}\right) (1-r)(1-e^{-\alpha d}), \quad R = \frac{I_{Ph}}{P_o} = \frac{q}{h\nu} (1-r)(1-e^{-\alpha d})$$

→ Quantum Efficiency(external and internal)

$$\eta_e = \frac{I_{ph}/q}{P_0/h\nu} = (1-r)[1-e^{-\alpha d}], \eta_i = \frac{\eta_e}{(1-r)} = 1-e^{-\alpha d} \cong 1$$

- Avalanche Photodiodes: current gain and responsivity

$$M = \frac{Multiplied\ photocurrent}{Primary\ photocurrent} = \frac{I_M}{I_p}, R_{APD} = \frac{\eta q}{h v} M = R_0 M$$

→ Response Time: transit time, diffuse time and RC time constant

$$t_d = \frac{W}{v_D}$$
,  $t_{diff} = \frac{l^2}{2D_e}$ ,  $\tau = R_T C_T$ 

Туре	PMT	APD	SiPM	
Amplification	High (10 <sup>6</sup> )	Low (~10 <sup>2</sup> )	High (10 <sup>6</sup> )	
Magnetic field	Sensitive	Not sensitive	Not sensitive	
Compactness	bulky	compact	compact	
Bias (V)	HV (600~1200)	HV (300-1500)	20-70	
S/N ratio	High	Low	High	
Time resolution	~1 ns	> 1 ns (2-4 ns)	<1 ns (~200ps)	
Electronic readout	Voltage amplifier	Charge sensitive preamplifier	Voltage amplifier	

## K. Scintillation Detector

## K.1. General characteristics of scintillation detector

• High stopping power, density and Z

- Sensitivity to radiation energy Scintillation efficiency and light yield
- Fast time response Pulse shape discrimination
- Radiation hardening Usually expensive
- → Stokes Shift: emitted photons are at longer wavelengths (smaller energies) than the energy gap of the excitation. This allows the scintillation light to propagate through the material. Emitted photons can't be self-absorbed by exciting the material again
- → Light Output and Light Yield

$$L = L_0 \left( e^{-t/\tau_d} - e^{-t/\tau_r} \right), Y = \int_0^\infty L(t) dt$$

→ Scintillation Efficiency

$$\eta = \frac{Y \cdot \frac{hc}{\lambda}}{E}$$

#### K 2 Scintillators

- → Inorganic Scintillators: Intrinsic(self-activated)/Extrinsic(activated)
- → Efficiency for conversion of energy deposit to scintillation light

$$n = \beta SQ$$

where  $\beta$ - efficiency of energy conversion, S - efficiency of energy transfer, Q - quantum efficiency of luminiscent centers

- → Three mechanisms for scintillation
- Excitions (bound e-h pair)
- Defects (interstitial)
- activators (doped impurities): trace mounts of activators are purposely introduced to create some parrower levels within the forbidden band gap. E.g. NaI(TI), CsI(TI)
- → Organic Scintillators:low density; just C and H; photoelectric effect goes as  $Z^4$
- → Molecular states: Singlet states (spin=0)
- A series of levels (vibration states) Gap between  $S_0$  and  $S_1$  is 3-4
- Triplet states (spin=1)

Two scintillation processes

Fluorescence :  $S_1 \rightarrow S_0$  [ns] / Phosphorescence:  $T_0 \rightarrow S_0$  [ms]

→ Light yield and Birk's law:

$$\frac{dL}{dx} = S\frac{dE}{dx}, \frac{dL}{dx} = \frac{S\frac{dE}{dx}}{1 + kB\frac{dE}{dx}}$$

# K.3. Photomultiplier Tube (PMT)

$$G = \delta^{N} = 10^{6} - 10^{8}, \frac{dG}{G} = N \frac{dV_{d}}{V_{d}} = N \frac{dV_{d}}{V_{d}}$$

- → Causes of dark current include:
  - Thermionic emission from photocathode and dynodes

  - Leakage current between anode and other electrodes - Photocurrent by scintillation from glass or electrode supports
- Field emission current - Cosmic rays, radioactivity in glass envelope, radioactivity (gamma)
- from surroundings (cement)  $\rightarrow$  Energy Resolution:  $N_e = xp\delta$ ,  $\sigma_E^2(N_e) = \sigma_E^2(x) + \sigma_E^2(xp) + \sigma_E^2(xp\delta)$

$$\sigma_{\rm F}^2(N_{\rm e}) = \frac{1}{x} + \frac{1}{x} \frac{1-p}{p} + \frac{1}{xp} \frac{1}{(\delta-1)}$$

$$R_E = 2.35\sqrt{\frac{1}{\chi}\left(1 + \frac{1-p}{p} + \frac{1}{p(\delta-1)}\right)}$$

	Туре		Mechanism		Device Ener	Energy		Temporal	Position		
			Interaction	Signal	Proportio	Proportionality	lity Performance	Information	Information		
						Collect ions	lon Chamber	Excellent	Low ‡	Pour	Average
	See-filled		lonization charges	Multiply & Collect ions	Prop. Chamber	Very good	1	Average	Good		
	8			Create discharge	GM Counter & Spark chamber	No	1	Good to Excellent	Excellent*		
	Semi- conductor		Ionization charges	Collect ions	Silicon Diode & CZT	Excellent	1	Average	Excellent		
	Scintillator		Excitation light	Convert light into electrons	Scintillation Detector	Acceptable	1 1	Excellent	Poor*		
	Gas-filled	Current	lonization charges	Collect current	lon Chamber	Radiation Field	High	None	None		