# Calling Conventions

Radare2 uses calling conventions to help in identifying function formal arguments and return types. It is used also as a guide for basic function prototype and type propagation.

```
[0x00000000] afc?
|Usage: afc[agl?]
| afc convention
                 Manually set calling convention for current function
                 Show Calling convention for the Current function
| afc=([cctype])
                 Select or show default calling convention
                 Show register usage for the current function
| afcr[j]
                 Analyse function for finding the current calling convention
l afca
| afcf[j] [name] Prints return type function(arg1, arg2...), see afij
| afck
                 List SDB details of call loaded calling conventions
| afcl
                 List all available calling conventions
| afco path
                 Open Calling Convention sdb profile from given path
| afcR
                 Register telescoping using the calling conventions order
f0x000000001>
```

• To list all available calling conventions for current architecture using afcl command

```
[0x00000000]> afcl amd64 ms
```

cc.ms.arg3=r8
cc.ms.arg3=r9

 To display function prototype of standard library functions you have afcf command

```
[0x00000000]> afcf printf
int printf(const char *format)
[0x00000000]> afcf fgets
char *fgets(char *s, int size, FILE *stream)
All this information is loaded via sdb under /libr/anal/d/cc-[arch]-[bits].sdb
default.cc=amd64

ms=cc
cc.ms.name=ms
cc.ms.arg1=rcx
cc.ms.arg2=rdx
```

cc.ms.argn=stack
cc.ms.ret=rax

cc.x.argi=rax is used to set the ith argument of this calling convention to
register name rax

cc.x.argn=stack means that all the arguments (or the rest of them in case there was argi for any i as counting number) will be stored in stack from left to right

cc.x.argn=stack\_rev same as cc.x.argn=stack except for it means argument are passed right to left

# Code Analysis

Code analysis is a common technique used to extract information from assembly code.

Radare2 has different code analysis techniques implemented in the core and available in different commands.

As long as the whole functionalities of r2 are available with the API as well as using commands. This gives you the ability to implement your own analysis loops using any programming language, even with r2 oneliners, shellscripts, or analysis or core native plugins.

The analysis will show up the internal data structures to identify basic blocks, function trees and to extract opcode-level information.

The most common radare2 analysis command sequence is aa, which stands for "analyze all". That all is referring to all symbols and entry-points. If your binary is stripped you will need to use other commands like aaa, aab, aar, aac or so.

Take some time to understand what each command does and the results after running them to find the best one for your needs.

```
[0x08048440] > aa
[0x08048440] > pdf @ main
           ; DATA XREF from 0x08048457 (entry0)
/ (fcn) fcn.08048648 141
      ;-- main:
                                 lea ecx, [esp+0x4]
     0x08048648
                    8d4c2404
                   83e4f0
                                 and esp, 0xfffffff0
     0x0804864c
     0x0804864f
                   ff71fc
                                 push dword [ecx-0x4]
     0x08048652
                   55
                                 push ebp
      ; CODE (CALL) XREF from 0x08048734 (fcn.080486e5)
     0x08048653
                   89e5
                                 mov ebp, esp
     0x08048655
                    83ec28
                                 sub esp, 0x28
     0x08048658
                    894df4
                                 mov [ebp-0xc], ecx
     0x0804865b
                    895df8
                                 mov [ebp-0x8], ebx
                                 mov [ebp-0x4], esi
     0x0804865e
                   8975fc
                                 mov ebx, [ecx]
     0x08048661
                   8b19
     0x08048663
                   8b7104
                                 mov esi, [ecx+0x4]
     0x08048666
                    c744240c000. mov dword [esp+0xc], 0x0
```

```
0x0804866e
                    c7442408010. mov dword [esp+0x8], 0x1; 0x00000001
      0x08048676
                    c7442404000. mov dword [esp+0x4], 0x0
      0x0804867e
                    c7042400000. mov dword [esp], 0x0
      0x08048685
                    e852fdffff
                                  call sym..imp.ptrace
         sym..imp.ptrace(unk, unk)
      0x0804868a
                    85c0
                                  test eax, eax
  =< 0x0804868c
                    7911
                                  jns 0x804869f
                    c70424cf870. mov dword [esp], str.Don_tuseadebuguer_;
      0x0804868e
                                                                               0x080487cf
      0x08048695
                    e882fdffff
                                  call sym..imp.puts
         sym..imp.puts()
                                  call sym..imp.abort
      0x0804869a
                    e80dfdffff
         sym..imp.abort()
  `-> 0x0804869f
                    83fb02
                                  cmp ebx, 0x2
|,==<0x080486a2
                                  je 0x80486b5
                    7411
      0x080486a4
                    c704240c880. mov dword [esp], str.Youmustgiveapasswordforusethisprogram
\Pi
      0x080486ab
                    e86cfdffff
                                  call sym..imp.puts
11
         sym..imp.puts()
П
      0x080486b0
                    e8f7fcffff
                                  call sym..imp.abort
\Pi
         sym..imp.abort()
|`--> 0x080486b5
                    8b4604
                                  mov eax, [esi+0x4]
      0x080486b8
                    890424
                                  mov [esp], eax
      0x080486bb
                                  call fcn.080485a5
                    e8e5feffff
         fcn.080485a5(); fcn.080484c6+223
      0x080486c0
                    ъ800000000
                                  mov eax, 0x0
      0x080486c5
                    8b4df4
                                  mov ecx, [ebp-0xc]
      0x080486c8
                    8b5df8
                                  mov ebx, [ebp-0x8]
      0x080486cb
                    8b75fc
                                  mov esi, [ebp-0x4]
      0x080486ce
                    89ec
                                  mov esp, ebp
      0x080486d0
                    5d
                                  pop ebp
1
      0x080486d1
                    8d61fc
                                  lea esp, [ecx-0x4]
١
      0x080486d4
                    c3
```

In this example, we analyze the whole file (aa) and then print disassembly of the main() function (pdf). The aa command belongs to the family of auto analysis commands and performs only the most basic auto analysis steps. In radare2 there are many different types of the auto analysis commands with a different analysis depth, including partial emulation: aa, aaa, aab, aaaa, ... There is also a mapping of those commands to the r2 CLI options: r2 -A, r2 -AA, and so on.

It is a common sense that completely automated analysis can produce non sequitur results, thus radare2 provides separate commands for the particular stages of the analysis allowing fine-grained control of the analysis process. Moreover, there is a treasure trove of configuration variables for controlling the analysis outcomes. You can find them in anal.\* and emu.\* cfg variables' namespaces.

# Analyze functions

One of the most important "basic" analysis commands is the set of af subcommands. af means "analyze function". Using this command you can either allow automatic analysis of the particular function or perform completely manual one.

```
[0x00000000] > af?
Usage: af
| af ([name]) ([addr])
                                         analyze functions (start at addr or $$)
| afr ([name]) ([addr])
                                         analyze functions recursively
| af+ addr name [type] [diff]
                                         hand craft a function (requires afb+)
| af- [addr]
                                         clean all function analysis data (or function at add
| afa
                                         analyze function arguments in a call (afal honors d)
                                         add bb to function @ fcnaddr
| afb+ fcnA bbA sz [j] [f] ([t]( [d]))
                                         List basic blocks of given function
| afb[?] [addr]
                                         Toggle the basic-block 'folded' attribute
| afbF([0|1])
                                         set current function as thumb (change asm.bits)
| afB 16
                                         calculate the Cycles (afC) or Cyclomatic Complexity
| afC[lc] ([addr])@[addr]
| afc[?] type @[addr]
                                         set calling convention for function
| afd[addr]
                                         show function + delta for given offset
| afF[1|0|]
                                         fold/unfold/toggle
| afi [addr|fcn.name]
                                         show function(s) information (verbose afl)
| afj [tableaddr] [count]
                                         analyze function jumptable
| afl[?] [ls*] [fcn name]
                                         list functions (addr, size, bbs, name) (see afl1)
I afm name
                                         merge two functions
| afM name
                                         print functions map
| afn[?] name [addr]
                                         rename name for function at address (change flag to
| afna
                                         suggest automatic name for current offset
| afo[?j] [fcn.name]
                                         show address for the function name or current offset
| afs[!] ([fcnsign])
                                         get/set function signature at current address (afs!
| afS[stack_size]
                                         set stack frame size for function at current address
| afsr [function_name] [new_type]
                                         change type for given function
| aft[?]
                                         type matching, type propagation
| afu addr
                                         resize and analyze function from current address un
| afv[absrx]?
                                         manipulate args, registers and variables in function
```

list function references

You can use afl to list the functions found by the analysis.

There are a lot of useful commands under afl such as aflj, which lists the function in JSON format and aflm, which lists the functions in the syntax found in makefiles.

There's also afl=, which displays ASCII-art bars with function ranges.

You can find the rest of them under af1?.

Some of the most challenging tasks while performing a function analysis are merge, crop and resize. As with other analysis commands you have two modes: semi-

automatic and manual. For the semi-automatic, you can use afm <function name> to merge the current function with the one specified by name as an argument, aff to readjust the function after analysis changes or function edits, afu <address> to do the resize and analysis of the current function until the specified address.

Apart from those semi-automatic ways to edit/analyze the function, you can hand craft it in the manual mode with af+ command and edit basic blocks of it using afb commands. Before changing the basic blocks of the function it is recommended to check the already presented ones:

```
[0x00003ac0]> afb

0x00003ac0 0x00003b7f 01:001A 191 f 0x00003b7f

0x00003b7f 0x00003b84 00:0000 5 j 0x00003b92 f 0x00003b84

0x00003b84 0x00003b8d 00:0000 9 f 0x00003b8d

0x00003b8d 0x00003b92 00:0000 5

0x00003b92 0x00003ba8 01:0030 22 j 0x00003ba8

0x00003ba8 0x00003bf9 00:0000 81
```

#### Hand craft function

before start, let's prepare a binary file first, for example:

```
int code_block()
{
  int result = 0;
  for(int i = 0; i < 10; ++i)
    result += 1;
  return result;
}</pre>
```

then compile it with gcc -c example.c -m32 -00 -fno-pie, we will get the object file example.o. open it with radare2.

since we haven't analyzed it yet, the pdf command will not print out the disassembly here:

```
0x08000037
                     83ec10
                                    sub esp, 0x10
                                    mov dword [ebp - 8], 0
    0x0800003a
                     c745f8000000.
                                    mov dword [ebp - 4], 0
    0x08000041
                     c745fc000000.
                                    jmp 0x8000052
 =< 0x08000048
                     eb08
.--> 0x0800004a
                     8345f801
                                    add dword [ebp - 8], 1
                                    add dword [ebp - 4], 1
    0x0800004e
                     8345fc01
                                    cmp dword [ebp - 4], 9
: `-> 0x08000052
                     837dfc09
`==< 0x08000056
                     7ef2
                                    jle 0x800004a
    0x08000058
                     8b45f8
                                    mov eax, dword [ebp - 8]
    0x0800005b
                     с9
                                    leave
    0x0800005c
                     сЗ
                                    ret
```

our goal is to hand craft a function with the following structure

analyze one

create a function at 0x8000034 named code block:

```
[0x8000034] > af+ 0x8000034 code_block
```

In most cases, we use jump or call instructions as code block boundaries. so the range of first block is from 0x08000034 push ebp to 0x08000048 jmp 0x8000052. use afb+ command to add it.

[0x08000034] > afb+ code\_block 0x8000034 0x800004a-0x8000034 0x8000052

note that the basic syntax of afb+ is afb+ function\_address block\_address block\_size [jump] [fail]. the final instruction of this block points to a new address(jmp 0x8000052), thus we add the address of jump target (0x8000052) to reflect the jump info.

the next block ( $0x08000052 \sim 0x08000056$ ) is more likely an if conditional statement which has two branches. It will jump to 0x800004a if jle-less or equal, otherwise (the fail condition) jump to next instruction – 0x08000058.:

follow the control flow and create the remaining two blocks (two branches):

```
[0x08000034] > afb+ code_block 0x800004a 0x8000052-0x800004a 0x8000052 [0x08000034] > afb+ code_block 0x8000058 0x800005d-0x8000058
```

check our work:

```
[0x08000034] > afb

0x08000034 0x0800004a 00:0000 22 j 0x08000052

0x0800004a 0x08000052 00:0000 8 j 0x08000052

0x08000052 0x08000058 00:0000 6 j 0x0800004a f 0x08000058

0x08000058 0x0800005d 00:0000 5

[0x08000034] > VV

handcraft one
```

There are two very important commands for this: afc and afB. The latter is a must-know command for some platforms like ARM. It provides a way to change the "bitness" of the particular function. Basically, allowing to select between ARM and Thumb modes.

afc on the other side, allows to manually specify function calling convention. You can find more information on its usage in calling conventions.

# Recursive analysis

| axs addr [at]

There are 5 important program wide half-automated analysis commands:

- aab perform basic-block analysis ("Nucleus" algorithm)
- aac analyze function calls from one (selected or current function)
- aaf analyze all function calls
- aar analyze data references
- aad analyze pointers to pointers references

Those are only generic semi-automated reference searching algorithms. Radare2 provides a wide choice of manual references' creation of any kind. For this fine-grained control you can use ax commands.

```
Usage: ax[?d-1*]
                   # see also 'afx?'
| ax
                  list refs
                  output radare commands
| ax*
| ax addr [at]
                  add code ref pointing to addr (from curseek)
| ax- [at]
                  clean all refs/refs from addr
                  clean all refs/refs
| ax-*
axc addr [at]
                  add generic code ref
| axC addr [at]
                  add code call ref
| axg [addr]
                  show xrefs graph to reach current function
| axg* [addr]
                  show xrefs graph to given address, use .axg*;aggv
                  show xrefs graph to reach current function in json format
| axgj [addr]
 axd addr [at]
                  add data ref
| axq
                  list refs in quiet/human-readable format
                  list refs in json format
 axF [flg-glob]
                  find data/code references of flags
 axm addr [at]
                  copy data/code references pointing to addr to also point to curseek (or a
 axt [addr]
                  find data/code references to this address
 axf [addr]
                  find data/code references from this address
| axv [addr]
                  list local variables read-write-exec references
| ax. [addr]
                  find data/code references from and to this address
| axff[j] [addr]
                  find data/code references from this function
```

The most commonly used ax commands are axt and axf, especially as a part of various r2pipe scripts. Lets say we see the string in the data or a code section and want to find all places it was referenced from, we should use axt:

add string ref

```
[0x0001783a] > pd 2
;-- str.02x:
; STRING XREF from 0x00005de0 (sub.strlen d50)
; CODE XREF from 0x00017838 (str.._s_s_s + 7)
0x0001783a
               .string "%%%02x"; len=7
;-- str.src_ls.c:
; STRING XREF from 0x0000541b (sub.free_b04)
; STRING XREF from 0x0000543a (sub._assert_fail_41f + 27)
; STRING XREF from 0x00005459 (sub._assert_fail_41f + 58)
; STRING XREF from 0x00005f9e (sub._setjmp_e30)
; CODE XREF from 0x0001783f (str.02x + 5)
0x00017841 .string "src/ls.c" ; len=9
[0x0001783a] > axt
sub.strlen d50 0x5de0 [STRING] lea rcx, str.02x
(nofunc) 0x17838 [CODE] jae str.02x
```

There are also some useful commands under axt. Use axtg to generate radare2 commands which will help you to create graphs according to the XREFs.

```
[0x08048320]> s main
[0x080483e0]> axtg
agn 0x8048337 "entry0 + 23"
agn 0x80483e0 "main"
age 0x8048337 0x80483e0
```

Use axt\* to split the radare2 commands and set flags on those corresponding XREFs.

Also under ax is axg, which finds the path between two points in the file by showing an XREFs graph to reach the location or function. For example:

```
:> axg sym.imp.printf
- 0x08048a5c fcn 0x08048a5c sym.imp.printf
- 0x080483e5 fcn 0x080483e0 main
- 0x080483e0 fcn 0x080483e0 main
- 0x08048337 fcn 0x08048320 entry0
- 0x08048425 fcn 0x080483e0 main
```

Use axg\* to generate radare2 commands which will help you to create graphs using agn and age commands, according to the XREFs.

Apart from predefined algorithms to identify functions there is a way to specify a function prelude with a configuration option anal.prelude. For example, like e anal.prelude = 0x554889e5 which means

```
push rbp
mov rbp, rsp
```

on x86 64 platform. It should be specified before any analysis commands.

# Configuration

Radare2 allows to change the behavior of almost any analysis stages or commands. There are different kinds of the configuration options:

- Flow control
- Basic blocks control
- References control
- IO/Ranges
- Jump tables analysis control
- Platform/target specific options

# Control flow configuration

Two most commonly used options for changing the behavior of control flow analysis in radare2 are anal.hasnext and anal.jmp.after. The first one allows forcing radare2 to continue the analysis after the end of the function, even if the next chunk of the code wasn't called anywhere, thus analyzing all of the available functions. The latter one allows forcing radare2 to continue the analysis even after unconditional jumps.

In addition to those we can also set anal.jmp.indir to follow the indirect jumps, continuing analysis; anal.pushret to analyze push ...; ret sequence as a jump; anal.nopskip to skip the NOP sequences at a function beginning.

For now, radare 2 also allows you to change the maximum basic block size with anal.bb.maxsize option. The default value just works in most use cases, but it's useful to increase that for example when dealing with obfuscated code. Beware that some of basic blocks control options may disappear in the future in favor of more automated ways to set those.

For some unusual binaries or targets, there is an option anal.noncode. Radare2 doesn't try to analyze data sections as a code by default. But in some cases - malware, packed binaries, binaries for embedded systems, it is often a case. Thus - this option.

#### Reference control

The most crucial options that change the analysis results drastically. Sometimes some can be disabled to save the time and memory when analyzing big binaries.

- anal.jmp.ref to allow references creation for unconditional jumps
- anal.jmp.cref same, but for conditional jumps
- anal.datarefs to follow the data references in code
- anal.refstr search for strings in data references
- anal.strings search for strings and creating references

Note that strings references control is disabled by default because it increases the analysis time.

### Analysis ranges

There are a few options for this:

- anal.limits enables the range limits for analysis operations
- anal.from starting address of the limit range
- anal.to the corresponding end of the limit range
- anal.in-specify search boundaries for analysis. You can set it to io.maps, io.sections.exec, dbg.maps and many more. For example:
  - To analyze a specific memory map with anal.from and anal.to, set anal.in = dbg.maps.
  - To analyze in the boundaries set by anal.from and anal.to, set anal.in=range.
  - To analyze in the current mapped segment or section, you can put anal.in=bin.segment or anal.in=bin.section, respectively.
  - To analyze in the current memory map, specify anal.in=dbg.map.
  - To analyze in the stack or heap, you can set anal.in=dbg.stack or anal.in=dbg.heap.
  - To analyze in the current function or basic block, you can specify anal.in=anal.fcn or anal.in=anal.bb.

Please see e anal.in=?? for the complete list.

#### Jump tables

Jump tables are one of the trickiest targets in binary reverse engineering. There are hundreds of different types, the end result depending on the compiler/linker and LTO stages of optimization. Thus radare2 allows enabling some experimental jump tables detection algorithms using <code>anal.jmp.tbl</code> option. Eventually, algorithms moved into the default analysis loops once they start to work on every supported platform/target/testcase. Two more options can affect the jump tables analysis results too:

- anal.jmp.indir follow the indirect jumps, some jump tables rely on them
- anal.datarefs follow the data references, some jump tables use those

#### Platform specific controls

There are two common problems when analyzing embedded targets: ARM/Thumb detection and MIPS GP value. In case of ARM binaries radare2 supports some auto-detection of ARM/Thumb mode switches, but beware that it uses partial ESIL emulation, thus slowing the analysis process. If you will not like the results, particular functions' mode can be overridden with afB command.

The MIPS GP problem is even trickier. It is a basic knowledge that GP value can be different not only for the whole program, but also for some functions. To partially solve that there are options anal.gp and anal.gpfixed. The first

one sets the GP value for the whole program or particular function. The latter allows to "constantify" the GP value if some code is willing to change its value, always resetting it if the case. Those are heavily experimental and might be changed in the future in favor of more automated analysis.

#### Visuals

One of the easiest way to see and check the changes of the analysis commands and variables is to perform a scrolling in a Vv special visual mode, allowing functions preview:

vv

When we want to check how analysis changes affect the result in the case of big functions, we can use minimap instead, allowing to see a bigger flow graph on the same screen size. To get into the minimap mode type VV then press p twice:

vv2

This mode allows you to see the disassembly of each node separately, just navigate between them using Tab key.

# Analysis hints

l ahh 0x804840

It is not an uncommon case that analysis results are not perfect even after you tried every single configuration option. This is where the "analysis hints" radare2 mechanism comes in. It allows to override some basic opcode or meta-information properties, or even to rewrite the whole opcode string. These commands are located under ah namespace:

```
Usage: ah[lba-] Analysis Hints
l ah?
                     show this help
| ah? offset
                     show hint of given offset
| ah
                     list hints in human-readable format
                     list hints in human-readable format from current offset
lah.
 ah-
                     remove all hints
 ah- offset [size] remove hints at given offset
| ah* offset
                     list hints in radare commands format
                     force arch ppc for all addrs >= 0x42 or until the next hint
| aha ppc @ 0x42
 aha 0 @ 0x84
                     disable the effect of arch hints for all addrs >= 0x84 or until the neg
 ahb 16 @ 0x42
                     force 16bit for all addrs >= 0x42 or until the next hint
 ahb 0 @ 0x84
                     disable the effect of bits hints for all addrs >= 0x84 or until the ne
| ahc 0x804804
                     override call/jump address
| ahd foo a0,33
                     replace opcode string
| ahe 3,eax,+=
                     set vm analysis string
| ahf 0x804840
                     override fallback address for call
| ahF 0x10
                     set stackframe size at current offset
```

highlight this address offset in disasm

```
| ahi[?] 10
                     define numeric base for immediates (2, 8, 10, 10u, 16, i, p, S, s)
| ahj
                     list hints in JSON
| aho call
                     change opcode type (see aho?) (deprecated, moved to "ahd")
| ahp addr
                     set pointer hint
| ahr val
                     set hint for return value of a function
| ahs 4
                     set opcode size=4
| ahS jz
                     set asm.syntax=jz for this opcode
                     Mark immediate as a type offset (deprecated, moved to "aho")
| aht [?] <type>
                     change opcode's val field (useful to set jmptbl sizes in jmp rax)
| ahv val
```

One of the most common cases is to set a particular numeric base for immediates:

```
[0x00003d54] > ahi?
```

0x00003d59

```
Usage: ahi [2|8|10|10u|16|bodhipSs] [@ offset]
                                                  Define numeric base
| ahi <base> set numeric base (2, 8, 10, 16)
l ahi 10ld
              set base to signed decimal (10), sign bit should depend on receiver size
| ahi 10u|du set base to unsigned decimal (11)
| ahi b
              set base to binary (2)
| ahi o
              set base to octal (8)
              set base to hexadecimal (16)
| ahi h
| ahi i
              set base to IP address (32)
              set base to htons(port) (3)
| ahi p
| ahi S
              set base to syscall (80)
              set base to string (1)
| ahi s
[0x00003d54] > pd 2
0x00003d54
                0583000000
                                add eax, 0x83
                                cmp eax, 0x113
0x00003d59
                3d13010000
[0x00003d54] ahi d
[0x00003d54] > pd 2
0x00003d54
                0583000000
                                add eax, 131
0x00003d59
                3d13010000
                                cmp eax, 0x113
[0x00003d54] > ahi b
[0x00003d54] > pd 2
0x00003d54
                0583000000
                                add eax, 10000011b
```

It is notable that some analysis stages or commands add the internal analysis hints, which can be checked with ah command:

cmp eax, 0x113

```
[0x00003d54] > ah

0x00003d54 - 0x00003d54 => immbase=2

[0x00003d54] > ah*

ahi 2 @ 0x3d54
```

3d13010000

Sometimes we need to override jump or call address, for example in case of tricky relocation, which is unknown for radare2, thus we can change the value manually. The current analysis information about a particular opcode can be checked with

ao command. We can use ahc command for performing such a change: [0x00003cee] > pd 20x00003cee e83d080100 call sub.\_\_errno\_location\_530 0x00003cf3 85c0 test eax, eax [0x00003cee] ao address: 0x3cee opcode: call 0x14530 mnemonic: call prefix: 0 id: 56 bytes: e83d080100 refptr: 0 size: 5 sign: false type: call cycles: 3 esil: 83248,rip,8,rsp,-=,rsp,=[],rip,= jump: 0x00014530 direction: exec fail: 0x00003cf3 stack: null family: cpu stackop: null [0x00003cee] > ahc 0x5382[0x00003cee] > pd 20x00003cee e83d080100 call sub.\_\_errno\_location\_530 0x00003cf3 85c0 test eax, eax [0x00003cee] > ao address: 0x3cee opcode: call 0x14530 mnemonic: call prefix: 0 id: 56 bytes: e83d080100 refptr: 0 size: 5 sign: false type: call cycles: 3 esil: 83248,rip,8,rsp,-=,rsp,=[],rip,= jump: 0x00005382 direction: exec fail: 0x00003cf3

stack: null
family: cpu

```
stackop: null
[0x00003cee]> ah
    0x00003cee - 0x00003cee => jump: 0x5382
```

As you can see, despite the unchanged disassembly view the jump address in opcode was changed (jump option).

If anything of the previously described didn't help, you can simply override shown disassembly with anything you like:

### **Emulation**

One of the most important things to remember in reverse engineering is a core difference between static analysis and dynamic analysis. As many already know, static analysis suffers from the path explosion problem, which is impossible to solve even in the most basic way without at least a partial emulation.

Thus many professional reverse engineering tools use code emulation while performing an analysis of binary code, and radare2 is no difference here.

For partial emulation (or imprecise full emulation) radare uses its own ESIL intermediate language and virtual machine.

Radare2 supports this kind of partial emulation for all platforms that implement ESIL uplifting ( $x86/x86\_64$ , ARM, arm64, MIPS, powerpc, sparc, AVR, 8051, Gameboy, . . . ).

One of the most common usages of such emulation is to calculate indirect jumps and conditional jumps.

To see the ESIL representation of the program one can use the ao command or enable the asm.esil configuration variable, to check if the program uplifted correctly, and to grasp how ESIL works:

```
[0x00001660]> pdf
. (fcn) fcn.00001660 40
| fcn.00001660 ();
| ; CALL XREF from 0x00001713 (entry2.fini)
| 0x00001660 lea rdi, obj.__progname ; 0x207220
| 0x00001667 push rbp
| 0x00001668 lea rax, obj.__progname ; 0x207220
```

```
0x0000166f
                 cmp rax, rdi
      0x00001672
                 mov rbp, rsp
| .-< 0x00001675
                 je 0x1690
III
     0x00001677
                 mov rax, qword [reloc._ITM_deregisterTMCloneTable]; [0x206fd8:8]=0
     0x0000167e
                 test rax, rax
|.--< 0x00001681
                  je 0x1690
III
     0x00001683
                 pop rbp
     0x00001684
                  jmp rax
|``-> 0x00001690
                 pop rbp
      0x00001691 ret
[0x00001660] > e asm.esil=true
[0x00001660] > pdf
 (fcn) fcn.00001660 40
   fcn.00001660 ();
      ; CALL XREF from 0x00001713 (entry2.fini)
     0x00001660 \quad 0x205bb9, rip, +, rdi, =
     0x00001667
                 rbp,8,rsp,-=,rsp,=[8]
     0x00001668 0x205bb1,rip,+,rax,=
                 rdi,rax,==,$z,zf,=,$b64,cf,=,$p,pf,=,$s,sf,=,$o,of,=
     0x0000166f
     0x00001672
                 rsp,rbp,=
 .-< 0x00001675 zf,?{,5776,rip,=,}
     0x00001677
                 0x20595a,rip,+,[8],rax,=
1 1
     0x0000167e 0,rax,rax,&,==,$z,zf,=,$p,pf,=,$s,sf,=,$0,cf,=,$0,of,=
|.--< 0x00001681
                 zf,?{,5776,rip,=,}
\Pi
     0x00001683
                 rsp,[8],rbp,=,8,rsp,+=
| | |
     0x00001684
                 rax,rip,=
 `-> 0x00001690 rsp,[8],rbp,=,8,rsp,+=
      0x00001691 rsp,[8],rip,=,8,rsp,+=
```

To manually setup the ESIL imprecise emulation you need to run this command sequence:

- aei to initialize ESIL VM
- aeim to initialize ESIL VM memory (stack)
- aeip to set the initial ESIL VM IP (instruction pointer)
- a sequence of aer commands to set the initial register values.

While performing emulation, please remember, that ESIL VM cannot emulate external calls or system calls, along with SIMD instructions. Thus the most common scenario is to emulate only a small chunk of the code, like encryption/decryption, unpacking or calculating something.

After we successfully set up the ESIL VM we can interact with it like with a usual debugging mode. Commands interface for ESIL VM is almost identical to the debugging one:

- aes to step (or s key in visual mode)
- aesi to step over the function calls

- aesu <address> to step until some specified address
- aesue <ESIL expression> to step until some specified ESIL expression
  met
- aec to continue until break (Ctrl-C), this one is rarely used though, due to the omnipresence of external calls

In visual mode, all of the debugging hotkeys will work also in ESIL emulation mode.

Along with usual emulation, there is a possibility to record and replay mode:

- aets to list all current ESIL R&R sessions
- aets+ to create a new one
- aesb to step back in the current ESIL R&R session

More about this operation mode you can read in Reverse Debugging chapter.

# Emulation in analysis loop

Apart from the manual emulation mode, it can be used automatically in the analysis loop. For example, the aaaa command performs the ESIL emulation stage along with others. To disable or enable its usage you can use anal.esil configuration variable. There is one more important option, though setting it might be quite dangerous, especially in the case of malware - emu.write which allows ESIL VM to modify memory. Sometimes it is required though, especially in the process of deobfuscating or unpacking code.

To show the process of emulation you can set asm.emu variable, which will show calculated register and memory values in disassembly comments:

```
[0x00001660] e asm.emu=true
[0x00001660] > pdf
 (fcn) fcn.00001660 40
   fcn.00001660 ();
      ; CALL XREF from 0x00001713 (entry2.fini)
      0x00001660 lea rdi, obj.__progname ; 0x207220 ; rdi=0x207220 -> 0x464c457f
      0x00001667
                  push rbp
                                            ; rsp=0xffffffffffff8
      0x00001668 lea rax, obj.__progname; 0x207220; rax=0x207220 -> 0x464c457f
      0x0000166f
                  cmp rax, rdi
                                            ; zf=0x1 \rightarrow 0x2464c45 ; cf=0x0 ; pf=0x1 \rightarrow 0x2464c45
      0x00001672 mov rbp, rsp
                                           ; rbp=0xffffffffffff8
 .-< 0x00001675 je 0x1690
                                            ; rip=0x1690 -> 0x1f0fc35d ; likely
      0x00001677 mov rax, qword [reloc._ITM_deregisterTMCloneTable] ; [0x206fd8:8]=0 ; rax
1 1
      0x0000167e test rax, rax
                                            ; zf=0x1 \rightarrow 0x2464c45 ; pf=0x1 \rightarrow 0x2464c45 ; sf=0x1 \rightarrow 0x2464c45
                  je 0x1690
                                            ; rip=0x1690 -> 0x1f0fc35d ; likely
|.--< 0x00001681
      0x00001683 pop rbp
                                            ; rbp=0xffffffffffffff -> 0x4c457fff ; rsp=0x0
| | |
      0x00001684
                  jmp rax
                                            ; rip=0x0 ..
|``-> 0x00001690
                  pop rbp
                                            ; rbp=0x10102464c457f ; rsp=0x8 -> 0x464c457f
      0x00001691 ret
                                            ; rip=0x0 ; rsp=0x10 -> 0x3e0003
```

Note here likely comments, which indicates that ESIL emulation predicted for particular conditional jump to happen.

Apart from the basic ESIL VM setup, you can change the behavior with other options located in emu. and esil. configuration namespaces.

For manipulating ESIL working with memory and stack you can use the following options:

- esil.stack to enable or disable temporary stack for asm.emu mode
- esil.stack.addr to set stack address in ESIL VM (like aeim command)
- esil.stack.size to set stack size in ESIL VM (like aeim command)
- esil.stack.depth limits the number of PUSH operations into the stack
- esil.romem specifies read-only access to the ESIL memory
- esil.fillstack and esil.stack.pattern allows you to use a various pattern for filling ESIL VM stack upon initialization
- esil.nonull when set stops ESIL execution upon NULL pointer read or write.

# Graph commands

When analyzing data it is usually handy to have different ways to represent it in order to get new perspectives to allow the analyst to understand how different parts of the program interact.

Representing basic block edges, function calls, string references as graphs show a very clear view of this information.

Radare2 supports various types of graph available through commands starting with ag:

```
[0x00005000] > ag?
|Usage: ag<graphtype><format> [addr]
| Graph commands:
| aga[format]
                          Data references graph
| agA[format]
                          Global data references graph
| agc[format]
                          Function callgraph
| agC[format]
                          Global callgraph
| agd[format] [fcn addr] Diff graph
| agf[format]
                          Basic blocks function graph
| agi[format]
                          Imports graph
| agr[format]
                          References graph
| agR[format]
                          Global references graph
| agx[format]
                          Cross references graph
| agg[format]
                          Custom graph
| ag-
                          Clear the custom graph
| agn[?] title body
                          Add a node to the custom graph
| age[?] title1 title2
                          Add an edge to the custom graph
```

### Output formats:

| <blank>

*	r2 commands
d	Graphviz dot
l g	Graph Modelling Language (gml)
lj	<pre>json ('J' for formatted disassembly)</pre>
k	SDB key-value
t	Tiny ascii art
l v	Interactive ascii art
w [path]	Write to path or display graph image (see graph.gv.format and grap

The structure of the commands is as follows: ag <graph type> <output format>.

Ascii art

For example, agid displays the imports graph in dot format, while aggj outputs the custom graph in JSON format.

Here's a short description for every output format available:

### Ascii Art \*\* (e.g. agf)

Displays the graph directly to stdout using ASCII art to represent blocks and edges.

Warning: displaying large graphs directly to stdout might prove to be computationally expensive and will make r2 not responsive for some time. In case of a doubt, prefer using the interactive view (explained below).

### Interactive Ascii Art (e.g. agfv)

Displays the ASCII graph in an interactive view similar to VV which allows to move the screen, zoom in / zoom out, ...

## Tiny Ascii Art (e.g. agft)

Displays the ASCII graph directly to stdout in tiny mode (which is the same as reaching the maximum zoom out level in the interactive view).

### Graphviz dot (e.g. agfd)

Prints the dot source code representing the graph, which can be interpreted by programs such as graphviz or online viewers like this

# JSON (e.g. agfj)

Prints a JSON string representing the graph.

- In case of the f format (basic blocks of function), it will have detailed information about the function and will also contain the disassembly of the function (use J format for the formatted disassembly.
- In all other cases, it will only have basic information about the nodes of the graph (id, title, body, and edges).

### Graph Modelling Language (e.g. agfg)

Prints the GML source code representing the graph, which can be interpreted by programs such as yEd

# SDB key-value (e.g. agfk)

Prints key-value strings representing the graph that was stored by sdb (radare2's string database).

# R2 custom graph commands (e.g. agf\*)

Prints r2 commands that would recreate the desired graph. The commands to construct the graph are agn [title] [body] to add a node and age [title1] [title2] to add an edge. The [body] field can be expressed in base64 to include special formatting (such as newlines).

To easily execute the printed commands, it is possible to prepend a dot to the command (.agf\*).

### Web / image (e.g. agfw)

Radare2 will convert the graph to dot format, use the dot program to convert it to a .gif image and then try to find an already installed viewer on your system (xdg-open, open, ...) and display the graph there.

The extension of the output image can be set with the graph.extension config variable. Available extensions are png, jpg, gif, pdf, ps.

Note: for particularly large graphs, the most recommended extension is svg as it will produce images of much smaller size

If graph.web config variable is enabled, radare2 will try to display the graph using the browser (this feature is experimental and unfinished, and disabled by default.)

# Data and Code Analysis

Radare2 has a very rich set of commands and configuration options to perform data and code analysis, to extract useful information from a binary, like pointers, string references, basic blocks, opcode data, jump targets, cross references and much more. These operations are handled by the a (analyze) command family:

```
|Usage: a[abdefFghoprxstc] [...]
| aa[?]
                     analyze all (fcns + bbs) (aa0 to avoid sub renaming)
| a8 [hexpairs]
                     analyze bytes
| ab[b] [addr]
                     analyze block at given address
 abb [len]
                     analyze N basic blocks in [len] (section.size by default)
                     find paths in the bb function graph from current offset to given address
 abt [addr]
                     analyze which op could be executed in [cycles]
 ac [cycles]
| ad[?]
                     analyze data trampoline (wip)
| ad [from] [to]
                     analyze data pointers to (from-to)
| ae[?] [expr]
                     analyze opcode eval expression (see ao)
                     analyze Functions
| af[?]
                     same as above, but using anal.depth=1
 аF
| ag[?] [options]
                     draw graphs in various formats
| ah[?]
                     analysis hints (force opcode size, ...)
l ai [addr]
                     address information (show perms, stack, heap, ...)
                     show/rename/create whatever flag/function is used at addr
| an [name] [@addr]
| ao[?] [len]
                     analyze Opcodes (or emulate it)
| a0[?] [len]
                     Analyze N instructions in M bytes
                     find prelude for current offset
| ap
| ar[?]
                     like 'dr' but for the esil vm. (registers)
| as[?] [num]
                     analyze syscall using dbg.reg
| av[?] [.]
                     show vtables
| ax[?]
                     manage refs/xrefs (see also afx?)
```

In fact, a namespace is one of the biggest in radare2 tool and allows to control very different parts of the analysis:

- Code flow analysis
- Data references analysis
- Using loaded symbols
- Managing different type of graphs, like CFG and call graph
- Manage variables
- Manage types
- Emulation using ESIL VM
- Opcode introspection
- Objects information, like virtual tables

# **Symbols**

Radare2 automatically parses available imports and exports sections in the binary, moreover, it can load additional debugging information if present. Two main formats are supported: DWARF and PDB (for Windows binaries). Note that, unlike many tools radare2 doesn't rely on Windows API to parse PDB files, thus they can be loaded on any other supported platform - e.g. Linux or OS X.

DWARF debug info loads automatically by default because usually it's stored

right in the executable file. PDB is a bit of a different beast - it is always stored as a separate binary, thus the different logic of handling it.

At first, one of the common scenarios is to analyze the file from Windows distribution. In this case, all PDB files are available on the Microsoft server, which is by default is in options. See all pdb options in radare2:

```
pdb.autoload = 0
pdb.extract = 1
pdb.server = https://msdl.microsoft.com/download/symbols
pdb.useragent = Microsoft-Symbol-Server/6.11.0001.402
```

Using the variable pdb.server you can change the address where radare2 will try to download the PDB file by the GUID stored in the executable header. You can make use of multiple symbol servers by separating each URL with a semi-colon:

```
e pdb.server = https://msdl.microsoft.com/download/symbols;https://symbols.mozilla.org/
```

On Windows, you can also use local network share paths (UNC paths) as symbol servers.

Usually, there is no reason to change default pdb.useragent, but who knows where could it be handy?

Because those PDB files are stored as "cab" archives on the server, pdb.extract=1 says to automatically extract them.

Note that for the automatic downloading to work you need "cabextract" tool, and wget/curl installed.

Sometimes you don't need to do that from the radare2 itself, thus - two handy rabin2 options:

```
-P show debug/pdb information
-PP download pdb file for binary
```

where -PP automatically downloads the pdb for the selected binary, using those pdb.\* config options. -P will dump the contents of the PDB file, which is useful sometimes for a quick understanding of the symbols stored in it.

Apart from the basic scenario of just opening a file, PDB information can be additionally manipulated by the id commands:

Where idpi is basically the same as rabin2 -P. Note that idp can be also used not only in the static analysis mode, but also in the debugging mode, even if connected via WinDbg.

For simplifying the loading PDBs, especially for the processes with many linked DLLs, radare2 can autoload all required PDBs automatically - you need just set the e pdb.autoload=true option. Then if you load some file in debugging mode in Windows, using r2 -d file.exe or r2 -d 2345 (attach to pid 2345), all related PDB files will be loaded automatically.

DWARF information loading, on the other hand, is completely automated. You don't need to run any commands/change any options:

```
r2 `which rabin2`
[0x00002437 8% 300 /usr/local/bin/rabin2] > pd $r
0x00002437 jne 0x2468
0x00002439 cmp qword reloc.__cxa_finalize_224, 0
0x00002441 push rbp
0x00002442 mov rbp, rsp
0x00002445 je 0x2453
                                       ;[2]
0x00002447 lea rdi, obj.__dso_handle
                                       ; 0x207c40 ; "@| "
                                       ;[3]
0x0000244e call 0x2360
0x00002453 call sym.deregister_tm_clones;[4]
0x00002458 mov byte [obj.completed.6991], 1; obj.__TMC_END__; [0x2082f0:1]=0
0x0000245f pop rbp
0x00002460 ret
0x00002461 nop dword [rax]
0x00002468 ret
0x0000246a nop word [rax + rax]
;-- entry1.init:
;-- frame_dummy:
0x00002470 push rbp
0x00002471 mov rbp, rsp
0x00002474 pop rbp
0x00002475 jmp sym.register_tm_clones
;-- blob_version:
                                       ; ../blob/version.c:18
0x0000247a push rbp
0x0000247b mov rbp, rsp
0x0000247e sub rsp, 0x10
0x00002482 mov qword [rbp - 8], rdi
0x00002486 mov eax, 0x32
                                       ; ../blob/version.c:24 ; '2'
0x0000248b test al, al
                                       ; ../blob/version.c:19
                                       ;[6]
0x0000248d je 0x2498
0x0000248f lea rax, str.2.0.1_182_gf1aa3aa4d; 0x60b8; "2.0.1-182_gf1aa3aa4d"
0x00002496 jmp 0x249f
                                       ; [7]
0x00002498 lea rax, 0x000060cd
0x0000249f mov rsi, qword [rbp - 8]
```

```
0x000024a3 mov r8, rax
0x000024a6 mov ecx, 0x40
                                 ; section_end.ehdr
0x000024ab mov edx, 0x40c0
0x000024b7 mov eax, 0
0x000024bc call 0x2350
                                 ;[8]
                                 ; ../blob/version.c:25 ; 'f'
0x000024c1 mov eax, 0x66
0x000024c6 test al, al
                                 ;[9]
0x000024c8 je 0x24d6
0x000024ca lea rdi, str.commit:_f1aa3aa4d2599c1ad60e3ecbe5f4d8261b282385_build:_2017_11_06
0x000024d1 call sym.imp.puts
                                 ;[?]
0x000024d6 mov eax, 0
                                 ; ../blob/version.c:28
0x000024db leave
                                 ; ../blob/version.c:29
0x000024dc ret
;-- rabin_show_help:
0x000024dd push rbp
                                 ; .//rabin2.c:27
```

As you can see, it loads function names and source line information.

# **Syscalls**

Radare2 allows manual search for assembly code looking like a syscall operation. For example on ARM platform usually they are represented by the svc instruction, on the others can be a different instructions, e.g. syscall on x86 PC.

```
[0x0001ece0] > /ad/ svc
...
0x000187c2  # 2: svc 0x76
0x000189ea  # 2: svc 0xa9
0x00018a0e  # 2: svc 0x82
```

Syscalls detection is driven by asm.os, asm.bits, and asm.arch. Be sure to setup those configuration options accordingly. You can use asl command to check if syscalls' support is set up properly and as you expect. The command lists syscalls supported for your platform.

```
[0x0001ece0]> asl
...
sd_softdevice_enable = 0x80.16
sd_softdevice_disable = 0x80.17
sd_softdevice_is_enabled = 0x80.18
```

If you setup ESIL stack with aei or aeim, you can use /as command to search the addresses where particular syscalls were found and list them.

```
[0x0001ece0]> aei
[0x0001ece0]> /as
0x000187c2 sd_ble_gap_disconnect
0x000189ea sd_ble_gatts_sys_attr_set
0x00018a0e sd_ble_gap_sec_info_reply
```

To reduce searching time it is possible to restrict the searching range for only executable segments or sections with /as @e:search.in=io.maps.x

Using the ESIL emulation radare2 can print syscall arguments in the disassembly output. To enable the linear (but very rough) emulation use asm.emu configuration variable:

In case of executing aae (or aaaa which calls aae) command radare2 will push found syscalls to a special syscall. flagspace, which can be useful for automation purpose:

```
[0x000187c2] > fs
     0 * imports
     0 * symbols
2 1523 * functions
3 420 * strings
4 183 * syscalls
[0x000187c2] > f \sim syscall
0x000187c2 1 syscall.sd_ble_gap_disconnect.0
0x000189ea 1 syscall.sd ble gatts sys attr set
0x00018a0e 1 syscall.sd_ble_gap_sec_info_reply
It also can be interactively navigated through within HUD mode (V_)
0> syscall.sd_ble_gap_disconnect
 - 0x000187b2 syscall.sd_ble_gap_disconnect
   0x000187c2 syscall.sd_ble_gap_disconnect.0
   0x00018a16 syscall.sd_ble_gap_disconnect.1
   0x00018b32 syscall.sd_ble_gap_disconnect.2
   0x0002ac36 syscall.sd_ble_gap_disconnect.3
```

When debugging in radare2, you can use dcs to continue execution until the next syscall. You can also run dcs\* to trace all syscalls.

```
[0xf7fb9120] > dcs*
```

```
Running child until syscalls:-1
child stopped with signal 133
--> SN 0xf7fd3d5b syscall 45 brk (0xffffffda)
child stopped with signal 133
--> SN 0xf7fd28f3 syscall 384 arch_prctl (0xffffffda 0x3001)
child stopped with signal 133
--> SN 0xf7fc81b2 syscall 33 access (0xffffffda 0xf7fd8bf1)
child stopped with signal 133
```

radare2 also has a syscall name to syscall number utility. You can return the syscall name of a given syscall number or vice versa, without leaving the shell.

```
[0x08048436]> asl 1
exit
[0x08048436]> asl write
4
[0x08048436]> ask write
0x80,4,3,iZi
```

See as? for more information about the utility.

# **Types**

Radare2 supports the C-syntax data types description. Those types are parsed by a C11-compatible parser and stored in the internal SDB, thus are introspectable with k command.

Most of the related commands are located in t namespace:

```
[0x00000000] > t?
```

```
# cparse types commands
| Usage: t
| t
                             List all loaded types
                             List all loaded types as json
| ti
                             Show type in 'pf' syntax
| t <type>
| t*
                             List types info in r2 commands
| t- <name>
                             Delete types by its name
| t-*
                             Remove all types
                             Output the last part of files
| tail [filename]
| tc [type.name]
                             List all/given types in C output format
| te[?]
                             List all loaded enums
| td[?] <string>
                             Load types from string
                             List all loaded functions signatures
| tk <sdb-query>
                             Perform sdb query
| t1[?]
                             Show/Link type to an address
| tn[?] [-][addr]
                             manage noreturn function attributes and marks
                             Open cfg.editor to load types
| to -
| to <path>
                             Load types from C header file
```

```
| toe [type.name]
                             Open cfg.editor to edit types
                             Load types from parsed Sdb database
| tos <path>
| tp <type> [addr|varname]
                             cast data at <address> to <type> and print it (XXX: type can co
                             Show offset formatted for given type
| tpv <type> @ [value]
| tpx <type> <hexpairs>
                             Show value for type with specified byte sequence (XXX: type can
| ts[?]
                             Print loaded struct types
| tu[?]
                             Print loaded union types
| tx[f?]
                             Type xrefs
| tt[?]
                             List all loaded typedefs
```

Note that the basic (atomic) types are not those from C standard - not char, \_Bool, or short. Because those types can be different from one platform to another, radare2 uses definite types like as int8\_t or uint64\_t and will convert int to int32\_t or int64\_t depending on the binary or debuggee platform/compiler.

Basic types can be listed using t command. For the structured types you need to use ts, for unions use tu and for enums — te.

```
[0x00000000] > t
char
char *
double
float
gid_t
int
int16_t
int32_t
int64_t
int8_t
long
long long
pid_t
short
size_t
uid_t
uint16_t
uint32_t
uint64_t
uint8_t
unsigned char
unsigned int
unsigned short
void *
```

# Loading types

There are three easy ways to define a new type: \* Directly from the string using td command \* From the file using to <filename> command \* Open an \$EDITOR to type the definitions in place using to -

```
[0x00000000]> "td struct foo {char* a; int b;}"
[0x00000000]> cat ~/radare2-regressions/bins/headers/s3.h
struct S1 {
    int x[3];
    int y[4];
    int z;
};
[0x00000000]> to ~/radare2-regressions/bins/headers/s3.h
[0x00000000] > ts
foo
S1
```

Also note there is a config option to specify include directories for types parsing

```
[0x00000000]> e? dir.types
dir.types: Default path to look for cparse type files
[0x00000000] > e dir.types
/usr/include
```

#### Printing types

Notice below we have used ts command, which basically converts the C type description (or to be precise it's SDB representation) into the sequence of pf commands. See more about print format.

The tp command uses the pf string to print all the members of type at the current offset/given address:

```
[0x00000000]> "td struct foo {char* a; int b;}"
[0x00000000]> wx 68656c6c6f000c000000
[0x00000000] > wz world @ 0x00000010 ; wx 17 @ 0x00000016
xq <[00000000x0]
[0x00000000] > ts foo
pf zd a b
[0x00000000] > tp foo
 a : 0x00000000 = "hello"
b : 0x00000006 = 12
[0x00000000]> tp foo @ 0x00000010
 a : 0x00000010 = "world"
b : 0x00000016 = 23
```

Also, you could fill your own data into the struct and print it using tpx command

[0x00000000]> tpx foo 414243440010000000

```
a : 0x00000000 = "ABCD"
b : 0x00000005 = 16
```

### Linking Types

The tp command just performs a temporary cast. But if we want to link some address or variable with the chosen type, we can use tl command to store the relationship in SDB.

```
[0x000051c0]> tl S1 = 0x51cf
[0x000051c0]> tll
(S1)
    x : 0x000051cf = [ 2315619660, 1207959810, 34803085 ]
    y : 0x000051db = [ 2370306049, 4293315645, 3860201471, 4093649307 ]
    z : 0x000051eb = 4464399

Moreover, the link will be shown in the disassembly output or visual mode:
[0x000051c0 15% 300 /bin/ls]> pd $r @ entry0
```

```
;-- entry0:
0x000051c0
                xor ebp, ebp
0x000051c2
                mov r9, rdx
0x000051c5
                pop rsi
0x000051c6
                mov rdx, rsp
0x000051c9
                and rsp, 0xfffffffffffff0
0x000051cd
                push rax
0x000051ce
                push rsp
(S1)
x : 0x000051cf = [2315619660, 1207959810, 34803085]
y : 0x000051db = [2370306049, 4293315645, 3860201471, 4093649307]
z : 0x000051eb = 4464399
                lea rdi, loc._edata
0x000051f0
                                            ; 0x21f248
0x000051f7
                push rbp
0x000051f8
                lea rax, loc._edata
                                             ; 0x21f248
0x000051ff
                 cmp rax, rdi
0x00005202
                mov rbp, rsp
```

Once the struct is linked, radare2 tries to propagate structure offset in the function at current offset, to run this analysis on whole program or at any targeted functions after all structs are linked you have aat command:

```
[0x00000000] > aa? | aat [fcn] | Analyze all/given function to convert immediate to linked structure or
```

Note sometimes the emulation may not be accurate, for example as below:

```
|0x000006da push rbp
|0x000006db mov rbp, rsp
|0x000006de sub rsp, 0x10
```

```
|0x000006e2 mov edi, 0x20 ; "@"

|0x000006e7 call sym.imp.malloc ; void *malloc(size_t size)

|0x000006ec mov qword [local_8h], rax

|0x000006f0 mov rax, qword [local_8h]
```

The return value of malloc may differ between two emulations, so you have to set the hint for return value manually using ahr command, so run tl or aat command after setting up the return value hint.

#### Structure Immediates

There is one more important aspect of using types in radare2 - using aht you can change the immediate in the opcode to the structure offset. Lets see a simple example of [R]SI-relative addressing

Here 8 - is some offset in the memory, where rsi probably holds some structure pointer. Imagine that we have the following structures

```
[0x000052f0] > "td struct ms { char b[8]; int member1; int member2; };" [0x000052f0] > "td struct ms1 { uint64_t a; int member1; };" [0x000052f0] > "td struct ms2 { uint16_t a; int64_t b; int member1; };"
```

Now we need to set the proper structure member offset instead of 8 in this instruction. At first, we need to list available types matching this offset:

```
[0x000052f0]> ahts 8
ms.member1
ms1.member1
```

Note, that ms2 is not listed, because it has no members with offset 8. After listing available options we can link it to the chosen offset at the current address:

#### Managing enums

• Printing all fields in enum using te command

```
[0x00000000]> "td enum Foo {COW=1,BAR=2};"
[0x00000000]> te Foo
COW = 0x1
BAR = 0x2
```

• Finding matching enum member for given bitfield and vice-versa

```
[0x00000000]> te Foo 0x1
COW
[0x00000000]> teb Foo COW
0x1
```

# Internal representation

To see the internal representation of the types you can use tk command:

```
[0x000051c0]> tk~S1
S1=struct
struct.S1=x,y,z
struct.S1.x=int32_t,0,3
struct.S1.x.meta=4
struct.S1.y=int32_t,12,4
struct.S1.y.meta=4
struct.S1.z=int32_t,28,0
struct.S1.z.meta=0
[0x000051c0]>
```

Defining primitive types requires an understanding of basic pf formats, you can find the whole list of format specifier in pf??:

format	I	explanation
b	 	byte (unsigned)
l c	1	char (signed byte)
l d	1	0x%%08x hexadecimal value (4 bytes)
f	1	float value (4 bytes)
i	1	<pre>%%i integer value (4 bytes)</pre>
l o	1	0x%%08o octal value (4 byte)
l p	1	pointer reference (2, 4 or 8 bytes)
Ιq		quadword (8 bytes)
l s	1	32bit pointer to string (4 bytes)
l S		64bit pointer to string (8 bytes)
t		UNIX timestamp (4 bytes)
l T	1	show Ten first bytes of buffer
l u		uleb128 (variable length)
l w		word (2 bytes unsigned short in hex)
x	1	0x%%08x hex value and flag (fd @ addr)
X	1	show formatted hexpairs
l z	-	\0 terminated string
l Z	1	\O terminated wide string

there are basically 3 mandatory keys for defining basic data types: X=type type.X=format\_specifier type.X.size=size\_in\_bits For example, let's de-

fine UNIT, according to Microsoft documentation UINT is just equivalent of standard C unsigned int (or uint32\_t in terms of TCC engine). It will be defined as:

```
UINT=type
type.UINT=d
type.UINT.size=32
```

Now there is an optional entry:

```
X.type.pointto=Y
```

This one may only be used in case of pointer type.X=p, one good example is LPFILETIME definition, it is a pointer to \_FILETIME which happens to be a structure. Assuming that we are targeting only 32-bit windows machine, it will be defined as the following:

```
LPFILETIME=type
type.LPFILETIME=p
type.LPFILETIME.size=32
type.LPFILETIME.pointto=_FILETIME
```

This last field is not mandatory because sometimes the data structure internals will be proprietary, and we will not have a clean representation for it.

There is also one more optional entry:

```
type.UINT.meta=4
```

This entry is for integration with C parser and carries the type class information: integer size, signed/unsigned, etc.

#### Structures

Those are the basic keys for structs (with just two elements):

```
X=struct
struct.X=a,b
struct.X.a=a_type,a_offset,a_number_of_elements
struct.X.b=b_type,b_offset,b_number_of_elements
```

The first line is used to define a structure called  $\mathtt{X}$ , the second line defines the elements of  $\mathtt{X}$  as comma separated values. After that, we just define each element info.

For example, we can have a struct like this one:

```
struct _FILETIME {
    DWORD dwLowDateTime;
    DWORD dwHighDateTime;
}
```

assuming we have  ${\tt DWORD}$  defined, the struct will look like this

```
_FILETIME=struct
struct._FILETIME=dwLowDateTime,dwHighDateTime
struct._FILETIME.dwLowDateTime=DWORD,0,0
struct._FILETIME.dwHighDateTime=DWORD,4,0
```

Note that the number of elements field is used in case of arrays only to identify how many elements are in arrays, other than that it is zero by default.

#### Unions

Unions are defined exactly like structs the only difference is that you will replace the word struct with the word union.

# Function prototypes

Function prototypes representation is the most detail oriented and the most important one of them all. Actually, this is the one used directly for type matching

```
X=func
func.X.args=NumberOfArgs
func.x.arg0=Arg_type,arg_name
.
.
.
func.X.ret=Return_type
func.X.cc=calling_convention
```

It should be self-explanatory. Let's do strncasecmp as an example for x86 arch for Linux machines. According to man pages, strncasecmp is defined as the following:

```
int strcasecmp(const char *s1, const char *s2, size_t n);
```

When converting it into its sdb representation it will look like the following:

```
strcasecmp=func
func.strcasecmp.args=3
func.strcasecmp.arg0=char *,s1
func.strcasecmp.arg1=char *,s2
func.strcasecmp.arg2=size_t,n
func.strcasecmp.ret=int
func.strcasecmp.cc=cdecl
```

Note that the .cc part is optional and if it didn't exist the default calling-convention for your target architecture will be used instead. There is one extra optional key

```
func.x.noreturn=true/false
```

This key is used to mark functions that will not return once called, such as exit and \_exit.

# Managing variables

Radare2 allows managing local variables, no matter their location, stack or registers. The variables' auto analysis is enabled by default but can be disabled with anal.vars configuration option.

The main variables commands are located in afv namespace:

```
Usage: afv [rbs]
| afv*
                                output r2 command to add args/locals to flagspace
| afv-([name])
                                remove all or given var
| afv=
                                list function variables and arguments with disasm refs
l afva
                                analyze function arguments/locals
| afvb[?]
                                manipulate bp based arguments/locals
| afvd name
                                output r2 command for displaying the value of args/locals in
                                show BP relative stackframe variables
l afvf
| afvn [new_name] ([old_name]) rename argument/local
| afvr[?]
                                manipulate register based arguments
| afvR [varname]
                                list addresses where vars are accessed (READ)
| afvs[?]
                                manipulate sp based arguments/locals
| afvt [name] [new_type]
                                change type for given argument/local
| afvW [varname]
                                list addresses where vars are accessed (WRITE)
| afvx
                                 show function variable xrefs (same as afvR+afvW)
```

afvr, afvb and afvs commands are uniform but allow manipulation of register-based arguments and variables, BP/FP-based arguments and variables, and SP-based arguments and variables respectively. If we check the help for afvr we will get the way two others commands works too:

Like many other things variables detection is performed by radare2 automatically, but results can be changed with those arguments/variables control commands. This kind of analysis relies heavily on preloaded function prototypes and the calling-convention, thus loading symbols can improve it. Moreover, after changing something we can rerun variables analysis with afva command. Quite often variables analysis is accompanied with types analysis, see afta command.

The most important aspect of reverse engineering - naming things. Of course, you can rename variable too, affecting all places it was referenced. This can be achieved with afvn for *any* type of argument or variable. Or you can simply remove the variable or argument with afv- command.

As mentioned before the analysis loop relies heavily on types information while performing variables analysis stages. Thus comes next very important command - afvt, which allows you to change the type of variable:

```
[0x00003b92] > afvs
var int local_8h @ rsp+0x8
var int local 10h @ rsp+0x10
var int local_28h @ rsp+0x28
var int local_30h @ rsp+0x30
var int local 32h @ rsp+0x32
var int local_38h @ rsp+0x38
var int local 45h @ rsp+0x45
var int local_46h @ rsp+0x46
var int local_47h @ rsp+0x47
var int local_48h @ rsp+0x48
[0x00003b92] > afvt local 10h char*
[0x00003b92] > afvs
var int local_8h @ rsp+0x8
var char* local_10h @ rsp+0x10
var int local_28h @ rsp+0x28
var int local_30h @ rsp+0x30
var int local 32h @ rsp+0x32
var int local_38h @ rsp+0x38
var int local_45h @ rsp+0x45
var int local_46h @ rsp+0x46
var int local_47h @ rsp+0x47
var int local_48h @ rsp+0x48
```

Less commonly used feature, which is still under heavy development - distinction between variables being read and written. You can list those being read with afvR command and those being written with afvW command. Both commands provide a list of the places those operations are performed:

# Type inference

| ;-- main: | ;-- rip:

The type inference for local variables and arguments is well integrated with the command afta.

Let's see an example of this with a simple hello\_world binary

```
[0x000007aa] > pdf
           ;-- main:
/ (fcn) sym.main 157
| sym.main ();
| ; var int local_20h @ rbp-0x20
| ; var int local_1ch @ rbp-0x1c
| ; var int local_18h @ rbp-0x18
| ; var int local_10h @ rbp-0x10
| ; var int local_8h @ rbp-0x8
| ; DATA XREF from entry0 (0x6bd)
| 0x000007ab mov rbp, rsp
| 0x000007ae sub rsp, 0x20
| 0x000007b2 lea rax, str.Hello
                                         ; 0x8d4 ; "Hello"
| 0x000007b9 mov qword [local_18h], rax
                                         ; 0x8da ; " r2-folks"
| 0x000007bd lea rax, str.r2_folks
| 0x000007c4 mov qword [local_10h], rax
| 0x000007c8 mov rax, qword [local_18h]
| 0x000007cc mov rdi, rax
| 0x000007cf call sym.imp.strlen
                                         ; size_t strlen(const char *s)
  • After applying afta
[0x000007aa] > afta
[0x000007aa] > pdf
```

```
/ (fcn) sym.main 157
| sym.main ();
| ; var size_t local_20h @ rbp-0x20
| ; var size_t size @ rbp-0x1c
| ; var char *src @ rbp-0x18
| ; var char *s2 @ rbp-0x10
| ; var char *dest @ rbp-0x8
| ; DATA XREF from entry0 (0x6bd)
| 0x000007ab mov rbp, rsp
| 0x000007ae sub rsp, 0x20
| 0x000007b2 lea rax, str.Hello
                                        ; 0x8d4 ; "Hello"
| 0x000007b9 mov qword [src], rax
| 0x000007bd lea rax, str.r2 folks
                                         ; 0x8da ; " r2-folks"
| 0x000007c4 mov qword [s2], rax
| 0x000007c8 mov rax, gword [src]
| 0x000007cc mov rdi, rax
                                        ; const char *s
| 0x000007cf call sym.imp.strlen
                                        ; size_t strlen(const char *s)
```

It also extracts type information from format strings like printf ("fmt : %s , %u , %d", ...), the format specifications are extracted from anal/d/spec.sdb

You could create a new profile for specifying a set of format chars depending on different libraries/operating systems/programming languages like this:

```
win=spec
spec.win.u32=unsigned int
```

Then change your default specification to newly created one using this config variable e anal.spec = win

For more information about primitive and user-defined types support in radare2 refer to types chapter.

# Virtual Tables

There is a basic support of virtual tables parsing (RTTI and others). The most important thing before you start to perform such kind of analysis is to check if the anal.cpp.abi option is set correctly, and change if needed.

All commands to work with virtual tables are located in the av namespace. Currently, the support is very basic, allowing you only to inspect parsed tables.

| avra[j] search for vtables and try to parse RTTI at each of them

The main commands here are av and avr. av lists all virtual tables found when r2 opened the file. If you are not happy with the result you may want to try to parse virtual table at a particular address with avr command. avra performs the search and parsing of all virtual tables in the binary, like r2 does during the file opening.

# Using r2 with 8051

### **Features**

- □ Disassembler
- $\boxtimes$  Assembler
- ⊠ Emulation (esil)
- $\boxtimes$  Basic address space mapping

#### Untested

□ Debugger

### Missing

```
\square Full emulation of memory-mapped registers \square Memory banking for address spaces >64 \mathrm{K} \square Advanced analysis like local variables, function parameters .. \square More predefined CPU models
```

### r2 configuration

```
Set architecture to 8051:
```

```
r2 -a 8051
```

Set cpu to desired model:

```
e asm.cpu = ?
```

After changing the cpu model, run 'aei' to initialize/reset the registers and mapped memory. For example:

```
e asm.cpu = 8051-generic
aei
```

### Address spaces and memory mapping

Pseudo-registers are used to control how r2 emulates the multiple address spaces of the 8051. The registers hold the base address where the 8051 memory area is located in r2 address space.

register	address space	comment
_code	CODE	Program memory.
		Typically located at 0.
_idata	IDATA	256 bytes of internal
		RAM.
_sfr	SFR	128 bytes for special
		function registerssfr
		is the base address.
		Registers start at
		$\_sfr+0x80.$
_xdata	XDATA	64K of external RAM.
_pdata	PDATA, XREG	MSB of address of
		256-byte page in
		XDATA accessed with
		'movx @Ri' op codes.

The registers are initialized based on the selected CPU. See command 'e asm.cpu=?'.

The registers can be viewed and modified with the 'ar' command. When modifying the pseudo-registers or updating 'asm.cpu', memory will be (re)allocated automatically when the analyzer is invoked the next time (e.g. during 'aei'). Use the 'om' command to see the list of allocated memory blocks.

```
[0x00000000]> e asm.cpu=8051.generic

[0x00000000]> aei

[0x00000000]> om

4 fd: 6 +0x00000000 0x00000000 - 0x0000ffff -rwx

3 fd: 5 +0x00000000 0x20000000 - 0x2000ffff -rw- xdata

2 fd: 4 +0x00000000 0x10000180 - 0x100001ff -rw- sfr

1 fd: 3 +0x00000000 0x10000000 - 0x100000ff -rw- idata
```

Analysis and emulation rely on the address mapping. Setup the pseudo-registers before running analysis, or rerun analysis after updating pseudo-registers.

Address spaces can overlap in r2 memory. This allows emulating 8051 variants that mirror IDATA and SFR into XDATA, or have shared XDATA and CODE address spaces.

For example, the CC2430 from Texas Instruments maps SFR to 0xDF80 and IDATA to 0xFF00 in XDATA memory space. In r2 this can be setup with:

```
ar _sfr = _xdata + 0xdf00
ar _idata = _xdata + 0xff00
```

For overlapping areas, r2 will prioritize smaller memory blocks over larger ones. For example, if IDATA is mapped into XDATA, all r2 operations will use IDATA

in the overlapping addresses. If you want to use XDATA instead, you can delete the offending map with the command 'om-'. See 'om?' for more information.

For using emulation with overlapping code and RAM spaces, the r2 memory holding the firmware must allow write access. This is best achieved with the command 'omf 4 rwx', with 4 being the id of the firmware file's IO map entry. See 'om?' for more information.

Some 8051 variants use memory banking to address memory spaces larger than 64K. Currently, memory banking is not supported by r2.

### Tips & tricks

Use pseudo-registers in r2 commands to calculate addresses. For example:

Hex dump of all special function registers:

```
px @ _sfr
```

Write a value to a location in external RAM

```
wx deadbeef @ _xdata + 0x1234
```

Set a flag for a variable stored at 0x20 in internal RAM:

```
f sym.secret @ _idata + 0x20
```

### Adding support for new 8051 variants

Follow these steps to add support for new 8051 variants to r2.

- 1. Clone latest version of radare2
- 2. In '/libr/anal/p/anal\_8051.c' add a new entry to array 'cpu\_models[]' to define a name and a memory mapping. The name of the last entry in array must be NULL
- 3. In 'libr/asm/p/asm\_8051.c' append entry with the same name to '.cpus' attribute
- 4. Compile, test your addition, and submit a pull request

#### Architectures

This chapter covers architecture specific topics.

Even though most examples in the radare2 book are showing Intel x86 code, radare2 supports an extensive list of computer architectures. The concepts of radare2 apply to all architectures, but there are a few differences in the configuration and usage.

### **Block Size**

The block size determines how many bytes radare 2 commands will process when not given an explicit size argument. You can temporarily change the block size by specifying a numeric argument to the print commands. For example px 20.

#### [0x00000000] > b? Usage: b[f] [arg] # Get/Set block size set block size to 33 | b 33 | b eip+4 numeric argument can be an expression display current block size l b+3 increase blocksize by 3 | b-16 decrease blocksize by 16 display current block size in r2 command | b\* | bf foo set block size to flag size display block size information in JSON | bj | bm 1M set max block size

The b command is used to change the block size:

```
[0x00000000]> b 0x100  # block size = 0x100
[0x0000000]> b+16  # ... = 0x110
[0x00000000]> b-32  # ... = 0xf0
```

The bf command is used to change the block size to value specified by a flag. For example, in symbols, the block size of the flag represents the size of the function. To make that work, you have to either run function analysis af (which is included in aa) or manually seek and define some functions e.g. via Vd.

```
[0x00000000]> bf sym.main  # block size = sizeof(sym.main)
[0x00000000]> pD @ sym.main  # disassemble sym.main
```

You can combine two operations in a single pdf command. Except that pdf neither uses nor affects global block size.

```
[0x00000000] > pdf @ sym.main # disassemble sym.main
```

Another way around is to use special variables \$FB and \$FS which denote Function's Beginning and Size at the current seek. Read more about Usable variables.

```
[0x00000000]> s sym.main + 0x04

[0x00001ec9]> pD @ $FB !$FS # disassemble current function

/ 211: int main (int argc, char **argv, char **envp);

| 0x00001ec5 55 push rbp

| 0x00001ec6 4889e5 mov rbp, rsp

| 0x00001ec9 4881ecc0000000 sub rsp, 0xc0

...
```

Note: don't put space after! size designator. See also Command Format.

## Comparison Watchers

Watchers are used to record memory at 2 different points in time, then report if and how it changed.

### Basic watcher usage

First, create one with cw addr sz cmd. This will record sz bytes at addr. The command is stored and used to print the memory when shown.

```
# Create a watcher at 0x0 of size 4 using p8 as the command [0x00000000] \gt cw 0 4 p8
```

To record the second state, use cwu. Now, when you run cw, the watcher will report if the bytes changed and run the command given at creation with the size and address. When an address is an optional argument, the command will apply to all watchers if you don't pass one.

```
# Introduce a change to the block of data we're watching
[0x00000000]> wx 11223344

# Update all watchers
[0x00000000]> cwu

# Show changes
[0x00000000]> cw
0x000000000 modified
11223344
```

You may overwrite any watcher by creating another at the same address. This will discard the existing watcher completely.

### Reverting watcher state

When you create a watcher, the data read from memory is marked as "new". Updating the watcher with cwu will mark this data as "old", and then read the "new" data.

cwr will mark the current "old" state as being "new", letting you reuse it as your new base state when updating with cwu. Any existing "new" state from running cwu previously is lost in this process. Showing a watcher without updating will still run the command, but it will not report changes.

```
# Create a basic watcher
[0x00000000] > cw 0 4 p8
[0x0000000] > cw
0x0000000
00000000
# Modify the memory and update the watcher
[0x0000000]> wx 11223344
[0x0000000]> cwu
# Watcher reports modification
# The "new" state is 11223344, and the "old" state is 00000000
[0x0000000]> cw
0x00000000 modified
11223344
# Revert the watcher
[0x0000000]> cwr
# The "new" state is 00000000 again, and there is no "old" state
# The watcher reports no change since it is no longer up-to-date
[0x00000000] > cw
0x0000000
11223344
```

### Overlapping watcher areas

Watched memory areas may overlap with no ill effects, but may have unexpected results if you update some but not others.

```
# Create a watcher that watches 512 bytes starting at 0
[0x00000000]> cw 0 0x200 p8
# Create a watcher that watches 16 bytes starting at 0x100
[0x00000000]> cw 0x100 0x10 p8
# Modify memory watched by both watchers
[0x00000000]> wx 11223344 @ 0x100
# Watchers aren't updated, so they don't report a change
[0x00000000]> cw*
cw 0x00000000 512 p8
cw 0x00000100 16 p8
# Update only the watcher at 0x100
```

```
[0x00000000]> cwu 0x100
# Since only one watcher was updated, the other can't
# report the change
[0x00000000]> cw*
cw 0x00000000 512 p8
cw 0x00000100 16 p8 # differs
```

### Watching for code modification

Here is an example of using a disassembly command to watch code being modified.

```
# Write an initial binary blob for the example
[0x00000000] > wx 5053595a
# Use pD since it counts by bytes
[0x00000000] > cw 0 4 pD
# Watcher prints disassembly
[0x0000000] > cw
0x0000000
            0x00000000
                           50
                                          push rax
            0x0000001
                           53
                                          push rbx
            0x00000002
                           59
                                          pop rcx
            0x0000003
                           5a
                                          pop rdx
# Modify the code
[0x00000000]> wx 585b5152
[0x0000000] > cwu
# Watcher prints different disassembly and reports a change
[0x00000000] > cw
0x00000000 modified
            0x00000000
                           58
                                          pop rax
            0x0000001
                           5b
                                          pop rbx
            0x00000002
                           51
                                          push rcx
            0x0000003
                           52
                                          push rdx
```

### Comparing Bytes

For most generic reverse engineering tasks like finding the differences between two binary files, which bytes has changed, find differences in the graphs of the code analysis results, and other diffing operations you can just use radiff2:

#### \$ radiff2 -h

Inside r2, the functionalities exposed by radiff2 are available with the c command.

c (short for "compare") allows you to compare arrays of bytes from different sources. The command accepts input in a number of formats and then compares it against values found at current seek position.

```
[0x00404888] > c?
```

```
Usage: c[?dfx] [argument]
                             # Compare
| c [string]
                            Compare a plain with escaped chars string
| c* [string]
                            Same as above, but printing r2 commands instead
                            Compare 8 bits from current offset
| c1 [addr]
| c2 [value]
                            Compare a word from a math expression
| c4 [value]
                            Compare a doubleword from a math expression
| c8 [value]
                            Compare a quadword from a math expression
                            Show contents of file (see pwd, ls)
| cat [file]
| cc [at]
                            Compares in two hexdump columns of block size
| ccc [at]
                            Same as above, but only showing different lines
| ccd [at]
                            Compares in two disasm columns of block size
                            Compares decompiler output (e cmd.pdc=pdg|pdd)
| ccdd [at]
                            Compare contents of file at current seek
| cf [file]
| cg[?] [o] [file]
                            Graphdiff current file and [file]
                            Compare memory hexdumps of $$ and dst in unified diff
| cu[?] [addr] @at
| cud [addr] @at
                            Unified diff disasm from $$ and given address
| cv[1248] [hexpairs] @at
                            Compare 1,2,4,8-byte (silent return in $?)
| cV[1248] [addr] @at
                            Compare 1,2,4,8-byte address contents (silent, return in $?)
| cw[?] [us?] [...]
                            Compare memory watchers
                            Compare hexpair string (use '.' as nibble wildcard)
| cx [hexpair]
| cx* [hexpair]
                            Compare hexpair string (output r2 commands)
| cX [addr]
                            Like 'cc' but using hexdiff output
| cd [dir]
                            chdir
| cl|cls|clear
                            Clear screen, (clear0 to goto 0, 0 only)
To compare memory contents at current seek position against a given string of
values, use cx:
[0x08048000] > p8 4
7f 45 4c 46
[0x08048000] > cx 7f 45 90 46
Compare 3/4 equal bytes
0x00000002 (byte=03)
                       90 ' ' -> 4c 'L'
[0x08048000]>
Another subcommand of the c command is cc which stands for "compare code".
To compare a byte sequence with a sequence in memory:
[0x4A13B8C0] > cc 0x39e8e089 @ 0x4A13B8C0
To compare contents of two functions specified by their names:
[0x08049A80] > cc sym.main2 @ sym.main
c8 compares a quadword from the current seek (in the example below,
```

0x00000000) against a math expression:

[0x00000000]> c8 4

```
Compare 1/8 equal bytes (0%)
0x00000000 (byte=01) 7f '' -> 04 '''
0x00000001 (byte=02) 45 'E' -> 00 '''
0x00000002 (byte=03) 4c 'L' -> 00 '''
```

The number parameter can, of course, be math expressions which use flag names and anything allowed in an expression:

```
[0x00000000]> cx 7f469046
```

```
Compare 2/4 equal bytes
0x00000001 (byte=02) 45 'E' -> 46 'F'
0x00000002 (byte=03) 4c 'L' -> 90 ''
```

You can use the compare command to find differences between a current block and a file previously dumped to a disk:

```
r2 /bin/true
[0x08049A80]> s 0
[0x08048000]> cf /bin/true
Compare 512/512 equal bytes
```

### Dietline

Radare2 comes with the lean readline-like input capability through the lean library to handle the command edition and history navigation. It allows users to perform cursor movements, search the history, and implements autocompletion. Moreover, due to the radare2 portability, dietline provides the uniform experience among all supported platforms. It is used in all radare2 subshells - main prompt, SDB shell, visual prompt, and offsets prompt. It also implements the most common features and keybindings compatible with the GNU Readline.

Dietline supports two major configuration modes: Emacs-mode and Vi-mode.

It also supports the famous Ctrl-R reverse history search. Using TAB key it allows to scroll through the autocompletion options.

# Autocompletion

In the every shell and radare2 command autocompletion is supported. There are multiple modes of it - files, flags, and SDB keys/namespaces. To provide the easy way to select possible completion options the scrollable popup widget is available. It can be enabled with scr.prompt.popup, just set it to the true.

# Emacs (default) mode

By default dietline mode is compatible with readline Emacs-like mode key bindings. Thus active are:

### Moving

- Ctrl-a move to the beginning of the line
- Ctrl-e move to the end of the line
- Ctrl-b move one character backward
- Ctrl-f move one character forward

### **Deleting**

- Ctrl-w delete the previous word
- Ctrl-u delete the whole line
- Ctrl-h delete a character to the left
- Ctrl-d delete a character to the right
- Alt-d cuts the character after the cursor

### Killing and Yanking

- Ctrl-k kill the text from point to the end of the line.
- Ctrl-x kill backward from the cursor to the beginning of the current line
- Ctrl-t kill from point to the end of the current word, or if between words, to the end of the next word. Word boundaries are the same as forward-word.
- Ctrl-w kill the word behind point, using white space as a word boundary. The killed text is saved on the kill-ring.
- Ctrl-y yank the top of the kill ring into the buffer at point.
- Ctrl-] rotate the kill-ring, and yank the new top. You can only do this if the prior command is yank or yank-pop.

### History

• Ctrl-r - the reverse search in the command history

### Vi mode

Radare2 also comes with in vi mode that can be enabled by toggling scr.prompt.vi. The various keybindings available in this mode are:

### **Entering command modes**

• ESC - enter into the control mode

• i - enter into the insert mode

### Moving

- j acts like up arrow key
- k acts like down arrow key
- a move cursor forward and enter into insert mode
- I move to the beginning of the line and enter into insert mode
- $\bullet\,$  A move to the end of the line and enter into insert mode
- ^ move to the beginning of the line
- 0 move to the beginning of the line
- \$ move to the end of the line
- h move one character backward
- 1 move one character forward

### Deleting and Yanking

- x cuts the character
- dw delete the current word
- diw deletes the current word.
- db delete the previous word
- D delete the whole line
- dh delete a character to the left
- dl delete a character to the right
- d\$ kill the text from point to the end of the line.
- d^ kill backward from the cursor to the beginning of the current line.
- de kill from point to the end of the current word, or if between words, to the end of the next word. Word boundaries are the same as forward-word.
- p yank the top of the kill ring into the buffer at point.
- c acts similar to d based commands, but goes into insert mode in the end by prefixing the commands with numbers, the command is performed multiple times.

If you are finding it hard to keep track of which mode you are in, just set scr.prompt.mode=true to update the color of the prompt based on the vimode.

### Flags

Flags are conceptually similar to bookmarks. They associate a name with a given offset in a file. Flags can be grouped into 'flag spaces'. A flag space is a namespace for flags, grouping together flags of similar characteristics or type. Examples for flag spaces: sections, registers, symbols.

To create a flag:

[0x4A13B8C0] > f flag\_name @ offset

You can remove a flag by appending the – character to command. Most commands accept – as argument-prefix as an indication to delete something.

#### [0x4A13B8C0] > f-flag\_name

To switch between or create new flagspaces use the fs command:

```
[0x00005310] > fs?
|Usage: fs [*] [+-][flagspace|addr] # Manage flagspaces
               display flagspaces
| fs*
               display flagspaces as r2 commands
               display flagspaces in JSON
| fsj
| fs *
               select all flagspaces
| fs flagspace select flagspace or create if it doesn't exist
| fs-flagspace remove flagspace
             remove all flagspaces
| fs-*
               push previous flagspace and set
| fs+foo
               pop to the previous flagspace
l fs-
               remove the current flagspace
| fs-.
| fsq
               list flagspaces in quiet mode
| fsm [addr]
               move flags at given address to the current flagspace
               display flagspaces stack
| fss
               display flagspaces stack in r2 commands
| fss*
| fssj
               display flagspaces stack in JSON
| fsr newname
               rename selected flagspace
[0x00005310] > fs
0 439 * strings
   17 * symbols
   54 * sections
   20 * segments
4 115 * relocs
5 109 * imports
[0x00005310]>
```

Here there are some command examples:

You can rename flags with fr.

### Local flags

Every flag name should be unique for addressing reasons. But it is quite a common need to have the flags, for example inside the functions, with simple and ubiquitous names like loop or return. For this purpose you can use so called

"local" flags, which are tied to the function where they reside. It is possible to add them using  ${\tt f}$ . command:

```
[0x00003a04] > pd 10
                     0x00003a04
[0x2206d8:8]=0
                     c60522cc2100.
                                   mov byte [0x00220638], 0
                                                              ; [0x220638:1]=0
      0x00003a0f
      0x00003a16
                     83f802
                                   cmp eax, 2
                     0f84880d0000
                                   je 0x47a7
  .-< 0x00003a19
      0x00003a1f
                     83f803
                                   cmp eax, 3
 .--< 0x00003a22
                     740e
                                   je 0x3a32
1 11
      0x00003a24
                     83e801
                                   sub eax, 1
                                   je 0x431a
|.---< 0x00003a27
                     0f84ed080000
      0x00003a2d
                     e8fef8ffff
                                   call sym.imp.abort
                                                              ; void abort(void)
\Pi
      ; CODE XREF from main (0x3a22)
||\--> 0x00003a32
                     be07000000
                                   mov esi, 7
[0x00003a04] > f. localflag @ 0x3a32
[0x00003a04] > f.
                     [main + 210]
0x00003a32 localflag
[0x00003a04] > pd 10
      0x00003a04
                                   48c705c9cc21.
[0x2206d8:8]=0
                                                              ; [0x220638:1]=0
      0x00003a0f
                     c60522cc2100. mov byte [0x00220638], 0
      0x00003a16
                     83f802
                                   cmp eax, 2
  .-< 0x00003a19
                     0f84880d0000
                                   je 0x47a7
      0x00003a1f
                     83f803
                                   cmp eax, 3
                                   je 0x3a32
 .--< 0x00003a22
                     740e
                                                               ; main.localflag
     0x00003a24
                     83e801
                                   sub eax, 1
                                   je 0x431a
|.---< 0x00003a27
                     0f84ed080000
\Pi\Pi\Pi
      0x00003a2d
                     e8fef8ffff
                                   call sym.imp.abort
                                                              ; void abort(void)
      ; CODE XREF from main (0x3a22)
||`--> .localflag:
| | | | ; CODE XREF from main (0x3a22)
||`--> 0x00003a32
                     be07000000
                                   mov esi, 7
[0x00003a04] >
```

#### Flag Zones

radare2 offers flag zones, which lets you label different offsets on the scrollbar, for making it easier to navigate through large binaries. You can set a flag zone on the current seek using:

#### [0x00003a04] > fz flag-zone-name

Set scr.scrollbar=1 and go to the Visual mode, to see your flag zone appear on the scrollbar on the right end of the window.

See fz? for more information.

### **Basic Commands**

Most command names in radare are derived from action names. They should be easy to remember, as they are short. Actually, all commands are single letters. Subcommands or related commands are specified using the second character of the command name. For example, / foo is a command to search plain string, while /x 90 90 is used to look for hexadecimal pairs.

The general format for a valid command (as explained in the Command Format chapter) looks like this:

```
[.][times][cmd][~grep][@[@iter]addr!size][|>pipe]; ...
For example,
```

```
> 3s +1024 ; seeks three times 1024 from the current seek
```

If a command starts with =!, the rest of the string is passed to the currently loaded IO plugin (a debugger, for example). Most plugins provide help messages with =!? or =!help.

```
$ r2 -d /bin/ls
> =!help ; handled by the IO plugin
```

If a command starts with !, posix\_system() is called to pass the command to your shell. Check !? for more options and usage examples.

```
> !ls ; run `ls` in the shell
```

The meaning of the arguments (iter, addr, size) depends on the specific command. As a rule of thumb, most commands take a number as an argument to specify the number of bytes to work with, instead of the currently defined block size. Some commands accept math expressions or strings.

```
> px 0x17     ; show 0x17 bytes in hexs at current seek
> s base+0x33 ; seeks to flag 'base' plus 0x33
> / lib     ; search for 'lib' string.
```

The @ sign is used to specify a temporary offset location or a seek position at which the command is executed, instead of current seek position. This is quite useful as you don't have to seek around all the time.

```
> p8 10 @ 0x4010 ; show 10 bytes at offset 0x4010 > f patata @ 0x10 ; set 'patata' flag at offset 0x10
```

Using **@@** you can execute a single command on a list of flags matching the glob. You can think of this as a foreach operation:

The > operation is used to redirect the output of a command into a file (over-writing it if it already exists).

```
> pr > dump.bin ; dump 'raw' bytes of current block to file named 'dump.bin'
> f > flags.txt ; dump flag list to 'flags.txt'
```

The | operation (pipe) is similar to what you are used to expect from it in a \*NIX shell: an output of one command as input to another.

```
[0x4A13B8C0]> f | grep section | grep text
0x0805f3b0 512 section._text
0x080d24b0 512 section._text_end
```

You can pass several commands in a single line by separating them with a semicolon;:

```
> px ; dr
```

Using \_, you can print the result that was obtained by the last command.

```
[0x00001060]> axt 0x00002004
main 0x1181 [DATA] lea rdi, str.argv__2d_:_s
[0x00001060]> _
main 0x1181 [DATA] lea rdi, str.argv__2d_:_s
```

### Mapping Files

Radare's I/O subsystem allows you to map the contents of files into the same I/O space used to contain a loaded binary. New contents can be placed at random offsets.

The o command permits the user to open a file, this is mapped at offset 0 unless it has a known binary header and then the maps are created in virtual addresses.

Sometimes, we want to rebase a binary, or maybe we want to load or map the file in a different address.

When launching r2, the base address can be changed with the -B flag. But you must notice the difference when opening files with unknown headers, like bootloaders, so we need to map them using the -m flag (or specifying it as argument to the o command).

radare2 is able to open files and map portions of them at random places in memory specifying attributes like permissions and name. It is the perfect basic tooling to reproduce an environment like a core file, a debug session, by also loading and mapping all the libraries the binary depends on.

Opening files (and mapping them) is done using the  $\mathfrak o$  (open) command. Let's read the help:

```
[0x00000000]> o?
|Usage: o [com-] [file] ([offset])
```

```
1 0
                            list opened files
                            close file descriptor 1
| o-1
0-!*
                            close all opened files
                            close all files, analysis, binfiles, flags, same as !r2 --
0--
| o [file]
                            open [file] file in read-only
                            open file in read-write mode
| o+ [file]
| o [file] 0x4000 rwx
                            map file at 0x4000
| oa[-] [A] [B] [filename]
                            Specify arch and bits for given file
                            list all open files
                            list opened files in r2 commands
0*
l o. [len]
                            open a malloc://[len] copying the bytes from current offset
                            list opened files (ascii-art bars)
I 0=
| ob[?] [lbdos] [...]
                            list opened binary files backed by fd
| oc [file]
                            open core file, like relaunching r2
| of [file]
                            open file and map it at addr 0 as read-only
| oi[-|idx]
                            alias for o, but using index instead of fd
| oj[?]
                            list opened files in JSON format
| oL
                            list all IO plugins registered
| om[?]
                            create, list, remove IO maps
| on [file] 0x4000
                            map raw file at 0x4000 (no r_bin involved)
1 00[?]
                            reopen current file (kill+fork in debugger)
00+
                            reopen current file in read-write
| ood[r] [args]
                            reopen in debugger mode (with args)
                            see oo? for help
| oo[bnm] [...]
| op [fd]
                            prioritize given fd (see also ob)
| ox fd fdx
                            exchange the descs of fd and fdx and keep the mapping
Prepare a simple layout:
$ rabin2 -1 /bin/ls
[Linked libraries]
libselinux.so.1
librt.so.1
libacl.so.1
libc.so.6
4 libraries
Map a file:
[0x00001190] > o /bin/zsh 0x499999
List mapped files:
[0x00000000] > 0
- 6 /bin/ls @ 0x0 ; r
- 10 /lib/ld-linux.so.2 @ 0x100000000; r
- 14 /bin/zsh @ 0x499999 ; r
```

Print hexadecimal values from /bin/zsh:

```
[0x00000000]> px @ 0x499999
```

Unmap files using the o- command. Pass the required file descriptor to it as an argument:

```
[0x00000000] > o-14
```

You can also view the ascii table showing the list of the opened files:

```
[0x00000000] > ob=
```

### **Print Modes**

One of the key features of radare2 is displaying information in many formats. The goal is to offer a selection of display choices to interpret binary data in the best possible way.

Binary data can be represented as integers, shorts, longs, floats, timestamps, hexpair strings, or more complex formats like C structures, disassembly listings, decompilation listing, be a result of an external processing. . .

Below is a list of available print modes listed by p?:

```
[0x00005310] > p?
|Usage: p[=68abcdDfiImrstuxz] [arg|len] [@addr]
| p[b|B|xb] [len] ([S])
                          bindump N bits skipping S bytes
                          print N ops/bytes (f=func) (see pi? and pdi)
| p[iI][df] [len]
| p[kK] [len]
                          print key in randomart (K is for mosaic)
| p-[?][jh] [mode]
                          bar|json|histogram blocks (mode: e?search.in)
                          8x8 2bpp-tiles
| p2 [len]
                          print stereogram (3D)
| p3 [file]
| p6[de] [len]
                          base64 decode/encode
| p8[?][j] [len]
                          8bit hexpair list of bytes
| p=[?][bep] [N] [L] [b] show entropy/printable chars/chars bars
| pa[edD] [arg]
                          pa:assemble pa[dD]:disasm or pae: esil from hex
| pA[n_ops]
                          show n ops address and type
| pb[?] [n]
                          bitstream of N bits
| pB[?] [n]
                          bitstream of N bytes
| pc[?][p] [len]
                          output C (or python) format
| pC[aAcdDxw] [rows]
                          print disassembly in columns (see hex.cols and pdi)
| pd[?] [sz] [a] [b]
                          disassemble N opcodes (pd) or N bytes (pD)
| pf[?][.nam] [fmt]
                          print formatted data (pf.name, pf.name $<expr>)
| pF[?][apx]
                          print asn1, pkcs7 or x509
| pg[?][x y w h] [cmd]
                          create new visual gadget or print it (see pg? for details)
| ph[?][=|hash] ([len])
                          calculate hash for a block
| pj[?] [len]
                          print as indented JSON
| pm[?] [magic]
                          print libmagic data (see pm? and /m?)
```

```
| po[?] hex
                           print operation applied to block (see po?)
| pp[?][sz] [len]
                           print patterns, see pp? for more help
| pq[?][is] [len]
                           print QR code with the first Nbytes
| pr[?][glx] [len]
                           print N raw bytes (in lines or hexblocks, 'g'unzip)
| ps[?][pwz] [len]
                           print pascal/wide/zero-terminated strings
| pt[?][dn] [len]
                           print different timestamps
| pu[?][w] [len]
                           print N url encoded bytes (w=wide)
| pv[?][jh] [mode]
                           show variable/pointer/value in memory
                           display current working directory
| pwd
| px[?][owq] [len]
                           hexdump of N bytes (o=octal, w=32bit, q=64bit)
| pz[?] [len]
                           print zoom view (see pz? for help)
[0x00005310]>
Tip: when using json output, you can append the ~{} to the command to get a
pretty-printed version of the output:
[0x00000000] > oi
[{"raised":false, "fd":563280, "uri": "malloc://512", "from":0, "writable":true, "size":512, "over:
[0x00000000] > oj^{{}}
{
        "raised": false,
        "fd": 563280,
```

For more on the magical powers of  $\sim$  see the help in ?0?, and the Command Format chapter earlier in the book.

### Hexadecimal View

px gives a user-friendly output showing 16 pairs of numbers per row with offsets and raw representations:

hexprint

}

]

Show Hexadecimal Words Dump (32 bits) wordprint

#### 8 bits Hexpair List of Bytes

```
[0x00404888]> p8 16
31ed4989d15e4889e24883e4f0505449
```

"uri": "malloc://512",

"writable": true, "size": 512, "overlaps": false

"from": 0,

### Show Hexadecimal Quad-words Dump (64 bits) pxq

#### **Date/Time Formats**

Currently supported timestamp output modes are:

```
[0x00404888] > pt?
|Usage: pt [dn] print timestamps
| pt. print current time
      print UNIX time (32 bit `cfg.bigendian`) Since January 1, 1970
| ptd print DOS time (32 bit `cfg.bigendian`) Since January 1, 1980
| pth print HFS time (32 bit `cfg.bigendian`) Since January 1, 1904
| ptn print NTFS time (64 bit `cfg.bigendian`) Since January 1, 1601
For example, you can 'view' the current buffer as timestamps in the ntfs time:
[0x08048000] > e cfg.bigendian = false
[0x08048000] > pt 4
29:04:32948 23:12:36 +0000
[0x08048000] > e cfg.bigendian = true
[0x08048000] > pt 4
20:05:13001 09:29:21 +0000
As you can see, the endianness affects the result. Once you have printed a
timestamp, you can grep the output, for example, by year:
[0x08048000] > pt ~1974 | wc -1
[0x08048000] > pt ~2022
27:04:2022 16:15:43 +0000
The default date format can be configured using the cfg.datefmt variable.
Formatting rules for it follow the well known strftime(3) format. Check the
manpage for more details, but these are the most important:
%a The abbreviated name of the day of the week according to the current locale.
%A The full name of the day of the week according to the current locale.
%d The day of the month as a decimal number (range 01 to 31).
%D Equivalent to %m/%d/%y. (Yecch-for Americans only).
%H The hour as a decimal number using a 24-hour clock (range 00 to 23).
%I The hour as a decimal number using a 12-hour clock (range 01 to 12).
\mbox{\em %m} The month as a decimal number (range 01 to 12).
%M The minute as a decimal number (range 00 to 59).
%p Either "AM" or "PM" according to the given time value.
%s The number of seconds since the Epoch, 1970-01-01 00:00:00 +0000 (UTC). (TZ)
%S The second as a decimal number (range 00 to 60). (The range is up to 60 to allow for or
%T The time in 24-hour notation (%H:%M:%S). (SU)
%y The year as a decimal number without a century (range 00 to 99).
```

%Y The year as a decimal number including the century.

%z The +hhmm or -hhmm numeric timezone (that is, the hour and minute offset from UTC). (SU) %Z The timezone name or abbreviation.

#### **Basic Types**

There are print modes available for all basic types. If you are interested in a more complex structure, type pf?? for format characters and pf??? for examples:

```
[0x00499999] > pf??
|pf: pf[.k[.f[=v]]|[v]]|[n]|[0|cnt][fmt] [a0 a1 ...]
| Format:
  b
          byte (unsigned)
  В
          resolve enum bitfield (see t?)
           char (signed byte)
  С
  C
          byte in decimal
  d
          OxHEX value (4 bytes) (see 'i' and 'x')
          disassemble one opcode
  D
  e
          temporally swap endian
  Ε
          resolve enum name (see t?)
  f
          float value (4 bytes)
  F
          double value (8 bytes)
           signed integer value (4 bytes) (see 'd' and 'x')
  i
          next char specifies size of signed value (1, 2, 4 or 8 byte(s))
  n
  N
          next char specifies size of unsigned value (1, 2, 4 or 8 byte(s))
           octal value (4 byte)
  0
          pointer reference (2, 4 or 8 bytes)
  р
          quadword (8 bytes)
  q
  r
          CPU register `pf r (eax)plop`
           32bit pointer to string (4 bytes)
  s
  S
           64bit pointer to string (8 bytes)
          UNIX timestamp (4 bytes)
  t
  Τ
           show Ten first bytes of buffer
          uleb128 (variable length)
  11
  W
          word (2 bytes unsigned short in hex)
          OxHEX value and flag (fd @ addr) (see 'd' and 'i')
  x
  Х
          show formatted hexpairs
          null terminated string
  7.
          null terminated wide string
  ?
          data structure `pf ? (struct_name)example_name`
          next char is pointer (honors asm.bits)
          toggle show flags for each offset
           skip 4 bytes
           skip 1 byte
          rewind 4 bytes
          rewind 1 byte
```

Use triple-question-mark pf???? to get some examples using print format strings.

```
[0x00499999]> pf???
|pf: pf[.k[.f[=v]]|[v]]|[n]|[0|cnt][fmt] [a0 a1 ...]
| Examples:
| pf 3xi foo bar
                                                3-array of struct, each with named fields: ':
| pf B (BitFldType)arg_name`
                                                bitfield type
| pf E (EnumType)arg_name`
                                                enum type
| pf.obj xxdz prev next size name
                                                Define the obj format as xxdz
| pf obj=xxdz prev next size name
                                                Same as above
| pf *z*i*w nb name blob
                                                Print the pointers with given labels
| pf iwq foo bar troll
                                                Print the iwq format with foo, bar, troll as
| pf Oiwq foo bar troll
                                                Same as above, but considered as a union (all
| pf.plop ? (troll)mystruct
                                                Use structure troll previously defined
| pfj.plop @ 0x14
                                                Apply format object at the given offset
| pf 10xiz pointer length string
                                                Print a size 10 array of the xiz struct with
| pf 5sqw string quad word
                                                Print an array with sqw struct along with its
| pf {integer}? (bifc)
                                                Print integer times the following format (bi:
| pf [4]w[7]i
                                                Print an array of 4 words and then an array of
| pf ic...?i foo bar "(pf xw yo foo)troll" yo Print nested anonymous structures
                                                Print value located 6 bytes from current offs
| pf [10]z[3]i[10]Zb
                                                Print an fixed size str, widechar, and var
| pfj +F @ 0x14
                                                Print the content at given offset with flag
                                                print signed short (2 bytes) value. Use N ins
| pf n2
                                                Prints an array of structs
| pf [2]? (plop)structname @ 0
| pf eqew bigWord beef
                                                Swap endianness and print with given labels
| pf.foo rr (eax)reg1 (eip)reg2
                                                Create object referencing to register values
| pf tt troll plop
                                                print time stamps with labels troll and plop
Some examples are below:
[0x4A13B8C0] > pf i
0x00404888 = 837634441
```

### **High-level Languages Views**

0x00404888 = 837634432.000000

Valid print code formats for human-readable languages are:

• pc C

[0x4A13B8C0] > pf

- pc\* print 'wx' r2 commands
- pch C half-words (2 byte)
- pcw C words (4 byte)
- pcd C dwords (8 byte)
- pci C array of bytes with instructions
- pca GAS .byte blob
- pcA .bytes with instructions in comments
- pcs string

- pcS shellscript that reconstructs the bin
- pcj json
- pcJ javascript
- pco Objective-C
- pcp python
- pck kotlin
- pcr rust
- pcv JaVa
- pcV V (vlang.io)
- pcy yara
- pcz Swift

If we need to create a .c file containing a binary blob, use the pc command, that creates this output. The default size is like in many other commands: the block size, which can be changed with the b command.

We can also just temporarily override this block size by expressing it as an argument.

That estring can be used in many programming languages, not just C.

```
[0xB7F8E810] > pc 32

#define _BUFFER_SIZE 32

unsigned char buffer[_BUFFER_SIZE] = {

0x89, 0xe0, 0xe8, 0x49, 0x02, 0x00, 0x00, 0x89, 0xc7, 0xe8, 0xe2, 0xff, 0xff, 0xff, 0x81, 0xe2, 0xe2, 0xff, 0xff, 0xff, 0x81, 0xe2, 0xe2, 0xff, 0xf
```

[0x7fcd6a891630] > pcs

"\x48\x89\xe7\xe8\x68\x39\x00\x00\x49\x89\xc4\x8b\x05\xef\x16\x22\x00\x5a\x48\x8d\x24\xc4\x

#### Strings

Strings are probably one of the most important entry points when starting to reverse engineer a program because they usually reference information about functions' actions (asserts, debug or info messages...). Therefore, radare supports various string formats:

```
[0x00000000] > ps?
```

```
|Usage: ps[bijqpsuwWxz+] [N] Print String
l ps
          print string
| ps+[j]
          print libc++ std::string (same-endian, ascii, zero-terminated)
| psb
          print strings in current block
          print string inside curseek
| psi
          print string in JSON format
| psj
| psp[j]
          print pascal string
          alias for pqs
| psq
          print string in screen (wrap width)
| pss
| psu[zj] print utf16 unicode (json)
| psw[j]
          print 16bit wide string
| psW[j]
          print 32bit wide string
```

Most strings are zero-terminated. Below there is an example using the debugger to continue the execution of a program until it executes the 'open' syscall. When we recover the control over the process, we get the arguments passed to the syscall, pointed by %ebx. In the case of the 'open' call, it is a zero terminated string which we can inspect using psz.

```
[0x4A13B8C0] > dcs open
0x4a14fc24 syscall(5) open ( 0x4a151c91 0x00000000 0x00000000 ) = 0xffffffda
\lceil 0x4A13B8C0 \rceil > dr
  eax Oxfffffda
                    esi Oxfffffff
                                               0x4a14fc24
                                        eip
  ebx 0x4a151c91
                    edi 0x4a151be1
                                       oeax
                                              0x0000005
  ecx 0x00000000 esp 0xbfbedb1c
                                       eflags 0x200246
  edx 0x00000000
                    ebp 0xbfbedbb0
                                       cPaZstIdor0 (PZI)
[0x4A13B8C0]>
[0x4A13B8C0] > psz @ 0x4a151c91
/etc/ld.so.cache
```

#### **Print Memory Contents**

It is also possible to print various packed data types using the pf command:

```
[0xB7F08810]> pf xxS @ rsp
0x7fff0d29da30 = 0x00000001
0x7fff0d29da34 = 0x00000000
0x7fff0d29da38 = 0x7fff0d29da38 -> 0x0d29f7ee /bin/ls
```

This can be used to look at the arguments passed to a function. To achieve this, simply pass a 'format memory string' as an argument to pf, and temporally change the current seek position/offset using @. It is also possible to define arrays of structures with pf. To do this, prefix the format string with a numeric value. You can also define a name for each field of the structure by appending them as a space-separated arguments list.

A practical example for using pf on a binary of a GStreamer plugin:

```
$ radare2 /usr/lib/gstreamer-1.0/libgstflv.so
[0x00006020] > aa; pdf @ sym.gst_plugin_flv_get_desc
[x] Analyze all flags starting with sym. and entry0 (aa)
sym.gst_plugin_flv_get_desc ();
[\ldots]
      0x00013830
                      488d0549db0000 lea rax, section..data.rel.ro; 0x21380
      0x00013837
                                      ret
[0x00006020] > s section..data.rel.ro
[0x00021380] > pf ii*z*zp*z*z*z*z major minor name desc init version license source packa
            major : 0x00021380 = 1
            minor: 0x00021384 = 18
             name : (*0x19cf2)0x00021388 = "flv"
             desc: (*0x1b358)0x00021390 = "FLV muxing and demuxing plugin"
             init : 0x00021398 = (gword)0x000000000013460
          version : (*0x19cae)0x000213a0 = "1.18.2"
          license : (*0x19ce1)0x000213a8 = "LGPL"
           source : (*0x19cd0)0x000213b0 = "gst-plugins-good"
          package : (*0x1b378)0x000213b8 = "GStreamer Good Plugins (Arch Linux)"
           origin : (*0x19cb5)0x000213c0 = "https://www.archlinux.org/"
 release_datetime : (*0x19cf6)0x000213c8 = "2020-12-06"
```

#### Disassembly

The pd command is used to disassemble code. It accepts a numeric value to specify how many instructions should be disassembled. The pD command is similar but instead of a number of instructions, it decompiles a given number of bytes.

- d : disassembly N opcodes count of opcodes
- $\bullet\,$  D : asm.arch disassembler b size bytes

```
[0x00404888]> pd 1
;-- entry0:
0x00404888 31ed xor ebp, ebp
```

#### Selecting Target Architecture

The architecture flavor for the disassembler is defined by the asm.arch eval variable. You can use e asm.arch=?? to list all available architectures.

```
[0x00005310] > e asm.arch=??
                6502
                                     6502/NES/C64/Tamagotchi/T-1000 CPU
_dAe _8_16
                            LGPL3
_dAe _8
                8051
                            PD
                                     8051 Intel CPU
_dA_ _16_32
                             GPL3
                                     Argonaut RISC Core
                arc
a___ _16_32_64 arm.as
                            LGPL3
                                     as ARM Assembler (use ARM_AS environment)
adAe _16_32_64 arm
                             BSD
                                     Capstone ARM disassembler
                             GPL3
                                     Acorn RISC Machine CPU
_dA_ _16_32_64 arm.gnu
_d__ _16_32
                arm.winedbg LGPL2
                                     WineDBG's ARM disassembler
```

adAe	_8_16	avr	GPL	AVR Atmel
adAe	_16_32_64	bf	LGPL3	Brainfuck
_dA_	_32	chip8	LGPL3	Chip8 disassembler
_dA_	_16	cr16	LGPL3	cr16 disassembly plugin
_dA_	_32	cris	GPL3	Axis Communications 32-bit embedded processor
adA_	_32_64	dalvik	LGPL3	AndroidVM Dalvik
ad	_16	dcpu16	PD	Mojang's DCPU-16
_dA_	_32_64	ebc	LGPL3	EFI Bytecode
adAe	_16	gb	LGPL3	<pre>GameBoy(TM) (z80-like)</pre>
_dAe	_16	h8300	LGPL3	H8/300 disassembly plugin
_dAe	_32	hexagon	LGPL3	Qualcomm Hexagon (QDSP6) V6
_d	_32	hppa	GPL3	HP PA-RISC
_dAe	_0	i4004	LGPL3	Intel 4004 microprocessor
_dA_	_8	i8080	BSD	Intel 8080 CPU
adA_	_32	java	Apache	Java bytecode
_d	_32	lanai	GPL3	LANAI

#### Configuring the Disassembler

There are multiple options which can be used to configure the output of the disassembler. All these options are described in e? asm.

```
[Ox00005310] > e? asm.
asm.anal: Analyze code and refs while disassembling (see anal.strings)
asm.arch: Set the arch to be used by asm
asm.assembler: Set the plugin name to use when assembling
asm.bbline: Show empty line after every basic block
asm.bits: Word size in bits at assembler
asm.bytes: Display the bytes of each instruction
asm.bytespace: Separate hexadecimal bytes with a whitespace
asm.calls: Show callee function related info as comments in disasm
asm.capitalize: Use camelcase at disassembly
asm.cmt.col: Column to align comments
asm.cmt.flgrefs: Show comment flags associated to branch reference
asm.cmt.fold: Fold comments, toggle with Vz
...
```

Currently there are 136 asm. configuration variables so we do not list them all.

#### Disassembly Syntax

The asm.syntax variable is used to change the flavor of the assembly syntax used by a disassembler engine. To switch between Intel and AT&T representations:

```
e asm.syntax = intel
e asm.syntax = att
```

You can also check asm.pseudo, which is an experimental pseudocode view, and asm.esil which outputs ESIL ('Evaluable Strings Intermediate Language'). ESIL's goal is to have a human-readable representation of every opcode semantics. Such representations can be evaluated (interpreted) to emulate effects of individual instructions.

### SDB

SDB stands for String DataBase. It's a simple key-value database that only operates with strings created by pancake. It is used in many parts of r2 to have a disk and in-memory database which is small and fast to manage using it as a hashtable on steroids.

SDB is a simple string key/value database based on djb's cdb disk storage and supports JSON and arrays introspection.

There's also the sdbtypes: a vala library that implements several data structures on top of an sdb or a memcache instance.

#### SDB supports:

- namespaces (multiple sdb paths)
- atomic database sync (never corrupted)
- bindings for vala, luvit, newlisp and nodejs
- commandline frontend for sdb databases
- memcache client and server with sdb backend
- arrays support (syntax sugar)
- json parser/getter

### Usage example

Let's play with json:

```
Let's create a database!

$ sdb d hello=world
$ sdb d hello
world

Using arrays:

$ sdb - '[]list=1,2' '[0]list' '[0]list=foo' '[]list' '[+1]list=bar'

foo
2
foo
bar
2
```

```
$ sdb d g='{"foo":1,"bar":{"cow":3}}'
$ sdb d g?bar.cow
$ sdb - user='{"id":123}' user?id=99 user?id
Using the command line without any disk database:
$ sdb - foo=bar foo a=3 +a -a
4
3
$ sdb -
foo=bar
foo
bar
a=3
+a
-a
3
Remove the database
$ rm -f d
So what?
So, you can now do this inside your radare2 sessions!
Let's take a simple binary, and check what is already sdbized.
$ cat test.c
int main(){
    puts("Hello world\n");
$ gcc test.c -o test
$ r2 -A ./test
[0x08048320] > k **
bin
anal
syscall
debug
[0x08048320] > k bin/**
```

[0x08048320] > k bin/fd.6/\*

archs=0:0:x86:32

The file corresponding to the sixth file descriptor is a x86\_32 binary.

```
[0x08048320]> k anal/meta/*
meta.s.0x80484d0=12,SGVsbG8gd29ybGQ=
[...]
[0x08048320]> ?b64- SGVsbG8gd29ybGQ=
Hello world
```

Strings are stored encoded in base64.

## More Examples

List namespaces

k \*\*

List sub-namespaces

k anal/\*\*

List keys

k \*

k anal/\*

Set a key

k foo=bar

Get the value of a key

k foo

List all syscalls

k syscall/\*~^0x

List all comments

 $k = \frac{meta}{*}.C.$ 

Show a comment at given offset:

k %anal/meta/[1]meta.C.0x100005000

### Sections

The concept of sections is tied to the information extracted from the binary. We can display this information by using the i command.

Displaying information about sections:

```
[0x00005310] > iS
[Sections]
                                   0 ----
00 0x0000000
                 0 0x0000000
                                  28 -r-- .interp
01 0x00000238
                 28 0x00000238
02 0x00000254
                32 0x00000254
                                 32 -r-- .note.ABI_tag
03 0x00000278
               176 0x00000278
                                 176 -r-- .gnu.hash
04 0x00000328 3000 0x00000328 3000 -r-- .dynsym
05 0x00000ee0
                               1412 -r-- .dynstr
              1412 0x00000ee0
06 0x00001464
               250 0x00001464
                                250 -r-- .gnu.version
07 0x00001560
              112 0x00001560
                                112 -r-- .gnu.version_r
08 0x000015d0 4944 0x000015d0 4944 -r-- .rela.dyn
09 0x00002920
              2448 0x00002920
                                2448 -r-- .rela.plt
10 0x000032b0
                23 0x000032b0
                                  23 - r - x .init
```

As you may know, binaries have sections and maps. The sections define the contents of a portion of the file that can be mapped in memory (or not). What is mapped is defined by the segments.

Before the IO refactoring done by condret, the S command was used to manage what we now call maps. Currently the S command is deprecated because iS and om should be enough.

Firmware images, bootloaders and binary files usually place various sections of a binary at different addresses in memory. To represent this behavior, radare offers the iS. Use iS? to get the help message. To list all created sections use iS (or iSj to get the json format). The iS= will show the region bars in ascii-art.

You can create a new mapping using the om subcommand as follows:

```
om fd vaddr [size] [paddr] [rwx] [name]
```

For Example:

[0x0040100] > om 4 0x00000100 0x00400000 0x0001ae08 rwx test

You can also use om command to view information about mapped sections:

#### [0x00401000] > om

```
6 fd: 4 +0x0001ae08 0x00000100 - 0x0004000ff rwx test
5 fd: 3 +0x00000000 0x000000000 - 0x00000055f r-- fmap.LOAD0
4 fd: 3 +0x00001000 0x00001000 - 0x000011e4 r-x fmap.LOAD1
3 fd: 3 +0x00002000 0x00002000 - 0x0000211f r-- fmap.LOAD2
2 fd: 3 +0x00002de8 0x00003de8 - 0x00000402f r-- fmap.LOAD3
1 fd: 4 +0x00000000 0x000004030 - 0x000004037 rw- mmap.LOAD3
```

Use om? to get all the possible subcommands. To list all the defined maps use om (or omj to get the json format or om\* to get the r2 commands format). To get the ascii art view use om=.

It is also possible to delete the mapped section using the om-mapid command.

For Example:

```
[0x00401000] > om-6
```

#### Seeking

To move around the file we are inspecting we will need to change the offset at which we are using the s command.

The argument is a math expression that can contain flag names, parenthesis, addition, substraction, multiplication of immediates of contents of memory using brackets.

Some example commands:

```
[0x0000000]> s 0x10
[0x00000010]> s+4
[0x00000014]> s-
[0x00000010]> s+
[0x00000014]>
```

Observe how the prompt offset changes. The first line moves the current offset to the address 0x10.

The second does a relative seek 4 bytes forward.

And finally, the last 2 commands are undoing, and redoing the last seek operations.

Instead of using just numbers, we can use complex expressions, or basic arithmetic operations to represent the address to seek.

To do this, check the ?? Help message which describes the internal variables that can be used in the expressions. For example, this is the same as doing s+4.

```
[0x00000000] > s $$+4
```

From the debugger (or when emulating) we can also use the register names as references. They are loaded as flags with the .dr\* command, which happens under the hood.

```
[0x00000000] > s rsp+0x40
```

Here's the full help of the s command. We will explain in more detail below.

```
[0x00000000] > s?
```

```
| s- n
                    Seek n bytes backward
                    Seek blocksize bytes backward (/=n)
| s--[n]
                    Redo seek
| s+
| s+ n
                    Seek n bytes forward
| s++[n]
                    Seek blocksize bytes forward (/=n)
                    List undo seek history (JSON, =list, *r2, !=names, s==)
| s[j*=!]
                    Search for next occurrence of 'DATA'
| s/ DATA
| s/x 9091
                    Search for next occurrence of \x90\x91
| sa [[+-]a] [asz] Seek asz (or bsize) aligned to addr
                    Seek aligned to bb start
| sC[?] string
                    Seek to comment matching given string
                    Seek to next function (f->addr+f->size)
| sf
| sf function
                    Seek to address of specified function
| sf.
                    Seek to the beginning of current function
| sg/sG
                    Seek begin (sg) or end (sG) of section or file
| sl[?] [+-]line
                    Seek to line
| sn/sp ([nkey])
                    Seek to next/prev location, as specified by scr.nkey
| so [N]
                    Seek to N next opcode(s)
                    Seek to register
| sr pc
ss
                    Seek silently (without adding an entry to the seek history)
> 3s++
              ; 3 times block-seeking
              ; seek at 0x80+10
> s 10+0x80
```

If you want to inspect the result of a math expression, you can evaluate it using the ? command. Simply pass the expression as an argument. The result can be displayed in hexadecimal, decimal, octal or binary formats.

```
> ? 0x100+200
0x1C8 ; 456d ; 710o ; 1100 1000
```

There are also subcommands of ? that display the output in one specific format (base 10, base 16,...). See ?v and ?vi.

In the visual mode, you can press u (undo) or U (redo) inside the seek history to return back to previous or forward to the next location.

#### Open file

As a test file, let's use a simple hello\_world.c compiled in Linux ELF format. After we compile it let's open it with radare2:

#### \$ r2 hello\_world

Now we have the command prompt:

[0x00400410] >

And it is time to go deeper.

### Seeking at any position

All seeking commands that take an address as a command parameter can use any numeral base such as hex, octal, binary or decimal.

Seek to an address 0x0. An alternative command is simply 0x0

```
[0x00400410]> s 0x0
[0x00000000]>
Print current address:
[0x00000000]> s
0x0
[0x00000000]>
```

There is an alternate way to print current position: ?v \$\$.

Seek N positions forward, space is optional:

```
[0x00000000]> s+ 128
[0x00000080]>
```

Undo last two seeks to return to the initial address:

```
[0x00000080]> s-
[0x00000000]> s-
[0x00400410]>
```

We are back at 0x00400410.

There's also a command to show the seek history:

```
[0x00400410]> s*
f undo_3 @ 0x400410
f undo_2 @ 0x40041a
f undo_1 @ 0x400410
f undo_0 @ 0x400411
# Current undo/redo position.
f redo_0 @ 0x4005b4
```

### Working with data types

Radare2 can also work with data types. You can use standard C data types or define your own using C. Currently, there is a support for structs, unions, function signatures, and enums.

```
| t- <name>
                             Delete types by its name
                             Remove all types
| t-*
| tail [filename]
                             Output the last part of files
                             List all/given types in C output format
| tc [type.name]
| te[?]
                             List all loaded enums
| td[?] <string>
                             Load types from string
                             List all loaded functions signatures
| tk <sdb-query>
                             Perform sdb query
                             Show/Link type to an address
| t1[?]
| tn[?] [-][addr]
                             manage noreturn function attributes and marks
                             Open cfg.editor to load types
l to -
                             Load types from C header file
| to <path>
                             Open cfg.editor to edit types
| toe [type.name]
| tos <path>
                             Load types from parsed Sdb database
                             cast data at <address> to <type> and print it (XXX: type can co
| tp <type> [addr|varname]
| tpv <type> @ [value]
                             Show offset formatted for given type
| tpx <type> <hexpairs>
                             Show value for type with specified byte sequence (XXX: type can
| ts[?]
                             Print loaded struct types
| tu[?]
                             Print loaded union types
| tx[f?]
                             Type xrefs
| tt[?]
                             List all loaded typedefs
```

#### Defining new types

There are three different methods to define new types:

1. Defining a new type from r2 shell immediately, to do this you will use td command, and put the whole line between double quotes. For example:

```
"td struct person {int age; char *name; char *address;};"
```

- 2. You can also use to to open a text editor and write your own types in there. This is preferable when you got too many types to define.
- 3. Radare2 also supports loading header files using the command to followed by a path to the header file you want to load.

You can View loaded types in r2 using ts for structures, tu for unions, tf for function signatures, te for enums.

You can also cast pointers to data types and view data in there accordingly with tp. EX:

```
[0x00400511]> tp person = 0x7fff170a46b0
age : 0x7fff170a46b0 = 20
name : (*0x4005b0) 0x7fff170a46b4 = My name
address : (*0x4005b8) 0x7fff170a46bc = My age
[0x00400511]>
```

## Writing Data

Radare can manipulate a loaded binary file in many ways. You can resize the file, move and copy/paste bytes, insert new bytes (shifting data to the end of the block or file), or simply overwrite bytes. New data may be given as a wide-string, assembler instructions, or the data may be read in from another file.

Resize the file using the  $\mathbf{r}$  command. It accepts a numeric argument. A positive value sets a new size for the file. A negative one will truncate the file to the current seek position minus N bytes.

```
r 1024 ; resize the file to 1024 bytes r -10 @ 33 ; strip 10 bytes at offset 33
```

Write bytes using the w command. It accepts multiple input formats like inline assembly, endian-friendly dwords, files, hexpair files, wide strings:

```
[0x00404888] > w?
Usage: w[x] [str] [<file] [<<EOF] [@addr]
| w[1248][+-][n]
                       increment/decrement byte, word...
| w foobar
                       write string 'foobar'
| w0 [len]
                       write 'len' bytes with value 0x00
| w6[de] base64/hex
                       write base64 [d]ecoded or [e]ncoded string
| wa[?] push ebp
                       write opcode, separated by ';' (use '"' around the command)
| waf f.asm
                       assemble file and write bytes
| waF f.asm
                       assemble file and write bytes and show 'wx' op with hexpair bytes of
                       modify opcode (change conditional of jump. nop, etc)
| wao[?] op
| wA[?] r 0
                       alter/modify opcode at current seek (see wA?)
| wb 010203
                       fill current block with cyclic hexpairs
| wB[-]0xVALUE
                       set or unset bits with given value
                       list all write changes
l wc
                       write cache undo/commit/reset/list (io.cache)
| wc[?][jir+-*?]
| wd [off] [n]
                       duplicate N bytes from offset at current seek (memcpy) (see y?)
| we[?] [nNsxX] [arg]
                       extend write operations (insert instead of replace)
| wf[fs] -|file
                       write contents of file at current offset
l wh r2
                       whereis/which shell command
| wm fOff
                       set binary mask hexpair to be used as cyclic write mask
| wo[?] hex
                       write in block with operation. 'wo?' fmi
| wp[?] -|file
                       apply radare patch file. See wp? fmi
I wr 10
                       write 10 random bytes
| ws pstring
                       write 1 byte for length and then the string
| wt[f][?] file [sz]
                       write to file (from current seek, blocksize or sz bytes)
| wts host:port [sz]
                       send data to remote host:port via tcp://
                       write wide string f\x000\x000\x000\x000\x000\x000'
| ww foobar
| wx[?][fs] 9090
                       write two intel nops (from wxfile or wxseek)
| wv[?] eip+34
                       write 32-64 bit value honoring cfg.bigendian
| wz string
                       write zero terminated string (like w + \x00)
```

#### Some examples:

```
[0x00000000]> wx 123456 @ 0x8048300
[0x0000000]> wv 0x8048123 @ 0x8049100
[0x00000000]> wa jmp 0x8048320
```

#### Write Over

The wo command (write over) has many subcommands, each combines the existing data with the new data using an operator. The command is applied to the current block. Supported operators include XOR, ADD, SUB...

```
[0x4A13B8C0] > wo?
|Usage: wo[asmdxoArl24] [hexpairs] @ addr[:bsize]
|Example:
  wox 0x90
            ; xor cur block with 0x90
  wox 90
             ; xor cur block with 0x90
  wox 0x0203; xor cur block with 0203
  woa 02 03 ; add [0203][0203][...] to curblk
  woe 02 03 ; create sequence from 2 to 255 with step 3
|Supported operations:
  WOW
      == write looped value (alias for 'wb')
      += addition
  woa
  wos
       -= substraction
  wom
      *= multiply
  wod
      /= divide
  wox
       ^=
           xor
       |=
  WOO
           or
  woA &=
           and
  woR random bytes (alias for 'wr $b'
       >>= shift right
  wol <<= shift left
  wo2 2= 2 byte endian swap
  wo4 4= 4 byte endian swap
```

It is possible to implement cipher-algorithms using radare core primitives and wo. A sample session performing xor(90) + add(01, 02):

```
      0x7fcd6a891640
      1374
      60d8
      b290
      d91d
      1dc5
      98a1
      9090
      d81d

      0x7fcd6a891650
      90dc
      197c
      9f8f
      1490
      d81d
      95d9
      9f8f
      1490

      0x7fcd6a891660
      13d7
      9491
      9f8f
      1490
      13ff
      9491
      9f8f
      1490

      [0x7fcd6a891630] > woa
      01
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
      02
```

### Yank/Paste

Radare2 has an internal clipboard to save and write portions of memory loaded from the current io layer.

This clipboard can be manipulated with the y command.

The two basic operations are

- copy (yank)
- paste

The yank operation will read N bytes (specified by the argument) into the clipboard. We can later use the yy command to paste what we read before into a file.

You can yank/paste bytes in visual mode selecting them with the cursor mode (Vc) and then using the y and Y key bindings which are aliases for y and yy commands of the command-line interface.

#### [0x00000000] > y?

```
Usage: y[ptxy] [len] [[@]addr]
                                 # See wd? for memcpy, same as 'yf'.
                  open cfg.editor to edit the clipboard
| y!
| y 16 0x200
                  copy 16 bytes into clipboard from 0x200
| y 16 @ 0x200
                  copy 16 bytes into clipboard from 0x200
                  copy 16 bytes into clipboard
| y 16
                  show yank buffer information (srcoff len bytes)
Ιу
                  print in r2 commands what's been yanked
| y*
| yf 64 0x200
                  copy file 64 bytes from 0x200 from file
| yfa file copy
                  copy all bytes from file (opens w/ io)
| yfx 10203040
                  yank from hexpairs (same as ywx)
                  print in JSON commands what's been vanked
lуj
                  print contents of clipboard
I ур
                  print contents of clipboard in hexpairs
l yq
                  print contents of clipboard as string
l ys
| yt 64 0x200
                  copy 64 bytes from current seek to 0x200
| ytf file
                  dump the clipboard to given file
| yw hello world yank from string
```

```
| ywx 10203040
                  yank from hexpairs (same as yfx)
                  print contents of clipboard in hexadecimal
| yx
                 paste clipboard
l yy 0x3344
                  copy nul-terminated string (up to blocksize) into clipboard
| yz [len]
Sample session:
[0x00000000] > s 0x100
                        ; seek at 0x100
[0x00000100]> y 100
                        ; yanks 100 bytes from here
                        ; seek 0x200
[0x00000200] > s 0x200
[0x00000200]> yy
                        ; pastes 100 bytes
You can perform a yank and paste in a single line by just using the yt command
(yank-to). The syntax is as follows:
[0x4A13B8C0] > x
   offset 0 1 2 3 4 5 6 7 8 9 A B 0123456789AB
0x4A13B8C0, 89e0 e839 0700 0089 c7e8 e2ff ...9......
0x4A13B8CC, ffff 81c3 eea6 0100 8b83 08ff ......
0x4A13B8D8, ffff 5a8d 2484 29c2
                                          ..Z.$.).
[0x4A13B8C0] > yt 8 0x4A13B8CC @ 0x4A13B8C0
[0x4A13B8C0] > x
   offset 0 1 2 3 4 5 6 7 8 9 A B 0123456789AB
0x4A13B8C0, 89e0 e839 0700 0089 c7e8 e2ff ...9......
0x4A13B8CC, 89e0 e839 0700 0089 8b83 08ff ...9......
0x4A13B8D8, ffff 5a8d 2484 29c2
                                          ..Z.$.).
```

#### Zoom

The zoom is a print mode that allows you to get a global view of the whole file or a memory map on a single screen. In this mode, each byte represents file\_size/block\_size bytes of the file. Use the pz command, or just use Z in the visual mode to toggle the zoom mode.

The cursor can be used to scroll faster through the zoom out view. Pressing z again will zoom-in at the cursor position.

```
calculate entropy and expand to 0-255 range
| pze
| pzh
               head (first byte value); This is the default mode
Let's see some examples:
[0x08049790] > e zoom.byte=h
[0x08049790] > pz // or default pzh
0x00000000 7f00 0000 e200 0000 146e 6f74 0300 0000
0x00000010 0000 0000 0068 2102 00ff 2024 e8f0 007a
0x00000020 8c00 18c2 ffff 0080 4421 41c4 1500 5dff
0x00000030 ff10 0018 0fc8 031a 000c 8484 e970 8648
0x00000040 d68b 3148 348b 03a0 8b0f c200 5d25 7074
0x00000050 7500 00e1 ffe8 58fe 4dc4 00e0 dbc8 b885
[0x08049790] > e zoom.byte=p
[0x08049790] > pz // or pzp
0x00000000 2f47 0609 070a 0917 1e9e a4bd 2a1b 2c27
0x00000010 322d 5671 8788 8182 5679 7568 82a2 7d89
0x00000020 8173 7f7b 727a 9588 a07b 5c7d 8daf 836d
0x00000030 b167 6192 a67d 8aa2 6246 856e 8c9b 999f
0x00000040 a774 96c3 b1a4 6c8e a07c 6a8f 8983 6a62
0x00000050 7d66 625f 7ea4 7ea6 b4b6 8b57 a19f 71a2
[0x08049790] > eval zoom.byte = flags
[0x08049790] > pz // or pzf
0x00406e65 48d0 80f9 360f 8745 ffff ffeb ae66 0f1f
0x00406e75 4400 0083 f801 0f85 3fff ffff 410f b600
0x00406e85 3c78 0f87 6301 0000 0fb6 c8ff 24cd 0026
0x00406e95 4100 660f 1f84 0000 0000 0084 c074 043c
0x00406ea5 3a75 18b8 0500 0000 83f8 060f 95c0 e9cd
0x00406eb5 feff ff0f 1f84 0000 0000 0041 8801 4983
0x00406ec5 c001 4983 c201 4983 c101 e9ec feff ff0f
[0x08049790] > e zoom.byte=F
[0x08049790] > p0 // or pzF
0x00000010 0000 2b5c 5757 3a14 331f 1b23 0315 1d18
0x00000020 222a 2330 2b31 2e2a 1714 200d 1512 383d
0x00000030 1e1a 181b 0a10 1a21 2a36 281e 1d1c 0e11
0x00000040 1b2a 2f22 2229 181e 231e 181c 1913 262b
0x00000050 2b30 4741 422f 382a 1e22 0f17 0f10 3913
You can limit zooming to a range of bytes instead of the whole bytespace. Change
zoom.from and zoom.to eval variables:
```

number of bytes with value OxFF

| pzF

```
[0x00003a04] > e? zoom.
zoom.byte: Zoom callback to calculate each byte (See pz? for help)
zoom.from: Zoom start address
```

```
zoom.in: Specify boundaries for zoom
zoom.maxsz: Zoom max size of block
zoom.to: Zoom end address
[0x00003a04]> e zoom.
zoom.byte = h
zoom.from = 0
zoom.in = io.map
zoom.maxsz = 512
zoom.to = 0
```

#### Charset

Sometimes, a binary can contain custom characters in another charsets than ascii. It is as example the case of the gameboy. The gameboy has his own custom charset for each game. To select as example a custom charset corresponding to the game pokemon red and blue of the gameboy, do:

#### e cfg.charset=pokered;

You can now do commands such as ps and w with custom charset.

Sadly, as you can imagine, very often the charset will be missing. There can not be as many plugin as there are games for gameboy. If the charset does not exists yet, fell free to write it. See the chapters plugins and then 'charset" to read about charsets.

It works of course for each architecture. Not only the gameboy.

You can also use visual mode with the custom charset for single char encodings.

#### Colors

Console access is wrapped in API that permits to show the output of any command as ANSI, W32 Console or HTML formats. This allows radare's core to run inside environments with limited displaying capabilities, like kernels or embedded devices. It is still possible to receive data from it in your favorite format.

To enable colors support by default, add a corresponding configuration option to the .radare2 configuration file:

```
$ echo 'e scr.color=1' >> ~/.radare2rc
```

Note that enabling colors is not a boolean option. Instead, it is a number because there are different color depth levels. This is:

- 0: black and white
- 1: 16 basic ANSI colors
- 2: 256 scale colors
- 3: 24bit true color

The reason for having such user-defined options is because there's no standard or portable way for the terminal programs to query the console to determine the best configuration, same goes for charset encodings, so r2 allows you to choose that by hand.

Usually, serial consoles may work with 0 or 1, while xterms may support up to 3. RCons will try to find the closest color scheme for your theme when you choose a different them with the eco command.

It is possible to configure the color of almost any element of disassembly output. For \*NIX terminals, r2 accepts color specification in RGB format. To change the console color palette use ec command.

Type ec to get a list of all currently used colors. Type ecs to show a color palette to pick colors from:

img

### Themes

You can create your own color theme, but radare2 have its own predefined ones. Use the eco command to list or select them.

After selecting one, you can compare between the color scheme of the shell and the current theme by pressing Ctrl-Shift and then right arrow key for the toggle.

In visual mode use the R key to randomize colors or choose the next theme in the list.

### Configuration Variables

Below is a list of the most frequently used configuration variables. You can get a complete list by issuing e command without arguments. For example, to see all variables defined in the "cfg" namespace, issue e cfg. (mind the ending dot). You can get help on any eval configuration variable by using e? cfg.

The e?? command to get help on all the evaluable configuration variables of radare2. As long as the output of this command is pretty large you can combine it with the internal grep ~ to filter for what you are looking for:

e??~color

The Visual mode has an eval browser that is accessible through the Vbe command.

#### asm.arch

Defines the target CPU architecture used for disassembling (pd, pD commands) and code analysis (a command). You can find the list of possible values by looking at the result of e asm.arch=? or rasm2 -L. It is quite simple to add new architectures for disassembling and analyzing code. There is an interface for

that. For x86, it is used to attach a number of third-party disassembler engines, including GNU binutils, Udis86 and a few handmade ones.

#### asm.bits

Determines width in bits of registers for the current architecture. Supported values: 8, 16, 32, 64. Note that not all target architectures support all combinations for asm.bits.

#### asm.syntax

Changes syntax flavor for disassembler between Intel and AT&T. At the moment, this setting affects Udis86 disassembler for Intel 32/Intel 64 targets only. Supported values are intel and att.

#### asm.pseudo

A boolean value to set the psuedo syntax in the disassembly. "False" indicates a native one, defined by the current architecture, "true" activates a pseudocode strings format. For example, it'll transform:

	0x080483ff	e832000000	call 0x8048436
	0x08048404	31c0	xor eax, eax
	0x08048406	0205849a0408	add al, byte [0x8049a84]
1	0x0804840c	83f800	cmp eax, 0
1	0x0804840f	7405	je 0x8048416
to			
1	0x080483ff	e832000000	0x8048436 ()
1	0x08048404	31c0	eax = 0
1	0x08048406	0205849a0408	al += byte [0x8049a84]
1	0x0804840c	83f800	var = eax - 0
1	0x0804840f	7405	if (!var) goto 0x8048416

It can be useful while disassembling obscure architectures.

#### asm.os

Selects a target operating system of currently loaded binary. Usually, OS is automatically detected by rabin -rI. Yet, asm.os can be used to switch to a different syscall table employed by another OS.

#### asm.flags

If defined to "true", disassembler view will have flags column.

#### asm.lines.call

If set to "true", draw lines at the left of the disassemble output (pd, pD commands) to graphically represent control flow changes (jumps and calls) that are targeted inside current block. Also, see asm.lines.out.

#### asm.lines.out

When defined as "true", the disassembly view will also draw control flow lines that go outside of the block.

#### asm.linestyle

A boolean value which changes the direction of control flow analysis. If set to "false", it is done from top to bottom of a block; otherwise, it goes from bottom to top. The "false" setting seems to be a better choice for improved readability and is the default one.

#### asm.offset

Boolean value which controls the visibility of offsets for individual disassembled instructions.

#### asm.trace

A boolean value that controls displaying of tracing information (sequence number and counter) at the left of each opcode. It is used to assist with programs trace analysis.

#### asm.bytes

A boolean value used to show or hide displaying of raw bytes of instructions.

#### asm.sub.reg

A boolean value used to replace register names with arguments or their associated role alias.

For example, if you have something like this:

	0x080483ea	83c404	add esp, 4
	0x080483ed	68989a0408	push 0x8049a98
	0x080483f7	e870060000	call sym.imp.scanf
	0x080483fc	83c408	add esp, 8
1	0x08048404	31c0	xor eax, eax
This va	riable changes it to:		
1	0x080483ea	83c404	add SP, 4
1	0x080483ed	68989a0408	push 0x8049a98

```
| 0x080483f7 e870060000 call sym.imp.scanf
| 0x080483fc 83c408 add SP, 8
| 0x08048404 31c0 xor AO, AO
```

#### asm.sub.jmp

A boolean value used to substitute jump, call and branch targets in disassembly.

For example, when turned on, it'd display jal 0x80001a40 as jal fcn.80001a40 in the disassembly.

#### asm.sub.rel

A boolean value which substitutes pc relative expressions in disassembly. When turned on, it shows the references as string references.

For example:

When turned on, this variable lets you display the above instruction as:

```
0x5563844a0181 488d3d7c0e00. lea rdi, str.argv__2d_:__s ; 0x5563844a1004 ; "argv[%]
```

#### asm.sub.section

Boolean which shows offsets in disassembly prefixed with the name of the section or map.

That means, from something like:

```
0x000067ea 488d0def0c01. lea rcx, [0x000174e0]
```

to the one below, when toggled on.

```
0x000067ea 488d0def0c01. lea rcx, [fmap.LOAD1.0x000174e0]
```

#### asm.sub.varonly

Boolean which substitutes the variable expression with the local variable name.

```
For example: var_14h as rbp - var_14h, in the disassembly.
```

### cfg.bigendian

Change endianness. "true" means big-endian, "false" is for little-endian. "file.id" and "file.flag" both to be true.

#### cfg.newtab

If this variable is enabled, help messages will be displayed along with command names in tab completion for commands.

#### scr.color

This variable specifies the mode for colorized screen output: "false" (or 0) means no colors, "true" (or 1) means 16-colors mode, 2 means 256-colors mode, 3 means 16 million-colors mode. If your favorite theme looks weird, try to bump this up.

#### scr.seek

This variable accepts a full-featured expression or a pointer/flag (eg. eip). If set, radare will set seek position to its value on startup.

#### scr.scrollbar

If you have set up any flagzones (fz?), this variable will let you display the scrollbar with the flagzones, in Visual mode. Set it to 1 to display the scrollbar at the right end, 2 for the top and 3 to display it at the bottom.

#### scr.utf8

A boolen variable to show UTF-8 characters instead of ANSI.

#### cfg.fortunes

Enables or disables "fortune" messages displayed at each radare start.

#### cfg.fortunes.type

Fortunes are classified by type. This variable determines which types are allowed for displaying when cfg.fortunes is true, so they can be fine-tuned on what's appropriate for the intended audience. Current types are tips, fun, nsfw, creepy.

#### stack.size

This variable lets you set the size of stack in bytes.

#### **Files**

Use r2 -H to list all the environment variables that matter to know where it will be looking for files. Those paths depend on the way (and operating system) you have built r2 for.

R2\_PREFIX=/usr
MAGICPATH=/usr/share/radare2/2.8.0-git/magic
PREFIX=/usr
INCDIR=/usr/include/libr
LIBDIR=/usr/lib64
LIBEXT=so
RCONFIGHOME=/home/user/.config/radare2

```
RDATAHOME=/home/user/.local/share/radare2
RCACHEHOME=/home/user/.cache/radare2
LIBR_PLUGINS=/usr/lib/radare2/2.8.0-git
USER_PLUGINS=/home/user/.local/share/radare2/plugins
USER_ZIGNS=/home/user/.local/share/radare2/zigns
```

#### RC Files

RC files are r2 scripts that are loaded at startup time. Those files must be in 3 different places:

#### System

radare2 will first try to load /usr/share/radare2/radare2rc

#### Your Home

Each user in the system can have its own r2 scripts to run on startup to select the color scheme, and other custom options by having r2 commands in there.

- ~/.radare2rc
- ~/.config/radare2/radare2rc
- ~/.config/radare2/radare2rc.d/

#### Target file

If you want to run a script everytime you open a file, just create a file with the same name of the file but appending .r2 to it.

# Configuration

The core reads ~/.config/radare2/radare2rc while starting. You can add e commands to this file to tune the radare2 configuration to your taste.

To prevent radare2 from parsing this file at startup, pass it the -N option.

All the configuration of radare2 is done with the eval commands. A typical startup configuration file looks like this:

```
$ cat ~/.radare2rc
e scr.color = 1
e dbg.bep = loader
```

The configuration can also be changed with -e <config=value> command-line option. This way you can adjust configuration from the command line, keeping the .radare2rc file intact. For example, to start with empty configuration and then adjust scr.color and asm.syntax the following line may be used:

```
$ radare2 -N -e scr.color=1 -e asm.syntax=intel -d /bin/ls
```

Internally, the configuration is stored in a hash table. The variables are grouped in namespaces: cfg., file., dbg., scr. and so on.

To get a list of all configuration variables just type e in the command line prompt. To limit the output to a selected namespace, pass it with an ending dot to e. For example, e file. will display all variables defined inside the "file" namespace.

To get help about e command type e?:

```
Usage: e [var[=value]] Evaluable vars
e?asm.bytes
                  show description
l e??
                  list config vars with description
l e a
                  get value of var 'a'
| e a=b
                  set var 'a' the 'b' value
                  print all valid values of var
| e var=?
                  print all valid values of var with description
| e var=??
                  same as 'e a=b' but without using a space
l e.a=b
| e, k=v, k=v, k=v
                  comma separated k[=v]
                  reset config vars
| e*
                  dump config vars in r commands
                  invert the boolean value of 'a' var
| e!a
| ec [k] [color]
                  set color for given key (prompt, offset, ...)
 eevar
                  open editor to change the value of var
 ed
                  open editor to change the ~/.radare2rc
                  list config vars in JSON
 еj
| env [k[=v]]
                  get/set environment variable
| er [key]
                  set config key as readonly. no way back
| es [space]
                  list all eval spaces [or keys]
| et [key]
                  show type of given config variable
| ev [key]
                  list config vars in verbose format
| evj [key]
                  list config vars in verbose format in JSON
```

A simpler alternative to the e command is accessible from the visual mode. Type Ve to enter it, use arrows (up, down, left, right) to navigate the configuration, and q to exit it. The start screen for the visual configuration edit looks like this:

#### [EvalSpace]

```
> anal asm scr asm bin cfg diff dir dbg cmd
```

```
fs
hex
http
graph
hud
scr
search
```

For configuration values that can take one of several values, you can use the =? operator to get a list of valid values:

```
[0x00000000]> e scr.nkey = ? scr.nkey = fun, hit, flag
```

### Crackmes

Crackmes (from "crack me" challenge) are the training ground for reverse engineering people. This section will go over tutorials on how to defeat various crackmes using r2.

#### Authors & Contributors

This book wouldn't be possible without the help of a large list of contributors who have been reviewing, writing and reporting bugs and stuff in the radare2 project as well as in this book.

#### The radare2 book

This book was started by maijin as a new version of the original radare book written by pancake.

• Old radare1 book http://www.radare.org/get/radare.pdf

Many thanks to everyone who has been involved with the gitbook:

Adrian Studer, Ahmed Mohamed Abd El-Mawgood, Akshay Krishnan R, Andrew Hoog, Anton Kochkov, Antonio Sánchez, Austin Hartzheim, Aswin C (official-cjunior), Bob131, DZ\_ruyk, David Tomaschik, Eric, Fangrui Song, Francesco Tamagni, FreeArtMan, Gerardo García Peña, Giuseppe, Grigory Rechistov, Hui Peng, ITAYCOHEN, Itay Cohen, Jeffrey Crowell, John, Judge Dredd (key 6E23685A), Jupiter, Kevin Grandemange, Kevin Laeufer, Luca Di Bartolomeo, Lukas Dresel, Maijin, Michael Scherer, Mike, Nikita Abdullin, Paul, Paweł Łukasik, Peter C, RandomLive, Ren Kimura, Reto Schneider, SchumBlubBlub, SkUaTeR, Solomon, Srimanta Barua, Sushant Dinesh, TDKPS, Thanat0s, Vanellope, Vex Woo, Vorlent, XYlearn, Yuri Slobodyanyuk, ali, aoighost, condret, hdznrrd, izhuer, jvoisin, kij, madblobfish, muzlightbeer, pancake, polym (Tim), puddl3glum, radare, sghctoma, shakreiner, sivaramaaa, taiyu, vanel1ope, xarkes.

# **Files**

The radare2 debugger allows the user to list and manipulate the file descriptors from the target process.

This is a useful feature, which is not found in other debuggers, the functionality is similar to the lsof command line tool, but have extra subcommands to change the seek, close or duplicate them.

So, at any time in the debugging session you can replace the stdio file descriptors to use network sockets created by r2, or replace a network socket connection to hijack it.

This functionality is also available in r2frida by using the dd command prefixed with a backslash. In r2 you may want to see the output of dd? for proper details.

# Getting Started

### Small session in radare2 debugger

- r2 -d /bin/ls: Opens radare2 with file /bin/ls in debugger mode using the radare2 native debugger, but does not run the program. You'll see a prompt (radare2) all examples are from this prompt.
- db flag: place a breakpoint at flag, where flag can be either an address or a function name
- db flag: remove the breakpoint at flag, where flag can be either an address or a function name
- db: show list of breakpoint
- dc: run the program
- dr: Show registers state
- drr: Show registers references (telescoping) (like peda)
- ds: Step into instruction
- dso: Step over instruction
- dbt: Display backtrace
- dm: Show memory maps
- dk <signal>: Send KILL signal to child
- ood: reopen in debug mode
- ood arg1 arg2: reopen in debug mode with arg1 and arg2

# Heap

dmhb

| dmhbg [bin\_num]

| dmhb [bin\_num|bin\_num:malloc\_state]

radare2's dm subcommands can also display a map of the heap which is useful for those who are interested in inspecting the heap and its content. Simply execute dmh to show a map of the heap:

```
[0x7fae46236ca6] > dmh
 Malloc chunk @ 0x55a7ecbce250 [size: 0x411][allocated]
 Top chunk @ 0x55a7ecbce660 - [brk_start: 0x55a7ecbce000, brk_end: 0x55a7ecbef000]
You can also see a graph layout of the heap:
[0x7fae46236ca6] > dmhg
Heap Layout
   ,-----
       Malloc chunk @ 0x55a7ecbce000
   | size: 0x251
   | fd: 0x0, bk: 0x0
   `_____|
     Malloc chunk @ 0x55a7ecbce250
 | size: 0x411
  | fd: 0x57202c6f6c6c6548, bk: 0xa21646c726f |
  Top chunk @ 0x55a7ecbce660
[brk_start:0x55a7ecbce000, brk_end:0x55a7ecbef000] |
 Another heap commands can be found under dmh, check dmh? for the full list.
[0x00000000] > dmh?
|Usage: dmh # Memory map heap
| dmh
                   List chunks in heap segment
| dmh [malloc_state] List heap chunks of a particular arena
| dmha
                   List all malloc_state instances in application
```

Display all parsed Double linked list of main\_arena's bins instance

Display double linked list graph of main\_arena's bin [Under developem

Display parsed double linked list of bins in

| dmhc @[chunk\_addr] Display malloc\_chunk struct for a given malloc chunk

To print safe-linked lists (glibc >= 2.32) with demangled pointers, the variable dbg.glibc.demangle must be true.

# Debugger

Debuggers are implemented as IO plugins. Therefore, radare can handle different URI types for spawning, attaching and controlling processes. The complete list of IO plugins can be viewed with r2 -L. Those that have "d" in the first column ("rwd") support debugging. For example:

```
r_d debug Debug a program or pid. dbg://bin/ls, dbg://1388 (LGPL3)
rwd gdb Attach to gdbserver, 'qemu -s', gdb://localhost:1234 (LGPL3)
```

There are different backends for many target architectures and operating systems, e.g., GNU/Linux, Windows, MacOS X, (Net,Free,Open)BSD and Solaris.

Process memory is treated as a plain file. All mapped memory pages of a debugged program and its libraries can be read and interpreted as code or data structures.

Communication between radare and the debugger IO layer is wrapped into system() calls, which accept a string as an argument, and executes it as a command. An answer is then buffered in the output console, its contents can be additionally processed by a script. Access to the IO system is achieved with =!. Most IO plugins provide help with =!? or =!help. For example:

```
$ r2 -d /bin/ls
...
[0x7fc15afa3cc0]> =!help
Usage: =!cmd args
=!ptrace - use ptrace io
=!mem - use /proc/pid/mem io if possible
=!pid - show targeted pid
=!pid <#> - select new pid
```

In general, debugger commands are portable between architectures and operating systems. Still, as radare tries to support the same functionality for all target architectures and operating systems, certain things have to be handled separately.

They include injecting shellcodes and handling exceptions. For example, in MIPS targets there is no hardware-supported single-stepping feature. In this case, radare2 provides its own implementation for single-step by using a mix of code analysis and software breakpoints.

To get basic help for the debugger, type 'd?':

```
# Debug commands
Usage: d
| db[?]
                            Breakpoints commands
| dbt[?]
                           Display backtrace based on dbg.btdepth and dbg.btalgo
| dc[?]
                            Continue execution
                           File descriptors (!fd in r1)
| dd[?]
| de[-sc] [perm] [rm] [e] Debug with ESIL (see de?)
| dg <file>
                            Generate a core-file (WIP)
| dH [handler]
                            Transplant process to a new handler
| di[?]
                            Show debugger backend information (See dh)
| dk[?]
                           List, send, get, set, signal handlers of child
| dL[?]
                           List or set debugger handler
| dm[?]
                            Show memory maps
| do[?]
                            Open process (reload, alias for 'oo')
| doo[args]
                            Reopen in debug mode with args (alias for 'ood')
| doof[file]
                            Reopen in debug mode from file (alias for 'oodf')
                            Close debug session
| doc
| dp[?]
                            List, attach to process or thread id
| dr[?]
                            Cpu registers
| ds[?]
                            Step, over, source line
| dt[?]
                           Display instruction traces
| dw <pid>
                           Block prompt until pid dies
                            Inject and run code on target process (See gs)
\int dx [?]
```

To restart your debugging session, you can type oo or oo+, depending on desired behavior.

```
oo reopen current file (kill+fork in debugger)
oo+ reopen current file in read-write
```

# Memory Maps

The ability to understand and manipulate the memory maps of a debugged program is important for many different Reverse Engineering tasks. radare2 offers a rich set of commands to handle memory maps in the binary. This includes listing the memory maps of the currently debugged binary, removing memory maps, handling loaded libraries and more.

First, let's see the help message for dm, the command which is responsible for handling memory maps:

```
[0x55f2104cf620] > dm?
```

```
# Memory maps commands
Usage: dm
| dm
                                    List memory maps of target process
| dm address size
                                    Allocate <size> bytes at <address> (anywhere if address:
                                    List memory maps of target process (ascii-art bars)
I dm=
| dm.
                                    Show map name of current address
                                    List memmaps in radare commands
| dm*
                                    Deallocate memory map of <address>
| dm- address
| dmd[a] [file]
                                    Dump current (all) debug map region to a file (from-to.dr
                                    Show map of heap
| dmh[?]
| dmi [addr|libname] [symname]
                                    List symbols of target lib
| dmi* [addr|libname] [symname]
                                    List symbols of target lib in radare commands
                                    List closest symbol to the current address
 dmi.
| dmiv
                                    Show address of given symbol for given lib
| dmj
                                    List memmaps in JSON format
| dml <file>
                                    Load contents of file into the current map region
| dmm[?][j*]
                                    List modules (libraries, binaries loaded in memory)
| dmp[?] <address> <size> <perms>
                                    Change page at <address> with <size>, protection <perms>
| dms[?] <id> <mapaddr>
                                    Take memory snapshot
| dms- <id> <mapaddr>
                                    Restore memory snapshot
| dmS [addr|libname] [sectname]
                                    List sections of target lib
| dmS* [addr|libname] [sectname]
                                    List sections of target lib in radare commands
| dmL address size
                                    Allocate <size> bytes at <address> and promote to huge page 2
```

In this chapter, we'll go over some of the most useful subcommands of dm using simple examples. For the following examples, we'll use a simple helloworld program for Linux but it'll be the same for every binary.

First things first - open a program in debugging mode:

```
$ r2 -d helloworld
Process with PID 20304 started...
= attach 20304 20304
bin.baddr 0x56136b475000
Using 0x56136b475000
asm.bits 64
[0x7f133f022fb0]>
```

Note that we passed "helloworld" to radare2 without "./". radare2 will try to find this program in the current directory and then in \$PATH, even if no "./" is passed. This is contradictory with UNIX systems, but makes the behaviour consistent for windows users

Let's use dm to print the memory maps of the binary we've just opened:

For those of you who prefer a more visual way, you can use dm= to see the memory maps using an ASCII-art bars. This will be handy when you want to see how these maps are located in the memory.

If you want to know the memory-map you are currently in, use dm.:

```
[0x7f133f022fb0] > dm.
```

```
0x00007f947eed9000 # 0x00007f947eefe000 * usr 148K s r-x /usr/lib/ld-2.27.so /usr/lib/ld-2
```

Using dmm we can "List modules (libraries, binaries loaded in memory)", this is quite a handy command to see which modules were loaded.

```
[0x7fa80a19dfb0]> dmm
0x55ca23a4a000 /tmp/helloworld
0x7fa80a19d000 /usr/lib/ld-2.27.so
```

Note that the output of dm subcommands, and dmm specifically, might be different in various systems and different binaries.

We can see that along with our helloworld binary itself, another library was loaded which is ld-2.27.so. We don't see libc yet and this is because radare2 breaks before libc is loaded to memory. Let's use dcu (debug continue until) to execute our program until the entry point of the program, which radare flags as entry0.

```
[0x7fa80a19dfb0]> dcu entry0
Continue until 0x55ca23a4a520 using 1 bpsize
hit breakpoint at: 55ca23a4a518
[0x55ca23a4a520]> dmm
0x55ca23a4a000 /tmp/helloworld
0x7fa809de1000 /usr/lib/libc-2.27.so
0x7fa80a19d000 /usr/lib/ld-2.27.so
```

Now we can see that libc-2.27.so was loaded as well, great!

Speaking of libc, a popular task for binary exploitation is to find the address of a specific symbol in a library. With this information in hand, you can build, for example, an exploit which uses ROP. This can be achieved using the dmi command. So if we want, for example, to find the address of system() in the loaded libc, we can simply execute the following command:

```
[0x55ca23a4a520]> dmi libc system
514 0x00000000 0x7fa809de1000 LOCAL FILE 0 system.c
515 0x00043750 0x7fa809e24750 LOCAL FUNC 1221 do_system
4468 0x001285a0 0x7fa809f095a0 LOCAL FUNC 100 sycerr_systemerr
```

```
5841 0x001285a0 0x7fa809f095a0 LOCAL FUNC 100 svcerr_systemerr 6427 0x00043d10 0x7fa809e24d10 WEAK FUNC 45 system 7094 0x00043d10 0x7fa809e24d10 GLBAL FUNC 45 system 7480 0x001285a0 0x7fa809f095a0 GLBAL FUNC 100 svcerr_systemerr
```

Similar to the  $\mathtt{dm}$ . command, with  $\mathtt{dmi}$ . you can see the closest symbol to the current address.

Another useful command is to list the sections of a specific library. In the following example we'll list the sections of 1d-2.27.so:

```
[0x55a7ebf09520] > dmS 1d-2.27
[Sections]
00 0x0000000
                 0 0x00000000
                                  0 ---- 1d-2.27.so.
                36 0x4652d1c8
01 0x000001c8
                                 36 -r-- ld-2.27.so..note.gnu.build_id
02 0x000001f0 352 0x4652d1f0 352 -r-- ld-2.27.so..hash
03 0x00000350 412 0x4652d350 412 -r-- ld-2.27.so..gnu.hash
04 0x000004f0 816 0x4652d4f0 816 -r-- ld-2.27.so..dynsym
05 0x00000820
              548 0x4652d820 548 -r-- ld-2.27.so..dynstr
06 0x00000a44
                68 0x4652da44
                                 68 -r-- 1d-2.27.so..gnu.version
                                164 -r-- ld-2.27.so..gnu.version_d
07 0x00000a88
              164 0x4652da88
08 0x00000b30 1152 0x4652db30 1152 -r-- ld-2.27.so..rela.dyn
09 0x00000fb0 11497 0x4652dfb0 11497 -r-x 1d-2.27.so..text
10 0x0001d0e0 17760 0x4654a0e0 17760 -r-- ld-2.27.so..rodata
11 0x00021640 1716 0x4654e640 1716 -r-- ld-2.27.so..eh_frame_hdr
12 0x00021cf8 9876 0x4654ecf8 9876 -r-- ld-2.27.so..eh_frame
13 0x00024660 2020 0x46751660 2020 -rw- ld-2.27.so..data.rel.ro
                               336 -rw- ld-2.27.so..dynamic
14 0x00024e48
              336 0x46751e48
15 0x00024f98
              96 0x46751f98
                               96 -rw- ld-2.27.so..got
16 0x00025000 3960 0x46752000 3960 -rw- ld-2.27.so..data
17 0x00025f78
                              376 -rw- ld-2.27.so..bss
              0 0x46752f80
                                 17 ---- ld-2.27.so..comment
18 0x00025f78
                17 0x00000000
                                 63 ---- ld-2.27.so..gnu.warning.llseek
19 0x00025fa0
                63 0x00000000
20 0x00025fe0 13272 0x00000000 13272 ---- ld-2.27.so..symtab
21 0x000293b8 7101 0x00000000 7101 --- ld-2.27.so..strtab
22 0x0002af75
               215 0x00000000
                                215 ---- ld-2.27.so..shstrtab
```

# Migration from ida, GDB or WinDBG

How to run the program using the debugger

```
r2 -d /bin/ls - start in debugger mode => [video]
```

How do I attach/detach to running process? (gdb -p)

```
r2 -d <pid> - attach to process
```

r2 ptrace://pid - same as above, but only for io (not debugger backend hooked)
[0x7fff6ad90028]> o-225 - close fd=225 (listed in o~[1]:0)
r2 -D gdb gdb://localhost:1234 - attach to gdbserver

# How to set args/environment variable/load a specific libraries for the debugging session of radare

Use rarun2 (libpath=PWD:/tmp/lib, arg2=hello, setenv=F00=BAR ...) see rarun2 -h / man rarun2

### How to script radare2?

r2 -i <scriptfile> ... - run a script after loading the file => [video]

r2 -I <scriptfile> ... - run a script before loading the file

r2 -c \$0 | awk \$0 - run through awk to get asm from function => [link]

[0x80480423]> . scriptfile - interpret this file => [video]

<code>[0x80480423]> #!c</code> - enter C repl (see #! to list all available RLang plugins) => [video], everything have to be done in a oneliner or a .c file must be passed as an argument.

To get #!python and much more, just build radare2-bindings

### How to list Source code as in gdb list?

CL @ sym.main - though the feature is highly experimental

### shortcuts

Command	IDA Pro	radare2	r2 (visual mode)	GDB	WinDbg
Analysis					
Analysis of everything	Automatical launched when opening a	(aaaa or -AA for even experimental	N/A	N/A	N/A
	binary	analysis)			
Navigation					
xref to	X	axt	X	N/A	N/A
xref from	ctrl + j	axf	X	N/A	N/A
xref to graph	?	agt [offset]	?	N/A	N/A
xref from graph	?	agf [offset]	?	N/A	N/A

Command	IDA Pro	radare2	r2 (visual mode)	GDB	WinDbg
list	alt + 1	afl;is	t	N/A	N/A
functions				,	,
listing	alt + 2	pdf	p	N/A	N/A
hex mode	alt + 3	pxa	P	N/A	N/A
imports	alt + 6	ii	:ii	N/A	N/A
exports	alt + 7	is~FUNC	?	N/A	N/A
follow	enter	s offset	enter or 0-9	N/A	N/A
$\mathrm{jmp/call}$					
undo seek	esc	s-	u	N/A	N/A
redo seek	ctrl+enter	s+	U	N/A	N/A
show graph	space	agv	V	N/A	N/A
$\mathbf{Edit}$					
rename	n	afn	dr	N/A	N/A
graph view	space	agv	V	N/A	N/A
define as	d	Cd [size]	$\mathtt{dd},\mathtt{db},\mathtt{dw},\mathtt{dW}$	N/A	N/A
data					
define as	С	C- [size]	d- or du	N/A	N/A
code					
define as	u	C- [size]	d- or du	N/A	N/A
undefined					
define as	A	Cs [size]	ds	N/A	N/A
string					
define as	Alt+Q	Cf [size]	dF	N/A	N/A
struct					
$\mathbf{Debugger}$					
Start	F9	dc	F9	r	g
Process/				and	
Continue				С	
execution					
Terminate	Ctrl+F2	dk 9	?	kill	q
Process			_		
Detach	?	0-	?	detac	h
step into	F7	ds	S	n	t
step into 4	?	ds 4	F7	n 4	t 4
instructions					
step over	F8	dso	S	s	p
step until a	?	dsu <addr></addr>	?	S	g
specific					<addr></addr>
address		_	0		_
Run until	Ctrl+F7	dcr	?	finis	hgu
return		W 2 4 2	W 2.40	37/4	37/1
Run until	F4	#249	#249	N/A	N/A
cursor					

Command	IDA Pro	radare2	r2 (visual mode)	GDB	WinDbg
Show Backtrace	?	dbt	?	bt	
display	On register	dr all	Shown in Visual	info	r
Register	Windows		$\operatorname{mode}$	regis	ters
display eax	On register	dr?eax	Shown in Visual	info	r
	Windows		mode	regis	t <b>eras</b> x
				eax	
display old state of all registers	?	dro	?	?	?
display function addr + N	?	afi \$\$ - display function information of current offset (\$\$)	?	?	?
display	?	pxw	?	i f	?
frame state		rbp-rsp@rsp			
How to step until condition is true	?	dsi	?	?	?
Update a register value	?	dr rip=0x456	?	set \$rip=	r 0 <b>x45<del>6</del>4</b> 56
Disassembly					
disassembly forward	N/A	pd	Vp	disas	uf, u
disassembly N instructions	N/A	pd X	Vp	x/i	u <addr> LX</addr>
disassembly N (backward) Information on the bin	N/A	pd -X	Vp	disas <a-o> <a></a></a-o>	ub
Sections/region	າກຟັ⇔ກາາ	iS or S	N/A	maint	!address
sections/regic	sections	(append j for json)	11/11	info sec- tions	.address

Load symbol file

	add- r symbol- file bt k
$\begin{array}{cccccccccccccccccccccccccccccccccccc$	
Stack Trace N/A dbtj N/A in Json Partial N/A dbt N/A Backtrace (dbg.btdepth	bt k
in Json Partial N/A dbt N/A Backtrace (dbg.btdepth	
Partial N/A dbt N/A Backtrace (dbg.btdepth	
Backtrace (dbg.btdepth	
( 9 1	bt k
(innermost) dbg.btalgo)	1.4
Partial N/A dbt N/A	bt -
Backtrace (dbg.btdepth	
$ \begin{array}{ccc} (outermost) & & dbg.btalgo) \\ Stacktrace & N/A & dbt@t & N/A \end{array} $	thread~*
for all	apply k
threads	all
	bt
Breakpoints	
Breakpoint Ctrl+Alt+B db ?	info bl
list	breakpoints
add F2 db [offset] F2	break bp
breakpoint	
Threads	
Switch to Thread dp N/A	thread~ <n>s</n>
thread menu	<n></n>
Frames Frame N/A ? N/A	any kn
Numbers : N/A	bt
TVIIIDOID	command
Select N/A ? N/A	frame .frame
Frame	
Parameters/Locals	
Display N/A afv $N/A$	info dv
parameters	args /t
	/i
7.4	<b>/</b> V
Display N/A afv N/A	info dv
parameters	locals/t
	/i /V
Display N/A afvj N/A	/V info dv
parame-	locals/t
ters/locals	/i
in json	/ V

Command	IDA Pro	radare2	r2 (visual mode)	GDB	WinDbg
list addresses where vars are ac- cessed(R/W) <b>Project</b>	N/A	afvR/afvW	N/A	?	?
Related					
open project		Po [file]		?	
save project show project in- formations	automatic	Ps [file] Pi [file]		?	
Miscellaneo	us				
Dump byte char array	N/A	pc? (json, C, char, etc.)	Vpppp	x/bc	db
options	option menu	e?	е		
search	search menu	/?	Select the zone with the cursor c then /		s

# Equivalent of "set-follow-fork-mode" gdb command

This can be done using 2 commands:

- 1. dcf until a fork happen
- 2. then use dp to select what process you want to debug.

# Common features

- r2 accepts FLIRT signatures
- r2 can connect to GDB, LLVM and WinDbg
- r2 can write/patch in place
- r2 have fortunes and [s]easter eggs[/s]balls of steel
- r2 can do basic loading of ELF core files from the box and MDMP (Windows minidumps)

# Registers

The registers are part of a user area stored in the context structure used by the scheduler. This structure can be manipulated to get and set the values of those

registers, and, for example, on Intel hosts, it is possible to directly manipulate DR0-DR7 hardware registers to set hardware breakpoints.

There are different commands to get values of registers. For the General Purpose ones use:

```
[0x4A13B8C0] > dr
r15 = 0x00000000
r14 = 0x00000000
r13 = 0x00000000
r12 = 0x00000000
rbp = 0x00000000
rbx = 0x00000000
r11 = 0x00000000
r10 = 0x00000000
r9 = 0x00000000
r8 = 0x00000000
rax = 0x00000000
rcx = 0x00000000
rdx = 0x00000000
rsi = 0x00000000
rdi = 0x00000000
oeax = 0x0000003b
rip = 0x7f20bf5df630
rsp = 0x7fff515923c0
[0x7f0f2dbae630] > dr rip ; get value of 'rip'
0x7f0f2dbae630
[0x4A13B8C0] > dr rip = esp
                            ; set 'rip' as esp
```

Interaction between a plugin and the core is done by commands returning radare instructions. This is used, for example, to set flags in the core to set values of registers.

```
[0x7f0f2dbae630]> dr* ; Appending '*' will show radare commands f r15 1 0x0 f r14 1 0x0 f r13 1 0x0 f r12 1 0x0 f rbp 1 0x0 f rbx 1 0x0 f r11 1 0x0 f r11 1 0x0 f r10 1 0x0 f r10 1 0x0 f r8 1 0x0 f rax 1 0x0 f rax 1 0x0 f rax 1 0x0 f rcx 1 0x0
```

```
f rdx 1 0x0
f rsi 1 0x0
f rdi 1 0x0
f oeax 1 0x3b
f rip 1 0x7fff73557940
f rflags 1 0x200
f rsp 1 0x7fff73557940
```

#### [0x4A13B8C0]> .dr\* ; include common register values in flags

An old copy of registers is stored all the time to keep track of the changes done during execution of a program being analyzed. This old copy can be accessed with oregs.

```
[0x7f1fab84c630] > dro
r15 = 0x00000000
r14 = 0x00000000
r13 = 0x00000000
r12 = 0x00000000
rbp = 0x00000000
rbx = 0x00000000
r11 = 0x00000000
r10 = 0x00000000
r9 = 0x00000000
r8 = 0x00000000
rax = 0x00000000
rcx = 0x00000000
rdx = 0x00000000
rsi = 0x00000000
rdi = 0x00000000
oeax = 0x0000003b
rip = 0x7f1fab84c630
rflags = 0x00000200
rsp = 0x7fff386b5080
```

Current state of registers

```
[0x7f1fab84c630]> dr
r15 = 0x00000000
r14 = 0x00000000
r13 = 0x00000000
r12 = 0x00000000
rbp = 0x00000000
rbx = 0x00000000
r11 = 0x00000000
r10 = 0x00000000
r9 = 0x00000000
```

```
rax = 0x00000000
rcx = 0x00000000
rdx = 0x00000000
rsi = 0x00000000
rdi = 0x7fff386b5080
oeax = 0xffffffffffffffff
rip = 0x7f1fab84c633
rflags = 0x00000202
rsp = 0x7fff386b5080
```

Values stored in eax, oeax and eip have changed.

To store and restore register values you can just dump the output of 'dr\*' command to disk and then re-interpret it again:

```
[0x4A13B8C0]> dr* > regs.saved ; save registers [0x4A13B8C0]> drp regs.saved ; restore
```

EFLAGS can be similarly altered. E.g., setting selected flags:

```
[0x4A13B8C0]> dr eflags = pst
[0x4A13B8C0]> dr eflags = azsti
```

You can get a string which represents latest changes of registers using drd command (diff registers):

```
[0x4A13B8C0]> drd

oeax = 0x0000003b was 0x00000000 delta 59

rip = 0x7f00e71282d0 was 0x00000000 delta -418217264

rflags = 0x00000200 was 0x00000000 delta 512

rsp = 0x7fffe85a09c0 was 0x00000000 delta -396752448
```

# Debugging with gdbserver

radare2 allows remote debugging over the gdb remote protocol. So you can run a gdbserver and connect to it with radare2 for remote debugging. The syntax for connecting is:

```
$ r2 -d gdb://<host>:<port>
```

Note that the following command does the same, r2 will use the debug plugin specified by the uri if found.

```
$ r2 -D gdb gdb://<host>:<port>
```

The debug plugin can be changed at runtime using the dL or Ld commands.

Or if the gdbserver is running in extended mode, you can attach to a process on the host with:

```
$ r2 -d gdb://<host>:<port>/<pid>
```

It is also possible to start debugging after analyzing a file using the **doof** command which rebases the current session's data after opening gdb

```
[0x00404870] > doof gdb://<host>:<port>/<pid>
```

After connecting, you can use the standard r2 debug commands as normal.

radare2 does not yet load symbols from gdbserver, so it needs the binary to be locally present to load symbols from it. In case symbols are not loaded even if the binary is present, you can try specifying the path with e dbg.exe.path:

```
$ r2 -e dbg.exe.path=<path> -d gdb://<host>:<port>
```

If symbols are loaded at an incorrect base address, you can try specifying the base address too with e bin.baddr:

```
$ r2 -e bin.baddr=<baddr> -e dbg.exe.path=<path> -d gdb://<host>:<port>
```

Usually the gdbserver reports the maximum packet size it supports. Otherwise, radare2 resorts to sensible defaults. But you can specify the maximum packet size with the environment variable R2\_GDB\_PKTSZ. You can also check and set the max packet size during a session with the IO system, =!.

```
$ export R2_GDB_PKTSZ=512
$ r2 -d gdb://<host>:<port>
= attach <pid> <tid>
Assuming filepath <path/to/exe>
[0x7ff659d9fcc0]> =!pktsz
packet size: 512 bytes
[0x7ff659d9fcc0]> =!pktsz 64
[0x7ff659d9fcc0]> =!pktsz
packet size: 64 bytes
```

The gdb IO system provides useful commands which might not fit into any standard radare2 commands. You can get a list of these commands with =!?. (Remember, =! accesses the underlying IO plugin's system()).

```
[0x7ff659d9fcc0] > = !?
Usage: =!cmd args
=!pid
                  - show targeted pid
=!pkt s
                 - send packet 's'
=!monitor cmd
                - hex-encode monitor command and pass to target interpreter
                  - show reverse debugging availability
=!rd
=!dsb
                  - step backwards
=!dcb
                  - continue backwards
=!detach [pid] - detach from remote/detach specific pid
=!inv.reg
                 - invalidate reg cache
=!pktsz
                - get max packet size used
=!pktsz bytes - set max. packet size as 'bytes' bytes
=!exec file [pid] - get file which was executed for current/specified pid
```

Note that <code>=!dsb</code> and <code>=!dcb</code> are only available in special gdbserver implementations such as Mozilla's rr, the default gdbserver doesn't include remote reverse debugging support. Use <code>=!rd</code> to print the currently available reverse debugging capabilities.

If you are interested in debugging radare2's interaction with gdbserver you can use =!monitor set remote-debug 1 to turn on logging of gdb's remote protocol packets in gdbserver's console and =!monitor set debug 1 to show general debug messages from gdbserver in it's console.

radare2 also provides its own gdbserver implementation:

And then connect to it like you would to any gdbserver. For example, with radare2:

```
$ r2 -d gdb://localhost:8000
```

# Remote Access Capabilities

Radare can be run locally, or it can be started as a server process which is controlled by a local radare2 process. This is possible because everything uses radare's IO subsystem which abstracts access to system(), cmd() and all basic IO operations so to work over a network.

Help for commands useful for remote access to radare:

```
[0x00405a04] > = ?
Usage: =[:!+-=ghH] [...]
                            # connect with other instances of r2
remote commands:
                                 list all open connections
| = < [fd]  cmd
                                 send output of local command to remote fd
| = [fd] cmd
                                 exec cmd at remote 'fd' (last open is default one)
| =! cmd
                                 run command via r_io_system
| =+ [proto://]host:port
                                 connect to remote host:port (*rap://, raps://, tcp://, udp://)
| = -[fd]
                                 remove all hosts or host 'fd'
| ==[fd]
                                 open remote session with host 'fd', 'q' to quit
```

```
| =!=
                                  disable remote cmd mode
| !=!
                                  enable remote cmd mode
servers:
1 .:9000
                                  start the tcp server (echo x|nc ::1 9090 or curl ::1:9090/cr
| =:port
                                  start the rap server (o rap://9999)
|=g[?]
                                  start the gdbserver
| =h[?]
                                  start the http webserver
| =H[?]
                                  start the http webserver (and launch the web browser)
other:
| =&:port
                                  start rap server in background (same as '&_=h')
                                  run 'cmd' command on remote server
| =:host:port cmd
examples:
| =+tcp://localhost:9090/
                                  connect to: r2 -c.:9090 ./bin
| =+rap://localhost:9090/
                                  connect to: r2 rap://:9090
| =+http://localhost:9090/cmd/ connect to: r2 -c'=h 9090' bin
| o rap://:9090/
                                  start the rap server on tcp port 9090
You can learn radare2 remote capabilities by displaying the list of supported IO
plugins: radare2 -L.
A little example should make this clearer. A typical remote session might look
like this:
At the remote host1:
$ radare2 rap://:1234
At the remote host2:
$ radare2 rap://:1234
At localhost:
$ radare2 -
Add hosts
[0x004048c5] > = + rap://<host1>:1234//bin/ls
Connected to: <host1> at port 1234
waiting... ok
[0x004048c5] > =
0 - rap://<host1>:1234//bin/ls
You can open remote files in debug mode (or using any IO plugin) specifying
URI when adding hosts:
[0x004048c5] > =+ =+ rap://<host2>:1234/dbg:///bin/ls
Connected to: <host2> at port 1234
```

```
waiting... ok
0 - rap://<host1>:1234//bin/ls
1 - rap://<host2>:1234/dbg:///bin/ls
To execute commands on host1:
[0x004048c5] > = 0 px
[0x004048c5] > = s 0x666
To open a session with host2:
[0x004048c5] > ==1
fd:6> pi 1
fd:6> q
To remove hosts (and close connections):
[0x004048c5] > = -
You can also redirect radare output to a TCP or UDP server (such as nc -1).
First, Add the server with '=+ tcp://' or '=+ udp://', then you can redirect
the output of a command to be sent to the server:
[0x004048c5] > =+ tcp://<host>:<port>/
Connected to: <host> at port <port>
5 - tcp://<host>:<port>/
```

The =< command will send the output from the execution of cmd to the remote connection number N (or the last one used if no id specified).

# Reverse Debugging

[0x004048c5] > = < 5 cmd...

Radare2 has reverse debugger, that can seek the program counter backward. (e.g. reverse-next, reverse-continue in gdb) Firstly you need to save program state at the point that you want to start recording. The syntax for recording is:

```
[0x004028a0] > dts+
```

You can use dts commands for recording and managing program states. After recording the states, you can seek pc back and forth to any points after saved address. So after recording, you can try single step back:

```
[0x004028a0]> 2dso
[0x004028a0]> dr rip
0x004028ae
[0x004028a0]> dsb
continue until 0x004028a2
hit breakpoint at: 4028a2
[0x004028a0]> dr rip
```

#### 0x004028a2

When you run dsb, reverse debugger restore previous recorded state and execute program from it until desired point.

Or you can also try continue back:

```
[0x004028a0] > db 0x004028a2
[0x004028a0] > 10dso
[0x004028a0] > dr rip
0x004028b9
[0x004028a0] > dcb
[0x004028a0] > dr rip
0x004028a2
```

dcb seeks program counter until hit the latest breakpoint. So once set a breakpoint, you can back to it any time.

You can see current recorded program states using dts:

```
[0x004028a0] > dts
session: 0 at:0x004028a0 ""
session: 1 at:0x004028c2 ""
```

NOTE: Program records can be saved at any moments. These are diff style format that save only different memory area from previous. It saves memory space rather than entire dump.

And also can add comment:

```
[0x004028c2]> dtsC 0 program start

[0x004028c2]> dtsC 1 decryption start

[0x004028c2]> dts

session: 0 at:0x004028a0 "program start"

session: 1 at:0x004028c2 "decryption start"
```

You can leave notes for each records to keep in your mind. dsb and dcb commands restore the program state from latest record if there are many records.

Program records can exported to file and of course import it. Export/Import records to/from file:

```
[0x004028c2]> dtst records_for_test
Session saved in records_for_test.session and dump in records_for_test.dump
[0x004028c2]> dtsf records_for_test
session: 0, 0x4028a0 diffs: 0
session: 1, 0x4028c2 diffs: 0
```

Moreover, you can do reverse debugging in ESIL mode. In ESIL mode, program state can be managed by aets commands.

```
[0x00404870] > aets+
```

And step back by aesb:

[0x00404870]> aer rip 0x00404870 [0x00404870]> 5aeso [0x00404870]> aer rip 0x0040487d [0x00404870]> aesb [0x00404870]> aer rip 0x00404879

In addition to the native reverse debugging capabilities in radare2, it's also possible to use gdb's remote protocol to reverse debug a target gdbserver that supports it. =!dsb and =!dcb are available as dsb and dcb replacementments for this purpose, see remote gdb's documentation for more information.

# WinDBG Kernel-mode Debugging (KD)

The WinDBG KD interface support for r2 allows you to attach to VM running Windows and debug its kernel over a serial port or network.

It is also possible to use the remote GDB interface to connect and debug Windows kernels without depending on Windows capabilities.

Bear in mind that WinDBG KD support is still work-in-progress, and this is just an initial implementation which will get better in time.

# Setting Up KD on Windows

For a complete walkthrough, refer to Microsoft's documentation.

#### Serial Port

```
Enable KD over a serial port on Windows Vista and higher like this:
```

```
bcdedit /debug on
bcdedit /dbgsettings serial debugport:1 baudrate:115200
```

Or like this for Windows XP: Open boot.ini and add /debug /debugport=COM1 /baudrate=115200:

```
[boot loader]
timeout=30
default=multi(0)disk(0)rdisk(0)partition(1)\WINDOWS
[operating systems]
multi(0)disk(0)rdisk(0)partition(1)\WINDOWS="Debugging with Cable" /fastdetect /debug /debug
```

uniti(0)disk(0)fdisk(0)partition(1) \windows- bedugging with cable /lastdetect /debug /de

In case of VMWare

```
Virtual Machine Settings -> Add -> Serial Port
   Device Status:
    [v] Connect at power on
    Connection:
    [v] Use socket (named pipe)
    [_/tmp/winkd.pipe____]
    From: Server To: Virtual Machine
Configure the VirtualBox Machine like this:
   Preferences -> Serial Ports -> Port 1
    [v] Enable Serial Port
   Port Number: [_COM1____[v]]
   Port Mode: [ Host Pipe [v]]
                 [v] Create Pipe
    Port/File Path: [_/tmp/winkd.pipe____]
Or just spawn the VM with qemu like this:
$ qemu-system-x86_64 -chardev socket,id=serial0,\
     path=/tmp/winkd.pipe,nowait,server \
     -serial chardev:serialO -hda Windows7-VM.vdi
```

#### Network

Enable KD over network (KDNet) on Windows 7 or later likes this:

```
bcdedit /debug on
bcdedit /dbgsettings net hostip:w.x.y.z port:n
```

Starting from Windows 8 there is no way to enforce debugging for every boot, but it is possible to always show the advanced boot options, which allows to enable kernel debugging:

bcedit /set {globalsettings} advancedoptions true

# Connecting to KD interface on r2

#### Serial Port

Radare2 will use the winkd io plugin to connect to a socket file created by virtualbox or qemu. Also, the winkd debugger plugin and we should specify the x86-32 too. (32 and 64 bit debugging is supported)

```
$ r2 -a x86 -b 32 -D winkd winkd:///tmp/winkd.pipe
On Windows you should run the following line:
```

\$ radare2 -D winkd winkd://\\.\pipe\com\_1

#### Network

```
$ r2 -a x86 -b 32 -d winkd://<hostip>:<port>:w.x.y.z
```

#### Using KD

When connecting to a KD interface, r2 will send a breakin packet to interrupt the target and we will get stuck here:

```
[0x828997b8] > pd 20
    ;-- eip:
    0x828997b8
                                 int3
    0x828997b9
                   c20400
                                ret 4
    0x828997bc
                   СС
                                 int3
    0x828997bd
                   90
                                nop
    0x828997be
                   сЗ
                                 ret
    0x828997bf
                   90
                                nop
```

In order to skip that trap we will need to change eip and run 'dc' twice:

```
dr eip=eip+1
dc
dr eip=eip+1
dc
```

Now the Windows VM will be interactive again. We will need to kill r2 and attach again to get back to control the kernel.

In addition, the dp command can be used to list all processes, and dpa or dp= to attach to the process. This will display the base address of the process in the physical memory layout.

# WinDBG Backend for Windows (DbgEng)

On Windows, radare2 can use DbgEng.dll as a debugging backend, allowing it to make use of WinDBG's capabilities, supporting dump files, local and remote user and kernel mode debugging.

You can use the debugging DLLs included on Windows or get the latest version from Microsoft's download page (recommended).

You cannot use DLLs from the Microsoft Store's WinDbg Preview app folder directly as they are not marked as executable for normal users.

 $radare 2\ will\ try\ to\ load\ {\tt dbgeng.dll}\ from\ the\ {\tt \_NT\_DEBUGGER\_EXTENSION\_PATH}\ environment\ variable\ before\ using\ Windows'\ default\ library\ search\ path.$ 

### Using the plugin

To use the windbg plugin, pass the same command-line options as you would for WinDBG or kd (see Microsoft's documentation), quoting/escaping when necessary:

```
> r2 -d "windbg://-remote tcp:server=Server,port=Socket"
> r2 -d "windbg://MyProgram.exe \"my arg\""
> r2 -d "windbg://-k net:port=<n>,key=<MyKey>"
> r2 -d "windbg://-z MyDumpFile.dmp"
```

You can then debug normally (see d? command) or interact with the backend shell directly with the =! command:

```
[0x7ffcac9fcea0]> dcu 0x0007ffc98f42190

Continue until 0x7ffc98f42190 using 1 bpsize

ModLoad: 00007ffc`ab6b0000 00007ffc`ab6e0000 C:\WINDOWS\System32\IMM32.DLL

Breakpoint 1 hit
```

hit breakpoint at: 0x7ffc98f42190

```
[0x7fffcf232190]> =!k4
Child-SP RetAddr Call Site
00000033`73b1f618 00007ff6`c67a861d r_main!r_main_radare2
00000033`73b1f620 00007ff6`c67d0019 radare2!main+0x8d
00000033`73b1f720 00007ff6`c67cfebe radare2!invoke_main+0x39
00000033`73b1f770 00007ff6`c67cfd7e radare2!__scrt_common_main_seh+0x12e
```

# Windows Messages

On Windows, you can use dbw while debugging to set a breakpoint for the message handler of a specific window.

Get a list of the current process windows with dW:

#### [0x7ffe885c1164] > dW

Ξ.								_
·		-				-	Class Name	   
1   1	0x0023038e 0x0029049e 0x002c048a		9432 9432 9432 9432	 	22432 22432 22432 22432	     	MSCTFIME UI IME Edit msctls_statusbar32	
٦.								- '

Set the breakpoint with a message type, together with either the window class name or its handle:

```
[0x7ffe885c1164]> dbW WM_KEYDOWN Edit Breakpoint set.
```

Or

[0x7ffe885c1164]> dbW WM\_KEYDOWN 0x002c048a Breakpoint set.

If you aren't sure which window you should put a breakpoint on, use dWi to identify it with your mouse:

# Adding Metadata to Disassembly

The typical work involved in reversing binary files makes powerful annotation capabilities essential. Radare offers multiple ways to store and retrieve such metadata.

By following common basic UNIX principles, it is easy to write a small utility in a scripting language which uses objdump, otool or any other existing utility to obtain information from a binary and to import it into radare. For example, take a look at idc2r.py shipped with radare2ida. To use it, invoke it as idc2r.py file.idc > file.r2. It reads an IDC file exported from an IDA Pro database and produces an r2 script containing the same comments, names of functions and other data. You can import the resulting 'file.r2' by using the dot . command of radare:

```
[0x00000000]> . file.r2
```

The . command is used to interpret Radare commands from external sources, including files and program output. For example, to omit generation of an intermediate file and import the script directly you can use this combination:

```
[0x00000000] > .!idc2r.py < file.idc
```

Please keep in mind that importing IDA Pro metadata from IDC dump is deprecated mechanism and might not work in the future. The recommended way to do it - use python-idb-based ida2r2.py which opens IDB files directly without IDA Pro installed.

The C command is used to manage comments and data conversions. You can define a range of program's bytes to be interpreted as either code, binary data or string. It is also possible to execute external code at every specified flag location

in order to fetch some metadata, such as a comment, from an external file or database

There are many different metadata manipulation commands, here is the glimpse of all of them:

```
[0x00404cc0] > C?
| Usage: C[-LCvsdfm*?][*?] [...]
                                   # Metadata management
I C
                                                  list meta info in human friendly form
| C*
                                                  list meta info in r2 commands
| C*.
                                                  list meta info of current offset in r2 com
| C- [len] [[@]addr]
                                                  delete metadata at given address range
                                                  list meta info of current offset in human
| C.
| CC! [@addr]
                                                  edit comment with $EDITOR
| CC[?] [-] [comment-text] [@addr]
                                                  add/remove comment
| CC. [addr]
                                                  show comment in current address
| CCa[-at]|[at] [text] [@addr]
                                                  add/remove comment at given address
| CCu [comment-text] [@addr]
                                                  add unique comment
| CF[sz] [fcn-sign..] [@addr]
                                                  function signature
| CL[-][*] [file:line] [addr]
                                                  show or add 'code line' information (bining
| CS[-][space]
                                                  manage meta-spaces to filter comments, etc
| C[Cthsdmf]
                                                  list comments/types/hidden/strings/data/mag
| C[Cthsdmf]*
                                                  list comments/types/hidden/strings/data/mag
| Cd[-] [size] [repeat] [@addr]
                                                  hexdump data array (Cd 4 10 == dword [10])
| Cd. [@addr]
                                                  show size of data at current address
| Cf[?][-] [sz] [0|cnt][fmt] [a0 a1...] [@addr]
                                                  format memory (see pf?)
| Ch[-] [size] [@addr]
                                                  hide data
| Cm[-] [sz] [fmt..] [@addr]
                                                  magic parse (see pm?)
| Cs[?] [-] [size] [@addr]
                                                  add string
| Ct[?] [-] [comment-text] [@addr]
                                                  add/remove type analysis comment
| Ct.[@addr]
                                                  show comment at current or specified address
| Cv[bsr][?]
                                                  add comments to args
| Cz[@addr]
                                                  add string (see Cs?)
```

Simply to add the comment to a particular line/address you can use Ca command:

```
[0x00000000]> CCa 0x0000002 this guy seems legit
[0x00000000]> pd 2
0x00000000 0000 add [rax], al
; this guy seems legit
0x000000002 0000 add [rax], al
```

The C? family of commands lets you mark a range as one of several kinds of types. Three basic types are: code (disassembly is done using asm.arch), data (an array of data elements) or string. Use the Cs command to define a string, use the Cd command for defining an array of data elements, and use the Cf command to define more complex data structures like structs.

Annotating data types is most easily done in visual mode, using the "d" key,

short for "data type change". First, use the cursor to select a range of bytes (press c key to toggle cursor mode and use HJKL keys to expand selection), then press 'd' to get a menu of possible actions/types. For example, to mark the range as a string, use the 's' option from the menu. You can achieve the same result from the shell using the Cs command:

```
[0x00000000]> f string_foo @ 0x800
[0x00000000]> Cs 10 @ string_foo
```

The Cf command is used to define a memory format string (the same syntax used by the pf command). Here's an example:

```
[0x7fd9f13ae630] > Cf 16 2xi foo bar
[0x7fd9f13ae630] > pd
;-- rip:
0x7fd9f13ae630 format 2xi foo bar {
0x7fd9f13ae630 [0] {
 foo : 0x7fd9f13ae630 = 0xe8e78948
bar : 0x7fd9f13ae634 = 14696
0x7fd9f13ae638 [1] {
 foo : 0x7fd9f13ae638 = 0x8bc48949
 bar : 0x7fd9f13ae63c = 571928325
}
} 16
0x7fd9f13ae633
                  e868390000
                                call 0x7fd9f13b1fa0
0x7fd9f13ae638
                  4989c4
                               mov r12, rax
```

The [sz] argument to Cf is used to define how many bytes the struct should take up in the disassembly, and is completely independent from the size of the data structure defined by the format string. This may seem confusing, but has several uses. For example, you may want to see the formatted structure displayed in the disassembly, but still have those locations be visible as offsets and with raw bytes. Sometimes, you find large structures, but only identified a few fields, or only interested in specific fields. Then, you can tell r2 to display only those fields, using the format string and using 'skip' fields, and also have the disassembly continue after the entire structure, by giving it full size using the sz argument.

Using Cf, it's easy to define complex structures with simple oneliners. See pf? for more information. Remember that all these C commands can also be accessed from the visual mode by pressing the d (data conversion) key. Note that unlike t commands Cf doesn't change analysis results. It is only a visual boon.

Sometimes just adding a single line of comments is not enough, in this case radare2 allows you to create a link for a particular text file. You can use it with CC, command or by pressing, key in the visual mode. This will open an \$EDITOR to create a new file, or if filename does exist, just will create a link. It will be shown in the disassembly comments:

```
[0x00003af7 11% 290 /bin/ls]> pd $r @ main+55 # 0x3af7

|0x00003af7 call sym.imp.setlocale ; [1] ; ,(locale-help.txt) ; char *setlocale(int of lox00003afc lea rsi, str.usr_share_locale ; 0x179cc ; "/usr/share/locale"

|0x00003b03 lea rdi, [0x000179b2] ; "coreutils"

|0x00003b0a call sym.imp.bindtextdomain ; [2] ; char *bindtextdomain(char *domainname, characteristics)
```

Note ,(locale-help.txt) appeared in the comments, if we press , again in the visual mode, it will open the file. Using this mechanism we can create a long descriptions of some particular places in disassembly, link datasheets or related articles.

## **ESIL**

ESIL stands for 'Evaluable Strings Intermediate Language'. It aims to describe a Forth-like representation for every target CPU opcode semantics. ESIL representations can be evaluated (interpreted) in order to emulate individual instructions. Each command of an ESIL expression is separated by a comma. Its virtual machine can be described as this:

```
while ((word=haveCommand())) {
  if (word.isOperator()) {
    esilOperators[word](esil);
} else {
    esil.push (word);
}
  nextCommand();
}
```

As we can see ESIL uses a stack-based interpreter similar to what is commonly used for calculators. You have two categories of inputs: values and operators. A value simply gets pushed on the stack, an operator then pops values (its arguments if you will) off the stack, performs its operation and pushes its results (if any) back on. We can think of ESIL as a post-fix notation of the operations we want to do.

So let's see an example:

```
4, esp, -=, ebp, esp, = [4]
```

Can you guess what this is? If we take this post-fix notation and transform it back to in-fix we get

```
esp -= 4
4bytes(dword) [esp] = ebp
```

We can see that this corresponds to the x86 instruction push ebp! Isn't that cool? The aim is to be able to express most of the common operations performed by CPUs, like binary arithmetic operations, memory loads and stores, processing syscalls. This way if we can transform the instructions to ESIL we can see what

a program does while it is running even for the most cryptic architectures you definitely don't have a device to debug on for.

## Using ESIL

r2's visual mode is great to inspect the ESIL evaluations.

There are 3 environment variables that are important for watching what a program does:

```
[0x00000000] > e emu.str = true
```

asm.emu tells r2 if you want ESIL information to be displayed. If it is set to true, you will see comments appear to the right of your disassembly that tell you how the contents of registers and memory addresses are changed by the current instruction. For example, if you have an instruction that subtracts a value from a register it tells you what the value was before and what it becomes after. This is super useful so you don't have to sit there yourself and track which value goes where.

One problem with this is that it is a lot of information to take in at once and sometimes you simply don't need it. r2 has a nice compromise for this. That is what the emu.str variable is for (asm.emustr on <= 2.2). Instead of this super verbose output with every register value, this only adds really useful information to the output, e.g., strings that are found at addresses a program uses or whether a jump is likely to be taken or not.

The third important variable is asm.esil. This switches your disassembly to no longer show you the actual disassembled instructions, but instead now shows you corresponding ESIL expressions that describe what the instruction does. So if you want to take a look at how instructions are expressed in ESIL simply set "asm.esil" to true.

```
[0x00000000] e asm.esil = true
```

In visual mode you can also toggle this by simply typing 0.

### **ESIL Commands**

• "ae" : Evaluate ESIL expression.

```
[0x00000000]> "ae 1,1,+"
0x2
[0x00000000]>
```

• "aes": ESIL Step.

[0x00000000] > aes [0x00000000] > 10aes

• "aeso" : ESIL Step Over.

[0x00000000] > aeso [0x00000000] > 10aeso

• "aesu": ESIL Step Until.

[0x00001000]> aesu 0x1035 ADDR BREAK [0x00001019]>

• "ar": Show/modify ESIL registry.

[0x00001ec7]> ar r\_00 = 0x1035 [0x00001ec7]> ar r\_00 0x00001035 [0x00001019]>

#### **ESIL** Instruction Set

Here is the complete instruction set used by the ESIL VM:

ESIL Opcode	Operands	Name	Operation	example
TRAP	src	Trap	Trap signal	

\*\* |src|Interrupt|interrupt|0x80, ()\*\* | src | Syscall | syscall | rax,() \$\$ | src | Instruction address | Get address of current instructionstack=instruction address == | src, dst | Compare | stack = (dst == src) ; update | selfags(dst - src) | < |src,dst | Smaller (signed comparison) | stack = (dst < src); update eflags(dst src) | [0x00000000]> "ae 1,5,<" 0x0> "ae 5,5"0x0" <= | src,dst | Smaller or Equal (signed comparison) |  $stack = (dst \le src)$ ; update\_eflags(dst - src) | [0x00000000] > "ae 1,5,<" 0x0 > "ae 5,5"0x1" > | src,dst | Bigger (signed) |comparison) | stack = (dst > src); update\_eflags(dst - src) | > "ae 1,5,>"0x1> "ae 5,5,>"0x0 >= | src,dst | Bigger or Equal (signed comparison) | stack = (dst >= src); update\_eflags(dst - src) | > "ae 1,5,>="0x1> "ae 5,5,>="0x1 « | src,dst | Shift Left | stack = dst « src | > "ae 1,1,«"0x2> "ae 2,1,«"0x4 » | src,dst | Shift Right | stack = dst » src | > "ae 1,4, $\rangle$ " 0x2> "ae 2,4, $\rangle$ " 0x1 «< | src,dst | Rotate Left | stack=dst ROL src | > "ae 31,1, << "0x80000000> "ae 32,1, << "0x1 »> | src,dst | Rotate Right | stack=dst ROR src | > "ae 1,1,"> "0x80000000> "ae 32,1,">"0x1 & | src,dst | AND | stack = dst & src | > "ae 1,1,&"0x1> "ae 1,0,& "0x0> "ae 0,1,&"0x0> "ae 0,0,&"0x0 | | src,dst | OR | stack = dst | src | > "ae 1,1,|"0x1> "ae 1,0,|"0x1> "ae 0,1,|"0x1> "ae 0,0,|"0x0 ^ | src,dst | XOR |  $stack = dst \ src \ | \ = (1,1,\ 0x0) = (ae 1,0,\ 0x1) = (ae 0,1,\ 0x1) = (ae 0,0,\ 0x0)$ + | src, dst | ADD | stack = dst + src | > "ae 3,4,+"0x7> "ae 5,5,+"0xa- | src,dst | SUB | stack = dst - src | > "ae 3,4,-"0x1> "ae 5,5,-"0x0> "ae 4,3,-"0xfffffffffffff \* | src,dst | MUL | stack = dst \* src | > "ae 3,4,\*"0xc> "ae 5.5,\*"0x19 / | src,dst | DIV | stack = dst / src | > "ae 2.4,/"0x2> "ae 5.5,/"0x1> "ae 5.9./"0x1 % | src,dst | MOD | stack = dst % src | > "ae 2.4.%"0x0> "ae 5.5.%"0x0> "ae 5.9.%"0x4 ~ | bits,src | SIGNEXT | stack = src sign extended |

> "ae 8,0x80,~"0xffffffffffff80 ~/ | src,dst | SIGNED DIV | stack = dst / src (signed) | > "ae 2,-4, $\sim$ /"0xfffffffffffffe  $\sim$ % | src,dst | SIGNED MOD | stack = > "ae 1,!"0x0> "ae 4,!"0x0> "ae 0,!"0x1 ++ | src | INC | stack = src++ | > arr 00=0; arr 000x000000000> "aer 00,++"0x1> arr 000x000000000> "ae $r_0,-"0x4> ar r_000x00000005> "ae 5,-"0x4 = | src,reg | EQU | reg = src | > |$ "ae 3,r 00,="> aer r 000x00000003> "ae r 00,r 01,="> aer r 010x00000003 := | src,reg | weak EQU | reg = src without side effects | > "ae 3,r 00,:="> aer r 000x00000003 > "ae r 00,r 01,:=" > aer r 010x00000003 += | src,reg |ADD eq | reg = reg + src | > ar r 01=5; ar r 00=0; ar r 000x000000000> "ae  $r_01,r_00,+=$ "> ar  $r_000x00000005$ > "ae  $5,r_00,+=$ "> ar  $r_000x000000000$  -= "ae 3,r 00,-="> ar r 000x00000001 \*= | src,reg | MUL eq | reg = reg \* eq | reg = reg / src | > ar r\_01=3;ar r\_00=6;ar r\_000x00000006> "ae r 01,r 00,/="> ar r 000x00000002> "ae 1,r 00,/="> ar r 000x00000002% | src,reg | MOD eq | reg = reg % src | > ar r\_01=3; ar r\_00=7; ar r\_00 0x00000007 > "ae r 01,r 00,%=" > ar r 00 0x00000001 > ar r 00=9;arr 00 0x00000009 > "ae 5,r 00,%=" > ar r 00 0x00000004  $\ll$  | src,reg | Shift Left eq | reg = reg « src | > ar r 00=1; ar r 01=1; ar r 010x00000001> "ae r 00,r 01, ="> ar r 010x00000002> "ae 2,r 01, ="> ar r 010x00000008»= | src,reg | Shift Right eq | reg = reg « src | > ar r 00=1;ar r 01=8;ar r 010x00000008 "ae r 00, r 01, ="> ar r 010x00000004 "ae 2, r 01, ="> ar r 010x00000001 & = | src, reg | AND eq | reg = reg & src | > ar r <math>00=2; ar $r_01=6; ar r_010x00000006>$  "ae  $r_00,r_01,&=$ "> ar  $r_010x000000002>$  "ae  $2,r_01,\&=$ "> ar  $r_010x000000002$ > "ae  $1,r_01,\&=$ "> ar  $r_010x000000000$  |= |  $src,reg \mid OR \ eq \mid reg = reg \mid src \mid > ar \ r_00=2; ar \ r_01=1; ar \ r_010x00000001>$ "ae r\_00,r\_01,|="> ar r\_010x00000003> "ae 4,r\_01,|="> ar r\_010x00000007 ^= | src,reg | XOR eq | reg = reg ^ src | > ar r\_00=2;ar r\_01=0xab;ar r 010x000000ab> "ae r 00,r 01,^="> ar r 010x000000a9> "ae 2,r 01,^="> ar r 010x000000ab ++= | reg | INC eq | reg = reg + 1 | > ar r 00=4; arr = 000x00000004 > "ae r = 00, ++=" > ar r = 000x00000005 -= |reg| DEC eq |reg| $= \text{reg - 1} \mid > \text{ar r} \quad 00 = 4; \text{ar r} \quad 000 \times 000000004 > \text{"ae r} \quad 00, -=\text{"} > \text{ar r} \quad 000 \times 000000003$  $!= | reg | NOT eq | reg = !reg | > ar r_00=4; ar r_000x000000004> "ae$ r = 00,!="> ar r = 000x000000000> "ae r = 00,!="> ar r = 000x00000001 -- |--|\_ | \_ | \_ --=[]=[\*]=[1]=[2]=[4]=[8] | src,dst |poke |\*dst=src | > "ae 0xdeadbeef,0x10000,=[4],"> pxw 4@0x100000x00010000 0xdeadbeef ....> "ae 0x0,0x10000,=[4],"> pxw 4@0x100000x000100000x000000000 [[[\*][1][2][4][8] | src | peek | stack=\*src | > w test@0x10000> "ae 0x10000,[4],"0x74736574> ar  $r_00=0x10000$ > "ae  $r_00,[4]$ ,"0x74736574|=[1]=[1]|=[2]|=[4]|=[8] | reg | nombre | code | > SWAP | | Swap | Swap two top elements | SWAP DUP | | Duplicate | Duplicate top element in stack | DUP NUM | Numeric | If top element is a reference (register name, label, etc), dereference it and push its real value | NUM CLEAR | | Clear | Clear stack |

CLEAR BREAK | | Break | Stops ESIL emulation | BREAK GOTO | n | Goto | Jumps to Nth ESIL word | GOTO 5 TODO | | To Do | Stops execution (reason: ESIL expression not completed) | TODO

## ESIL Flags

js

ESIL VM provides by default a set of helper operations for calculating flags. They fulfill their purpose by comparing the old and the new value of the dst operand of the last performed eq-operation. On every eq-operation (e.g. =) ESIL saves the old and new value of the dst operand. Note, that there also exist weak eq operations (e.g. :=), which do not affect flag operations. The == operation affects flag operations, despite not being an eq operation. Flag operations are prefixed with \$ character.

```
- zero flag, only set if the result of an operation is 0
b
       - borrow, this requires to specify from which bit (example: 4,$b - checks if borrow:
       - carry, same like above (example: 7,$c - checks if carry from bit 7)
С
0
       - overflow
       - parity
р
       - regsize (asm.bits/8)
r
s
       - sign
ds
       - delay slot state
       - jump target
jt
```

## Syntax and Commands

- jump target set

A target opcode is translated into a comma separated list of ESIL expressions.

```
xor eax, eax -> 0,eax,=,1,zf,=
```

Memory access is defined by brackets operation:

```
mov eax, [0x80480] -> 0x80480,[],eax,=
```

Default operand size is determined by size of operation destination.

```
movb $0, 0x80480 \rightarrow 0,0x80480,=[1]
```

The ? operator uses the value of its argument to decide whether to evaluate the expression in curly braces.

- 1. Is the value zero? -> Skip it.
- 2. Is the value non-zero? -> Evaluate it.

```
cmp eax, 123 -> 123,eax,==,$z,zf,=
jz eax -> zf,?{,eax,eip,=,}
```

If you want to run several expressions under a conditional, put them in curly braces:

```
zf,?{,eip,esp,=[],eax,eip,=,$r,esp,-=,}
```

Whitespaces, newlines and other chars are ignored. So the first thing when processing a ESIL program is to remove spaces:

```
esil = r_str_replace (esil, " ", "", R_TRUE);
```

Syscalls need special treatment. They are indicated by '\$' at the beginning of an expression. You can pass an optional numeric value to specify a number of syscall. An ESIL emulator must handle syscalls. See (r\_esil\_syscall).

## **Arguments Order for Non-associative Operations**

As discussed on IRC, the current implementation works like this:

```
a,b,- b-a a,b,/= b/=a
```

This approach is more readable, but it is less stack-friendly.

### Special Instructions

NOPs are represented as empty strings. As it was said previously, interrupts are marked by "command.Forexample," 0x80,". It delegates emulation from the ESIL machine to a callback which implements interrupt handler for a specific OS/kernel/platform.

Traps are implemented with the TRAP command. They are used to throw exceptions for invalid instructions, division by zero, memory read error, or any other needed by specific architectures.

### **Quick Analysis**

Here is a list of some quick checks to retrieve information from an ESIL string. Relevant information will be probably found in the first expression of the list.

```
indexOf('[')
               -> have memory references
indexOf("=[")
               -> write in memory
indexOf("pc,=") -> modifies program counter (branch, jump, call)
indexOf("sp,=") -> modifies the stack (what if we found sp+= or sp-=?)
               -> retrieve src and dst
indexOf("=")
               -> unknown esil, raw opcode ahead
indexOf(":")
indexOf("$")
               -> accesses internal esil vm flags ex: $z
indexOf("$")
               -> syscall ex: 1,$
indexOf("TRAP") -> can trap
indexOf('++')
               -> has iterator
indexOf('--')
               -> count to zero
indexOf("?{")
               -> conditional
equalsTo("")
               -> empty string, aka nop (wrong, if we append pc+=x)
```

Common operations: \* Check dstreg \* Check srcreg \* Get destinaion \* Is jump \* Is conditional \* Evaluate \* Is syscall

## **CPU Flags**

CPU flags are usually defined as single bit registers in the RReg profile. They are sometimes found under the 'flg' register type.

### Variables

Properties of the VM variables:

- 1. They have no predefined bit width. This way it should be easy to extend them to 128, 256 and 512 bits later, e.g. for MMX, SSE, AVX, Neon SIMD.
- 2. There can be unbound number of variables. It is done for SSA-form compatibility.
- 3. Register names have no specific syntax. They are just strings.
- 4. Numbers can be specified in any base supported by RNum (dec, hex, oct, binary ...).
- 5. Each ESIL backend should have an associated RReg profile to describe the ESIL register specs.

## Bit Arrays

What to do with them? What about bit arithmetics if use variables instead of registers?

### Arithmetics

- 1. ADD ("+")
- 2. MUL ("\*")
- 3. SUB ("-")
- 4. DIV ("/")
- 5. MOD ("%")

### Bit Arithmetics

- 1. AND "&"
- 2. OR "|"
- 3. XOR "^"
- 4. SHL "«"
- 5. SHR "»"
- 6. ROL "«<"
- 7. ROR "»>"
- 8. NEG "!"

## Floating Point Unit Support

At the moment of this writing, ESIL does not yet support FPU. But you can implement support for unsupported instructions using r2pipe. Eventually we will get proper support for multimedia and floating point.

## Handling x86 REP Prefix in ESIL

ESIL specifies that the parsing control-flow commands must be uppercase. Bear in mind that some architectures have uppercase register names. The corresponding register profile should take care not to reuse any of the following:

```
3,SKIP - skip N instructions. used to make relative forward GOTOs
3,GOTO - goto instruction 3

LOOP - alias for 0,GOTO

BREAK - stop evaluating the expression

STACK - dump stack contents to screen

CLEAR - clear stack
```

### Usage Example: rep cmpsb

```
cx,!,?{,BREAK,},esi,[1],edi,[1],==,?{,BREAK,},esi,++,edi,++,cx,--,0,GOTO
```

## Unimplemented/Unhandled Instructions

Those are expressed with the 'TODO' command. They act as a 'BREAK', but displays a warning message describing that an instruction is not implemented and will not be emulated. For example:

```
fmulp ST(1), ST(0) \Rightarrow TODO, fmulp ST(1), ST(0)
```

## ESIL Disassembly Example:

```
[0x1000010f8] > e asm.esil=true
[0x1000010f8] > pd $r @ entry0
0x1000010f8
               55
                             8,rsp,-=,rbp,rsp,=[8]
0x1000010f9
               4889e5
                             rsp,rbp,=
0x1000010fc
               4883c768
                             104, rdi, +=
0x100001100
               4883c668
                             104,rsi,+=
0x100001104
               5d
                             rsp,[8],rbp,=,8,rsp,+=
0x100001105
               e950350000
                             0x465a,rip,=;[1]
                             8,rsp,-=,rbp,rsp,=[8]
0x10000110a
               55
0x10000110b
               4889e5
                             rsp,rbp,=
0x10000110e
               488d4668
                             rsi,104,+,rax,=
0x100001112
               488d7768
                             rdi,104,+,rsi,=
0x100001116
               4889c7
                             rax,rdi,=
0x100001119
                             rsp,[8],rbp,=,8,rsp,+=
0x10000111a
                             0x465a,rip,=;[1]
               e93b350000
```

```
8, rsp, -=, rbp, rsp, = [8]
0x10000111f
               55
0x100001120
               4889e5
                             rsp,rbp,=
0x100001123
               488b4f60
                             rdi,96,+,[8],rcx,=
                             rcx,48,+,[8],r8,=
0x100001127
               4c8b4130
0x10000112b
               488b5660
                             rsi,96,+,[8],rdx,=
0x10000112f
                             1,eax,=
               b801000000
               4c394230
                             rdx,48,+,[8],r8,==,cz,?=
0x100001134
                             sf,of,!,^,zf,!,&,?{,0x1154,rip,=,};[2]
0x100001138
               7f1a
                             of,!,sf,^,?{,0x1143,rip,};[3]
0x10000113a
               7d07
                             Oxffffffff,eax,= ; Oxffffffff
0x10000113c
               b8fffffff
0x100001141
               eb11
                             0x1154,rip,=;[2]
                             rcx,56,+,[8],rcx,=
0x100001143
               488b4938
                             rdx,56,+,[8],rcx,==,cz,?=
0x100001147
               48394a38
```

### Introspection

To ease ESIL parsing we should have a way to express introspection expressions to extract the data that we want. For example, we may want to get the target address of a jump. The parser for ESIL expressions should offer an API to make it possible to extract information by analyzing the expressions easily.

```
> ao~esil,opcode
opcode: jmp 0x10000465a
esil: 0x10000465a,rip,=
```

We need a way to retrieve the numeric value of 'rip'. This is a very simple example, but there are more complex, like conditional ones. We need expressions to be able to get:

- opcode type
- destination of a jump
- condition depends on
- all regs modified (write)
- all regs accessed (read)

#### API HOOKS

It is important for emulation to be able to setup hooks in the parser, so we can extend it to implement analysis without having to change it again and again. That is, every time an operation is about to be executed, a user hook is called. It can be used for example to determine if RIP is going to change, or if the instruction updates the stack. Later, we can split that callback into several ones to have an event-based analysis API that may be extended in JavaScript like this:

```
esil.on('regset', function(){..
esil.on('syscall', function(){esil.regset('rip'
```

For the API, see the functions hook\_flag\_read(), hook\_execute() and hook\_mem\_read(). A callback should return true or 1 if you want to override the action that it takes. For example, to deny memory reads in a region, or voiding memory writes, effectively making it read-only. Return false or 0 if you want to trace ESIL expression parsing.

Other operations require bindings to external functionalities to work. In this case, r\_ref and r\_io. This must be defined when initializing the ESIL VM.

```
Io Get/Set
Out ax, 44
44,ax,:ou
Selectors (cs,ds,gs...)
Mov eax, ds: [ebp+8]
Ebp,8,+,:ds,eax,=
```

# Disassembling

Disassembling in radare is just a way to represent an array of bytes. It is handled as a special print mode within p command.

In the old times, when the radare core was smaller, the disassembler was handled by an external rsc file. That is, radare first dumped current block into a file, and then simply called objdump configured to disassemble for Intel, ARM or other supported architectures.

It was a working and unix friendly solution, but it was inefficient as it repeated the same expensive actions over and over, because there were no caches. As a result, scrolling was terribly slow.

So there was a need to create a generic disassembler library to support multiple plugins for different architectures. We can list the current loaded plugins with

```
$ rasm2 -L
```

Or from inside radare2:

```
> e asm.arch=??
```

This was many years before capstone appeared. So r2 was using udis86 and olly disassemblers, many gnu (from binutils).

Nowadays, the disassembler support is one of the basic features of radare. It now has many options, endianness, including target architecture flavor and disassembler variants, among other things.

To see the disassembly, use the pd command. It accepts a numeric argument to specify how many opcodes of current block you want to see. Most of the commands in radare consider the current block size as the default limit for data input. If you want to disassemble more bytes, set a new block size using the b command.

```
[0x00000000] > b 100 ; set block size to 100 [0x00000000] > pd ; disassemble 100 bytes [0x00000000] > pd 3 ; disassemble 3 opcodes [0x00000000] > pD 30 ; disassemble 30 bytes
```

The pD command works like pd but accepts the number of input bytes as its argument, instead of the number of opcodes.

The "pseudo" syntax may be somewhat easier for a human to understand than the default assembler notations. But it can become annoying if you read lots of code. To play with it:

```
[0x00405e1c] > e asm.pseudo = true
[0x00405e1c] > pd 3
         ; JMP XREF from 0x00405dfa (fcn.00404531)
         0x00405e1c 488b9424a80. rdx = [rsp+0x2a8]
                      64483314252. rdx ^= [fs:0x28]
         0x00405e24
         0x00405e2d
                      4889d8
                                 rax = rbx
[0x00405e1c] > e asm.syntax = intel
[0x00405e1c] > pd 3
         ; JMP XREF from 0x00405dfa (fcn.00404531)
         0x00405e1c 488b9424a80. mov rdx, [rsp+0x2a8]
                      64483314252. xor rdx, [fs:0x28]
         0x00405e24
         0x00405e2d
                      4889d8
                              mov rax, rbx
[0x00405e1c] > e asm.syntax=att
[0x00405e1c] > pd 3
         ; JMP XREF from 0x00405dfa (fcn.00404531)
         0x00405e1c 488b9424a80. mov 0x2a8(%rsp), %rdx
         0x00405e24 64483314252. xor %fs:0x28, %rdx
         0x00405e2d 4889d8 mov %rbx, %rax
```

# Basic Debugger Session

To debug a program, start radare with the -d option. Note that you can attach to a running process by specifying its PID, or you can start a new program by specifying its name and parameters:

```
$ pidof mc
32220
$ r2 -d 32220
$ r2 -d /bin/ls
$ r2 -a arm -b 16 -d gdb://192.168.1.43:9090
```

. . .

In the second case, the debugger will fork and load the debugee ls program in memory.

It will pause its execution early in ld.so dynamic linker. As a result, you will not yet see the entrypoint or any shared libraries at this point.

You can override this behavior by setting another name for an entry breakpoint. To do this, add a radare command e dbg.bep=entry or e dbg.bep=main to your startup script, usually it is ~/.config/radare2/radare2rc.

Another way to continue until a specific address is by using the dcu command. Which means: "debug continue until" taking the address of the place to stop at. For example:

#### dcu main

Be warned that certain malware or other tricky programs can actually execute code before main() and thus you'll be unable to control them. (Like the program constructor or the tls initializers)

Below is a list of most common commands used with debugger:

```
> d?
                ; get help on debugger commands
> ds 3
                ; step 3 times
> db 0x8048920 ; setup a breakpoint
> db -0x8048920 ; remove a breakpoint
> dc
               ; continue process execution
               ; continue until syscall
> dcs
               ; manipulate file descriptors
> dd
                ; show process maps
> dm
               ; change permissions of page at A and size S
> dmp A S rwx
                ; set register value. eax = 33
> dr eax=33
```

There is another option for debugging in radare, which may be easier: using visual mode.

That way you will neither need to remember many commands nor to keep program state in your mind.

To enter visual debugger mode use Vpp:

## [0xb7f0c8c0] > Vpp

The initial view after entering visual mode is a hexdump view of the current target program counter (e.g., EIP for x86). Pressing p will allow you to cycle through the rest of visual mode views. You can press p and P to rotate through the most commonly used print modes. Use F7 or s to step into and F8 or S to step over current instruction. With the c key you can toggle the cursor mode to mark a byte range selection (for example, to later overwrite them with nop). You can set breakpoints with F2 key.

In visual mode you can enter regular radare commands by prepending them with :. For example, to dump a one block of memory contents at ESI:

```
<Press ':'>
x @ esi
```

To get help on visual mode, press?. To scroll the help screen, use arrows. To exit the help view, press q.

A frequently used command is dr, which is used to read or write values of the target's general purpose registers. For a more compact register value representation you might use dr= command. You can also manipulate the hardware and the extended/floating point registers.

#### **Command Format**

A general format for radare2 commands is as follows:

```
[.][times][cmd][~grep][@[@iter]addr!size][|>pipe];
```

People who use Vim daily and are familiar with its commands will find themselves at home. You will see this format used throughout the book. Commands are identified by a single case-sensitive character [a-zA-Z].

To repeatedly execute a command, prefix the command with a number:

```
px # run px
3px # run px 3 times
```

The ! prefix is used to execute a command in shell context. If you want to use the cmd callback from the I/O plugin you must prefix with =!.

Note that a single exclamation mark will run the command and print the output through the RCons API. This means that the execution will be blocking and not interactive. Use double exclamation marks – !! – to run a standard system call.

All the socket, filesystem and execution APIs can be restricted with the cfg.sandbox configuration variable.

A few examples:

```
ds ; call the debugger's 'step' command
px 200 @ esp ; show 200 hex bytes at esp
pc > file.c ; dump buffer as a C byte array to file.c
wx 90 @@ sym.* ; write a nop on every symbol
pd 2000 | grep eax ; grep opcodes that use the 'eax' register
px 20 ; pd 3 ; px 40 ; multiple commands in a single line
```

The standard UNIX pipe | is also available in the radare 2 shell. You can use it to filter the output of an r2 command with any shell program that reads from stdin, such as grep, less, wc. If you do not want to spawn anything, or

you can't, or the target system does not have the basic UNIX tools you need (Windows or embedded users), you can also use the built-in grep (~).

```
See ~? for help.
```

The  $\sim$  character enables internal grep-like function used to filter output of any command:

```
pd 20~call ; disassemble 20 instructions and grep output for 'call'
```

Additionally, you can grep either for columns or for rows:

Or even combine them:

```
pd 20~call:0[0] ; grep the first column of the first row matching 'call'
```

This internal grep function is a key feature for scripting radare2, because it can be used to iterate over a list of offsets or data generated by disassembler, ranges, or any other command. Refer to the loops section (iterators) for more information.

The @ character is used to specify a temporary offset at which the command to its left will be executed. The original seek position in a file is then restored.

For example, pd 5 @ 0x100000fce to disassemble 5 instructions at address 0x100000fce.

Most of the commands offer autocompletion support using <TAB> key, for example seek or flags commands. It offers autocompletion using all possible values, taking flag names in this case. Note that it is possible to see the history of the commands using the !~... command - it offers a visual mode to scroll through the radare2 command history.

To extend the autocompletion support to handle more commands or enable autocompletion to your own commands defined in core, I/O plugins you must use the !!! command.

## Command-line Options

The radare core accepts many flags from the command line.

This is an excerpt from the usage help message:

```
read file from stdin (use -i and -c to run cmds)
            perform !=! command to run all commands remotely
-0
            print \x00 after init and every command
-2
            close stderr file descriptor (silent warning messages)
-a [arch]
            set asm.arch
            run 'aaa' command to analyze all referenced code
-A
-b [bits] set asm.bits
-B [baddr] set base address for PIE binaries
-c 'cmd..'
            execute radare command
-C
            file is host:port (alias for -c+=http://%s/cmd/)
            debug the executable 'file' or running process 'pid'
-d
-D [backend] enable debug mode (e cfg.debug=true)
-e k=v
            evaluate config var
-f
            block size = file size
-F [binplug] force to use that rbin plugin
-h, -hh
            show help message, -hh for long
-H ([var])
            display variable
-i [file]
            run script file
-I [file]
            run script file before the file is opened
-k [OS/kern] set asm.os (linux, macos, w32, netbsd, ...)
-l [lib]
            load plugin file
-L
            list supported IO plugins
-m [addr]
            map file at given address (loadaddr)
-M
            do not demangle symbol names
-n, -nn
            do not load RBin info (-nn only load bin structures)
            do not load user settings and scripts
-N
-q
            quiet mode (no prompt) and quit after -i
-Q
            quiet mode (no prompt) and quit faster (quickLeak=true)
            use project, list if no arg, load if no file
-p [prj]
-P [file]
            apply rapatch file and quit
-r [rarun2] specify rarun2 profile to load (same as -e dbg.profile=X)
-R [rr2rule] specify custom rarun2 directive
-s [addr]
            initial seek
-S
            start r2 in sandbox mode
            load rabin2 info in thread
-t
            set bin.filter=false to get raw sym/sec/cls names
-u
-v, -V
            show radare2 version (-V show lib versions)
-w
            open file in write mode
            open without exec-flag (asm.emu will not work), See io.exec
-x
            same as -e bin.usextr=false (useful for dyldcache)
-X
            do not load strings or load them even in raw
-z, -zz
```

### Common usage patterns

Open a file in write mode without parsing the file format headers.

\$ r2 -nw file

Quickly get into an r2 shell without opening any file.

\$ r2 -

Specify which sub-binary you want to select when opening a fatbin file:

\$ r2 -a ppc -b 32 ls.fat

Run a script before showing interactive command-line prompt:

\$ r2 -i patch.r2 target.bin

Execute a command and quit without entering the interactive mode:

\$ r2 -qc ij hi.bin > imports.json

Set the configuration variable:

\$ r2 -e scr.color=0 blah.bin

Debug a program:

\$ r2 -d ls

Use an existing project file:

\$ r2 -p test

### Android

Radare2 can be cross-compiled for other architectures/systems as well, like Android.

## Prerequisites

- Python 3
- Meson
- Ninja
- Git
- Android NDK

### Step-by-step

**Download and extract the Android NDK** Download the Android NDK from the official site and extract it somewhere on your system (e.g. /tmp/android-ndk)

Make

## Specify NDK base path

\$ echo NDK=/tmp/android-ndk > ~/.r2androidrc

## Compile + create tar.gz + push it to connected android device

```
./sys/android-build.sh arm64-static
```

You can build for different architectures by changing the argument to ./sys/android-build.sh. Run the script without any argument to see the accepted values.

#### Meson

Create a cross-file for meson Meson needs a configuration file that describes the cross compilation environment (e.g. meson-android.ini). You can adjust it as necessary, but something like the following should be a good starting point:

#### [binaries]

```
c = '/tmp/android-ndk/toolchains/llvm/prebuilt/linux-x86_64/bin/aarch64-linux-android:
cpp = '/tmp/android-ndk/toolchains/llvm/prebuilt/linux-x86_64/bin/aarch64-linux-android:
ar = '/tmp/android-ndk/toolchains/llvm/prebuilt/linux-x86_64/bin/aarch64-linux-android:
as = '/tmp/android-ndk/toolchains/llvm/prebuilt/linux-x86_64/bin/aarch64-linux-android:
ranlib = '/tmp/android-ndk/toolchains/llvm/prebuilt/linux-x86_64/bin/aarch64-linux-android:
ld = '/tmp/android-ndk/toolchains/llvm/prebuilt/linux-x86_64/bin/aarch64-linux-android:
strip = '/tmp/android-ndk/toolchains/llvm/prebuilt/linux-x86_64/bin/aarch64-linux-android:
pkgconfig = 'false'

[properties]
sys_root = '/tmp/android-ndk/sysroot'
```

```
[host_machine]
system = 'android'
cpu_family = 'arm'
cpu = 'aarch64'
endian = 'little'
```

Compile with meson + ninja Now setup the build directory with meson as usual:

```
$ CFLAGS="-static" LDFLAGS="-static" meson --default-library static --prefix=/tmp/android-d:
```

A bit of explanation about all the options: \* CFLAGS="-static", LDFLAGS="-static", --default-library static: this ensure that libraries and binaries are statically compiled, so you do not need to properly set LD\_\* environment variables in your Android environment to make it find the right libraries. Binaries have everything they need inside. \* -Dblob=true: it tells meson to compile just one binary with all the needed code for running radare2, rabin2, rasm2, etc. and creates symbolic links to those names. This avoids creating many statically compiled large binaries and just create one that provides all features. You will still have rabin2, rasm2, rax2, etc. but

they are just symlinks to radare2. \* --cross-file ./meson-android.ini: it describes how to compile radare2 for Android

Then compile and install the project:

```
$ ninja -C build
$ ninja -C build install
```

Move files to your android device and enjoy At this point you can copy the generated files in /tmp/android-dir to your Android device and running radare2 from it. For example:

## Compilation and Portability

Currently the core of radare2 can be compiled on many systems and architectures, but the main development is done on GNU/Linux with GCC, and on MacOS X with clang. Radare is also known to compile on many different systems and architectures (including TCC and SunStudio).

People often want to use radare as a debugger for reverse engineering. Currently, the debugger layer can be used on Windows, GNU/Linux (Intel x86 and x86\_64, MIPS, and ARM), OS X, FreeBSD, NetBSD, and OpenBSD (Intel x86 and x86\_64)..

Compared to core, the debugger feature is more restrictive portability-wise. If the debugger has not been ported to your favorite platform, you can disable the debugger layer with the –without-debugger configure script option when compiling radare2.

Note that there are I/O plugins that use GDB, WinDbg, or Wine as back-ends, and therefore rely on presence of corresponding third-party tools (in case of remote debugging - just on the target machine).

To build on a system using acr and GNU Make (e.g. on \*BSD systems):

```
$ ./configure --prefix=/usr
$ gmake
$ sudo gmake install
```

There is also a simple script to do this automatically:

```
$ sys/install.sh
```

### Static Build

You can build radare2 statically along with all other tools with the command:

```
$ sys/static.sh
```

### Meson build

You can use meson + ninja to build:

```
$ sys/meson.py --prefix=/usr --shared --install
```

If you want to build locally:

```
$ sys/meson.py --prefix=/home/$USER/r2meson --local --shared --install
```

#### Docker

Radare2 repository ships a Dockerfile that you can use with Docker.

This dockerfile is also used by Remnux distribution from SANS, and is available on the docker registryhub.

## Cleaning Up Old Radare2 Installations

```
./configure --prefix=/old/r2/prefix/installation make purge
```

## Contributing

#### Radare2 Book

If you want to contribute to the Radare2 book, you can do it at the Github repository. Suggested contributions include:

- Crackme writeups
- CTF writeups
- Documentation on how to use Radare2
- Documentation on developing for Radare2
- $\bullet$  Conference presentations/workshops using Radare2
- Missing content from the Radare1 book updated to Radare2

Please get permission to port any content you do not own/did not create before you put it in the Radare2 book.

See https://github.com/radareorg/radare2/blob/master/DEVELOPERS.md for general help on contributing to radare2.

## Expressions

Expressions are mathematical representations of 64-bit numerical values. They can be displayed in different formats, be compared or used with all commands

accepting numeric arguments. Expressions can use traditional arithmetic operations, as well as binary and boolean ones. To evaluate mathematical expressions prepend them with command ?:

```
[0xb7f9d810]> ?vi 0x8048000
134512640
[0xv7f9d810] > ?vi 0x8048000+34
134512674
[0xb7f9d810]> ?vi 0x8048000+0x34
134512692
[0xb7f9d810] > ? 1+2+3-4*3
hex
       0xffffffffffffa
     017777777777777777772
octal
unit
     17179869184.0G
segment fffff000:0ffa
int64
fvalue: -6.0
float: nanf
double: nan
       0t11112220022122120101211020120210210211201
trits
Supported arithmetic operations are:
  \bullet + : addition
  • -: subtraction
  \bullet *: multiplication
  • / : division
  • \%: modulus
  • » : shift right
  \bullet~ « : shift left
[0x00000000] > ?vi 1+2+3
To use of binary OR should quote the whole command to avoid executing the |
pipe:
[0x0000000]> "? 1 | 2"
       0x3
hex
octal
       03
unit
       3
segment 0000:0003
int32
string "\x03"
binary 0b00000011
fvalue: 2.0
float: 0.000000f
```

double: 0.000000
trits 0t10

Numbers can be displayed in several formats:

0x033 : hexadecimal can be displayed

3334 : decimal

sym.fo : resolve flag offset
10K : KBytes 10\*1024
10M : MBytes 10\*1024\*1024

You can also use variables and seek positions to build complex expressions.

Use the ?\$? command to list all the available commands or read the refcard chapter of this book.

```
$$ here (the current virtual seek)
$1 opcode length
$s file size
$j jump address (e.g. jmp 0x10, jz 0x10 => 0x10)
$f jump fail address (e.g. jz 0x10 => next instruction)
$m opcode memory reference (e.g. mov eax,[0x10] => 0x10)
$b block size
```

Some more examples:

```
140293837812900 0x7f98b45df4a4 03771426427372244 130658.0G 8b45d000:04a4 140293837812900 10:
[0x4A13B8C0] > pd 1 @ +$1
0x4A13B8C2 call 0x4a13c000
```

### Downloading radare2

[0x4A13B8C0] > ? \$m + \$1

You can get radare from the GitHub repository: https://github.com/radareorg/radare2

Binary packages are available for a number of operating systems (Ubuntu, Maemo, Gentoo, Windows, iPhone, and so on). But you are highly encouraged to get the source and compile it yourself to better understand the dependencies, to make examples more accessible and, of course, to have the most recent version.

A new stable release is typically published every month.

The radare development repository is often more stable than the 'stable' releases. To obtain the latest version:

```
$ git clone https://github.com/radareorg/radare2.git
```

This will probably take a while, so take a coffee break and continue reading this book.

To update your local copy of the repository, use git pull anywhere in the radare2 source code tree:

### \$ git pull

If you have local modifications of the source, you can revert them (and lose them!) with:

\$ git reset --hard HEAD

Or send us a patch:

\$ git diff > radare-foo.patch

The most common way to get r2 updated and installed system wide is by using:

\$ sys/install.sh

## Building with meson + ninja

There is also a work-in-progress support for Meson.

Using clang and ld.gold makes the build faster:

```
CC=clang LDFLAGS=-fuse-ld=gold meson . release --buildtype=release --prefix ~/.local/stow/raninja -C release # ninja -C release install
```

### **Helper Scripts**

Take a look at the scripts in sys/, they are used to automate stuff related to syncing, building and installing r2 and its bindings.

The most important one is sys/install.sh. It will pull, clean, build and symstall r2 system wide.

Symstalling is the process of installing all the programs, libraries, documentation and data files using symlinks instead of copying the files.

By default it will be installed in /usr/local, but you can specify a different prefix using the argument --prefix.

This is useful for developers, because it permits them to just run 'make' and try changes without having to run make install again.

## Cleaning Up

Cleaning up the source tree is important to avoid problems like linking to old objects files or not updating objects after an ABI change.

The following commands may help you to get your git clone up to date:

```
$ git clean -xdf
$ git reset --hard origin/master
$ git pull
```

If you want to remove previous installations from your system, you must run the following commands:

```
$ ./configure --prefix=/usr/local
$ make purge
```

## History

In 2006, Sergi Àlvarez (aka pancake) was working as a forensic analyst. Since he wasn't allowed to use the company software for his personal needs, he decided to write a small tool-a hexadecimal editor-with very basic characteristics:

- be extremely portable (unix friendly, command line, c, small)
- open disk devices, this is using 64bit offsets
- search for a string or hexpair
- review and dump the results to disk

The editor was originally designed to recover a deleted file from an HFS+ partition.

After that, pancake decided to extend the tool to have a pluggable io to be able to attach to processes and implemented the debugger functionalities, support for multiple architectures, and code analysis.

Since then, the project has evolved to provide a complete framework for analyzing binaries, while making use of basic UNIX concepts. Those concepts include the famous "everything is a file", "small programs that interact using stdin/stdout", and "keep it simple" paradigms.

The need for scripting showed the fragility of the initial design: a monolithic tool made the API hard to use, and so a deep refactoring was needed. In 2009 radare2 (r2) was born as a fork of radare1. The refactor added flexibility and dynamic features. This enabled much better integration, paving the way to use r2 from different programming languages. Later on, the r2pipe API allowed access to radare2 via pipes from any language.

What started as a one-man project, with some eventual contributions, gradually evolved into a big community-based project around 2014. The number of users was growing fast, and the author-and main developer-had to switch roles from coder to manager in order to integrate the work of the different developers that were joining the project.

Instructing users to report their issues allows the project to define new directions to evolve in. Everything is managed in radare2's GitHub and discussed in the Telegram channel.

The project remains active at the time of writing this book, and there are several side projects that provide, among other things, a graphical user interface (Cutter), a decompiler (r2dec, radeco), Frida integration (r2frida), Yara, Unicorn, Keystone, and many other projects indexed in the r2pm (the radare2 package manager).

Since 2016, the community gathers once a year in r2con, a congress around radare2 that takes place in Barcelona.

## Basic Radare2 Usage

The learning curve is usually somewhat steep at the beginning. Although after an hour of using it you should easily understand how most things work, and how to combine the various tools radare offers. You are encouraged to read the rest of this book to understand how some non-trivial things work, and to ultimately improve your skills.

learning curve

Navigation, inspection and modification of a loaded binary file is performed using three simple actions: seek (to position), print (buffer), and alternate (write, append).

The 'seek' command is abbreviated as s and accepts an expression as its argument. The expression can be something like 10, +0x25, or  $[0x100+ptr_table]$ . If you are working with block-based files, you may prefer to set the block size to a required value with b command, and seek forward or backwards with positions aligned to it. Use s++ and s-- commands to navigate this way.

If radare2 opens an executable file, by default it will open the file in Virtual Addressing (VA) mode and the sections will be mapped to their virtual addresses. In VA mode, seeking is based on the virtual address and the starting position is set to the entry point of the executable. Using -n option you can suppress this default behavior and ask radare2 to open the file in non-VA mode for you. In non-VA mode, seeking is based on the offset from the beginning of the file.

The 'print' command is abbreviated as p and has a number of submodes — the second letter specifying a desired print mode. Frequent variants include px to print in hexadecimal, and pd for disassembling.

To be allowed to write files, specify the -w option to radare2 when opening a file. The w command can be used to write strings, hexpairs (x subcommand), or even assembly opcodes (a subcommand). Examples:

> wf inline.bin ; write contents of file

Appending a ? to a command will show its help message, for example, p?. Appending ?\* will show commands starting with the given string, e.g. p?\*.

To enter visual mode, press V<enter>. Use q to quit visual mode and return to the prompt.

In visual mode you can use HJKL keys to navigate (left, down, up, and right, respectively). You can use these keys in cursor mode toggled by c key. To select a byte range in cursor mode, hold down SHIFT key, and press navigation keys HJKL to mark your selection.

While in visual mode, you can also overwrite bytes by pressing i. You can press TAB to switch between the hex (middle) and string (right) columns. Pressing q inside the hex panel returns you to visual mode. By pressing p or P you can scroll different visual mode representations. There is a second most important visual mode - curses-like panels interface, accessible with V! command.

### The Framework

The Radare2 project is a set of small command-line utilities that can be used together or independently.

This chapter will give you a quick understanding of them, but you can check the dedicated sections for each tool at the end of this book.

#### radare2

The main tool of the whole framework. It uses the core of the hexadecimal editor and debugger. radare2 allows you to open a number of input/output sources as if they were simple, plain files, including disks, network connections, kernel drivers, processes under debugging, and so on.

It implements an advanced command line interface for moving around a file, analyzing data, disassembling, binary patching, data comparison, searching, replacing, and visualizing. It can be scripted with a variety of languages, including Python, Ruby, JavaScript, Lua, and Perl.

### rabin2

A program to extract information from executable binaries, such as ELF, PE, Java CLASS, Mach-O, plus any format supported by r2 plugins. rabin2 is used by the core to get data like exported symbols, imports, file information, cross references (xrefs), library dependencies, and sections.

### rasm2

A command line assembler and disassembler for multiple architectures (including Intel x86 and x86-64, MIPS, ARM, PowerPC, Java, and myriad of others).

## Examples

```
$ rasm2 -a java 'nop'
00

$ rasm2 -a x86 -d '90'
nop

$ rasm2 -a x86 -b 32 'mov eax, 33'
b821000000

$ echo 'push eax;nop;nop' | rasm2 -f -
509090
```

#### rahash2

An implementation of a block-based hash tool. From small text strings to large disks, rahash2 supports multiple algorithms, including MD4, MD5, CRC16, CRC32, SHA1, SHA256, and others. rahash2 can be used to check the integrity or track changes of big files, memory dumps, or disks.

## Examples

```
$ rahash2 file
file: 0x00000000-0x00000007 sha256: 887cfbd0d44aaff69f7bdbedebd282ec96191cce9d7fa7336298a18c
$ rahash2 -a md5 file
file: 0x00000000-0x00000007 md5: d1833805515fc34b46c2b9de553f599d
```

#### radiff2

A binary diffing utility that implements multiple algorithms. It supports by televel or delta diffing for binary files, and code-analysis diffing to find changes in basic code blocks obtained from the radare code analysis.

### rafind2

A program to find byte patterns in files.

### ragg2

A frontend for r\_egg. ragg2 compiles programs written in a simple high-level language into tiny binaries for x86, x86-64, and ARM.

### Examples

```
$ cat hi.r
/* hello world in r_egg */
write@syscall(4); //x64 write@syscall(1);
exit@syscall(1); //x64 exit@syscall(60);
```

```
main@global(128) {
    .var0 = "hi!\n";
    write(1,.var0, 4);
    exit(0);
}
$ ragg2 -0 -F hi.r
$ ./hi
hi!

$ cat hi.c
main@global(0,6) {
    write(1, "Helloo", 6);
    exit(0);
}
$ ragg2 hi.c
$ ./hi.c.bin
Hello
```

#### rarun2

A launcher for running programs within different environments, with different arguments, permissions, directories, and overridden default file descriptors. rarun2 is useful for:

- Solving crackmes
- Fuzzing
- Test suites

## Sample rarun2 script

```
$ cat foo.rr2
#!/usr/bin/rarun2
program=./pp400
arg0=10
stdin=foo.txt
chdir=/tmp
#chroot=.
./foo.rr2
```

## Connecting a Program with a Socket

```
$ nc -1 9999
$ rarun2 program=/bin/ls connect=localhost:9999
```

## Debugging a Program Redirecting the stdio into Another Terminal

1 - open a new terminal and type 'tty' to get a terminal name:

```
$ tty; clear; sleep 999999
/dev/ttyS010
2 - Create a new file containing the following rarun2 profile named foo.rr2:
#!/usr/bin/rarun2
program=/bin/ls
stdio=/dev/ttys010
3 - Launch the following radare2 command:
r2 -r foo.rr2 -d /bin/ls
```

#### rax2

A minimalistic mathematical expression evaluator for the shell that is useful for making base conversions between floating point values, hexadecimal representations, hexpair strings to ASCII, octal to integer, and more. It also supports endianness settings and can be used as an interactive shell if no arguments are given.

## Examples

```
$ rax2 1337
0x539

$ rax2 0x400000
4194304

$ rax2 -b 01111001
y

$ rax2 -S radare2
72616461726532

$ rax2 -s 617765736f6d65
awesome
```

## **User Interfaces**

Radare2 has seen many different user interfaces being developed over the years.

Maintaining a GUI is far from the scope of developing the core machinery of a reverse engineering toolkit: it is preferred to have a separate project and community, allowing both projects to collaborate and to improve together - rather than forcing cli developers to think in gui problems and having to jump back and forth between the graphic aspect and the low level logic of the implementations.

In the past, there have been at least 5 different native user interfaces (ragui, r2gui, gradare, r2net, bokken) but none of them got enough maintenance power to take off and they all died.

In addition, r2 has an embedded webserver and ships some basic user interfaces written in html/js. You can start them like this:

### r2 -c=H /bin/ls

After 3 years of private development, Hugo Teso; the author of Bokken (pythongtk gui of r2) released to the public another frontend of r2, this time written in c++ and qt, which has been very welcomed by the community.

This GUI was named Iaito, but as long as he prefered not to keep maintaining it, Xarkes decided to fork it under the name of Cutter (name voted by the community), and lead the project. This is how it looks:

• https://github.com/radareorg/cutter.

Cutter

### Windows

To build r2 on Windows you have to use the Meson build system. Despite being able to build r2 on Windows using cygwin, mingw or wsl using the acr/make build system it is not the recommended/official/supported method and may result on unexpected results.

Binary builds can be downloaded from the release page or the github CI artifacts from every single commit for 32bit and 64bit Windows.

• https://github.com/radareorg/radare2/releases

## Prerequisites

- 3 GB of free disk space
- Visual Studio 2019 (or higher)
- Python 3
- Meson
- Ninja
- Git

### Step-by-Step

Install Visual Studio 2015 (or higher) Visual Studio must be installed with a Visual C++ compiler, supporting C++ libraries, and the appropriate Windows SDK for the target platform version.

• Ensure Programming Languages > Visual C++ is selected

If you need a copy of Visual Studio, the Community versions are free and work great.

• Download Visual Studio 2019

**Install Python 3 and Meson via Conda** Conda is our probably the best Python distribution for Windows. But you can skip the next steps if you have Python installed already

- https://docs.conda.io/en/latest/miniconda.html
- https://repo.anaconda.com/archive/

Create a Python Environment for Radare2 Follow these steps to create and activate a Conda environment named r2. All instructions from this point on will assume this name matches your environment, but you may change this if desired.

- 1. Start > Anaconda Prompt
- 2. conda create -n r2 python=3
- 3. activate r2

Any time you wish to enter this environment, open the Anaconda Prompt and re-issue activate r2. Conversely, deactivate will leave the environment.

**Install Git for Windows** All Radare2 code is managed via the Git version control system and hosted on GitHub.

Follow these steps to install Git for Windows.

Download Git for Windows

• https://git-scm.com/download/win

Check the following options during the Wizard steps.

- Use a TrueType font in all console windows
- Use Git from the Windows Command Prompt
- Use the native Windows Secure Channel library (instead of OpenSSL)
- Checkout Windows-style, commit Unix-style line endings (core.autocrlf=true)
- Use Windows' default console window (instead of Mintty)
- Ensure git --version works after install

Get Radare2 Code Follow these steps to clone the Radare2 git repository.

git clone https://github.com/radareorg/radare2

Compile Radare2 Code Follow these steps to compile the Radare2 Code.

\* \*\*Visual Studio 2017:\*\*

Note 1: Change `Community` to either `Professional` or `Enterprise` in the command below

Note 2: Change `vcvars32.bat` to `vcvars64.bat` in the command below for the 64-bit vers

"%ProgramFiles(x86)%\Microsoft Visual Studio\2017\Community\VC\Auxiliary\Build\vcvars

4. Generate the build system with Meson:

Meson takes some arguments to configure the build type, but in short you should be able to build r2 without any meson flag. For Visual Studio. Note: Change Debug to Release in the command below depending on the version desired.

meson b --buildtype debug --backend vs2019 --prefix %cd%\dest
msbuild build\radare2.sln /p:Configuration=Debug /m

For Ninja (no visual studio interface required, just msvc compiler toolchain installed):

meson b ninja -C b

Finally run this line to install r2 into the given absolute prefix directory:

meson install -C build --no-rebuild

Build options notes The /m[axcpucount] switch creates one MSBuild worker process per logical processor on your machine. You can specify a numeric value (e.g. /m:2) to limit the number of worker processes if needed. (This should not be confused with the Visual C++ Compiler switch /MP.)

If you get an error with the 32-bit install that says something along the lines of error MSB4126: The specified solution configuration "Debug|x86" is invalid. Get around this by adding the following argument to the command: /p:Platform=Win32

Check your Radare2 version: dest\bin\radare2.exe -v

Check That Radare2 Runs From All Locations Note that r2 in UNIX systems is just a symlink to the radare2 executable. So, in case you want to have it in Windows you can just copy radare2.exe r2.exe and add the directory into the system-wide PATH env var in the File Explorer settings.

Open the cmd.exe console and type r2 -v to confirm the whole process was successful.

### Notes about setting up the system-wide env var

- 1. In the file explorer go to the folder Radare was just installed in.
- 2. From this folder go to dest > bin and keep this window open.
- 3. Go to System Properties: In the Windows search bar enter sysdm.cpl.
- 4. Go to Advanced > Environment Variables.
- 5. Click on the PATH variable and then click edit (if it exists within both the user and system variables, look at the user version).
- 6. Ensure the file path displayed in the window left open is listed within the PATH variable. If it is not add it and click ok.
- 7. Log out of your Windows session.
- 8. Open up a new Windows Command Prompt: type cmd in the search bar. Ensure that the current path is not in the Radare2 folder.
- 9. Check Radare2 version from Command Prompt Window: radare2 -v

# Debugging

It is common to have an issues when you write a plugin, especially if you do this for the first time. This is why debugging them is very important. The first step for debugging is to set an environment variable when running radare2 instance:

```
R_DEBUG=yes r2 /bin/ls
Loading /usr/local/lib/radare2/2.2.0-git//bin_xtr_dyldcache.so
Cannot find symbol 'radare_plugin' in library '/usr/local/lib/radare2/2.2.0-git//bin_xtr_dy
Cannot open /usr/local/lib/radare2/2.2.0-git//2.2.0-git
Loading /home/user/.config/radare2/plugins/asm_mips_ks.so
PLUGIN OK 0x55b205ea6070 fcn 0x7f298de08762
Loading /home/user/.config/radare2/plugins/asm_sparc_ks.so
PLUGIN OK 0x55b205ea6070 fcn 0x7f298de08762
Cannot open /home/user/.config/radare2/plugins/pimp
Cannot open /home/user/.config/radare2/plugins/yara
Loading /home/user/.config/radare2/plugins/asm_arm_ks.so
PLUGIN OK 0x55b205ea6070 fcn 0x7f298de08762
Loading /home/user/.config/radare2/plugins/core_yara.so
Module version mismatch /home/user/.config/radare2/plugins/core_yara.so (2.1.0) vs (2.2.0-g.
Loading /home/user/.config/radare2/plugins/asm_ppc_ks.so
PLUGIN OK 0x55b205ea6070 fcn 0x7f298de08762
Loading /home/user/.config/radare2/plugins/lang_python3.so
PLUGIN OK 0x55b205ea5ed0 fcn 0x7f298de08692
Loading /usr/local/lib/radare2/2.2.0-git/bin_xtr_dyldcache.so
Cannot find symbol 'radare_plugin' in library '/usr/local/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.2.0-git/bin_xtr_dylocal/lib/radare2/2.0-git/bin_xtr_dylocal/lib/radare2/2.0-git/bin_xtr_dylocal/lib/radare2/2.0-git/bin_xtr_dylocal/lib/radare2/2.0-git/bin_xtr_dylocal/lib/radare2/2.0-git/
Cannot open /usr/local/lib/radare2/2.2.0-git/2.2.0-git
Cannot open directory '/usr/local/lib/radare2-extras/2.2.0-git'
Cannot open directory '/usr/local/lib/radare2-bindings/2.2.0-git'
```

-- In visual mode press 'c' to toggle the cursor mode. Use tab to navigate

USER CONFIG loaded from /home/user/.config/radare2/radare2rc

## Implementing a new analysis plugin

After implementing disassembly plugin, you might have noticed that output is far from being good - no proper highlighting, no reference lines and so on. This is because radare2 requires every architecture plugin to provide also analysis information about every opcode. At the moment the implementation of disassembly and opcodes analysis is separated between two modules - RAsm and RAnal. Thus we need to write an analysis plugin too. The principle is very similar - you just need to create a C file and corresponding Makefile.

They structure of RAnal plugin looks like

```
RAnalPlugin r_anal_plugin_v810 = {
    .name = "mycpu",
    .desc = "MYCPU code analysis plugin",
    .license = "LGPL3",
    .arch = "mycpu",
    .bits = 32,
    .op = mycpu_op,
    .esil = true,
    .set_reg_profile = set_reg_profile,
};
```

Like with disassembly plugin there is a key function - mycpu\_op which scans the opcode and builds RAnalOp structure. On the other hand, in this example analysis plugins also performs uplifting to ESIL, which is enabled in .esil = true statement. Thus, mycpu\_op obliged to fill the corresponding RAnalOp ESIL field for the opcodes. Second important thing for ESIL uplifting and emulation - register profile, like in debugger, which is set within set\_reg\_profile function.

### Makefile

```
NAME=anal_snes
R2_PLUGIN_PATH=$(shell r2 -H R2_USER_PLUGINS)
LIBEXT=$(shell r2 -H LIBEXT)
CFLAGS=-g -fPIC $(shell pkg-config --cflags r_anal)
LDFLAGS=-shared $(shell pkg-config --libs r_anal)
OBJS=$(NAME).o
LIB=$(NAME).$(LIBEXT)
all: $(LIB)
clean:
    rm -f $(LIB) $(OBJS)
```

```
$(CC) $(CFLAGS) $(LDFLAGS) $(OBJS) -o $(LIB)
install:
    cp -f anal_snes.$(SO_EXT) $(R2_PLUGIN_PATH)
uninstall:
   rm -f $(R2_PLUGIN_PATH)/anal_snes.$(S0_EXT)
anal snes.c:
/* radare - LGPL - Copyright 2015 - condret */
#include <string.h>
#include <r_types.h>
#include <r lib.h>
#include <r_asm.h>
#include <r anal.h>
#include "snes_op_table.h"
static int snes_anop(RAnal *anal, RAnalOp *op, ut64 addr, const ut8 *data, int len) {
    memset (op, '\0', sizeof (RAnalOp));
    op->size = snes_op[data[0]].len;
    op->addr = addr;
    op->type = R_ANAL_OP_TYPE_UNK;
    switch (data[0]) {
        case 0xea:
            op->type = R_ANAL_OP_TYPE_NOP;
            break;
   return op->size;
}
struct r_anal_plugin_t r_anal_plugin_snes = {
    .name = "snes",
    .desc = "SNES analysis plugin",
    .license = "LGPL3",
    .arch = R_SYS_ARCH_NONE,
    .bits = 16,
    .init = NULL,
    .fini = NULL,
    .op = &snes_anop,
    .set_reg_profile = NULL,
    .fingerprint_bb = NULL,
    .fingerprint_fcn = NULL,
    .diff_bb = NULL,
    .diff_fcn = NULL,
    .diff_eval = NULL
```

```
#ifndef R2_PLUGIN_INCORE
R_API RLibStruct radare_plugin = {
    .type = R_LIB_TYPE_ANAL,
    .data = &r_anal_plugin_snes,
    .version = R2_VERSION
};
#endif
```

After compiling radare2 will list this plugin in the output:

```
_dA_ _8_16 snes LGPL3 SuperNES CPU
```

snes\_op\_table.h: https://github.com/radareorg/radare2/blob/master/libr/asm/arch/snes/snes\_op\_table.h
Example:

- $\bullet \ \, \mathbf{6502} \colon \text{https://github.com/radareorg/radare2/commit/} \\ 64636e9505f9ca8b408958d3c01ac8e3ce254a9barder \\ \mathbf{6502} \colon \text{https://github.com/radareorg/radare2/commit/} \\ \mathbf{64636e9505f9ca8b408958d3c01ac8e3ce254a9barder } \\ \mathbf{6602} \colon \text{https://github.com/radareorg/radare2/commit/} \\ \mathbf{6602} \colon \text{https://github.com/radareorg/radare0/commit/} \\ \mathbf{6602} \colon \text{https://github.com/radareorg/radareo$
- $\bullet \ \mathbf{SNES}: \ https://github.com/radareorg/radare2/commit/60d6e5a1b9d244c7085b22ae8985d00027624b49$

#### Implementing a new disassembly plugin

Radare2 has modular architecture, thus adding support for a new architecture is very easy, if you are fluent in C. For various reasons it might be easier to implement it out of the tree. For this we will need to create single C file, called <code>asm\_mycpu.c</code> and makefile for it.

The key thing of RAsm plugin is a structure

```
RAsmPlugin r_asm_plugin_mycpu = {
    .name = "mycpu",
    .license = "LGPL3",
    .desc = "MYCPU disassembly plugin",
    .arch = "mycpu",
    .bits = 32,
    .endian = R_SYS_ENDIAN_LITTLE,
    .disassemble = &disassemble
};
where .disassemble is a pointer to disassembly function, which accepts the
bytes buffer and length:
static int disassemble(RAsm *a, RAsmOp *op, const ut8 *buf, int len)
Makefile
NAME=asm snes
R2_PLUGIN_PATH=$(shell r2 -H R2_USER_PLUGINS)
LIBEXT=$(shell r2 -H LIBEXT)
CFLAGS=-g -fPIC $(shell pkg-config --cflags r_anal)
```

```
LDFLAGS=-shared $(shell pkg-config --libs r_anal)
OBJS=$(NAME).o
LIB=$(NAME).$(LIBEXT)
all: $(LIB)
clean:
   rm -f $(LIB) $(OBJS)
$(LIB): $(OBJS)
    $(CC) $(CFLAGS) $(LDFLAGS) $(OBJS) -o $(LIB)
install:
   cp -f asm_mycpu.$(SO_EXT) $(R2_PLUGIN_PATH)
   rm -f $(R2_PLUGIN_PATH)/asm_mycpu.$(S0_EXT)
asm_mycpu.c
/* radare - LGPL - Copyright 2018 - user */
#include <stdio.h>
#include <string.h>
#include <r_types.h>
#include <r_lib.h>
#include <r_asm.h>
static int disassemble(RAsm *a, RAsmOp *op, const ut8 *buf, int len) {
    struct op_cmd cmd = {
        .instr = "",
        .operands = ""
   };
    if (len < 2) return -1;
   int ret = decode_opcode (buf, len, &cmd);
   if (ret > 0) {
        snprintf (op->buf_asm, R_ASM_BUFSIZE, "%s %s",
              cmd.instr, cmd.operands);
    }
   return op->size = ret;
}
RAsmPlugin r_asm_plugin_mycpu = {
    .name = "mycpu",
    .license = "LGPL3",
    .desc = "MYCPU disassembly plugin",
    .arch = "mycpu",
```

```
.bits = 32,
    .endian = R_SYS_ENDIAN_LITTLE,
    .disassemble = &disassemble
};
#ifndef R2_PLUGIN_INCORE
R_API RLibStruct radare_plugin = {
    .type = R_LIB_TYPE_ASM,
    .data = &r_asm_plugin_mycpu,
    .version = R2_VERSION
};
#endif
```

After compiling radare2 will list this plugin in the output:

```
_d_ _8_32 mycpu LGPL3 MYCPU
```

#### Moving plugin into the tree

Pushing a new architecture into the main branch of r2 requires to modify several files in order to make it fit into the way the rest of plugins are built.

List of affected files:

- plugins.def.cfg: add the asm.mycpu plugin name string in there
- libr/asm/p/mycpu.mk: build instructions
- libr/asm/p/asm\_mycpu.c : implementation
- libr/include/r\_asm.h : add the struct definition in there

Check out how the NIOS II CPU disassembly plugin was implemented by reading those commits:

 $those\ commits: \\ Implement\ RAsm\ plugin:\ https://github.com/radareorg/radare2/commit/933dc0ef6ddfe44c88bbb261165bf8f8b55c0eff8dfe46c0eff8dfe46c$ 

Implement RAnal plugin: https://github.com/radareorg/radare2/commit/ad430f0d52fbe933e0830c49ee607e9b0e

# Implementing a new format

#### To enable virtual addressing

In info add et->has\_va = 1; and ptr->srwx with the R\_BIN\_SCN\_MAP; attribute

#### Create a folder with file format name in libr/bin/format

#### Makefile:

```
NAME=bin_nes
R2_PLUGIN_PATH=$(shell r2 -H R2_USER_PLUGINS)
LIBEXT=$(shell r2 -H LIBEXT)
CFLAGS=-g -fPIC $(shell pkg-config --cflags r_bin)
```

```
LDFLAGS=-shared $(shell pkg-config --libs r_bin)
OBJS=$(NAME).o
LIB=$(NAME).$(LIBEXT)
all: $(LIB)
clean:
   rm -f $(LIB) $(OBJS)
$(LIB): $(OBJS)
   $(CC) $(CFLAGS) $(LDFLAGS) $(OBJS) -o $(LIB)
install:
   cp -f $(NAME).$(SO_EXT) $(R2_PLUGIN_PATH)
   rm -f $(R2_PLUGIN_PATH)/$(NAME).$(S0_EXT)
bin_nes.c:
#include <r_util.h>
#include <r_bin.h>
static bool load_buffer(RBinFile *bf, void **bin_obj, RBuffer *b, ut64 loadaddr, Sdb *sdb) -
   ut64 size;
   const ut8 *buf = r_buf_data (b, &size);
   r_return_val_if_fail (buf, false);
    *bin_obj = r_bin_internal_nes_load (buf, size);
   return *bin_obj != NULL;
}
static void destroy(RBinFile *bf) {
   r_bin_free_all_nes_obj (bf->o->bin_obj);
   bf->o->bin_obj = NULL;
}
static bool check_buffer(RBuffer *b) {
    if (!buf || length < 4) return false;</pre>
    return (!memcmp (buf, "x4Ex45x53x1A", 4));
static RBinInfo* info(RBinFile *arch) {
   RBinInfo \*ret = R_NEWO (RBinInfo);
   if (!ret) return NULL;
    if (!arch || !arch->buf) {
        free (ret);
```

```
return NULL;
    }
    ret->file = strdup (arch->file);
    ret->type = strdup ("ROM");
    ret->machine = strdup ("Nintendo NES");
    ret->os = strdup ("nes");
    ret->arch = strdup ("6502");
    ret->bits = 8;
    return ret;
}
struct r_bin_plugin_t r_bin_plugin_nes = {
    .name = "nes",
    .desc = "NES",
    .license = "BSD",
    .get_sdb = NULL,
    .load_buffer = &load_buffer,
    .destroy = &destroy,
    .check_buffer = &check_buffer,
    .baddr = NULL,
    .entries = NULL,
    .sections = NULL,
    .info = &info,
};
#ifndef R2_PLUGIN_INCORE
R_API RLibStruct radare_plugin = {
    .type = R_LIB_TYPE_BIN,
    .data = &r_bin_plugin_nes,
    .version = R2_VERSION
};
#endif
```

#### Some Examples

- XBE https://github.com/radareorg/radare2/pull/972
- COFF https://github.com/radareorg/radare2/pull/645
- TE https://github.com/radareorg/radare2/pull/61
- $\bullet \quad Zimgz https://github.com/radareorg/radare2/commit/d1351cf836df3e2e63043a6dc728e880316f00ebarrows and the statement of the statement of$
- $\bullet \quad OMF-https://github.com/radareorg/radare2/commit/44fd8b2555a0446ea759901a94c06f20566bbc40$

#### Charset

1. Create a file in radare2/libr/util/d/yourfile.sdb.txt. The extension .sdb.txt is important.

- Edit the file radare2/libr/util/charset.c. -add extern SdbGperf gperf\_latin\_1\_ISO\_8859\_1\_western\_european;. -then add your variable &gperf\_latin\_1\_ISO\_8859\_1\_western\_european, in static const SdbGperf \*gperfs[]
- 3. Update the Makefile: radare2/libr/util/Makefile: -Add OBJS+=d/latin\_1\_ISO\_8859\_1\_western\_eur
- 4. Update the Makefile radare2/libr/util/d/Makefile to add your file name with not .sdb and not .txt in FILES=latin\_1\_ISO\_8859\_1\_western\_european
- 5. Update the unit tests of radare2/test/db/cmd/charset

Congratulation! You can now type the command:

```
e cfg.charset=latin_1_ISO_8859_1_western_european;
```

If you have any issue with this tutorial you can check out the example at https://github.com/radareorg/radare2/pull/19627/files.

#### Implementing a new architecture

radare2 splits the logic of a CPU into several modules. You should write more than one plugin to get full support for a specific arch. Let's see which are those:

- $\bullet\,$  r\_asm : assembler and disassembler
- r\_anal : code analysis (opcode,type,esil,..)
- r reg : registers
- r syscall: system calls
- r debug : debugger

The most basic feature you usually want to support from a specific architecture is the disassembler. You first need to read into a human readable form the bytes in there.

Bear in mind that plugins can be compiled static or dynamically, this means that the arch will be embedded inside the core libraries or it will distributed as a separated shared library.

To configure which plugins you want to compile use the ./configure-plugins script which accepts the flags -shared and -static to specify them. You can also add it manually inside the plugins.def.cfg and then remove the plugins.cfg and run ./configure-plugins again to update the libr/config.mk and libr/config.h.

You may find some examples of external plugins in radare2-extras repository.

#### Writing the r asm plugin

The official way to make third-party plugins is to distribute them into a separate repository. This is a sample disasm plugin:

- \$ cd my-cpu
- \$ cat Makefile

```
NAME=mycpu
R2_PLUGIN_PATH=$(shell r2 -hh|grep R2_LIBR_PLUGINS|awk '{print $$2}')
CFLAGS=-g -fPIC $(shell pkg-config --cflags r_asm)
LDFLAGS=-shared $(shell pkg-config --libs r_asm)
OBJS=$(NAME).o
SO_EXT=$(shell uname|grep -q Darwin && echo dylib || echo so)
LIB=$(NAME).$(SO_EXT)
all: $(LIB)
clean:
   rm -f $(LIB) $(OBJS)
$(LIB): $(OBJS)
    $(CC) $(CFLAGS) $(LDFLAGS) $(OBJS) -o $(LIB)
install:
    cp -f $(NAME).$(SO_EXT) $(R2_PLUGIN_PATH)
uninstall:
   rm -f $(R2_PLUGIN_PATH)/$(NAME).$(S0_EXT)
$ cat mycpu.c
/* example r_asm plugin by pancake at 2014 */
#include <r_asm.h>
#include <r_lib.h>
#define OPS 17
static const char *ops[OPS*2] = {
   "nop", NULL,
   "if", "r",
   "ifnot", "r",
   "add", "rr",
    "addi", "ri"
    "sub", "ri",
    "neg", "ri",
    "xor", "ri",
    "mov", "ri",
    "cmp", "rr",
    "load", "ri",
    "store", "ri",
    "shl", "ri",
   "br", "r",
    "bl", "r",
```

```
"sys", "i"
};
/* Main function for disassembly */
//b for byte, l for length
static int disassemble (RAsm *a, RAsmOp *op, const ut8 *b, int 1) {
    char arg[32];
        int idx = (b[0]\&0xf)\*2;
    op->size = 2;
    if (idx>=(0PS*2)) {
        strcpy (op->buf_asm, "invalid");
        return -1;
    }
    strcpy (op->buf_asm, ops[idx]);
    if (ops[idx+1]) {
        const char \*p = ops[idx+1];
        arg[0] = 0;
        if (!strcmp (p, "rr")) {
            sprintf (arg, "r%d, r%d", b[1]>>4, b[1]&0xf);
        } else
        if (!strcmp (p, "i")) {
            sprintf (arg, "%d", (char)b[1]);
        } else
        if (!strcmp (p, "r")) {
            sprintf (arg, "r%d, r%d", b[1]>>4, b[1]&0xf);
        } else
        if (!strcmp (p, "ri")) {
            sprintf (arg, "r%d, %d", b[1]>>4, (char)b[1]&0xf);
        if (*arg) {
            strcat (op->buf_asm, " ");
            strcat (op->buf_asm, arg);
        }
    }
    return op->size;
}
/* Structure of exported functions and data */
RAsmPlugin r_asm_plugin_mycpu = {
        .name = "mycpu",
        .arch = "mycpu",
        .license = "LGPL3",
        .bits = 32,
        .desc = "My CPU disassembler",
        .disassemble = &disassemble,
```

"ret", NULL,

```
};
#ifndef CORELIB
struct r_lib_struct_t radare_plugin = {
        .type = R_LIB_TYPE_ASM,
        .data = &r_asm_plugin_mycpu
};
#endif
To build and install this plugin just type this:
$ sudo make install
```

#### Write a debugger plugin

- Adding the debugger registers profile into the shlr/gdb/src/core.c
- Adding the registers profile and architecture support in the libr/debug/p/debug native.c and libr/debug/p/debug\_gdb.c
- Add the code to apply the profiles into the function r\_debug\_gdb\_attach(RDebug \*dbg, int pid)

If you want to add support for the gdb, you can see the register profile in the active gdb session using command maint print registers.

#### More to come..

• Related article: http://radare.today/posts/extending-r2-with-newplugins/

Some commits related to "Implementing a new architecture"

- Extensa: https://github.com/radareorg/radare2/commit/6f1655c49160fe9a287020537afe0fb8049085d7
- Malbolge: https://github.com/radareorg/radare2/pull/579
- 6502: https://github.com/radareorg/radare2/pull/656
- h8300: https://github.com/radareorg/radare2/pull/664
- GBA: https://github.com/radareorg/radare2/pull/702
- CR16: https://github.com/radareorg/radare2/pull/721/ && 726
- $\bullet \quad XCore: https://github.com/radareorg/radare2/commit/bb16d1737ca5a471142f16ccfa7d444d2713a54d17d2f16ccfa7d44d27f16cfa7d44d2f16cfa7d4f16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df16cfa7df1$ SharpLH5801: https://github.com/neuschaefer/radare2/commit/f4993cca634161ce6f82a64596fce45fe6b818
- MSP430: https://github.com/radareorg/radare2/pull/1426
- V810: https://github.com/radareorg/radare2/pull/2899
- TMS320: https://github.com/radareorg/radare2/pull/596

#### Implementing a new pseudo architecture

This is an simple plugin for z80 that you may use as example:

# **Plugins**

radare2 is implemented on top of a bunch of libraries, almost every of those libraries support plugins to extend the capabilities of the library or add support for different targets.

This section aims to explain what are the plugins, how to write them and use them

#### Types of plugins

```
$ ls libr/*/p | grep : | awk -F / '{ print $2 }'
         # analysis plugins
anal
asm
          # assembler/disassembler plugins
         # binary format parsing plugins
bin
          # breakpoint plugins
bp
          # core plugins (implement new commands)
core
         # encrypt/decrypt/hash/...
crypto
debug
          # debugger backends
egg
          # shellcode encoders, etc
fs
         # filesystems and partition tables
io
         # io plugins
         # embedded scripting languages
lang
parse
          # disassembler parsing plugins
          # arch register logic
reg
```

#### Listing plugins

Some r2 tools have the -L flag to list all the plugins associated to the functionality.

```
rasm2 -L  # list asm plugins
r2 -L  # list io plugins
rabin2 -L  # list bin plugins
rahash2 -L  # list hash/crypto/encoding plugins
```

There are more plugins in r2land, we can list them from inside r2, and this is done by using the L suffix.

Those are some of the commands:

```
L # list core plugins

iL # list bin plugins

dL # list debug plugins

mL # list fs plugins

ph # print support hash algoriths
```

You can use the ? as value to get the possible values in the associated eval vars.

```
e asm.arch=? # list assembler/disassembler plugins
e anal.arch=? # list analysis plugins
```

#### Notes

Note there are some inconsistencies that most likely will be fixed in the future radare2 versions.

### IO plugins

All access to files, network, debugger and all input/output in general is wrapped by an IO abstraction layer that allows radare to treat all data as if it were just a file.

IO plugins are the ones used to wrap the open, read, write and 'system' on virtual file systems. You can make radare understand anything as a plain file. E.g. a socket connection, a remote radare session, a file, a process, a device, a gdb session.

So, when radare reads a block of bytes, it is the task of an IO plugin to get these bytes from any place and put them into internal buffer. An IO plugin is chosen by a file's URI to be opened. Some examples:

```
• Debugging URIs
$ r2 dbg:///bin/ls<br />
$ r2 pid://1927
  • Remote sessions
$ r2 rap://:1234<br />
$ r2 rap://<host>:1234//bin/ls
  • Virtual buffers
$ r2 malloc://512<br />
shortcut for
$ r2 -
You can get a list of the radare IO plugins by typing radare2 -L:
$ r2 -L
     ar
              Open ar/lib files [ar|lib]://[file//path] (LGPL3)
rw_
     bfdbg
              BrainFuck Debugger (bfdbg://path/to/file) (LGPL3)
rw_
              Attach to a BOCHS debugger (LGPL3)
rwd bochs
r_d debug
              Native debugger (dbg:///bin/ls dbg://1388 pidof:// waitfor://) (LGPL3) v0.2.0
              open local files using def_mmap:// (LGPL3)
     default
rw_
              Attach to gdbserver, 'qemu -s', gdb://localhost:1234 (LGPL3)
rwd
     gdb
              open gprobe connection using gprobe:// (LGPL3)
     gprobe
rw_
```

```
read/write gzipped files (LGPL3)
rw_
    gzip
              http get (http://rada.re/) (LGPL3)
rw_ http
              Intel HEX file (ihex://eeproms.hex) (LGPL)
rw ihex
              mach debug io (unsupported in this platform) (LGPL)
    mach
    malloc
              memory allocation (malloc://1024 hex://cd8090) (LGPL3)
rw_
              open file using mmap:// (LGPL3)
rw_
    mmap
              null-plugin (null://23) (LGPL3)
    null
rw_
     procpid /proc/pid/mem io (LGPL3)
              ptrace and /proc/pid/mem (if available) io (LGPL3)
rwd
    ptrace
              Attach to QNX pdebug instance, qnx://host:1234 (LGPL3)
rwd qnx
              kernel access API io (r2k://) (LGPL3)
    r2k
rw_
              r2pipe io plugin (MIT)
    r2pipe
rw
    r2web
              r2web io client (r2web://cloud.rada.re/cmd/) (LGPL3)
rw_
              radare network protocol (rap://:port rap://host:port/file) (LGPL3)
rw
    rap
    rbuf
              RBuffer IO plugin: rbuf:// (LGPL)
rw_
              read memory from myself using 'self://' (LGPL3)
rw
     self
     shm
              shared memory resources (shm://key) (LGPL3)
rw_
              sparse buffer allocation (sparse://1024 sparse://) (LGPL3)
rw_
    sparse
              load files via TCP (listen or connect) (LGPL3)
rw_
    tcp
rwd windbg
              Attach to a KD debugger (windbg://socket) (LGPL3)
rwd winedbg Wine-dbg io and debug.io plugin for r2 (MIT)
              Open zip files [apk|ipa|zip|zipall]://[file//path] (BSD)
rw_
    zip
```

# Python plugins

At first, to be able to write a plugins in Python for radare2 you need to install r2lang plugin: r2pm -i lang-python. Note - in the following examples there are missing functions of the actual decoding for the sake of readability!

For this you need to do this: 1. import r2lang and from r2lang import R (for constants) 2. Make a function with 2 subfunctions - assemble and disassemble and returning plugin structure - for RAsm plugin

```
def mycpu(a):
    def assemble(s):
        return [1, 2, 3, 4]

def disassemble(memview, addr):
        try:
        opcode = get_opcode(memview) # https://docs.python.org/3/library/stdtypes.html#
        opstr = optbl[opcode][1]
        return [4, opstr]
    except:
        return [4, "unknown"]
```

3. This structure should contain a pointers to these 2 functions - assemble

```
and disassemble
   return {
            "name" : "mycpu",
           "arch" : "mycpu",
           "bits" : 32,
           "endian" : R.R_SYS_ENDIAN_LITTLE,
           "license" : "GPL",
           "desc" : "MYCPU disasm",
           "assemble" : assemble,
           "disassemble" : disassemble,
   }
  4. Make a function with 2 subfunctions - set_reg_profile and op and
    returning plugin structure - for RAnal plugin
def mycpu_anal(a):
      def set_reg_profile():
       profile = "=PC pc\n" + \
        "=SP
              sp\n" + \
        "qpr
               r0 .32 0
                          0\n" + \
              r1 .32 4 0 n'' + 
        "gpr
        "qpr r2 .32 8 0 n'' + 
        "gpr r3 .32 12 0\n" + \
        "qpr
               r4 .32 16 0\n" + \
        "gpr r5 .32 20 0 \n" + \
               sp .32 24 0\n" + \
        "qpr
        "gpr pc .32 28 0\n"
       return profile
   def op(memview, pc):
       analop = {
           "type" : R.R_ANAL_OP_TYPE_NULL,
           "cycles" : 0,
           "stackop" : 0,
           "stackptr" : 0,
           "ptr" : -1,
           "jump" : -1,
           "addr" : 0,
           "eob" : False,
           "esil" : "",
       }
       try:
           opcode = get_opcode(memview) # https://docs.python.org/3/library/stdtypes.html#
           esilstr = optbl[opcode][2]
           if optbl[opcode][0] == "J": # it's jump
               analop["type"] = R.R_ANAL_OP_TYPE_JMP
```

```
analop["jump"] = decode_jump(opcode, j_mask)
                esilstr = jump_esil(esilstr, opcode, j_mask)
        except:
            result = analop
        # Don't forget to return proper instruction size!
        return [4, result]
  5. This structure should contain a pointers to these 2 functions -
    set_reg_profile and op
    return {
            "name" : "mycpu",
            "arch" : "mycpu",
            "bits" : 32,
            "license" : "GPL",
            "desc" : "MYCPU anal",
            "esil" : 1,
            "set_reg_profile" : set_reg_profile,
            "op" : op,
    }
  6. (Optional) To add extra information about op sizes and alignment, add a
    archinfo subfunction and point to it in the structure
def mycpu_anal(a):
    def set_reg_profile():
        [...]
    def archinfo(query):
        if query == R.R_ANAL_ARCHINFO_MIN_OP_SIZE:
            return 1
        if query == R.R_ANAL_ARCHINFO_MAX_OP_SIZE:
        if query == R.R_ANAL_ARCHINFO_INV_OP_SIZE: # invalid op size
            return 2
        return 0
    def analop(memview, pc):
        [...]
    return {
            "name" : "mycpu",
            "arch" : "mycpu",
            "bits" : 32,
            "license" : "GPL",
            "desc" : "MYCPU anal",
            "esil" : 1,
            "set_reg_profile" : set_reg_profile,
            "archinfo": archinfo,
```

```
"op" : op,
}
7. Register both plugins using r2lang.plugin("asm") and r2lang.plugin("anal")
    respectively
print("Registering MYCPU disasm plugin...")
print(r2lang.plugin("asm", mycpu))
print("Registering MYCPU analysis plugin...")
print(r2lang.plugin("anal", mycpu_anal))
You can combine everything in one file and load it using -i option:
r2 -I mycpu.py some_file.bin
Or you can load it from the r2 shell: #!python mycpu.py
See also:
    Python
    Javascript
```

#### Implementing new format plugin in Python

return [0]

Note - in the following examples there are missing functions of the actual decoding for the sake of readability!

and so on. Please be sure of the parameters for each function and format of returns. Note, that functions entries, sections, imports, relocs returns a list of special formed dictionaries - each with a different type. Other functions

return just a list of numerical values, even if single element one. There is a special function, which returns information about the file - info:

```
def info(binf):
    return [{
        "type" : "le",
        "bclass" : "le",
        "rclass" : "le",
        "os" : "OS/2",
        "subsystem" : "CLI",
        "machine" : "IBM",
        "arch" : "x86",
        "has_va" : 0,
        "bits" : 32,
        "big_endian" : 0,
        "dbg_info" : 0,
        }]
```

3. This structure should contain a pointers to the most important functions like check\_bytes, load and load\_bytes, entries, relocs, imports.

```
return {
        "name" : "le",
        "desc" : "OS/2 LE/LX format",
        "license" : "GPL",
        "load" : load,
        "load_bytes" : load_bytes,
        "destroy" : destroy,
        "check_bytes" : check_bytes,
        "baddr" : baddr,
        "entries" : entries,
        "sections" : sections,
        "imports" : imports,
        "symbols" : symbols,
        "relocs" : relocs,
        "binsym" : binsym,
        "info" : info,
}
```

4. Then you need to register it as a file format plugin:

```
print("Registering OS/2 LE/LX plugin...")
print(r2lang.plugin("bin", le_format))
```

# Creating an r2pm package of the plugin

As you remember radare 2 has its own packaging manager and we can easily add newly written plugin for everyone to access.

All packages are located in radare2-pm repository, and have very simple text format.

```
R2PM_BEGIN
```

```
R2PM_GIT "https://github.com/user/mycpu"
R2PM_DESC "[r2-arch] MYCPU disassembler and analyzer plugins"

R2PM_INSTALL() {
    ${MAKE} clean
    ${MAKE} all || exit 1
    ${MAKE} install R2PM_PLUGDIR="${R2PM_PLUGDIR}"
}

R2PM_UNINSTALL() {
    rm -f "${R2PM_PLUGDIR}/asm_mycpu."*
    rm -f "${R2PM_PLUGDIR}/anal_mycpu."*
}
```

Then add it in the /db directory of radare2-pm repository and send a pull request to the mainline.

# Testing the plugin

This plugin is used by rasm2 and r2. You can verify that the plugin is properly loaded with this command:

Let's open an empty file using the 'mycpu' arch and write some random code there.

0x00000006	7ef6	bl r15, r6
8000000x0	2701	xor r0, 1
0x0000000a	9826	mov r2, 6
0x000000c	478d	xor r8, 13
0x0000000e	6b6b	store r6, 11
0x0000010	1382	add r8, r2
0x00000012	7f15	ret

Yay! it works.. and the mandatory oneliner too!

r2 -nqamycpu -cwoR -cpd' 10' -

### Radare2 Reference Card

This chapter is based on the Radare 2 reference card by Thanat0s, which is under the GNU GPL. Original license is as follows:

This card may be freely distributed under the terms of the GNU general public licence - Copyright by ThanatOs - v0.1 -

#### Survival Guide

Those are the basic commands you will want to know and use for moving around a binary and getting information about it.

Command	Description
s (tab)	Seek to a different place
x [nbytes]	Hexdump of nbytes, \$b by default
aa	Auto analyze
pdf@ funcname	Disassemble function (main, fcn, etc.)
f fcn(Tab)	List functions
f str(Tab)	List strings
fr [flagname] [newname]	Rename flag
psz [offset]~grep	Print strings and grep for one
axF [flag]	Find cross reference for a flag

### Flags

Flags are like bookmarks, but they carry some extra information like size, tags or associated flagspace. Use the **f** command to list, set, get them.

Command	Description
f	List flags
fd \$\$	Describe an offset
fj	Display flags in JSON

Command	Description
fl fx [flagname] fC [name] [comment]	Show flag length Show hexdump of flag Set flag comment

### Flagspaces

Flags are created into a flagspace, by default none is selected, and listing flags will list them all. To display a subset of flags you can use the fs command to restrict it.

Command	Description
fs fs * fs [space]	Display flagspaces Select all flagspaces Select one flagspace

#### Information

Binary files have information stored inside the headers. The i command uses the RBin api and allows us to the same things rabin2 do. Those are the most common ones.

Command	Description
ii	Information on imports
iI	Info on binary
ie	Display entrypoint
iS	Display sections
ir	Display relocations
iz	List strings (izz, izzz)

### Print string

There are different ways to represent a string in memory. The ps command allows us to print it in utf-16, pascal, zero terminated, .. formats.

Command	Description
psz [offset] psb [offset] psx [offset] psp [offset] psw [offset]	Print zero terminated string Print strings in current block Show string with scaped chars Print pascal string Print wide string

## Visual mode

The visual mode is the standard interactive interface of radare2.

To enter in visual mode use the v or V command, and then you'll only have to press keys to get the actions happen instead of commands.

Command	Description
V	Enter visual mode
p/P	Rotate modes (hex, disasm, debug, words, buf)
c c	Toggle (c)ursor
q	Back to Radare shell
hjkl	Move around (or HJKL) (left-down-up-right)
Enter	Follow address of jump/call
sS	Step/step over
0	Toggle asm.pseudo and asm.esil
	Seek to program counter
/	In cursor mode, search in current block
:cmd	Run radare command
;[-]cmt	Add/remove comment
/*+-[]	Change block size, [] = resize hex.cols
<,>	Seek aligned to block size
i/a/A	(i)nsert hex, (a)ssemble code, visual (A)ssembler
b	Toggle breakpoint
В	Browse evals, symbols, flags, classes,
d[f?]	Define function, data, code,
D	Enter visual diff mode (set diff.from/to)
e	Edit eval configuration variables
f/F	Set/unset flag
gG	Go seek to begin and end of file (0-\$s)
$\mathrm{mK/'K}$	Mark/go to Key (any key)
M	Walk the mounted filesystems
n/N	Seek next/prev function/flag/hit (scr.nkey)
C	Toggle (C)olors
R	Randomize color palette (ecr)
$\mathrm{tT}$	Tab related. see also tab
v	Visual code analysis menu
V	(V)iew graph (agv?)
wW	Seek cursor to next/prev word
$\mathrm{uU}$	Undo/redo seek
X	Show xrefs of current func from/to data/code
yY	Copy and paste selection
Z	fold/unfold comments in diassembly

## Searching

There are many situations where we need to find a value inside a binary or in some specific regions. Use the e search.in=? command to choose where the / command may search for the given value.

Command	Description
/ foo\00	Search for string 'foo\0'
/b	Search backwards
//	Repeat last search
/w foo	Search for wide string $f \circ 0 \circ 0$
/wi foo	Search for wide string ignoring case
/! ff	Search for first occurrence not matching
/i foo	Search for string 'foo' ignoring case
/e /E.F/i	Match regular expression
/x a1b2c3	Search for bytes; spaces and uppercase nibbles are
	allowed, same as $/x$ A1 B2 C3
/x a1c3	Search for bytes ignoring some nibbles (auto-generates
	mask, in this example: ff00ff)
/x a1b2:fff3	Search for bytes with mask (specify individual bits)
/d 101112	Search for a deltified sequence of bytes
/!x 00	Inverse hexa search (find first byte $!= 0x00$ )
/c  jmp  [esp]	Search for asm code (see search.asmstr)
/a jmp eax	Assemble opcode and search its bytes
/A	Search for AES expanded keys
/r sym.printf	Analyze opcode reference an offset
$/\mathrm{R}$	Search for ROP gadgets
/P	Show offset of previous instruction
/m magicfile	Search for matching magic file
/p patternsize	Search for pattern of given size
z min max	Search for strings of given size
/v[?248] num	Look for a asm.bigendian 32bit value

### Saving (Broken)

This feature has broken and not been resolved at the time of writing these words (Nov.16th 2020). check #Issue 6945: META - Project files and #Issue 17034 for more details.

To save your analysis for now, write your own script which records the function name, variable name, etc. for example:

```
vim sample_A.r2
```

- e scr.utf8 = false
- s 0x000403ce0

```
aaa
s fcn.00403130
afn return_delta_to_heapaddr
afvn iter var_04h
```

### Usable variables in expression

The ?? command will display the variables that can be used in any math operation inside the r2 shell. For example, using the ? \$\$ command to evaluate a number or ?v to just the value in one format.

All commands in r2 that accept a number supports the use of those variables.

<u></u>	Description
Command	Description
,	tualsnek) \$\forall \text{Snon-temporary virtual seek}
\$?	last comparison value
\$alias=value	alias commands (simple macros)
\$b	block size
B	base address (aligned lowest map address)
\$f	jump fail address (e.g. $jz 0x10 => next instruction)$
\$fl	flag length (size) at current address (fla; pD \$1 @ entry0)
\$F	current function size
\$FB	begin of function
\$Fb	address of the current basic block
\$Fs	size of the current basic block
\$FE	end of function
\$FS	function size
\$Fj	function jump destination
\$Ff	function false destination
\$FI	function instructions
c,r	get width and height of terminal
\$Cn	get nth call of function
Dn	get nth data reference in function
\$D	current debug map base address?v \$D @ rsp
\$DD	current debug map size
\$e	1 if end of block, else 0
\$j	jump address (e.g. jmp $0x10$ , jz $0x10 => 0x10$ )
\$Ja	get nth jump of function
\$Xn	get nth xref of function
\$1	opcode length
m	opcode memory reference (e.g. mov eax, $[0x10] = 0x10$ )
\$M	map address (lowest map address)
\$o	here (current disk io offset)
\$p	getpid()
\$P	pid of children (only in debug)

Command	Description
\$s	file size
\$S	section offset
\$SS	section size
v	opcode immediate value (e.g. lui $a0.0x8010 => 0x8010$ )
\$w	get word size, 4 if asm.bits=32, 8 if 64,
$\{ev\}$	get value of eval config variable
$r{reg}$	get value of named register
$k\{kv\}$	get value of an sdb query value
\$s{flag}	get size of flag
RNum	\$variables usable in math expressions

#### Scripting

Radare2 provides a wide set of a features to automate boring work. It ranges from the simple sequencing of the commands to the calling scripts/another programs via IPC (Inter-Process Communication), called r2pipe.

As mentioned a few times before there is an ability to sequence commands using ; semicolon operator.

[0x00404800] > pd 1 ; ao 1

0x00404800 b827e66100 mov eax, 0x61e627 ; "tab"

address: 0x404800

opcode: mov eax, 0x61e627

prefix: 0

bytes: b827e66100 ptr: 0x0061e627

refptr: 0
size: 5
type: mov

esil: 6415911,rax,=

stack: null
family: cpu
[0x00404800]>

It simply runs the second command after finishing the first one, like in a shell.

The second important way to sequence the commands is with a simple pipe |

#### ao|grep address

Note, the I pipe only can pipe output of r2 commands to external (shell) commands, like system programs or builtin shell commands. There is a similar way to sequence r2 commands, using the backtick operator `command`. The quoted part will undergo command substitution and the output will be used as an argument of the command line.

For example, we want to see a few bytes of the memory at the address referred to by the 'mov eax, addr' instruction. We can do that without jumping to it, using a sequence of commands:

```
[0x00404800] > pd 1
              0x00404800
                                                                     ; "tab"
                              b827e66100
                                             mov eax, 0x61e627
[0x00404800] > ao
address: 0x404800
opcode: mov eax, 0x61e627
prefix: 0
bytes: b827e66100
ptr: 0x0061e627
refptr: 0
size: 5
type: mov
esil: 6415911, rax,=
stack: null
family: cpu
[0x00404800] > ao~ptr[1]
0x0061e627
0
[0x00404800] > px 10 @ `ao~ptr[1]`
- offset - 0 1 2 3 4 5 6 7 8 9 A B C D E F 0123456789ABCDEF
0x0061e627 7461 6200 2e69 6e74 6572
                                                      tab..inter
[0x00404800]>
```

And of course it's possible to redirect the output of an r2 command into a file, using the > and >> commands

```
[0x00404800] > px 10 @ `ao~ptr[1]` > example.txt
[0x00404800] > px 10 @ `ao~ptr[1]` >> example.txt
```

Radare2 also provides quite a few Unix type file processing commands like head, tail, cat, grep and many more. One such command is Uniq, which can be used to filter a file to display only non-duplicate content. So to make a new file with only unique strings, you can do:

```
[0x00404800] > uniq file > uniq_file
```

The head command can be used to see the first N number of lines in the file, similarly tail command allows the last N number of lines to be seen.

```
[0x00404800]> head 3 foodtypes.txt
1 Protein
2 Carbohydrate
3 Fat
[0x00404800]> tail 2 foodtypes.txt
3 Shake
4 Milk
```

The join command could be used to merge two different files with common first field

```
[0x00404800]> cat foodtypes.txt
1 Protein
2 Carbohydrate
3 Fat
[0x00404800]> cat foods.txt
1 Cheese
2 Potato
3 Butter
[0x00404800]> join foodtypes foods.txt
1 Protein Cheese
2 Carbohydrate Potato
3 Fat Butter
```

Similarly, sorting the content is also possible with the sort command. A typical example could be:

```
[0x00404800]> sort file
eleven
five
five
great
one
one
radare
```

The \$? command describes several helpful variables you can use to do similar actions even more easily, like the \$v "immediate value" variable, or the \$m opcode memory reference variable.

# Loops

One of the most common task in automation is looping through something, there are multiple ways to do this in radare2.

We can loop over flags:

```
00 flagname-regex
```

For example, we want to see function information with afi command:

```
[0x004047d6] > afi
#
offset: 0x004047d0
name: entry0
```

size: 42 realsz: 42

stackframe: 0 call-convention: amd64 cyclomatic-complexity: 1 bits: 64 type: fcn [NEW] num-bbs: 1 edges: 0 end-bbs: 1 call-refs: 0x00402450 C data-refs: 0x004136c0 0x00413660 0x004027e0 code-xrefs: data-xrefs: locals:0 args: 0 diff: type: new [0x004047d6] >

Now let's say, for example, that we'd like see a particular field from this output for all functions found by analysis. We can do that with a loop over all function flags (whose names begin with fcn.):

```
[0x004047d6]> fs functions [0x004047d6]> afi @@ fcn.* ~name
```

This command will extract the name field from the afi output of every flag with a name matching the regexp fcn.\*. There are also a predefined loop called @@f, which runs your command on every functions found by r2:

```
[0x004047d6] > afi @@f ~name
```

We can also loop over a list of offsets, using the following syntax:

```
@@=1 2 3 ... N
```

For example, say we want to see the opcode information for 2 offsets: the current one, and at current + 2:

[0x004047d6]> ao @@=\$\$ \$\$+2 address: 0x4047d6 opcode: mov rdx, rsp prefix: 0 bytes: 4889e2 refptr: 0 size: 3 type: mov esil: rsp,rdx,= stack: null family: cpu address: 0x4047d8 opcode: loop 0x404822

```
prefix: 0
bytes: e248
refptr: 0
size: 2
type: cjmp
esil: 1,rcx,-=,rcx,?{,4212770,rip,=,}
jump: 0x00404822
fail: 0x004047da
stack: null
cond: al
family: cpu
[0x004047d6]>
```

Note we're using the \$\$ variable which evaluates to the current offset. Also note that \$\$+2 is evaluated before looping, so we can use the simple arithmetic expressions.

A third way to loop is by having the offsets be loaded from a file. This file should contain one offset per line.

```
[0x004047d0]> ?v $$ > offsets.txt
[0x004047d0]> ?v $$+2 >> offsets.txt
[0x004047d0]> !cat offsets.txt
4047d0
4047d2
[0x004047d0]> pi 1 @@.offsets.txt
xor ebp, ebp
mov r9, rdx
```

radare2 also offers various foreach constructs for looping. One of the most useful is for looping through all the instructions of a function:

```
[0x004047d0] > pdf
/ (fcn) entry0 42
; UNKNOWN XREF from 0x00400018 (unk)
|; DATA XREF from 0x004064bf (sub.strlen_460)
|; DATA XREF from 0x00406511 (sub.strlen_460)
|; DATA XREF from 0x0040b080 (unk)
|; DATA XREF from 0x0040b0ef (unk)
|0x004047d0| xor ebp, ebp
|0x004047d2 \mod r9, rdx
|0x004047d5 | pop rsi
|0x004047d6 mov rdx, rsp
|0x004047d9 and rsp, 0xfffffffffffff
|0x004047dd| push rax
|0x004047de push rsp
|0x004047df mov r8, 0x4136c0
|0x004047e6 mov rcx, 0x413660
                                  ; "AWA..AVI..AUI..ATL.%.."
```

```
OA..AVI..AUI.
|0x004047ed mov rdi, main
                                    ; "AWAVAUATUH..S..H...." @
0
|0x004047f4 call sym.imp.__libc_start_main
\0x004047f9 hlt
[0x004047d0] > pi 1 @@i
mov r9, rdx
pop rsi
mov rdx, rsp
and rsp, 0xfffffffffffff0
push rax
push rsp
mov r8, 0x4136c0
mov rcx, 0x413660
mov rdi, main
call sym.imp.__libc_start_main
hlt
```

In this example the command pi 1 runs over all the instructions in the current function (entry0). There are other options too (not complete list, check @@? for more information): - @@k sdbquery - iterate over all offsets returned by that sdbquery - @@t- iterate over on all threads (see dp) - @@b - iterate over all basic blocks of current function (see afb) - @@f - iterate over all functions (see aflq)

The last kind of looping lets you loop through predefined iterator types:

- symbols
- imports
- registers
- threads
- comments
- functions
- flags

This is done using the **@@@** command. The previous example of listing information about functions can also be done using the **@@@** command:

```
[0x004047d6]> afi @@@ functions ~name
```

This will extract name field from afi output and will output a huge list of function names. We can choose only the second column, to remove the redundant name: on every line:

```
[0x004047d6] > afi @@@ functions ~name[1]
```

Beware, @@@ is not compatible with JSON commands.

## Macros

Apart from simple sequencing and looping, radare 2 allows to write simple macros, using this construction:

```
[0x00404800] > (qwe; pd 4; ao)
```

This will define a macro called 'qwe' which runs sequentially first 'pd 4' then 'ao'. Calling the macro using syntax . (macro) is simple:

```
[0x00404800] > (qwe; pd 4; ao)
[0x00404800] > .(qwe)
                                     ; "tab"
0x00404800 mov eax, 0x61e627
0x00404805 push rbp
0x00404806 sub rax, section_end.LOAD1
0x0040480c mov rbp, rsp
address: 0x404800
opcode: mov eax, 0x61e627
prefix: 0
bytes: b827e66100
ptr: 0x0061e627
refptr: 0
size: 5
type: mov
esil: 6415911, rax,=
stack: null
family: cpu
[0x00404800]>
To list available macroses simply call (*:
[0x00404800] > (*
(qwe ; pd 4; ao)
And if want to remove some macro, just add '-' before the name:
[0x00404800] > (-qwe)
Macro 'qwe' removed.
[0x00404800]>
```

Moreover, it's possible to create a macro that takes arguments, which comes in handy in some simple scripting situations. To create a macro that takes arguments you simply add them to macro definition.

```
[0x00404800]

[0x004047d0]> (foo x y; pd $0; s +$1)

[0x004047d0]> .(foo 5 6)

;-- entry0:

0x004047d0 xor ebp, ebp
```

As you can see, the arguments are named by index, starting from 0: \$0, \$1, ...

#### Aliases

radare2 also offers aliases which might help you save time by quickly executing your most used commands. They are under \$?

The general usage of the feature is: \$alias=cmd

```
[0x00404800] > $disas=pdf
```

The above command will create an alias disas for pdf. The following command prints the disassembly of the main function.

```
[0x00404800] > $disas @ main
```

Apart from commands, you can also alias a text to be printed, when called.

```
[0x00404800]> $my_alias=$test input [0x00404800]> $my_alias test input
```

To undefine alias, use \$alias=:

```
[0x00404800]> $pmore='b 300;px'
[0x00404800]> $
$pmore
[0x00404800]> $pmore=
[0x00404800]> $
```

A single \$\$ in the above will list all defined aliases. It's also possible check the aliased command of an alias:

```
[0x00404800] > $pmore?
b 200; px
```

Can we create an alias contains alias? The answer is yes:

```
0x00000040
0x0000050
          4000 0000 0000 0000 4000 0000 0000 0000
                                              @.....
0x00000060
          d802 0000 0000 0000 d802 0000 0000 0000
                                              . . . . . . . . . . . . . . . .
          0800 0000 0000 0000 0300 0000 0400 0000
0x00000070
                                              . . . . . . . . . . . . . . . .
08000000x0
          1803 0000 0000 0000 1803 0000 0000 0000
                                              . . . . . . . . . . . . . . . .
0x00000090
          1803 0000 0000 0000 1c00 0000 0000 0000
0x000000a0
          . . . . . . . . . . . . . . . .
          0x00000b0
0x00000c0 0000 0000 0000 0000
[0x00000000]>
```

# R2pipe

The r2pipe api was initially designed for NodeJS in order to support reusing the web's r2.js API from the commandline. The r2pipe module permits interacting with r2 instances in different methods:

- spawn pipes (r2 -0)
- http queries (cloud friendly)
- tcp socket (r2 -c)

	pipe	spawn	async	http	tcp	rap	json
nodejs	x	x	x	x	x	-	x
python	x	x	-	x	x	x	x
swift	x	x	x	x	-	-	x
dotnet	x	x	x	x	-	-	-
haskell	x	x	-	x	-	-	x
java	-	x	-	x	-	-	-
golang	x	x	-	-	-	-	x
ruby	x	x	-	-	-	-	x
rust	x	x	-	-	-	-	X
vala	-	x	x	-	-	-	-
erlang	x	x	-	-	-	-	-
newlisp	x	-	-	-	-	-	-
dlang	X	-	-	-	-	-	x
perl	x	-	-	-	-	-	-

# Examples

#### Python

```
$ pip install r2pipe
import r2pipe
r2 = r2pipe.open("/bin/ls")
```

```
r2.cmd('aa')
print(r2.cmd("afl"))
print(r2.cmdj("aflj")) # evaluates JSONs and returns an object

NodeJS
```

Use this command to install the r2pipe bindings

\$ npm install r2pipe

```
Here's a sample hello world

const r2pipe = require('r2pipe');
r2pipe.open('/bin/ls', (err, res) => {
  if (err) {
   throw err;
  }
  r2.cmd ('af @ entry0', function (o) {
   r2.cmd ("pdf @ entry0", function (o) {
     console.log (o);
     r.quit ()
  });
  });
});
```

Checkout the GIT repository for more examples and details.

https://github.com/radareorg/radare2-r2pipe/blob/master/nodejs/r2pipe/README.md

#### Go

```
$ r2pm -i r2pipe-go
https://github.com/radare/r2pipe-go
package main

import (
    "fmt"
    "github.com/radare/r2pipe-go"
)

func main() {
    r2p, err := r2pipe.NewPipe("/bin/ls")
    if err != nil {
        panic(err)
    }
    defer r2p.Close()
    buf1, err := r2p.Cmd("?E Hello World")
    if err != nil {
```

```
panic(err)
  fmt.Println(buf1)
Rust
$ cat Cargo.toml
[dependencies]
r2pipe = "*"
#[macro_use]
extern crate r2pipe;
use r2pipe::R2Pipe;
fn main() {
  let mut r2p = open_pipe!(Some("/bin/ls")).unwrap();
  println!("{:?}", r2p.cmd("?e Hello World"));
  let json = r2p.cmdj("ij").unwrap();
  println!("{}", serde_json::to_string_pretty(&json).unwrap());
  println!("ARCH {}", json["bin"]["arch"]);
 r2p.close();
Ruby
$ gem install r2pipe
require 'r2pipe'
puts 'r2pipe ruby api demo'
puts '======='
r2p = R2Pipe.new '/bin/ls'
puts r2p.cmd 'pi 5'
puts r2p.cmd 'pij 1'
puts r2p.json(r2p.cmd 'pij 1')
puts r2p.cmd 'px 64'
r2p.quit
Perl
#!/usr/bin/perl
use R2::Pipe;
use strict;
my r = R2::Pipe->new ("/bin/ls");
print $r->cmd ("pd 5")."\n";
```

```
print $r->cmd ("px 64")."\n";
$r->quit ();
Erlang
#!/usr/bin/env escript
%% -*- erlang -*-
%%! -smp enable
%% -sname hr
-mode(compile).
-export([main/1]).
main(_Args) ->
  %% adding r2pipe to modulepath, set it to your r2pipe_erl location
 R2pipePATH = filename:dirname(escript:script_name()) ++ "/ebin",
 true = code:add_pathz(R2pipePATH),
  \%\% initializing the link with r2
 H = r2pipe:init(lpipe),
  %% all work goes here
  io:format("~s", [r2pipe:cmd(H, "i")]).
Haskell
import R2pipe
import qualified Data.ByteString.Lazy as L
showMainFunction ctx = do
 cmd ctx "s main"
 L.putStr =<< cmd ctx "pD `fl $$`"</pre>
main = do
  -- Run r2 locally
 open "/bin/ls" >>= showMainFunction
  -- Connect to r2 via HTTP (e.g. if "r2 -qc=h /bin/ls" is running)
  open "http://127.0.0.1:9090" >>= showMainFunction
Dotnet
using System;
using System.Collections.Generic;
using System.Diagnostics;
using System.Linq;
```

```
using System.Text;
using System.Threading.Tasks;
using r2pipe;
namespace LocalExample {
  class Program {
    static void Main(string[] args) {
#if __MonoCS_
      using(IR2Pipe pipe = new R2Pipe("/bin/ls")) {
#else
      using (IR2Pipe pipe = new R2Pipe(@"C:\Windows\notepad.exe",
        @"C:\radare2\radare2.exe")) {
#endif
        Console.WriteLine("Hello r2! " + pipe.RunCommand("?V"));
        Task<string> async = pipe.RunCommandAsync("?V");
        Console.WriteLine("Hello async r2!" + async.Result);
        QueuedR2Pipe qr2 = new QueuedR2Pipe(pipe);
        qr2.Enqueue(new R2Command("x", (string result) => {
             Console.WriteLine("Result of x:\n {0}", result); }));
        qr2.Enqueue(new R2Command("pi 10", (string result) => {
             Console.WriteLine("Result of pi 10:\n {0}", result); }));
        qr2.ExecuteCommands();
   }
 }
}
Java
import org.radare.r2pipe.R2Pipe;
public class Test {
 public static void main (String[] args) {
    try {
      R2Pipe r2p = new R2Pipe ("/bin/ls");
      // new R2Pipe ("http://cloud.rada.re/cmd/", true);
      System.out.println (r2p.cmd ("pd 10"));
      System.out.println (r2p.cmd ("px 32"));
     r2p.quit();
    } catch (Exception e) {
      System.err.println (e);
   }
 }
}
```

#### Swift

```
if let r2p = R2Pipe(url:nil) {
  r2p.cmd ("?V", closure:{
    (str:String?) in
    if let s = str {
      print ("Version: \(s)");
      exit (0);
    } else {
      debugPrint ("R2PIPE. Error");
      exit (1);
    }
  });
  NSRunLoop.currentRunLoop().run();
} else {
  print ("Needs to run from r2")
Vala
public static int main (string[] args) {
  MainLoop loop = new MainLoop ();
  var r2p = new R2Pipe ("/bin/ls");
  r2p.cmd ("pi 4", (x) => {
    stdout.printf ("Disassembly:\n%s\n", x);
    r2p.cmd ("ie", (x) => {
      stdout.printf ("Entrypoint:\n%s\n", x);
      r2p.cmd ("q");
    });
  });
  ChildWatch.add (r2p.child_pid, (pid, status) => {
    Process.close_pid (pid);
    loop.quit ();
  });
  loop.run ();
  return 0;
}
{\bf NewLisp}
(load "r2pipe.lsp")
(println "pd 3:\n" (r2pipe:cmd "pd 3"))
(exit)
```

## Dlang

```
import std.stdio;
import r2pipe;

void main() {
   auto r2 = r2pipe.open ();
   writeln ("Hello "~ r2.cmd("?e World"));
   writeln ("Hello "~ r2.cmd("?e Works"));

   string uri = r2.cmdj("ij")["core"]["uri"].str;
   writeln ("Uri: ",uri);
}
```

#### **Search Automation**

The cmd.hit configuration variable is used to define a radare2 command to be executed when a matching entry is found by the search engine. If you want to run several commands, separate them with ;. Alternatively, you can arrange them in a separate script, and then invoke it as a whole with . script-file-name command. For example:

```
[0x00404888] > e cmd.hit = p8 8
[0x00404888] > / lib
Searching 3 bytes from 0x00400000 to 0x0041ae08: 6c 69 62
hits: 9
0x00400239 hit4_0 "lib64/ld-linux-x86-64.so.2"
31ed4989d15e4889
0x00400f19 hit4_1 "libselinux.so.1"
31ed4989d15e4889
0x00400fae hit4_2 "librt.so.1"
31ed4989d15e4889
0x00400fc7 hit4_3 "libacl.so.1"
31ed4989d15e4889
0x00401004 hit4 4 "libc.so.6"
31ed4989d15e4889
0x004013ce hit4_5 "libc_start_main"
31ed4989d15e4889
0x00416542 hit4_6 "libs/"
31ed4989d15e4889
0x00417160 hit4_7 "lib/xstrtol.c"
31ed4989d15e4889
0x00417578 hit4_8 "lib"
31ed4989d15e4889
```

## Searching Backwards

Sometimes you want to find a keyword backwards. This is, before the current offset, to do this you can seek back and search forward by adding some search.from/to restrictions, or use the /b command.

```
[0x100001200]> / nop

0x100004b15 hit0_0 .STUWabcdefghiklmnopqrstuvwxbin/ls.

0x100004f50 hit0_1 .STUWabcdefghiklmnopqrstuwx1] [file .

[0x100001200]> /b nop

[0x100001200]> s 0x100004f50p

[0x100004f50]> /b nop

0x100004b15 hit2_0 .STUWabcdefghiklmnopqrstuvwxbin/ls.

[0x100004f50]>
```

Note that /b is doing the same as /, but backward, so what if we want to use /x backward? We can use /bx, and the same goes for other search subcommands:

```
[0x100001200] > /x 90
0x100001a23 hit1_0 90
0x10000248f hit1_1 90
0x1000027b2 hit1 2 90
0x100002b2e hit1 3 90
0x1000032b8 hit1_4 90
0x100003454 hit1_5 90
0x100003468 hit1_6 90
0x10000355b hit1 7 90
0x100003647 hit1_8 90
0x1000037ac hit1_9 90
0x10000389c hit1_10 90
0x100003c5c hit1_11 90
[0x100001200] > /bx 90
[0x100001200] > s 0x10000355b
[0x10000355b] > /bx 90
0x100003468 hit3_0 90
0x100003454 hit3_1 90
0x1000032b8 hit3_2 90
0x100002b2e hit3 3 90
0x1000027b2 hit3_4 90
0x10000248f hit3_5 90
0x100001a23 hit3_6 90
[0x10000355b]>
```

#### Basic Search

A basic search for a plain text string in a file would be something like:

```
$ r2 -q -c "/ lib" /bin/ls
Searching 3 bytes from 0x00400000 to 0x0041ae08: 6c 69 62
hits: 9
0x00400239 hit0_0 "lib64/ld-linux-x86-64.so.2"
0x00400f19 hit0_1 "libselinux.so.1"
0x00400fae hit0_2 "librt.so.1"
0x00400fc7 hit0_3 "libacl.so.1"
0x00401004 hit0_4 "libc.so.6"
0x004013ce hit0_5 "libc_start_main"
0x00416542 hit0_6 "libs/"
0x00417160 hit0_7 "lib/xstrtol.c"
0x00417578 hit0_8 "lib"
```

As can be seen from the output above, radare2 generates a "hit" flag for every entry found. You can then use the ps command to see the strings stored at the offsets marked by the flags in this group, and they will have names of the form hit0\_<index>:

```
[0x00404888]> / ls ... [0x00404888]> ps @ hit0_0 lseek
```

You can search for wide-char strings (e.g., unicode letters) using the /w command:

```
[0x00000000] > /w Hello 0 results found.
```

To perform a case-insensitive search for strings use /i:

```
[0x0040488f]> /i Stallman
Searching 8 bytes from 0x00400238 to 0x0040488f: 53 74 61 6c 6c 6d 61 6e
[#]hits: 004138 < 0x0040488f hits = 0
```

It is possible to specify hexadecimal escape sequences in the search string by prepending them with  $\xspace$ x:

```
[0x00000000] > / x7FELF
```

if, instead, you are searching for a string of hexadecimal values, you're probably better of using the /x command:

```
[0x00000000]> /x 7F454C46
```

If you want to mask some nibble during the search you can use the symbol . to allow any nibble value to match:

```
[0x00407354]> /x 80..80
0x0040d4b6 hit3_0 800080
0x0040d4c8 hit3_1 808080
0x004058a6 hit3_2 80fb80
```

You may not know some bit values of your hexadecimal pattern. Thus you may use a bit mask on your pattern. Each bit set to one in the mask indicates to search the bit value in the pattern. A bit set to zero in the mask indicates that the value of a matching value can be 0 or 1:

```
[0x00407354]> /x 808080:ff80ff
0x0040d4c8 hit4_0 808080
0x0040d7b0 hit4_1 808080
0x004058a6 hit4 2 80fb80
```

You can notice that the command /x 808080:ff00ff is equivalent to the command /x 80..80.

Once the search is done, the results are stored in the searches flag space.

To remove "hit" flags after you do not need them anymore, use the f- hit\* command.

Often, during long search sessions, you will need to launch the latest search more than once. You can use the // command to repeat the last search.

```
[0x00000f2a] > // ; repeat last search
```

#### Configuring Search Options

The radare2 search engine can be configured through several configuration variables, modifiable with the e command.

e search.flags = true ; if enabled, create flags on hits

The search.align variable is used to limit valid search hits to certain alignment. For example, with e search.align=4 you will see only hits found at 4-bytes aligned offsets.

The search.flags boolean variable instructs the search engine to flag hits so that they can be referenced later. If a currently running search is interrupted with Ctrl-C keyboard sequence, current search position is flagged with search\_stop.

## Searching for Bytes

The radare2 search engine is based on work done by esteve, plus multiple features implemented on top of it. It supports multiple keyword searches, binary masks, and hexadecimal values. It automatically creates flags for search hit locations ease future referencing.

Search is initiated by / command.

| /0 [n]

```
[0x00000000]> /?
|Usage: /[!bf] [arg]Search stuff (see 'e??search' for options)
|Use io.va for searching in non virtual addressing spaces
| / foo\x00
                          search for string 'foo\0'
| /j foo\x00
                          search for string 'foo\0' (json output)
| /! ff
                          search for first occurrence not matching, command modifier
| /!x 00
                          inverse hexa search (find first byte != 0x00)
| /+ /bin/sh
                          construct the string with chunks
1 //
                          repeat last search
                          assemble opcode and search its bytes
/a jmp eax
| /A jmp
                          find analyzed instructions of this type (/A? for help)
                          search backwards, command modifier, followed by other command
| /b
| /B
                          search recognized RBin headers
| /c jmp [esp]
                          search for asm code matching the given string
| /ce rsp,rbp
                          search for esil expressions matching
| /C[ar]
                          search for crypto materials
| /d 101112
                          search for a deltified sequence of bytes
| /e /E.F/i
                          match regular expression
| /E esil-expr
                          offset matching given esil expressions %%= here
                          search forwards, command modifier, followed by other command
| /F file [off] [sz]
                          search contents of file with offset and size
                          find all graph paths A to B (/gg follow jumps, see search.count as
| /g[g] [from]
anal.depth)
| /h[t] [hash] [len]
                          find block matching this hash. See ph
| /i foo
                          search for string 'foo' ignoring case
| /m magicfile
                          search for matching magic file (use blocksize)
| /M
                          search for known filesystems and mount them automatically
/o[n]
                          show offset of n instructions backward
```

same as /o, but with a different fallback if anal cannot be used

```
/p patternsize
                          search for pattern of given size
| /P patternsize
                          search similar blocks
/r[erwx][?] sym.printf analyze opcode reference an offset (/re for esil)
                         search for matching ROP gadgets, semicolon-separated
| /R [grepopcode]
| /s
                          search for all syscalls in a region (EXPERIMENTAL)
                          look for an `cfg.bigendian` 32bit value
| /v[1248] value
                          look for an `cfg.bigendian` 32bit value in range
| /V[1248] min max
                          search for wide string f\00\00
| /w foo
| /wi foo
                          search for wide string ignoring case 'f\0o\0o\0'
| /x ff..33
                          search for hex string ignoring some nibbles
| /x ff0033
                          search for hex string
/x ff43:ffd0
                          search for hexpair with mask
/z min max
                         search for strings of given size
```

Because everything is treated as a file in radare2, it does not matter whether you search in a socket, a remote device, in process memory, or a file.

note that '/' starts multiline comment. It's not for searching. type '/' to end comment.

## Pattern Matching Search

The /p command allows you to apply repeated pattern searches on IO backend storage. It is possible to identify repeated byte sequences without explicitly specifying them. The only command's parameter sets minimum detectable pattern length. Here is an example:

```
[0x0000000]> /p 10
```

This command output will show different patterns found and how many times each of them is encountered.

It is possible to search patterns with a known difference between consecutive bytes with /d command. For example, the command to search all the patterns with the first and second bytes having the first bit which differs and the second and third bytes with the second bit which differs is:

```
[0x00000000] > /d 0102
Searching 2 bytes in [0x0-0x400]
hits: 2
0x00000118 hit2_0 9a9b9d
0x000000202 hit2_1 a4a5a7
```

## Assembler Search

If you want to search for a certain assembler opcodes, you can use /a commands.

The command /ad/ jmp [esp] searches for the specified category of assembly mnemonic:

```
[0x00404888] > /ad/ jmp qword [rdx]

f hit_0 @ 0x0040e50d  # 2: jmp qword [rdx]

f hit_1 @ 0x00418dbb  # 2: jmp qword [rdx]

f hit_2 @ 0x00418fcb  # 3: jmp qword [rdx]

f hit_3 @ 0x004196ab  # 6: jmp qword [rdx]

f hit_4 @ 0x00419bf3  # 3: jmp qword [rdx]

f hit_5 @ 0x00419c1b  # 3: jmp qword [rdx]

f hit_6 @ 0x00419c43  # 3: jmp qword [rdx]
```

The command /a jmp eax assembles a string to machine code, and then searches for the resulting bytes:

```
[0x00404888] > /a jmp eax
hits: 1
0x004048e7 hit3 0 ffe00f1f8000000000b8
```

#### Searching for Cryptography materials

#### Searching AES keys

radare2 is capable of finding **expanded AES** keys with /ca command. It searches from current seek position up to the search.distance limit, or until end of file is reached. You can interrupt current search by pressing Ctrl-C. For example, to look for AES keys in a memory dump:

```
0x00000000]> /ca
Searching 40 bytes in [0x0-0x1ab]
hits: 1
0x000000fb hit0_0 6920e299a5202a6d656e636869746f2a
```

The output length gives you the size of the AES key used: 128, 192 or 256 bits. If you are simply looking for plaintext AES keys in your binary, /ca will not find them they must have been expanded by the key expansion algorithm.

#### Searching private keys and certificates

/cr command implements the search of private keys (RSA and ECC). /cd command implements a similar feature to search certificates.

```
[0x00000000]> /cr
Searching 11 bytes in [0x0-0x15a]
hits: 2
```

 $0 x 0 0 0 0 0 0 fa \ hit1\_0 \ 302 e 0 2 0 1 0 0 3 0 0 5 0 6 0 3 2 b 6 5 7 0 0 4 2 2 0 4 2 0 fb 3 d5 8 8 2 9 6 fed 5 6 9 4 ff 7 0 4 9 ea fb 7 4 4 9 0 b f 4 b c 6 4 6 7 6 2 b$ 

#### **Entropy** analysis

p=e might give some hints if high entropy sections are found trying to cover up a hardcoded secret.

There is the possibility to delimit entropy sections for later use with \s command:

```
[0x00000000] > b
0x100
[0x00000000] > b 4096
[0x00000000] > /s
0x00100000 - 0x00101000 \sim 5.556094
0x014e2c88 - 0x014e3c88 \sim 0.000000
0x01434374 - 0x01435374 \sim 6.332087
0x01435374 - 0x0144c374 \sim 3.664636
0x0144c374 - 0x0144d374 \sim 1.664368
0x0144d374 - 0x0144f374 \sim 4.229199
0x0144f374 - 0x01451374 \sim 2.000000
(\ldots)
[0x00000000] > /s*
f entropy section 0 0x00001000 0x00100000
f entropy_section_1 0x00001000 0x014e2c88
f entropy_section_2 0x00001000 0x01434374
f entropy_section_3 0x00017000 0x01435374
f entropy_section_4 0x00001000 0x0144c374
f entropy_section_5 0x00002000 0x0144d374
f entropy_section_6 0x00002000 0x0144f374
```

The blocksize is increased to 4096 bytes from the default 100 bytes so that the entropy search /s can work on reasonably sized chunks for entropy analysis. The sections flags can be applied with the dot operator, ./s\* and then looped through px 32 @@ entropy\*.

## Signatures

Radare2 has its own format of the signatures, allowing to both load/apply and create them on the fly. They are available under the z command namespace:

```
[0x00000000] > z?
Usage: z[*j-aof/cs] [args]
                              # Manage zignatures
Ιz
               show zignatures
| z.
               find matching zignatures in current offset
| zb[?][n=5]
               search for best match
               show zignatures in radare format
| z*
               show zignatures in quiet mode
| zq
               show zignatures in json format
l zj
               show zignatures in sdb format
| zk
| z-zignature
               delete zignature
| z-*
               delete all zignatures
| za[?]
               add zignature
               generate zignatures (alias for zaF)
| zg
| zo[?]
               manage zignature files
               manage FLIRT signatures
| zf[?]
```

```
| z/[?] search zignatures
| zc[?] compare current zignspace zignatures with another one
| zs[?] manage zignspaces
| zi show zignatures matching information
```

To load the created signature file you need to load it from SDB file using zo command or from the compressed SDB file using zoz command.

To create signature you need to make function first, then you can create it from the function:

```
r2 /bin/ls
[0x000051c0] > aaa # this creates functions, including 'entry0'
[0x000051c0] > zaf entry0 entry
[0x000051c0] > z
entry:
 bytes: 31ed4989d15e4889e24883e4f050544c.......48......48.......ff.....
 graph: cc=1 nbbs=1 edges=0 ebbs=1
  offset: 0x000051c0
[0x000051c0] >
As you can see it made a new signature with a name entry from a function
entry0. You can show it in JSON format too, which can be useful for scripting:
[0x000051c0] > zj~{}
{
    "name": "entry",
    "bytes": "31ed4989d15e4889e24883e4f050544c......48......48.........ff...
    "graph": {
      "cc": "1",
      "nbbs": "1",
      "edges": "0",
      "ebbs": "1"
    },
    "offset": 20928,
    "refs": [
 }
[0x000051c0]>
To remove it just run z-entry.
```

If you want, instead, to save all created signatures, you need to save it into the SDB file using command zos myentry.

Then we can apply them. Lets open a file again:

```
r2 /bin/ls
```

```
-- Log On. Hack In. Go Anywhere. Get Everything.
[0x000051c0] > zo myentry
[0x000051c0] > z
entry:
  bytes: 31ed4989d15e4889e24883e4f050544c......48......48............
  graph: cc=1 nbbs=1 edges=0 ebbs=1
  offset: 0x000051c0
[0x000051c0]>
This means that the signatures were successfully loaded from the file myentry
and now we can search matching functions:
[0x000051c0] > z.
[+] searching 0x000051c0 - 0x000052c0
[+] searching function metrics
hits: 1
[0x000051c0]>
Note that z. command just checks the signatures against the current address.
To search signatures across the all file we need to do a bit different thing. There
is an important moment though, if we just run it "as is" - it wont find anything:
[0x000051c0] > z/
[+] searching 0x0021dfd0 - 0x002203e8
[+] searching function metrics
hits: 0
[0x000051c0]>
Note the searching address - this is because we need to adjust the searching
range first:
[0x000051c0] > e search.in=io.section
[0x000051c0] > z/
[+] searching 0x000038b0 - 0x00015898
[+] searching function metrics
hits: 1
[0x000051c0] >
We are setting the search mode to io.section (it was file by default) to search
in the current section (assuming we are currently in the .text section of course).
Now we can check, what radare2 found for us:
[0x000051c0] > pd 5
;-- entry0:
;-- sign.bytes.entry_0:
0x000051c0
                 31ed
                                 xor ebp, ebp
0x000051c2
                 4989d1
                                 mov r9, rdx
0x000051c5
                                 pop rsi
                 5e
                                 mov rdx, rsp
0x000051c6
                 4889e2
```

and rsp, 0xfffffffffffff0

4883e4f0

0x000051c9

#### [0x000051c0]>

Here we can see the comment of entry0, which is taken from the ELF parsing, but also the sign.bytes.entry\_0, which is exactly the result of matching signature.

Signatures configuration stored in the zign. config vars' namespace:

```
[0x000051c0] > e? zign.
      zign.autoload: Autoload all zignatures located in ~/.local/share/radare2/zigns
         zign.bytes: Use bytes patterns for matching
  zign.diff.bthresh: Threshold for diffing zign bytes [0, 1] (see zc?)
  zign.diff.gthresh: Threshold for diffing zign graphs [0, 1] (see zc?)
         zign.graph: Use graph metrics for matching
          zign.hash: Use Hash for matching
         zign.maxsz: Maximum zignature length
         zign.mincc: Minimum cyclomatic complexity for matching
         zign.minsz: Minimum zignature length for matching
         zign.offset: Use original offset for matching
        zign.prefix: Default prefix for zignatures matches
           zign.refs: Use references for matching
     zign.threshold: Minimum similarity required for inclusion in zb output
         zign.types: Use types for matching
[0x000051c0]>
```

## Finding Best Matches zb

Often you know the signature should exist somewhere in a binary but  $\mathbf{z}/$  and  $\mathbf{z}$ . still fail. This is often due to very minor differences between the signature and the function. Maybe the compiler switched two instructions, or your signature is not for the correct function version. In these situations the  $\mathbf{z}\mathbf{b}$  commands can still help point you in the right direction by listing near matches.

The **zb** (zign best) command will show the top 5 closest signatures to a function. Each will contain a score between 1.0 and 0.0.

```
[0x0041e390]> s sym.fclose

[0x0040fc10]> zb

0.96032  0.92400 B  0.99664 G  sym.fclose

0.65971  0.35600 B  0.96342 G  sym._nl_expand_alias

0.65770  0.37800 B  0.93740 G  sym.fdopen

0.65112  0.35000 B  0.95225 G  sym._run_exit_handlers

0.62532  0.34800 B  0.90264 G  sym._cxa_finalize
```

In the above example, zb correctly associated the sym.fclose signature to the current function. The z/ and z. command would have failed to match here since both the Byte and Graph scores are less then 1.0. A 30% separation between the first and second place results is also a good indication of a correct match.

The zbr (zign best reverse) accepts a zignature name and attempts to find the closet matching functions. Use an analysis command, like aa to find functions first.

```
[0x00401b20] > aa
[x] Analyze all flags starting with sym. and entry0 (aa)
[0x00401b20] > zo ./libc.sdb
[0x00401b20] > zbr sym.__libc_malloc 10
sym.malloc
0.65245   0.40600 B   0.89891 G
                          sym. mid memalign
sym. IO flush all lockp
0.59200 0.28200 B 0.90201 G
                          sym. IO file underflow
0.57802 0.30400 B 0.85204 G
                          sym.__libc_realloc
0.57094 0.35200 B 0.78988 G
                          sym.__calloc
sym._IO_un_link.part.0
sym._IO_cleanup
0.56064 0.26000 B 0.86127 G
                          sym.intel_check_word.constprop.0
0.55726   0.28400 B   0.83051 G
                          sym.linear_search_fdes
```

#### Tools

Radare2 is not just the only tool provided by the radare2 project. The rest if chapters in this book are focused on explaining the use of the radare2 tool, this chapter will focus on explaining all the other companion tools that are shipped inside the radare2 project.

All the functionalities provided by the different APIs and plugins have also different tools to allow to use them from the commandline and integrate them with shellscripts easily.

Thanks to the ortogonal design of the framework it is possible to do all the things that r2 is able from different places:

- these companion tools
- native library apis
- scripting with r2pipe
- the r2 shell

## Visual Mode

The visual mode is a more user-friendly interface alternative to radare2's command-line prompt. It allows easy navigation, has a cursor mode for se-

lecting bytes, and offers numerous key bindings to simplify debugger use. To enter visual mode, use V command. To exit from it back to command line, press  $\alpha$ .

#### Navigation

Navigation can be done using HJKL or arrow keys and PgUp/PgDown keys. It also understands usual Home/End keys. Like in Vim the movements can be repeated by preceding the navigation key with the number, for example 5j will move down for 5 lines, or 21 will move 2 characters right.

Visual Mode

#### Print Modes, a.k.a.: Panels

The Visual mode uses "print modes" which are basically different panels that you can rotate. By default those are:

Hexdump panel -> Disassembly panel -> Debugger panel -> Hexadecimal words dump panel -> Hex-less hexdump panel -> Op analysis color map panel -> Annotated hexdump panel -> Hexdump panel -> [...]

Notice that the top of the panel contains the command which is used, for example for the disassembly panel:

[0x00404890 16% 120 /bin/ls] > pd \$r @ entry0

#### Getting Help

To see help on all key bindings defined for visual mode, press?:

#### Visual mode help:

```
?
         show this help
??
         show the user-friendly hud
%
         in cursor mode finds matching pair, or toggle autoblocksz
@
         redraw screen every 1s (multi-user view)
         seek to the begining of the function
         enter into the visual panels mode
         enter the flag/comment/functions/.. hud (same as VF_)
         set cmd.vprompt (top row)
         set cmd.cprompt (right column)
         seek to program counter
         toggle visual split mode
         toggle the column mode (uses pC..)
         in cursor mode search in current block
        run radare command
; [-] cmt add/remove comment
```

```
seek to beginning of current function
 [1-9]
          follow jmp/call identified by shortcut (like;[1])
 ,file
          add a link to the text file
 /*+-[]
          change block size, [] = resize hex.cols
 </>
          seek aligned to block size (seek cursor in cursor mode)
          (a)ssemble code, visual (A)ssembler
 a/A
          browse symbols, flags, configurations, classes, ...
 В
          toggle breakpoint
 c/C
          toggle (c)ursor and (C)olors
 d[f?]
          define function, data, code, ...
          enter visual diff mode (set diff.from/to
          edit eval configuration variables
 f/F
          set/unset or browse flags. f- to unset, F to browse, ...
 gG
          go seek to begin and end of file (0-$s)
hjkl
          move around (or HJKL) (left-down-up-right)
          insert hex or string (in hexdump) use tab to toggle
 mK/'K
          mark/go to Key (any key)
 М
          walk the mounted filesystems
 n/N
          seek next/prev function/flag/hit (scr.nkey)
          go/seek to given offset
 g
 0
          toggle asm.pseudo and asm.esil
 p/P
          rotate print modes (hex, disasm, debug, words, buf)
          back to radare shell
 q
          refresh screen / in cursor mode browse comments
 r
 R
          randomize color palette (ecr)
 sS
          step / step over
          browse types
 t
          enter textlog chat console (TT)
 Т
          undo/redo seek
 пIJ
          visual function/vars code analysis menu
 v
 V
          (V) iew graph using cmd.graph (agv?)
 wW
          seek cursor to next/prev word
 xx
          show xrefs/refs of current function from/to data/code
 yY
          copy and paste selection
          fold/unfold comments in disassembly
 z
 Z
          toggle zoom mode
          follow address of jump/call
Function Keys: (See 'e key.'), defaults to:
 F2
          toggle breakpoint
 F4
          run to cursor
  F7
          single step
 F8
          step over
 F9
          continue
```

## Visual Assembler

You can use Visual Mode to assemble code using A. For example let's replace the push by a jmp:

Before

Notice the preview of the disassembly and arrows:

After

You need to open the file in writing mode (r2 -w or oo+) in order to patch the file. You can also use the cache mode: e io.cache = true and wc?.

Remember that patching files in debug mode only patch the memory not the file.

# Visual Configuration Editor

Ve or e in visual mode allows you to edit radare2 configuration visually. For example, if you want to change the assembly display just select asm in the list and choose your assembly display flavor.

First Select asm

Example switch to pseudo disassembly:

Pseudo disassembly disabled

Pseudo disassembly enabled

# Visual Disassembly

## Navigation

Move within the Disassembly using arrow keys or hjkl. Use g to seek directly to a flag or an offset, type it when requested by the prompt: [offset]>. Follow a jump or a call using the number of your keyboard [0-9] and the number on the right in disassembly to follow a call or a jump. In this example typing 1 on the keyboard would follow the call to sym.imp.\_\_libc\_start\_main and therefore, seek at the offset of this symbol.

0x00404894 e857dcffff call sym.imp.\_\_libc\_start\_main ;[1]

Seek back to the previous location using u, U will allow you to redo the seek.

#### d as define

d can be used to change the type of data of the current block, several basic types/structures are available as well as more advanced one using pf template:

To improve code readability you can change how radare2 presents numerical values in disassembly, by default most of disassembly display numerical value as hexadecimal. Sometimes you would like to view it as a decimal, binary or even custom defined constant. To change value format you can use d following by i then choose what base to work in, this is the equivalent to ahi:

```
d \rightarrow i \rightarrow ...
0x004048f7
d \rightarrow i \rightarrow 10
0x004048f7
d \rightarrow i \rightarrow 2
0x004048f7
d \rightarrow i \rightarrow 2
0x004048f7
d \rightarrow i \rightarrow 2
d \rightarrow i \rightarrow 3
```

#### Usage of the Cursor for Inserting/Patching...

Remember that, to be able to actually edit files loaded in radare2, you have to start it with the -w option. Otherwise a file is opened in read-only mode.

Pressing lowercase **c** toggles the cursor mode. When this mode is active, the currently selected byte (or byte range) is highlighted.

#### Cursor at 0x00404896

The cursor is used to select a range of bytes or simply to point to a byte. You can use the cursor to create a named flag at specifc location. To do so, seek to the required position, then press f and enter a name for a flag. If the file was opened in write mode using the <code>-w</code> flag or the <code>o+</code> command, you can also use the cursor to overwrite a selected range with new values. To do so, select a range of bytes (with HJKL and SHIFT key pressed), then press i and enter the hexpair values for the new data. The data will be repeated as needed to fill the range selected. For example:

```
<select 10 bytes in visual mode using SHIFT+HJKL>
s 'i' and then enter '12 34'>
```

The 10 bytes you have selected will be changed to "12 34 12 34 12 ...".

The Visual Assembler is a feature that provides a live-preview while you type in new instructions to patch into the disassembly. To use it, seek or place the cursor

at the wanted location and hit the 'A' key. To provide multiple instructions, separate them with semicolons, ;.

#### **XREF**

When radare 2 has discovered a XREF during the analysis, it will show you the information in the Visual Disassembly using XREF tag:

```
; DATA XREF from 0x00402e0e (unk)
str.David_MacKenzie:
```

To see where this string is called, press x, if you want to jump to the location where the data is used then press the corresponding number [0-9] on your keyboard. (This functionality is similar to axt)

X corresponds to the reverse operation aka axf.

#### Function Argument display

To enable this view use this config var e dbg.funcarg = true funcarg

#### Add a comment

To add a comment press;.

#### Type other commands

Quickly type commands using:.

## Search

/: allows highlighting of strings in the current display. :cmd allows you to use one of the "/?" commands that perform more specialized searches.

#### The HUDS

#### The "UserFriendly HUD"

The "UserFriendly HUD" can be accessed using the ?? key-combination. This HUD acts as an interactive Cheat Sheet that one can use to more easily find and execute commands. This HUD is particularly useful for new-comers. For experienced users, the other HUDS which are more activity-specific may be more useful.

## The "flag/comment/functions/.. HUD"

This HUD can be displayed using the \_ key, it shows a list of all the flags defined and lets you jump to them. Using the keyboard you can quickly filter the list down to a flag that contains a specific pattern.

Hud input mode can be closed using ^C. It will also exit when backspace is pressed when the user input string is empty.

## Tweaking the Disassembly

The disassembly's look-and-feel is controlled using the "asm.\* configuration keys, which can be changed using the e command. All configuration keys can also be edited through the Visual Configuration Editor.

#### Visual Configuration Editor

This HUD can be accessed using the e key in visual mode. The editor allows you to easily examine and change radare2's configuration. For example, if you want to change something about the disassembly display, select asm from the list, navigate to the item you wish to modify it, then select it by hitting Enter. If the item is a boolean variable, it will toggle, otherwise you will be prompted to provide a new value.

First Select asm

Example switch to pseudo disassembly:

Pseudo disassembly disabled

Pseudo disassembly enabled

Following are some example of eval variable related to disassembly.

#### Examples

asm.arch: Change Architecture && asm.bits: Word size in bits at assembler You can view the list of all arch using e asm.arch=?

```
e asm.arch = dalvik
0x00404870
                31ed4989
                                cmp-long v237, v73, v137
0x00404874
                d15e4889
                                rsub-int v14, v5, 0x8948
0x00404878
                e24883e4
                                ushr-int/lit8 v72, v131, 0xe4
0x0040487c
                f0505449c7c0
                                +invoke-object-init-range {}, method+18772 ;[0]
0x00404882
                90244100
                                add-int v36, v65, v0
e asm.bits = 16
0000:4870
               31ed
                               xor bp, bp
0000:4872
               49
                               dec cx
0000:4873
               89d1
                               mov cx, dx
```

```
      0000:4875
      5e
      pop si

      0000:4876
      48
      dec ax

      0000:4877
      89e2
      mov dx, sp
```

This latest operation can also be done using & in Visual mode.

#### asm.pseudo: Enable pseudo syntax

#### asm.syntax: Select assembly syntax (intel, att, masm...)

```
e asm.syntax = att
0x00404870
               31ed
                              xor %ebp, %ebp
0x00404872
               4989d1
                              mov %rdx, %r9
0x00404875
               5e
                              pop %rsi
                              mov %rsp, %rdx
0x00404876
               4889e2
0x00404879
               4883e4f0
                              and $0xfffffffffffff, %rsp
```

## asm.describe: Show opcode description

```
e asm.describe = true

0x00404870 xor ebp, ebp ; logical exclusive or

0x00404872 mov r9, rdx ; moves data from src to dst

0x00404875 pop rsi ; pops last element of stack and stores the result in argument

0x00404876 mov rdx, rsp ; moves data from src to dst

0x00404879 and rsp, -0xf ; binary and operation between src and dst, stores result on dst
```

## Visual Panels

#### Concept

Visual Panels is characterized by the following core functionalities:

- 1. Split Screen
- 2. Display multiple screens such as Symbols, Registers, Stack, as well as custom panels
- 3. Menu will cover all those commonly used commands for you so that you don't have to memorize any of them

CUI met some useful GUI as the menu, that is Visual Panels.

Panels can be accessed by using v or by using! from the visual mode.

#### Overview

Panels Overview

#### Commands

```
|Visual Ascii Art Panels:
         split the current panel vertically
         split the current panel horizontally
        run r2 command in prompt
        add/remove comment
         start the hud input mode
1 \
         show the user-friendly hud
| ?
        show this help
| !
        run r2048 game
         seek to PC or entrypoint
| *
         show decompiler in the current panel
| "
         create a panel from the list and replace the current one
        highlight the keyword
1 /
1 (
        toggle snow
        toggle cache
| &
| [1-9] follow jmp/call identified by shortcut (like ;[1])
         (space) toggle graph / panels
        go to the next panel
| tab
| Enter start Zoom mode
        toggle auto update for decompiler
        browse symbols, flags, configurations, classes, ...
l c
        toggle cursor
I C
        toggle color
l d
        define in the current address. Same as Vd
| D
         show disassembly in the current panel
         change title and command of current panel
| e
| f
         set/add filter keywords
| F
        remove all the filters
        go/seek to given offset
l g
l G
        go/seek to highlight
Ιi
        insert hex
        move around (left-down-up-right)
| hjkl
| HJKL
        move around (left-down-up-right) by page
l m
         select the menu panel
l M
        open new custom frame
| n/N
         seek next/prev function/flag/hit (scr.nkey)
| p/P
        rotate panel layout
         quit, or close a tab
Ιq
         close all the tabs and quit
I Q
| r
         toggle callhints/jmphints/leahints
```

```
l R
        randomize color palette (ecr)
| s/S
         step in / step over
| t/T
        tab prompt / close a tab
        undo / redo seek
| u/U
l w
         start Window mode
l V
         go to the graph mode
         show xrefs/refs of current function from/to data/code
| xX
l z
         swap current panel with the first one
```

## Basic Usage

Use tab to move around the panels until you get to the targeted panel. Then, use hjkl, just like in vim, to scroll the panel you are currently on. Use S and s to step over/in, and all the panels should be updated dynamically while you are debugging. Either in the Registers or Stack panels, you can edit the values by inserting hex. This will be explained later. While hitting tab can help you moving between panels, it is highly recommended to use m to open the menu. As usual, you can use hjkl to move around the menu and will find tons of useful stuff there. You can also press " to quickly browse through the different options View offers and change the contents of the selected panel.

## Split Screen

 $\mid$  is for the vertical and  $\neg$  is for the horizontal split. You can delete any panel by pressing X.

Split panels can be resized from Window Mode, which is accessed with w.

## Window Mode Commands

```
|Panels Window mode help:
| ?
         show this help
| ??
         show the user-friendly hud
| Enter
        start Zoom mode
| c
        toggle cursor
| hjkl
        move around (left-down-up-right)
| JK
        resize panels vertically
| HL
        resize panels horizontally
Ιq
         quit Window mode
```

#### **Edit Values**

Either in the Register or Stack panel, you can edit the values. Use c to activate cursor mode and you can move the cursor by pressing hjkl, as usual. Then, hit i, just like the insert mode of vim, to insert a value.

## **Tabs**

Visual Panels also offer tabs to quickly access multiple forms of information easily. Press t to enter Tab Mode. All the tabs numbers will be visible in the top right corner.

By default you will have one tab and you can press t to create a new tab with the same panels and T to create a new panel from scratch.

For traversing through the tabs, you can type in the tab number while in Tab Mode.

And pressing - deletes the tab you are in.

## Saving layouts

You can save your custom layout of your visual panels either by picking the option 'Save Layout' from the File menu of the menu bar or by running:

#### v= test

Where test is the name with which you'd like to save it.

You can open a saved layout by passing the name as the parameter to v:

#### v test

More about that can be found under v?.