The finite element method for the Navier-Stokes equations

Lucas Payne

August 19, 2021

Contents

C	onter	ats .	1					
1	Cor	Continuum mechanics						
	1.1	Newton's laws of motion	3					
		1.1.1 Symmetry, momenta, and inertia	3					
	1.2	The Euler-Lagrange equations: From $F = ma$ to $\frac{\partial \mathcal{L}}{\partial a} - \frac{d}{dt} \frac{\partial \mathcal{L}}{\partial \dot{a}} = 0$	3					
		1.2.1 A Lagrangian of a mechanical system	3					
		1.2.2 The first variation of a functional	4					
		1.2.3 From the Lagrangian to the equations of motion	4					
		1.2.4 Why —?	5					
	1.3	Transport	5					
		1.3.1 Continuity equations and conservation laws	5					
		1.3.2 The Reynolds transport theorem	6					
		1.3.3 Incompressible and compressible transport	8					
		1.3.4 Transport of vector and tensor quantities	8					
	1.4	The kinematics of the continuum	9					
		1.4.1 Position maps	10					
		1.4.2 Velocity	10					
		1.4.3 The deformation and velocity gradients	11					
1.5 The dynamics of the continuum								
		1.5.1 Conservation of mass	12					
		1.5.2 Conservation of linear momentum	12					
		1.5.3 Constitutive relations	14					
2	The	Navier-Stokes equations 1	L 7					
	2.1	Deriving the Navier-Stokes equations	17					
	2.2	Scaling and dimension	17					
		2.2.1 The Reynolds number	17					
	2.3	Stokes flow and the meaning of pressure	17					
			19					
	2.4	Pressure	9					

2	CONTENTS

3	The finite element method						
	3.1	Discre	tizing variational principles	21			
		3.1.1	Solving the Poisson equation	21			
Bi	bliog	graphy		23			

Chapter 1

Continuum mechanics

Corpus omne perseverare in statu suo quiescendi vel movendi uniformiter in directum, nisi quatenus a viribus impressis cogitur statum suum mutare.

Mutationem motus proportionalem esse vi motrici impressae, \mathcal{E} fieri secundum lineam rectam qua vis illa imprimitur.

Actioni contrariam semper & aequalem esse reactionem: sive corporum duorum actiones in se mutuo semper esse aequales & in partes contrarias dirigi.

Newton [1]

1.1 Newton's laws of motion

Newton's three laws, namely those of inertia, force, and equilibrium, have found universal success in application to mechanical systems such as the pendulum, the motion of an rigid body, the evolution of a bending beam, and, as we shall see, the motion of fluid. *Mechanics* could be thought of as the study of physical motion, but the word "physical" might be misleading. Newton's principles are mathematical in nature, applicable to the study of motion in a general sense as some unambiguously measurable state which evolves in time.

1.1.1 Symmetry, momenta, and inertia

Mechanics as a theory of physical motion will require a definition of physical motion. A first attempt might be to posit that "physical states" are representable as points in a finite-dimensional manifold, which we call the configuration space C, which is the case for typical notions of state such as the two angles in a double pendulum, or the position and orientation of a rigid body. We might define a motion as a continuous time-parameterized curve

$$\gamma: [t_1, t_2] \to C.$$

We start in the middle:

Total force = change of momentum.
$$(1.1)$$

In this form, Newton's second law of motion states that a (non-explanatory) measurement of change of momentum will be called "force".

1.2 The Euler-Lagrange equations: From F = ma to $\frac{\partial \mathcal{L}}{\partial q} - \frac{d}{dt} \frac{\partial \mathcal{L}}{\partial \dot{q}} = 0$

1.2.1 A Lagrangian of a mechanical system

Force is an intensive measurement of the change in momentum. In the language of calculus,

$$\int_{s_1}^{s_2} F \, dt = \mathcal{P}(s_2) - \mathcal{P}(s_1) \tag{1.2}$$

for all time subintervals $[s_1, s_2] \subset [t_1, t_2]$. If we restrict F to be conservative and a function only of position q, then we may let $F = -\frac{\partial V}{\partial q}$ for some potential function V. Suppose also that $\mathcal{P} = \frac{\partial T}{\partial \dot{q}}$ for some potential function (called the "kinetic energy") independent of position q. We then define a Lagrangian of the mechanical system to be

$$\mathcal{L}(q, \dot{q}, t) = T(\dot{q}, t) - V(q, t) = \text{kinetic - potential.}$$

By definition, we have the force equation (1.2) as

$$-\int_{s_1}^{s_2} \frac{\partial \mathcal{L}}{\partial q} dt = \frac{\partial \mathcal{L}}{\partial \dot{q}}(s_2) - \frac{\partial \mathcal{L}}{\partial \dot{q}}(s_1).$$

The step toward the calculus of variations (—)

$$\int_{s_1}^{s_2} \frac{\partial \mathcal{L}}{\partial q} h \, dt + \int_{s_1}^{s_2} \frac{\partial \mathcal{L}}{\partial \dot{q}} \frac{dh}{dt} \, dt = 0 \quad \equiv \quad \left\langle \frac{\partial \mathcal{L}}{\partial q}, h \right\rangle + \left\langle \frac{\partial \mathcal{L}}{\partial \dot{q}}, \frac{dh}{dt} \right\rangle = 0. \tag{1.3}$$

Adjointness of differential operator $\frac{d}{dt}$ to $-\frac{d}{dt}$, and integration by parts. (—) By linearity, we then get the reformulation of (1.3) as

$$\left\langle \frac{\partial \mathcal{L}}{\partial q} - \frac{d}{dt} \frac{\partial \mathcal{L}}{\partial \dot{q}}, h \right\rangle = 0$$

for all perturbation functions h.

1.2.2 The first variation of a functional

In the calculus of variations, $\frac{\partial \mathcal{L}}{\partial q} - \frac{d}{dt} \frac{\partial \mathcal{L}}{\partial \dot{q}}$ is an instance of the *Gâteaux derivative*, also called the "first variation" of the functional

$$S[q] := \int_{t_1}^{t_2} \mathcal{L}(q, \dot{q}, t) dt.$$

The first variation measures response of the value of S, called the *action*, to perturbations of the (differentiable) input function q, and is denoted

$$\frac{\delta S}{\delta q(t)} \coloneqq \frac{\partial \mathcal{L}}{\partial q} - \frac{d}{dt} \frac{\partial \mathcal{L}}{\partial \dot{q}}.$$
 (1.4)

The first variation is linear in the perturbation function, and so another term for the Gâteaux derivative could be "functional gradient". Setting this to zero gives the Euler-Lagrange equations, and the practice of determining trajectories of motions as stationary curves of the action is called the "principle of stationary action".

1.2.3 From the Lagrangian to the equations of motion

In the framework of Lagrangian mechanics, $\mathcal{P} := \frac{\partial \mathcal{L}}{\partial \dot{q}}$ is the momentum. If there are d degrees of freedom in the mechanical system, and we suppose that q_1, \dots, q_d are (local) variables of state, then we say that $\mathcal{P}_i := \frac{\partial \mathcal{L}}{\partial \dot{q}_i}$ are *conjugate* to the q_i .

(—) By inducing the equations of motion by a Lagrangian, we get systems with a "physical interpretation" with "physically meaningful" force measurements.

1.3. TRANSPORT 5

1.2.4 Why —?

These variational ideas appear because, no matter if our configuration space is finite-dimensional, time forms a continuum, and therefore if we globally consider the calculus of the motion as a whole, it must be a "variational" calculus. (—)

(—) Physical process, conservation laws, conservative forces (hint at thermodynamics limiting the range of stress tensors?)

When we consider mechanical models of continuum processes, we will see that these same ideas appear in the spatial dimensions too. A variational understanding of a continuum mechanics model leads very easily to a class of methods called Galerkin methods for solving the corresponding (PDE) equations of motion.

1.3 Transport

Before considering continuum processes in the framework of Newtonian and Lagrangian mechanics, we will look at a fundamental notion of a "motion" of a point in a function space. Many continuum models in physics, such as the heat equation, Maxwell's equations, and the equations of fluid motion, are formed by *continuity equations*. These laws posit that the evolution of the state (represented by a function) is due to the transport of the quantity that the function measures, which is either pushed around (by some flux either predetermined or dependent on the current state) or created and destroyed at sources and sinks.

(figure of some manifold embedded in space, and some vector field pushing quantity around)

We consider here the transport of quantities (scalar, vector, and tensor) on a general finite-dimensional manifold M, colloquially called "the continuum". All transporting vector fields (or flux functions) are considered to be tangent to this manifold M.

1.3.1 Continuity equations and conservation laws

The integral form of a continuity equation

Consider some spatial quantity ϕ on M and a flux function j which by which this quantity flows around M. For clarity, we will begin by specializing ϕ to be a scalar, although later we will find it useful to transport vector quantities such as momentum. By definition we want this flux function to just push quantity around, and not create or destroy it: the creation and destruction of quantity is determined by some arbitrary source function s (of the same kind as ϕ). These variables are related by the continuity condition

$$\frac{d}{dt} \int_{\Omega_0} \phi \, dx = \int_{\Omega_0} s \, dx + \int_{\partial \Omega_0} \phi j \cdot (-\hat{n}) \, dx \tag{1.5}$$

for arbitrary control volumes Ω_0 in the continuum. The term $-\hat{n}$ denotes the inward-pointing normal to the boundary of the control volume. This simply says that the change in the total quantity in the fixed control volume is accounted for exactly by that quantity pushed through the boundary by the flux function j, and the internal sources and sinks of quantity s.

The differential form of a continuity equation

A common technique in continuum modelling is the use of Stokes' theorem to simplify integral expressions. Equation (1.5) becomes

$$\frac{\partial \phi}{\partial t} = s - \nabla \cdot (\phi j) \tag{1.6}$$

assuming that ϕj is sufficiently differentiable such that the limiting integral exists. It should be noted that Stokes' theorem and its specializations are really definitions of pointwise quantities such as the divergence and curl as limits of these integral expressions for arbitrarily small regions. Continuity relations are most naturally expressed in form (1.5), while the form (1.6) may be more useful for techniques such as finite differences. For example, it is a theorem of Gauss that in Euclidean space $(M = \mathbb{R}^3)$ we have

$$\nabla \cdot j = \frac{\partial j_x}{\partial x} + \frac{\partial j_y}{\partial y} + \frac{\partial j_z}{\partial z},\tag{1.7}$$

and we get (1.6) in the form

$$\frac{\partial \phi}{\partial t} = s - \nabla \phi \cdot j - \phi \left(\frac{\partial j_x}{\partial x} + \frac{\partial j_y}{\partial y} + \frac{\partial j_z}{\partial z} \right), \tag{1.8}$$

by the product rule. As one equation in a system of PDEs, (1.8) is readily discretized by finite differences. For example, using forward difference in time and central differences in space, our discrete scheme is

$$\frac{\phi(t + \Delta t) - \phi(t)}{\Delta t} = s - \frac{\phi(\hat{x} + e_1 \Delta x/2) - \phi(\hat{x} - e_1 \Delta x/2)}{\Delta x} j_x
- \frac{\phi(\hat{x} + e_2 \Delta y/2) - \phi(\hat{x} - e_2 \Delta y/2)}{\Delta y} j_y
- \frac{\phi(\hat{x} + e_3 \Delta z/2) - \phi(\hat{x} - e_3 \Delta z/2)}{\Delta z} j_z
- \frac{j_x(\hat{x} + e_1 \Delta x/2) - j_x(\hat{x} - e_1 \Delta x/2)}{\Delta x} \phi
- \frac{j_y(\hat{x} + e_2 \Delta y/2) - j_y(\hat{x} - e_2 \Delta y/2)}{\Delta y} \phi
- \frac{j_z(\hat{x} + e_3 \Delta z/2) - j_z(\hat{x} - e_3 \Delta z/2)}{\Delta x} \phi$$
(1.9)

for e_1, e_2, e_3 the standard basis vectors in \mathbb{R}^3 . Later, when we discuss numerical methods for solving continuum models, we will not take this route. The methods of interest, *Galerkin* methods, work naturally with the integral form (1.5). It will be seen later that some constructions in the presentation of Galerkin methods, such as the "weak form" of a PDE, simply undo the differentialization of the original integral form of physical PDEs.

1.3.2 The Reynolds transport theorem

The integral form of Reynolds transport

With our integral formulation of a continuity relation (1.5), the control volume Ω_0 is fixed. We may change our perspective by considering, in addition to the flux function j (which transports quantity ϕ), another vector field \hat{u} which will transport our control volume Ω_0 . The rate of change of some time-dependent quantity γ in this *moving* control volume is expressed as

$$\frac{d}{dt} \int_{\Omega_0(t)} \gamma \, dx,\tag{1.10}$$

1.3. TRANSPORT 7

where $\Omega_0(t)$ implicitly denotes that Ω_0 is being transported under the flow of \hat{u} . Clearly, this rate of change of quantity γ is due to the motion of the control volume,

(a picture of positive and negative contributions at the boundary)

as well as internal changes of γ inside the (fixed) control volume. The formal expression of these contributions to the rate of change (1.10) is

$$\frac{d}{dt} \left[\int_{\Omega_0(t)} \gamma \, dx \right] \bigg|_{t=0} = \int_{\Omega_0(0)} \frac{\partial \gamma}{\partial t} \, dx + \int_{\partial \Omega_0(0)} \gamma \hat{u} \cdot \hat{n} \, dx. \tag{1.11}$$

This result is called the *Reynolds transport theorem*, a generalization of Feynman's popularized "differentiation under the integral sign" [10], otherwise named the Leibniz integral rule.

The differential form of Reynolds transport

In the limit, with the routine application of Stokes' theorem, we can differentialize (1.11) to get

$$\frac{d}{dt} \left[\int_{\Omega_0(t)} \gamma \, dx \right] \bigg|_{t=0} \longrightarrow \frac{\partial \gamma}{\partial t} + \nabla \cdot (\gamma \hat{u}), \tag{1.12}$$

as Ω_0 becomes small. The right-hand-side of (1.12) measures the change in volume of a quantity when a small control volume around the point of evaluation is moved, expanded or contracted by the flow field \hat{u} .

Reynolds transport applied to a continuity equation

Letting our quantity γ in (1.11) be the quantity ϕ transported by flux function j, described in continuity equation (1.5), we get a specialized form of the Reynolds transport theorem for continuity equations. Term $\frac{\partial \gamma}{\partial t}$ in (1.11) becomes $\frac{\partial \phi}{\partial t}$ in the differential form of the continuity equation (1.6), giving

$$\frac{d}{dt} \left[\int_{\Omega_0(t)} \phi \, dx \right] \bigg|_{t=0} = \int_{\Omega_0(0)} -\nabla \cdot (\phi j) + s \, dx + \int_{\partial\Omega_0(0)} \phi \hat{u} \cdot \hat{n} \, dx$$

$$= \int_{\Omega_0(0)} s \, dx + \int_{\partial\Omega_0(0)} \phi (\hat{u} - j) \cdot \hat{n} \, dx$$
(1.13)

by Stokes' theorem. This has a clear interpretation. The $\hat{u} - j$ term is due to us wanting to measure the contributions to the total ϕ due to the moving boundary of Ω_0 , where the motion that matters is *relative* to the flux of the quantity j. Specifically, if we move the control volume by the same flux function j (letting $\hat{u} = j$), we get

$$\frac{d}{dt} \left[\int_{\Omega_0(t)} \phi \, dx \right] \bigg|_{t=0} = \int_{\Omega_0(0)} s \, dx. \tag{1.14}$$

In fact, (1.14) is just another form for the conservation law (1.5), where the "frame of reference" for measurement of ϕ follows the transport of ϕ . This simply means that as we follow some volume of quantity original situated in Ω_0 , a conservation law posits that the only change detected is due to the source function s. In differential form (1.14) becomes

$$\frac{\partial \gamma}{\partial t} + \nabla \cdot (\gamma \hat{u}) = s, \tag{1.15}$$

a succint equivalent to (1.6). The idea of following the flow while making measurements is called the *Lagrangian* perspective, in contrast to the *Eulerian*, fixed, perspective.

1.3.3 Incompressible and compressible transport

Analogous to constraints on the motion of a finite mechanical system, we can constrain possible movement of our continuous quantity to *incompressible transport*. Much like how, in the framework of Lagrangian mechanics, constraints on motion are implicitly enforced by strong "virtual forces", constraining transport to be non-compressing will lead to the notion of *pressure*, when we later consider the dynamics of the continuum.

Incompressibility

Incompressibility of control volumes gives a constraint on the form of a flux function j. We call this constrained flux function j non-compressing. By incompressibility we mean that a control volume being transported by j will have constant volume. While j may transport other quantities, we express incompressibility by requiring the flux function to transport a constant "volume quantity" with a corresponding null source function,

$$\phi_{\text{vol}} = 1$$
, $s_{\text{vol}} = 0$.

The corresponding conservation law, in differential form (1.6), is

$$\frac{\partial \phi_{\text{vol}}}{\partial t} = -\nabla \cdot (\phi_{\text{vol}} j) + s_{\text{vol}} \quad \Rightarrow \quad \nabla \cdot j = 0. \tag{1.16}$$

This is our non-compressing constraint on j, and has a clear interpretation, as there is a non-zero divergence of j if and only if there is an inward or outward flux which would contract or expand a transported control volume.

The material derivative

We define here a differential operator which will be useful later. Assuming an non-compressing flux function j which transports quantity ϕ , the "convective derivative" in (1.15) following a control volume becomes

$$\frac{\partial \phi}{\partial t} + \nabla \cdot (\phi j) = \frac{\partial \phi}{\partial t} + j \cdot \nabla \phi + \phi \nabla \cdot j. \tag{1.17}$$

We define the material derivative to be

$$\frac{D}{Dt} := \frac{\partial}{\partial t} + j \cdot \nabla. \tag{1.18}$$

It is a convention to leave the vector field j implicit, as material derivatives are usually taken with respect to some unambiguous velocity field. The material derivative may be taken with respect to a compressing flux j, in which case it measures change from the perspective of an ideal point mass with no extent under the flow of j. As j has no extent, it can not expand under the flow of j.

(figure of a point mass flowing along a scalar field, and a mass with extent being compressed)

1.3.4 Transport of vector and tensor quantities

All previous discussion on the transport of scalar quantities applies trivially to vector and tensor quantities. This will soonest be of use in the discussion of conservation of linear momentum, a vector quantity However, some notational discussion is needed in order to establish differentialized forms of continuity equations and the Reynolds transport theorem.

Reynolds transport of vector and tensor quantities

For a general tensor quantity Γ , the integral form of Reynolds transport (1.11) is trivially

$$\frac{d}{dt} \left[\int_{\Omega_0(t)} \Gamma \, dx \right] \bigg|_{t=0} = \int_{\Omega_0(0)} \frac{\partial \Gamma}{\partial t} \, dx + \int_{\partial \Omega_0(0)} \Gamma \left(\hat{u} \cdot \hat{n} \right) \, dx. \tag{1.19}$$

The step to the differential form (1.12), however, needs some thought as rearranging

"
$$\Gamma(\hat{u} \cdot \hat{n}) = (\Gamma \hat{u}) \cdot \hat{n}$$
"

in order to apply the divergence theorem makes no sense. However, the divergence ∇ was defined to evaluate the limit of this boundary integral for arbitrarily small Ω_0 . We therefore have a natural generalization of the divergence for arbitrary tensors Ψ , as the limit of the boundary integral of the contraction of Ψ with the outward normal \hat{n} (which is a contravariant vector). The divergence of a rank n tensor is then a rank n-1 tensor,

$$\int_{\Omega_0} \nabla \cdot \Psi \, dx := \int_{\partial \Omega_0} \Psi : \hat{n} \, dx. \tag{1.20}$$

We can then rewrite $\Gamma(\hat{u} \cdot \hat{n})$ in (1.19) as

$$\Gamma\left(\hat{u}\cdot\hat{n}\right) = (\Gamma\otimes\hat{u}):\hat{n},$$

where the tensor product \otimes "defers contraction" of \hat{u} with \hat{n} , by storing it as a component of product tensor $\Gamma \otimes \hat{u}$. This leads to a differentialization of (1.19),

$$\frac{d_{\hat{u}}\Gamma}{d_{\hat{v}}t} = \frac{\partial\Gamma}{\partial t} + \nabla \cdot (\Gamma \otimes \hat{u}). \tag{1.21}$$

Continuity equations for vector and tensor quantities

With the previous ideas from tensor algebra, it will be easy to describe continuity relations for transport of tensors. The integral form of the scalar continuity equation (1.5), generalized to transported tensor Φ , trivially becomes

$$\frac{d}{dt} \int_{\Omega_0} \Phi \, dx = \int_{\partial\Omega_0} \Phi \left(j \cdot (-\hat{n}) \right) \, dx + \int_{\Omega_0} s \, dx. \tag{1.22}$$

By the same tensor algebra as above we have

$$\Phi(j \cdot (-\hat{n})) = -(\Phi \otimes j) : \hat{n},$$

giving (1.22) differentialized as

$$\frac{\partial \Phi}{\partial t} = -\nabla \cdot (\Phi \otimes j) + s. \tag{1.23}$$

1.4 The kinematics of the continuum

Transport equations are just one notion of "physical motion" in a continuum model. These transport equations, with prescribed flux and source functions, determine a continuous process on a fixed domain M. These conserved quantities are time-varying maps from M to some measurement space of scalars or tensors. Each map is a component of the total configuration space C, which clearly must be infinite-dimensional. We now consider another component of C which will let us model a physical domain with alterable shape. In our discussion we will consider a fixed time interval $[t_1, t_2]$ in which our physical motions will take place.

1.4.1 Position maps

We may consider the manifold M as the parametric domain of some points living in an ambient manifold N. We will call this the "position map"

$$y: M \times [t_1, t_2] \to N.$$

In general, y needs not be continuous, differentiable, or invertible. These restrictions are only introduced in accord to the physical meaning of the position map. For example, models of small beam deflections may require continuity, and invertibility to prevent self-intersections.

(figure of abstract square domain mapping to a bent beam, and a figure of a map from a reference configuration to itself.)

As an example, suppose we are modelling the heat distribution of a 2D beam supporting a point load which is also a heat source. We could model the beam geometry as a smooth invertible map $y:[0,1]^2\to\mathbb{R}^2$, letting $M=[0,1]^2$ and $N=\mathbb{R}^2$. The heat distribution on the beam could be represented by a function $h:M\to\mathbb{R}$, and a heat flux function j could be pulled back to M from N.

(picture of this)

Although this model is so far hopelessly incomplete, we can see that position maps and transport equations are fundamental tools used for modelling the *geometry* of a problem.

1.4.2 Velocity

As in the mechanics of a particle, each component of our state $q \in C$ will have a corresponding velocity which "generates" a physical motion of that component. In the case of the position map $y: M \times [t_1, t_2] \to N$, the velocity will be given by a vector in the tangent space of N at y(x) for each parameter $x \in M$. This vector field is denoted \dot{y} . This is the Lagrangian description of motion. We will find it useful to instead use the Eulerian description, where we measure the velocity of the position map in the position domain N. Formally we denote this Eulerian velocity by the letter u, ubiquitous in fluid mechanics, and let

$$u(y,t) := \dot{y}(y^{-1}(y,t),t)$$
 for all valid $y \in N$.

(draw this)

For some transported scalar quantity $\phi: M \times [t_1, t_2] \to \mathbb{R}$, the tangent space at each point of \mathbb{R} is \mathbb{R} , and therefore our velocity is represented by a scalar function $\frac{\partial \phi}{\partial t}$ giving local change in time of $\phi(x)$ for each $x \in M$.

(draw this)

We may denote our total velocities as a state variable \dot{q} . When we have state q, the corresponding velocity \dot{q} will be in the tangent space of C at q, denoted T_qC . We can then define the space of velocities as the tangent bundle of the configuration space,

$$TC = \bigcup_{q \in C} T_q C.$$

1.4.3 The deformation and velocity gradients

We may think of the mechanics of a particle as a special case of our continuum model, where M is a single point. In this case we have only one $x \in M$, so we cannot vary x. However, for a continuum parameter domain M we can take derivatives with respect to our parameter as well as time. We can extract important geometric/kinematic information from the spatial derivatives of our position map y.

The deformation gradient

The gradient of the position map y with respect to parameter $x \in M$ is called the deformation gradient

$$\nabla y$$
. (1.24)

The deformation gradient is equivalent to the *Jacobian matrix*, used to compute the *pushforward* of tangent vectors under the displacement map.

(draw this)

The determinant of the Jacobian matrix is usually denoted $J = \det(\nabla y)$, and is called the Jacobian.

The velocity gradient

Letting u be our Eulerian velocity as defined above, we may express the position map through an ODE,

$$\frac{d}{dt}y(x,t) = u(y(x,t),t), \quad y(x,0) = y_0(x). \tag{1.25}$$

It is common, especially in flow problems, to let M be a subset of N which is the "initial geometry". In this case we could let the initial position map be the identity map

$$y_0(x) = x \in M \subset N$$
.

For example, given an initial disc in \mathbb{R}^2 , we may prescribe a constant Eulerian velocity field u and see how the original disc is "mixed".

(draw this)

We can see that, in this case, it is meaningful to take spatial gradients in (1.25) to derive an ODE for the deformation gradient ∇y :

$$\nabla \frac{d}{dt}y(x,t) = \nabla u(y(x,t),t), \quad \nabla y(x,0) = I,$$
(1.26)

where I is the identity tensor. This is easily visualized.

(draw this)

We can see that the term ∇u is a "differential generator" of the deformation gradient. We call ∇u , the spatial gradient of the Eulerian velocity, the *velocity gradient*.

1.5 The dynamics of the continuum

1.5.1 Conservation of mass

We will take for granted that there is some initial mass density function $\rho_0: M \to \mathbb{R}^+$ which we would like to conserve.

The Lagrangian form of mass conservation

As the position map y evolves, for example under the action of Eulerian velocity field u in the ODE (1.25), we would like a mass density function $\rho: N \to \mathbb{R}^+$ to be greater if the position map "compresses" the material, and smaller if it "stretches" the material. Our aim is that the total mass measured in a control volume of N is the same as in its initial configuration. We can express this by the integral equation

$$\int_{\Omega_0} \rho_0(x) \, dx = \int_{y(\Omega_0, t)} \rho(y, t) \, dy, \tag{1.27}$$

where $y(\Omega_0, t)$ denotes the domain pushed forward by the position map. By the usual change of variables formula we have

$$\int_{\Omega_0} \rho_0(x) dx = \int_{\Omega_0} \det(\nabla y) \rho(y(x, t), t) dx, \qquad (1.28)$$

where $J = \det(\nabla y)$ is the Jacobian, measuring the local change in the volume element due to the change of variables.

(draw this)

As (1.28) must hold identically for all Ω_0 , we have the localized conservation law

$$\rho_0 = \det(\nabla y)\rho. \tag{1.29}$$

The Eulerian form of mass conservation

Conservation law (1.29) is simple. However, it is given in terms of absolute deformation gradient ∇y . Instead of asking how mass is distributed in comparison to its initial configuration, in order to conserve it, we can ask how mass is transported by u. This gives an instance of the continuity equation (1.5), where we have no source:

$$\frac{d}{dt} \int_{\Omega_0} \rho \, dx + \int_{\partial \Omega_0} \rho u \cdot \hat{n} \, dx = 0. \tag{1.30}$$

With application of Stokes' theorem we have

$$\frac{\partial \rho}{\partial t} + \nabla \cdot (\rho u) = 0. \tag{1.31}$$

1.5.2 Conservation of linear momentum

If we conserve the linear momentum ρu , a "quantity of motion", under the flow of u, then we get a continuity equation

$$\frac{d}{dt} \left[\int_{\Omega_0(t)} \rho u \, dx \right] \bigg|_{t=0} = \int_{\Omega_0(0)} \rho g \, dx + \int_{\partial\Omega_0(0)} \hat{t} \, dx, \tag{1.32}$$

a specific realization of the Lagrangian continuity equation (1.14). The Lagrangian perspective is convenient as it allows us to factor out certain forces on a moving piece of material. The term g is a regular body force per unit mass, where ρg corresponds to the source term s in (1.14). The boundary term involving \hat{t} , however, has no analogue in the scalar continuity equation (1.14). This vector term \hat{t} is called the *traction* in continuum mechanics, and measures a local force exerted across the boundary of the control volume due to the immediately adjacent material.

The Euler-Cauchy stress principle

Clearly, in accord with Newton, we would like that two Ω_0 and Ω'_0 which share a boundary element should have equal and opposite tractions across that boundary element. Since the normal \hat{n} represents a boundary element, and is negative for the opposite element, if \hat{t} is linear in \hat{n} we have this required property. We can then let (1.32) become

$$\frac{d}{dt} \left[\int_{\Omega_0(t)} \rho u \, dx \right] \bigg|_{t=0} = \int_{\Omega_0(0)} \rho g \, dx + \int_{\partial\Omega_0(0)} \sigma : \hat{n} \, dx$$
 (1.33)

where σ is termed the Cauchy stress tensor.

Differentializing the Cauchy momentum equation

By application of the Reynolds transport theorem (1.19) to (1.33) we get

$$\frac{d}{dt} \int_{\Omega_0} \rho u \, dx + \int_{\partial\Omega_0} \rho u (u \cdot \hat{n}) \, dx = \int_{\Omega_0} \rho g \, dx + \int_{\partial\Omega_0} \sigma : \hat{n} \, dx. \tag{1.34}$$

Differentializing (1.34), by our previously derived tensor identities, gives

$$\frac{\partial(\rho u)}{\partial t} + \nabla \cdot (\rho u \otimes u) = \rho g + \nabla \cdot \sigma. \tag{1.35}$$

This is called the *conservative form* of the Cauchy momentum equation. We can derive another, possibly more convenient form of (1.35) using the fact that ρ is conserved and has no source. Here, this will be derived purely algebraically, although the final form of the equation has a useful interpretation. Expanding the partial derivative

$$\frac{\partial(\rho u)}{\partial t} = \rho \frac{\partial u}{\partial t} + u \frac{\partial \rho}{\partial t}$$

is simple. The tensor divergence $\nabla \cdot (\rho u \otimes u)$ is defined such that

$$\int_{\Omega_0} \nabla \cdot (\rho u \otimes u) \, dx = \int_{\partial \Omega_0} (\rho u \otimes u) : \hat{n} \, dx = \int_{\partial \Omega_0} \rho u (u \cdot \hat{n}) \, dx$$

for arbitrary control volumes Ω_0 . As Ω_0 becomes small, we can separately assume u and ρu are constant to derive

$$\int_{\partial\Omega_0} \rho u(u \cdot \hat{n}) \, dx = u \int_{\partial\Omega_0} (\rho u) \cdot \hat{n} \, dx + \rho u \cdot \int_{\partial\Omega_0} u \hat{n} \, dx + \cdots$$

where a trailing term becomes neglible for a small control volume. This gives a "tensor product rule" for the divergence,

$$\nabla \cdot (\rho u \otimes u) = u \nabla \cdot (\rho u) + \rho u \cdot \nabla u. \tag{1.36}$$

Equation (1.35) then becomes

$$\rho \frac{\partial u}{\partial t} + u \frac{\partial \rho}{\partial t} + u \nabla \cdot (\rho u) + \rho u \cdot \nabla u = \rho g + \nabla \cdot \sigma.$$

Noting that $\frac{\partial \rho}{\partial t}$ is already given by continuity equation (1.31)

$$\frac{\partial \rho}{\partial t} = -\nabla \cdot (\rho u),$$

as mass is transported by u and has no source, we get

$$\rho \frac{\partial u}{\partial t} - \underline{u} \nabla (\rho \underline{u}) + \underline{u} \nabla \cdot (\rho \underline{u}) + \rho \underline{u} \cdot \nabla \underline{u} = \rho \underline{g} + \nabla \cdot \sigma.$$

Finally, the material derivative as defined in section (ref) is helpful in simplifying the above to

$$\rho \frac{Du}{Dt} = \rho g + \nabla \cdot \sigma. \tag{1.37}$$

This form of (1.35) is called the *convective form* of the Cauchy momentum equation, and is more obviously a form of F = ma. Recall that the material derivative is defined as

$$\frac{D}{Dt} := \frac{\partial}{\partial t} + u \cdot \nabla,$$

which measures the rate of change of a pointwise quantity from the perspective of a particle moving with the flow field u. The equation (1.37) then says that, if the continuum consists of idealized points each with a certain linear momentum (in the particle sense), deflection of their inertial path is due only to the application of a body force ρg at this point, and a total traction force exerted by the surrounding material.

1.5.3 Constitutive relations

Body forces typically model external fields such as gravity, which act on a material in bulk. We here forget the body forces, and investigate the possible forms of the Cauchy stress tensor. σ models the "material constitution", and therefore we call its specification a constitutive relation. A constitutive relation specifies how the kinematics of the continuum relate to its dynamics, as in, how the material configuration induces forces on the material. With σ specified, the Cauchy momentum equation (1.37) becomes well-posed.

Deviatoric and volumetric stresses

Suppose that the tractions are determined only by the velocity gradient,

$$\sigma = \sigma(\nabla u)$$
.

Pressure in incompressible materials

If we require the velocity field u of the position map x to be non-compressing (as described in section (ref)), then we add to our model equations the constraint

$$\nabla \cdot u = 0. \tag{1.38}$$

We proceed by analogy to a simple mechanical system. The state of a pendulum of mass m might be described by two spatial variables X and Y with a constraint

$$X^2 + Y^2 = 1.$$

Given a differentiable pendulum motion, the linear momenta mv_X and mv_Y clearly cannot be constant, as then the pendulum would "fly out" of its arc. From the perspective of the X, Y coordinate system there exists "virtual forces" which are exactly those that are needed to maintain constraints. These forces have no necessary physical interpretation, as the pendulum model does not explicitly reference the tension of the pendulum rod, but are rather those strong forces that must "come from somewhere" such that the constraints are satisfied.

(figure)

From a constraint on position (X, Y) we can derive a constraint on velocity (v_X, v_Y) by noting that the velocity must stay inside the tangent plane in the configuration space. In this case, we require

$$Xv_X + Yv_Y = 0. (1.39)$$

(— add Lagrange multipliers to the system, then pressure here is a sort of Lagrange multiplier). The continuum velocity constraint (1.38) is completely analogous to (1.39). Motions of x are restricted to those which do not compress mass. Clearly, our (per-point) linear momentum ρu cannot be constant except in simple parallel flows, implying the existence of some virtual (per-point) force. We call this force the *pressure* p, and we are now solving for ρ , u, and p in a coupled system of equations (1.37) and (1.38), repeated here:

$$\rho \frac{Du}{Dt} = \rho g + \nabla \cdot \sigma, \quad \nabla \cdot u = 0.$$

As there is no explicit mention of p, it must be part of the constitutive relation for σ . We let σ be

$$\sigma = -pI + \tau \quad \Rightarrow \quad \nabla \cdot \sigma = -\nabla p + \nabla \cdot \tau,$$

where I is the identity tensor and τ is called the *deviatoric* component of the Cauchy stress tensor. τ is chosen such that the pressure p entirely encapsulates the isotropic forces which push material volumes apart.

Completing our equations

We have so far been working quite generally with the forms of continuum mechanics models and their constraints. Although we have made some assumptions (for example, we require σ to be a purely local function, an idealisation due to Cauchy [ref]), we must so far leave our systems underdetermined. In the next chapter, we will investigate an important constitutive relation for the deviatoric stress τ , forming what is called a *Navier-Stokes fluid*, giving a complete system of equations called the *Navier-Stokes equations*.

Chapter 2

The Navier-Stokes equations

2.1 Deriving the Navier-Stokes equations

The incompressible Navier-Stokes equations model the motion of a common kind of viscous fluid called a *Newtonian fluid*. They are:

- The Cauchy momentum equation (1.37) for mass density ρ and velocity u,
- an incompressibility constraint $\nabla \cdot u = 0$ and unknown pressure p,
- and a concrete constitutive relation for the deviatoric stress τ .

In anticipation, their common form is

$$\rho \frac{Du}{Dt} = -\nabla p + \nabla \cdot \tau + \rho g, \quad \nabla \cdot u = 0, \tag{2.1}$$

where τ is defined by Stokes' constitutive relation

$$\tau = \mu \left(\nabla u + \nabla u^T \right), \tag{2.2}$$

where μ is called the *viscosity*, and ∇u is the velocity gradient measuring the local deformation of a small control volume under the flow of u. Alongside a domain and appropriate initial and boundary conditions, the Navier-Stokes equations (2.1) form a concrete flow problem which can be solved numerically, or in special situations analytically.

2.2 Scaling and dimension

2.2.1 The Reynolds number

2.3 Stokes flow and the meaning of pressure

If we assume that the advective term $u \cdot \nabla u$ in the incompressible Navier-Stokes equations is "small", we can ignore it and derive the linear unsteady Stokes equations:

$$\rho \frac{\partial u}{\partial t} = \mu \Delta u + \rho g - \nabla p, \quad \nabla \cdot u = 0. \tag{2.3}$$

We are assuming validity for low Reynolds number $Re \ll 1$, where convective behaviour is neglible compared to the viscous forces, which for a Navier-Stokes fluid "diffuse" the linear momentum. Setting the left-hand-side of (2.3) to zero results in the *steady Stokes equations*

$$\mu \Delta u + \rho g - \nabla p = 0, \quad \nabla \cdot u = 0. \tag{2.4}$$

Time-dependent equation (2.3) can be thought of as a "gradient descent" to find the steady Stokes flow (2.4). The steady Stokes equation is a constrained vector Poisson equation, where we have introduced pressure p explicitly. It is well-known, by Dirichlet's principle, that we can think of a weak solution to the unconstrained vector Poisson equation as a minimizer of the Dirichlet energy

$$E(u) := \int_{\Omega} \frac{\mu}{2} \|\nabla u\|^2 - \langle \rho g, u \rangle \ dx = \int_{\Omega} \mathcal{L} \ dx. \tag{2.5}$$

We can see that the Euler-Lagrange equations are

$$\frac{\delta E}{\delta u} = \frac{\partial \mathcal{L}}{\partial u} - \frac{d}{dx} \frac{\partial \mathcal{L}}{\partial \nabla u} = -\rho g - \mu \Delta u = 0.$$

We now introduce the incompressibility constraint $c(u) := \nabla \cdot u = 0$. We have the constrained Euler-Lagrange equations

$$\begin{split} \frac{\delta E}{\delta u} &= -\rho g - \mu \Delta u = \lambda \left(\frac{\partial c}{\partial u} - \frac{d}{dx} \frac{\partial c}{\partial \nabla u} \right) \\ \Rightarrow &- \rho g - \mu \Delta u = \lambda \frac{\partial c}{\partial u}. \end{split}$$

The interpretation is simple. Our functional gradient $\frac{\delta E}{\delta u}$ measures the local change in energy when the velocity field u is perturbed, by

$$\left. \frac{\delta E}{\delta u} \right|_{\delta u} = \left\langle \frac{\delta E}{\delta u}, \delta u \right\rangle.$$

 δu is an unconstrained virtual displacement of the velocity field. We want a principle of stationary action which only cares about *constrained* virtual displacements, so we cannot simply say that $\frac{\delta E}{\delta u} = 0$. However, if we say that

$$\frac{\delta E}{\delta u} = \lambda \frac{\partial c}{\partial u} \quad \Rightarrow \quad \left\langle \frac{\delta E}{\delta u}, \delta u \right\rangle = \left\langle \frac{\partial c}{\partial u}, \lambda \delta u \right\rangle$$

we mean that, as we must have $\langle \frac{\partial c}{\partial u}, \delta u \rangle = 0$ for valid virtual displacements, E is stationary with respect to valid displacements. $\frac{\partial c}{\partial u}$ is such that

$$\left\langle \frac{\partial c}{\partial u}, \delta u \right\rangle = \nabla \cdot \delta u.$$

For weak solutions of the steady Stokes equation (2.4) we then want

$$\langle \rho g + \mu \Delta u, \delta u \rangle + \nabla \cdot (\lambda \delta u) = 0, \quad \nabla \cdot u = 0.$$
 (2.6)

We have by a product rule of the divergence that

$$\nabla \cdot (\lambda \delta u) = \nabla \lambda \cdot \delta u + \lambda \nabla \cdot \delta u,$$

giving the form

$$\langle \rho q + \mu \Delta u + \nabla \lambda, \delta u \rangle + \lambda \nabla \cdot \delta u = 0, \quad \nabla \cdot u = 0.$$

for a weakened steady Stokes equation. If we constrain our virtual displacement δu to be divergence-free (as in, the virtual displacements maintain the constraint of incompressibility), we get the form

$$\langle \rho g + \mu \Delta u + \nabla \lambda, \delta u \rangle = 0, \quad \nabla \cdot u = 0,$$

2.4. PRESSURE

and, noting that the inner product integral must vanish identically for all valid virtual displacements δu , we have

$$\rho g + \mu \Delta u + \nabla \lambda = 0, \quad \nabla \cdot u = 0.$$

This is just the steady Stokes equations (2.4), where $\lambda = -p!$ We can see that p is "actually" a Lagrange multiplier, which measures a virtual force that responds to virtual displacements which would break the constraint of incompressibility. In fact, we may think of this as a derivation of the pressure. To see this more clearly, we can substitute -p into (2.6) to get

$$\langle \rho g + \mu \Delta u, \delta u \rangle = \nabla \cdot (p \delta u), \quad \nabla \cdot u = 0$$
 (2.7)

for unconstrained test functions δu .—discuss hydrostatics, gravity.

2.3.1 Application to hydrostatics

For example, we may imagine the steady Stokes equations modelling a calm sea with a flat seabed. We can let the body force be gravity described by a potential ϕ :

$$\rho g = -\nabla \phi.$$

If we make a perturbed displacement of the velocity field at the bottom of the ocean, supposing that some volume of water is beginning to expand, we are working against gravity as well as our virtual force, pressure.

(draw this)

2.4 Pressure

Chapter 3

The finite element method

3.1 Discretizing variational principles

3.1.1 Solving the Poisson equation

As a first example, we will derive a finite element method for the Poisson equation. Poisson's equation is a steady-state version of the heat equation.

Diffusion processes

A diffusion process "levels out" some quantity, such as heat or chemical concentration. We can intuitively think of a diffusion as a progressive "blurring" such as is seen in a camera defocus, and in fact many common image processing techniques use diffusion PDEs from physics. We will stick with the notion of heat h as the diffused quantity. Fick's law of diffusion is a constitutive relation giving the bulk flux of heat h as proportional to the negative gradient:

$$hj = -\mu \nabla h$$
,

where μ is called the diffusion coefficient. This is one way of saying that heat tends to "level out". If we form a continuity equation (1.5) for heat, with source s, we get

$$\frac{d}{dt} \int_{\Omega_0} h \, dx = \int_{\Omega_0} s \, dx + \int_{\partial \Omega_0} \mu \nabla h \cdot \hat{n} \, dx, \tag{3.1}$$

which by application of Stokes' theorem becomes

$$\frac{dh}{dt} = s + \nabla \cdot (\mu \nabla h). \tag{3.2}$$

If we further assume that the diffusion coefficient μ is constant, we get

$$\frac{dh}{dt} = s + \mu \nabla \cdot \nabla h = s + \mu \Delta h, \tag{3.3}$$

which is the standard heat equation, and simplest example of the use of the Laplacian. The steady-state heat equation is then

$$-\Delta h = s/\mu. \tag{3.4}$$

It is a standard model of diffusion processes which leads directly to the Laplacian.

$$\int_{\partial\Omega_0} -\nabla u \cdot \hat{n} \, dx = \int_{\Omega_0} dx$$

$$-\Delta u = g \quad \text{in } \Omega,$$

$$u = 0 \quad \text{on } \partial\Omega.$$
(3.5)

Bibliography

- [1] Isaac Newton, Philosophiae Naturalis Principia Mathematica (Third edition), 1726.
- [2] Johann Bernoulli, "Problema novum ad cujus solutionem Mathematici invitantur." (A new problem to whose solution mathematicians are invited.), 1696. (retrieved from wikipedia/brachistochrone_curve)
- [3] A. F. Monna, Dirichlet's principle: A mathematical comedy of errors and its influence on the development of analysis, 1975
- [4] Stig Larsson, Partial differential equations with numerical methods, 2003
- [5] Peter Lax, Hyperbolic Systems of Conservation Laws and the Mathematical Theory of Shock Waves, 1973
- [6] Cornelius Lanczos, The Variational Principles of Mechanics, 1952
- [7] G. K. Batchelor, Introduction to Fluid Dynamics, 1967
- [8] L. Gary Leal, Advanced Transport Phenomena: Fluid Mechanics and Convective Transport Processes, 2007
- [9] Vivette Girault, Pierre-Arnaud Raviart, Finite Element Methods for Navier-Stokes equations, 1986
- [10] Richard Feynman, Surely You're Joking, Mr. Feynman!, 1985
- [11] V.I. Arnol'd, Mathematical Methods of Classical Mechanics, 1978
- [12] Alan Turing, The Chemical Basis of Morphogenesis, 1952
- [13] The Princeton Companion to Applied Mathematics, 2015