
# **Chapter 5: Process Synchronization**





## **Chapter 5: Process Synchronization**

- Background
- The Critical-Section Problem
- Peterson's Solution
- Synchronization Hardware
- Mutex Locks
- Semaphores
- Classic Problems of Synchronization
- Monitors
- Synchronization Examples
- Alternative Approaches





## **Objectives**

- To present the concept of process synchronization.
- To introduce the critical-section problem, whose solutions can be used to ensure the consistency of shared data
- To present both software and hardware solutions of the critical-section problem
- To examine several classical process-synchronization problems
- To explore several tools that are used to solve process synchronization problems






## **Background**


- Processes can execute concurrently
  - May be interrupted at any time, partially completing execution
- Concurrent access to shared data may result in data inconsistency
- Maintaining data consistency requires mechanisms to ensure the orderly execution of cooperating processes
- Illustration of the problem: Suppose that we wanted to provide a solution to the consumer-producer problem that fills all the buffers. We can do so by having an integer counter that keeps track of the number of full buffers. Initially, counter is set to 0. It is incremented by the producer after it produces a new buffer and is decremented by the consumer after it consumes a buffer.





#### **Producer**






#### Consumer

```
while (true) {
    while (counter == 0)
        ; /* do nothing */
    next_consumed = buffer[out];
    out = (out + 1) % BUFFER_SIZE;
    counter--;
    /* consume the item in next consumed */
}
```





#### **Race Condition**

**counter++** could be implemented as

```
register1 = counter
register1 = register1 + 1
counter = register1
```

**counter--** could be implemented as

```
register2 = counter
register2 = register2 - 1
counter = register2
```

■ Consider this execution interleaving with "count = 5" initially:

```
S0: producer execute register1 = counter {register1 = 5}
S1: producer execute register1 = register1 + 1 {register1 = 6}
S2: consumer execute register2 = counter {register2 = 5}
S3: consumer execute register2 = register2 - 1 {register2 = 4}
S4: producer execute counter = register1 {counter = 6}
S5: consumer execute counter = register2 {counter = 4}
```





#### **Critical Section Problem**

- Consider system of n processes  $\{p_0, p_1, \dots p_{n-1}\}$
- Each process has **critical section** segment of code
  - Process may be changing common variables, updating table, writing file, etc
  - When one process in critical section, no other may be in its critical section
- Critical section problem is to design protocol to solve this
- Each process must ask permission to enter critical section in entry section, may follow critical section with exit section, then remainder section





#### **Critical Section**

 $\blacksquare$  General structure of process  $P_i$ 

```
do {
    entry section
    critical section

exit section

remainder section
} while (true);
```





# Solution to Critical-Section Problem

- 1. Mutual Exclusion If process  $P_i$  is executing in its critical section, then no other processes can be executing in their critical sections
- 2. Progress If no process is executing in its critical section and there exist some processes that wish to enter their critical section, then the selection of the processes that will enter the critical section next cannot be postponed indefinitely
- 3. **Bounded Waiting** A bound must exist on the number of times that other processes are allowed to enter their critical sections after a process has made a request to enter its critical section and before that request is granted
  - Assume that each process executes at a nonzero speed
  - No assumption concerning relative speed of the n processes






#### Peterson's Solution

- Good algorithmic description of solving the problem
- Two process solution
- Assume that the load and store machine-language instructions are atomic; that is, cannot be interrupted
- The two processes share two variables:
  - int turn;
  - Boolean flag[2]
- The variable turn indicates whose turn it is to enter the critical section
- The flag array is used to indicate if a process is ready to enter the critical section. flag[i] = true implies that process P<sub>i</sub> is ready!





## Algorithm for Process Pi

```
do {
    flag[i] = true;
    turn = j;
    while (flag[j] && turn = = j);
        critical section

    flag[i] = false;
    remainder section
} while (true);
```





## Peterson's Solution (Cont.)

- Provable that the three CS requirement are met:
  - 1. Mutual exclusion is preserved
    - P<sub>i</sub> enters CS only if:

```
either flag[j] = false or turn = i
```

- 2. Progress requirement is satisfied
- 3. Bounded-waiting requirement is met





## **Synchronization Hardware**

- Many systems provide hardware support for implementing the critical section code.
- All solutions below based on idea of locking
  - Protecting critical regions via locks
- Uniprocessors could disable interrupts
  - Currently running code would execute without preemption
  - Generally too inefficient on multiprocessor systems
    - Operating systems using this not broadly scalable
- Modern machines provide special atomic hardware instructions
  - → Atomic = non-interruptible
  - Either test memory word and set value
  - Or swap contents of two memory words





#### **Solution to Critical-section Problem Using Locks**






## test\_and\_set Instruction

#### Definition:

```
boolean test_and_set (boolean *target)
{
    boolean rv = *target;
    *target = TRUE;
    return rv:
}
```

- 1. Executed atomically
- 2. Returns the original value of passed parameter
- 3. Set the new value of passed parameter to "TRUE".






## Solution using test\_and\_set()

- Shared Boolean variable lock, initialized to FALSE
- Solution:





## compare\_and\_swap Instruction

#### Definition:


```
int compare_and_swap(int *value, int expected, int new_value) {
   int temp = *value;

   if (*value == expected)
        *value = new_value;

   return temp;
}
```

- 1. Executed atomically
- 2. Returns the original value of passed parameter "value"
- 3. Set the variable "value" the value of the passed parameter "new\_value" but only if "value" == "expected". That is, the swap takes place only under this condition.





## Solution using compare\_and\_swap

- Shared integer "lock" initialized to 0;
- Solution:

```
do {
    while (compare_and_swap(&lock, 0, 1) != 0)
    ; /* do nothing */
    /* critical section */
lock = 0;
    /* remainder section */
} while (true);
```





#### **Bounded-waiting Mutual Exclusion with test\_and\_set**

```
do {
   waiting[i] = true;
   key = true;
   while (waiting[i] && key)
      key = test and set(&lock);
   waiting[i] = false;
   /* critical section */
   j = (i + 1) \% n;
   while ((j != i) && !waiting[j])
      j = (j + 1) % n;
   if (j == i)
      lock = false;
   else
      waiting[j] = false;
   /* remainder section */
} while (true);
```





#### **Mutex Locks**

- Previous solutions are complicated and generally inaccessible to application programmers
- OS designers build software tools to solve critical section problem
- Simplest is mutex lock
- Protect a critical section by first acquire() a lock then release() the lock
  - Boolean variable indicating if lock is available or not
- Calls to acquire() and release() must be atomic
  - Usually implemented via hardware atomic instructions
- But this solution requires busy waiting
  - This lock therefore called a spinlock





## acquire() and release()

```
acquire() {
     while (!available)
         ; /* busy wait */
      available = false;;
   release() {
      available = true;
   do {
   acquire lock
      critical section
   release lock
     remainder section
} while (true);
```





## **Semaphore**

- Synchronization tool that provides more sophisticated ways (than Mutex locks) for process to synchronize their activities.
- Semaphore *S* integer variable
- Can only be accessed via two indivisible (atomic) operations
  - wait() and signal()Originally called P() and V()
- Definition of the wait() operation

```
wait(S) {
    while (S <= 0)
        ; // busy wait
    S--;
}</pre>
```

■ Definition of the **signal()** operation

```
signal(S) {
    S++;
}
```





## Semaphore Usage

- Counting semaphore integer value can range over an unrestricted domain
- Binary semaphore integer value can range only between 0 and 1
  - Same as a mutex lock
- Can solve various synchronization problems
- Consider  $P_1$  and  $P_2$  that require  $S_1$  to happen before  $S_2$  Create a semaphore "synch" initialized to 0

```
P1:

S<sub>1</sub>;

signal(synch);

P2:

wait(synch);

S<sub>2</sub>;
```





## **Semaphore Implementation**

- Must guarantee that no two processes can execute the wait() and signal() on the same semaphore at the same time
- Thus, the implementation becomes the critical section problem where the wait and signal code are placed in the critical section
  - Could now have busy waiting in critical section implementation
    - But implementation code is short
    - Little busy waiting if critical section rarely occupied
- Note that applications may spend lots of time in critical sections and therefore this is not a good solution






#### Semaphore Implementation with no Busy waiting

- With each semaphore there is an associated waiting queue
- Each entry in a waiting queue has two data items:
  - value (of type integer)
  - pointer to next record in the list
- Two operations:
  - block place the process invoking the operation on the appropriate waiting queue
  - wakeup remove one of processes in the waiting queue and place it in the ready queue

```
typedef struct{
  int value;
  struct process *list;
} semaphore;
```





#### Implementation with no Busy waiting (Cont.)

```
wait(semaphore *S) {
   S->value--;
   if (S->value < 0) {
      add this process to S->list;
      block();
signal(semaphore *S) {
   S->value++;
   if (S->value <= 0) {
      remove a process P from S->list;
      wakeup(P);
```





#### **Deadlock and Starvation**

- Deadlock two or more processes are waiting indefinitely for an event that can be caused by only one of the waiting processes
- Let S and Q be two semaphores initialized to 1

```
P_0 P_1 wait(S); wait(Q); wait(Q); wait(Q); ... signal(S); signal(Q); signal(S);
```

- Starvation indefinite blocking
  - A process may never be removed from the semaphore queue in which it is suspended





# **Classical Problems of Synchronization**

- Classical problems used to test newly-proposed synchronization schemes
  - Bounded-Buffer Problem
  - Readers and Writers Problem






#### **Bounded-Buffer Problem**

- **n** buffers, each can hold one item
- Semaphore mutex initialized to the value 1
- Semaphore full initialized to the value 0
- Semaphore empty initialized to the value n






## **Bounded Buffer Problem (Cont.)**

The structure of the producer process

```
do {
      /* produce an item in next produced */
   wait(empty);
   wait(mutex);
      /* add next produced to the buffer */
   signal(mutex);
   signal(full);
} while (true);
```





## **Bounded Buffer Problem (Cont.)**

The structure of the consumer process





#### **Readers-Writers Problem**

- A data set is shared among a number of concurrent processes
  - Readers only read the data set; they do not perform any updates
  - Writers can both read and write
- Problem allow multiple readers to read at the same time
  - Only one single writer can access the shared data at the same time
- Several variations of how readers and writers are considered all involve some form of priorities
- Shared Data
  - Data set
  - Semaphore rw\_mutex initialized to 1
  - Semaphore mutex initialized to 1
  - Integer read count initialized to 0





## Readers-Writers Problem (Cont.)

■ The structure of a writer process





## Readers-Writers Problem (Cont.)

The structure of a reader process

```
do {
       wait(mutex);
       read count++;
       if (read count == 1)
       wait(rw_mutex);
    signal(mutex);
       /* reading is performed */
    wait(mutex);
       read count--;
       if (read_count == 0)
    signal(rw mutex);
    signal(mutex);
} while (true);
```





## **Readers-Writers Problem Variations**

- *First* variation no reader kept waiting unless writer has permission to use shared object
- Second variation once writer is ready, it performs the write ASAP
- Both may have starvation leading to even more variations
- Problem is solved on some systems by kernel providing reader-writer locks



## **End of Chapter 5**

