Electrodynamics

Michael Brodskiy

Professor: D. Wood

November 9, 2023

• Current

- Ohm's "Law"¹
 - * Holds when there is some current density such that $\vec{J} = \sigma \vec{E}$, with σ as conductivity
 - * The unit of conductivity is $\left[\frac{A}{V\,m}\right]$
 - * The resistivity is the inverse of the conductivity, $\rho = \sigma^{-1}$, with units $[\Omega \, m]^2$
- The average velocity of a particle accelerated over an interval due to an electric field is:

$$v_{avg} = \sqrt{\frac{q\vec{E}d}{2m}}$$

- The current density can be defined as

$$\vec{J} = nq\vec{v}$$

- An electron's drift velocity may be defined as:

$$v_d = \frac{1}{2} \frac{q\vec{E}d}{mv}$$

- * As long as $v_d \ll v$
- Given a wire of length L and potential V_o , we can calculate:

$$\vec{E} = \frac{V_o}{L}$$

$$R = \frac{V}{I} = \frac{\vec{E}L}{\vec{J}A} = \frac{\rho L}{A}$$

 1 Note: this is not a fundamental law

²Note: Ohms are equal to $\frac{V}{A}$

- Circuits and Power
 - We know:

$$V = \frac{Q}{C}$$

$$W = \frac{1}{2}QV = \frac{Q^2}{2C}$$

- By conservation of charge, we can write:

$$P = \frac{dW}{dt} = \frac{1}{2C} \frac{d}{dt}(Q^2) = -IV$$
$$P = \frac{V^2}{R}$$

- We can also derive:

$$\frac{dQ}{Q} = -\frac{dt}{RC}$$
$$Q = Q_o e^{-\frac{t}{RC}}$$

- Electromotive Force (EMF)
 - The EMF can be defined as:

$$\varepsilon = \int \vec{f} \, d\vec{l}$$

- Where:

$$\vec{f} = \frac{\vec{F}}{q}$$

- Magnetic flux can be defined as:

$$\Phi = \int \vec{B} \cdot d\vec{a}$$

- The EMF can also be defined as:

$$\varepsilon = -\frac{d\Phi}{dt}$$

- Lenz's Law: Induced effect opposes the change
- $-\,$ There are several ways flux may be changed:
 - $\ast\,$ Loop is stationary, move B-field
 - * Loop stationary, change strength of B-field

- * Change relative direction of loop and \vec{B}
- Faraday's Law:

$$\oint \vec{E} \cdot d\vec{l} = -\frac{d}{dt} \int_{S} \vec{B} \cdot d\vec{a}$$

- According to Stokes' Theorem, we may write:

$$\int_{S} (\vec{\nabla} \times \vec{E}) \cdot d\vec{a} = -\int_{S} \frac{d}{dt} (\vec{B} \cdot d\vec{a})$$

- Which gives us one of Maxwell's equations:

$$\vec{\nabla} \times \vec{E} = -\frac{d\vec{B}}{dt}$$

• We can define flux as:

$$\Phi_B(t) = BA\cos(\omega t)$$

- Which then gives us:

$$\varepsilon = -\frac{d}{dt}(\Phi_B(t)) = AB\omega\sin(\omega t)$$

- When the magnetic field is constant, but the area is changing, we can write:

$$\varepsilon = -B \frac{dA}{dt}$$

- Thus, for a moving loop, we can write:

$$\varepsilon = -Bwv$$

- Mutual Inductance
 - Since \vec{B} is proportional to I (via Biot-Savart), we can also say that Φ will be proportional to the current I. Thus, we may write:

$$\Phi = MI$$

- Where M is known as the mutual inductance
- Likewise, we can define:

$$\varepsilon = -M \frac{dI}{dt}$$

- We can observe:
 - 1. Φ is proportional to I
 - 2. M depends only on the geometry
 - 3. $M_{1,2} = M_{2,1} = M$
- Self Inductance

$$\Phi = LI$$

- L describes the self inductance
- \bullet Work

$$P = \varepsilon I$$

- From the above, we may write for an inductor:

$$\int \frac{dW}{dt} = -L \int \frac{dI}{dt} I$$

$$W = \frac{1}{2} L I^2$$

- The energy may be written as:

$$U = \frac{1}{2}(\mu_o n^2 I^2)(Al)$$
$$U = \frac{1}{2\mu_o} B^2(Al)$$

- For energy density we may simply write:

$$\mathcal{U}_M = \frac{1}{2\mu_o} B^2$$

– Given that $\tau = \frac{L}{R}$, we may write:

$$I = I_o e^{-\frac{t}{\tau}}$$