## Plane-Wave Propagation

## Michael Brodskiy

Professor: E. Marengo Fuentes

October 16, 2023

- We will have problems about fields from sources radiating
  - In a source-free region, there are no electric and magnetic fields. That would make Maxwell's equations:

$$\nabla \cdot \tilde{E} = 0$$

$$\nabla \times \tilde{E} = -j\omega\mu\tilde{H}$$

$$\nabla \cdot \tilde{H} = 0$$

$$\nabla \times \tilde{H} = \tilde{J} + j\omega\varepsilon\tilde{E}$$

- In a region with a source, Maxwell's equations may be written as:

$$\nabla \cdot \tilde{E} = \frac{\rho_V}{\varepsilon}$$

$$\nabla \times \tilde{E} = -j\omega\mu\tilde{H}$$

$$\nabla \cdot \tilde{H} = 0$$

$$\nabla \times \tilde{H} = \tilde{J}_{cond} + j\omega\varepsilon\tilde{E}$$

- There are two components that contribute to current density:

$$\tilde{J} = \tilde{J}_{impressed} + \tilde{J}_{cond}$$

\* Impressed is from a source, and conductive is an intrinsic property

$$\tilde{J} = \sigma \tilde{E}$$

- The homogenous form of Maxwell's equations can thus be written as:

$$\nabla \cdot \tilde{E} = 0$$
 
$$\nabla \times \tilde{E} = -j\omega\mu\tilde{H}$$
 
$$\nabla \cdot \tilde{H} = 0$$
 
$$\nabla \times \tilde{H} = (\sigma + j\omega\varepsilon)\tilde{E}$$

- Far from sources, fields propagate like a plane wave (the circle becomes so large, it can be approximated as a line)
- $\bullet$  The  $\tilde{J}$  conduction component is known as drift
  - If the conductivity is non-zero, we can see from the equation above that:

$$\nabla \times \tilde{H} = j\omega \left(\varepsilon - \frac{j\sigma}{\omega}\right) \tilde{E}$$
$$\varepsilon_c = \varepsilon - \frac{j\sigma}{\omega}$$

\* If  $\frac{\sigma}{\omega} << \varepsilon$ , then the material is an insulator, and:

$$\varepsilon_c = \varepsilon$$

- \* If  $\frac{\sigma}{\omega} >> \varepsilon$ , the material is conductive; Note: this means that a good conductor depends on the angular frequency
- \* We can determine that:

$$\tan(\theta) = \frac{\sigma}{\omega \varepsilon}$$

- \* If the tangent is approximately 0, the conductivity is negligible
- Wave Equations
  - From manipulating the first non-zero equation, we get:

$$\nabla \times \nabla \times \vec{E} - \omega^2 \mu \varepsilon_c \tilde{E} = 0$$

- We can also get:

$$\nabla^2 \vec{E} - \omega \mu \varepsilon_c \tilde{E} = 0$$

– In lossy media,  $\sigma \neq 0$  and  $\varepsilon_c$  is a complex value. We assign  $\gamma = -\omega^2 \mu \varepsilon_c$ , and can now write:

$$(\nabla^2 - \gamma^2)\tilde{E} = 0$$

$$(\nabla^2 - \gamma^2)\tilde{H} = 0$$

- For lossless media,  $\sigma = 0$ , and  $\varepsilon_c$  is purely real
- We can rewrite the equation as:

$$(\nabla^2 + k^2)\tilde{E}(r) = 0$$
, where  $r = (x, y, z)$ 

- \* k is the wave number,  $\omega \sqrt{\mu \varepsilon}$
- Mapping from source to field is known as radiation

- A long distance from the source, the spherical wavefront may be approximated to a line
- Using one of our equations from above, and plugging in the value of  $\nabla \times \tilde{H}$ , we can obtain:

$$\nabla^2 \tilde{E} + \omega^2 \mu \varepsilon \tilde{E} - j\omega \mu \sigma \tilde{E} = 0$$

• For plane waves, we end up with two important equations:

$$\tilde{H} = \frac{1}{\eta}\hat{k} \times \tilde{E}$$
$$\tilde{E} = -\eta\hat{k} \times \tilde{E}$$

– Where  $\tilde{E}$  and  $\tilde{H}$  are plane waves,  $\hat{k}$  is the direction of propagation, and  $\eta = \sqrt{\frac{\mu}{\varepsilon}}$ . This means we know:

$$\tilde{E} \cdot \hat{k} = 0$$

$$\tilde{H} \cdot \hat{k} = 0$$

- Polarization
  - Occurs when two components or more components of a wave are in different phases