User guide

$\mathcal{H}\Phi$ version 1.2.0

© 2015- The University of Tokyo All rights reserved.

Nov. 15, 2016

Contents

1	$\mathbf{W}\mathbf{h}$	at is \mathcal{H}^{q}	$\Phi ?$	1
	1.1	What is	s $\mathcal{H}\Phi$?	1
		1.1.1	License	2
		1.1.2	Copyright	2
		1.1.3	Contributors	2
	1.2	Operat	ing environment	3
2	Hov	v to use	$_{ ext{P}}$ $\mathcal{H}\Phi$?	4
	2.1	Prerequ	uisite	4
	2.2	Installa	ation	4
		2.2.1	Using HPhiconfig.sh	5
		2.2.2	Using cmake	6
	2.3	Directo	ory structure	7
	2.4	Basic u		8
		2.4.1	Standard mode	8
		2.4.2	Expert mode	9
		2.4.3	Setting a process number for MPI/Hybrid parallelization	11
		2.4.4	Printing version ID	11
3	Tut	orial]	12
	3.1	Standa	$rd mode \dots \dots \dots \dots \dots$	12
		3.1.1	Heisenberg model	12
			<u> </u>	18
	3.2	Expert	mode	18
		3.2.1	A file list for input files	19
				19
				21
				22
				23
				23
	3.3			25
4	File	specifi	cation	26
	4.1	-	illes for Standard mode	_
				$\frac{1}{27}$

ii Contents

	4.1.2	Parameters for the lattice
	4.1.3	Parameters for conserved quantities
	4.1.4	Parameters for the Hamiltonian
	4.1.5	Parameters for the numerical condition
4.2	Input	files for \textit{Expert} mode
	4.2.1	List file for Input files
	4.2.2	CalcMod file
	4.2.3	ModPara file
	4.2.4	LocSpin file
	4.2.5	Trans file
	4.2.6	InterAll file
	4.2.7	CoulombIntra file
	4.2.8	CoulombInter file
	4.2.9	Hund file
	4.2.10	PairHop file
	4.2.11	Exchange file
		Ising file
	4.2.13	PairLift file
		OneBodyG file
	4.2.15	TwoBodyG file
	4.2.16	SingleExcitation file
	4.2.17	PairExcitation file
		SpectrumVec File
4.3		t files
	4.3.1	CHECK_Chemi.dat
	4.3.2	CHECK_InterAll.dat
	4.3.3	CHECK_CoulombIntra.dat
	4.3.4	CHECK_Hund.dat
	4.3.5	CHECK_INTER_U.dat
	4.3.6	CHECK_Memory.dat
	4.3.7	WarningOnTransfer.dat
	4.3.8	CalcTimer.dat
	4.3.9	TimeKeeper.dat
	4.3.10	sz_TimeKeeper.dat
	4.3.11	Time_CG_EigenVector.dat
	4.3.12	energy.dat
	4.3.13	Lanczos_Step.dat
	4.3.14	Time_TPQ_Step.dat
	4.3.15	Norm_rand.dat
	4.3.16	SS_rand.dat
	4.3.17	Flct_rand.dat
		Eigenvalue.dat
		phys.dat
		cisajs.dat
		cisaiscktalt.dat

Contents

		4.3.22 eigenvec.dat	102
		4.3.23 tmpvec.dat	103
		4.3.24 DynamicalGreen.dat	104
		4.3.25 recalcvec.dat	105
		4.3.26 TMcomponents.dat	106
	4.4	Error messages	
5	Alg	gorithm	108
	5.1	Lanczos method	108
		5.1.1 Details of Lanczos method	108
		5.1.2 Inverse iteration method	109
		5.1.3 Details of implementation	
	5.2	Full Diagonalization method	
		5.2.1 Over view	
		5.2.2 Finite-temperature calculations	
	5.3	Finite-temperature calculations by TPQ method	111
		5.3.1 Details of implementation	
	5.4	Bogoliubov representation	
6	Ack	nowledgement	113

1

What is $\mathcal{H}\Phi$?

1.1 What is $\mathcal{H}\Phi$?

Comparison between experimental observation and theoretical analysis is a crucial step in condensed-matter physics research. Temperature dependence of specific heat and magnetic susceptibility, for example, have been studied to extract nature of low energy excitations of and magnetic interactions among electrons, respectively, through comparison with theories such as Landau's Fermi liquid theory and Curie-Weiss law.

For the flexible and quantitative comparison with experimental data, an exact diagonalization approach [1] is one of the most reliable numerical tools without any approximation or inspiration of genius. For last few decades, a numerical diagonalization package for quantum spin hamiltonians, TITPACK developed by Prof. Hidetoshi Nishimori in Tokyo Institute of Technology, has been widely used in the condensed-matter physics community. Nevertheless, limitation of computational resources had hindered the non-expert users from applying the package to quantum systems with large number of electrons or spins.

In contrast, recent and rapid development of parallel computing infrastructure opens up new avenues for user-friendly larger scale diagonalizations up to 18 site Hubbard clusters or 36 S=1/2 quantum spins. In addition, recent advances in quantum statistical mechanics [2–5] enable us to calculate finite temperature properties of quantum many-body systems with computational costs similar to calculations of ground state properties, which also enables us to compare theoretical results for temperature dependence of, for example, specific heat and magnetic susceptibility with experimental results quantitatively [6]. To utilize the parallel computing infrastructure with narrow bandwidth and distributed-memory architectures, efficient, user-friendly, and highly parallelized diagonalization packages are highly desirable.

 $\mathcal{H}\Phi$, a flexible diagonalization package for solving quantum lattice hamiltonians, has been developed to be such a descendant of the pioneering package TIT-PACK. The Lanczos method for calculations of the ground state and a few excited states properties, and finite temperature calculations based on thermal pure quantum states [5] are implemented in the package $\mathcal{H}\Phi$, with an easy-to-use and flexible user interface. By using $\mathcal{H}\Phi$, you can analyze a wide range of quantum lattice hamiltonians including simple Hubbard and Heisenberg models, multi-band extensions of the Hubbard model, exchange couplings that break SU(2) symmetry of quantum spins such as Dzyaloshinskii-Moriya and Kitaev interactions, and Kondo lattice models describing itinerant electrons coupled with quantum spins. $\mathcal{H}\Phi$ calculates a variety of physical quantities such as internal energy at zero temperature or

finite temperatures, temperature dependence of specific heat, charge/spin structure factors, and so on. A broad spectrum of users including experimental scientists is cordially welcome.

1.1.1 License

The distribution of the program package and the source codes for $\mathcal{H}\Phi$ follow GNU General Public License version 3 (GPL v3).

1.1.2 Copyright

© 2015- The University of Tokyo All rights reserved. This software is developed under the support of "Project for advancement of software usability in materials science" by The Institute for Solid State Physics, The University of Tokyo.

1.1.3 Contributors

This software is developed by following contributors.

- ver.1.2 (released at 2016/11/14)
- ver.1.1 (released at 2016/5/13)
- ver.1.0 (released at 2016/4/5)

- Developers

- * Takahiro Misawa (Department of Applied Physics, The University of Tokyo)
- * Kazuyoshi Yoshimi (The Institute for Solid State Physics, The University of Tokyo)
- * Mitsuaki Kawamura (The Institute for Solid State Physics, The University of Tokyo)
- * Youhei Yamaji (Department of Applied Physics, The University of Tokyo)
- * Synge Todo (Department of Physics, The University of Tokyo)

- Project coordinator

- * Naoki Kawashima (The Institute for Solid State Physics, The University of Tokyo)
- ver.0.3 (released at 2016/2/24)
- ver.0.2 (released at 2015/12/28)
- ver.0.1 (released at 2015/10/09)

- Developers

- * Takahiro Misawa (Department of Applied Physics, The University of Tokyo)
- * Kazuyoshi Yoshimi (The Institute for Solid State Physics, The University of Tokyo)
- * Mitsuaki Kawamura (The Institute for Solid State Physics, The University of Tokyo)

- Advisers

- * Youhei Yamaji (Department of Applied Physics, The University of Tokyo)
- * Synge Todo (Department of Physics, The University of Tokyo)

- Project coordinator

* Naoki Kawashima (The Institute for Solid State Physics, The University of Tokyo)

1.2 Operating environment

 $\mathcal{H}\Phi$ is tested in the following platforms:

- The supercomputer system-B "sekirei" and system-C "maki" in ISSP
- Linux PC + intel compiler
- Linux PC + gcc
- Mac + gcc

2

How to use $\mathcal{H}\Phi$?

2.1 Prerequisite

 $\mathcal{H}\Phi$ requires the following packages:

- C compiler (intel, Fujitsu, GNU, etc.)
- LAPACK library (intel MKL, Fujitsu, ATLAS, etc.)
- MPI library (If you do not use MPI, it is not necessary.)

Tips

E. g. / Settings of intel compiler

When you use the intel compiler, you can use easily scripts attached to the compiler. In the case of the bash in 64 bit OS, write the following in your ~/.bashrc:

source /opt/intel/bin/compilervars.sh intel64

or

source /opt/intel/bin/iccvars.sh intel64
source /opt/intel/mkl/bin/mklvars.sh

Please read manuals of your compiler/library for more information.

2.2 Installation

You can download $\mathcal{H}\Phi$ in the following place. https://github.com/QLMS/HPhi/releases You can obtain the $\mathcal{H}\Phi$ directory by typing

\$ tar xzvf HPhi-xxx.tar.gz

There are two kind of procedures to install $\mathcal{H}\Phi$.

2.2.1 Using HPhiconfig.sh

Please run HPhiconfig.sh script in the $\mathcal{H}\Phi$ directory as follow (for ISSP system-B "sekirei"):

\$ bash HPhiconfig.sh sekirei

Then environmental configuration file make.sys is generated in src/directory. The command-line argument of HPhiconfig.sh is as follows:

- sekirei : ISSP system-B "sekirei"
- maki : ISSP system-C "maki"
- sr : HITACHI SR16000
- intel: intel compiler + Linux PC
- mpicc-intel: intel compiler + MPI (excepting intelMPI) + Linux PC
- gcc : GCC + Linux PC
- gcc-mac : GCC + Mac

make.sys is as follows (for ISSP-system-B "sekirei"):

```
CC = mpiicc
LAPACK_FLAGS = -Dlapack -mkl=parallel
FLAGS = -qopenmp   -03 -xCORE-AVX2 -mcmodel=large -shared-intel -D MPI
MTFLAGS = -DDSFMT_MEXP=19937 $(FLAGS)
INCLUDE_DIR=./include
```

We explain macros of this file as:

- CC: The Compilation command (icc, gcc, fccpx)
- LAPACK_FLAGS : Compilation options for LAPACK. -Dlapack can not be removed.
- FLAGS: Other compilation options. OpenMP utilization option (-openmp, -fopenmp, -qopenmp, etc.) must be specified. When you use MPI, please set -D MPI.
- MTFLAGS, INCLUDE_DIR: Options for the Mersenne Twister and additional include directory. You do not have to modify them.

Then you are ready to compile HPhi. Please type

\$ make HPhi

and obtain an executable HPhi in src/directory; you should add this directory to the \$PATH.

Tips

login shell)

You can make a PATH to $\mathcal{H}\Phi$ as follows: \$ export PATH=\${PATH}: $HPhi_top_directory/src/$ If you keep this PATH, you should write above in ~/.bashrc (for bash as a

2.2.2 Using cmake

Tips

Before using cmake for sekirei, you must type

source /home/issp/materiapps/tool/env.sh

while for maki, you must type

source /global/app/materiapps/tool/env.sh

We can compile Hphi as

```
cd $HOME/build/hphi
cmake -DCONFIG=gcc $PathTohphi
make
```

Here, we set a path to $\mathcal{H}\Phi$ as \$PathTohphi and to a build directory as \$HOME/build/hphi. After compiling, a src folder is constructed below a \$HOME/build/hphi folder and obtain an executable HPhi in src/ directory. When there is not a MPI library in your system, an executable HPhi is automatically compiled without a MPI library.

In the above example, we compile $\mathcal{H}\Phi$ by using a gcc compiler. We can select a compiler by using following options

- sekirei : ISSP system-B "sekirei"
- fujitsu : Fujitsu compiler (ISSP system-C "maki")
- intel: intel compiler + Linux PC
- gcc : GCC compiler + Linux PC.

An example for compiling $\mathcal{H}\Phi$ by an intel compiler is shown as follows,

```
mkdir ./build
cd ./build
cmake -DCONFIG=intel ../
make
```

After compiling, a **src** folder is made below the **build** folder and an execute $\mathcal{H}\Phi$ is made in the **src** folder. It is noted that we must delete the **build** folder and do the above works again when we change the compilers.

2.3 Directory structure

When HPhi-xxx.tar.gz is unzipped, the following directory structure is composed.

```
|--CMakeLists.txt
|--COPYING
|--config/
     |--fujitsu.cmake
     |--gcc.cmake
     |--intel.cmake
     ---sekirei.cmake
|--doc/
     |--en/
     |--jp/
     |--userguide_en.pdf
     ---userguide_jp.pdf
|--HPhiconfig.sh
|--samples/
     |--Expert/
          |--Hubbard/
               |-square/
                       |--*.def
                       |--output_FullDiag/*.dat
                       |--output_Lanczos/*.dat
                      ---output_TPQ/*.dat
               --triangular/...
          |--Kondo/chain/...
          ---Spin/
               |-HeisenbergChain/...
               |-HeisenbergSquare/...
               |-Kagome/...
               |-Kagome36Boost/...
               |-Kitaev/...
               --S1Chain/...
     ---Standard/
          |--Hubbard/
               |-square/
                   |--StdFace.def
                   |--output_FullDiag/*.dat
                    |--output_Lanczos/*.dat
```

```
---output_TPQ/*.dat
               --triangular/...
          |--Kondo/chain/...
          ---Spin/
                |-HeisenbergChain/...
               |-HeisenbergSquare/...
               |-Kitaev/...
               --S1Chain/...
|--src/
     |--*.c
     |--CMakeLists.txt
     |--include/*.h
     |--makefile_src
     ---StdFace/
|--test/
---test_tool/
```

2.4 Basic usage

 $\mathcal{H}\Phi$ has two modes; standard mode and expert mode. Here, the basic flows of calculations by standard and expert modes are shown.

2.4.1 Standard mode

The procedure of calculation through the standard mode is shown as follows:

1. Make a directory for a calculation scenario.

First, you make a working directory for the calculation.

2. Make input files for standard mode

In the standard mode, you can choose a model (the Heisenberg model, the Hubbard model, etc.) and a lattice (the square lattice, the triangular lattice, etc.) from ones provided; you can specify some parameters (such as the first/second nearest neighbor hopping integrals, the on-site Coulomb integral, etc.) for them. Finally, you have to specify the numerical method (such as the Lanczos method) employed in this calculation. The input file format is described in the Sec. 4.

3. Run

Run a executable HPhi in terminal by setting option "-s" (or "--standard") and the name of input file written in previous step.

• Serial/OpenMP parallel \$ Path/HPhi -s Input_file_name

• MPI parallel/ Hybrid parallel

\$ mpiexec -np number_of_processes Path/HPhi -s Input_file_name When you use a queuing system in workstations or super computers, sometimes the number of processes is specified as an argument for the job-submitting command. If you need more information, please refer manuals for your system. A number of processes depend on a target of system for models. The details of setting a number of processes are shown in 2.4.3.

4. Watch calculation logs

Log files are outputted in the "output" folder which is automatically made in the directory for a calculation scenario. The details of output files are shown in 4.3.

5. Results

If the calculation is finished normally, the result files are outputted in the "output" folder. The details of output files are shown in 4.3.

Tips

The number of threads for OpenMP

If you specify the number of OpenMP threads for $\mathcal{H}\Phi$, you should set it as follows (in case of 16 threads) before the running:

export OMP_NUM_THREADS=16

2.4.2 *Expert* mode

The procedure of calculation for expert mode is shown as follows.

- 1. Make a directory for a calculation scenario. First, you make a directory named as a calculation scenario (you can attach an arbitrary name to a directory).
- 2. Make input files for expert mode

For expert mode, you should make input files for constructing Hamiltonian operators, calculation condition and a list file for the filenames of input files (see the file formats shown in 4.2).

Note: A List file can be easily made by using standard mode.

3. Run

Run $\mathcal{H}\Phi$ in terminal by setting option "-e" (or "--expert") and a file name of a list file.

- Serial/OpenMP
 - \$ Path/HPhi -e Input_List_file_name
- MPI/Hybrid

\$ mpiexec -np number_of_processes Path/HPhi -e Input_List_file_name A number of processes depend on a target of system for models. The details of setting a number of processes are shown in 2.4.3.

4. Under running

Log files are outputted in the "output" folder which is automatically made in the directory for a calculation scenario. The details of output files are shown in 4.3.

5. Results

If the calculation is finished normally, the result files are outputted in the "output" folder. The details of output files are shown in 4.3.

2.4.3 Setting a process number for MPI/Hybrid parallelization

For using MPI/Hybrid parallelization, a process number must be set as follows.

1. Standard mode

- Hubbard / Kondo model
 When model in an input file for Standard mode is set as "Fermion Hubbard",
 "Kondo Lattice" or "Fermion HubbardGC", a process number must be equal to 4ⁿ.
- Spin model
 When model in an input file for Standard mode is set as "Spin" or
 "SpinGC", a process number must be equal to $(2S+1)^n$ where 2S is set in
 the input file (a default value is 1).

2. Expert mode

- Hubbard / Kondo model
 When a model is selected as fermion Hubbard model or Kondo model by setting CalcModel in a CalcMod file, a process number must be equal to 4ⁿ. See 4.2.2 for details of a CalcModel file.
- Spin model

When a model is selected as Spin model by setting CalcModel in a CalcMod file, a process number is fixed by a LocSpin file. A process number must be equal to a number calculated by multiplying a state number of localized spin (2S+1) in descending order about site numbers. See 4.2.4 for details of a LocSpin file.

For example, when a **LocSpin** file is given as follws, a process number must be equal to 2 = 1 + 1, $6 = 2 \times (2 + 1)$, $24 = 6 \times (3 + 1)$.

2.4.4 Printing version ID

By using -v option as follows, you can check which version of $\mathcal{H}\Phi$ you are using.

\$ PATH/HPhi -v

Tutorial

3.1 Standard mode

3.1.1 Heisenberg model

This tutorial should be performed in

samples/Standard/Spin/HeisenbergChain/

The input file, reference outputs, and the redirected standard output are provided as follows:

```
samples/Standard/Spin/HeisenbergChain/StdFace.def
samples/Standard/Spin/HeisenbergChain/output_FullDiag/
samples/Standard/Spin/HeisenbergChain/output_Lanczos/
samples/Standard/Spin/HeisenbergChain/output_TPQ/
samples/Standard/Spin/HeisenbergChain/FullDiag.out
samples/Standard/Spin/HeisenbergChain/Lanczos.out
samples/Standard/Spin/HeisenbergChain/TPQ.out
```

In this case, we treat the one dimensional antiferromagnetic Heisenberg chain which has a nearest neighbor spin coupling.

$$\hat{H} = J \sum_{i=1}^{N_{\text{site}}} \hat{\mathbf{S}}_i \cdot \hat{\mathbf{S}}_{i+1} \tag{3.1}$$

The input file is as follows:

```
L = 16
model = "Spin"
method = "Lanczos"
lattice = "chain lattice"
J = 1.0
2Sz = 0
```

In this tutorial, J and the number of sites are set to 1 (arbitral unit) and 16 respectively.

Log output

Log messages are outputted to the standard output. Log files for calculation procedure are made in "output" directory which is automatically created. In this example, the following files are outputted.

```
CHECK_InterAll.dat Time_CG_EigenVector.dat zvo_Lanczos_Step.dat CHECK_Memory.dat WarningOnTransfer.dat zvo_sz_TimeKeeper.dat check_Sdim.dat zvo_TimeKeeper.dat
```

The details for the outputted files are shown in 4.3.1-4.3.11.

We execute

\$ Path/HPhi -s StdFace.def

and obtain following standard outputs (a compilation mode is MPI parallel/ Hybrid parallel):

```
##### Parallelization Info. #####
```

```
OpenMP threads : 4 MPI PEs : 1
```

Standard Intarface Mode STARTS

Open Standard-Mode Inputfile ./StdFace.def

```
KEYWORD : 1| VALUE : 16KEYWORD : model| VALUE : spinKEYWORD : method| VALUE : lanczos
```

Skipping a line. Skipping a line.

KEYWORD : lattice | VALUE : chainlattice

Parameter Summary

```
L = 16
   a = 1.00000
                   ######
                           DEFAULT VALUE IS USED
                                                   ######
   2S = 1
                           DEFAULT VALUE IS USED
                   ######
                                                   ######
   h = 0.00000
                   ######
                           DEFAULT VALUE IS USED
                                                   ######
Gamma = 0.00000
                   ###### DEFAULT VALUE IS USED
                                                   ######
   D = 0.00000
                   #####
                           DEFAULT VALUE IS USED
                                                   ######
   J = 1.00000
  Jz = 1.00000
                   ##### DEFAULT VALUE IS USED
                                                   ######
                           DEFAULT VALUE IS USED
  Jxy = 1.00000
                   ######
                                                   ######
   Jx = 1.00000
                   ######
                           DEFAULT VALUE IS USED
                                                   ######
   Jy = 1.00000
                   ######
                           DEFAULT VALUE IS USED
                                                   ######
   J' = 0.00000
                   ###### DEFAULT VALUE IS USED
                                                   ######
```

14 3 Tutorial

```
Jz' = 0.00000
                                ######
                                        DEFAULT VALUE IS USED
                                                               ######
             Jxy' = 0.00000
                                ###### DEFAULT VALUE IS USED
                                                               ######
              Jx' = 0.00000
                                ###### DEFAULT VALUE IS USED
                                                               ######
              Jy' = 0.00000
                                ###### DEFAULT VALUE IS USED
                                                               ######
      LargeValue = 1
                                ###### DEFAULT VALUE IS USED
                                                               ######
        filehead = zvo
                                ###### DEFAULT VALUE IS USED
                                                               ######
     Lanczos_max = 2000
                                ###### DEFAULT VALUE IS USED
                                                               ######
       initial_iv = 1
                                ###### DEFAULT VALUE IS USED
                                                               ######
            nvec = 1
                                ######
                                       DEFAULT VALUE IS USED
                                                               ######
             exct = 1
                                ###### DEFAULT VALUE IS USED
                                                               ######
      LanczosEps = 14
                                       DEFAULT VALUE IS USED
                                ######
                                                               ######
    LanczosTarget = 2
                                ###### DEFAULT VALUE IS USED
                                                               ######
           NumAve = 5
                                ###### DEFAULT VALUE IS USED
                                                               ######
   ExpecInterval = 20
                                ###### DEFAULT VALUE IS USED
                                                               ######
             2Sz = 0
      ioutputmode = 1
                                ##### DEFAULT VALUE IS USED #####
##### Print Expert input files #####
    zlocspin.def is written.
      zTrans.def is written.
   zInterAll.def is written.
   namelist.def is written.
     calcmod.def is written.
    modpara.def is written.
    greenone.def is written.
    greentwo.def is written.
######
        Input files are generated. ######
 Read File 'namelist.def'.
 Read File 'calcmod.def' for CalcMod.
 Read File 'modpara.def' for ModPara.
  Read File 'zlocspn.def' for LocSpin.
  Read File 'zTrans.def' for Trans.
  Read File 'zInterAll.def' for InterAll.
  Read File 'greenone.def' for OneBodyG.
  Read File 'greentwo.def' for TwoBodyG.
       Definition files are correct. #####
######
 Read File 'zlocspn.def'.
 Read File 'zTrans.def'.
 Read File 'zInterAll.def'.
 Read File 'greenone.def'.
 Read File 'greentwo.def'.
```

Indices and Parameters of Definition files(*.def) are complete.

MAX DIMENSION idim_max=12870
APPROXIMATE REQUIRED MEMORY max_mem=0.001236 GB

MPI site separation summary

INTRA process site

_	
Site	Bit
0	2
1	2
2	2
3	2
4	2
5	2
6	2
7	2
8	2
9	2
10	2
11	2
12	2
13	2
14	2
15	2

INTER process site
Site Bit

Process element info

Process Dimension Nup Ndown Nelec Total2Sz State
0 12870 8 8 8 0

Total dimension: 12870

LARGE ALLOCATE FINISH !

Start: Calculate HilbertNum for fixed Sz. End : Calculate HilbertNum for fixed Sz.

Start: Calculate diagaonal components of Hamiltonian. End : Calculate diagaonal components of Hamiltonian.

Start: Calculate Lanczos Eigenvalue.

initial_mode=0 normal: iv = 6437 i_max=12870 k_exct =1

16 3 Tutorial

```
LanczosStep E[1] E[2] E[3] E[4], E_Max / Nsite
  stp = 2 0.7192235936 2.7807764064 xxxxxxxxx xxxxxxxx
  stp = 4 - 1.1878294823 \ 0.6833997592 \ 2.1864630296 \ 3.4242789858 \ 0.2140174366
  stp = 6 -2.4623912732 -0.8925857144 0.5104359160 1.7443963706 0.2277205490
  stp = 8 - 3.5878334190 - 2.0969913075 - 0.8250723080 0.3369317092 0.2325450330
(snip)
  stp = 60 - 7.1422963606 - 6.8721066784 - 6.6965474265 - 6.5234070570 0.2499999989
  stp = 62 - 7.1422963606 - 6.8721066784 - 6.6965474266 - 6.5234070573 0.2499999996
  stp = 64 - 7.1422963606 - 6.8721066784 - 6.6965474266 - 6.5234070574 0.2499999999
        End : Calculate Lanczos EigenValue.
######
                                               ######
###### Start: Calculate Eigenvector. ######
  Start: Calculate Lanczos Eigenvector.
  End : Calculate Lanczos Eigenvector.
  Start: Calculate Energy.
  End : Calculate Energy.
  Accuracy check !!!
  LanczosEnergy = -7.14229636061676e+00
  EnergyByVec = -7.14229636061616e+00
  diff_ene
                = 8.50586433832080e-14
                = 9.97303843188625e-14
  var
  Accuracy of Lanczos vectors is enough.
######
        End : Calculate Eigenvector.
  Start: Calculate one body Green functions.
  End : Calculate one body Green functions.
  Start: Calculate two bodies Green functions.
  End : Calculate two bodies Green functions.
```

In the beginning of this run, files describing the detail of considered Hamiltonian (zlocspin.def, zTrans.def, zInterAll.def, namelist.def, calcmod.def, modpara.def) and files specifying elements of correlation functions that will be calculated (greenone.def, greentwo.def) are generated.

Tips

In the standard outputs at each even step, the quantity of E_Max / Nsite column indicates the maximum energy per sites (In this example, it converges to 0.249999999=0.25). In the TPQ calculation, you can set Largevalue larger than E_Max / Nsite.

Outputs for calculation results

Lanczos method

When a calculation by Lanczos method is finished normally, eigenenergies, one-body Green's functions and two-body Green's functions are calculated and outputted to the files, respectively. In this sample, following files are outputted.

```
zvo_energy.dat zvo_cisajs.dat zvo_cisajscktalt.dat
```

For standard mode, all pairs of $\langle n_{i\sigma} \rangle$ are calculated as one-body Green's functions and those of $\langle n_{i\sigma}n_{j\sigma'}\rangle$ are calculated as two-body Green's functions on the basis of the definition files, greenone.def and greentwo.def.

When accuracy of Lanczos vectors is enough, one-body and two-body Green's functions are calculated by eigenvectors obtained by Lanczos method. While accuracy of Lanczos vectors is *not* enough, a message "Accuracy of Lanczos vector is not enough" is outputted to the standard output and one-body and two-body Green's functions are calculated by eigenvectors obtained by CG method. The details of output files are shown in 4.3.12, 4.3.20, 4.3.21.

TPQ method

When method="TPQ" is selected in an input file, a calculation by TPQ method is started. After finishing of the calculation normally, following files are outputted, where %% is a number of run and && is a number of steps for TPQ method.

```
Norm_rand%%.dat SS_rand%%.dat
zvo_cisajs_set%%step&&.dat
zvo_cisajscktalt_set%%step&&.dat
```

In Norm_rand%%.dat, basic informations such as inverse of temperature and a norm of wave function before normalization are outputted with a TPQ step for each number of runs. In SS_rand%%.dat, physical quantities such as inverse of temperature, energy and expected value of square of Hamiltonian are outputted with a TPQ step for each number of runs. In zvo_cisajs_set%%step&&.dat and zvo_cisajscktalt_set%%step&&.dat, one-body and two-body Green's functions are outputted for each number of a TPQ steps and runs. The details of these files are shown in 4.3.15, 4.3.16, 4.3.20, 4.3.21.

Full diagonalization method

When method = "fulldiag" is selected in an input file, a calculation by Full diagonalization method is started. After finishing of the calculation normally, following files are outputted, where xx is a number of an eigenstate counting from 0.

18 3 Tutorial

```
Eigenvalue.dat zvo_cisajs_eigen_xx.dat zvo_cisajscktalt_eigen_xx.dat zvo_phys_Nup4_Ndown4.dat
```

In Eigenvalue.dat, an eigennumber and an eigenvalue are outputted for each lines. In zvo_cisajs_eigen_xx.dat and zvo_cisajscktalt_eigen_xx.dat, one-body Green's functions and two-body Green's functions are outputted for each eigennumber. In zvo_phys_Nup4_Ndown4.dat, physical quantities such as expected values of energy and doublon are outputted. The details of these files are shown in 4.3.18 - 4.3.21.

3.1.2 Other tutorials

There are following tutorials in samples/Standard/.

- The Hubbard model on the two dimensional square lattice (samples/Standard/Hubbard/square/)
- The Hubbard model on the two dimensional triangular lattice (samples/Standard/Hubbard/triangular/)
- The one dimensional Kondo chain (samples/Standard/Kondo/chain/)
- The one dimensional antiferromagnetic Heisenberg chain (samples/Standard/Spin/HeisenbergChain/HeisenbergChain/)
- The antiferromagnetic Heisenberg model on the two dimensional square lattice (samples/Standard/Spin/HeisenbergSquare/)
- The Kitaev model with 2×3 unit cells to Honeycomb lattice (samples/Standard/Spin/Kitaev/)

We can perform these tutorials in the same way to the previous one.

3.2 Expert mode

For expert mode, following input files are needed

- 1. A file list for input files,
- 2. Files for basic parameters,
- 3. Files for constructing Hamiltonian,
- 4. Files for setting output components.

The process after calculation is same as standard mode. In this section, we show the demonstration for one dimensional antiferromagnetic Heisenberg chain model which has a nearest neighbor spin coupling,

$$H = \sum_{i=0}^{15} J \boldsymbol{S}_i \cdot \boldsymbol{S}_{i+1}, \tag{3.2}$$

where J = 2, $S_{16} = S_0$.

We use following input files in samples/Expert/Spin/HeisenbergChain.

```
calcmod.def greentwo.def namelist.def zTrans.def greenone.def modpara.def zInterAll.def zlocspn.def
```

3.2.1 A file list for input files

In namelist.def, kinds of input files and filenames are defined as shown below. By writing keyword and filenames at each lines, kinds of files are distinguished. The details for namelist.def are shown in 4.2.1.

```
CalcMod calcmod.def
ModPara modpara.def
LocSpin zlocspn.def
Trans zTrans.def
InterAll zInterAll.def
OneBodyG greenone.def
TwoBodyG greentwo.def
```

3.2.2 Files for basic parameters

In this subsection, we show the way to set a calculation mode, parameters for calculation and positions of localized spins.

Setting a calculation mode

Calculation mode is set in a CalcMod file (in this sample file, calcmod.def). The contents of files are shown as below.

```
#CalcType = 0:Lanczos, 1:TPQCalc, 2:FullDiag
#CalcMod = 0:Hubbard, 1:Spin, 2:Kondo, 3:HubbardGC,
4:SpinGC, 5:KondoGC
CalcType 0
CalcModel 1
```

We select a calculation method by CalcType and a target model by CalcModel. In this sample, we set Lanczos method as a calculation method and a target model as a spin system (canonical ensemble). The details of a CalcMod file are shown in 4.2.2.

20 3 Tutorial

Setting parameters for calculation

Parameter for calculation are set in a ModPara file (in this sample, modpara.def). The contents of files are shown as below.

```
Model_Parameters
_____
VMC_Cal_Parameters
CDataFileHead zvo
CParaFileHead
              zqp
Nsite
              16
Ncond
               0
2Sz
              0
              1000
Lanczos_max
initial_iv
               12
nvec
               1
exct
LanczosEps
              14
LanczosTarget
              2
LargeValue
              12
NumAve
               5
              20
ExpecInterval
```

In this file, we set parameters for calculation such as a site number, a total number of conduction electrons, a total S_z and a number of Lanczos step etc. The details of ModPara file are shown in 4.2.3.

Setting positions of localized spins

Positions and S of localized spins are defined by a LocSpin file (in this sample, locspn.def). The contents of files are shown as below.

When CalcModel in a CalcMod file is set as spin system, all sites automatically treated as localized spins. The details of a LocSpin file is shown in 4.2.4.

3.2.3 Files for constructing Hamiltonian

After setting basic parameters, we make input files for constructing Hamiltonian. Since calculations are done by the representation of fermion operators in $\mathcal{H}\Phi$, we must rewrite spin operator. For example, in the case of S=1/2, we rewrite the equation by using the following relation

$$S_z^{(i)} = (c_{i\uparrow}^{\dagger} c_{i\uparrow} - c_{i\downarrow}^{\dagger} c_{i\downarrow})/2, \tag{3.3}$$

$$S_{+}^{(i)} = c_{i\uparrow}^{\dagger} c_{i\downarrow}, \tag{3.4}$$

$$S_{-}^{(i)} = c_{i\downarrow}^{\dagger} c_{i\uparrow}. \tag{3.5}$$

Setting transfer integrals

In a Trans file (in this sample, zTrans.def), we set a transfer part of Hamiltonian,

$$H + = -\sum_{ij\sigma_1\sigma_2} t_{ij\sigma_1\sigma_2} c_{i\sigma_1}^{\dagger} c_{j\sigma_2}. \tag{3.6}$$

The contents of files are shown as below.

We can use this term when an electric magnetic field is added in spin system. For example, when an magnetic field is added at a site 1 such as $-0.5S_z^{(1)}$ for S=1/2, this term can be rewritten as $-0.5/2(c_{1\uparrow}^{\dagger}c_{1\uparrow}-c_{1\downarrow}^{\dagger}c_{1\downarrow})$. Thus, the input file becomes as follows.

```
NTransfer 1
======i_j_s_tijs=====

1 0 1 0 -0.25 0
1 1 1 1 0.25 0
```

The details for a Trans file are shown in 4.2.5.

Setting general two-body interactions

In an InterAll file (in this sample, zInterall.def), we set a general two-body

22 3 Tutorial

interaction part of Hamiltonian,

$$H + = \sum_{i,j,k,l} \sum_{\sigma_1,\sigma_2,\sigma_3,\sigma_4} I_{ijkl\sigma_1\sigma_2\sigma_3\sigma_4} c_{i\sigma_1}^{\dagger} c_{j\sigma_2} c_{k\sigma_3}^{\dagger} c_{l\sigma_4}. \tag{3.7}$$

The contents of files are shown as below.

======			===						
NInterAl	.1	96							
			===						
=======		 CVTT===							
0	0	0	0	1	0	1	0	0.500000	0.000000
0	0	0	0	1	1	1	1	-0.500000	0.000000
0	1	0	1	1	0	1	0	-0.500000	0.000000
0	1	0	1	1	1	1	1	0.500000	0.000000
0	0	0	1	1	1	1	0	1.000000	0.000000
0	1	0	0	1	0	1	1	1.000000	0.000000

Here, we explain an interaction between a site i and a site j in the case of S=1/2, for simplicity. Using fermion operators, interaction terms for spin operators can be rewritten as

$$\begin{split} H_{i,i+1} &= J(S_x^{(i)} S_x^{(i+1)} + S_y^{(i)} S_y^{(i+1)} + S_z^{(i)} S_z^{(i+1)}) \\ &= J\left(\frac{1}{2} S_+^{(i)} S_-^{(i+1)} + \frac{1}{2} S_-^{(i)} S_+^{(i+1)} + S_z^{(i)} S_z^{(i+1)}\right) \\ &= J\left[\frac{1}{2} c_{i\uparrow}^{\dagger} c_{i\downarrow} c_{i+1\downarrow}^{\dagger} c_{i+1\uparrow} + \frac{1}{2} c_{i\downarrow}^{\dagger} c_{i\uparrow} c_{i+1\uparrow}^{\dagger} c_{i+1\downarrow} + \frac{1}{4} (c_{i\uparrow}^{\dagger} c_{i\uparrow} - c_{i\downarrow}^{\dagger} c_{i\downarrow}) (c_{i+1\uparrow}^{\dagger} c_{i+1\uparrow} - c_{i+1\downarrow}^{\dagger} c_{i+1\downarrow})\right]. \end{split}$$

Thus, the interaction $S_z^{(i)} S_z^{(i+1)}$ for J=2 can be written as

i	0	i	0	i+1	0	i+1	0	0.500000	0.000000
i	0	i	0	i+1	1	i+1	1	-0.500000	0.000000
i	1	i	1	i+1	0	i+1	0	-0.500000	0.000000
i	1	i	1	i+1	1	i+1	1	0.500000	0.000000
)

in the format of an InterAll file. The other terms can be written as below.

	/										\
-		i	0	i	1	i+1	1	i+1	0	1.000000	0.000000
		i	1	i	0	i+1	0	i+1	1	1.000000	0.00000
,											/

There are other file formats for constructing Hamiltonian. The details for input formats of two-body interactions are shown in 4.2.6-4.2.13.

3.2.4 Setting output components

In OneBodyG and TwoBodyG files, calculating components for one-body and two-body Green's functions are defined, respectively.

Setting calculating components for one-body Green's functions

In a OneBodyG file (in this sample, greenone.def), calculating components for $\langle c_{i\sigma_1}^{\dagger} c_{j\sigma_2} \rangle$ are defined. The contents of files are shown as below.

NCisAjs		32		
=======	====== = Greer	funct	tions	======
0	0	0	0	
0	1 0 1	0	1	
1	0	1	0	
1	1	1	1	
2	0	2	0	

The details for input formats of a OneBodyG file are shown in 4.2.14.

Setting calculating components for two-body Green's functions

In a TwoBodyG file (in this sample, greentwo.def), calculating components for $\langle c_{i\sigma_1}^{\dagger} c_{j\sigma_2} c_{k\sigma_3}^{\dagger} c_{l\sigma_4} \rangle$ are defined. The contents of files are shown as below.

NCisAjsCktAltDC 1024						
 	====== Green ======	functions	for Sq	===== AND Nq ======	====== _ =======	
0	0	0 0	0	0	0	0
0	0	0 0	0	1	0	1
0	0	0 0	1	0	1	0
0	0	0 0 0	1	1	1	1
0	0	0 0	2	0	2	0

The details for input formats of a TwoBodyG file are shown in 4.2.15.

3.2.5 Running

After making all input files above, we ready to run a program. For expert mode, we must set an option "-e" and a file name list (in this sample, namelist.def) as arguments to run $\mathcal{H}\Phi$.

\$ Path/HPhi -e namelist.def

The process after calculating is same as that of standard mode.

3.2.6 Other tutorials

There are following tutorials in samples/Expert/.

24 3 Tutorial

- The Hubbard model on the two dimensional square lattice (samples/Expert/Hubbard/square/)
- The Hubbard model on the two dimensional triangular lattice (samples/Expert/Hubbard/triangular/)
- The one dimensional Kondo chain (samples/Expert/Kondo/chain/)
- The one dimensional antiferromagnetic Heisenberg chain (samples/Expert/Spin/HeisenbergChain/HeisenbergChain/)
- The antiferromagnetic Heisenberg model on the two dimensional square lattice (samples/Expert/Spin/HeisenbergSquare/)
- The Kitaev model with 2×3 unit cells to Honeycomb lattice (samples/Expert/Spin/Kitaev/)

We can perform these tutorials in the same way to the previous one.

3.3 Making input files for Expert mode

This mode is to make input files for *Expert* mode. A set of input files made by this mode gives a model provided in *Standard* mode. The usage is shown as below.

- 1. Make an input file for *Standard* mode.
- 2. Setting an option "-sdry" and an input file (in this example, StdFace.def), run $\mathcal{H}\Phi$.
 - \$ Path/HPhi -sdry StdFace.def

In this case, you should not use MPI parallelization (mpirun, mpiexec, etc.).

3. Following files are made as input files for *Expert* mode in the present working directory.

```
calcmod.def greentwo.def namelist.def zTrans.def
greenone.def modpara.def zInterAll.def zlocspn.def
```

4

File specification

4.1 Input files for Standard mode

An example of input file for the standard mode is shown below:

```
W = 2
L = 4
model = "spin"
method = "Lanczos"

lattice = "triangular lattice"
//mu = 1.0
// t = -1.0
// t' = -0.5
// U = 8.0
//V = 4.0
//V'=2.0
J = -1.0
J'=-0.5
// nelec = 8
2Sz = 0
```

Basic rules for input files

- In each line, there is a set of a keyword (before an "=") and a parameter (after an "="); they are separated by "=".
- You can describe keywords in a random order.
- Empty lines and lines beginning in a "//" (comment outs) are skipped.
- Upper- and lowercase are not distinguished. Double quotes and blanks are ignored.
- There are three kinds of parameters.
 - 1. Parameters that must be specified (if not, $\mathcal{H}\Phi$ will stop with error messages),
 - 2. Parameters that is not necessary be specified (if not, default values are used),
 - 3. Parameters that must not be specified (if specified, $\mathcal{H}\Phi$ will stop with error messages).

An example of 3 is transfer t for the Heisenberg spin system. If you choose "model=spin", you should not specify "t".

We explain each keywords as follows:

4.1.1 Parameters about the kind of a calculation

• model

Type: String (Choose from "Fermion Hubbard", "Spin", "Kondo Lattice", "Fermion HubbardGC", "SpinGC", "Kondo LatticeGC", "SpinGCBoost") *1

Description : The target model is specified with this parameter; above words denote the canonical ensemble of the Fermion in the Hubbard model

$$H = -\mu \sum_{i\sigma} c_{i\sigma}^{\dagger} c_{i\sigma} - \sum_{i \neq j\sigma} t_{ij} c_{i\sigma}^{\dagger} c_{j\sigma} + \sum_{i} U n_{i\uparrow} n_{i\downarrow} + \sum_{i \neq j} V_{ij} n_{i} n_{j}, \tag{4.1}$$

canonical ensemble in the Spin model $(\{\sigma_1, \sigma_2\} = x, y, z)$

$$H = -h \sum_{i} S_{iz} - \Gamma \sum_{i} S_{ix} + D \sum_{i} S_{iz} S_{iz} + \sum_{ij,\sigma_{1} \neq \sigma_{2}} J_{ij\sigma_{1}\sigma_{2}} S_{i\sigma_{1}} S_{j\sigma_{2}},$$

$$+ \sum_{ij,\sigma_{1}} J_{ij\sigma_{1}} S_{i\sigma_{1}} S_{j\sigma_{1}} + \sum_{ij,\sigma_{1} \neq \sigma_{2}} J_{ij\sigma_{1}\sigma_{2}} S_{i\sigma_{1}} S_{j\sigma_{2}},$$
(4.2)

canonical ensemble in the Kondo lattice model

$$H = -\mu \sum_{i\sigma} c_{i\sigma}^{\dagger} c_{i\sigma} - t \sum_{\langle ij \rangle \sigma} c_{i\sigma}^{\dagger} c_{j\sigma} + \frac{J}{2} \sum_{i} \left\{ S_{i}^{+} c_{i\downarrow}^{\dagger} c_{i\uparrow} + S_{i}^{-} c_{i\uparrow}^{\dagger} c_{i\downarrow} + S_{iz} (n_{i\uparrow} - n_{i\downarrow}) \right\},$$

$$(4.3)$$

grand canonical ensemble of the Fermion in the Hubbard model [Eqn. (4.1)], grand canonical ensemble in the Spin model [Eqn. (4.2)], and grand canonical ensemble in Kondo lattice model [Eqn. (4.3)] respectively.

When model="SpinGCBoost", by using more efficient algorithm*², $\mathcal{H}\Phi$ calculates a system the same as "SpinGC". However, supported models and MPI processes are highly limited. See "Lattice" section.

• method

Type: String (Choose from "Lanczos", "TPQ", "Full Diag")

Description: The calculation type is specified with this parameter; above words denote the single eigenstate calculation by using the Lanczos method, at the finite-temperature by thermally pure quantum state, and the full diagonalization method, respectively.

^{*1}GC=Grand Canonical

^{*2}Y. Yamaji et. al., manuscript in preparation.

• lattice

Type: String (Choose from "Chain Lattice", "Square Lattice", "Triangular Lattice", "Honeycomb Lattice", "Ladder", "Kagome")

Description: The lattice shape is specified with this parameter; above words denote the one dimensional chain lattice (Fig. 4.1(a)), the two dimensional square lattice (Fig. 4.1(b)), the two dimensional triangular lattice (Fig. 4.1(c)), the two dimensional anisotropic honeycomb lattice (Fig. 4.2), the ladder lattice (Fig. 4.4), and the Kagome Lattice(Fig. 4.3) respectively.

In method="SpinGCBoost", only "Chain Lattice", "Honeycomb Lattice", "Ladder", and "Kagome" are supported. Limits of L, W, and the number of MPI processes $(N_{\rm proc})$ are as follows:

- "Chain Lattice"
 - L=8n (where n is an integer number under the condition $n\geq 1$), $N_{\rm proc}\leq 2(L=8),\,N_{\rm proc}\leq 2^{L/2-2}(L>8).$
- "Honeycomb Lattice"

$$W = 3, L \ge 2, N_{\text{proc}} \le 2(L = 2), N_{\text{proc}} \le 64(L > 2).$$

- "Ladder"

W=2, L=2n (where n is an integer number under the condition $n\geq 4$), $N_{\mathrm{proc}}\leq 2^{L-4}$.

- "Kagome"

 $W = 3, L \ge 2, N_{\text{proc}} \le 1(L = 2), N_{\text{proc}} \le 512(L > 2).$

4.1.2 Parameters for the lattice

Chain [Fig. 4.1(a)]

• L

Type: Integer

Description: The length of the chain is specified with this parameter.

Ladder (Fig. 4.4)

• L

Type: Integer

Description: The length of the ladder is specified with this parameter.

W

Type: Integer

Description: The number of the ladder is specified with this parameter.




Figure 4.1: Schematic illustration of (a) one dimensional chain lattice, (b) two dimensional square lattice, and (c) two dimensional triangular lattice. They have t, V, and J as a nearest neighbor hopping, an offsite Coulomb integral, and a spin-coupling constant, respectively (magenta solid lines); They also have t', V', and J' as a next nearest neighbor hopping, offsite Coulomb integral, and spin-coupling constant, respectively (green dashed line).




Figure 4.2: Schematic illustration of the anisotropic honeycomb lattice. The nearest neighbor hopping integral, spin coupling, offsite Coulomb integral depend on the bond direction. Those between second nearest neighbor sites are not supported.




Figure 4.3: Schematic illustration of the Kagome lattice.




Figure 4.4: Schematic illustration of the ladder lattice.




Figure 4.5: The shape of the numerical cell when $\mathbf{a}_0 = (6, 2)$, $\mathbf{a}_1 = (2, 4)$ in the triangular lattice. The region surrounded by \mathbf{a}_0 (Magenta dashed arrow) and \mathbf{a}_1 (Green dashed arrow) becomes the cell to be calculated (20 sites).

Tetragonal lattice [Fig. 4.1(b)], Triangular lattice[Fig. 4.1(c)], Honeycomb lattice(Fig. 4.2), Kagome lattice(Fig. 4.3)

In these lattices, we can specify the shape of the numerical cell by using the following two methods.

• W, L

Type: Integer

Description: The alignment of original unit cells (dashed black lines in Figs. 4.1 - 4.3) is specified with these parameter.

• a0W, a0L, a1W, a1L

Type: Integer

Description: We can specify two vectors $(\boldsymbol{a}_0, \boldsymbol{a}_1)$ that surrounds the numerical cell (Fig. 4.5). These vectors should be specified in the Fractional coordinate.

If we use both of these method, $\mathcal{H}\Phi$ stops. When model=SpinGCBoost, we can use only the former.

We can check the shape of the numerical cell by using a file lattice.gp which is written in the Standard mode. This file can be read by gnuplot as follows:

\$ gnuplot lattice.gp

4.1.3 Parameters for conserved quantities

• nelec

Type: Positive integer

Description: The number of valence electrons is specified with this parameter. When model = "Fermion HubbardGC", "Spin", or "SpinGC", it should not be specified.

• 2Sz

Type: Integer

Description: The z component of the twofold total spin is specified with this parameter. When model = "Fermion HubbardGC" or SpinGC, it should not be specified.

4.1.4 Parameters for the Hamiltonian

A default value is set as 0 unless a specific value is not defined in a description. Table 4.1 shows the parameters for each models. In the case of a complex type, a file format is "a real part, an imaginary part" while in the case of a real type, only "a real part".

Local terms

• mu

Type: Real

Description : (Hubbard and Kondo lattice model) The chemical potential μ (including the site potential) is specified with this parameter.

U

Type: Real

Description: (Hubbard and Kondo lattice model) The onsite Coulomb integral U is specified with this parameter.

• Jx, Jy, Jz, Jxy, Jyx, Jxz, Jzx, Jyz, Jzy

Type: Real

Description: (Kondo lattice model) The spin-coupling constant between the valence and the local electrons is specified with this parameter. If the exchange coupling J is specified in the input file, instead of Jx, Jy, Jz, the diagonal exchange couplings, Jx, Jy, Jz, are set as Jx = Jy = Jz = J. When both the set of exchange couplings (Jx, Jy, Jz) and the exchange coupling J are specified in the input file, $\mathcal{H}\Phi$ will stop.

• h, Gamma, D

Type: Real

Description: (Spin model) The longitudinal magnetic field, transverse magnetic field, and the single-site anisotropy parameter are specified with these parameters. The single-site anisotropy parameter is not available for model=SpinGCBoost.

The non-local terms described below should be specified in different ways depending on the lattice structure: For lattice=Ladder, the non-local terms are specified in the different way from lattice=Chain Lattice, Square Lattice, Triangular Lattice, Honeycomb Lattice, Kagome. Below, the available parameters for each lattice are shown in Table 4.1.

Interactions	1D chain	2D square	2D triangular	Honeycomb	Kagome	Ladder
J, t, V (simplified)	0	0	0	0	0	-
J', t', V'	0	0	0	0	0	-
J0, t0, V0	0	0	0	0	0	0
J1, t1, V1	-	0	0	0	0	0
J2, t2, V2	-	-	0	0	0	0
J1', t1', V1'	-	-	-	-	-	0
J2',t2', V2'	-	-	-	-	-	0

Table 4.1: Interactions for each models defined in an input file. We can define spin couplings as matrix format.

Non-local terms for Ladder (Fig. 4.4)]

• t0, t1, t1', t2, t2'

Type: Complex

Description: (Hubbard and Kondo lattice model) Hopping integrals in the ladder lattice (See Fig. 4.4) is specified with this parameter.

• VO, V1, V1', V2, V2'

Type: Real

Description: (Hubbard and Kondo lattice model) Offsite Coulomb integrals on the ladder lattice (Fig. 4.2 are specified with these parameters.

- JOx, JOy, JOz, JOxy, JOyx, JOxz, JOzx, JOyz, JOzy
- J1x, J1y, J1z, J1xy, J1yx, J1xz, J1zx, J1yz, J1zy
- J1'x, J1'y, J1'z, J1'xy, J1'yx, J1'xz, J1'zx, J1'yz, J1'zy
- J2x, J2y, J2z, J2xy, J2yx, J2xz, J2zx, J2yz, J2zy

• J2'x, J2'y, J2'z, J2'xy, J2'yx, J2'xz, J2'zx, J2'yz, J2'zy

Type: Real

Description: (Spin model) Spin-coupling constants in the ladder lattice (See Fig. 4.4) are specified with these parameter. If the simplified parameter J0 is specified in the input file instead of the diagonal couplings, J0x, J0y, J0z, these diagonal couplings are set as J0x = J0y = J0z = J0. If both J0 and the set of the couplings (J0x, J0y, J0z) are specified, $\mathcal{H}\Phi$ will stop. The above rules are also valid for the simplified parameters, J1, J1', J2, and J2'.

Non-local terms [other than Ladder (Figs. 4.1, 4.2, 4.3)]

• t0, t1, t2

Type: Complex

Description: (Hubbard and Kondo lattice model) Nearest neighbor hoppings for each direction (See Figs. 4.1-4.3) are specified with these parameter. If there is no bond dependence of the hoppings, the simplified parameter t is available to specify t0, t1, and t2 as t0 = t1 = t2 = t. If both t and the set of the hoppings (t0, t1, t2) are specified, $\mathcal{H}\Phi$ will stop.

• V0, V1, V2

Type: Real

Description: (Hubbard and Kondo lattice model) Nearest-neighbor offsite Coulomb integrals V for each direction (See Figs. 4.1-4.3) are specified with these parameters. If there is no bond dependence of the offsite Coulomb integrals, the simplified parameter V is available to specify VO, V1, and V2 as VO = V1 = V2 = V. If both V and the set of the Coulomb integrals (VO, V1, V2) are specified, $\mathcal{H}\Phi$ will stop.

- J0x, J0y, J0z, J0xy, J0yx, J0xz, J0zx, J0yz, J0zy
- J1x, J1y, J1z, J1xy, J1yx, J1xz, J1zx, J1yz, J1zy
- J2x, J2y, J2z, J2xy, J2yx, J2xz, J2zx, J2yz, J2zy

Type: Real

Description : (Spin model) Nearest-neighbor exchange couplings for each direction are specified with thees parameters. If the simplified parameter J0 is specified, instead of J0x, J0y, J0z, the exchange couplings, J0x, J0y, J0z, are set as J0x = J0y = J0z = J0. If both J0 and the set of the exchange couplings (J0x, J0y, J0z) are specified, $\mathcal{H}\Phi$ will stop. The above rules are valid for J1 and J2.

If there is no bond dependence of the exchange couplings, the simplified parameters, Jx, Jy, Jz, Jxy, Jyx, Jxz, Jzx, Jyz, Jzy, are available to specify the exchange couplings for every bond as J0x = J1x = J2x = Jx. If any simplified parameter $(Jx\sim Jzy)$ is specified in addition to its counter parts

 $(J0x\sim J2zy)$, $\mathcal{H}\Phi$ will stop. Below, examples of parameter sets for nearest-neighbor exchange couplings are shown.

- If there are no bond-dependent, no anisotropic and offdiagonal exchange couplings (such as J_{xy}), please specify J in the input file.
- If there are no bond-dependent and offdiagonal exchange couplings but are anisotropic couplings, please specify the non-zero couplings in the diagonal parameters, Jx, Jy, Jz.
- If there are no bond-dependent exchange couplings but are anisotropic and offdiagonal exchange couplings, please specify the non-zero couplings in the nine parameters, Jx, Jy, Jz, Jxy, Jyz, Jxz, Jyx, Jzy, Jzx.
- If there are no anisotropic and offdiagonal exchange couplings, but are bond-dependent couplings, please specify the non-zero couplings in the three parameters, J0, J1, J2.
- If there are no anisotropic exchange couplings, but are bond-dependent and offdiagonal couplings, please specify the non-zero couplings in the nine parameters, J0x, J0y, J0z, J1x, J1y, J1z, J2x, J2y, J2z.
- If there are bond-dependent, anisotropic and offdiagonal exchange couplings, please specify the non-zero couplings in the twenty-seven parameters from J0x to J2zy.

• t'

Type: Complex

Description: (Hubbard and Kondo lattice model) Nearest neighbor hoppings for each direction (See Figs. 4.1-4.3) are specified with these parameter.

V,

Type: Real

Description : (Hubbard and Kondo lattice model) Nearest neighbor-offsite Coulomb integrals V for each direction (See Figs. 4.1-4.3) are specified with these parameters.

• J'x, J'y, J'z, J'xy, J'yx, J'xz, J'zx, J'yz, J'zy

Type: Real

Description: (Spin model) Second nearest-neighbor exchange couplings are specified. However, for lattice = Honeycomb Lattice and lattice = Kagome with model=SpinGCBoost, the second nearest-neighbor exchange couplings are not available in the Standard mode. If the simplified parameter J' is specified, instead of J'x, J'y, J'z, the exchange couplings are set as J'x = J'y = J'z = J'. If both J' and the set of the couplings (J'x, J'y, J'z), $\mathcal{H}\Phi$ will stop.

4.1.5 Parameters for the numerical condition

• Lanczos_max

Type: Positive integer (2000 as a default)

Description : Upper limit of the Lanczos step is specified with this parameter.

• initial_iv

Type: Integer (-1 as a default)

Description: An initial vector is specified with this parameter.

Lanczos method

- * For canonical ensemble and initial_iv ≥ 0 The non-zero components of an initial vector is specified with this parameter.
- * For grand canonical ensemble or initial_iv < 0
 A seed of random generator is given by this parameter and the random vector is used as an initial vector.

- TPQ method

A seed of random generator is given by this parameter and the random vector is used as an initial vector.

See 5 for details of setting an initial vector.

• exct

Type: Positive integer (1 as a default)

Description : We specify the number of getting eigenvectors from the ground energy by Lanczos method.

When exct=2, we obtain the eigenvector of the first-excited state.

Note: the following condition must be satisfied: nvec >= exct.

• LanczosEps

Type: Positive Integer (14 as a default)

Description : The convergence criteria for the Lanczos method is specified with this parameter. If the difference between the old and the new target eigenvalue fall below $10^{-\text{LanczosEps}}$, the Lanczos step will finish.

• LancczosTarget

Type: Positive integer (2 as a default)

Description: We specify the target eigenenergy for the convergence criteria. If this set to 1, target eigenenergy becomes the ground state.

• LargeValue

Type: Double (The default value is written below.)

Description : (Only for TPQ) We use l as $l - \hat{H}/N_s$ in the TPQ calculation. Usually, the largest eigenvalue of Hamiltonian is used as l. Thus, we take the default value of l as a summation of the absolute values of each coefficients in the Hamiltonian divided by the number of sites.

• NumAve

Type: Positive integer (5 as a default)

Description: (Only for the TPQ) The number of independent runs for the TPQ method is specified with this parameter.

• ExpecInterval

Type: Positive integer (20 as a default)

Description: (Only for the TPQ) We specify the interval steps of calculating correlation functions in TPQ method.

Note: The small interval increases the time cost of calculations.

• OutputMode

Type: Choose from "none", "correlation", and "full" (correlation as a default)

Description: Indices of correlation functions are specified with this keyword. "none" indicates correlation functions will not calculated. When outputmode="correlation", $\langle c_{i\sigma}^{\dagger}c_{i\sigma}\rangle$ is computed at all i,σ , and $\langle c_{i\sigma}^{\dagger}c_{i\sigma}c_{j\sigma'}^{\dagger}c_{j\sigma'}\rangle$ is computed at all i,j,σ,σ' . If "full" is selected, $\langle c_{i\sigma}^{\dagger}c_{j\sigma'}\rangle$ is computed at all i,j,σ,σ' , and $\langle c_{i_1\sigma_1}^{\dagger}c_{i_2\sigma_2}c_{i_3\sigma_3}^{\dagger}c_{i_4\sigma_4}\rangle$ is computed at all $i,j,\sigma,\sigma,\sigma'$, and i,j,σ,σ' , and i,j,σ' , and i

In spin system, indices are specified as those on the Bogoliubov representation (See 5.4).

4.2 Input files for Expert mode

In this section, details of input files for expert mode are explained. Input files are categorized by the following four parts.

- (1) List: This file is a list of input file names with keywords. Each keywords is fixed, but file names are free to be determined.
- (2) Basic parameters: The following input files give basic parameters. The kinds of input files are determined by keywords.

CalcMod: Set the parameters for calculation modes.

ModPara: Set the parameters for basic parameters such as site number, electron number, Lanczos step *etc*.

LocSpin: Set the location of local spin (only used in Kondo model).

(3) Hamiltonian: Hamiltonian for $\mathcal{H}\Phi$ is denoted by the format of interactions for electron system. The kinds of interactions are determined by the following keywords.

Trans: The one body part, $c_{i\sigma_1}^{\dagger}c_{j\sigma_2}$.

InterAll: The general two body interactions, $c_{i\sigma_1}^{\dagger}c_{j\sigma_2}c_{k\sigma_3}^{\dagger}c_{l\sigma_4}$. We can set interactions which are often used by the following keywords.

CoulombIntra: On-site Coulomb interactions, $n_{i\uparrow}n_{i\downarrow}$ $(n_{i\sigma}=c_{i\sigma}^{\dagger}c_{i\sigma})$.

CoulombInter: Off-site Coulomb interactions, $n_i n_j$ $(n_i = n_{i\uparrow} + n_{i\downarrow})$.

Hund: Hund couplings, $n_{i\uparrow}n_{j\uparrow} + n_{i\downarrow}n_{j\downarrow}$.

PairHop: Pair hopping couplings, $c_{i\uparrow}^{\dagger}c_{j\uparrow}c_{j\downarrow}^{\dagger}c_{j\downarrow}$.

Exchange: Exchange couplings, $c_{i\uparrow}^{\dagger}c_{j\uparrow}c_{j\downarrow}^{\dagger}c_{i\downarrow}$.

Ising: Ising interactions, $S_i^z S_j^z$.

PairLift: PairLift couplings, $c_{i\uparrow}^{\dagger} c_{i\downarrow} c_{j\uparrow}^{\dagger} c_{j\downarrow}$.

(4) Output: Targets for output is determined.

OneBodyG: One-body green functions, $\langle c_{i\sigma_1}^{\dagger} c_{j\sigma_2} \rangle$.

TwoBodyG: Two-body green functions, $\langle c_{i\sigma_1}^{\dagger} c_{j\sigma_2} c_{k\sigma_3}^{\dagger} c_{l\sigma_4} \rangle$.

4.2.1List file for Input files

. This file determines input filenames which are correlated with keywords. File format is shown as follows.

CalcMod calcmod.def ModPara modpara.def LocSpin zlocspn.def Trans ztransfer.def InterAll zinterall.def OneBodyG zcisajs.def TwoBodyG zcisajscktaltdc.def

File format

[string01] [string02]

Parameters

• [string01]

Type: string-type

Description: Select a word from keywords.

• [string02]

Type: string-type

Description: An input filename which is correlated with keywords.

Use rules

- After setting keywords at [string 01], half-width state is needed for writing a filename. You can set the filename freely.
- Keywords for input files are shown in Table 4.2.
- \bullet Essential keywords are "CalcMod", "ModPara" and "LocSpin".
- Keywords can be set in random order.
- If keywords or filenames are incorrect, the program is terminated.
- When the head of line is "#", the line is skipped.

Keywords	Details for corresponding files
CalcMod	Parameters for modes of calculation.
ModPara	Parameters for calculation.
LocSpin	Configurations of the local spins for Hamiltonian.
Trans	Transfer and chemical potential for Hamiltonian.
InterAll	Two-body interactions for Hamiltonian.
CoulombIntra	CoulombIntra interactions.
CoulombInter	CoulombInter interactions.
Hund	Hund couplings.
PairHop	Pair hopping couplings.
Exchange	Exchange couplings.
Ising	Ising interactions.
PairLift	Pair lift couplings.
OneBodyG	Output components for Green functions $\langle c_{i\sigma}^{\dagger} c_{j\sigma} \rangle$
TwoBodyG	Output components for Correlation functions $\langle c_{i\sigma}^{\dagger} c_{j\sigma} c_{k\tau}^{\dagger} c_{l\tau} \rangle$
SingleExcitation	Operators for generating single excited state
PairExcitation	Operators for generating pair excited state
SpectrumVec	An input vector to calculate a restart vector

Table 4.2: List of the definition files.

4.2.2 CalcMod file

This file determines parameters for calculation method, model and output mode. File format is shown as follows.

```
CalcType 0
CalcModel 2
CalcEigenVec 0
```

File format

```
[string01] [int01]
```

Parameters

• [string01]

Type: string-type

 $\bf Description:$ Select a word from keywords.

• [int01]

Type: int-type

Description: A parameter which is correlated with a keyword.

Use rules

- After setting keywords at [string 01], a half-width blank is needed for setting a parameter.
- Keywords can be set in random order.
- If keywords or filenames are incorrect, the program is terminated.
- The following keywords, "CalcType" and "CalcModel" are essential.
- When the head of line is "#", the line is skipped.

Keywords and parameters

Parameters correlated with keywords are shown as follows.

• CalcType

Type: int-type

Description: Select the method for calculation from the following list:

0: Lanczos method,

- 1: Analysis of the physical properties by using TPQ,
- 2: Full diagonalization method.
- 3. Calculate dynamical Green's functions.

• CalcModel

Type: int-type

Description: Select the model from the following list:

- 0: fermion Hubbard model (Canonical ensemble: conservation of particles or conservation of particles and the component of S_z)
- 1: Spin model (Canonical ensemble: conservation of the component of S_z)
- 2: Kondo lattice model (Canonical ensemble: conservation of particles, the component of S_z)
- 3: fermion Hubbard model (Grand canonical ensemble)
- 4: Spin model (Grand canonical ensemble)
- 5: Kondo lattice model (Grand canonical ensemble) For fermion Hubbard model, you can select the model under the conservation of particles by setting NCond in the ModPara file. When you want to select the model under the conservation of particles and the component of S_z , you set both NCond and 2Sz in the ModPara file.

• CalcEigenVec

Type: int-type (default value: 0)

Description : Select the method to calculate eigenvectors:

0:Lanczos+CG methods (When the convergence of eigenvectors are not enough for using Lanczos method, CG method is applied to calculate eigenvectors). 1:Lanczos method.

• InitialVecType

Type: int-type (default value: 0)

Description: Select the type of an initial vector:

0:Complex type.1:Real type.

• OutputEigenVec

Type: int-type (default value: 0)

Description : Select the mode of outputting an eigenvector:

0: not output an eigen vector.

1: output an eigen vector.

• InputEigenVec

Type: int-type (default value: 0)

Description: Select the mode of inputting an eigenvector:

0: not input an eigen vector.

1: input an eigen vector.

• ReStart

Type: int-type (default value: 0)

Description: Select the mode of inputting a restart vector:

0: not restart calculation,

1: output a restart vector,

- 2: input a restart vector and output a new restart vector,
- 3: input a restart vector.

• CalcSpec

Type: int-type (default value: 0)

Description : Select the mode of calculating dynamical Green's functions.

0: not calculate dynamical Green's functions,

- 1: (not restart) input an initial vector and files for generating single excited or pair excited states,
- 2: input components of triangular diagonal matrix,
- 3: output both components of triangular diagonal matrix and a restart vector,
- 4: input both components of triangular diagonal matrix and a restart vector,
- 5: input and output both components of triangular diagonal matrix and a restart vector.

4.2.3 ModPara file

This file determines parameters for calculation. File format is shown as follows.

Model Dammete	
Model_Paramete	rs 0
VMC_Cal_Parame	ters
CDataFileHead	zvo
CParaFileHead	zqp
Nsite	16
Ncond	16
2Sz	0
Lanczos_max	1000
initial_iv	12
exct	1
LanczosEps	14
${\tt LanczosTarget}$	2
LargeValue	12
NumAve	5
ExpecInterval	20

File format

- Lines 1-4: Header
- Line 6: [string01] [string02]
- Lines 7-8: Header
- Lines 9- : [string01] [int01]

Parameters

• [string01]

Type: string-type

Description: Select a word from keywords.

• [string02]

Type: string-type (blank parameter not allowed)

Description: Set a header for output files.

• [int01]

Type: int-type (blank parameter not allowed)

Description: A parameter which is correlated with a keyword.

Use rules

- From Line 9: After setting keywords at [string 01], a half-width blank is needed for setting a parameter.
- All Parameters are needed and the order for parameters is fixed.

Keywords and parameters

• CDataFileHead

Type: string-type (blank parameter not allowed)

Description: A header for output files. For example, the output filename for one body Green's function becomes "xxx_Lanczos_cisajs.dat" (xxx are characters set by CDataFileHead).

• Nsite

Type: int-type (Positive integer)

Description: The number of sites.

• Ncond

Type: int-type (Positive integer)

Description: The number of conduction electrons (not used in grand canonical ensemble).

• 2Sz

Type: int-type (Positive integer)

Description: The total value of $2S_z$ (not used in grand canonical ensemble). For conservation of S_z in the case of CalcModel =0 (fermion Hubbard model) or 2 (Kondo lattice model), we must set Ncond.

Lanczos_max

Type: int-type (Positive integer)

Description: The number of Lanczos steps in calculation. When the convergence within the specified accuracy is satisfied, the calculation is finished before a step becomes Lanczos_max.

• initial_iv

Type: int-type

Description: An initial vector is specified with this parameter.

- Lanczos method

- * For canonical ensemble and initial_iv ≥ 0 The non-zero components of an initial vector is specified with this parameter.
- * For grand canonical ensemble or initial_iv < 0
 A seed of random generator is given by this parameter and the random vector is used as an initial vector.

- TPQ method

A seed of random generator is given by this parameter and the random vector is used as an initial vector.

See 5 for details of setting an initial vector.

• exct

Type: int-type (Positive integer)

Description: An integer for setting the number of getting eigenvectors from the ground energy by Lanczos method.

• LanczosEps

Type: int-type (Positive integer)

Description : An integer for judging a convergence of Lanczos method. The convergence is judged by satisfying the condition that the relative error between an eigenvalue and an eigenvalue at the Lanczos step of the one step before becomes less than $10^{-\text{LanczosEps}}$.

• LanczosTarget

Type: int-type (Positive integer)

Description: An integer giving the target of eigenvalue for judging the convergence of Lanczos method. For example, the target becomes a ground state when LanczosTarget is equal to one, and a 1st excited state when LanczosTarget is equal to two.

• LargeValue

Type: double-type

Description : (Only use for TPQ method) An integer giving l of $l - \hat{H}/N_s$ used in TPQ method.

• NumAve

Type: int-type

Description : (Only use for TPQ method) An integer giving the number of independent runs for TPQ method.

• ExpecInterval

Type: int-type

Description: (Only use for TPQ method) An integer giving the interval

steps of calculating correlation functions in TPQ method.

Note: The small interval increases the time cost of calculations.

OmegaMax

Type: double-type

Description : (Only use for calculating dynamical green's functions) The maximum value of the real part of the frequency ω_{max} to calculate dynamical green's functions.

• OmegaMin

Type: double-type

Description : (Only use for calculating dynamical green's functions) The minimum value of the real part of the frequency ω_{\min} to calculate dynamical green's functions.

• OmegaIm

Type: double-type

Description : (Only use for calculating dynamical green's functions) The imaginary part of the frequency η to calculate dynamical green's functions.

• NOmega

Type: int-type

Description : (Only use for calculating dynamical green's functions) The integer to define the step size of the frequency $\Delta \omega = (\omega_{\text{max}} - \omega_{\text{min}})/N_{\omega}$. The frequency is given by $z_n = \omega_{\text{min}} + \Delta \omega \times n + i\eta$.

4.2.4 LocSpin file

This file determines sites with localized spins. File format is shown as follows.

====== NlocalSp	===== oin	6 ====================================
=======	=i_0Loc	Spn_1IteElc ======
0	 1	
1	0	
2	1	
3	0	
4	1	
5	0	
6	1	
7	0	
8	1	
9	0	
10	1	
11	0	

File format

• Line 1: Header

• Line 2: [string01] [int01]

• Lines 3-5: Header

• Lines 6-: [int02] [int03]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description : A keyword for total number of localized spins. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description: An integer giving total number of localized spins.

• [int02]

Type: int-type (blank parameter not allowed)

Description : An integer giving a site index $(0 \le [int02] \le Nsite)$.

• [int03]

Type: int-type (blank parameter not allowed)

Description: An integer for selecting an electron state whether localized spin or itinerant electron states:

0: Itinerant electron state,

n > 0: localized spin state with 2S = n.

Use rules

- Headers cannot be omitted.
- A program is terminated, when [int01] is different from the total number of localized spins indicated by [int03].
- A program is terminated, when [int02] is different from the total number of sites.
- A program is terminated under the condition [int02] < 0 or Nsite <= [int02].

4.2.5 Trans file

This file determines values of transfer integrals $t_{ij\sigma_1\sigma_2}$,

$$H + = -\sum_{ij\sigma_1\sigma_2} t_{ij\sigma_1\sigma_2} c_{i\sigma_1}^{\dagger} c_{j\sigma_2}. \tag{4.4}$$

An example of file format is shown as follows.

======					
NTransfe	er	24			
	====== =i i c	 +iig=-			
=======					
0	0	2	0	1.000000)
2	0	0	0	1.000000	
0	1	2	1	1.000000	
2	1	0	1	1.000000	
2	0	4	0	1.000000	
4	0	2	0	1.000000	
2	1	4	1	1.000000	
4	1	2	1	1.000000	
4	0	6	0	1.000000	
6	0	4	0	1.000000	
4	1	6	1	1.000000	
6	1	4	1	1.000000	
6	0	8	0	1.000000	
8	0	6	0	1.000000	
• • •					

File format

• Line 1: Header

• Line 2: [string01] [int01]

• Lines 3-5: Header

• Lines 6-: [int02] [int03] [int04] [int05] [double01] [double02]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description: A keyword for total number of transfer integrals. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description: An integer giving total number of transfer integrals.

• [int02], [int04]

Type: int-type (blank parameter not allowed)

Description: An integer giving a site index $(0 \le [int02], [int04] < Nsite)$.

• [int03], [int05]

Type: int-type (blank parameter not allowed)

Description: An integer giving a spin index,

0: up-spin,1: down-spin.

• [double01]

Type: double-type (blank parameter not allowed)

Description: A value for a real part of $t_{ij\sigma_1\sigma_2}$.

• [double02]

Type: double-type (blank parameter not allowed)

Description : A value for an imaginary part of $t_{ij\sigma_1\sigma_2}$.

Use rules

- Headers cannot be omitted.
- Since Hamiltonian must be Hermitian, the following relation must be satisfied, $t_{ij\sigma_1\sigma_2} = t^{\dagger}_{ii\sigma_2\sigma_1}$. A program is terminated when the above relation is broken.
- A program is terminated, when components of on-site interactions are double counted.
- A program is terminated, when [int01] is different from the total number of transfer integrals defined in this file.
- A program is terminated, when [int02]-[int05] are out of range from the defined values.

4.2.6 InterAll file

This file determines values of generalized two body interactions integrals $I_{ijkl\sigma_1\sigma_2\sigma_3\sigma_4}$,

$$H + = \sum_{i,j,k,l} \sum_{\sigma_1,\sigma_2,\sigma_3,\sigma_4} I_{ijkl\sigma_1\sigma_2\sigma_3\sigma_4} c_{i\sigma_1}^{\dagger} c_{j\sigma_2} c_{k\sigma_3}^{\dagger} c_{l\sigma_4}. \tag{4.5}$$

For Spin, the condition i=j and k=l must be satisfied. An example of file format is shown as follows.

=== NT	=====	=====	=====	====					
NTD	terAl =====	===== T	36 =====						
======zInterAll=====									
)	0	0	1	1	1	1	0	0.50	0.0
	1	0	0	1	0	1	1	0.50	0.0
	0	0	0	1	0	1	0	0.25	0.0
	0	0	0	1	1	1	1	-0.25	0.0
	1	0	1	1	0	1	0	-0.25	0.0
	1	0	1	1	1	1	1	0.25	0.0
	0	2	1	3	1	3	0	0.50	0.0
	1	2	0	3	0	3	1	0.50	0.0
	0	2	0	3	0	3	0	0.25	0.0
	0	2	0	3	1	3	1	-0.25	0.0
	1	2	1	3	0	3	0	-0.25	0.0
	1	2	1	3	1	3	1	0.25	0.0
	0	4	1	5	1	5	0	0.50	0.0
:	1	4	0	5	0	5	1	0.50	0.0
:	0	4	0	5	0	5	0	0.25	0.0
Ŀ	0	4	0	5	1	5	1	-0.25	0.0
	1	4	1	5	0	5	0	-0.25	0.0
Ŀ	1	4	1	5	1	5	1	0.25	0.0

File format

- Line 1: Header
- Line 2: [string01] [int01]
- Lines 3-5: Header
- \bullet Lines 6-: [int02] [int03] [int04] [int05] [int06] [int07] [int08] [int09] [double01] [double02]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description : A keyword for total number of generalized two body interactions. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description: An integer giving total number of generalized two body interactions.

• [int02], [int04], [int06], [int08]

Type: int-type (blank parameter not allowed)

Description : An integer giving a site index $(0 \le [int02], [int04], [int06], [int08] \le Nsite).$

• [int03], [int05], [int07], [int09]

Type: int-type (blank parameter not allowed)

Description: An integer giving a spin index,

0: up-spin,1: down-spin.

• [double01]

Type: double-type (blank parameter not allowed)

Description: A value for a real part of $I_{ijkl\sigma_1\sigma_2\sigma_3\sigma_4}$.

• [double02]

Type: double-type (blank parameter not allowed)

Description: A value for an imaginary part of $I_{ijkl\sigma_1\sigma_2\sigma_3\sigma_4}$.

Use rules

- Headers cannot be omitted.
- Since Hamiltonian must be Hermitian, the following relation must be satisfied, $I_{ijkl\sigma_1\sigma_2\sigma_3\sigma_4} = I^{\dagger}_{lkji\sigma_4\sigma_3\sigma_2\sigma_1}$. A program is terminated when the above relations are broken. It is noted that a term of Hermitian conjugate for $I_{ijkl\sigma_1\sigma_2\sigma_3\sigma_4}c^{\dagger}_{i\sigma_1}c_{j\sigma_2}c^{\dagger}_{k\sigma_3}c_{l\sigma_4}$ should be inputted as $I_{lkji\sigma_4\sigma_3\sigma_2\sigma_1}c^{\dagger}_{l\sigma_4}c_{k\sigma_3}c^{\dagger}_{j\sigma_2}c_{i\sigma_1}$.
- A program is terminated, when i = j and k = l are not satisfied for spin model.
- A program is terminated, when components of on-site interactions are double counted.

- A program is terminated, when [int01] is different from the total number of generalized two body interactions defined in this file.
- A program is terminated, when [int02]-[int09] are out of range from the defined values.

4.2.7 CoulombIntra file

This file determines values of on-site interactions U_i (for S = 1/2 system),

$$H + = \sum_{i} U_{i} n_{i\uparrow} n_{i\downarrow}. \tag{4.6}$$

An example of file format is shown as follows.

4 4.000000

5 4.000000

File format

• Line 1: Header

• Line 2: [string01] [int01]

• Lines 3-5: Header

• Lines 6-: [int02] [double01]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description : A keyword for total number of on-site interactions. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description: An integer giving total number of on-site interactions.

• [int02]

Type: int-type (blank parameter not allowed)

Description : An integer giving a site index $(0 \le [int02] \le Nsite)$.

• [double01]

Type: double-type (blank parameter not allowed)

Description: A value for U_i .

Use rules

• Headers cannot be omitted.

- A program is terminated, when components of on-site interactions are double counted.
- A program is terminated, when [int01] is different from the total number of on-site interactions defined in this file.
- A program is terminated, when [int02] is out of range from the defined values.

4.2.8 CoulombInter file

This file determines values of off-site interactions V_{ij} (for S = 1/2 system),

$$H+=\sum_{i,j}V_{ij}n_in_j. (4.7)$$

An example of file format is shown as follows.

======		========	
NCoulom	bInt	er 6	
======	====	========	
======	=Cou	lombInter =====	
======	====	========	
0	1	1.0000	
1	2	1.0000	
2	3	1.0000	
3	4	1.0000	
4	5	1.0000	
5	0	1.0000	J

File format

• Line 1: Header

• Line 2: [string01] [int01]

• Lines 3-5: Header

• Lines 6-: [int02] [int03] [double01]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description : A keyword for total number of off-site interactions. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description: An integer giving total number of off-site interactions.

• [int02], [int03]

Type: int-type (blank parameter not allowed)

Description: An integer giving a site index $(0 \le [int02], [int03] \le Nsite)$.

• [double01]

Type: double-type (blank parameter not allowed)

Description: A value for V_{ij} .

Use rules

• Headers cannot be omitted.

- A program is terminated, when components of off-site interactions are double counted.
- A program is terminated, when [int01] is different from the total number of off-site interactions defined in this file.
- A program is terminated, when either [int02] or [int03] are out of range from the defined values.

4.2.9 Hund file

This file determines values of Hund couplings J_{ij}^{Hund} (for S=1/2 system),

$$H + = -\sum_{i,j} J_{ij}^{\text{Hund}} (n_{i\uparrow} n_{j\uparrow} + n_{i\downarrow} n_{j\downarrow}). \tag{4.8}$$

An example of file format is shown as follows.

NHund 6 =======Hund ===== 0 1 -0.250000 1 2 -0.250000 2 3 -0.250000 3 4 -0.250000 4 5 -0.250000 5 0 -0.250000	======	
0 1 -0.250000 1 2 -0.250000 2 3 -0.250000 3 4 -0.250000 4 5 -0.250000	NHund 6	3
0 1 -0.250000 1 2 -0.250000 2 3 -0.250000 3 4 -0.250000 4 5 -0.250000	======	
1 2 -0.250000 2 3 -0.250000 3 4 -0.250000 4 5 -0.250000	======	==Hund =====
1 2 -0.250000 2 3 -0.250000 3 4 -0.250000 4 5 -0.250000	======	
2 3 -0.250000 3 4 -0.250000 4 5 -0.250000	0	1 -0.250000
3 4 -0.250000 4 5 -0.250000	1	2 -0.250000
4 5 -0.250000	2	3 -0.250000
	3	4 -0.250000
5 0 -0.250000	4	5 -0.250000
	5	0 -0.250000

File format

• Line 1: Header

• Line 2: [string01] [int01]

• Lines 3-5: Header

• Lines 6-: [int02] [int03] [double01]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description: A keyword for total number of Hund couplings. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description: An integer giving total number of Hund couplings.

• [int02], [int03]

Type: int-type (blank parameter not allowed)

Description: An integer giving a site index $(0 \le [int02], [int03] \le Nsite)$.

• [double01]

Type : double-type (blank parameter not allowed)

Description : A value for J_{ij}^{Hund} .

Use rules

- Headers cannot be omitted.
- A program is terminated, when components of Hund couplings are double counted.
- A program is terminated, when [int01] is different from the total number of Hund couplings defined in this file.
- A program is terminated, when either [int02] or [int03] are out of range from the defined values.

4.2.10 PairHop file

This file determines values of Pair Hop couplings $J_{ij}^{\rm Pair}$ (for S=1/2 system),

$$H + = \sum_{i,j} J_{ij}^{\text{Pair}} c_{i\uparrow}^{\dagger} c_{j\uparrow} c_{i\downarrow}^{\dagger} c_{j\downarrow}. \tag{4.9}$$

An example of file format is shown as follows.

====== NPairho		=======
======	=Pai	======================================
0	1	0.50000
1	0	0.50000
1	2	0.50000
2	1	0.50000
2	3	0.50000
3	2	0.50000
3	4	0.50000
4	3	0.50000
4	5	0.50000
5	4	0.50000
5	0	0.50000
0	5	0.50000

File format

• Line 1: Header

• Line 2: [string01] [int01]

• Lines 3-5: Header

• Lines 6-: [int02] [int03] [double01]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description : A keyword for total number of PairHop couplings. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description: An integer giving total number of PairHop couplings.

• [int02], [int03]

Type: int-type (blank parameter not allowed)

Description : An integer giving a site index $(0 \le [int02], [int03] \le Nsite)$.

• [double01]

Type: double-type (blank parameter not allowed)

Description : A value for J_{ij}^{Pair} .

Use rules

• Headers cannot be omitted.

- A program is terminated, when components of PairHop couplings are double counted.
- A program is terminated, when [int01] is different from the total number of PairHop couplings defined in this file.
- A program is terminated, when either [int02] or [int03] are out of range from the defined values.

4.2.11 Exchange file

This file determines values of Exchange couplings J_{ij}^{Ex} (for S=1/2 system). For fermion electronic system, exchange terms are given as

$$H + = \sum_{i,j} J_{ij}^{\text{Ex}} (c_{i\uparrow}^{\dagger} c_{j\uparrow} c_{j\downarrow}^{\dagger} c_{i\downarrow} + c_{i\downarrow}^{\dagger} c_{j\downarrow} c_{j\uparrow}^{\dagger} c_{i\uparrow}). \tag{4.10}$$

While for Spin system, they are given as

$$H + = \sum_{i,j} J_{ij}^{\text{Ex}} (S_i^+ S_j^- + S_i^- S_j^+). \tag{4.11}$$

We note that $(S_i^+S_j^- + S_i^-S_j^+)$ in Spin system is written by the operators for electrons as $-(c_{i\uparrow}^{\dagger}c_{j\uparrow}c_{j\downarrow}^{\dagger}c_{i\downarrow} + c_{i\downarrow}^{\dagger}c_{j\downarrow}c_{j\uparrow}^{\dagger}c_{i\uparrow})$. An example of file format is shown as follows.

======	====	========		
NExchan	ge 6			
======	====	========		
======	=Exc	hange =====		
======	====	========		
0	1	0.50000		
1	2	0.50000		
2	3	0.50000		
3	4	0.50000		
4	5	0.50000		
5	0	0.50000		

File format

• Line 1: Header

• Line 2: [string01] [int01]

• Lines 3-5: Header

• Lines 6-: [int02] [int03] [double01]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description: A keyword for total number of Exchange couplings. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description: An integer giving total number of Exchange couplings.

• [int02], [int03]

Type: int-type (blank parameter not allowed)

Description : An integer giving a site index $(0 \le [int02], [int03] \le Nsite)$.

• [double01]

Type: double-type (blank parameter not allowed)

Description: A value for J_{ij}^{Ex} .

Use rules

• Headers cannot be omitted.

- A program is terminated, when components of Exchange couplings are double counted.
- A program is terminated, when [int01] is different from the total number of Exchange couplings defined in this file.
- A program is terminated, when either [int02] or [int03] are out of range from the defined values.

4.2.12 Ising file

This file determines values of Ising interactions J_{ij}^z (for S=1/2 system). For fermion electronic system, Ising terms are given as

$$H + = \sum_{i,j} J_{ij}^{z} (n_{i\uparrow} - n_{i\downarrow})(n_{j\uparrow} - n_{j\downarrow}). \tag{4.12}$$

For Spin system, they are given as

$$H + = \sum_{i,j} J_{ij}^z S_i^z S_j^z. \tag{4.13}$$

An example of file format is shown as follows.

====== NIsing	==== 6 			
======	 =Isi	ng =====		
0	1	0.50000		
1	2	0.50000		
2	3	0.50000		
3	4	0.50000		
4	5	0.50000		
5	0	0.50000		

File format

• Line 1: Header

• Line 2: [string01] [int01]

• Lines 3-5: Header

• Lines 6-: [int02] [int03] [double01]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description : A keyword for total number of Ising interactions. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description: An integer giving total number of Ising interactions.

• [int02], [int03]

Type: int-type (blank parameter not allowed)

Description : An integer giving a site index $(0 \le [int02], [int03] \le Nsite)$.

• [double01]

Type: double-type (blank parameter not allowed)

Description: A value for J_{ij}^{z} .

Use rules

• Headers cannot be omitted.

- A program is terminated, when components of Ising interactions are double counted.
- A program is terminated, when [int01] is different from the total number of Ising interactions defined in this file.
- A program is terminated, when either [int02] or [int03] are out of range from the defined values.

4.2.13 PairLift file

This file determines values of PairLift couplings J_{ij}^{PairLift} (for S=1/2 system),

$$H + = \sum_{i,j} J_{ij}^{\text{PairLift}} (c_{i\uparrow}^{\dagger} c_{i\downarrow} c_{j\uparrow}^{\dagger} c_{j\downarrow} + c_{i\downarrow}^{\dagger} c_{i\uparrow} c_{j\downarrow}^{\dagger} c_{j\uparrow}). \tag{4.14}$$

An example of file format is shown as follows.

File format

• Line 1: Header

• Line 2: [string01] [int01]

• Lines 3-5: Header

• Lines 6-: [int02] [int03] [double01]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description : A keyword for total number of PairLift couplings. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description: An integer giving total number of PairLift couplings.

• [int02], [int03]

Type: int-type (blank parameter not allowed)

Description: An integer giving a site index $(0 \le [int02], [int03] \le Nsite)$.

• [double01]

Type : double-type (blank parameter not allowed)

Description : A value for J_{ij}^{PairLift} .

Use rules

• Headers cannot be omitted.

- A program is terminated, when components of PairLift couplings are double counted.
- A program is terminated, when [int01] is different from the total number of PairLift couplings defined in this file.
- A program is terminated, when either [int02] or [int03] are out of range from the defined values.

4.2.14 OneBodyG file

This file determines the target components of one-body Green's function $\langle c_{i\sigma_1}^{\dagger} c_{j\sigma_2} \rangle$. An example of file format is shown as follows.

=======	=====	====		====
NCisAjs		24		
=======	 Cmoon	=====	======= -+:ona ===	-===
=======	Green	1 unc	 	 -===
0	0	0	0	
0	1	0	1	
1	0	1	0	
1	1	1	1	
2	0	2	0	
2	1	2	1	
3	0	3	0	
3	1	3	1	
4	0	4	0	
4	1	4	1	
5	0	5	0	
5	1	5	1	
6	0	6	0	
6	1	6	1	
7	0	7	0	
7	1	7	1	
8	0	8	0	
8	1	8	1	
9	0	9	0	
9	1	9	1	
10	0	10	0	
10	1	10	1	
11	0	11	0	
11	1	11	1	

File format

- Line 1: Header
- Line 2: [string01] [int01]
- Lines 3-5: Header
- Lines 6-: [int02] [int03] [int04] [int05]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description : A keyword for total number of one-body Green's functions. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description: An integer giving total number of one-body Green's functions.

• [int02], [int04]

Type: int-type (blank parameter not allowed)

Description : An integer giving a site index $(0 \le [int02], [int04] < Nsite)$.

• [int03], [int05]

Type: int-type (blank parameter not allowed)

Description: An integer giving a spin index,

0: up-spin,1: down-spin.

Use rules

- Headers cannot be omitted.
- A program is terminated, when components of one-body Green's functions are double counted.
- A program is terminated, when [int01] is different from the total number of one-body Green's functions defined in this file.
- A program is terminated, when [int02]-[int05] are out of range from the defined values.

4.2.15 TwoBodyG file

This file determines the target components of two-body Green's function $\langle c_{i\sigma_1}^{\dagger}c_{j\sigma_2}c_{k\sigma_3}^{\dagger}c_{l\sigma_4}\rangle$. For Spin, the condition i=j and k=l must be satisfied. An example of file format is shown as follows.

CisAjsCktAltDC 576								
						Nq =====		
0	0	0	0	0	0	0	C	
0	0	0	0	0	1	0	1	
0	0	0	0	1	0	1	C	
0	0	0	0	1	1	1	1	
0	0	0	0	2	0	2	0	
0	0	0	0	2	1	2	1	
0	0	0	0	3	0	3	0	
0	0	0	0	3	1	3	1	
0	0	0	0	4	0	4	0	
0	0	0	0	4	1	4	1	
0	0	0	0	5	0	5	0	
0	0	0	0	5	1	5	1	
0	0	0	0	6	0	6	0	
0	0	0	0	6	1	6	1	
0	0	0	0	7	0	7	0	
0	0	0	0	7	1	7	1	
0	0	0	0	8	0	8	0	
0	0	0	0	8	1	8	1	
0	0	0	0	9	0	9	0	
0	0	0	0	9	1	9	1	
0	0	0	0	10	0	10	0	
0	0	0	0	10	1	10	1	
0	0	0	0	11	0	11	0	
0	0	0	0	11	1	11	1	
0	1	0	1	0	0	0	0	

File format

- Line 1: Header
- Line 2: [string01] [int01]
- Lines 3-5: Header
- Lines 6-: [int02] [int03] [int04] [int05] [int06] [int07] [int08] [int09]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description : A keyword for total number of two-body Green's functions. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description : An integer giving total number of two-body Green's functions.

• [int02], [int04], [int06], [int08]

Type: int-type (blank parameter not allowed)

Description : An integer giving a site index $(0 \le [int02], [int04], [int06], [int08] \le Nsite).$

• [int03], [int05], [int07], [int09]

Type: int-type (blank parameter not allowed)

Description: An integer giving a spin index,

0: up-spin,1: down-spin.

Use rules

- Headers cannot be omitted.
- A program is terminated, when components of two-body Green's functions are double counted.
- A program is terminated, when i = j and k = l are not satisfied for spin model
- A program is terminated, when [int01] is different from the total number of two-body Green's functions defined in this file.
- A program is terminated, when [int02]-[int09] are out of range from the defined values.

4.2.16 SingleExcitation file

Operators to generate single excited state $S_{i\sigma_1}c_{i\sigma_1}(S_{i\sigma_1}c_{i\sigma_1}^{\dagger})$ are defined. An example of file format is shown as follows.

(=		=====	=====		=====
ı	VSingle		24		
=		==== Sing =====	===== le Exc =====	====== citatior ======	===== 1 ======
	0	0	0	1.0	0.0
	0	1	0	1.0	0.0
	1	0	0	1.0	0.0
	(cont	inue.)		
	11	0	0	1.0	0.0
	11	1	0	1.0	0.0
/					

File format

- Line 1: Header
- Line 2: [string01] [int01]
- Lines 3-5: Header
- Lines 6-: [int02] [int03] [int04] [double01] [double02]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description : A keyword for total number of single excitation operators. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description: An integer giving total number of total number of single excitation operators.

• [int02]

Type: int-type (blank parameter not allowed)

Description : An integer giving a site index $(0 \le [int02] \le Nsite)$.

• [int03]

Type: int-type (blank parameter not allowed)

Description: An integer giving a spin index,

0: up-spin,1: down-spin.

• [int04]

Type: int-type (blank parameter not allowed)

Description: An integer giving a type of single excitation operators,

0: $c_{i\sigma_1}$, 1: $c_{i\sigma_1}^{\dagger}$.

• [double01], [double02]

Type: double-type (blank parameter not allowed)

Description: [double01] gives the real part of $S_{i\sigma_1}$, while [double02] gives the imaginary part of $S_{i\sigma_1}$.

Use rules

- Headers cannot be omitted.
- A program is terminated, when components of single excitation operators are double counted.
- A program is terminated, when i = j and k = l are not satisfied for spin model.
- A program is terminated, when [int01] is different from the total number of two-body Green's functions defined in this file.
- A program is terminated, when [int02]-[int04] are out of range from the defined values.

4.2.17 PairExcitation file

Operators to generate pair excited state $S_{i\sigma_1j\sigma_2}c_{i\sigma_1}c_{j\sigma_2}^{\dagger}(S_{i\sigma_1j\sigma_2}c_{i\sigma_1}^{\dagger}c_{j\sigma_2})$ are defined. The type of pair excitation operators $(c_{i\sigma_1}c_{j\sigma_2}^{\dagger} \text{ or } c_{i\sigma_1}^{\dagger}c_{j\sigma_2})$ must be same in the input file. In S_z conserved system, σ_1 must be equal to σ_2 . An example of file format is shown as follows.

======	=====			=====	=		
NPair		24					
=======	===== Pair 	Excita	ation	===== ======	= = =		
0	0	0	0	0	1.0	0.0	
0	1	0	1	0	1.0	0.0	
1	0	1	0	0	1.0	0.0	
(cont	inue.)					
11	0	11	0	0	1.0	0.0	
11	1	11	1	0	1.0	0.0	

File format

- Line 1: Header
- Line 2: [string01] [int01]
- Lines 3-5: Header
- \bullet Lines 6-: [int02] [int03] [int04] [int05] [int06] [double01] [double02]

Parameters

• [string01]

Type: string-type (blank parameter not allowed)

Description : A keyword for total number of single excitation operators. You can freely give a name of the keyword.

• [int01]

Type: int-type (blank parameter not allowed)

Description : An integer giving total number of total number of single excitation operators.

• [int02], [int04]

Type: int-type (blank parameter not allowed)

Description: An integer giving a site index $(0 \le [int02], [int04] < Nsite)$.

• [int03], [int05]

Type: int-type (blank parameter not allowed)

Description: An integer giving a spin index,

0: up-spin,1: down-spin.

• [int06]

Type: int-type (blank parameter not allowed)

Description: An integer giving a type of pair excitation operators,

0: $c_{i\sigma_1}c_{j\sigma_2}^{\dagger}$, 1: $c_{i\sigma_1}^{\dagger}c_{j\sigma_2}$.

• [double01], [double02]

Type: double-type (blank parameter not allowed)

Description: [double01] gives the real part of $S_{i\sigma_1j\sigma_2}$, while [double02] gives the imaginary part of $S_{i\sigma_1j\sigma_2}$.

Use rules

- Headers cannot be omitted.
- A program is terminated, when components of single excitation operators are double counted.
- ullet A program is terminated, when i=j and k=l are not satisfied for spin model
- A program is terminated, when [int01] is different from the total number of two-body Green's functions defined in this file.
- A program is terminated, when [int02]-[int06] are out of range from the defined values.

4.2.18 SpectrumVec File

The header of input file for the initial vector to calculate dynamical Green's functions is defined. The file name and the file format (binary type) are shown as follows.

File name

• ##_rank_\$\$.dat

is a name of head indicated by the key word SpectrumVec in the CalcMod file, \$\$ is a number of rank respectively.

File format

• Line 1: [int01]

• Line 2: [int02]

• Lines 3 -: [double01] [double02]

Parameters

• [int01]

Type: int-type

Description: A total number of targets of Hilbert spaces.

• [int02]

Type: int-type

Description: A number of Lanczos or TPQ steps.

• [double01], [double02]

Type: double

Description: The coefficient value of an input vector. [double01] is a real part, [double02] is an imaginary part.

4.3 Output files

In this section, details of output files for expert mode are explained.

4.3.1 CHECK_Chemi.dat

This file is outputted to check the input of chemical potential $\mu_{i\sigma}$,

$$H + = \sum_{i,\sigma} \mu_{i\sigma} c_{i\sigma}^{\dagger} c_{i\sigma}. \tag{4.15}$$

An example of file format is shown as follows.

```
i=0 spin=0 isite1=1 tmp_V=0.000000
i=1 spin=0 isite1=2 tmp_V=0.000000
i=2 spin=0 isite1=3 tmp_V=0.000000
i=3 spin=0 isite1=4 tmp_V=0.000000
i=4 spin=0 isite1=5 tmp_V=0.000000
i=5 spin=0 isite1=6 tmp_V=0.000000
...
```

File format

• i=[int01] spin=[int02] isite1=[int03] tmp_V=[double01]

Parameters

• [int01]

Type: int-type

Description: A counted number of inputting terms.

• [int02]

Type: int-type

Description: An integer for showing a spin index of $\mu_{i\sigma}$,

0: up-spin,1: down-spin.

• [int03]

Type: int-type

Description: An integer for showing a site index of $\mu_{i\sigma}$.

• [double01]

Type: double-type

Description: A value for $\mu_{i\sigma}$.

4.3.2 CHECK_InterAll.dat

This file is outputted to check the input of diagonal components of general two body interactions,

$$H + = \sum_{i,j,\sigma} I_{iijj\sigma_1\sigma_1\sigma_2\sigma_2} c_{i\sigma_1}^{\dagger} c_{i\sigma_1} c_{i\sigma_2}^{\dagger} c_{i\sigma_2}. \tag{4.16}$$

An example of file format is shown as follows.

```
i=0 isite1=1 A_spin=0 isite2=2 B_spin=0 tmp_V=0.500000
i=1 isite1=1 A_spin=0 isite2=2 B_spin=1 tmp_V=-0.500000
i=2 isite1=1 A_spin=1 isite2=2 B_spin=0 tmp_V=-0.500000
i=3 isite1=1 A_spin=1 isite2=2 B_spin=1 tmp_V=0.500000
i=4 isite1=2 A_spin=0 isite2=3 B_spin=0 tmp_V=0.500000
i=5 isite1=2 A_spin=0 isite2=3 B_spin=1 tmp_V=-0.500000
...
```

File format

• i=[int01] isite1=[int02] A_spin=[int03] isite2=[int04] B_spin=[int05] $tmp_V=[double01]$

Parameters

• [int01]

Type: int-type

Description: A counted number of inputting terms.

• [int02], [int04]

Type: int-type

Description : An integer for showing a site index of $I_{iijj\sigma_1\sigma_1\sigma_2\sigma_2}$. [int02] and [int04] correspond to i and j, respectively.

• [int03], [int05]

Type: int-type

Description: An integer for showing a spin index of $I_{iijj\sigma_1\sigma_1\sigma_2\sigma_2}$,

0: up-spin,1: down-spin.

[int03] and [int05] correspond to σ_1 and σ_2 , respectively.

• [double01]

Type: double-type

Description: A value for $I_{iijj\sigma_1\sigma_1\sigma_2\sigma_2}$.

4.3.3 CHECK_CoulombIntra.dat

This file is outputted to check the input of on-site interactions U_i ,

$$H + = \sum_{i} U_{i} n_{i\uparrow} n_{j\downarrow}. \tag{4.17}$$

An example of file format is shown as follows.

File format

• i=[int01] isite1=[int02] $tmp_V=[double01]$

Parameters

• [int01]

 $\mathbf{Type}: \mathbf{int}$ -type

Description: A counted number of inputting terms.

• [int02]

Type: int-type

Description: An integer for showing a site index of U_i .

• [double01]

Type: double-type

Description: A value for U_i .

4.3.4 CHECK_Hund.dat

This file is outputted to check the input of Hund couplings J_{ij}^{Hund} ,

$$H + = -\sum_{i,j} J_{ij}^{\text{Hund}} (n_{i\uparrow} n_{j\uparrow} + n_{i\downarrow} n_{j\downarrow}). \tag{4.18}$$

An example of file format is shown as follows.

```
i=0 isite1=1 isite2=2 tmp_V=0.250000
i=1 isite1=2 isite2=3 tmp_V=0.250000
i=2 isite1=3 isite2=4 tmp_V=0.250000
i=3 isite1=4 isite2=5 tmp_V=0.250000
i=4 isite1=5 isite2=6 tmp_V=0.250000
i=5 isite1=6 isite2=1 tmp_V=0.250000
```

File format

• i=[int01] isite1=[int02] isite2=[int03] $tmp_V=[double01]$

Parameters

• [int01]

Type: int-type

Description: A counted number of inputting terms.

• [int02], [int03]

Type: int-type

Description : An integer for showing a site index of J_{ij}^{Hund} . [int02] and [int03] correspond to i and j, respectively.

• [double01]

Type: double-type

Description : A value for J_{ij}^{Hund} .

4.3.5 CHECK_INTER_U.dat

This file is outputted to check the input of diagonal components of on-site interactions V_{ii} ,

$$H + = \sum_{i} V_{ij} n_i n_j \tag{4.19}$$

An example of file format is shown as follows.

```
i=0 isite1=1 isite2=2 tmp_V=-0.125000
i=1 isite1=2 isite2=3 tmp_V=-0.125000
i=2 isite1=3 isite2=4 tmp_V=-0.125000
i=3 isite1=4 isite2=5 tmp_V=-0.125000
i=4 isite1=5 isite2=6 tmp_V=-0.125000
i=5 isite1=6 isite2=1 tmp_V=-0.125000
```

File format

• i=[int01] isite1=[int02] isite2=[int03] $tmp_V=[double01]$

Parameters

• [int01]

Type: int-type

Description : A counted number of inputting terms.

• [int02], [int03]

Type: int-type

Description : An integer giving a site index of V_{ij} . [int02] and [int03] correspond to i and j, respectively.

• [double01]

Type: double-type

Description: A value for V_{ij} .

4.3.6 CHECK_Memory.dat

This file shows the size of memory using the calculation. An example of file format is shown as follows.

```
MAX DIMENSION idim_max=400
REQUIRED MEMORY max_mem=0.000019 GB
```

File format

- MAX DIMENSION idim_max=[int01]
- REQUIRED MEMORY max_mem =[double01] GB

Parameters

• [int01]

Type: int-type

Description : An integer to show total numbers of the Hilbert space under a calculation.

• [double01]

Type: double-type

Description : A size of memory to store the Hilbert space under a calculation (GB unit).

4.3.7 WarningOnTransfer.dat

This file shows the components double counted of transfer integrals. An example of file format is shown as follows.

```
double conuntings in transfers: i=0 j=2 spni 0 spnj 0 double conuntings in transfers: i=2 j=0 spni 0 spnj 0 double conuntings in transfers: i=0 j=2 spni 1 spnj 1 double conuntings in transfers: i=2 j=0 spni 1 spnj 1
```

File format

• double countings in transfers: i=[int01] j=[int02] spni [int03] spnj [int04]

Parameters

• [int01], [int02]

Type: int-type

Description : An integer of a site number where transfer integrals are double counted.

• [int03], [int04]

Type: int-type

Description: An integer of a spin index of a transfer integral,

0: up-spin,1: down-spin.

4.3.8 CalcTimer.dat

The name of calculation process, process number and the calculation process time are output in order at each lines in the CalcTime.dat file. An example of file format for TPQ method is shown as follows.

All	[0000]	12.94052
sz	[1000]	0.01795
diagonalcalc	[2000]	0.00693
CalcByTPQ	[3000]	12.90670
FirstMultiply	[3100]	0.08416
rand in FirstMultiply	[3101]	0.00172
mltply in FirstMultiply	[3102]	0.07707
expec_energy_flct	[3200]	9.06255
calc flctuation in expec_energy_flct	[3201]	1.67779
<pre>mltply in expec_energy_flct</pre>	[3202]	7.31207
expec_onebody	[3300]	0.11640
expec_twobody	[3400]	3.28796
Multiply	[3500]	0.14840
FileIO	[3600]	0.20493
=======================================		
All mltply	[0001]	7.38883
diagonal	[0100]	0.04153
Hubbard	[0300]	7.34636
trans in Hubbard	[0310]	7.34595
double	[0311]	0.00000
single	[0312]	0.00000
inner	[0313]	7.34299
interall in Hubbard	[0320]	0.00008
interPE	[0321]	0.00000
inner	[0322]	0.00000
pairhopp in Hubbard	[0330]	0.00006
interPE	[0331]	0.00000
inner	[0332]	0.00000
exchange in Hubbard	[0340]	0.00004
interPE	[0341]	0.00000
inner	[0342]	0.00000

4.3.9 TimeKeeper.dat

This file is outputted to show the calculation process information. An example of file format for Lanczos method is shown as follows.

```
diagonal calculation finishes: Wed Sep 16 22:58:49 2015
Lanczos Eigen Value start: Wed Sep 16 22:58:49 2015
1 th Lanczos step: Wed Sep 16 22:58:49 2015
...

122 th Lanczos step: Wed Sep 16 22:58:49 2015
Lanczos Eigenvalue finishes: Wed Sep 16 22:58:49 2015
Lanczos Eigenvector finishes: Wed Sep 16 22:58:49 2015
Lanczos expec energy finishes: Wed Sep 16 22:58:49 2015
CG Eigenvector finishes: Wed Sep 16 22:58:49 2015
CG expec energy finishes: Wed Sep 16 22:58:50 2015
CG expec_cisajs finishes: Wed Sep 16 22:58:50 2015
CG expec_cisajacktalt begins: Wed Sep 16 22:58:50 2015
```

File name

• ##_TimeKeeper.dat

indicates a header defined by [string02] in a ModPara file.

4.3.10 sz_TimeKeeper.dat

This file is outputted to show the process information to obtain the Hilbert space needed for calculation . An example of file format is shown as follows.

```
initial sz : Wed Sep 16 22:58:49 2015
num_threads==4
omp parallel sz finishes: Wed Sep 16 22:58:49 2015
mid omp parallel sz : Wed Sep 16 22:58:49 2015
omp parallel sz finishes: Wed Sep 16 22:58:49 2015
```

File name

• ##_sz_TimeKeeper.dat

indicates a header defined by [string02] in a ModPara file.

4.3.11 Time_CG_EigenVector.dat

(For Lanczos method) The process for calculating eigenvector by CG method is outputted. An example of file format is shown as follows.

```
allocate succeed !!!
b[4341]=1.000000 bnorm== 1.000000
i_itr=0 itr=5 0.0411202543 0.0000100000
i_itr=0 itr=155 0.0000000058 0.0000100000
CG OK:
         t_itr=155
i_itr=0 itr=155 time=0.000000
fabs(fabs(xb)-1.0)=0.9955114473313577
b[4341]=0.004489 bnorm== 1.000000
i_itr=1 itr=5 13.0033983157 0.0000100000
. . .
CG OK:
         t_itr=275
i_itr=1 itr=120 time=0.000000
fabs(fabs(xb)-1.0)=0.0000000000001295
number of iterations in inv1:i_itr=1 itr=120
t_itr=275 0.000000
```

File name

• ##_Time_CG_EigenVector.dat

indicates a header defined by [string02] in a ModPara file.

4.3.12 energy.dat

(For Lanczos method) The values of energy, doublon and $\langle S_z \rangle$ calculated by using eigenvector obtained by Lanczos or CG method are outputted. An example of file format is shown as follows.

```
Energy -7.1043675920
Doublon 0.4164356536
Sz 0.0000000000
```

File name

• ##_energy.dat

indicates a header defined by [string02] in a ModPara file.

File format

• Line 1: Energy [double01]

• Line 2: Doublon [double02]

• Line 3: Sz [double02]

Parameters

• [double01]

Type: double-type

Description : The value of energy calculated by the eigenvetor obtained by Lanczos or CG method.

• [double02]

Type: double-type

Description : The value of doublon calculated by the eigenvetor obtained by Lanczos or CG method, $\frac{1}{N_s} \sum_i \langle n_{i\uparrow} n_{i\downarrow} \rangle$ (N_s is a total number of sites).

• [double03]

Type: double-type

Description: The value of S_z calculated by the eigenvetor obtained by Lanczos or CG method.

4.3.13 Lanczos_Step.dat

(For Lanczos method) This file is outputted to show the process information for calculating eigenvector by Lanczos method. An example of file format for Lanczos method is shown as follows.

```
      stp=4 -4.7732163164 -1.7790936582 1.2246691944 4.4823068739

      stp=6 -5.8159638812 -3.6807425834 -1.3738652472 0.9326262962

      stp=8 -6.2772935672 -4.8650501184 -3.1096996066 -1.1940653342

      ...

      stp=120 -7.1043675920 -7.0817672578 -7.0646589929 -7.0008766356

      stp=122 -7.1043675920 -7.0817672578 -7.0646589929 -7.0008766356
```

File name

• ##_Lanczos_Step.dat

indicates a header defined by [string02] in a ModPara file.

File format

• stp= [int01] [double01] [double02] [double03] [double04]

Parameters

• [int01]

Type: int-type

Description: An integer showing Lanczos step.

• [double01], [double02], [double03], [double04]

Type: double-type

Description: The eigenvalue at the Lanczos step [int01]. [double01] is a ground energy, [double02], [double03] and [double04] are 1st, 2nd and 3rd excited energies, respectively.

4.3.14 Time_TPQ_Step.dat

(For TPQ method) This file is outputted to show the time for starting calculation of TPQ method at each seeds and steps. An example is shown as follows.

```
set 0 step 1:TPQ begins: Wed Jul 13 07:59:20 2016
set 0 step 2:TPQ begins: Wed Jul 13 07:59:20 2016
set 0 step 3:TPQ begins: Wed Jul 13 07:59:20 2016
...
set 4 step 1997:TPQ begins: Wed Jul 13 07:59:32 2016
set 4 step 1998:TPQ begins: Wed Jul 13 07:59:32 2016
set 4 step 1999:TPQ begins: Wed Jul 13 07:59:32 2016
```

File name

• ##_TPQ_Step.dat

indicates a header defined by [string02] in a ModPara file.

File format

• set [int01] stp [int02]: TPQ begins: [string01]

Parameters

• [int01]

Type: int-type

Description: A seed number under calculation of TPQ method.

• [int02]

Type: int-type

Description: A step number under calculation of TPQ method.

• [string01]

Type: string-type

Description : A time for starting calculation of TPQ method at each seeds and steps.

4.3.15 Norm_rand.dat

(For TPQ method) This file is outputted to show the calculation process information for TPQ method. An example of file format is shown as follows.

```
# inv_temp, global_norm, global_1st_norm, step_i
0.017471 19.046586 11.288975 1
0.034863 19.089752 11.288975 2
...
31.999572 20.802362 11.288975 1997
32.015596 20.802362 11.288975 1998
32.031620 20.802362 11.288975 1999
```

File name

• Norm_rand??.dat

?? indicates a number of runs under calculation of TPQ method.

File format

• Line 1: Header

• Lines 2-: [double01] [double02] [double03] [int01]

Parameters

• [double01]

Type: double-type

Description: Inverse temperature $1/k_{\rm B}T$.

• [double02]

Type: double-type

Description : A norm of a wave function before normalization given by $\langle \tilde{\psi}_k | \tilde{\psi}_k \rangle$, where $|\tilde{\psi}_k \rangle \equiv (l - \hat{H}/N_s) |\psi_{k-1}\rangle$.

• [double03]

Type: double-type

Description : A norm of an initial wave function before normalization given by $\langle \tilde{\psi}_0 | \tilde{\psi}_0 \rangle$, where $|\tilde{\psi}_0 \rangle$ is an initial random vector.

• [int01]

Type: int-type

Description: A number of operations of $(l - \hat{H}/N_s)$ to an initial wave function, where l is LargeValue defined in ModPara file and N_s is a total number of sites.

4.3.16 SS_rand.dat

(For TPQ method) This file is outputted to show the calculation results for TPQ method. An example of file format is shown as follows.

```
# inv_tmp, energy, phys_var, phys_doublon, phys_num, step_i
0.017471  5.526334  45.390269  1.464589  6.000000  1
0.034863  5.266718  42.655559  1.434679  6.000000  2
...
31.999572  -4.814170  23.176231  0.590568  6.000000  1997
32.015596  -4.814170  23.176231  0.590568  6.000000  1998
32.031620  -4.814170  23.176231  0.590568  6.000000  1999
```

File name

• SS_rand??.dat

?? indicates a number of runs under calculation of TPQ method.

File format

- Line 1: Header
- Lines 2-: [double01] [double02] [double03] [double04] [double05] [int01]

Parameters

• [double01]

Type: double-type

Description : Inverse temperature $1/k_{\rm B}T$.

• [double02]

Type: double-type

Description : The expected value of energy $\langle H \rangle$.

• [double03]

Type: double-type

Description : The expected value of square of Hamiltonian $\langle H^2 \rangle$.

• [double03]

Type: double-type

Description : The expected value of doublon, $\frac{1}{N_s} \sum_i \langle n_{i\uparrow} n_{i\downarrow} \rangle$ (N_s is a total number of sites).

• [double05]

 $\mathbf{Type}: \mathbf{double}$ -type

Description : A total number of particles $\langle \hat{n} \rangle$.

• [int01]

Type: int-type

Description : A number of operations of $(l - \hat{H}/N_s)$ to an initial wave function, where l is LargeValue defined in ModPara file and N_s is a total number of sites.

4.3.17 Flct_rand.dat

(For TPQ method) This file is outputted to show the calculation results of the fluctuation of the particle number, doublon and S_z for TPQ method. An example of file format is shown as follows.

```
# inv_temp, N, N^2, D, D^2, Sz, Sz^2, step_i
0.0826564 12.00 144.00 0.00 0.00 0.0009345626081113 0.2500 1
0.1639935 12.00 144.00 0.00 0.00 0.0023147006319775 0.2500 2
0.2440168 12.00 144.00 0.00 0.00 0.0037424057659867 0.2500 3
...
135.97669 12.00 144.00 0.00 0.00 -0.000000000167368 0.2500 1998
136.04474 12.00 144.00 0.00 0.00 -0.0000000000165344 0.2500 1999
```

File name

• Flct_rand??.dat

?? indicates a number of runs under calculation of TPQ method.

File format

- Line 1: Header
- Lines 2-: [double01] [double02] [double03] [double04] [double05] [double06] [double07] [int01]

Parameters

• [double01]

Type: double-type

Description : Inverse temperature $1/k_{\rm B}T$.

• [double02]

Type: double-type

Description : A total particle number $\sum_{i} \langle \hat{n}_i \rangle$.

• [double03]

Type: double-type

Description: The expected value of square of particle number $\sum_{i} \langle \hat{n}_{i}^{2} \rangle$.

• [double04]

Type: double-type

Description : The expected value of doublon $\frac{1}{N_s} \sum_i \langle n_{i\uparrow} n_{i\downarrow} \rangle$ (N_s is a total number of sites).

• [double05]

Type: double-type

Description : The expected value of square of doublon $\frac{1}{N_s} \sum_i \langle (n_{i\uparrow} n_{i\downarrow})^2 \rangle$ (N_s is a total number of sites).

• [double06]

Type: double-type

Description : The expected value of $S_z \frac{1}{N_s} \sum_i \langle \hat{S}_i^z \rangle$ (N_s is a total number of sites).

• [double07]

Type: double-type

Description : The expected value of square of $S_z \frac{1}{N_s} \sum_i \langle (\hat{S}_i^z)^2 \rangle$ (N_s is a total number of sites).

• [int01]

Type: int-type

Description : A number of operations of $(l - \hat{H}/N_s)$ to an initial wave function, where l is LargeValue defined in ModPara file and N_s is a total number of sites.

4.3.18 Eigenvalue.dat

(For FullDiag method) This file is outputted to show the energies calculated by FullDiag method. An example of file format is shown as follows.

```
0 -4.8141698096

1 -3.7968502453

2 -3.2462822372

...

397 13.9898305290

398 14.4896221034

399 14.8525199079
```

File format

• [int01] [double01]

Parameters

• [int01]

Type: int-type

Description : An index of eigenvalues. The index 0 is for an energy of a ground state and indexes are counted from the low order of energies.

• [double01]

Type: double-type

Description : The expected value of energy $\langle H \rangle$.

4.3.19 phys.dat

(For FullDiag method) This file is outputted to show the physical values calculated by FullDiag method. The datas are outputted in the low order of energies. An example of file format is shown as follows.

<h> -4.814170 -3.796850</h>	<n> 0.000000 0.000000</n>	<sz> 0.000000 0.000000</sz>	<s2> -0.000000 1.333333</s2>	<d> 0.590568 0.423804</d>
14.489622 14.852520	0.000000	0.000000	0.000000	2.550240 2.329157

File name

- Canonical ensemble: ##_phys_Nup_\$\$Ndown%%.dat
- Grand canonical ensemble: ##_phys.dat

##, \$\$ and %% indicate [string02], Nup and Ndown defined in a ModPara file, respectively.

File format

- Line 1: Header
- Lines 2-: [double01] [double02] [double03] [double04] [double05]

Parameters

• [double01]

Type: double-type

Description : The energy $\langle H \rangle$.

• [double02]

Type: double-type

Description: A total number of particles $\langle \hat{n} \rangle$.

• [double03]

Type: double-type

Description : The expected value of S_z , $\langle S_z \rangle$.

• [double04]

Type: double-type

Description: The expected value of S^2 , $\langle S^2 \rangle$.

\bullet [double05]

 $\mathbf{Type}: \mathbf{double}$ -type

Description : The expected value of doublon, $\frac{1}{N_s} \sum_i \langle n_{i\uparrow} n_{i\downarrow} \rangle$ (N_s is a total number of sites).

4.3.20 cisajs.dat

This file is output files for one-body Green's function $\langle c_{i\sigma_1}^{\dagger} c_{j\sigma_2} \rangle$. The target components are set in the input file with the keyword "OneBodyG". An example of file format is shown as follows.

```
0
     0
                0 0.4452776740 0.0000000000
          0
0
     1
          0
                1 0.4452776740 0.0000000000
1
               0 0.500000000 0.0000000000
          1
1
     1
               1 0.5000000000 0.0000000000
          1
2
     0
          2
               0 0.4452776740 0.0000000000
2
               1 0.4452776740 0.0000000000
     1
          2
3
          3
               0 0.500000000 0.0000000000
3
     1
                1 0.5000000000 0.0000000000
          3
```

File name

• Lanczos method: ##_cisajs.dat

• TPQ method: ##_cisajs_set??step%%.dat

• Full diagonalization method: ##_cisajs_eigen&&.dat

##, ??, %% and && indicate [string02] in ModPara file, a number of runs under calculation in TPQ method, a number of steps in TPQ method and an index of eigenvalues, respectively.

File format

• [int01] [int02] [int03] [int04] [double01] [double02]

Parameters

• [int01], [int03]

Type: int-type

Description: An integer of the site number. [int01] and [int03] show the i and j site numbers, respectively.

• [int02], [int04]

Type: int-type

Description: An integer of the spin index,

0: up-spin,1: down-spin.

[int02] and [int04] show σ_1 and σ_2 , respectively.

 \bullet [double01], [double02]

 $\mathbf{Type}: \mathbf{double}$ -type

Description : The value of $\langle c_{i\sigma_1}^{\dagger} c_{j\sigma_2} \rangle$. [double01] and [double02] show the real and imaginary part of $\langle c_{i\sigma_1}^{\dagger} c_{j\sigma_2} \rangle$, re-

spectively.

4.3.21 cisajscktalt.dat

This file is output files for Two body Green's function $\langle c_{i\sigma_1}^{\dagger} c_{j\sigma_2} c_{k\sigma_3}^{\dagger} c_{l\sigma_4} \rangle$. The target components are set in the input file with the keyword "TwoBodyG". An example of file format is shown as follows.

	0	0	0	0	0	0	0	0 0.4452776740 0.0000000000
	0	0	0	0	0	1	0	1 0.1843355815 0.0000000000
	0	0	0	0	1	0	1	0 0.1812412105 0.0000000000
	0	0	0	0	1	1	1	1 0.2640364635 0.0000000000
	0	0	0	0	2	0	2	0 0.0279690007 0.0000000000
	0	0	0	0	2	1	2	1 0.2009271524 0.0000000000
	0	0	0	0	3	0	3	0 0.2512810778 0.0000000000
	0	0	0	0	3	1	3	1 0.1939965962 0.0000000000
/								

File name

- Lanczos method: ##_cisajscktalt.dat
- TPQ method: ##_cisajscktalt_set??step%%.dat
- Full diagonalization method: ##_cisajscktalt_eigen&&.dat

##, ??, %% and && indicate [string02] in ModPara file, a number of runs under calculation in TPQ method, a number of steps in TPQ method and an index of eigenvalues, respectively.

File format

 \bullet [int01] [int02] [int03] [int04] [int05] [int06] [int07] [int08] [double01] [double02]

Parameters

• [int01], [int03], [int05], [int07]

Type: int-type

Description: An integer of the site number. [int01], [int03], [int05] and [int07] show the i, j, k and lsite numbers, respectively.

• [int02], [int04], [int06], [int08]

Type: int-type

Description: An integer of the spin index,

0: up-spin,1: down-spin.

[int02], [int04], [int06] and [int08] show σ_1 , σ_2 , σ_3 and σ_4 , respectively.

 \bullet [double01], [double02]

 $\mathbf{Type}: \mathbf{double}$ -type

Description : The value of $\langle c_{i\sigma_1}^{\dagger} c_{j\sigma_2} c_{k\sigma_3}^{\dagger} c_{l\sigma_4} \rangle$. [double01] and [double02] show the real and imaginary part of $\langle c_{i\sigma_1}^{\dagger} c_{j\sigma_2} c_{k\sigma_3}^{\dagger} c_{l\sigma_4} \rangle$,

respectively.

4.3.22 eigenvec.dat

When OutputEigenVec=1 in a CalcMod file, eigenvectors calculated by a Lanczos method are outputted. When InputEigenVec=1 in a CalcMod file, eigenvectors are inputted by this outputted file. A file format is a binary type.

File name

• ##_eigenvec_&&_rank_\$\$.dat

indicates [string02] in ModPara file, && is a number of eigenvalues, \$\$ is a number of rank respectively.

File format

• Line 1: [int01]

• Line 2: [int02]

• Lines 3 -: [double01] [double02]

Parameters

• [int01]

Type: int-type

Description: A total number of targets of Hilbert spaces.

• [int02]

Type: int-type

Description: A number of Lanczos steps.

• [double01], [double02]

Type: double

Description: A value of eigenvectors.

[double01] is a real part, [double02] is an imaginary part.

4.3.23 tmpvec.dat

When ReStart=1, 2 in a CalcMod file, vectors after stopping calculation at an indicated step are outputted. A file format is a binary type. An example of file format is shown as follows.

File name

- Lanczos method: ##_tmpvec_rank_\$\$.dat
- TPQ method: ##_tmpvec_set_&&_rank_\$\$.dat

indicates [string02] in ModPara file, \$\$ is a number of rank respectively. && is a sampling number for TPQ calculation.

File format

- Line 1: [int01]
- Line 2: [int02]
- Lines 3 3+[int01]: [double01] [double02]
- Lines $4+[int01] 3+2\times[int01]$: [double03] [double04]

Parameters

• [int01]

Type: int-type

Description: A total number of targets of Hilbert spaces.

• [int02]

Type: int-type

Description: A number of Lanczos (TPQ) steps for Lanczos (TPQ) method.

• [double01], [double02]

Type: double

Description : A value of two vectors (v_{k+1} in Eq. (5.6) for Lanczos method and y_{k+1} in Eq. (5.8) for TPQ method). [double01] is a real part, [double02] is an imaginary part.

• [double03], [double04]

Type: double

Description: A value of two vectors (v_k in Eq. (5.6) for Lanczos method and y_k in Eq. (5.8) for TPQ method). [double03] is a real part, [double04] is an imaginary part.

4.3.24 DynamicalGreen.dat

This file is output files for calculating dynamical Green's function. An example of file format is shown as follows.

File name

• ##_DynamicalGreen.dat

indicates [string02] in ModPara file.

File format

• Lines 1-: [double01] [double02] [double03] [double04]

Parameters

• [double01], [double02]

Type: double-type

Description : The value of the frequency z.

[double01] and [double02] are a real and an imaginary part of z, respectively.

• [double03], [double04]

Type: double-type

Description: The value of dynamical Green's functions G(z).

[double03] and [double04] are a real and an imaginary part of G(z), respec-

tively.

4.3.25 recalcvec.dat

This file is output files for two vectors to recalculate dynamical Green's function by Lanczos method. A file format is a binary type. An example of file format is shown as follows.

File name

• ##_recalcvec_rank_\$\$.dat

indicates [string02] in ModPara file, \$\$ is a number of rank respectively.

File format

• Line 1: [int01]

• Line 2: [int02]

• Lines 3 - 3+[int02]: [double01] [double02]

• Lines $4+[int02] - 3+2\times[int02]$: [double03] [double04]

Parameters

• [int01]

Type: int-type

Description: The step for calculating dynamical Green's functions by Lanczos method N_d .

• [int02]

Type: int-type

Description: A total number of targets of Hilbert spaces.

• [double01], [double02]

Type: double-type

Description: The value of the vector v_{k+1} for recalculating dynamical Green's functions by Lanczos method.

[double01] and [double02] are a real part and an imaginary part of v_{k+1} , respectively.

• [double03], [double04]

Type: double-type

Description : The value of the vector v_k for recalculating dynamical Green's functions by Lanczos method.

[double03] and [double04] are a real part and an imaginary part of v_k , respectively.

4.3.26 TMcomponents.dat

This file is output files for the components of tridiagonal matrix and the norm of the excited state to recalculate dynamical Green's function by Lanczos method. A file format is a binary type. An example of file format is shown as follows.

File name

• ##_TMcomponents.dat

indicates [string02] in ModPara file, \$\$ is a number of rank respectively.

File format

• Line 1: [int01]

• Line 2: [double01]

• Lines 3 -: [double02] [double03]

Parametes

• [int01]

Type: int-type

Description : The step for calculating dynamical Green's functions by Lanczos method N_d .

• [double01]

Type: double-type

Description: The value of the norm of the excited state.

• [double02], [double03]

Type: double-type

Description: The value of the components of the tridiagonal matrix to recalculate dynamical Green'S functions by Lanczos method α_i , β_i $(i = 1, \dots, N_d)$. [double02] is α_i and [double03] is β_i , respectively

4.4 Error messages

• ERROR! Unsupported Keyword!

The program stops because unsupported keyword is specified.

- "ERROR! Keyword keyword is duplicated!

 The program stops because a parameter is specified twice.
- ERROR ! Unsupported Solver : solver
- ullet ERROR ! Unsupported Model : model
- \bullet Sorry, this system is unsupported in the STANDARD MODE... Please use the EXPART MODE, or write a NEW FUNCTION and post it us.

The program stops because unsupported parameter for method, model, or lattice is specified.

- ERROR ! abs(2 * Sz) > nsite in Hubbard model !
- ERROR ! Nelec > 2 * nsite in Hubbard model !
- ERROR ! (nelec + 2 * Sz) % 2 != 0 in Hubbard model !
- ERROR ! nelec <= nsite && 2 * |Sz| > nelec in Hubbard model !
- ERROR ! nelec > nsite && 2 * |Sz| > 2 * nsite nelec in Hubbard model !
- ERROR ! abs(2 * Sz) > nsite in Spin model !
- ERROR ! (nsite + 2 * Sz) % 2 != 0 in Spin model !
- ERROR ! abs(2 * Sz) > nsite in Hubbard model !
- ERROR ! Nelec_cond / 2 + Nelec_loc > nsite in Kondo model !
- ERROR ! (nelec_cond + nelec_loc + 2 * Sz) % 2 != 0 in Kondo model !
- ERROR ! nelec_cond <= nsite / 2 && 2 * |Sz| > nelec_cond + nelec_loc ...
- ERROR ! nelec_cond > nsite / 2 && abs(Sz2) > nsite / 2 * 3 nelec...

In the calculation of the canonical ensemble, there are some irrelevant combinations of the number of electrons, the number of sites, and the total spin moment (the number of electrons is larger twice than the number of sites); If these situations are detected, the program will stop.

• Check ! keyword is SPECIFIED but will NOT be USED.

Please COMMENT-OUT this line
or check this input is REALLY APPROPRIATE for your purpose !

Because an unnecessary parameter is specified, the program suggests checking the input file. If that parameter is actually unnecessary, please delete or comment out this line.

- ERROR ! keyword is NOT specified !

 The program stops because a prerequisite keyword is not specified.
- keyword = value ##### DEFAULT VALUE IS USED #####

 This is not an error message. The program states that the default value is used because this keyword is not specified.

Algorithm

5.1 Lanczos method

5.1.1 Details of Lanczos method

Some parts of this section are based on the manual of titpack [7] and textbook by M. Sugihara and K. Murota [8] (These references are written in Japanese).

In the Lanczos method, by successively operating the Hamiltonian to the initial vector, we obtain the accurate eigenvalues around the maximum and minimum eigenvalues and associated eigenvectors. Because we can perform Lanczos method by using only two vectors whose dimensions are the dimension of the total Hilbert space *1, Lanczos method is frequently used for the diagonalization of the large matrices. As we detail below, one additional vector is necessary for obtaining the eigenvector.

The principle of the Lanczos method is based on the power method. In the power method, by successively operating the Hamiltonian $\hat{\mathcal{H}}$ to the arbitrary vector \mathbf{x}_0 , we generate $\hat{\mathcal{H}}^n \mathbf{x}_0$. The obtained space $\mathcal{K}_{n+1}(\hat{\mathcal{H}}, \mathbf{x}_0) = \{\mathbf{x}_0, \hat{\mathcal{H}}^1 \mathbf{x}_0, \dots, \hat{\mathcal{H}}^n \mathbf{x}_0\}$ is called Krylov subspace. Initial vector is represented by the superposition of the eigenvectors \mathbf{e}_i (corresponding eigenvalues are E_i) of $\hat{\mathcal{H}}$ as

$$\boldsymbol{x}_0 = \sum_i a_i \boldsymbol{e}_i. \tag{5.1}$$

Here, E_0 is maximum absolute values of the eigenvalues. We note that all the eigenvalues are real number because Hamiltonian is Hermite. By operating $\hat{\mathcal{H}}^n$ to the initial vector, we obtain the relation as

$$\hat{\mathcal{H}}^n \mathbf{x}_0 = E_0^n \left[a_0 \mathbf{e}_0 + \sum_{i \neq 0} \left(\frac{E_i}{E_0} \right)^n a_i \mathbf{e}_i \right]. \tag{5.2}$$

This relation indicates that the eigenvector of E_0 becomes dominant for sufficiently large n. In the Lanczos method, we obtain the eigenvalues and eigenvectors by performing the proper transformation for obtained Krylov subspace.

In the Lanczos method, we successively generate the normalized orthogonal basis v_0, \ldots, v_{n-1} from the Krylov subspace $\mathcal{K}_n(\hat{\mathcal{H}}, x_0)$. We define initial vector and

^{*1}In $\mathcal{H}\Phi$, to reduce the numerical cost, we use some additional vectors; vector for accumulating the real-space diagonal elements of the Hamiltonian, vector for specifying the given S_z space and given particle space. The dimension of these vectors is that of the Hilbert space.

associated components as $\mathbf{v}_0 = \mathbf{x}_0/|\mathbf{x}_0|$, $\beta_0 = 0$, $\mathbf{x}_{-1} = 0$. From this initial condition, we can obtain the normalized orthogonal basis as follows:

$$\alpha_k = (\hat{\mathcal{H}}\boldsymbol{v}_k, \boldsymbol{v}_k), \tag{5.3}$$

$$\mathbf{w} = \hat{\mathcal{H}} \mathbf{v}_k - \beta_k \mathbf{v}_{k-1} - \alpha_k \mathbf{v}_k, \tag{5.4}$$

$$\beta_{k+1} = |\boldsymbol{w}|, \tag{5.5}$$

$$\boldsymbol{v}_{k+1} = \frac{\boldsymbol{v}_k}{|\boldsymbol{v}_k|}.\tag{5.6}$$

From these definitions, it it obvious that α_k , β_k are real number.

In the subspace spanned by these normalized orthogonal basis, the Hamiltonian is transformed as

$$T_n = V_n^{\dagger} \hat{\mathcal{H}} V_n. \tag{5.7}$$

Here, V_n is matrix whose column vectors are $\mathbf{v}_i (i=0,1,\ldots,n-1)$. T_n is tridiagonal matrix and its diagonal elements are α_i and subdiagonal elements are β_i . It is known that the eigenvalues of $\hat{\mathcal{H}}$ are well approximated by the eigenvalues of T_n for sufficiently large n. (We note that $V^{\dagger}V=I,I$ is identity matrix). The original eigenvectors of $\hat{\mathcal{H}}$ is obtained by $\mathbf{e}_i=V\tilde{\mathbf{e}}_i$, where $\tilde{\mathbf{e}}_i$ are the eigenvectors of T_n . From V, we can obtain the eigenvectors of $\hat{\mathcal{H}}$ by performing the Lanczos method. However, in the actual calculations, it is difficult to keep V because its dimension is large [dimension of V=(dimension of the total Hilbert space) \times (# of Lanczos iterations)]. Thus, to obtain the eigenvectors, we again perform the same Lanczos calculations after we obtain the eigenvalues from the Lanczos methods. In the first Lanczos calculation, we keep $\tilde{\mathbf{e}}_i$ because its dimension is small *2. From this procedure, we obtain the eigenvectors from V.

In the Lanczos method, within a few hundred or thousand Lanczos iterations, we obtain the accurate eigenvalues near the maximum and minimum values of eigenvalues. The necessary number of iterations is small enough compared to the dimensions of the total Hilbert space. We note that it is shown that the errors of the maximum and minimum eigenvalues becomes exponentially small as a function of Lanczos iteration (for details, see Ref. [8]).

5.1.2 Inverse iteration method

From the approximate value of the eigenvalues (E_n) , by successively operating $(\hat{\mathcal{H}} - E_n)^{-1}$ to the initial vector \mathbf{y}_0 , we can obtain the accurate eigenvector for E_n . From $(\hat{\mathcal{H}} - E_n)^{-1}\mathbf{y}_0$, we obtain the linear simultaneous equations such as

$$\mathbf{y}_k = (\hat{\mathcal{H}} - E_n)\mathbf{y}_{k+1}. \tag{5.8}$$

By solving this equation by using the conjugate gradient method (CG method), we obtain the eigenvector. From the obtained eigenvector, we can calculate the eigenvalues and correlation functions. We note that additional four vectors are necessary to perform the CG method. For large system size, it may be impossible to allocate memory to the additional vectors.

^{*2}upper bound of the dimensions of $\tilde{e_i}$ is # of Lanczos iterations.

110 5 Algorithm

5.1.3 Details of implementation

Initial vector

For Lanczos method, an initial vector is specified with initial_iv($\equiv r_s$) defined in an input file for Standard mode or a ModPara file for Expert mode. A type of an initial vector can be selected from a real number or complex number by using InitialVecType in a ModPara file.

• For canonical ensemble and initial_iv ≥ 0

A component of a target of Hilbert space is given by

$$(N_{\rm dim}/2 + r_s)\% N_{\rm dim},$$
 (5.9)

where N_{dim} is a total number of the Hilbert space and $N_{\text{dim}}/2$ is added to avoid selecting a special Hilbert space for a default value initial_iv = 1. When a type of an initial vector is selected as a real number, a coefficient value is given by 1, while as a complex number, the value is given by $(1+i)/\sqrt{2}$.

• For grand canonical ensemble or initial_iv < 0

An initial vector is given by using a random generator, i.e. coefficients of all components for the initial vector is given by random numbers. The seed is calculated as

$$123432 + |r_s|, (5.10)$$

where r_s is a number given by an input file and n_{run} is a number of runs. A maximum value of n_{run} is defined by NumAve in an input file for Standard mode or a ModPara file for Expert mode. Random numbers are generated by using SIMD-oriented Fast Mersenne Twister (dSFMT) [9].

Convergence condition

In $\mathcal{H}\Phi$, we use **dsyev** (routine of lapack) for diagonalization of T_n . We use the energy of the first excited state of T_n as a criteria of convergence. In the standard setting, after five Lanczos step, we diagonalize T_n every two Lanczos step. If the energy of the first excited states coincides with the previous energy within the specified accuracy, the Lanczos iteration finishes. The accuracy of the convergence can be specified by CDataFileHead (ModPara file in the expert mode).

After obtaining the eigenvalues, we again perform the Lanczos iteration to obtain the eigenvector. From the eigenvectors $|n\rangle$, we calculate energy $E_n = \langle n|\hat{\mathcal{H}}|n\rangle$ and variance $\Delta = \langle n|\hat{\mathcal{H}}^2|n\rangle - (\langle n|\hat{\mathcal{H}}|n\rangle)^2$. If E_n coincides with the eigenvalues obtained by the Lanczos iteration and Δ is smaller than the specified value, we finish diagonalization.

If the accuracy of Lanczos method is not enough, we perform the CG method to obtain the eigenvector. As an initial vector of the CG method, we use the eigenvectors obtained by the Lanczos method in the standard setting. This often accelerates the convergence.

5.2 Full Diagonalization method

5.2.1 Over view

We generate matrix of \hat{H} by using the real space configuration $|\psi_j\rangle(j=1\cdots d_{\rm H}, d_{\rm H})$ is dimension of the Hilbert space): $H_{ij}=\langle\psi_i|\hat{H}|\psi_j\rangle$. By diagonalizing this matrix, we can obtain all the eigenvalues E_i and eigenvectors $|\Phi_i\rangle$ $(i=1\cdots d_{\rm H})$. In the diagonalization, we use lapack routine such as dsyev or zheev. We also calculate and out put the expectation values $\langle A_i\rangle \equiv \langle \Phi_i|\hat{A}|\Phi_i\rangle$. These values are used for the finite-temperature calculations.

5.2.2 Finite-temperature calculations

From $\langle A_i \rangle \equiv \langle \Phi_i | \hat{A} | \Phi_i \rangle$, we calculate finite-temperature properties by using the relation

$$\langle \hat{A} \rangle = \frac{\sum_{i=1}^{N} \langle A_i \rangle e^{-\beta E_i}}{\sum_{i=1}^{N} e^{-\beta E_i}}.$$
 (5.11)

In the actual calculation are performed as the post scripts.

5.3 Finite-temperature calculations by TPQ method

Sugiura and Shimizu show that it is possible to calculate the finite-temperature properties from a few wavefunctions (in the thermodynamic limit, only one wave function is necessary) [5]. The wavefunction is called thermal pure quantum (TPQ) state. Because TPQ state can be generated by operating the Hamiltonian to the random initial wavefunction, we directly use the routine Lanczos method to the TPQ calculations. Here, we explain how to construct micro canonical TPQ (mTPQ) state, which offers the simplest way for finite-temperature calculations.

Let $|\psi_0\rangle$ a random initial vector. By operating $(l - \hat{H}/N_s)^k(l)$ is constant, N_s represents number of sites) to $|\psi_0\rangle$, we obtain the kth TPQ states as

$$|\psi_k\rangle \equiv \frac{(l-\hat{H}/N_s)|\psi_{k-1}\rangle}{|(l-\hat{H}/N_s)|\psi_{k-1}\rangle|}.$$
(5.12)

From $|\psi_k\rangle$, we estimate corresponding inverse temperature β_k as

$$\beta_k \sim \frac{2k/N_s}{l-u_k}, \quad u_k = \langle \psi_k | \hat{H} | \psi_k \rangle / N_s,$$
 (5.13)

where u_k is the internal energy. Arbitrary local physical properties at β_k is also estimated as

$$\langle \hat{A} \rangle_{\beta_k} = \langle \psi_k | \hat{A} | \psi_k \rangle / N_s.$$
 (5.14)

In finite-size system, error is caused by the choice of the initial random vector. To estimate the average value and error of the physical properties, we perform some independent calculations by changing $|\psi_0\rangle$.

112 5 Algorithm

5.3.1 Details of implementation

Initial vector

For TPQ method, an initial vector is given by using a random generator, i.e. coefficients of all components for the initial vector is given by random numbers. The seed is calculated as

$$123432 + (n_{\text{run}} + 1) \times |r_s| + k_{\text{Thread}} + N_{\text{Thread}} \times k_{\text{Process}}$$
 (5.15)

where r_s is a number given by an input file and $n_{\rm run}$ is a number of runs. r_s and a maximum value of $n_{\rm run}$ are defined by initial_iv and NumAve in an input file for Standard mode or a ModPara file for Expert mode, respectively. Random numbers are generated by using SIMD-oriented Fast Mersenne Twister (dSFMT) [9]. We can select a type of initial vector from a real number or complex number by using InitialVecType in a ModPara file. $k_{\rm Thread}$, $N_{\rm Thread}$, $k_{\rm Process}$ indicate the thread ID, the number of threads, the process ID, respectively; the initial vector depends both on initial_iv and the number of parallelism.

5.4 Bogoliubov representation

In the spin system, the spin indices in input files of transfer, InterAll, and correlation functions are specified as those of the Bogoliubov representation. Spin operators are written by using creation/annihilation operators as follows:

$$S_{iz} = \sum_{\sigma = -S}^{S} \sigma c_{i\sigma}^{\dagger} c_{i\sigma} \tag{5.16}$$

$$S_{i}^{+} = \sum_{\sigma=-S}^{S-1} \sqrt{S(S+1) - \sigma(\sigma+1)} c_{i\sigma+1}^{\dagger} c_{i\sigma}$$
 (5.17)

$$S_{i}^{-} = \sum_{\sigma=-S}^{S-1} \sqrt{S(S+1) - \sigma(\sigma+1)} c_{i\sigma}^{\dagger} c_{i\sigma+1}$$
 (5.18)

O Acknowledgement

We would like to express our sincere gratitude to Prof. Hidetoshi Nishimori and Mr. Daisuke Tahara. Implementation of the Lanczos algorithm in $\mathcal{H}\Phi$ written in C is based on the pioneering diagonalization package TITPACK written in Fortran by Prof. Nishimori. For developing the user interface of $\mathcal{H}\Phi$, we follow the design concept of the user interface in the program for variational Monte Carlo developed by Mr. Tahara. A part of the user interface in $\mathcal{H}\Phi$ is based on his original codes. We would also like to thank the support from "Project for advancement of software usability in materials science" by The Institute for Solid State Physics, The University of Tokyo, for development of $\mathcal{H}\Phi$ ver.0.1, ver.0.2, ver.0.3, ver.1.0, ver.1.1 and ver.1.2.

References

- [1] E. Dagotto, Rev. Mod. Phys. **66**, 763–840 (1994).
- [2] M. Imada, M. Takahashi, Journal of the Physical Society of Japan **55**, 3354–3361 (1986).
- [3] J. Jaklič, P. Prelovšek, Phys. Rev. B 49, 5065–5068 (1994).
- [4] A. Hams, H. De Raedt, Phys. Rev. E **62**, 4365–4377 (2000).
- [5] S. Sugiura, A. Shimizu, Phys. Rev. Lett. **108**, 240401 (2012).
- [6] Y. Yamaji, Y. Nomura, M. Kurita, R. Arita, M. Imada, Phys. Rev. Lett. 113, 107201 (2014).
- [7] http://www.stat.phys.titech.ac.jp/ nishimori/titpack2_new/index-e.html.
- [8] M. Sugihara, K. Murota, Theoretical Numerical Linear Algebra, Iwanami Studies in Advanced Mathematics, Iwanami Shoten, Publishers, 2009.
- [9] http://www.math.sci.hiroshima-u.ac.jp/ m-mat/MT/SFMT.