Loaders

Loaders

- A loader is a system program that performs the loading function.
 - many also support relocation & linking
 - others have a separate linker and loader
- Basic Functions
 - bringing an object program into memory
 - starting its execution

Input

Object program:

- contains translated instructions and data from the source program.
- specifies addresses in memory where these items are to be loaded.


Basic Functions

- Allocation: allocate space in memory for the programs
- Linking: Resolve symbolic references between object files
 - combines two or more separate object programs
 - supplies the information needed to allow references between them

Basic Functions

- Relocation: Adjust all address dependent locations, such as address constants, to correspond to the allocated space
 - modifies the object program so that it can be loaded at an address different from the location originally specified
- Loading: Physically place the machine instructions and data into memory

Basic Functions




Design of an Absolute Loader

- Its operation is very simple
 - no linking or relocation
- Single pass operation
 - check H record to verify that correct program has been presented for loading
 - read each T record, and move object code into the indicated address in memory
 - at E record, jump to the specified address to begin execution of the loaded program.

Loader Schemes

- Compile and Go
 - The assembler run in one part of memory
 - place the assembled machine instructions and data, as they are assembled, directly into their assigned memory locations
 - When the assembly is completed, the assembler causes a transfer to the starting instruction of the program

Absolute Loader



Disadvantages

- A portion of memory is wasted because the memory occupied by the assembler is unavailable to the object program.
- It is necessary to re-translate (assemble) the user's program file every time it is run.
- It is very difficult to handle multiple segments, especially if the source programs are in different.

Disadvantages

- If changes were made to MAIN that increased its length to more than 300 bytes
 - the end of MAIN (at 100 + 300 = 400) would overlap the start of SQRT (at 400)
 - It would then be necessary to assign SQRT to a new location
 - changing its START and re-assembling it?!
- Furthermore, it would also be necessarily to modify all other subroutines that referred to the address of SQRT.

A Simple Bootstrap Loader

- Automatically executed when the computer is first turned on
- Loads the first program to be run: usually the O/S itself begins at address 0 in memory
 - loads the O/S starting at address 80
 - After all code is loaded, bootstrap jumps to address 80.
 - No H or E records, no control information

Disadvantages of Absolute Loaders

- Actual load address must be specified
- The programmer must be careful not to assign two subroutines to the same or overlapping locations
- Difficult to use subroutine libraries (scientific and mathematical) efficiently
 - important to be able to select and load exactly those routines that are needed

Disadvantages of Absolute Loaders

- Allocation by programmer
- Linking by programmer
- Relocation None required-loaded where assembler assigned
- Loading by loader

General Loader Scheme

- Linking
- Relocation
- Loading

Subroutine Linkages

- The main program A wishes to transfer to subprogram B.
- The programmer, in program A, could write a transfer instruction (e g, BSR B) to subprogram B.
- The assembler does not know the value of this symbol reference and will declare it as an error

Externals and Entries

- The assembler pseudo-op EXT followed by a list of symbols indicates that the symbols are defined in other programs but referenced in the present program
- If a symbol is defined in one program and referenced in others,
 - insert it into a symbol list following the pseudo-op ENT.

MAIN ORG \$10

EXT SUBROUT

BSR SUBROUT

DONE HLT

Relocation

- Relocating loaders or relative loaders:
 - loaders that allow for program relocation.
- Two methods for specifying relocation as part of the object program:

1. A Modification record

- describe each part of the object code that must be changed when the program is relocated
- M0000_16

Second Method

- Bit mask: A relocation bit/byte associated with each word of object code
 - S for Absolute: does not need modification
 - R for Relative: needs relocation
 - X for external.
- Example
- T00106119SFE00S4003S0E01R

Two Pass Direct Linking Loader

Pass 1

- Allocate and assign each program location in core.
- Create a symbol table filling in the values of the external symbols.

Pass 2

- Load the actual program text.
- Perform the **relocation** modification of any address constants needing to be altered.
- Resolve external references. (linking)

Data Structures

- External Symbol Table (ESTAB)
 - stores the name and address of each external symbol in the set of programs being loaded.
 - Indicates in which program the symbol is defined.
 - A hash table is generally used.
- Program Load Address (PROGADDR)
 - beginning address in memory where the linked program is to be loaded.
 - supplied by the O/S

More Databases

- Control Section Address (CSADDR)
 - starting address assigned to the CS currently being scanned by the loader
 - Its value is added to all relative addresses within the control section to convert them to actual addresses

The Algorithm

- Pass 1: concerned only w/Header records
 - PROGADDR is obtained from O/S
 - CSADDR is set accordingly
 - All external symbols are entered into External Symbol Table (ESTAB)
 - Their addresses are obtained by adding values specified in header to CSADDR (- First ORG?!)
 - Starting address and length of each CS are determined. CSADDR = CSADDR + CSLEN
 - Print Load Map

ESTAB

| Program/ CS | Symbol | Address | Length |
|----------------|--------|---------|--------|
| Test | | 0040 | 0046 |
| | EXE | 0060 | |
| ProgA | | 0086 | 0010 |
| | LISTA | 0090 | |
| ProgB | | 0096 | 6 |

Pass II

- Does actual loading, relocation, and linking
- As each Text record is read
 - The object code is moved to the specified address (plus the current value of CSADDR)
 - When "R" is encountered, the value is added or subtracted from the indicated location in memory
 - When "X" is encountered resolve symbol from ESTAB
 - Last step: transfer control to loaded program to begin execution, as indicated in the End record

Relocating Loaders

- Allocating subroutines to prevent reassembling the code every time a subroutine changes
- Binary Symbolic Subroutine (BSS) Loader
 - The program length information is for allocation.
 - Bit Mask is used for relocation
 - The transfer vector is used to solve the problem of linking

Binary Symbolic Subroutine Loader

- The assembler assembles Provides the loader
 - Object program + relocation information
 - Prefixed with information about all other program it references (transfer vector).
 - The length of the entire program
 - The length of the transfer vector portion

Transfer Vector

- A transfer vector consists of
 - addresses containing names of the subroutines referenced by the source program
 - if a Square Root Routine (SQRT) was referenced and was the first subroutine called, the first location in the transfer vector could contain the symbolic name SQRT.
 - The statement calling SQRT would be translated into a branch to the location of the transfer vector associated with SQRT

The loader

- loads the text and the transfer vector
- loads each subroutine identified in the transfer vector.
- place a transfer instruction to the corresponding subroutine in each entry in the transfer vector.
 - The execution of the call SQRT statement result in a branch to the first location in the transfer vector
 - which contains a branch to the location of SQRT.

Example

| MAIN | START | |
|------|----------|---------|
| | EXTERNAL | SORT |
| | EXTERNAL | ERR4 |
| | LOAD | 1,=F9 |
| | BALINK | 14,SQRT |
| | COMPARE | 1,=F3 |
| | BNE ERR | |
| | HLT | |
| =9 | DATA | 9 |
| =3 | DATA | 3 |
| END | | |

| LC | r/s/e | |
|----|-------|--------------|
| 0 | 00 | SORT |
| 4 | 00 | ERR |
| 8 | 01 | LOAD 1,1C |
| С | 01 | BALINK 14, 0 |
| 10 | 01 | COMPARE 1,20 |
| 14 | 01 | BNE 4 |
| 18 | 00 | HLT |
| 1C | 00 | 0009 |
| 20 | 00 | 0003 |
| | | |
| | | |

After Loading Using BSS Scheme

- Program Length
 - 20 bytes
- Transfer vector
 - 8 bytes

| 0 | 400 | BALINK 14,448 |
|----|-----|---------------|
| 4 | 404 | BALINK 14,526 |
| 8 | 408 | LOAD 1,41C |
| С | 40C | BALINK 14,400 |
| 10 | 410 | COMPARE 1,420 |
| 14 | 414 | BNE 404 |
| 18 | 418 | HLT |
| 1C | 41C | 0009 |
| 20 | 420 | 0003 |
| | | |
| | | |

BSS Scheme Disadvantages

- 1. the transfer vector increases the size of the object program in memory
- 2. the BSS loader does not facilitate access to data segments that can be shared
 - the transfer vector linkage is only useful for transfers or BSRs
 - not well suited for loading or storing external data (data located in another procedure segment)

Direct Linking Loader

- The assembler provides
 - 1. The length of segment
 - 2. A list of all entries and their relative location within the segment
 - 3. A list of all external symbols
 - 4. Information as to where address constants are loaded in the segment and a description of how to revise their values.
 - 5. The machine code translation of the source program and the relative addresses assigned

Example

| John | START ENTRY EXTERNAL LOAD LD-ADDR BALR STORE HLT | RESULT L 1,POINTER 15 ASUM 14 15 1 RESULT | SUM 0 4 8 12 1C | I LOAD LD-ADDR BALR STORE HLT | 1,48 15,56 14 15 1,52 0,0 |
|---------------------------|---|--|--------------------------------|--|---------------------------------------|
| TABLE | DC | 1,7,9,10,13 | 28 2A 2C 30 34 | 0001 0007 0009 000A 000D | |
| POINTER RESULT ASUM | DATA NUM DATA END | ADDR(TABLE) 0 ADDR(SUM) | 48 52 56 | 0028 0000 ???? | EXTERNAL |

Assembler records

- External Symbol Dictionary (ESD) record:
 Entries and Externals
- (TXT) records control the actual object code translated version of the source program.
- The Relocation and Linkage Directory (RLD) records relocation information
- The END record specifies the starting address for execution

ESD and RLD

- SD: Segment Definition
- Local Definition
- External Reference

ESD records

| symbol | type | Rel- location | Length |
|--------|------|------------------|--------|
| JOHN | SD | 0 | 64 |
| RESULT | LD | 52 | |
| SUM | ER | _ | |

RLD record

| | | | Relative |
|--------|------|--------|----------|
| Symbol | Flag | Length | location |
| JOHN | + | 4 | 48 |
| SUM | + | 4 | 56 |

Disadvantages of Direct Linking

- It is necessary to allocate, relocate, link, and load all of the subroutines each time in order to execute a program
 - loading process can be extremely time consuming.
- Though smaller than the assembler, the loader absorbs a considerable amount of space
 - Dividing the loading process into two separate programs a binder and a module loader can solve these problems.

Binder

- A binder is a program that performs the same functions as the direct linking loader
 - allocation, relocation, and linking
- Outputs the text in a file rather than memory
 - called a load module.
- The module loader merely has to physically load the module into memory.

Binder Classes

- Core image builder:
 - Produces a load module that looks very much like a "snapshot" or "image" of a section of core,
 - Called Core image module.
- Link editor, can keep track of the relocation Information
 - The load module can be further relocated
 - The module loader must perform allocation and relocation as well as loading
 - No linking.

Disadvantage

- If a subroutine is referenced but never executed
 - if the programmer had placed a call statement in the program but was never executed because of a condition that branched around it
 - the loader would still incur the overhead or linking the subroutine.
- All of these schemes require the programmer to explicitly name all procedures that might be called.

Dynamic Loading


- If the total amount of memory required by all subroutines exceeds the amount available
- The module loader loads the only the procedures as they are needed.
 - Allocating an overlay structure
- The Flipper or overlay supervisor is the portion of the loader that actually intercepts the "calls" and loads the necessary procedure.

Example

- Suppose a program consisting of five subprograms (A{20k},B{20k}, C{30k}, D{10k}, and E{20k}) that require 100K bytes of core.
 - Subprogram A only calls B, D and E;
 - subprogram B only calls C and E;
 - subprogram D only calls E
 - subprogram C and E do not call any other routines
- Note that procedures B and D are never in used the same time; neither are C and E.

Longest Path Overlay Structure

100k vs 70k needed



Dynamic Linking

- The loading and linking of external references are postponed until execution time.
- The loader loads only the main program
- If the main program should
 - execute a branch to an external address,
 - reference an external variable
- The loader is called
 - Only then has the segment containing the external reference loaded.

Design of Direct Linking Loader

| 1 2 | О | PGA | START ENTRY | A1,A2 |
|----------|----------|-----|-----------------|-------------------|
| 3 | | | EXTERNAL | B1,PGB |
| 4 | 20 | A1 | | |
| 5 | 30 | A2 | | |
| 6 | 40 | | ADDR | A(A1) |
| 7 | 44 | | ADDR | A(A2+15) |
| 8 | 48 | | ADDR | A(A2-A1-3) |
| 9 | 52 | | ADDR | A(PGB) |
| 10 | 56 | | ADDR | A(B1+PGB-A1+4) |
| 11 | | | END | |
| 12 | 0 | PGB | START | |
| 13 | | | ENTRY | B1 |
| 14 | | | EXTERNAL | A1,A2 |
| 15 | 1.0 | D1 | | |
| | 16 | B1 | | |
| 16 | 24 | BI | ADDR | A(A1) |
| 16 17 | | BI | ADDR ADDR | A(A1) A(A2+15) |
| | 24 | BI | | |
| 17 | 24 28 | ві | ADDR | A(A2+15) |

ESD Records

| Variable Name | Туре | address | Length | Reference: to source line |
|------------------|----------------|---------|--------|---------------------------|
| PGA | Program Name | 0 | 60 | 1 |
| A1 | Local variable | 20 | | 2 |
| A2 | Local variable | 30 | | 2 |
| PGB | External Var | | | 3 |
| B1 | External Var | | | 3 |

TXT Records

| Relative Address | Contents | What the assembler did | Reference to source line |
|------------------|----------|------------------------|--------------------------|
| 40 | 20 | | 6 |
| 44 | 45 | =30+15 | 7 |
| 48 | 7 | 30-20-3 | 8 |
| 52 | 0 | unknown | 9 |
| 56 | -16 | -20+4 | 10 |

RLD Records

| Relative Address | Arithmetic Operator | Variable Name | Length | Reference to source line |
|---------------------|------------------------|------------------|--------|--------------------------|
| 40 | + | PGA | 4 | 6 |
| 44 | + | PGA | 4 | 7 |
| 52 | + | PGB | 4 | 9 |
| 56 | + | B1 | 4 | 10 |
| 56 | + | PGB | 4 | 10 |
| 56 | - | PGA | 4 | 10 |

ESD Records

| Variable Name | Туре | address | Length | Reference: to source line |
|------------------|----------------|---------|--------|---------------------------|
| PGB | Program Name | 0 | 36 | 12 |
| B1 | Local Variable | 16 | N/A | 13 |
| A1 | External Var | unknown | N/A | 14 |
| A2 | External Var | unknown | N/A | 14 |

TXT Records

| Relative | Contents | What the assembler | Reference to |
|----------|----------|--------------------|--------------|
| Address | | did | source line |
| 24 | 0 | =0 A1 unknown | 16 |
| 28 | 15 | =15 A2 unknown | 17 |
| 32 | -3 | =-3 A1,A2 unknown | 18 |

RLD Records

| Relative | Arithmetic | Variable | Length | Reference to |
|----------|------------|----------|--------|--------------|
| Address | Operator | Name | | source line |
| 24 | + | A1 | 4 | 16 |
| 28 | + | A2 | 4 | 17 |
| 32 | + | A2 | 4 | 18 |
| 32 | - | A1 | 4 | 18 |

Algorithm

- Pass 1
 - Allocate Segments
 - Initial Program Load Address (IPLA)
 - Assign each segment the next table location after the preceding segment.
 - Define Symbols
 - SD
 - LD
 - ER?!

Pass 2: load text and relocate/link


- ESD record types is processed differently.
 - SD The LENGTH of the segment is temporarily saved in the variable SLENGTH.
 - LD does not require any processing during pass 2.
 - ER The Global External Symbol Table (GEST) is searched for match with the ER symbol
 - If found in the GEST, Substitute value
 - If it is not found \rightarrow error

Pass 2


- TXT: the text is copied from the record to the relocated core location (PLA + ADDR).
- RLD: The value to be used for relocation and linking is extracted from the GEST
 - If Flag is Plus the value is added, if Flag is minus
 the value is subtracted from the address constant
- The relocated address of the address constant is the sum of the PLA and the ADDR field specified on the RLD record.


Pass 2

- END: The execution start address is relocated by the PLA
 - The Program Load Address is incremented by the length of the segment and saved in SLENGTH, becoming the PLA for the next segment.
- LDT/E0F record
 - The loader transfers control to the loaded program at the address specified by current contents of the execution, address variable (EXADDR)




Case 2: Multiple Programs in the same Language, Compiled Independently








Case 4: Source Libraries



Case 5: Object Libraries







Final Exam

14/1/2008 וلاثنين 12:45-10:45 Salah Al-Deen