### **NAME**

gmaproto - GMA client/server communication functions

## **SYNOPSIS**

```
(If package installed globally)
package require gmaproto
(Otherwise)
source gmaproto.tcl
::gmaproto::add_image name sizes
::gmaproto::add_obj_attributes id attr values
::gmaproto::adjust_view x y
::gmaproto::allow features
::gmaproto::auth_response challenge → response
::gmaproto::background_redial tries
::qmaproto::chat_message message sender recipients to all to gm
::qmaproto::clear id
::gmaproto::clear_chat silent target
::gmaproto::clear_from server_id
::gmaproto::combat_mode bool
::gmaproto::comment text
::qmaproto::DEBUG msg
::gmaproto::define_dice_presets plist append
::gmaproto::dial host port user pass proxy pport puser ppass client
::gmaproto::filter_dice_presets regex
::gmaproto::from_enum key int \rightarrow value
::gmaproto::GMATypeToObjType gtype \rightarrow otype
::gmaproto::int_bool bool \rightarrow int
::gmaproto::is\_connected \rightarrow bool
::gmaproto::is\_ready \rightarrow bool
::gmaproto::json_bool bool \rightarrow str
::gmaproto::ls type d
::gmaproto::load_from server_id cache_only merge
::gmaproto::mark x y
::gmaproto::new_dict command ?key value? ?key value...? \rightarrow d
::gmaproto::new_id \rightarrow uuid
::gmaproto::ObjTypeToGMAType otype?-protocol? \rightarrow gtype
:: gmaproto::place\_someone\_d d
::gmaproto::polo
::gmaproto::query_dice_presets
::gmaproto::query_image name size
::gmaproto::remove_obj_attributes id attr values
```

```
::gmaproto::redial
::gmaproto::roll_dice spec recipients to_all blind_to_gm
::gmaproto::set_debug cmd
::gmaproto::subscribe msglist
::gmaproto::sync
::gmaproto::sync_chat target
::gmaproto::to_enum key value → int
::gmaproto::toolbar bool
::gmaproto::update_clock abs rel
::gmaproto::update_obj_attributes id kvdict
::gmaproto::update_progress id title value max done → id
::gmaproto::update_status_marker condition shape color description
::gmaproto::write_only main
```

## **DESCRIPTION**

This module provides the functionality for communicating with the server, including low-level communications, legacy protocol translation, and dispatching incoming server commands to the mapper for execution.

::gmaproto::add\_image name sizes

Send image information to the server for the image with the given *name* (the messsage ID as referenced in map files and in the client). The *sizes* parameter is a Tcl list of dictionaries describing each instance of each zoomed size of that image as documented in mapper(6). This sends the AI protocol command.

 $\verb|::gmaproto::add_obj_attributes| \textit{id attr values} \\$ 

Tell the other clients to adjust the object with the given *id* by adding each string in the Tcl list *values* to their field named *attr*, which must be a field that accepts a list of strings. This sends the OA+ protocol command.

::gmaproto::adjust\_view x y

Tell other clients to ajust their scrollbars so that the distance scrolled is x to the right and y down, where x and y are values between 0 and 1, which indicate the proportion of full range to move the scrollbars. This sends the AV protocol command.

::qmaproto::allow features

Tell the server that you will allow the use of the listed optional *features* (a Tcl list of feature name strings). This sends the ALLOW protocol command.

::gmaproto::auth\_response *challenge* 

You should not normally need to invoke this procedure directly. Given a binary challenge value from the server, this calculates and returns the binary response needed to authenticate to the server, using the password previously given to ::gmaproto::dial. If the username given is still empty, it also attempts to find the local username and sets the configured username to that value.

::gmaproto::background\_redial tries

You should not normally need to invoke this procedure directly. Attempts to reconnect to the server. If this fails, it schedules itself to run again in a few seconds, with the *tries* value incremented.

::gmaproto::chat\_message message sender recipients to\_all to\_gm

Sends a chat *message* to other clients. Clients should not set the *sender* value. If *to\_gm* is true, the message will be sent only to the GM; otherwise, if *to\_all* is true, the message is sent to all clients; otherwise it is sent to the list of usernames in *recipients*. This sends the To protocol

command.

::gmaproto::clear id

Tells other clients to remove the object identified by id as documented in mapper(6). This sends the CLR protocol command.

::gmaproto::clear\_chat silent target

Tells others to clear chat messages specified by the *target* value. If *silent* is true, ask them not to advertise that this was done. This sends the CC protocol command.

::gmaproto::clear\_from server\_id

Instruct other clients to remove all elements from the map file *server\_id*. This sends the CLR@ protocol command.

::gmaproto::combat\_mode bool

Tell others to set combat mode if *bool* is true, otherwise unset it. This sends the CO protocol command.

::gmaproto::comment text

Send *text* as a comment to the server, which is probably a pointless thing to do. This sends the // protocol command.

::gmaproto::DEBUG msg

Send *msg* to the callback function configured via ::gmaproto::set\_debug.

::gmaproto::define\_dice\_presets plist append

Send a new set of die-roll presets to the server for storage. The *plist* parameter is a Tcl list of dictionaries describing each preset as per mapper(6). If *append* is true, the elements in *plist* are added to the ones already on the server; otherwise they replace the server's current set. This sends the DD or DD+ protocol command.

::gmaproto::dial host port user password proxy pport puser ppass client

This is the initial command you should call to establish a connection to the server on *host* at the TCP *port* specified. Once the connection is established, the client will authenticate as the given *user* and *password* and will note that the connecting client is called *client*. If a SOCKS proxy is needed, *proxy*, *pport*, *puser*, and *ppass* give the proxy host, port, and login credentials to use.

If the connection is lost, this package will automatically try to reconnect using the same parameters.

As incoming commands are received from the server, they are dispatched back to the application by calling a procedure named

```
:: DoCommand cmd d
```

where cmd is the server's command name. The single parameter d is a dictionary holding the command's parameter set. For example, if the server sent an AV command, then ::DoCommandAV would be called in the application.

If that failed, either because the command does not exist in the application or because it threw an error, then an error-handling function is called:

```
::DoCommandError cmd d err
```

where cmd is the original command name, d is the parameter dictionary, and err is the error message received.

```
::gmaproto::filter_dice_presets regex
```

Asks the server to remove all stored die-roll presets whose names match the regular expression *regex*. This sends the DD/ protocol command.

```
::gmaproto::from_enum key int
```

Converts the integer value *int* into the enum string corresponding to that value for the enumerated type *key* (Dash, Join, MoveMode, etc.).

::gmaproto::GMATypeToObjType gtype

Converts the object type name as used by the server to the corresponding name used inside the mapper application, and returns it.

::gmaproto::int\_bool bool

Returns 1 if bool is true, otherwise returns 0.

::qmaproto::is\_connected

Returns true if the client has an active network connection to the server.

::qmaproto::is\_ready

Returns true if the client has an active network connection and has successfully completed the initial negotion and authentication with the server.

::gmaproto::json\_bool bool

Returns the boolean value passed as the string true or false, suitable for JSON strings.

::qmaproto::ls type d

Sends a map object to peer clients. Type is the GMA protocol type name (ARC, LINE, etc.) and d is an appropriate dictionary value for that type. This sends the LS-ARC, LS-LINE, etc. protocol commands.

::gmaproto::load\_from server\_id cache\_only merge

Tells other clients to load elements from the given server map file called *server\_id*. If *merge* is true, the contents of that file should be merged with the existing map contents instead of replacing them. If *cache\_only* is true, tell the clients to cache a copy of the file without actually loading anything from it. This sends the L protocol command.

::gmaproto::mark x y

Tell other clients to visually mark the location with the given map coordinates. This sends the MARK protocol command.

::gmaproto::new\_dict command ?key value? ?key value...?

Construct a new dictionary suitable to hold the parameters for the given *command*, with all fields defaulted. Additionally, any *key* and *value* pairs specified set the given fields in the new dictionary. The dictionary value is returned.

::gmaproto::new\_id

Generate a new unique ID suitable for use as object identifiers, and returns it.

::gmaproto::ObjTypeToGMAType otype ?-protocol?

Computes and returns the server type name corresponding to the mapper internal type name *otype*. If the -protocol option is given, the protocol command name (with LS- prefix) is returned instead of the base type name.

 $::gmaproto::place\_someone\_d d$ 

Tells the other clients to place a creature token on the map as described. If another creature is already present with the same name, it is replaced by the new one. This sends the PS protocol command. The parameter is a dictionary holding a creature object.

::gmaproto::polo

Sends a "still alive" response to the server, typically in response to receiving a MARCO command. This sends the POLO server command.

::gmaproto::query\_dice\_presets

Asks the server to send all of the stored presets. This sends the DR protocol command.

::gmaproto::query\_image name size

Asks the server and other clients if any of them have heard of the given image *name* at the requested zoom *size*. This sends the AI? protocol command.

### ::gmaproto::query\_peers

Requests that the server send the list of currently-connected clients. This sends the /CONN protocol command.

### ::gmaproto::redial

Try to reconnect using the parameters given with the initial ::gmaproto::dial command. You don't normally need to call this directly.

### ::gmaproto::roll\_dice spec recipients to\_all blind\_to\_gm

Ask the server to roll the dice indicated by *spec*. If *blind\_to\_gm* is true, the results are visible only to the GM; otherwise, if *to\_all* is true, the results are sent to everyone; otherwise only to the list of user names in *recipients*. This sends the D protocol command.

#### ::gmaproto::set\_debug cmd

Protocol debugging statements will be sent by calling *cmd* with a string parameter.

## ::gmaproto::subscribe *msglist*

Tell the server that we're only interested in receiving the command names listed in *msglist*. If *msglist* is empty, then tell the server we accept all messages. This sends the ACCEPT protocol command.

#### ::gmaproto::sync

Request that the server send a set of commands which will bring the client up to date with the current game state. This sends the SYNC protocol command.

### ::gmaproto::sync\_chat target

Request that the server send some or all (per the *target*) value of the historical chat messages to the client. This sends the SYNC-CHAT protocol command.

#### ::qmaproto::to\_enum key value

Converts and returns the integer associated with the *value* in the enumerated type *key*.

#### ::gmaproto::toolbar bool

Tells other clients to turn on their toolbars if *bool* is true; otherwise turn them off. This sends the TB protocol command.

## ::gmaproto::update\_clock absolute relative

Updates the game clock to the given *absolute* and *relative* time values. This sends the CS protocol command.

# ::gmaproto::update\_obj\_attributes id kvdict

Instructs the other clients to update the state of the object with the given *id* by setting each of the objects fields named as keys in *kvdict* with their corresponding values. This sends the OA protocol command.

## ::gmaproto::update\_progress id title value max done

Instructs peers to display a progress meter with the given *id* (creating a new one if that is not an existing progress bar *id*). If *done* is true, this is notice that the progress bar is no longer needed.

If id is specified as \*, then a new ID will be generated.

If max is zero or \*, then we are saying we don't know what the maximum value will be and the client should give a progress bar that shows activity but not specific progress toward a known goal.

This sends the PROGRESS potocol command.

The progress indicator's id is returned.

# ::gmaproto::update\_status\_marker condition shape color description

Tells the server to define a new status marker for *condition* with the given *shape*, *color*, and *description*. This sends the DSM protocol command.

::gmaproto::write\_only main

Tells the server that this client no longer wishes to receive any messages from it. If *main* is true, the client is also signalling that it wishes to be the primary client in the conversation.

### **EXTERNAL HOOKS**

This package will invoke the following procedures in the main application to carry out its operations, typically in response to having received a server command for the client to do something.

::DEBUG level message

This is called to report a diagnostic condition or provide some level of verbose detail about the operation of the communications package, except for the debugging of the actual protocol interactions, which is handled by the callback registered via ::gmaproto::set\_debug.

::report\_progress message

Reports user-friendly progress information.

::say message

Displays an urgent message, probably in a modal dialog or alert box.

::DoCommand*cmd params* 

Handles the receipt of the server command *cmd* by the client. The *params* parameter is a dictionary of values as sent by the server.

::DoCommandError cmd params err

Handles any error encountered when trying to execute a :: DoCommandcmd call.

### **DIAGNOSTICS**

An exception is thrown if a serious error is encountered.

Messages are printed to standard output to indicate progress or provide debugging information.

The registered debugging hook is also used to print debugging and diagnostic messages.

#### SEE ALSO

## **AUTHOR**

Steve Willoughby / steve@madscience.zone.

#### **HISTORY**

This document describes version 1.0 of the qmaproto package, released in December 2022.

### **COPYRIGHT**

Part of the GMA software suite, copyright © 1992–2025 by Steven L. Willoughby, Aloha, Oregon, USA. All Rights Reserved. Distributed under BSD-3-Clause License.