


# Interrupts, Exceptions, System Calls and Context Switching

Chester Rebeiro

IIT Madras

# OS and Events


- OS is event driven
  - i.e. executes only when there is an interrupt, trap, or system call



# Why event driven design?

- OS cannot **trust** user processes
  - User processes may be buggy or malicious
  - User process crash should not affect OS
- OS needs to guarantee **fairness** to all user processes
  - One process cannot ‘hog’ CPU time
  - Timer interrupts

# Event Types




# Events

- **Interrupts** : raised by hardware or programs to get OS attention
  - Types
    - **Hardware interrupts**: raised by hardware devices
    - **Software Interrupts**: raised by user programs (such as ecall instruction)
- **Exceptions** : due to illegal operations

# Why Hardware Interrupts?

- Several devices connected to the CPU
  - eg. Keyboards, mouse, network card, etc.
- These devices occasionally need to be serviced by the CPU
  - eg. Inform CPU that a key has been pressed
- These events are asynchronous i.e. we cannot predict when they will happen.

# Event view of CPU



# Interrupts in RISC V

- Different interrupts for different modes
- Enabling and Disabling Interrupts **globally**
  - MIE bit in mstatus register for enabling machine mode interrupts
  - SIE bit in the mstatus register for enabling supervisor mode interrupts
- Previous Mode before the interrupt
  - MPP (2 bits) and SPP (1 bit)

User Mode

Supervisor Mode

Machine Mode

mstatus

MXLEN-1	MXLEN-2	38	37	36	35	34	33	32	31	23	22	21	20	19	18		
SD	WPRI		MBE	SBE	SXL[1:0]	UXL[1:0]		WPRI	TSR	TW	TVM	TVM	MXR	SUM			
1	MXLEN-39	1	1	2	2	9	1	1	1	1	1	1	1	1	1		
17	16	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
MPRV	XS[1:0]	FS[1:0]	MPP[1:0]	WPRI	SPP	MPIE	UBE	SPIE	WPRI	MIE	WPRI	SIE	WPRI				
1	2	2	2	2	2	1	1	1	1	1	1	1	1	1	1	1	1

# Interrupts in RISC V

- Interrupts Pending and Interrupt Enable

15	12	11	10	9	8	7	6	5	4	3	2	1	0
0	MEIP	0	SEIP	0	MTIP	0	STIP	0	MSIP	0	SSIP	0	0
4	1	1	1	1	1	1	1	1	1	1	1	1	1

Figure 3.14: Standard portion (bits 15:0) of `mip`.

15	12	11	10	9	8	7	6	5	4	3	2	1	0
0	MEIE	0	SEIE	0	MTIE	0	STIE	0	MSIE	0	SSIE	0	0
4	1	1	1	1	1	1	1	1	1	1	1	1	1

Figure 3.15: Standard portion (bits 15:0) of `mie`.

## Machine mode visible

15	10	9	8	6	5	4	2	1	0
0	SEIP	0	0	STIP	0	0	SSIP	0	0
6	1	3		1	3	1	1	1	1

Figure 4.6: Standard portion (bits 15:0) of `sip`.

15	10	9	8	6	5	4	2	1	0
0	SEIE	0	0	STIE	0	0	SSIE	0	0
6	1	3		1	3	1	1	1	1


## Supervisor mode visible

`mip.ssip` : supervisor software interrupt pending  
`mip.msip` : machine mode software interrupt pending  
`mie.ssie` : supervisor software interrupt enable  
`mip.msie` : machine mode software interrupt enable

`mip.stip` : supervisor timer interrupt pending  
`mip.mtip` : machine mode timer interrupt pending  
`mie.stie` : supervisor timer interrupt enable  
`mip.mtie` : machine mode timer interrupt enable


`mip.seip` : supervisor external interrupt pending  
`mip.meip` : machine mode external interrupt pending  
`mie.seie` : supervisor external interrupt enable  
`mip.meie` : machine mode external interrupt enable

# RISC V Exception & Interrupt Handling




# Interrupt Vector Handlers in xv6

- kernelvec (kernelvec.S)
  - Used to handle interrupts when in kernel address space
- uservect (trampoline.S)
  - Used to handle interrupts when in user address space
  - (recollect) uservect is mapped to the highest page in each user process




stvec contains → uservect → kernelvec → uservect


# Interrupt Handlers in xv6



# Interrupt Handlers in xv6



# scause register: what caused the interrupt?



scause register

Figure 4.11: Supervisor Cause register **scause**.

Interrupt	Exception Code	Description
1	0	<i>Reserved</i>
1	1	Supervisor software interrupt
1	2–4	<i>Reserved</i>
1	5	Supervisor timer interrupt
1	6–8	<i>Reserved</i>
1	9	Supervisor external interrupt
1	10–15	<i>Reserved</i>
1	$\geq 16$	<i>Designated for platform use</i>
0	0	Instruction address misaligned
0	1	Instruction access fault
0	2	Illegal instruction
0	3	Breakpoint
0	4	Load address misaligned
0	5	Load access fault
0	6	Store/AMO address misaligned
0	7	Store/AMO access fault
0	8	Environment call from U-mode
0	9	Environment call from S-mode
0	10–11	<i>Reserved</i>
0	12	Instruction page fault
0	13	Load page fault
0	14	<i>Reserved</i>
0	15	Store/AMO page fault
0	16–23	<i>Reserved</i>
0	24–31	<i>Designated for custom use</i>
0	32–47	<i>Reserved</i>
0	48–63	<i>Designated for custom use</i>
0	$\geq 64$	<i>Reserved</i>

# Service system calls

## usertrap (trap.c)

```
53 if(r_scause() == 8){  
54     // system call  
55  
56     if(p->killed)  
57         exit(-1);  
58  
59     // sepc points to the ecall instruction,  
60     // but we want to return to the next instruction.  
61     p->trapframe->epc += 4;  
62  
63     // an interrupt will change sstatus &c registers,  
64     // so don't enable until done with those registers.  
65     intr_on();  
66  
67     syscall();
```


## syscall.c

```
132 void  
133 syscall(void)  
134 {  
135     int num;  
136     struct proc *p = myproc();  
137  
138     num = p->trapframe->a7;  
139     if(num > 0 && num < NELEM(syscalls) && syscalls[num]) {  
140         p->trapframe->a0 = syscalls[num]();  
141     } else {  
142         printf("%d %s: unknown sys call %d\n",  
143                 p->pid, p->name, num);  
144         p->trapframe->a0 = -1;  
145     }  
146 }
```

Invoke system call according to syscall number (in a7)

(a0 passed back to user program as system call return)

# External and Timer Interrupts



## trap.c

```
176 int  
177 devintr()  
178 {  
179     uint64 scause = r_scause();  
180  
181     if((scause & 0x8000000000000000L) &&  
182         (scause & 0xff) == 9){  
183         // this is a supervisor external interrupt, via PLIC.  
184  
185         // irq indicates which device interrupted.  
186         int irq = plic_claim();  
187  
188         if(irq == UART0_IRQ){  
189             uartintr();  
190         } else if(irq == VIRTIO0_IRQ){  
191             virtio_disk_intr();  
192         } else if(irq){  
193             printf("unexpected interrupt irq=%d\n", irq);  
194         }  
195  
196         // the PLIC allows each device to raise at most one  
197         // interrupt at a time; tell the PLIC the device is  
198         // now allowed to interrupt again.  
199         if(irq)  
200             plic_complete(irq);  
201  
202         return 1;  
203     } else if(scause == 0x8000000000000001L){  
204         // software interrupt from a machine-mode timer interrupt,  
205         // forwarded by timervec in kernelvec.S.  
206  
207         if(cpuid() == 0){  
208             clockintr();  
209         }  
210  
211         // acknowledge the software interrupt by clearing  
212         // the SSIP bit in sip.  
213         w_sip(r_sip() & ~2);  
214  
215         return 2;  
216     } else {  
217         return 0;  
218     }  
219 }
```

Check if its an interrupt

Check if its an external interrupt

Read more information from  
the PLIC and identify which  
device caused the interrupt.  
Call the corresponding interrupt  
handler

Is it a software interrupt from  
the machine mode


# Identifying External Interrupts

Invoked by usertrap  
and kerneltrap  
functions to identify  
what caused the  
interrupt

# Interrupt Handlers

- Typical Interrupt Handler
  - Save additional CPU context (written in assembly)  
(done by alltraps in xv6)
  - Process interrupt (communicate with I/O devices)
  - Invoke kernel scheduler
  - Restore CPU context and return (written in assembly)

# Interrupt Latency




Interrupt latency can be significant

# Importance of Interrupt Latency

- Real time systems
  - OS should ‘guarantee’ interrupt latency is less than a specified value
- Minimum Interrupt Latency
  - Mostly due to the interrupt controller
- Maximum Interrupt Latency
  - Due to the OS
  - Occurs when interrupt handler cannot be serviced immediately
    - Eg. when OS executing atomic operations, interrupt handler would need to wait till completion of atomic operations.


# Atomic Operations



Value of `x` depends on whether an interrupt occurred or not!

Solution : make the part of code atomic (i.e. disable interrupts while executing this code)

# Nested Interrupts



- Typically interrupts disabled until handler executes
  - This reduces system responsiveness
- To improve responsiveness, enable Interrupts within handlers
  - This often causes nested interrupts
  - Makes system more responsive but difficult to develop and validate
- **Linux Interrupt handler approach:** design interrupt handlers to be small so that nested interrupts are less likely
- RISC V supports 2 levels of interrupts

# Small Interrupt Handlers

- Do as little as possible in the interrupt handler
  - Often just queue a work item or set a flag
- Defer non-critical actions till later

# Top and Bottom Half Technique (Linux)

- **Top half** : do minimum work and return from interrupt handler
  - Saving registers
  - Unmasking other interrupts
  - Restore registers and return to previous context
- **Bottom half** : deferred processing
  - eg. Workqueue
  - Can be interrupted

# Timers in RISC V

- **mtime**
  - 64-bit register that increments at a constant frequency
- **mtimecmp**
  - 64-bit register that is used to compare with mtime.
  - Interrupt occurs if  $\text{mtime} > \text{mtimecmp}$

**Note:** there is no stime and stimecmp, which means supervisor mode cannot configure timers

**Workaround:**

Configure timers to interrupt in machine mode.

In machine mode trigger software interrupt to supervisor mode

# Timers in xv6

## memlayout.h

```
// local interrupt controller, which contains the timer.  
#define CLINT 0x2000000L  
#define CLINT_MTIMECMP(hartid) (CLINT + 0x4000 + 8*(hartid))  
#define CLINT_MTIME (CLINT + 0xBFF8) // cycles since boot.
```

Note: 1 mtime for all cores  
but each core has a different mtimetcmp

# Timers in xv6

start.c (invoked from start from machine mode before switching to supervisor mode)

```
// set up to receive timer interrupts in machine mode,
// which arrive at timervec in kernelvec.S,
// which turns them into software interrupts for
// devintr() in trap.c.
void
timerinit()
{
    // each CPU has a separate source of timer interrupts.
    int id = r_mhartid();

    // ask the CLINT for a timer interrupt.
    int interval = 1000000; // cycles; about 1/10th second in qemu.
    *(uint64*)CLINT_MTIMECMP(id) = *(uint64*)CLINT_MTIME + interval;

    // prepare information in scratch[] for timervec.
    // scratch[0..3] : space for timervec to save registers.
    // scratch[4] : address of CLINT MTIMECMP register.
    // scratch[5] : desired interval (in cycles) between timer interrupts.
    uint64 *scratch = &mscratch0[32 * id];
    scratch[4] = CLINT_MTIMECMP(id);
    scratch[5] = interval;
    w_mscratch((uint64)scratch);

    // set the machine-mode trap handler.
    w_mtvec((uint64)timervec);

    // enable machine-mode interrupts.
    w_mstatus(r_mstatus() | MSTATUS_MIE);

    // enable machine-mode timer interrupts.
    w_mie(r_mie() | MIE_MTIE);
}
```

Each hart configures its mtimecmp to interrupt after 100ms.

Set up timervec as the interrupt handler

Enable machine mode interrupts

Enable timer interrupts

# Timers in xv6

## timervc (in kernelvec.S)

```
93 timervc:  
94     # start.c has set up the memory that mscratch points to:  
95     # scratch[0,8,16] : register save area.  
96     # scratch[32] : address of CLINT's MTIMECMP register.  
97     # scratch[40] : desired interval between interrupts.  
98  
99     csrrw a0, mscratch, a0  
100    sd a1, 0(a0)  
101    sd a2, 8(a0)  
102    sd a3, 16(a0)  
103  
104    # schedule the next timer interrupt  
105    # by adding interval to mtimetcmp.  
106    ld a1, 32(a0) # CLINT_MTIMECMP(hart)  
107    ld a2, 40(a0) # interval  
108    ld a3, 0(a1)  
109    add a3, a3, a2  
110    sd a3, 0(a1)  
111  
112    # raise a supervisor software interrupt.  
113    li a1, 2  
114    csrwr sip, a1  
115  
116    ld a3, 16(a0)  
117    ld a2, 8(a0)  
118    ld a1, 0(a0)  
119    csrrw a0, mscratch, a0  
120  
121    mret
```

1

2

Does two important things:

1. Set the timecmp for the next interrupt
2. Raise the supervisor software interrupt

## trap.c

```
176 int  
177 devintr()  
178 {  
179     uint64 scause = r_scause();  
180  
181     if((scause & 0x8000000000000000L) &&  
182         (scause & 0xff) == 9){  
183         // this is a supervisor external interrupt, via PLIC.  
184  
185         // irq indicates which device interrupted.  
186         int irq = plic_claim();  
187  
188         if(irq == UART0_IRQ){  
189             uartintr();  
190         } else if(irq == VIRTIO0_IRQ){  
191             virtio_disk_intr();  
192         } else if(irq){  
193             printf("unexpected interrupt irq=%d\n", irq);  
194         }  
195  
196         // the PLIC allows each device to raise at most one  
197         // interrupt at a time; tell the PLIC the device is  
198         // now allowed to interrupt again.  
199         if(irq)  
200             plic_complete(irq);  
201  
202         return 1;  
203     } else if(scause == 0x800000000000001L){  
204         // software interrupt from a machine-mode timer interrupt,  
205         // forwarded by timervec in kernelvec.S.  
206  
207         if(cpuid() == 0){  
208             clockintr();  
209         }  
210  
211         // acknowledge the software interrupt by clearing  
212         // the SSIP bit in sip.  
213         w_sip(r_sip() & ~2);  
214  
215         return 2;  
216     } else {  
217         return 0;  
218     }  
219 }
```

Check if its an interrupt

Check if its an external interrupt


Read more information from  
the PLIC and identify which  
device caused the interrupt.  
Call the corresponding interrupt  
handler

Is it a software interrupt from  
the machine mode

# Timer Interrupts


Invoked by usertrap  
and kerneltrap  
functions to identify  
what caused the  
interrupt

# Timer Interrupts




Use function  
`devintr` to identify cause of interrupt

# Timer Interrupts




# Context Switching



## trampoline.S


```
16 uservec:  
17     #  
18     # trap.c sets stvec to point here, so  
19     # traps from user space start here,  
20     # in supervisor mode, but with a  
21     # user page table.  
22     #  
23     # sscratch points to where the process's p->tf is  
24     # mapped into user space, at TRAPFRAME.  
25     #  
26  
27     # swap a0 and sscratch  
28     # so that a0 is TRAPFRAME  
29     csrrw a0, sscratch, a0  
30  
31     # save the user registers in TRAPFRAME  
32     sd ra, 40(a0)  
33     sd sp, 48(a0)  
34     sd gp, 56(a0)  
35     sd tp, 64(a0)  
36     sd t0, 72(a0)  
37     sd t1, 80(a0)  
38     sd t2, 88(a0)  
39     sd s0, 96(a0)  
40     sd s1, 104(a0)  
41     sd a1, 120(a0)  
42     sd a2, 128(a0)  
43     sd a3, 136(a0)  
44     sd a4, 144(a0)  
45     sd a5, 152(a0)  
46     sd a6, 160(a0)  
47     sd a7, 168(a0)  
48     sd s2, 176(a0)  
49     sd s3, 184(a0)  
50     sd s4, 192(a0)  
51     sd s5, 200(a0)  
52     sd s6, 208(a0)  
53     sd s7, 216(a0)  
54     sd s8, 224(a0)  
55     sd s9, 232(a0)
```

# Context Switching



Identify cause of the interrupt. If the interrupt happens to be a timer interrupt invoke yield


# Context Switching



proc.c

```
499 void  
500 yield(void)  
501 {  
502     struct proc *p = myproc();  
503     acquire(&p->lock);  
504     p->state = RUNNABLE;  
505     sched();  
506     release(&p->lock);  
507 }
```

# Context Switching



proc.c

```

478 void
479 sched(void)
480 {
481     int intena;
482     struct proc *p = myproc();
483
484     if(!holding(&p->lock))
485         panic("sched p->lock");
486     if(mycpu()->noff != 1)
487         panic("sched locks");
488     if(p->state == RUNNING)
489         panic("sched running");
490     if(int_get())
491         panic("sched interruptible");
492
493     intena = mycpu()->intena;
494     swtch(&p->context, &mycpu()->scheduler);
495     mycpu()->intena = intena;
496 }
  
```


Process context saved in proc struct;  
 Scheduler context loaded from mycpu()->scheduler  
 On return from swtch, CPU continues executing from the  
 location of the saved scheduler's context

a0: &p->context  
 a1: &mycpu()->scheduler  
 swtch.c

```

8 .globl swtch
9 swtch:
10     sd ra, 0(a0)
11     sd sp, 8(a0)
12     sd s0, 16(a0)
13     sd s1, 24(a0)
14     sd s2, 32(a0)
15     sd s3, 40(a0)
16     sd s4, 48(a0)
17     sd s5, 56(a0)
18     sd s6, 64(a0)
19     sd s7, 72(a0)
20     sd s8, 80(a0)
21     sd s9, 88(a0)
22     sd s10, 96(a0)
23     sd s11, 104(a0)
24
25     ld ra, 0(a1)
26     ld sp, 8(a1)
27     ld s0, 16(a1)
28     ld s1, 24(a1)
29     ld s2, 32(a1)
30     ld s3, 40(a1)
31     ld s4, 48(a1)
32     ld s5, 56(a1)
33     ld s6, 64(a1)
34     ld s7, 72(a1)
35     ld s8, 80(a1)
36     ld s9, 88(a1)
37     ld s10, 96(a1)
38     ld s11, 104(a1)
39
40     ret
  
```

# Context



Context saves registers and permits to continue executing at a later time by reloading the registers.

Process 1 context

Process 2 context

Scheduler context


```
// Saved registers
struct context {
    uint64 ra;
    uint64 sp;

    // callee-saved
    uint64 s0;
    uint64 s1;
    uint64 s2;
    uint64 s3;
    uint64 s4;
    uint64 s5;
    uint64 s6;
    uint64 s7;
    uint64 s8;
    uint64 s9;
    uint64 s10;
    uint64 s11;
};
```

Process 1  
context

proc.c:494

# Context Switching



proc.c

```
478 void
479 sched(void)
480 {
481     int intena;
482     struct proc *p = myproc();
483
484     if(!holding(&p->lock))
485         panic("sched p->lock");
486     if(mycpu()->noff != 1)
487         panic("sched locks");
488     if(p->state == RUNNING)
489         panic("sched running");
490     if(intr_get())
491         panic("sched interruptible");
492
493     intena = mycpu()->intena;
494     swtch(&p->context, &mycpu()->scheduler);
495     mycpu()->intena = intena;
496 }
```


Scheduler  
context

proc.c:460

Assume scheduler context is  
this for now

Process context saved in proc.context (proc.c:494)  
Scheduler context loaded from mycpu()->scheduler  
The current register has context proc.c:494

# Context Switching




proc.c

Process 1 context	proc.c:494
Process 2 context	proc.c:494
Scheduler context	proc.c:460

```

441 void
442 scheduler(void)
443 {
444     struct proc *p;
445     struct cpu *c = mycpu();
446
447     c->proc = 0;
448     for(;;){
449         // Avoid deadlock by ensuring that devices can interrupt.
450         intr_on();
451
452         for(p = proc; p < &proc[NPROC]; p++) {
453             acquire(&p->lock);
454             if(p->state == RUNNABLE) {
455                 // Switch to chosen process. It is the process's job
456                 // to release its lock and then reacquire it
457                 // before jumping back to us.
458                 p->state = RUNNING;
459                 c->proc = p;
460                 swtch(&c->scheduler, &p->context);
461
462                 // Process is done running for now.
463                 // It should have changed its p->state before coming back.
464                 c->proc = 0;
465             }
466             release(&p->lock);
467         }
468     }
469 }
  
```

# Context Switching



proc.c



```

478 void
479 sched(void)
480 {
481     int intena;
482     struct proc *p = myproc();
483
484     if(!holding(&p->lock))
485         panic("sched p->lock");
486     if(mycpu()->noff != 1)
487         panic("sched locks");
488     if(p->state == RUNNING)
489         panic("sched running");
490     if(intr_get())
491         panic("sched interruptible");
492
493     intena = mycpu()->intena;
494     swtch(&p->context, &mycpu()->scheduler);
495     mycpu()->intena = intena;
496 }
  
```

Process 1 context	proc.c:494
Process 2 context	proc.c:494
Scheduler context	proc.c:460


Process 2 continues to execute from its last known context that was at proc.c:494

# Context Switching



Setup trapframe with pointers to kernel satp, kernel stack for process2 and change from kernel address space to process address space



# Context Switching



Process 1 context	proc.c:494
Process 2 context	proc.c:494
Scheduler context	proc.c:460


Executes in trampoline in the process 2's address space.  
Restores the process 2's registers from the trapframe  
and return from interrupt using mret

# Context Switching



Process 2 finally executes from where had previously stopped ☺☺☺

# Multitasking and Context Switch



# Context Switching Overheads

- Direct Factors affecting context switching time
  - Timer Interrupt latency
  - Saving/restoring contexts
  - Finding the next process to execute
- Indirect factors
  - TLB needs to be reloaded
  - Loss of cache locality (therefore more cache misses)
  - Processor pipeline flush

# Context Switch Quantum

- A short quantum
  - Good because, processes need not wait long before they are scheduled in.
  - Bad because, context switch overhead increase
- A long quantum
  - Bad because processes no longer appear to execute concurrently
  - May degrade system performance
- Typically kept between 10ms to 100ms
  - xv6 programs timers to interrupt every 10ms.