Bits, Bytes and Words

Troels Henriksen

Based on slides by Randal E. Bryant and David R. O'Hallaron

Agenda

Representing information as bits

Bit-level manipulation

Integers

Representation: unsigned and signed

Conversion, casting

Expanding, truncating

Representing information as bits

Bit-level manipulation

Integers

Representation: unsigned and signed Conversion, casting Expanding, truncating

Everything is bits


- Each bit is 0 or 1
- By interpreting sets of bits in various ways...
 - ...computers determine what to do.
 - ► ...represent and manipulate numbers, sets, strings—data.

Why bits? Why not decimals? Could it have been some other way?

Everything is bits

Why bits? Electronic implementation.

- Easy to store with bistable elements.
- ► Reliably transmitted on noisy and inaccurate wires via *error correction*.



... But there exist models that do not use bits.

- ► The Setun computer developed in the Soviet Union used ternary *trits*.
- Quantum computers use *qubits* that are in a superposition of the two states.
 - ...error correction is the main challenge here.

Everything is bit vectors

A sequence of bits is called a bit vector

$$\langle x_{w-1},\ldots,x_0\rangle$$

- Number bits from 0 to w-1.
- Bit x_0 typically called *least significant* and x_{w-1} *most significant*.
 - ▶ Due to how bit vectors can be interpreted as binary numbers.
- Bit vectors are not numbers.
 - ► Can represent many kinds of objects.
 - ...but we will mostly focus on number representations.

Binary numbers

Base 2 numbers.

- ► Represent 15213₁₀ as 11101101101101₂
 - ightharpoonup (0011 1011 0110 1101) (with w = 16)
- ► Represent $\frac{15_{10}}{213_{10}}$ as $\frac{1111_2}{11010101_2}$
 - ightharpoonup (0000 0000 0000 1111 0000 0000 1101 0101) (w = 32)
 - ▶ 16 bits for each of numerator and denominator.
 - (This is not how we actually represent rational numbers in a computer-we'll see how next week.)

Machine numbers are of some finite size.

- ightharpoonup If we use w bits to represent a number, only 2^w distinct values are possible.
- How we interpret those bits can vary.
- Why do we use finite-sized numbers?
 - ► A "w-bit machine" handles numbers of up to w bits "natively" (meaning fast).
 - ► A bit vector of some natively supported size is called a word.

Encoding byte values

	Hex	Dec	Bits
Byte = 8 bit word	0	0	⟨0000⟩
•	1	1	$\langle 0001 \rangle$
(Machine-specific, but is true for all	2	2	(0010)
mainstream machines.)	3	3	⟨0011⟩
 256 different values. 	4	4	$\langle 0100 \rangle$
	5	5	$\langle 0101 \rangle$
 Binary 00000000₂ to 11111111₂. 	6	6	$\langle 0110 \rangle$
 Decimal 0₁₀ to 255₁₀. 	7	7	$\langle 0111 \rangle$
 Hexadecimal 00₁₆ to FF₁₆. 	8	8	$\langle 1000 \rangle$
10 10	9	9	$\langle 1001 \rangle$
► Base 16 number representation.	Α	10	$\langle 1010 \rangle$
► Uses characters 0−9 and A−F.	В	11	$\langle 1011 \rangle$
► In C we write FA1D37B ₁₆ as	C	12	(1100)
• 0xFA1D37B	D	13	(1101)
0xfa1d37b (case does not matter)	E	14	$\langle 1110 \rangle$
	F	15	$\langle 1111 \rangle$

Let's play a game

http://topps.diku.dk/compsys/integers.html

Example data representations

C data type	Typical 16-bit	Typical 32-bit	Typical 64-bit	x86-64
char	1	1	1	1
short	1	2	2	2
int	2	4	4	4
long	4	4	8	8
int32_t	4	4	4	4
int64_t	8	8	8	8
float	4	4	4	4
double	8	8	8	8
pointer	2	4	8	8

Representing information as bits

Bit-level manipulation

Integers


Representation: unsigned and signed Conversion, casting

Expanding, truncating

Boolean algebra

Developed by George Boole in the 19th century

- Algebraic representation of logic ("truth values").
- Encode *true* as 1 and *false* as 0.



■ These operations can be implemented with tiny electronic *gates*.

Boolean algebra on bit vectors

• The truth tables generalise to bit vectors, applied elementwise.

- This is the form they take when available in programming languages such as C.
- ...although C uses different symbols.

Bit-level operations in C

Operators & (\land), | (\lor), $^{\land}$ (\oplus), $^{\sim}$ (\neg) available in C.

- Apply to any integral type.
 - ► E.g. long, int, short, char...
- Interpret operands as bit vectors.
- Applied element-wise.

Examples

- $\sim 0 \times 41 = 0 \times BE$
 - $ightharpoonup \neg \langle 01000001 \rangle = \langle 101111110 \rangle$
- $\sim 0 \times 00 = 0 \times FF$
 - ightharpoonup $\langle 000000000 \rangle = \langle 1111111111 \rangle$
- -0x69 & 0x55 = 0x41
 - ightharpoonup $\langle 01101001 \rangle \wedge \langle 01010101 \rangle = \langle 01000001 \rangle$
- -0x69 & 0x55 = 0x7D
 - $\blacktriangleright \ \langle 01101001 \rangle \land \langle 01010101 \rangle = \langle 01111101 \rangle$

Contrast: logical operators in C

The logical operators interpret numbers as *single boolean values*, not as bit vectors!

- **&** & & , | | , !
 - ► View 0 as false.
 - Anything nonzero as true.
 - ► Always produce 0 or 1.
 - ► Short circuiting: $1 \mid \mid (0/0)$ is safe.

Examples

- \triangleright !0x41 = 0x00
- \triangleright !0x00 = 0x01
- \triangleright !!0x41 = 0x01
- \triangleright 0x69 && 0x55 = 0x01
- \triangleright 0x69 || 0x55 = 0x01
- Do not confuse the logical and bitwise operators!

Shift operations

Left shift x << y</p>

- ► Shift bit-vector x left by y positions.
 - ► Throws away excess bits on the left.
 - Fills with zeroes on right.

Right shift x >> y

- ► Shift bit-vector x right by y positions.
 - ► Throws away excess bits on the left.
- ► Logical shift: Fill with 0s on left.
- Arithmetic shift: Replicate most significant bit on left.

Undefined behaviour in C

Shifting a negative amount or by the vector size or more.

X	$\langle 01100010 \rangle$
x < < 3	(00010000)

- x << 3 $\langle 00010000 \rangle$ x >> 2 $\langle 00011000 \rangle$
- $x >> a 2 \langle 00011000 \rangle$

- $\frac{x}{x << 3} \quad \langle 10100010 \rangle$
- x >> 2 $\langle 00101000 \rangle$
- $x>>^a 2 \quad \langle 11101000 \rangle$

Representing information as bits

Bit-level manipulation

Integers

Representation: unsigned and signed

Conversion, casting Expanding, truncating

Encoding integers

Suppose x_i is the *i*th bit of a *w*-bit word (with x_0 being the least significant bit).

Unsigned

Two's complement (AKA *signed*)

	Decimal	Hex	Bits
Х	15213	3 B 6 D	〈0011 1011 0110 1101〉
У	-15213	C 4 9 3	〈1100 0100 1001 0011〉

Sign bit

- For 2's complement, most significant bit (x_{w-1}) indicates sign.
 - ▶ 0 for non-negative.
 - ► 1 for negative.

Two's complement encoding example

```
int16_t x = 15213; // 0011 1011 0110 1101 int16_t y = -15213; // 1100 0100 1001 0011
```

Weight	1	.5213		-15213
1	1	1	1	1
2	0	0	1	2
4	1	4	0	0
8	1	8	0	0
16	0	0	1	16
32	1	32	0	0
64	1	64	0	0
128	0	0	1	128
256	1	256	0	0
512	1	512	0	0
1024	0	0	1	1024
2048	1	2047	0	0
4096	1	4096	0	0
8192	1	8192	0	0
16384	0	0	1	16384
-32768	0	0	1	-32768
Sum		15213		-15213

Numeric ranges

Unsigned

Two's complement

UMin =

$$0 = 0 \dots 0_2$$
 SMin =
 $-2^{w-1} = 10 \dots 0_2$

 UMax =
 $2^w - 1 = 1 \dots 1_2$
 SMax =
 $2^{w-1} - 1 = 01 \dots 1_2$
 -1
 $= 1 \dots 1_2$

Values for w = 16:

	Decimal	Hex	Bits
UMax	65535	FFFF	$\langle 1111\ 1111\ 1111\ 1111 \rangle$
SMax	32767	7 F F F	〈0111 1111 1111 1111〉
SMin	-32768	8 0 0 0	⟨1000 0000 0000 0000⟩
-1	-1	FFFF	(1111 1111 1111 1111)
0	0	0 0 0 0	⟨0000 0000 0000 0000⟩

Values for different word sizes

	W					
	8	16	32	64		
UMax	255	65,535	4,294,967,295	18,446,744,073,709,551,615		
SMax	127	32,767	2,147,483,647	9,223,372,036,854,775,807		
SMin	-128	-32,768	-2,147,483,648	-9,223,372,036,854,775,808		

Observations

$$\begin{aligned} |\mathsf{SMin}| &= \mathsf{SMax} + 1 \\ |\mathsf{UMax}| &= 2 \cdot \mathsf{SMax} + 1 \end{aligned}$$

Note the asymmetric range.

C Programming

- #include <limits.h>
- Declares constants, e.g:
 - ► ULONG_MAX
 - ► LONG_MAX
 - ► LONG_MIN
- Values are platform-specific.

Unsigned and signed numeric values (here w=4)

X	Bits2N(x)	TC2Int(x)
⟨0000⟩	0	0
⟨0001⟩	1	1
⟨0010⟩	2	2
⟨0011⟩	3	3
⟨0100⟩	4	4
⟨0101⟩	5	5
⟨0110⟩	6	6
$\langle 0111 \rangle$	7	7
⟨1000⟩	8	-8
$\langle 1001 \rangle$	9	-7
$\langle 1010 \rangle$	10	-6
⟨1011⟩	11	-5
$\langle 1100 \rangle$	12	-4
(1101)	13	-3
〈1110 〉	14	-2
$\langle 1111 \rangle$	15	-1

Equivalence

► Same encoding for non-negative values.

Uniqueness

- ► Every bit vector represents distinct integer value.
- ► Each representable integer has unique bit encoding.
- ► The representation is **bijective**.

Can invert mappings

- $N2Bits(x) = Bits2N^{-1}(x)$
 - Bit vector for unsigned integer in range.
- ► Int2TC(x) = TC2Int⁻¹(x)
 - ► Bit vector for Two's Complement integer in range.

Representing information as bits

Bit-level manipulation


Integers

Representation: unsigned and signed

Conversion, casting

Expanding, truncating

Mapping between signed and unsigned




Mapping between unsigned and two's complement numbers: **Keep bit representations and reinterpret.**

Mapping signed ⇔ unsigned

Bits	Signed		Unsigned
⟨0000⟩	0		0
⟨0001⟩	1		1
⟨0010⟩	2		2
⟨0011⟩	3		3
⟨0100⟩	4		4
⟨0101⟩	5		5
⟨0110⟩	6	\longrightarrow T2U \longrightarrow	6
⟨0111⟩	7		7
$\langle 1000 \rangle$	-8	← <u>U2T</u> ←	8
$\langle 1001 \rangle$	-7		9
$\langle 1010 \rangle$	-6		10
$\langle 1011 \rangle$	-5		11
$\langle 1100 \rangle$	-4		12
$\langle 1101 \rangle$	-3		13
$\langle 1110 \rangle$	-2		14
$\langle 1111 \rangle$	-1		15


Relation between signed and unsigned



Conversion (that is, reinterpretation) visualized

Two's complement to unsigned

- Ordering inversion.
- Negative numbers become large positive numbers.



Signed versus unsigned in C

C makes working with this more error-prone than it should be.

Types Constants

- Signedness part of type: unsigned int, int32_t, uint32_t.
- By default are considered signed integers.
- Unsigned with U suffix: 0U, 4294967259U

Casting

Explicit casting between signed and unsigned:

```
int tx, ty;
unsigned int ux, uy;
tx = (int) ux;
uy = (unsigned int) ty;
```

Implicit casting due to assignments and other expressions:

```
tx = ux;

uy = ty;
```

- If there is a mix of unsigned and signed in single expression, *signed* values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for w = 32: SMin = -2, 147, 483, 648, <math>SMax = 2, 147, 483, 647:

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	

- If there is a mix of unsigned and signed in single expression, *signed* values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for w = 32: SMin = -2, 147, 483, 648, <math>SMax = 2, 147, 483, 647:

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned

- If there is a mix of unsigned and signed in single expression, *signed* values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for w = 32: SMin = 2

$$w = 32$$
: $SMin = -2, 147, 483, 648$, $SMax = 2, 147, 483, 647$:

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	

- If there is a mix of unsigned and signed in single expression, *signed* values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for w = 32: SMin = -2, 147, 483, 648, <math>SMax = 2, 147, 483, 647:

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed

Evaluation

- If there is a mix of unsigned and signed in single expression, *signed* values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for w = 32: SMin = -2

w = 32: SMin = -2, 147, 483, 648, SMax = 2, 147, 483, 647:

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	

- If there is a mix of unsigned and signed in single expression, signed values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for W = 32: SMin = -2

$$w = 32$$
: $SMin = -2, 147, 483, 648$, $SMax = 2, 147, 483, 647$:

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned

Evaluation

- If there is a mix of unsigned and signed in single expression, signed values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for

w = 32: SMin = -2, 147, 483, 648, <math>SMax = 2, 147, 483, 647:

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned
2147483647	>	-2147483647-1	

Evaluation

- If there is a mix of unsigned and signed in single expression, signed values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for

w = 32: SMin = -2, 147, 483, 648, SMax = 2, 147, 483, 647:

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned
2147483647	>	-2147483647-1	signed

Evaluation

- If there is a mix of unsigned and signed in single expression, signed values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned
2147483647	>	-2147483647-1	signed
2147483647U	<	-2147483647-1	

Evaluation

- If there is a mix of unsigned and signed in single expression, *signed* values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned
2147483647	>	-2147483647-1	signed
2147483647U	<	-2147483647-1	unsigned

- If there is a mix of unsigned and signed in single expression, *signed* values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for

w = 32: SMin =	-2, 147, 483	3, 648, <i>SMa</i>	x = 2,147	, 483, 647:

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned
2147483647	>	-2147483647-1	signed
2147483647U	<	-2147483647-1	unsigned
-1	>	-2	

- If there is a mix of unsigned and signed in single expression, *signed* values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for

w = 32: SMin =	= -2, 147, 483	5, 648, <i>SM</i>	ax = 2, 14	47, 483,	647:

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned
2147483647	>	-2147483647-1	signed
2147483647U	<	-2147483647-1	unsigned
-1	>	-2	signed

Evaluation

- If there is a mix of unsigned and signed in single expression, *signed* values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned
2147483647	>	-2147483647-1	signed
2147483647U	<	-2147483647-1	unsigned
-1	>	-2	signed
(unsigned int)-1	>	-2	

Evaluation

- If there is a mix of unsigned and signed in single expression, signed values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned
2147483647	>	-2147483647-1	signed
2147483647U	<	-2147483647-1	unsigned
-1	>	-2	signed
(unsigned int)-1	>	-2	unsigned

Evaluation

- If there is a mix of unsigned and signed in single expression, *signed* values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned
2147483647	>	-2147483647-1	signed
2147483647U	<	-2147483647-1	unsigned
-1	>	-2	signed
(unsigned int)-1	>	-2	unsigned
2147483647	<	2147483648U	

Evaluation

- If there is a mix of unsigned and signed in single expression, *signed* values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Examples for

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned
2147483647	>	-2147483647-1	signed
2147483647U	<	-2147483647-1	unsigned
-1	>	-2	signed
(unsigned int)-1	>	-2	unsigned
2147483647	<	2147483648U	unsigned

- If there is a mix of unsigned and signed in single expression, signed values implicitly cast to unsigned.
- Including comparison operations <, >, ==, <=, >=.
- Evamples for

Examples for
w = 32: $SMin = -2, 147, 483, 648, SMax = 2, 147, 483, 647:$

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned
2147483647	>	-2147483647-1	signed
2147483647U	<	-2147483647-1	unsigned
-1	>	-2	signed
(unsigned int)-1	>	-2	unsigned
2147483647	<	2147483648U	unsigned
2147483647	>	(int) 2147483648U	

- If there is a mix of unsigned and signed in single expression, signed values implicitly cast to unsigned.
 - Including comparison operations <, >, ==, <=, >=.
 - Evamples for

Examples for			
w = 32: SMin = 1	-2, 147, 483, 64	8, $SMax = 2, 1$	L47, 483, 647:

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned
2147483647	>	-2147483647-1	signed
2147483647U	<	-2147483647-1	unsigned
-1	>	-2	signed
(unsigned int)-1	>	-2	unsigned
2147483647	<	2147483648U	unsigned
2147483647	>	(int) 2147483648U	signed

- If there is a mix of unsigned and signed in single expression, signed values implicitly cast to unsigned.
 - Including comparison operations <, >, ==, <=, >=.
 - Evamples for

Examples for			
w = 32: SMin = 1	-2, 147, 483, 64	8, $SMax = 2, 1$	L47, 483, 647:

Const LHS	Relation	Const RHS	Evaluation
0	==	0U	unsigned
-1	<	0	signed
-1	>	0U	unsigned
2147483647	>	-2147483647-1	signed
2147483647U	<	-2147483647-1	unsigned
-1	>	-2	signed
(unsigned int)-1	>	-2	unsigned
2147483647	<	2147483648U	unsigned
2147483647	>	(int) 2147483648U	signed

Casting between signed and unsigned: basic rules

- Bit representation is maintained.
- ...but reinterpreted.
- Can have unexpected effects: adding or subtracting 2^w .
- Expression containing signed and unsigned int:
 - ▶ int is cast to unsigned int!
 - ► When can this go bad?

Casting between signed and unsigned: basic rules

- Bit representation is maintained.
- ...but reinterpreted.
- Can have unexpected effects: adding or subtracting 2^w .
- Expression containing signed and unsigned int:
 - ▶ int is cast to unsigned int!
 - ► When can this go bad?

```
for (unsigned int i = n-1; i >= 0; i--) {
   // do something with x[i]
}
```

Casting between signed and unsigned: basic rules

- Bit representation is maintained.
- ...but reinterpreted.
- Can have unexpected effects: adding or subtracting 2^w .
- Expression containing signed and unsigned int:
 - ▶ int is cast to unsigned int!
 - ▶ When can this go bad?

```
for (unsigned int i = n-1; i >= 0; i--) {
   // do something with x[i]
}
```

Advice: Avoid arithmetic on unsigned types—only use them for bit operations.

But: Some C operators (sizeof) and many functions return unsigned types (e.g. size_t). C is always ready to stab you in the back.

Representing information as bits

Bit-level manipulation

Integers

Representation: unsigned and signed Conversion, casting Expanding, truncating

Truncation

Task

- Given k + w-bit signed integer x.
- Convert it to w-bit integer x' with same value i possible.

Approach

- Remove the *k* most significant bits.
- Equivalent to computing $x' = x \mod 2^w$.
- Numerical change if number has no representation in w bits.
- Otherwise safe.

W	X	TC2Int(x)
8	$\langle 11111111 \rangle$	-1
4	$\langle 1111 \rangle$	-1
8	⟨10000000⟩	-128
4	⟨0000⟩	0

Sign extension


Task

- Given *w*-bit signed integer *x*.
- Convert it to w + k-bit integer x' with same value.

Approach

■ Make *k* copies of sign bit (most significant bit):

$$x' = \langle \underbrace{x_{w-1}, \dots, x_{w-1}}_{k \text{ copies of sign bit.}} x_{w-1} \cdots x_0 \rangle$$



Sign extension example

```
short int x = 15213;
int         ix = (int) x;
short int y = -15213;
int         iy = (int) y;
```

	Decimal	Hex	Bits
Х	15213 ₁₀	3B 6D	(0011 1011 0110 1101)
ix	15213 ₁₀	00 00 3B 6D	(0000 0000 0000 0000 0011 1011 0110 1101)
У	-15213_{10}	C4 93	〈1100 0100 1001 0011〉
iy	-15213_{10}	FF FF C4 93	〈1111 1111 1111 1111 1100 0100 1001 0011〉

Summary: basic rules for expanding and truncating

Expanding (e.g. short to int)

- Unsigned: zeros added.
- Signed: sign extension.
- Both yield expected result.

Truncating (e.g. unsigned int to unsigned short)

- Bits are truncated.
- Result reinterpreted.
- Unsigned: modulo operation.
- Signed: similar to a modulo operation.
- For small numbers yield expected behaviour.