Medium Access Control: Stochastic Methods - CSMA

In this lesson, we'll study the carrier sense multiple access protocol.

We'll cover the following

- ^
- Carrier Sense Multiple Access (CSMA)
 - Why CSMA?
 - How It Works
 - Pseudocode
 - Non-persistent CSMA
 - Performance of CSMA Variants
- Quick Quiz!

Carrier Sense Multiple Access (CSMA)

Why CSMA?

- ALOHA and slotted ALOHA can easily be implemented, but using them in anything but a lightly loaded network will be extremely inefficient.

 Designing a network for a very low utilization is possible, but it clearly increases the cost of the network.
- To overcome the problems of ALOHA, many Medium Access Control mechanisms have been proposed which **improve channel utilization**.
- Carrier Sense Multiple Access (CSMA) is one of these and is a significant improvement compared to ALOHA.

How It Works

CSMA requires all nodes to listen to the transmission channel to verify that it's free before transmitting a frame. When a node senses the channel to be busy, it defers its transmission until the channel becomes free again.

Pseudocode :

The pseudocode below provides a more detailed description of the operation of CSMA.

```
# persistent CSMA
N=1
while N <= max:
wait(channel_becomes_free)
send(frame)
wait(ack or timeout)
if ack:
break # transmission was successful
else:
# timeout
N=N+1
# end of while loop
# Too many transmission attempts</pre>
```

Pseudocode: operation of CSMA terminal

The above pseudocode is often called **persistent CSMA** as the terminal will **continuously listen** to the channel and transmit its frame as soon as the channel becomes free.

Non-persistent CSMA

Another important variant of CSMA is the **non-persistent CSMA**. The main difference between persistent and non-persistent CSMA described in the pseudocode below is that a non-persistent CSMA node **does not continuously listen to the channel** to determine when it becomes free. When a non-persistent **CSMA terminal senses the transmission channel to be busy, it waits for a random time before sensing the channel again**. This improves channel utilization compared to persistent CSMA. With persistent CSMA, when two terminals sense the channel to be busy, they will both transmit (and thus cause a collision) as soon as the channel becomes free.

However, the higher channel utilization achieved by non-persistent CSMA comes at the expense of **slightly higher waiting time** in the terminals when the network is lightly loaded.

```
N=1
while N <= max:
  listen(channel)

if free(channel):
  send(frame)
  wait(ack or timeout)
  if received(ack):
    break # transmission was successful
  else:
    # timeout
    N=N+1
  else:
    wait(random_time)
  # end of while loop
# Too many transmission attempts</pre>
```

Performance of CSMA Variants

Kleinrock and Tobagi analyzed the performance of several CSMA variants in detail. Under some assumptions about the transmission channel and the traffic, here's a table of the channel utilization of each protocol we've looked at so far.

Protocol	Channel Utilization
ALOHA	18.4%
Slotted ALOHA	36.6%
Persistent CSMA	52.9%
non-persistent CSMA	81.5%

Quick Quiz!



What's the difference between persistent and non-persistent CSMA?



A) Persistent CSMA constantly monitors the channel to

	determine when it is free, whereas non-persistent CSMA checks the channel at random intervals.	
(B)	Non-persistent CSMA constantly monitors the channel to determine when it's free, whereas persistent CSMA checks the channel at random intervals.	
○ C)	Persistent CSMA doesn't monitor the channel to determine when it's free whereas non-persistent CSMA checks the channel at random intervals.	
COMPLETED	1 of 2 >	

In the next lesson, we'll look at an incredibly popular variant of the carrier sense multiple access protocol.