CSCI3150 Introduction to Operating Systems


Lecture 5: Synchronization 1: Critical Region and Lock

Hong Xu

https://github.com/henryhxu/CSCI3150

Synchronization: why?

 A running computer has multiple processes; each process may have multiple threads



Kernel space

- Threads access the shared data!
 - Need proper sequencing
- Analogy: two people talking at the same time

A simple game

- Two volunteers to play two threads
 - Producer: produce 1 cookie per iteration
 - Step1: increment the counter on the board
 - Step2: put one cookie on the table
 - Consumer:
 - Step1: read out the counter LOUD
 - Step2a: if the counter is zero, go back to step1
 - Step2b: if the counter is nonzero, take a cookie from the table
 - Step 3: decrement counter on the board
 - Rule: only one should "operate" at any time
- You are the OS, decide when to context switch
 - Can you get them into "trouble" before cookies run out?

A simple game (cont.)

- Producer: produce 1 cookie per iteration
 - Step1: increment the counter on the board
 - Step2: put one cookie on the table

Switch to consumer, what will happen?

- Consumer:
 - Step1: read out the counter LOUD
 - Step2a: if the counter is zero, go back to step1
 - Step2b: if the counter is nonzero, take a cookie from the table
 - Step 3: decrement counter on the board

Switch to producer, what will happen?


Data races

- Why are we having this problem?
- Reason:
 - concurrency
 - data sharing
- What are shared in this game?
 - Share the counter
 - Share the cookie
- A race occurs when correctness of the program depends on one threa d reaching point x before another thread reaches point y

Shared Resources

- The problem is that two concurrent threads (or processes) access shared resources without synchronization (i.e. coordination)
 - Known as a race condition (memorize this)
- We need mechanisms to control access to shared resources in face of concurrency
 - So we can reason about how the program will operate
- Shared data structures
 - Buffers, queues, lists, hash tables, etc.

When are resources shared?



When are resources shared?

- Local variables are not shared (private)
 - Live on the stack
 - Each thread has its own stack
 - Never pass/share/store a pointer to a local variable on the stack for thread T1 to another thread T2
- Global variables and static objects are shared
 - Stored in the data segment, accessible by any thread
- Dynamic objects and other heap objects are shared
 - Allocated from heap with malloc/free or new/delete

A Classic Example

Suppose we have to implement a function to handle withdrawals from a bank account:

```
withdraw (account, amount) {
   balance = get_balance(account);
   balance = balance - amount;
   put_balance(account, balance);
   return amount;
}
```

- Now suppose that you and your significant other share a bank account with a balance of \$1000.
- Then you <u>each</u> go to separate ATM machines and simultaneously withdraw \$100 from the account.

Example Continued

- We'll represent the situation by creating a separate thread for each person to do the withdrawals
- These threads run on the same bank server:

```
withdraw (account, amount) {
   balance = get_balance(account);
   balance = balance - amount;
   put_balance(account, balance);
   return amount;
}
```

```
withdraw (account, amount) {
   balance = get_balance(account);
   balance = balance - amount;
   put_balance(account, balance);
   return amount;
}
```

- What's the problem with this implementation?
 - Think about possible schedules of these two threads

Interleaved Schedules

Execution of the two threads can be interleaved:

```
balance = get_balance(account);
balance = balance - amount;

balance = get_balance(account);
balance = get_balance(account);
balance = balance - amount;
balance = balance - amount;
put_balance(account, balance);
Context switch
put_balance(account, balance);
```

- What is the balance of the account now?
- Is the bank happy with our implementation?
 - What if this is not withdraw, but deposit?

How Interleaved Can It Get?

- We'll assume that the only atomic operations are reads and writes of words
 - Some architectures don't even give you that!
- We'll assume that a context switch can occur at any time
- We'll assume that you can delay a thread as long as you like, provided that it's not delayed forever

```
..... get_balance(account);
balance = get_balance(account);
balance = ....
balance = balance - amount;
balance = balance - amount;
put_balance(account, balance);
put_balance(account, balance);
```

Mutual Exclusion

- We want to use mutual exclusion to synchronize access to shared resources
 - This allows us to have larger atomic code blocks
- Code that uses mutual exclusion to synchronize its execution is called a critical region, or critical section
 - Only one thread at a time can execute in the critical region
 - All other threads are forced to wait on entry
 - When a thread leaves a critical region, another can enter
 - Example: sharing your bathroom with roommates

Critical Region


```
Process {
    while (true) {
        ENTER CRITICAL SECTION
        Access shared variables; // Critical Section;
        LEAVE CRITICAL SECTION
        Do other work
    }
}
```

What requirements would you place on a critical region?

Critical Region Requirements (for thread and process)

- Mutual exclusion (mutex)
 - No other thread can execute in the critical region while a thread is in it
- Progress
 - A thread in the critical region will eventually leave
 - If some thread T is not in the critical region, T cannot prevent another thread S from entering the critical region
- Bounded waiting (no starvation)
 - If thread T is waiting on the critical region, it will not wait indefinitely
- No assumption
 - No assumption may be made about the speed or number of CPUs

Critical Region Illustrated



Mechanisms For Building Critical Regions

- Atomic read/write
 - Cannot be "interrupted" when running -> "All or nothing"
- Locks
 - Primitive, minimal semantics, used to build others
- Semaphores
 - Basic, easy to get the hang of, but hard to program with
- Monitors
 - High-level, requires language support, operations implicit
- Messages
 - Simple model of communication and synchronization
 - Direct application to distributed systems

Critical Region with Atomic Read/Write: First Try

```
while (true) {
  while (true) {
    while (turn != 1);
    critical region
    turn = 2;
    outside of critical region
}
while (true) {
    while (true) {
        while (turn != 2);
        critical region
        turn = 1;
        outside of critical region
    }
}
```

This is called alternation It satisfies mutex:

- If blue is in the critical region, then turn == 1 and if yellow is in the critical region, then turn == 2 (why?)
- $(turn == 1) \equiv (turn != 2)$

It violates progress: the thread could go into an infinite loop outside of the critical section, which will prevent the yellow one from entering.

Easy to use? (what if more than 2 threads? what if we don't know how many threads?)

Locks

- A lock is an object in memory providing two operations
 - acquire(): before entering the critical region
 - release(): after leaving a critical region
- Threads pair the acquire() and release() calls
 - Between acquire()/release(), the thread holds the lock
 - acquire() does not return until any previous holder releases
 - What can happen if the calls are not paired?
- Locks can spin (a spinlock) or block (a mutex)

Using Locks

```
withdraw (account, amount) {
    acquire(lock);
    balance = get_balance(account);
    balance = balance - amount;
    put_balance(account, balance);
    release(lock);
    return amount;
}
```

Critical Region

```
acquire(lock);
balance = get_balance(account);
balance = balance - amount;
acquire(lock);
put_balance(account, balance);
release(lock);
balance = get_balance(account);
balance = balance - amount;
put_balance(account, balance);
release(lock);
```

- What happens when blue tries to acquire the lock?
- Why is the "return" outside the critical region? Is this OK?
- What happens when a third thread calls acquire?

Implementing Locks (1)

How do we implement locks? Here is one attempt:

```
struct lock {
   int held = 0;
}

void acquire (lock) {
   while (lock->held);
   lock->held = 1;
}

void release (lock) {
   lock->held = 0;
}
```

- This is called a spinlock because a thread spins waiting for the lock to be released
 - Does this work?

Implementing Locks (2)

No! Two independent threads may both notice that a lock has been released and thereby acquire it.

```
struct lock {
   int held = 0;
void acquire (lock) {
   while (lock->held);
   lock->held = 1;
void release (lock) {
   lock->held = 0;
```

A context switch can occur here, causing a race condition

Implementing Locks (3)

- The problem is that the implementation of locks has critical sections,
 too
 - How do we stop the recursion?
- The implementation of acquire/release must be atomic
 - "All or nothing"
- How do we make them atomic?
- Need help from <u>hardware</u>
 - Atomic instructions (e.g., test-and-set)
 - Disable/enable interrupts (prevents context switches)

Atomic Instructions: Test-And-Set

- The semantics of test-and-set are:
 - Record the old value
 - Set the value to TRUE
 - Return the old value
- Hardware executes it atomically!
- When executing test-and-set on "flag"
 - What is the value of flag afterwards if it was initially False?
 - What is the return result if flag was initially False?

```
bool test_and_set (bool *flag) {
   bool old = *flag;
   *flag = True;
   return old;
}
```

Using Test-And-Set

Here is our lock implementation with test-and-set:

```
struct lock {
   int held = 0;
}
void acquire (lock) {
   while (test-and-set(&lock->held));
}
void release (lock) {
   lock->held = 0;
}
```

- When will the while return? What is the value of held?
- Does it work? What about multiprocessors?

Problems with Spinlocks

- The problem with spinlocks is that they are wasteful
 - If a thread is spinning on a lock, then the thread holding the lock cannot make progress
- Solution 1:
 - If cannot get the lock, call thread_yield to give up the CPU
- Solution 2: sleep and wakeup
 - When blocked, go to sleep
 - Wakeup when it is OK to retry entering the critical region

Disabling Interrupts

Another implementation of acquire/release is to disable interrupts:

```
struct lock {
}

void acquire (lock) {
    disable interrupts,
}

void release (lock) {
    enable interrupts,
}
```

- Note that there is no state associated with the lock
- Can two threads disable interrupts simultaneously?

On Disabling Interrupts

- Disabling interrupts blocks notifications of external events that could trigger a context switch (e.g., timer)
- In a "real" system, this is only available to the kernel
 - Why?
- Disabling interrupts is insufficient on a multiprocessor
 - Back to atomic instructions

Critical regions without hardware support?

- So far, we have seen how to implement critical regions (lock) with hardware support
 - Atomic instruction
 - Disabling interrupts
- Can we implement lock without HW support?
 - Software only solution
- Yes, but...
 - Complicated (easy to make mistake)
 - Poor performance
 - Production OSes use hardware support

Mutex without hardware support: Peterson's Algorit hm

```
int turn = 1;
bool try1 = false, try2 = false;
```

```
while (true) {
   try1 = true;
   turn = 2;
   while (try2 && turn != 1);
   critical section
   try1 = false;
   outside of critical section
}
```

```
while (true) {
   try2 = true;
   turn = 1;
   while (try1 && turn != 2);
   critical section
   try2 = false;
   outside of critical section
}
```

Did I execute "turn=2" before thread 2 executed "turn=1"?

Has thread 2 executed "try2=true?". If not, I am safe. If yes, let's see...

- Does it work?
 - Yes!
- Try all possible interleavings

Summarize Where We Are

- Goal: Use mutual exclusion to protect critical sections of code that access shared resources
- Method: Use locks (spinlocks or disable interrupts)
- Problem: Critical sections can be long

Spinlocks:

- Threads waiting to acquire lock spin in test-and-set loop
- Wastes CPU cycles
- Longer the CS, the longer the spin
- Greater the chance for lock holder to be interrupted

acquire(lock)
...

Critical section
...
release(lock)

Disabling Interrupts:

- Should not disable interrupts for long periods of time
- Can miss or delay important events (e.g., timer, I/O)

Takeaway from this lecture

 When you have concurrency and shared resources, protect your critical region with synchronization primitives (e.g., locks, semaphore (next lecture), etc.)