Sediment Organic Matter



<u>How to cite this work:</u> Seagrass Habitats: MarineGEO Protocols. (2019) Tennenbaum Marine Observatories Network, MarineGEO, Smithsonian Institution. DOI:



Introduction

This protocol provides standardized data on sediment bulk density and organic matter content, which is obtained through loss-on-ignition using a combustion furnace. Additional copies of this protocol, field datasheets, data entry templates, instructional videos, literature, and more can be found at: https://marinegeo.github.io/modules/sediment-organic-matter.

Measured Parameters

This protocol quantifies the organic matter content in marine sediments, measured as:

- Bulk density (g/mL) *if possible
- Sediment dry mass (g)
- Sediment ash-free dry mass (g)

Requirements



Methods

Fully review this and any additional protocols necessary for the sampling excursion. Address any questions or concerns to marinegeo@si.edu before beginning this protocol.

Preparation:

- 1. Review the MarineGEO Seagrass Habitats Survey Design for site selection and setup. This protocol assumes n=3 sediment samples taken every 10-12 m along a 50-m transect, replicated along 3 separate transects.
- 2. Label 9 disposable plastic bags with the sampling location, transect, and replicate number using a permanent marker.
- 3. Place a plastic syringe and an internal label with the same metadata written on waterproof paper inside the corresponding plastic bag.
- 4. Fill a cooler with ice immediately before departing for the field.

Fieldwork:

- 1. At each predetermined point along the transect where the sample is to be collected, randomly select an unvegetated patch ~1 m to any side of the transect.
- 2. Remove the plunger from the syringe. Take the open end of the 5-mL syringe and gently insert it into the sediment to a depth of \sim 5 cm. Take care to avoid any structures like rhizomes or woody debris.
- 3. Place the plunger into the syringe to create suction, and then gently extract the syringe from the sediment.
- 4. Place the syringe with the trapped sediment into a plastic bag with an internal label and seal it.
- 5. Repeat steps 1-4 at the next location along the first transect until all 3 replicates are taken.
- 6. Repeat steps 1-5 for the remaining two transects for a total of 9 samples.
- 7. Place all bags on ice in the cooler. Transport cooler with samples back to the lab for processing.

Post-Processing:

Samples are best processed immediately (within 24 hours) of returning from the field. Samples can be stored for longer in the refrigerator, but risks evaporation.

- 1. Print lab data sheets.
- 2. Weigh foil tins and record the weight of the tin directly on the foil using a pen. Tins can be either pre-made or constructed by folding an aluminum foil square over on itself and sealing the sides.
- 3. Select a replicate syringe and push the plunger to discard all but the top 5 cm of sediment.
- 4. Use the plunger to push the sediment plug into a pre-weighed tin.
- 5. Remove all visible fauna, large shells, rhizomes/roots/woody debris from the sample. Work quickly to minimize loss of water.
- 6. Place the labeled foil tins in a drying oven at 60°C and dry to constant weight (usually 1-3 days, depending on the volume of material).
- 7. Weigh the tin and dried sediment plug, and record the dry weight on the lab data sheet
- 8. Combust the samples at 520°C for 5 hours.
- 9. Let the sample cool in the drying oven to avoid taking on any moisture, then weigh the tin and combusted sediment plug, and record the ash-free dry weight on the lab data sheet.

Data Submission

- 1. Scan the completed field data sheets and save both paper and electronic versions locally.
- 2. Enter data into provided data entry template.
- 3. Use our online submission portal to upload the Excel Spreadsheet (coming Fall 2019).
- 4. Contact us if you have any questions: marinegeo@si.edu.