# Sediment Organic Matter



<u>How to cite this work:</u> Seagrass Habitats: MarineGEO Protocols. (2019) Tennenbaum Marine Observatories Network, MarineGEO, Smithsonian Institution. DOI:





# Introduction

This protocol provides standardized data on sediment bulk density and organic matter content, which is obtained through loss-on-ignition using a combustion furnace. Additional copies of this protocol, field datasheets, data entry templates, instructional videos, literature, and more can be found at: <a href="https://marinegeo.github.io/modules/sediment-organic-matter">https://marinegeo.github.io/modules/sediment-organic-matter</a>.

## **Measured Parameters**

This protocol quantifies the organic matter content in marine sediments, measured as:

- Bulk density (g/mL) \*if possible
- Sediment dry mass (g)
- Sediment ash-free dry mass (g)

# Requirements

Personnel: 2 people
Estimated Total Time Per Location ( $n = 3$ transects):
Preparation: 1 person x 1 day Field work: 2 people x 1 day Post processing: 1 person x 3-5 days Data processing: 1 person x 1 day
*Estimated times will vary by site and conditions
Replication: Three (3) 5cm x 5cm sediment cores taken along three (3) transects (total $n = 9$ )
Materials:
Survey Design:  ☐ 1 50-m metric transect tape ☐ Hand-held GPS unit ☐ 2 PVC marker poles (diameter and length as needed)
Fieldwork:  ☐ 9 small plastic bags with external and internal labels (example)  ☐ 9 5-mL plastic syringes with graduations (at least every 1 mL) with the applicator tip cut off (example)  ☐ 1 cooler with ice (optional)
Post-Processing:  ☐ 9 pre-weighed foil tins (example)  ☐ Pencil/pen ☐ Drying oven
□ Combustion furnace



## Methods

Fully review this and any additional protocols necessary for the sampling excursion. Address any questions or concerns to marinegeo@si.edu before beginning this protocol.

#### Preparation:

- 1. Review the MarineGEO Seagrass Habitats Survey Design for site selection and setup. This protocol assumes n=3 sediment samples taken every 10-12 m along a 50-m transect, replicated along 3 separate transects.
- 2. Label 9 disposable plastic bags with the sampling location, transect, and replicate number using a permanent marker.
- 3. Place a plastic syringe and an internal label with the same metadata written on waterproof paper inside the corresponding plastic bag.
- 4. Fill a cooler with ice immediately before departing for the field.

#### Fieldwork:

- 1. At each predetermined point along the transect where the sample is to be collected, randomly select an unvegetated patch  $\sim 1$  m to any side of the transect.
- 2. Remove the plunger from the syringe. Take the open end of the 5-mL syringe and gently insert it into the sediment to a depth of  $\sim$ 5 cm. Take care to avoid any structures like rhizomes or woody debris.
- 3. Place the plunger into the syringe to create suction, and then gently extract the syringe from the sediment.
- 4. Place the syringe with the trapped sediment into a plastic bag with an internal label and seal it.
- 5. Repeat steps 1-4 at the next location along the first transect until all 3 replicates are taken.
- 6. Repeat steps 1-5 for the remaining two transects for a total of 9 samples.
- 7. Place all bags on ice in the cooler. Transport cooler with samples back to the lab for processing.

## Post-Processing:

Samples are best processed immediately (within 24 hours) of returning from the field. Samples can be stored for longer in the refrigerator, but risks evaporation.

- 1. Print lab data sheets.
- 2. Weigh foil tins and record the weight of the tin directly on the foil using a pen. Tins can be either pre-made or constructed by folding an aluminum foil square over on itself and sealing the sides.
- 3. Select a replicate syringe and push the plunger to discard all but the top 5 cm of sediment.
- 4. Use the plunger to push the sediment plug into a pre-weighed tin.
- 5. Remove all visible fauna, large shells, rhizomes/roots/woody debris from the sample. Work quickly to minimize loss of water.
- 6. Place the labeled foil tins in a drying oven at 60°C and dry to constant weight (usually 1-3 days, depending on the volume of material).
- 7. Weigh the tin and dried sediment plug, and record the dry weight on the lab data sheet
- 8. Combust the samples at 520°C for 5 hours.
- 9. Let the sample cool in the drying oven to avoid taking on any moisture, then weigh the tin and combusted sediment plug, and record the ash-free dry weight on the lab data sheet.

#### **Data Submission**

- 1. Scan the completed field data sheets and save both paper and electronic versions locally.
- 2. Enter data into provided data entry template.
- 3. Use our online submission portal to upload the Excel Spreadsheet (coming Fall 2019).
- 4. Contact us if you have any questions: marinegeo@si.edu.