# Control Systems

## Mathias Balling & Mads Thede


Last updated: February 14, 2024

## ${\bf Contents}$

1	Linear Time Invariant Systems		
	1.1	Time-Domain models	2
	1.2	Frequency-Domain models	3
		1.2.1 State space to transfer function	3
		1.2.2 Transfer function to state space	3
		1.2.3 Discrete-time transfer function	3
	1.3	Examples	4
2	Stal	bility and Performance Analysis	5
	2.1	Basic System Classes	5
		2.1.1 First Order Systems	5
		2.1.2 Second Order Systems	5
	2.2	Performance specifications	6
	2.3	Poles and Zeros of Space-State Models	7
	2.4	Stability	8
	2.5	Examples	8
3	Intr	roduction to Control	9
	3.1	Open Loop Control	9
	3.2	Feedback Control	9
	3.3	Steady State Tracking	.0
	3.4	Cascade Control	1
	3.5	DC Motor Dynamics	. 1
	3.6	·	1

## 1 Linear Time Invariant Systems

#### Overview



### 1.1 Time-Domain models

## Linear Map

The map  $f: \mathbb{R}^n \to \mathbb{R}^m$  is said to be linear if for any  $x, y \in \mathbb{R}^n$  and  $\alpha \in \mathbb{R}$ , the following conditions hold

$$f(x+y) = f(x) + f(y)$$
 Super position  $f(ax) = \alpha f(x)$  Homogeneity

The function has to go through (0,0) in 2D for it to be linear due to homogeneity.

#### Time-Invariant System

Let  $\sigma: \mathbb{R} \times \mathbb{R}^m \to \mathbb{R}^p$  define the input-output behavior of a system model  $\Sigma$ . The system  $\Sigma$  is time-invariant if for any input signal  $u: \mathbb{R} \to \mathbb{R}^m$  and any delay  $\tau \in \mathbb{R}$  the following relation holds:

$$y(t - \tau) = \sigma(t, u(t - \tau))$$

for all times  $t \in \mathbb{R}$ , where y denotes the output signal of the system.

The importance is that the system does not change its behavior due to time. This can be seen as a canon firing at 8am it will not fire different compared to if you do the same at 5pm.

Two types of linear time-domain models.

Continous-time state space models (based on differential equations)

$$\dot{x} = Ax + Bu$$

$$y = Cx + Du$$

- $x \in \mathbb{R}^n$  is state. e.g. position or velocity
- $u \in \mathbb{R}^m$  is input
- $y \in \mathbb{R}^p$  is output
- $A \in \mathbb{R}^{n \times n}$  is system matrix

- $B \in \mathbb{R}^{n \times m}$  is input matrix
- $C \in \mathbb{R}^{p \times n}$  is output matrix
- $D \in \mathbb{R}^{p \times m}$  is the direct feedthrough matrix

Discrete-time state space models (based on difference equations)

$$x_{k+1} = \Phi x_k + \Gamma u_k$$

$$y_k = Cx_k + Du_k$$

## 1.2 Frequency-Domain models

Transfer function:

$$G(s) = \frac{Q(s)}{P(s)}$$

where Q(s) and P(s) are polynomials in s.

- The roots of P(s) are called the **poles** of G(s)
- The roots of Q(s) are called the **zeros** of G(s)

### 1.2.1 State space to transfer function

Taking Laplace transforms of the system and assuming  $x_0 = 0$ :

$$\dot{x}(t) = Ax(t) + Bu(t)$$

$$y(t) = Cx(t) + Du(t)$$

yields:

$$sX(s) = AX(s) + BU(s)$$

$$Y(s) = CX(s) + DU(s)$$

Which can be rewritten as (I is the identity matrix):

$$X(s) = (sI - A)^{-1} BU(s)$$

$$Y(s) = \left(C(sI - A)^{-1}B + D\right)U(s)$$

where

$$Y(s) = G(s)U(s)$$

$$G(s) = C (sI - A)^{-1} B + D$$

### 1.2.2 Transfer function to state space

#### 1.2.3 Discrete-time transfer function

Discretization from s-domain to z-domain can be done using:

- Matched z-transform
- Bilinear z-transform
- Impulse invariance z-transform



## 1.3 Examples

## 2 Stability and Performance Analysis

## 2.1 Basic System Classes

## 2.1.1 First Order Systems

State-space representation of first order system:

$$\dot{x} = -\frac{1}{\tau}x + \frac{k}{\tau}u$$

$$u = x$$

A first-order system has one pole and is described by:

$$H(s) = \frac{k}{\tau s + 1}$$

Where k is the DC-gain and  $\tau$  is the time-constant. The system has a pole in  $s=-\frac{1}{\tau}$  i.e., the smaller time-constant, the faster system response.

#### 2.1.2 Second Order Systems

The transfer function of a second-order system is given by:

$$H(s) = \frac{k\omega_n^2}{s^2 + 2\zeta\omega_n s + \omega_n^2}$$

Where  $\omega_n > 0$  is the natural frequency and  $\zeta > 0$  is the damping ratio and k is the gain.

The system has two poles, which are  $s \in \mathbb{C}$  where:


$$s^2 + 2\zeta\omega_n s + \omega_n^2 = 0$$

The values of s is given by:

$$s = -\zeta \omega_n \pm j\omega_n \sqrt{1 - \zeta^2}$$

When  $\zeta = 1$  the system is critically damped and H(s) has a double pole in  $s = -\zeta \omega_n$ , when  $0 < \zeta < 1$  the system is underdamped and has complex poles. When  $\zeta > 1$  the system is overdamped and has real and distinct poles.

$$-\underbrace{\zeta\omega_n}_{\sigma} \pm j\underbrace{\omega_n\sqrt{1-\zeta^2}}_{\omega_d}.$$



Impulse response of a underdamped second-order system:

$$h(t) = k \frac{\omega_n}{\sqrt{1 - \zeta^2}} e^{-\sigma t} sin(\omega_d t) 1(t)$$

The step resonse of a underdamped second-order system:

$$y(t) = k(1 - e^{-\sigma t}(\cos(\omega_d t) + \frac{\sigma}{\omega_d}\sin(\omega_d t)))$$

Impulse response of a critically damped second order system:


$$h(t) = k\omega_n^2 t e^{-\omega_n t}$$

Having a overdamped system with a damping ration that is greater than one leads to a slower impulse response.

The step response of a critically damped second order system:

$$y(t) = k(1 - e^{-\omega_n t} - \omega_n t e^{-\omega_n t})$$

Looking at the bode plot of a second-order system depends on the damping ratio. For every pole the magnitude of the bode plot decreases by 20dB/decade. And the phase of the bode plot decreases by 90 degrees for every pole.



### 2.2 Performance specifications

Three different performance measurements of dynamical systems are:

- 1. The rise time  $t_r$  (stigetid)
- 2. The settling time  $t_s$  (indsvingingstid)
- 3. The overshoot  $M_p$  (oversying)

The rise time is the time it takes for the system to go from 10% to 90% of the final value. The settling time is the time it takes for the system to reach and stay within a certain % of the final value. The overshoot is the maximum percentage that the system goes over the final value.



The peak time is denoted  $t_p$  which is the time where the signal reaches its maximum value.

For a second-order system the rise time can be approximated as:

$$t_r = \frac{1.8}{\omega_n}$$

For a second-order system the settling time can be approximated as:

$$t_s = \frac{-log(\alpha/100)}{\zeta\omega_n}$$

Log is ln in the equation.

The peak time can be found using:


$$t_p = \frac{\pi}{\omega_d}$$

The overshoot is computed from the step response at the peak time. This gives an expression for the overshoot:

$$M_n = e^{-\frac{\zeta\pi}{\sqrt{1-\zeta^2}}}$$

for  $0 < \zeta < 1$ . The overshoot is given in percentage.

## Overview for determining performance variables



To obtain a rise rise shorter than  $t_r$ 

$$\omega_n \ge \frac{1.8}{t_r}$$

To obtain an overshoot that is smaller than  $M_p$ 

$$\zeta \ge \sqrt{\frac{\left(\frac{\log(M_p)}{-\pi}\right)^2}{1 + \left(\frac{\log(M_p)}{\pi}\right)^2}} \qquad \sigma \ge \frac{-\log(\alpha/100)}{t_s}$$

To obtain an  $\alpha$ %-settling time shorter than  $t_s$ 

$$\sigma \ge \frac{-\log(\alpha/100)}{t_s}$$

## Poles and Zeros of Space-State Models

Using thee state-space matrices:

$$G(s) = C(sI - A)^{-1}B + D$$

**Poles** can be found using the following equation:

When  $G(s) \to \infty$  the system has a pole at  $s \to p$ .

$$\det(pI - A) = 0$$

Here p is the eigenvalue of A.

**Zeros** can be found using the following equation:

When G(s) = 0 the system has a zero at s = z.

$$\begin{vmatrix} A - zI & B \\ C & D \end{vmatrix} = 0$$

## 2.4 Stability

The stability of the dynamical system can be determined from the eigenvalues of A in the time domain. This is the equivalent of poles in the frequency domain.

$$\dot{x} = Ax + Bu$$

When the eigenvalues of A have a negative real part, the system is stable.

**Definition** A linear discrete-time system

$$x_{k+1} = \Phi x_k$$

The state of the next time step is given by  $\phi$  mutliplied by  $x_k$ .

Where  $x_k \in \mathbb{R}^{n \times n}$  is asymptotically (asymptotisk) stable if

$$\lim_{k \to \infty} x_k = 0$$

for any  $x_0 \in \mathbb{R}^n$ .

A linear discrete-time system is stable if all the eigenvalues are inside the unit circle.

The closer the poles are to origin the more dominating the pole is in the system.

## 2.5 Examples

## 3 Introduction to Control

## 3.1 Open Loop Control

(åbensløjfe regulering)

Steady-State Value of Time Function:

Suppose that Y(s) is the Laplace transform of y(t). Then the final value of y(t) is either:

- Ubounded. If Y(s) has any poles in the open right half-plane (unstable)
- Undefined. If Y(s) has a pole pair on the imaginary axis.
- Constant. If all poles of Y(s) are in the open left half-plane, except for one at s=0

### The Final Value Theorem (slutværdi-sætningen)

If all poles of sY(s) are in the open left half-plane, then:

$$\lim_{t\to\infty}y(t)=\lim_{s\to 0}sY(s)$$

The Final Value Theorem determines the constant value that the impulse response of a stable system converges to. The theorem can also be used to determine the DC gain of a system, i.e., the output when a step input is applied to the system.


By integrating an impulse response, the step response is obtained. The step response is the integral of the impulse response, and the impulse response is the derivative of the step response.

If the system has a disturbance an open loop control system will not be able to compensate for this.

## 3.2 Feedback Control

(tilbagekobling). Tilbagekobling anvendes for at elminere forstyrrelsesundertrykkelse.

The connection of a controller K(s) and a system (also called plant) G(s) is called a closed-loop system.



e(s) is the error signal, and is the difference between the reference signal r(t) and the output signal y(t). The error signal is used to adjust the input signal u(t) to the system. The controller K(s) is used to adjust the input signal.

The closed-loop transfer function is given by:

$$\frac{y(s)}{r(s)} = \frac{G(s)K(s)}{1 + G(s)K(s)}$$

K(s) can be designed to meet certain requirements, such as stability, disturbance rejection, and sensitivity analysis.

#### Stability

The closed-loop system is stable if all the closed-loop poles are in the open left half-plane.

The **loop gain (sløjfe-forstærkning)** is defined as: L(s) = G(s)K(s). The closed-loop poles are given by:


$$1 + L(s) = 0$$

The closed loop poles satisfy:

$$1 + L(s) = 0 \Rightarrow L(s) = -1$$

#### Disturbance Rejection


Open loop control system:



The output is given by:

$$y_m(s) = G(s)d(s) + G(s)D(s)r(s)$$

Closed loop control system:



The output is given by (superposition can be applied for deriving the expression):

$$y_m(s) = \frac{G(s)}{1 + G(s)K(s)}v(s) + \frac{G(s)K(s)}{1 + G(s)K(s)}r(s)$$

The larger the amplification of the feedback loop, the smaller the effect of the disturbance on the output.

### Sensitivity Analysis

The sensitivity S of the open-loop system is given by the ratio of  $\delta T_{ol}/T_ol$  to  $\delta G_0/G_0$ . For the open loop system S=1.

For the closed loop the sensitivity is given by:

$$S = \frac{1}{1 + G_0 K_0}$$


This means that a large amplification leads to a low sensitivity.

#### Linearization

## 3.3 Steady State Tracking

### Definition of system type

Stable systems can be classified according to its system type, defined to be the degree of the polynomial for which the steady-state error in a nonzero finite constant.



An expression for the tracing error is computed to determine the steady-state error. The error is given by:


$$e(s) = \frac{1}{1 + L(s)}r(s)$$

Where r(s) is the reference signal and L(s) is the loop gain.

The amount of poles at s=0 in the denominator of L(s) determines the system type.

## 3.4 Cascade Control

A cascade control uses the output from one controller as the input to another controller.



The nested control loops are called the inner loop (secondary) and the outer loop (primary). A fundamental reason for applying cascade control is to obtain better disturbance rejection and lower sensitivity to parameter variations.

## 3.5 DC Motor Dynamics

## 3.6 Examples