



FragScape v2.0

User Manual

4/3/2020

Mathieu Chailloux (INRAE / UMR TETIS) - mathieu.chailloux@inrae.fr

Jennifer Amsallem (INRAE / UMR TETIS) - jennifer.amsallem@inrae.fr

Jean-Pierre Chéry (AgroParisTech / UMR TETIS) - jean-pierre.chery@teledection.fr

Table of contents

1 Overview	3
1.1 Landscape fragmentation metrics	3
1.1.1 Landscape division	3
1.1.2 Splitting index	3
1.1.3 Effective mesh size	3
1.1.4 Cross-Boundary Connection (CBC) method	4
1.2 Computation methods	4
1.2.1 Vector mode	4
1.2.2 Raster mode	4
1.3 Installation	5
1.4 Graphical User Interface (GUI) overview	5
2 Steps	6
2.1 Parameters	6
2.2 Land cover	7
2.3 Additional data	8
2.4 Results	9
3 Example	10
4 To go further...	11
4.1 Execution time and memory	11
4.1.1 Vector mode	11
4.1.2 Raster mode	11
4.2 Algorithms	11
4.3 Results comparison	12
4.4 Configuration file	12
5 FAQ	13
Bibliography	13

1 OVERVIEW

FragScape is a QGIS plugin that computes landscape fragmentation metrics defined in paper "Landscape division, splitting index, and effective mesh size: new measures of landscape fragmentation" (Jaeger 2000). Among these metrics, effective mesh size has been widely used to quantify landscape fragmentation. *FragScape* defines a 4 steps process from raw data to computed metrics and allow user to save configuration so that results can be reproduced with same context.

1.1 LANDSCAPE FRAGMENTATION METRICS

Jaeger defined in his paper (Jaeger 2000) three new measures of landscape fragmentation:

- landscape division
- splitting index
- effective mesh size

To compute these measures, landscape elements assessed as fragmenting are removed. Remaining areas are called patches. Landscape is then composed of n patches. A patch area is denoted by A_i with $1 \leq i \leq n$. The total area of the region is denoted by A_t .

1.1.1 Landscape division

The degree of coherence (C), an auxiliary measure, is defined as the probability that two points chosen randomly in a region are connected (e.g. not separated by fragmentation elements such as roads or urban areas):

The degree of landscape division (D) is defined as the probability that two points chosen randomly in a region are *not* connected:

$$C = \sum_{i=1}^n \left(\frac{A_i}{A_t} \right)^2 \quad D = 1 - C$$

1.1.2 Splitting index

The splitting index (S) is defined as the number of patches one gets when dividing the total region into parts of equal size (meshes) in such a way that this new configuration leads to the same degree of fragmentation of initial configuration:

$$S = \frac{A_t^2}{\sum_{i=1}^n A_i^2}$$

It can be interpreted as the effective mesh number of a grid with a constant mesh size dividing the region into S patches which all have the size A_t/S .

1.1.3 Effective mesh size

The effective mesh size (m) denotes the size of the areas when the region is divided into S areas (each of the same size A_t/S) with the same degree of landscape division as for the initial configuration:

$$m = \frac{A_t}{S} = \frac{1}{A_t} \sum_{i=1}^n A_i^2$$

Splitting density (s) is defined as the number of meshes per unit area. Net product (N) is defined as the product of the effective mesh size and the total area of the region:

$$s = \frac{S}{A_t} = \frac{A_t}{\sum_{i=1}^n A_i^2} = \frac{1}{m} \quad N = m \cdot A_t = \sum_{i=1}^n A_i^2$$

1.1.4 Cross-Boundary Connection (CBC) method

As other patch-based landscape metrics, above metrics can be biased by the boundaries and the extent of a reporting unit if the boundaries fragment patches. This issue is called the "boundary problem" and has been addressed in paper "Modification of the effective mesh size for measuring landscape fragmentation to solve the boundary problem" (Moser et al. 2007).

New method called *cross-boundary connections* (CBC) includes area outside boundaries. The complete area of a patch, regardless of boundaries, is denoted by A_i^{cmpl} . The formula of effective mesh size according to CBC method is:

$$m_{CBC} = \frac{1}{A_t} \sum_{i=1}^n A_i \cdot A_i^{cmpl}$$

Encart 1 : Métriques CBC

In CBC mode, only 2 metrics are defined : effective mesh size and net product

1.2 COMPUTATION METHODS

Metrics are computed from a layer of natural areas patches.

FragScape is designed to include patch layer creation from raw data (land cover, roads, ...) following a step-by-step procedure (cf section 2): natural areas selection from land cover and integration of additional data.

There are 2 computation methods depending on input data format, extent, precision needs and available computing resources. Vector mode is appropriate for vector land cover in case the amount of data is reasonable (cf section 4.1). Raster mode is appropriate otherwise (raster land cover, large extent, high geometric precision, ...).

1.2.1 Vector mode

In vector mode, features are selected from land cover layer and dissolved (one feature of type Multi-Polygon).

It is then possible to integrate additional data such as roads network, hydrographic network, or any missing data in initial layer. For each data source, features can be selected (paved roads for instance) and a buffer can be applied to modelize footprint for linear data. These selections are then merged with land cover, by union or difference depending on their contribution to fragmentation or to natural areas. Resulting layer is then dissolved and casted to single geometry (Polygon) to finally get a correct patch layer for metrics computation.

1.2.2 Raster mode

In raster mode, input data can be vector or raster but output layers are in raster format anymore (rasterization and reprojection according to extent and resolution parameters).

Resolution value is very important because it defines computation precision but also random-access memory (RAM) needed. If land cover is already in raster format, resolution shall be the same than land cover layer.

Land cover layer is reclassified: 1 for natural areas (selected classes), 0 for fragmentation data (unchecked classes). Additional data is reprojected and classified same way. Resulting layers are then merged according to specified ranking order in graphical user interface.

1.3 INSTALLATION

FragScape is a QGIS plugin.

FragScape is a cross-platform plugin. Tests were performed on Ubuntu bionic, Windows 10 and macOS Sierra.

Encart 2 : Prerequisites

QGIS version must be superior to 3.4.0.

To install *FragScape*, open QGIS:

- go to Extension menu
- open Install/Manage extensions dialog
- go to Parameters tab and check that Show experimental plugins option is checked
- go back to All tab, search for *FragScape*, select it and click on Install plugin button

Once installed, *FragScape* icon  shall appear in tools panel.

If not, go to Extension menu and a *FragScape* entry shall be present.

If not, installation failed. Please check error message or contact support team.

1.4 GRAPHICAL USER INTERFACE (GUI) OVERVIEW

Figure 1 show an overview of *FragScape* GUI. It contains 4 main components :

- top icons bar : action icons (configuration management, language switch)
- right panel : description of current step
- bottom progress bar : shows progress of current process
- main frame : current step content

In main frame, current step can be composed of :

- parameters that must be set (such as Workspace)
- visualisation table that displays current configuration/results
- action buttons (such as Launch selection)




FIGURE 1: *FragScape* v2.0 Graphical User Interface

2 STEPS

FragScape defines a 4 step procedure from raw data to computed metrics.

2.1 PARAMETERS

First step is to define global parameters used for current *FragScape* project.

Workspace must be set before any processing as it defines *FragScape* outputs path. Output file of each step is stored in *Workspace/outputs*. Be careful when setting workspace as existing file can be overridden. Mode defines processing chain executed to compute metrics (cf section 1.2). In raster mode, Resolution must be set to define pixel size in georeferenced unit (meter for a metric projection).

Extent layer defines data extent: data are clipped at layer limits. Optional in vector mode. In CBC mode, data extent must be larger than study area.

Projection is a projected coordinate reference system that must be set according to data geographic extent. It defines entities shape and area.

If option Save intermediate layers is checked, intermediate layers are stored in *Workspace/tmp*. Otherwise, they are stored in QGIS processing temporary directory (path is displayed in log when a layer is created).

2.2 LAND COVER

Second step is to select target features from land cover layer. To do so:

- Select land cover layer (Input layer parameter).
- Choose Mode and Selection field in input layer is vector
- Press button Show field values
- Check land cover classes matching natural areas in toSelect column of table
- Press button Launch selection. Output layer is loaded in QGIS and saved in *Workspace/outputs* (*landuseSelectionDissolve.gpkg* in vector mode, *landuseSelectionWarp.tif* in raster mode).

Encart 3 : Selection mode

There are 2 selections modes in In Vector mode:

- By field values to extract unique values from Selection field
- By expression to extract features verifying specified expression (all features if expression is empty)

In Raster mode, unique values are extracted from first band.

Figure 2 shows an example of land cover selection interface.




FIGURE 2: FragScape v2.0 Land cover tab

2.3 ADDITIONAL DATA

Third step is to integrate additional data that would be missing in land cover. For instance: roads, river courses, wildlife crossing, ...

For each data source, user should:

- Select Input layer
- (optional) Filter input features according to specified Expression (all features if expression is empty). Expression can be built with \mathcal{E} widget.
- Specify Buffer expression for line and point data in vector mode to modelize footprint. Expression must be a number and can be built with \mathcal{E} widget.
- Specify an Identifier (unique in project) for current selection
- Press Save selection button. Specified selection appears as a new line in visualisation table.

Once all data selections saved, user should rank lines (for instance wildlife corridors on top of roads) and then press Integrate additional data button.

For each line, data is selected, buffer is applied (if defined) and layer is rasterized in raster mode. Output layers are then merged and integrated to result of previous step.

Final layer is loaded in QGIS and stored and savec in output directory (*landuseFragmSingleGeom.gpkg* in vector mode, *landuseFragm.tif* in raster mode).

INPUT	SELECT_EXPR	BUFFER_EXPR	NAME	FRAGM
Source/BDROU...	"VOCATION" = 'Liaison locale'	10	petites_routes	true
Source/BDROU...	"VOCATION" = 'Liaison principale' or "VOCATIO...	case when "NB..."	autres_routes	true
Source/BDCAR...	"ETAT" = 'Permanent' and ("NATURE" = 'Aqueduc...'	case when "LAR..."	hydro	true

FIGURE 3: FragScape v2.0 Additional data tab

2.4 RESULTS

Fourth step is to compute fragmentation metrics. To do so:

- Specify Input layer (result of step 3 by default).
- Specify Reporting layer. Metrics are computed for each feature of reporting layer. To compute metrics for an entire region, specify a layer with a single feature.
- Check Include CBC metrics if needed (see section 1.1.4)
- Select Unit of area (from square meter to square kilometer)
- Specify Output layer. If not specified, a memory layer is created.
- Press Compute metrics button.




FIGURE 4: FragScape v2.0 Results tab

Figure 4 shows results step interface. Once metrics are computed, output layer is loaded in QGIS and global effective mesh size (on the whole territory) is displayed. Output layer contains an attribute for each metric defined in section 1.1 and new fields:

- nb_patches: number of patches
- report_area: area of the reporting unit
- intersecting_area: intersection area of patches and reporting unit
- layer/path: temporary layer containing initial reporting unit
- divisor : divisor matching unit of area (for instance 100 for are unit)

3 EXAMPLE

This section illustrates *FragScape* use case with provided sample data (subdirectory `sample_data` in *FragScape* plugin directory).




FIGURE 5: *FragScape* use case : from raw data to effective mesh size

Figure 5 shows input data and each step result.

To reproduce results:

- Copy `sample_data` to a local directory
- Open *FragScape*
- Set workspace to `sample_data/CUT`
- Open configuration file `EPCI_Clermontais_2012_CUT.xml` from button
- Check that configuration has been correctly loaded
- Run steps 2 to 4

4 TO GO FURTHER...

4.1 EXECUTION TIME AND MEMORY

Use of *FragScape* depends on available computing resource when applied to large territory with high level of geometric precision.

4.1.1 Vector mode

In vector mode, execution time can be very long depending on study area extent and geometric precision. Given execution times are **indicative values**.

Figure 6 show the evolution of execution time according to region extent (small region, big region, country) from *Corine Land Cover* (vector data):

Study area	Step 2	Step 3	Step 4
Hérault	<1mn	1mn	1mn
Occitanie	5mn	11mn	2mn
France	122h	19h	5h

FIGURE 6: Execution time by extent

Figure 7 show the execution time according to data source geometric precision (*Corine Land Cover* vs *OCCupation du Sol Grande Échelle*) on a same territory (Hérault):

Cas de test	Étape 2	Étape 3	Étape 4
CLC	<1mn	1mn	1mn
OCSGE	6h	35h	3mn

FIGURE 7: Temps d'exécution - CLC vs OCSGE

If execution time is too long, user can switch to raster mode which is much faster but leads to a loss of geometric precision depending on resolution.

4.1.2 Raster mode

In raster mode, critical resource is the available live memory (RAM). RAM needs depends on the amount of data (number of pixels) that is directly linked to tuple (extent, resolution). If a memory error occurs, user can change resolution and try to relaunch computation.

4.2 ALGORITHMS

Algorithms (available in QGIS processing toolbox) implement specific treatments developed for *FragScape*. Figure 8 shows available algorithms. Groups Raster et Vector gather steps described in section 2.

- Compare results layer : computes difference between 2 *FragScape* results layer for each field (cf section 4.3)
- Raster Effective Mesh Size : computes fragmentation metrics in raster mode without reporting layer
- Raster Effective Mesh Size (Cross-Boundary Connection) : computes fragmentation metrics in raster and CBC modes
- Raster Effective Mesh Size per feature : computes fragmentation metrics in raster and CUT modes




FIGURE 8: *FragScapeAlgorithms*

- Integrates vector data to land cover : applies geometric difference/union between natural areas layer and additional data in vector mode
- Prepare land cover data : selection of natural areas from land cover layer in vector mode
- Vector Effective Mesh Size (Global) : computes fragmentation metrics in vector mode on the whole territory (features are dissolved if needed)
- Vector Effective Mesh Size per feature : computes fragmentation metrics in vector mode for each feature of reporting layer

4.3 RESULTS COMPARISON

FragScape finality is to study fragmentation evolution and so to compare results on a same territory at different times. Algorithm `Compare results layer` computes difference between 2 output layers of *FragScape* on each field.

Difference on `effective_mesh_size` and `net_product` fields is performed using CBC value if available. Field variation contains effective mesh size evolution in percentage: $(B_{val} - A_{val}) / (B_{val} + A_{val})$.

4.4 CONFIGURATION FILE

Configuration is saved as an XML file and thus can be opened in a text editor. Figure 9 shows the begining of configuration file `sample_data/ECPI_Clermontais_2012/CBC/ECPI_Clermontais_2012_CBC.xml`

```

<FragScapeModel>
  <Params workspace="D:/Projets/Meff/Tests/EPCI_Clermontais/EPCI_Clermontais_2012/CBC" crs="epsg:2154"/>
  <Landuse in_layer="../Source/CLC/CLC12_D034_RGF.shp" select_mode="0" select_field="CODE_12">
    <LanduseFieldItem value="111" description="Continuous urban fabric" toSelect="False"/>
    <LanduseFieldItem value="112" description="Discontinuous urban fabric" toSelect="False"/>
    <LanduseFieldItem value="121" description="Industrial or commercial units" toSelect="False"/>
    <LanduseFieldItem value="122" description="Road and rail networks and associated land" toSelect="False"/>
    <LanduseFieldItem value="123" description="Port areas" toSelect="False"/>
    <LanduseFieldItem value="124" description="Airports" toSelect="False"/>
  </Landuse>
</FragScapeModel>
    
```

FIGURE 9: Example of a configuration file

In `Landuse` tag, one can see attributes such as `in_layer` (input layer), `select_mode` (0 meaning selection mode by field values) and `select_field` (selection field of input layer is `CODE_12`). For each loaded field value, a `LanduseFieldItem` tag exists and contains same attributes as in *FragScape* (`value`, `description`, `toSelect`).

Such file can be manually edited if needs be. For instance if relative paths must be changed for a new project (./Source becoming . . . /Source), updating it in *FragScape* tables or creating a new project can be avoided by editing new paths in configuration file and then reloading it.

5 FAQ

- **Fields are not loaded in field/expression widget Σ , why ?** If they don't appear, it is because associated layer is not loaded even if its path is displayed in combo box. Select another layer and then re-select initial layer.
- **Which method should I use, CUT or CBC ?** CBC method has been designed to address boundary problem and then should be used. CUT method is available to allow comparison with already computed results, or in case boundaries are not a problem.
- **Elements of fragmentation are already included in my land cover layer, should I run step 3 ?** In *FragScape* 2.0, it is possible to specify step 4 input layer so taht step 3 is optional.
- **Can I apply *FragScape* processing to layer not produced by *FragScape* ?** To apply *FragScape* specific processing to specific data, one can use *FragScape* algorithms described in section 4.2.

Encart 4 : Good practices

- Do not use spaces and special characters in file names.
- Do not use special characters in field values.
- Save *FragScape* configuration at each step.
- Check each step result.
- If a problem occurs, save configuration, exit *FragScape* relaunch *FragScape* and re-open saved configuration. If problem still occurs, exit and relaunch QGIS. If problem still occurs, contact support team.

ERROR MESSAGES

- **Layer XXX is already loaded in QGIS, please remove it.** *FragScape* cannot delete file if it is already loaded. Just remove it from QGIS project and relaunch *FragScape* processing.
- **The process cannot access the file because it is being used by another process: XXX.** Check that XXX file is not used by another process. If not, save configuration, save QGIS project, exit QGIS, relaunch QGIS, relaunch *FragScape*, re-open configuration and relaunch *FragScape* processing.

If an unknown error occurs, please report it at <https://github.com/MathieuChailloux/FragScape/issues>

References

- [1] Jochen Jaeger. "Landscape division, splitting index, and effective mesh size: New measures of landscape fragmentation". In: *Landscape Ecology* 15 (Feb. 2000), pp. 115–130. DOI: 10.1023/A:1008129329289.
- [2] Brigitte Moser et al. "Modification of the effective mesh size for measuring landscape fragmentation to solve the boundary problem". In: *Landscape Ecology* 22 (Mar. 2007), pp. 447–459. DOI: 10.1007/s10980-006-9023-0.