COMP15111 notes

Todd Davies

January 1, 2014

1 Introduction

1.1 A Computational Model

The simplest, earliest, commonest, most important computational model is the Von-Neumann Imperative Procedural Computer Model

According to this model, a computer can:

- 1. Store information
- 2. Manipulate the stored information
- 3. Make decisions depending on the stored information

1.2 Simple View Of A Computer

The simplest model of a computer can be represented as:

$Memory \Leftrightarrow Bus \Leftrightarrow Processor$

1.2.1 Memory

Memory is a set of locations which can hold information, such as numbers, programs or many other types of data. Each memory location has a unique numerical address, and there are typically thousands of millions of different locations. There are various ways of depicting memory; a common one is a 'hex dump' that often looks something like this:

Run the command hexdump to generate hexdumps.

AddressHex valuesASCII0000000048 65 6C 6C 6F 0A Hello.

Each item that is in the memory has a unique address.

1.2.2 Bus

A bus is a bidirectional communication path. It is able to transmit addresses and numbers between components inside the computer.

1.2.3 Processor

The processor obeys a sequence of instructions, commonly referred to as a program. Historically the processor was often referred to as a CPU, however, this is inappropriate nowadays since typical processors consist of several processing cores.

1.3 Three-address instructions

Every kind of processor has a different set of instructions, real world examples include: Pentium, ARM and others

Each three-address instruction:

- 1. Copies the values from any two memory locations and sends them to the processor (source operands)
- 2. Copies some operation e.g. adds the copied numbers together
- 3. Copies the result back from the processor into a third memory location (destination operand)

For example, if we wanted to convert the Java code sum = a + b; into a three-address instruction we would:

- 1. Identify the two source operands: a holds 2, b holds 3
- 2. Perform the operation: 2 + 3 = 5
- 3. Let the variable sum equal the answer 5. This is the $destination \ operand$

1.3.1 Three address example

Question: Convert the Java code product = c * d; into the three- address style and draw a two box view of it.

First we need to re-write the Java code in the three-address style:

$$product \leftarrow c * d$$

Now we can draw the box view of it (figure 1).




Figure 1: An example of the two box model

1.3.2 Memory bottleneck

Most processors can process instructions faster than they can be fed by memory. Each instruction in the three-address cycle requires four memory cycles:

- 1. Fetch the instruction
- 2. Read the first operand
- 3. Read the second operand

4. Write the result to memory

Each of these memory cycles could take hundreds of processor clock cycles to complete, and so in this time the processor would be doing nothing. However, most modern processors employ a *cache* to temporarily store commonly accessed memory locations, and so avoid some of the memory cycles.

1.4 Registers

Registers are very small amounts of storage build into a processor. Since they are inside the processor data doesn't need to be transferred over the bus, and so they are very fast. Registers are used instead of the main memory which speeds up program execution.

Each register can only hold one value and each processor will only generally have a few dozen registers (e.g. ARM has sixteen).

1.5 Instruction Styles

1.5.1 One address

The one address style can only use up to one memory location in each instruction, all other operands must be registers. An example may be:

$$R1 \leftarrow R0 + memory\ location$$

1.5.2 Load-store

The load-store style cannot perform operations on memory locations at all. Instead, values from memory must be loaded into a registers before the operation takes place and then the operation can be performed on the registers. Following the operation, the result must be stored back into memory again.

$$R1 \leftarrow memory\ location$$

$$R1 \leftarrow R0 + R1$$

$$memory\ location \leftarrow R1$$

This means that we need extra instructions to do stuff with memory locations:

- 1. **Load** the value from memory into a register before the operation.
- 2. **Store** the value in the register back to memory after the operation.

For example, the Java code Sum = a + b + c; would be run as:

R1
$$\leftarrow$$
 a (i.e. load from a)
R2 \leftarrow b (i.e. load from b)
R3 \leftarrow R1 + R2 (i.e. a+b)
R4 \leftarrow c (i.e. load from c)
R5 \leftarrow R3 + R4 (i.e. (a+b)+c)
Sum \leftarrow R5 (i.e. store to sum)

You can see that the load-store style favours lots of very simple, very fast instructions.

2 ARM

Computers obey programs which are sequences of instructions. Instructions are coded as values in memory. The sequences are held in memory adjacent memory locations. Values in memory can be interpreted as you please, from numbers to text, images or anything really!

Any given set of binary digits can be read as a decimal number, but not always as text, so values in memory are often represented as numbers for convenience.

2.1 Assembly Language

Assembly language is a means of representing machine instructions in a human readable form.

Each type of processor has its own assembly language (since each language is specific to a particular architecture) but each instruction typically has a lot in common:

- A mnemonic, that specifies the type of operation
- A destination, such as a register or memory location
- And one or more sources that may be registers or memory locations.

• Possibly with a comment too which will help programmers understand what's happening and aren't interpreted by the assembler.

When a program has been written in assembler, it must be assembled by an assembler to run it.

2.2 ARM instructions

ARM has many instructions but we only need three categories:

- Memory operations that move data between the memory and the registers.
- Processing operations that perform calculations using value already in registers.
- Control flow instructions are used to make decisions, repeat operations etc.

2.3 Transferring data between registers and memory

Memory operations load a value into a register from an address in memory or store the value of a register to a memory address.

For example, a into register 1 $(R1 \leftarrow a)$ we would write: LDR R1, a

Or to store the value in register 5 into $sum~(sum \leftarrow R5)$: STR R5, sum

In these examples, a and sum are aliases for the addresses of memory locations.

2.4 ARM processing instructions

ARM has many different instructions to perform operations such as addition, subtraction and multiplication.

The syntax for such operations is usually:

[operand] [destination register] [register 1] [regist

For example, to add two numbers together, we might write:

ADD R2, R0, R1

This will add the value of R0 to the value of R1 and store it in R2.

2.5 ARM control instructions

The most common control instruction is the branch. Similar to GOTO in other languages, a branch will change the PC register (see section 2.6) to another value so the order of execution of the program is changed.

Branches can be made to be conditional by appending a conditional operator on to the command.

The syntax is something like:

B[conditional operator] [branch name]

Some examples of different conditional operators are:

Command	Function
В	Branches to a different location in the code.
BNE	Branches, but only if the previous condition
	was false.
BEQ	Branches, but only if the previous condition
	was true.

2.6 Stored programs and the Program Counter

A computer can make decisions, and choose which instructions to obey next depending upon the results of those decisions. A **Program Counter** (PC) register is used to hold the memory address of the next instruction to be executed. ARM uses register 15 as its PC.

2.7 Fetch-Execute Cycle

The processor must first fetch instructions from memory before it can execute them. This is called the fetch-execute cycle, and it involves:

- 1. **Fetch**: copy the instruction, pointed to by the PC, from memory and set PC to point to the next instruction
- 2. **Execute**: obey the instruction (exactly as before)
- 3. Repeat.

In ARM, the PC starts with a values of 0x00000000 when the program is initially run. On each cycle of the Fetch-Execute cycle, the PC is incremented by 4, since instructions each occupy 4 memory locations.

2.8 Decision Making

In order to make decisions, the computer mustn't just execute instructions one after the other in a linear manner. Instead, branches must be used to change the sequence of instructions to be executed.

In order to perform a conditional branch, we must first perform a compare command to perform the comparison before we do the branch.

2.8.1 An example

If we wanted to do a 1 discount on a shopping list if the price was over 20, we would do the following:

```
LDR RO, total; Load the total price
1
           ; into RO
2
3
      CMP RO, #20; Compare RO and 20
4
           ; (the literal)
5
      BLT nodiscount; If the price is too low,
6
           ; then don't discount
7
      SUB RO, #1; Deduct 1
8
      STR RO, total; Store the result back
9
           ; into memory
10
```

```
11
```

12 nodiscount SVC 2 ; Finish

13

14 total DEFW 25 ; Lets say the total is $\S25$

2.9 Allocating memory

The DEFW (define word) operation puts a value in memory before the program is run. Any define operation is executed before the program is run.

The actual memory location that is used to store the value isn't known to the running program, however, an *alias* is attached to the memory location by the programmer and the memory location can be referenced through that.

The syntax for the DEFW command is as follows:

myage DEFW 18

Where myage is the alias and 18 is the value.

DEFW can also be used to define a number of words:

The label is associated with the lowest address (i.e. 0)

squares DEFW 0, 1, 4, 9, 16, 25

DEFB stores a single byte in memory. It is useful for strings such as "hello":

hi DEFB "hello"

DEFS sets a block of bytes to a set value:

reserved_space DEFS 10, 5

The above will set 10 bytes to the value '5'.

3 Storing values

There are many ways to store data. For example, we could store what lights are one in a traffic light in many different ways. First, we must decide how many different states the traffic light can be in:

Red, Red Amber, Green, Amber

You can see that we have four states. This could be represented in binary as two bits:

00	Red	
01	Red Amber	
10	Green	
11	Amber	

We could also store the states as their binary representations of their names:

R	01010010
RA	0101001001000001
G	01000111
A	01000001

You can see though, that this isn't as efficient as storing just two binary digits.

4 ARM assembly programming

4.1 Different types of values

ARM has the capacity to work with many different types and sizes of values. Each type has a different use case. The main ones are described below:

\mathbf{Name}	length	Use
Byte	8 bits	Used for characters
Word	32 bits	Used for integers, addresses and instruc-
		tions

There are other types too (such as the halfword and doubleword) but they aren't needed for this module.

ARM processors require that memory locations are aligned. This means that values stored in memory start at specific places. For example, a word address must be a multiple of four. e This means that after a DEFW statement, the ALIGN command must be called (See 4.10.2 for more on the ALIGN command.).

4.2 Loading and storing values in memory

The commands LDR and STR are used to move values between memory and registers. The commands are detailed in full below:

Command STR	Function Copies the whole (32 bit) register into mem-
LDR	ory. Loads a 32 bit word from memory into a
CITED D	register.
STRB	Stores a single 8 bit byte into memory from a register.
LDRB	Loads a byte from memory into a register. The upper 24 bits of the register are zeroed.

4.3 Endianness

Endianness is a property of a memory location that defines the order of the bits. There are two types of endianness, little endian and big endian.

In the word 0x12345678 there are four bytes:

- 0x12
- 0x34
- 0x56
- 0x78

In little endian, the first byte would be 0x12 since bits are read from left to right in little endian.

In big endian, the first byte would by 0x78 since bits are read from right to left in big endian.

This is important when we deciding what the most and least significant bits in a word are. For example, in this instance the lsb is 0x12 in little endian, but 0x78 in big endian.

N.b. The least significant bit is the smallest address.

In this course, little endian is used, though ARM can use either.

4.4 Addressing memory

ARM uses 32 bit addresses, so there are 2^{32} different bytes that can be addressed in memory (or $\frac{2^{32}}{4}$ different words). However, there is no guarantee that the system on which the program is running will have that much memory available.

4.5 Instruction encoding

Each ARM instruction is encoded into a four byte word. The exact meaning of each of the bits varies per instruction.

For example, in the branch instruction, the first four bits specify the condition, the second four bits represent the actual operation to perform (i.e. branch) and the remaining twenty four bits define the memory location of the next instruction to branch to.

However, this presents a problem. We only have twenty four bits with which to define the next location to branch to, which allows us to define 2^{24} different locations. However, there are 2^{32} possible addresses that we could use!

This problem is overcome by treating the 24 bits as an offset to the address of the current instruction. This works since most of the time, the address that is being branched to is fairly close to the current instruction.

In order to be able to branch to addresses before and after the current instruction, we must use two's complement to allow signed integers to be used to specify the offset. This means we can branch to any instruction at an address $\pm 2^{23}$ from the current instruction.

4.6 Literals

ARM is able to encode literal values into instructions. This saves time having to access registers or memory in order to perform operations such as arithmetic.

An example is to increment a register:

ADD R1, R1, #1

However, ARM only assigns up to 12 bits for a literal value, so we can only have 2^{12} values. However, ARM employs a strange method of encoding these values so that more useful values are available (for example, #512 is allowed, but #257 isn't).

4.6.1 Negative literals

Technically, ARM doesn't support negative literals, however, the assembler will usually be able to find a way to implement them. Some examples are given below:

CMN is compare negative.

MVN is move not.

```
ADD R1, #-1 \rightarrow SUB R1, #1 CMP R2, #-2 \rightarrow CMN R2, #2 MOV R3, #-3 \rightarrow MVN R3, #3
```

4.7 Supervisor calls

Supervisor calls are functions implemented by the operating system, not ARM itself. The parameter of an SVC call defines it's exact operation.

SWI is another name for SVC - they do the same thing.

In this module, the SVC call does the following for each parameter:

SVC 0 Output a character
SVC 1 Input a character
SVC 2 Stop execution
SVC 3 Output a string
SVC 4 Output an integer

4.8 Pseudo instructions

The ARM assembler provides some instructions that are translated into sequences of more complicated instructions at the time of assembly for our convenience.

One such instruction is loading a literal into a register. This is done using the LDR command as usual, however a literal is used with the '=' character instead of a '#'. E.g. to load the value 100 into register one, we do:

LDR R1,=100

However, this is a pseudo instruction and will be converted by the assembler to:

MOV R1,#100

However, if the number is very large, it becomes:

constant DEFB 100 LDR R1, constant

4.9 Loading an address into a register

The ADR command loads an address into a register, for example:

- 1 constant DEFB 100
- 2 ADR R1, constant

It will load the memory address of constant relative to the PC into R1. When the code is assembled, it is turned into two instructions (so ADR is a pseudo instruction). They are:

- 1 ADD R1, R1, PC
- 2 LDR PC, R1

4.10 Directives

Directives are evaluated at the time of assembly.

4.10.1 DEF commands

The DEF{W,B,S} command reserves an amount of memory dependent on the operation used (see the table) and puts an initial value in it.

Command	Function	
DEFW num	Reserves a word of memory and puts	
	the initial value num in it.	
DEFB value	Reserves byte(s) of memory and puts	
	the initial value value in it. Note	
	that the value can be a string literal,	
	in which case the number of bytes re-	
	served will be equal to the length of	
	the string.	
DEFS size, fill	Reserves a <i>block</i> of memory of size	
	bytes and initialises them with the	
	value fill.	

4.10.2 Align

The align command leaves as many blank bytes as needed so that the next item in memory will start at a word boundary (a multiple of 4).

4.10.3 Entry

Sets the PC at the start of the program (i.e. where the program should start from)

4.10.4 EQU

Allows you to name a literal, which can go a long way to making the code more maintainable. We could define the literal 18 as *drinking_age*:

```
drinking_age EQU #18
; Check the person is over 18
CMP R1, #drinking_age
BLT too_young
```

5 Arithmetic

5.1 Making good use of registers

Registers are a precious resource when programming on ARM. When writing software to evaluate expressions, it's often tempting to load all the variables into registers first, and then perform the arithmetic in separate registers like so:

```
2 LDR R1, b
3 LDR R2, c
4 LDR R3, d
5 ADD R4, R1, R2
6 ADD R5, R4, R3
7 STR R5, a
```

1

: a = b + c + d

However, this is pointless - the values in the registers R4 and R5 aren't going to be needed again, so we may as well

do:

```
1 ; a = b + c + d

2 LDR R1, b

3 LDR R2, c

4 LDR R3, d

5 ADD R1, R1, R2

6 ADD R1, R1, R3

7 STR R1, a
```

But, we can optimise even further here. Instead of loading all the variables into registers before we do arithmetic, we can save a register and load only the ones we need before each ADD instruction:

```
1 ; a = b + c + d

2 LDR R1, b

3 LDR R2, c

4 ADD R1, R1, R2

5 LDR R2, d

6 ADD R1, R1, R2

7 STR R1, a
```

Sometimes, it's useful to re-order an arithmetic expression so it can be implemented using less registers. This can often be achieved by increasing the nesting of brackets in an expression such as this:

$$(b-e) + (c*d) = ((c*d) + b - e)$$

Though these expressions are both equal, the right hand side will use a register less in ARM code, since each instruction can be executed sequentially, however the left hand side requires two expressions to be evaluated (and stored in a total of three registers) and then both expressions added together.

5.2 Using literals in expressions

If there is a literal in the expression you want to evaluate, then it's possible to use a literal instead of a register. For example, these two programs will end up with the same answer in RO but the one on the right uses less registers:

```
(a + 5) * b
                                 : (a + 5) * b
1
                           1
     LDR RO, 5
                                LDR RO, a
2
                           2
     LDR R1, a
                                ADD RO, RO, #5
3
                           3
     ADD RO, RO, R1
                                LDR R1, b
4
                           4
     LDR R1, b
                                MUL RO, RO, R1
5
                           5
     MUL RO, RO, R1
6
                           6
7
                           7
    five DEFW 5
                           8
8
9
                           9
```

Literals can be any expression that the assembler can evaluate, for example, the following are all valid:

Note that MUL cannot use literals. To get around this, first MOV the literal into a register and then multiply.

```
ADD RO, RO, #(1 + 2)
ADD RO, RO, #-2
ADD RO, RO, #(2 - 1)
```

5.3 Status flags

ARM has some 1-bit status flags that are set after a CMP instruction as shown below:

Flag	Meaning	
Negative	Previous result was negative	
Zero	Previous result was zero	
Carry	Previous add or subtract generated	
	a carry	
Overflow	The previous add or subtract over-	
	flowed and went out of range	

You can get any data operation to alter the flags by appending S to the instruction. For example:

SUBS RO, R1, R2

The above command will subtract R2 from R1 and store the result in R0, but it will also set the flags according to the value of R0. For example, if the value in R0 was negative after the operation, the Negative flag would be set.

5.4 Other useful arithmetic commands

The RSB command is reverse subtract, and is useful for negating a literal:

RSB R1, R0, #0; R1 = 0 - R0 = -R0

The MLA command is multiply and add. It can only use registers as operands.

MLA R1, R2, R3, R4 ; R1 = (R2 * R3) + R4

6 If and While

6.1 If statements in ARM

Given an if statement written in Java such as this:

```
1  if(condition)
2  {
3   actionStatement;
4 }
```

How would we convert that into ARM assembly? The best way is to do the following:

- 1. Check to see if the condition is else
- 2. If it is, then branch to the end of the if statement
- 3. Otherwise, perform the action statement

An example implementation may be:

```
CMP R1, R2; Compare two registers
BGE endif; The condition
MOV R1, #0; Whatever the action
; statement may be
endif
```

Note that it is often easier to implement the inverse of some comparisons. For example, if we were evaluating (a >= b) we could do either of these:

- 1. Check whether a is greater than b
 - 2. Check whether a is equal to b

- 3. Work out how to branch away if both are false
- 1. Inverse the comparison and check if a is less than b
 - 2. Branch away if it is

6.2 If else statements

If else statements are much like if statements, except that if the condition is false then you branch to the else action, and if the condition is true, then you branch to after the else statement once you've executed the action. Here's an example:

```
Lets implement if (a==b) a += 1; else b += 1; :
```

```
1 LDR RO, a
```

- 2 LDR R1, b
- 3 CMP RO, R1; Compare
- 4 BNE else ; If they aren't equal
- 5 ADD RO, RO, #1
- 6 B end
- 7 else ADD R1, R1, #1
- 8 end

6.3 While statements

Implementing a while statement in ARM assembler is very similar to implementing an if statement, except after you have executed the action statement, you branch back to the initial condition again, like so:

Note that if the code in your while loop is being executed repeatedly, then it's probably worth optimising it!

- ; Compare two registers
- 2 start CMP R1, R2
- 3 ; The condition
- 4 BGE endif
- 5 ; Whatever the action statement may be
- 6 ADD R1, R1, #1
- 7 ; Branch back to the start
- 8 B start
- 9 endif

In ARM, we can make *any* instruction have a conditional code on it. Consequently, we can get rid of a branch instruction, like so:

- 1 ; Compare two registers
- 2 start CMP R1, R2
- 3 ; Add only if the flag is less than
- 4 ADDLT R1, R1, #1
- 5 ; Branch back to the start
- 6 BLT start
- 7 endif

You can compare the result of an arithmetic instruction with zero by appending S to the instruction like so:

- 1 start ADDS RO, #1
- 2 BNE start
- 3 endif

This will keep adding 1 to R0 until it reaches 0. This is often useful when translating for loops that count up to a number.

Instead of counting up, you can count down using the SUBS instruction and only iterate if the result isn't zero.

7 Addresses and Addressing

When a processor references memory it needs to produce an address.

The address needs the same number of bits as the memory address. i.e. 32 in ARM

addressing modes - mechanisms for generating addresses

7.1 Direct Addressing

Direct addressing is a mode where the address is simply contained within the instruction.

This requires an instruction longer than the address size which is a problem because ARMs maximum bit length is 32.

So far, we assumed that direct addressing uses LDR/STR instructions, for example:

LDR R0, b LDR R1, c ADD R0, R0, R2 STR R0, a

This looks like direct addressing but on ARM it's 'faked' by the assembler as a pseudo-instruction

7.1.1 Problems with direct addressing

ARM: both instructions and addresses are 32 bits, but the instruction also specifies operation so it can't contain every possible address.

Solution: allow a register to contain an address, use the address in the register to do loads and stores.

This is Register Indirect Addressing

7.2 Register Indirect Addressing

The address is held in the register

It takes only a few bits to select a register (4 bits in the case of ARM R0-R15)

A register can (typically) hold an arbitrary address (32 bits in the case of ARM)

ARM has register indirect addressing

Example loading a register from a memory location: LDR R0, b

Could be done using register indirect addressing:

ADR R2, b Move the **address** of b into R2

LDR R0, [R2] Use address in R2 to fetch the **value** of b

This is still a bit limited - addresses are:

- range limited (within ADR 'instruction')
- fixed

but:

- ADRL pseudo-op allows larger range (at a price)
- having addresses a variable once it is often used again
- variable are usually 'near' each other

7.2.1 Address Arithmetic

We can operate on registers, so we can:

- store/load/move addresses
- do arithmetic to calculate addresses

Rather than use e.g. extra ADD instructions, we often use **Base + Offset Addressing** - address addition done within the operand.

We have actually been using this all along: Base = PC register.

7.3 Offset Addressing

In offset addressing the address is calculated from a register value and a number.

The register specifier is just a few bits, The offset can be 'fairly small'.

With one register 'pointer' any of several variables in nearby addresses may be addressed.

ARM allows offsets of 12 bits in LDR/STR

These bits can be added or subtracted, for example:

LDR R0, [R1, #8] STR R3, [R6, #-0x240] LDR R7, [R2, #short-constant]

This provides a range of \pm 4 kilobytes around a 'base' register

In practice this method is adequate for most purposes.

8 Strings, bit shifts, rotations and tables

8.1 Working with Strings

A String is just a list of bytes where each byte represents a character. The last byte in the list is the null byte which contains the value 0.

8.1.1 Loading a String

In order to load the String into a register, the ADRL command must be used, for example:

```
1 msg DEFB "My message", 0
```

2 ALIGN

4 ADRL RO, msg

5 SVC 3

8.1.2 Finding the length of a String

In order to find the length of a String, we need only to loop over each byte in the String until we get to the null byte, and add up how many iterations we've done as we go along:

- 1 ADRL R1, message
- 2 MOV R2, #0
- ³Here, we use RI to store the message, RO to read each char-
- CMP RO, #0 acter, and R2, to keep the count. ADDNE R2, R2, #1
- 6 BNE count

78.1.3TRGetting that index of a character in a String

In order to do the equivalent of

String.indexOf(character), we can do something similar to finding the length of the String, but we only need to loop until we get to the character we're looking for.

- 1 ADRL R1, message
- 2 LDRB R2, character
- 3 count LDRB RO, [R1] #1
- 4 CMP RO, #0
- 5 BEQ end
- 6 CMP RO, R2
- 7 BNE count
- 8 end ADRL RO, message
- 9 SUB R1, R1, R0

character has been found.

SUB R1, R1, #1 118.2 STBites, hifting and rotations

Shift operations move all the bits in a word in one direction or another. For example:

Shift direction	Resultant word
No shift	10011011
Left shift	00110110
Right shift	01001101

Shifting to the left is like multiplying by two, and shifting to the right is like dividing by two.

You might have noticed that a zero is appended to whatever side the bits are moving away from in order to ensure that the word is still the same number of bits as before.

Rotation operations are very similar to shift operations, except instead of padding the word with zeroes, the bit that was lost is appended to the other side of the word:

Rotation direction	Resultant word
No rotation	10011011
Left rotation	00110111
Right rotation	11001101

ARM has four different operations for shifting and rotations:

Mnemonic	Meaning	Function
LSL n	Logical shift left	Shifts left by n bits.
		Any bits that are
		lost are zeroed.
LSR n	Logical shift right	Shifts right by n
		bits. Any bits that
		are lost are zeroed.
ASR n	Arithmetic shift	Shifts right by n
	right	bits. Any bits that
		are lost are set as the
		sign bit (to preserve
		the signed bit).
ROR n	Rotate Right	Rotates right by n
		bits.

8.3 Accessing a row in a table

We can use bit shifts to access a row in a table:

```
ADRL R1, table
1
     LDR
          R2, [R1, R0, LSL #2]
2
3
    table
            DEFW
4
                   0
     DEFW
            3
5
            6
6
     DEFW
            9
     DEFW
7
           12
8
     DEFW
           15
     DEFW
9
```

18

DEFW

10

This snippet will allow us to access the row with an index stored in R0, so if R0 was 2 then the output in R2 would be

9 Stacks

A stack is a data structure that is used by ARM assembly (an in a variety of other computing applications) to help maintain the state of a program.

The only operations that can be performed on a Stack are push and pop. The former adds an item onto the stack and the latter removes the last item from the stack. Because these are the only two operations, a Stack is a type of *Last In First Out* data structure.


is usually initialised using the DEFS command to reserve a block of space in memory. This means that the stack will be a fixed size.

In ARM assembly, one register is reserved as the Stack Pointer (SP). This keeps track of the memory location that addresses the last item in the stack.

Stacks can be implemented where the stack pointer starts at the highest memory address in the range allocated to the stack, or where it starts at the bottom. In ARM assembly, it is usual to start the stack pointer at the highest address and work down.

9.1 Pushing to a stack

Lets initialise a stack of five memory locations:



The stack pointer will currently be pointed at 0x00000420, so the next stackable memory location will be 0x00000416.

If we want to push an item onto the stack, we need to do two things:

- Write the value to the current memory location addressed by the stack pointer.
- Decrement the stack pointer by 4


The ARM command for a stack push is PUSH. An example might be:

PUSH \#20


Or if you wanted to push one or more registers:

PUSH R1, R2, R3

If we executed the first of these commands (PUSH #20), the stack would look like this:



Executing PUSH R2, R3 when the values of R2 and R3 were 523 and 8 respectively would result in a stack such as:




9.2 Poping from the stack

The ARM syntax to pop an item from the stack is very similar. To pop the last item from the stack into R1 the command would be:

POP R1

The stack would now look like:



Note that we don't actually have to reset the memory location 0x00000408 since it will be overwritten on any subsequent push and since the stack pointer is behind it, it will never be read from.

And the value of R1 would be 8. This works for multiple registers too just like the PUSH command does.

9.3 Other ways of accessing the stack

It's important to remember that the stack is just a set of memory locations, and the stack pointer is just a normal register. This means that other commands for accessing memory can also be used to access and manipulate the stack. For example, take a look at this block:

```
1 LDR R1, SP
2 ADD SP, SP, #4
```

Of course, we could use post indexed addressing in order to do the same thing: LDR R1, [SP], #4

This will load the value of the memory location addressed by the value inside the stack pointer into R1 and then increment the stack pointer by 4. Essentially, this is doing the same thing as POP R1 will do.

In order to do the same thing for pushing to the stack we can do:

```
1 SUB SP, SP, #4
2 STR R1, SP
```

Which is equal to STR R1, [SP, #-4]!

9.4 Stacks and method calls

It is important that when a program branches from one method to another, the values stored in the registers are not overwritten for when the program branches back to the original method. This problem is resolved by pushing the values stored in the registers onto the stack before a branch is made, and then poping them off the stack once the method has finished executing. Alternately, the method that is being called can preserve the values in the registers by pushing and poping them to and from the stack at the start and the end of the method. Obviously, only one such method needs to be employed, so it's best to stick to one convention for the whole program.

10 Methods

The most basic way of calling a method in ARM assembly is by using the BL command. This will do two things:

- 1. Move the current value of the program counter into the link register.
- 2. Branch to the label defined in the instruction.

The method being called will use move the value of the link register back into the program counter once it has finished execution. Here's an example:

```
1
2  start B main
3
4  add R1R2 ADD R1, R1, R2
5  ; Move the value of the Link
6  ; Register back into the PC
7  MOV PC, LR
8
```

```
9 main MOV R1, #4
10 MOV R2, #2
11 BL addR1R2
12
```

This program will move the values 4 and 2 into R1 and R2 respectively, and then branch to a method that will add the two registers together and store the result in R1.

10.1 Saving the value of registers

What if a method used lots of registers internally. We should make sure that the state of the registers is the same at the end of the method as they are at the start of the method, since otherwise there could be issues with corrupted data.

The easiest way to do this is to stack the parameters, like so:

```
1
    method
2
     ; First lets store the registers
     ; we're going to use into memory
3
          \{R.0-R.2\}
     PUSH
4
       5
     ; Do stuff with the registers
6
7
     POP {R0-R2}
8
     ; Branch back to the calling instruction
9
     MOV PC, LR
10
```

If a method calls another method, then the link register will need to be stacked too!

10.2 Passing parameters


Passing parameters to a method is easy; just add them to the stack! To do this, just load the variable into a register, then add it to the stack:

```
1 LDR RO, myvar
2 STR RO, [SP,#-4]!
```

When the method wants to access a parameter, it can just load the value in memory addressed by the stack pointer, adding an offset of #4 if the second parameter needs to be accessed, #8 for the third and so on. If the fourth parameter was to be loaded, then the instruction would be LDR RO [SP, #12].

10.3 Stack frames

A stack frame is a set of stacked values that are related to a particular method call. They usually have a format that is specific to the method being called. For example:



11 Switch statements

Obviously, a switch statement could be compiled down to a series of if else statements and then converted into ARM assembly. However, if we had a long list of conditions, and our condition was either near the bottom of the list, or maybe even the default choice, then we'd need to test the switch expression against all of the conditions before being able to decide what to do.

This has the potential to be very inefficient, so thankfully, there is another way to do it. We can use the value of the switch variable to branch directly to the piece of code that we want to execute for that case.

This can be achieved using a table of values where the offset in the table corresponds to the next address to load into the PC (i.e. the branch location). For example: The LSL command is used to shift the bits in R1 left. The number of places shifted is equal to the value of R0. This has the effect of adding (4*R0) onto R1.

```
: Define a table of variables with
1
     : the locations to branch to
2
3
    swtable DEFW case0
     DEFW case1
4
     DEFW default
5
     DEFW case2
6
7
     : Load the base address of the table
     ; into R1
8
    ADR R1. swtable
9
     : Load the value of R1 into the PC.
10
     ; Offset the value in R1 by (R0*4)
11
12
     LDR PC, [R1, R0, LSL, #2]
13
    case0 ; Do stuff
14
     B end
15
16
    case1 ; Do stuff
17
     B end
18
19
    case2 ; Do stuff
20
     B end
21
22
    default ; Do stuff
23
```

B end

24

It's important to catch cases where the expression isn't in the table too, for example, if (following the previous example) the values we wanted to implement specific logic for were (0, 1, 3), then we would need to catch cases where the value was less than 0 and greater than 3.

- 1 CMP RO, #0
- 2 BLT default
- 3 CMP RO, #3
- 4 BGT default

The above would go before the table lookup would occur.

12 Types of values

12.1 Signed and unsigned integers

Lets assume that integers only have 8 bits, and so can hold 2^8 (256) different values. If we use a signed integer, the most significant bit would indicate whether the number was negative or not. This means that we loose a bit's worth of data and therefore can only represent the numbers 0-128, though we do gain the ability to distinguish negative numbers from positive numbers.

As you should already know, using a signed integer is also known as 2's complement.

Note that the numbers 0-127 are represented as the same as both signed and unsigned integers, however, when a number reaches the value 128, then as a signed integer it would mean -1 and as an unsigned integer it would mean 128.

It is important to note, that ARM has different types of compare instructions for signed and unsigned integers. We

can use this to our advantage in the switch example outlined in the previous section (see page).

If we treat the register RO as a signed integer, we will have to check whether it is below 0 and whether it's above 4. However, if we use unsigned comparisons, we only need to check whether the register is above 4 since any negative value will be represented as a positive value much larger than 4!

- 1 CMP RO, #4
- 2 BHI default

12.2 Booleans in ARM assembly

Since a boolean value is either true or false, it is obvious that we only need a minimum of one bit to represent it. However, due to the difficulties of accessing just one bit in the ARM architecture, it actually make more sense to represent a boolean as a byte, where the least significant bit is either 1 or 0 depending on the value of the boolean.

This is easy, since it means that booleans are represented as the integers 0 and 1. Testing a boolean value is easy too, since all you need to do is compare it to zero or one.

CMP R1, #0

12.2.1 Logical operators in ARM

ARM assembly implements four logical operators:

- AND (logical AND)
- ORR (logical OR)
- EOR (logical XOR)
- BIC (bit clear)
- MVN (logical not)

All of these are self explanatory except from the bit clear one, which is explained using a table:

A	В	BIC A B
0	0	0
0	1	0
1	0	1
1	1	0

BIC is equivalent to A & !B. If B is high, then the output will be 0, otherwise, it will be A.

13 Communicating with Peripherals

A peripheral is a device that is attached to a computer. This could be a keyboard, mouse, printer or arguably even the main memory of the computer.

There are two methods of interfacing with peripherals; polling and interrupts.

13.1 Polling

Polling is where the CPU will constantly check for an update from a peripheral. This involves using a loop to check the contents of a status register and then reading any data from the peripheral.

The status register is a memory mapped register that both the CPU and peripheral have access to. When the peripheral has data to transfer to the CPU, it will change the value of the status register to match a specific pattern (usually setting just one bit in the register). For example, the test pattern may be setting bit 7 high. Next time the CPU checks the status register, if bit 7 is high, then it will know there is data waiting for it.

If this is the case, then the CPU will then read the data register. This is also a memory mapped register, and will contain the data from the peripheral.

13.1.1 Memory mapping

A memory mapped register appears to be located at a specific memory location, but instead actually is situated inside the peripheral and is *mapped* so that it appears to be at a memory address.

13.1.2 Implementing polling

In this simple implementation of a polling loop, we're assuming that the status_register and data_register have

already been set up as aliases to the correct memory locations.

```
; Load the program relative
1
      ; address into R1
2
3
      ADR R1, status_reg
     loop
4
      ; Use R1 as a pointer to
5
      : load the data in the status
6
      ; register into RO
7
      LDR RO. [R1]
8
      ; Test the content of the
9
      ; status register
10
      TST RO, 0x80
11
      ; Loop if the test failed
12
13
      BEQ loop
      : Load the content from the
14
      ; data register into RO
15
      ADR R1, data_reg
16
      LDR RO, [R1]
17
```

13.1.3 The TST instruction

TST performs a bitwise AND on it's operands (a register and a literal test pattern). It then updates the flags for a subsequent conditional instruction. If the result of the AND was zero, then subsequent EQ conditional instructions will execute - i.e. it compares the result of the AND operation to zero.

Using the example in the polling implementation, lets execute the command TST RO, 0x80, first where the test con-

dition is not met, and then when it is:

Content of R0	00000000
Test pattern	10000000
Result	00000000
C	10110100
Content of R0	10110100
Content of R0 Test pattern	10110100 10000000 10000000

In the second run, you can see that the result isn't zero, so the test pattern must have been met.

13.2 Interrupts

Unlike the polling method, and interrupt is initiated by the peripheral rather than the CPU. It follows the following steps:

- 1. Stop the program This is often done by the interrupt automatically, and works just like a branch and link.
- 2. Save important registers The STMFD command can be used to save important register. This would include the current program status register (CSPR) and any registers modified by the interrupt handler.
- 3. Run the interrupt handler This would usually involve double checking the status register to make sure that the data is ready to be read and then reading the data inside the data register.
- 4. Restore the saved registers Use LDMFD to restore the registers just like we did to save them.

5. **Restart the program** Copy the Link register into the program counter and add on #4 so that the next instruction is executed and the program carries on as before.

13.2.1 An implementation of an interrupt

This is how an interrupt may be implemented:

```
; Stage 1 has already happened
1
     ; When we branched here
2
    interrupt
3
      ; Stage 2 - save registers
4
     STMFD SP!, {RO, R1}
5
      ; Stage 3 - run the interrupt
6
      ; handler
7
8
      ; Check the status_reg
9
           R1, status_reg
     ADR.
     LDRB RO. [R1]
10
     TST RO, #0x80
11
12
     ; Go to an error if the
     ; TST failed
13
14
     BEQ error
      ; Load the data_reg info
15
     ADR.
           R1, data_reg
16
     LDRB RO, [R1]
17
      ; Store the data_reg info
18
     LDR R1, data
19
     STR RO, [R1]
20
     ; Acknowledge the transfer
21
           R1, acknowledge
22
     LDR.
```

STR #1, R1

23

```
; Step 4 - restore the
24
      ; registers
25
      LDMFD SP!, {RO, R1}
26
      ; Step 5 - Branch back to
27
      : were we came from
28
      SUBS PC, LR, #4
```

29

Having multiple interrupts 13.2.2

An interrupt vector table can be used to select the correct address to branch to when multiple interrupts are in place. All that is needed is a table of pointers to various methods for handling the different peripherals. Then, it's easy to find the correct peripheral by using the value set in the status register as an index in the table.

How an SVC call works 13.2.3

We know that an SVC call is a software *interrupt*. This means there will be an interrupt handler that will be called to do something once the SVC instruction is executed. However, we include a parameter between 0 and 4 when we use a software interrupt, and this parameter defines the exact behaviour of the interrupt.

How then, does the interrupt handler know what parameter was used then? Well, these are the processes that go on when an SVC call happens:

1. Branch an link to the interrupt handler, save registers using STMFD SP, RO-R2, LR.

- 2. Load the link register into a register and take off #4. This will be the SVC X instruction. LDR RO, [LR, #-4]
- 3. Clear the top eight bits (the conditional code and the instruction code). Use BIC RO, RO, 0xFF000000
- 4. Logic shift right by 8 places (this will give us the 16 bit parameter, with the upper 16 bits all zeroed) LSR R1, R0, #8.
- 5. Load the start of the interrupt vector table into R2: LDR R2, vector_table
- 6. Now, we should load the interrupt into the PC with an offset of R1 * #4 using LDR PC, [R2, R1, LSL #4]
- 7. We can finally restore the registers using LDMFD SP, RO-R2, PC. At the same time, we can set the PC back to where it was.

13.3 Direct Memory Access

Direct Memory Access (DMA) is a way of avoiding excess CPU overhead for data transfer between peripherals. If each interrupt takes 100 instructions to execute, and data is being sent byte by byte to the processor, then the process may use up a lot of CPU time, especially if there's lots of data being transferred.

The solution to this is to have an external, hardware based solution on the motherboard with access to memory. This will take care of the interrupts for us instead of the CPU. This allows peripherals to write directly to memory rather

than having to go through the CPU. The hardware controller can give the CPU an interrupt once every kilobyte or so is written, which would reduce the load on the CPU by 1000 times.

DMA is good, since it reduces load on the CPU, and enables greater parallelization, however, it requires extra hardware which makes the system more complicated. Besides, the memory of the computer and the peripheral itself are still doing the same amount of work; only the load on the CPU has been lessened.

14 Operating systems

Most operating systems consist of four elements; a stack, a kernel, multiple libraries for programs to use and a user interface.

14.1 The Kernel

The kernel is responsible for abstracting the implementation details of the hardware that the operating system is sitting on top of away so that programs and applications can interface with it more easily. It also protects programs from each other, so that one program cannot access another programs memory space. This is an important security feature, and it is important that the kernel cannot be bypassed.

14.1.1 Kernel modes

Most kernels have multiple different processing *modes* that will allow programs different privileges. The default mode is usually the *user* mode where programs can only access memory in their allocated space. There is also a *privileged* mode where programs can access any memory address. ARM has an *interrupt* mode too handle interrupts from peripherals.

15 Methods of running code

15.1 Compilers and assemblers

The job of compilers and assemblers is to convert human readable source code into machine executable code (often referred to as *machine code*). There are a number of steps associated with compilation:

Note that this process is referred to assembly when its assembly code that is being transformed, and compilation when it's higher level code such as Java, LISP or C++.

1. Lexical analysis is when the source code is broken down into tokens (groups of one or more characters that represent something, like a parameter, punctuation, operands etc). This is where comments are filtered out of the source code; they are not included in the tokens.

- 2. **Syntaxic analysis** checks that the tokens are formed so that together, they form structures in the correct syntax for the language of the code. This means checking that method calls have the right number of parameters, semicolons are in the correct place, etc.
- 3. **Semantic analysis** makes sure that the code makes sense; it'll check the types of variables, check that programmer defined names and definitions are legal and so on.
- 4. Code generation. If the compilation process gets this far, then the code is all correct and will run. All that remains now is to convert it into machine readable code. This can be in a variety of different formats, such as bytecode for Java or machine code if Assembly languages are being assembled.
- 5. **Optimisation** is an important part of compilation. Only higher level languages have any optimisation built into their compilation process though; most assemblers don't do it (since they rely on the human programmer doing so).

15.2 Interpreters

An interpreter reads code and executes it directly. This code can be written either by hand in a language such as Python, or it can have been assembled or compiled such as with most assembly languages and compiled languages such as Java.

Here are some of the pros and cons about interpreters:

- Simple to implement.
- Code is very portable, the interpreter guarantees that certain functions will be available and they will be accessible in the same way on whatever system the interpreter is running on.
- Theoretically, interpreters are fairly secure, though exploits in the past have proven that implementing a secure interpreter isn't something to be taken lightly (take a look at Java!)
- Interpreters can be used to prototype new hardware, since they can emulate what the hardware would do.
- Debugging is very easy on an interpreter since a programmer would have full access to the stack and so could see the value of variables and memory locations all the time. It potentially also allows for code execution to be paused or stepped through.
- Interpreters are often seen as being slow since they are running on top of the *real hardware*, so there will invariably be some (often significant) overhead.
- It's often hard to simulate a real computer. While this may not always be desirable, if the interpreter is designed to mimic hardware exactly, then this is often very hard to implement.