# COMP15111 Notes

# Chris Williamson, Todd Davies

# October 28, 2013

# Contents

1	Lec	ture 1: Introduction	3						
	1.1	A Computational Model	3						
	1.2	Simple View Of A Computer	3						
		1.2.1 Memory	3						
		1.2.2 Bus	3						
		1.2.3 Processor	3						
	1.3	Three-address instructions	4						
		1.3.1 Three address example	4						
		1.3.2 Memory bottleneck	4						
	1.4	Registers	5						
	1.5	Instruction Styles	5						
		1.5.1 One address	5						
		1.5.2 Load-store	5						
<b>2</b>	Lec	ecture 2							
_	2.1	Assembly Language	6						
	2.2	ARM instructions	7						
	2.3	Transferring data between registers and memory	7						
	2.4	ARM processing instructions	7						
	2.5	ARM control instructions	8						
	2.6	Stored programs and the Program Counter	8						
	2.7	Fetch-Execute Cycle	8						
	2.8	Decision Making	8						
		2.8.1 An example	9						
	2.9	Allocating memory	9						
3	Lec	ture 3: Storing values	10						
4	Lec	ture 4: ARM assembly programming	10						
	4.1	· - · ·	10						
	4.2		10						
	4.3	Endianness	10						

	4.4	Addressing memory	11
	4.5	Instruction encoding	11
	4.6	Literals	12
		4.6.1 Negative literals	12
	4.7	Supervisor calls	12
	4.8	Pseudo instructions	12
	4.9	Loading an address into a register	13
	4.10	Directives	13
		4.10.1 Align	13
		4.10.2 Entry	13
		4.10.3 EQU	13
5	Lect	ture 5: Arithmetic	14
6	Lect	ture 6: If and While	14
7	Lect	ture 7: Addresses and Addressing	14
		Direct Addressing	14
		7.1.1 Problems with direct addressing	14
	7.2	Register Indirect Addressing	14
		7.2.1 Address Arithmetic	15
8	Offs	7.2.1 Address Arithmetic	15 <b>15</b>
9	Lect	et Addressing	15

# 1 Lecture 1: Introduction

### 1.1 A Computational Model

The simplest, earliest, commonest, most important computational model is the Von-Neumann Imperative Procedural Computer Model

According to this model, a computer can:

- 1. Store information
- 2. Manipulate the stored information
- 3. Make decisions depending on the stored information

# 1.2 Simple View Of A Computer

The simplest model of a computer can be represented as:

 $Memory \Leftrightarrow Bus \Leftrightarrow Processor$ 

### 1.2.1 Memory

Memory is a set of locations which can hold information, such as numbers(or programs). Each memory location has a unique (numerical) address, and there are typically thousands of millions of different locations. There are various ways of depicting memory; a common one is a 'hex dump' that often looks something like this:

Address Values (8 bit numbers) Characters 00000000 48 65 6c 6c 6f 0a Hello.

Each item that is in the memory has a unique address.

Run the command hexdump to generate hexdumps.

### 1.2.2 Bus

A bus is a bidirectional communication path. It is able to transmit addresses and numbers between components inside the computer.

# 1.2.3 Processor

The processor obeys a sequence of instructions, commonly referred to as a program. Historically the processor was often referred to as a CPU, however, this is inappropriate nowadays since typical processors consist of several processing cores.

#### 1.3 Three-address instructions

Every kind of processor has a different set of instructions, real world examples include: Pentium, ARM and others

Each three-address instruction:

- 1. Copies the values from any two memory locations and sends them to the processor (source operands)
- 2. Copies some operation e.g. adds the copied numbers together
- 3. Copies the result back from the processor into a third memory location (destination operand)

For example, if we wanted to convert the Java code sum = a + b; into a three-address instruction we would:

- 1. Identify the two source operands: a holds 2, b holds 3
- 2. Perform the operation: 2 + 3 = 5
- 3. Let the variable sum equal the answer 5. This is the destination operand

### 1.3.1 Three address example

**Question:** Convert the Java code product = c \* d; into the three-address style and draw a two box view of it.

First we need to re-write the Java code in the three-address style:

$$product \leftarrow c * d$$

Now we can draw the box view of it:

#### 1.3.2 Memory bottleneck

Most processors can process instructions faster than they can be fed by memory. Each instruction in the three-address cycle requires four memory cycles:

- 1. Fetch the instruction
- 2. Read the first operand
- 3. Read the second operand
- 4. Write the result to memory

Each of these memory cycles could take hundreds of processor clock cycles to complete, and so in this time the processor would be doing nothing. However, most modern processors employ a *cache* to temporarily store commonly accessed memory locations, and so avoid some of the memory cycles.




Figure 1: An example of the two box model

# 1.4 Registers

Registers are very small amounts of storage build into a processor. Since they are inside the processor data doesn't need to be transferred over the bus, and so they are very fast. Registers are used instead of the main memory which speeds up program execution.

Each register can only hold one value and each processor will only generally have a few dozen registers (e.g. ARM has sixteen).

# 1.5 Instruction Styles

# 1.5.1 One address

The one address style can only use up to one memory location in each instruction, all other operands must be registers. An example may be:

$$R1 \leftarrow R0 + memory\ location$$

### 1.5.2 Load-store

The load-store style cannot perform operations on memory locations at all. Instead, values from memory must be loaded into a registers before the operation takes place and then the operation can be performed on the registers. Following the operation, the result must be stored back into memory again.

$$R1 \leftarrow memory\ location$$
 
$$R1 \leftarrow R0 + R1$$
 
$$memory\ location \leftarrow R1$$

This means that we need extra instructions to do stuff with memory locations:

- 1. **Load** the value from memory into a register before the operation.
- 2. **Store** the value in the register back to memory after the operation.

For example, the Java code Sum = a + b + c; would be run as:

```
R1
                          (i.e. load from a)
R2
            b
                          (i.e. load from b)
R3
       \leftarrow R1 + R2
                                 (i.e. a+b)
R4
                          (i.e. load from c)
            ^{\rm c}
R5
            R3 + R4
                            (i.e. (a+b)+c)
Sum
            R5
                         (i.e. store to sum)
```

You can see that the load-store style favours lots of very simple, very fast instructions.

# 2 Lecture 2

Computers obey programs which are sequences of instructions. Instructions are coded as values in memory. The sequences are held in memory adjacent memory locations. Values in memory can be interpreted as you please, from numbers to text, to images or anything really!

Any given set of binary digits can be read as a decimal number, but not always as text, so values in memory are often represented as numbers for convenience.

# 2.1 Assembly Language

Assembly language is a means of representing machine instructions in a human readable form.

Each type of processor has its own assembly language (since each language is specific to a partial architecture) but they typically have a lot in common:

- A mnemonic, that specifies the type of operation
- A destination, such as a register or memory location

- And one or more sources that may be registers or memory locations.
- Possibly with a comment too which will help programmers understand what's happening and aren't interpreted by the assembler.

When a program has been written in assembler, it must be assembled by an assembler to run it.

### 2.2 ARM instructions

ARM has many instructions but we only need three categories:

- Memory operations that move data between the memory and the registers.
- Processing operations that perform calculations using value already in registers.
- Control flow instructions are used to make decisions, repeat operations etc.

### 2.3 Transferring data between registers and memory

Memory operations load a register from the memory or store a register value to the memory.

For example, a into register 1  $(R1 \leftarrow a)$  we would write: LDR R1, a

Or to store the value in register 5 into  $sum\ (sum \leftarrow R5)$ : STR R5, sum

In these examples, a and sum are aliases for the addresses of memory locations.

# 2.4 ARM processing instructions

ARM has many different instructions to perform operations such as addition, subtraction and multiplication.

The syntax for such operations is usually:

[operand] [destination register] [register 1] [register 2]

For example, to add two numbers together, we might write:

ADD R2, R0, R1

This will add the value of R0 to the value of R1 and store it in R2.

### 2.5 ARM control instructions

The most common control instruction is the branch. Similar to GOTO in other languages, a branch will change the PC register (see section 2.6) to another value so the order of execution of the program is changed.

Branches can be made to be conditional by appending a conditional operator (coming up later) on to the command.

The syntax is something like:

B[conditional operator] [branch name]

Some examples of different conditional operators are:

Command	Function
В	Branches to a different location in the code.
BNE	Branches, but only if the previous condition was false.
BEQ	Branches, but only if the previous condition was true.

### 2.6 Stored programs and the Program Counter

A computer can make decisions, and choose which instructions to obey next depending upon the results of those decisions. A **Program Counter** (PC) register is used to hold the memory address of the next instruction to be executed. ARM uses register 15 as its PC.

### 2.7 Fetch-Execute Cycle

The processor must first fetch instructions from memory before it can execute them. This is called the fetch-execute cycle, and it involves:

- 1. **Fetch**: copy the instruction, pointed to by the PC, from memory and set PC to point to the next instruction
- 2. **Execute**: obey the instruction (exactly as before)
- 3. Repeat.

In ARM, the PC starts with a values of 0x00000000 when the program is initially run. On each cycle of the Fetch-Execute cycle, the PC is incremented by 4, since instructions each occupy 4 memory locations.

# 2.8 Decision Making

In order to make decisions, the computer mustn't just execute instructions one after the other in a linear manner. Instead, branches must be used to change the sequence of instructions to be executed.

In order to perform a conditional branch, we must first perform a compare command to perform the comparison before we do the branch.

### 2.8.1 An example

If we wanted to do a 1 discount on a shopping list if the price was over 20, we would do the following:

```
LDR RO, total; Load the total price into RO

CMP RO, #20; Compare RO and 20 (the literal)

BLT nodiscount; If the price is too low, then don't discount

SUB RO, #1; Deduct 1

STR RO, total; Store the result back into memory

nodiscount SVC 2; Finish

total DEFW 25; Lets say the total is $25
```

# 2.9 Allocating memory

The DEFW (define word) operation puts a value in memory before the program is run. Any define operation is executed before the program is run.

The actual memory location that is used to store the value isn't known to the running program, however, an *alias* is attached to the memory location by the programmer and the memory location can be referenced through that.

The syntax for the DEFW command is as follows:

```
myage DEFW 18
```

Where myage is the alias and 18 is the value.

DEFW can also be used to define a number of words:

```
squares DEFW 0, 1, 4, 9, 16, 25
```

DEFB stores a single byte in memory. It is useful for strings such as "hello":

```
hi DEFB "hello"
```

DEFS sets a block of bytes to a set value:

```
reserved_space DEFS 10, 5
```

The above will set 10 bytes to the value '5'.

The label is associated with the lowest address (i.e. 0)

# 3 Lecture 3: Storing values

# 4 Lecture 4: ARM assembly programming

### 4.1 Different types of values

ARM has the capacity to work with many different types and sizes of values. Each type has a different use case. The main ones are described below:

Name	$\mathbf{length}$	Use
Byte	8 bits	Used for characters
Word	32 bits	Used for integer es. addresses and instructions

There are other types too (such as the halfword and doubleword) but they aren't needed for this module.

ARM processors require that memory locations are aligned. This means that values stored in memory start at specific places. For example, a word address must be a multiple of four.

This means that after a DEFW statement, the ALIGN command must be called (See 4.10.1 for more on the ALIGN command.).

# 4.2 Loading and storing values in memory

The commands LDR and STR are used to move values between memory and registers. The commands are detailed in full below:

Command	Function
STR	Copies the whole (32 bit) register into memory.
LDR	Loads a 32 bit word from memory into a register.
STRB	Stores a single 8 bit byte into memory from a register.
LDRB	Loads a byte from memory into a register. The upper 24 bits
	of the register are zeroed.

#### 4.3 Endianness

Endianness is a property of a memory location that defines the order of the bits. There are two types of endianness, **little endian** and **big endian**.

In the word 0x12345678 there are four bytes:

- 0x12
- 0x34
- 0x56

#### • 0x78

In little endian, the first byte would be 0x12 since bits are read from left to right in little endian.

In big endian, the first byte would by 0x78 since bits are read from right to left in big endian.

This is important when we deciding what the most and least significant bits in a word are. For example, in this instance the lsb is 0x12 in little endian, but 0x78 in big endian.

In this course, little endian is used, though ARM can use either.

N.b. The least significant bit is the smallest address.

### 4.4 Addressing memory

ARM uses 32 bit addresses, so there are  $2^{32}$  different bytes that can be addressed in memory (or  $\frac{2^{32}}{4}$  different words). However, there is no guarantee that the system on which the program is running will have that much memory available.

# 4.5 Instruction encoding

Each ARM instruction is encoded into a four byte word. The exact meaning of each of the bits varies per instruction.

For example, in the branch instruction, the first four bits specify the condition, the second four bits represent the actual operation to perform (i.e. branch) and the remaining twenty four bits define the memory location of the next instruction to branch to.

However, this presents a problem. We only have twenty four bits with which to define the next location to branch to, which allows us to define  $2^24$  different locations. However, there are  $2^32$  possible addresses that we could use!

This problem is overcome by treating the 24 bits as an offset to the address of the current instruction. This works since most of the time, the address that is being branched to is fairly close to the current instruction.

In order to be able to branch to addresses before and after the current instruction, we must use two's complement to allow signed integers to be used to specify the offset. This means we can branch to any instruction at an address  $\pm 2^{23}$  from the current instruction.

### 4.6 Literals

ARM is able to encode literal values into instructions. This saves time having to access registers or memory in order to perform operations such as arithmetic.

An example is to increment a register:

```
ADD R1, R1, #1
```

However, ARM only assigns up to 12 bits for a literal value, so we can only have  $2^{12}$  values. However, ARM employs a strange method of encoding these values so that more useful values are available (for example, #512 is allowed, but #257 isn't).

### 4.6.1 Negative literals

Technically, ARM doesn't support negative literals, however, the assembler will usually be able to find a way to implement them. Some examples are given below:

```
ADD R1, #-1 \rightarrow SUB R1, #1 CMP R2, #-2 \rightarrow CMN R2, #2 MOV R3, #-3 \rightarrow MVN R3, #3
```

CMN is compare negative.
MVN is move not.

### 4.7 Supervisor calls

Supervisor calls are functions implemented by the operating system, not ARM itself. The parameter of an SVC call defines it's exact operation.

In this module, the SVC call does the following for each parameter:

SVC 0 Output a character
SVC 1 Input a character
SVC 2 Stop execution
SVC 3 Output a string
SVC 4 Output an integer

SWI is another name for SVC - they do the same thing.

#### 4.8 Pseudo instructions

The ARM assembler provides some instructions that are translated into sequences of more complicated instructions at the time of assembly for our convenience.

One such instruction is loading a literal into a register. This is done using the LDR command as usual, however a literal is used with the '=' character instead of a '#'. E.g. to load the value 100 into register one, we do:

```
LDR R1, =100
```

However, this is a pseudo instruction and will be converted by the assembler to:

```
MOV R1, #100
```

However, if the number is very large, it becomes:

```
constant DEFB 100 LDR R1, constant
```

# 4.9 Loading an address into a register

The ADR command loads an address into a register, for example:

```
constant DEFB 100 ADR R1, constant
```

Will load the memory address of constant into register one.

#### 4.10 Directives

Directives are evaluated at the time of assembly.

### 4.10.1 Align

The align command leaves as many blank bytes as needed so that the next item in memory will start at a word boundary (a multiple of 4).

### 4.10.2 Entry

Sets the PC at the start of the program (i.e. where the program should start from)

### 4.10.3 EQU

Allows you to name a literal, which can go a long way to making the code more maintainable. We could define the literal 18 as  $drinking_age$ :

```
drinking_age EQU #18
; Check the person is over 18
CMP R1, #drinking_age
BLT too_young
```

# 5 Lecture 5: Arithmetic

# 6 Lecture 6: If and While

# 7 Lecture 7: Addresses and Addressing

When a processor references memory it needs to produce an address.

The address needs the same number of bits as the memory address. i.e. 32 in ARM

addressing modes - mechanisms for generating addresses

# 7.1 Direct Addressing

Direct addressing is a mode where the address is simply contained within the instruction.

This requires an instruction longer than the address size which is a problem because ARMs maximum bit length is 32.

So far, we assumed that direct addressing uses LDR/STR instructions, for example:

LDR R0, b LDR R1, c ADD R0, R0, R2 STR R0, a

This looks like direct addressing but on ARM it's 'faked' by the assembler as a pseudo-instruction

### 7.1.1 Problems with direct addressing

ARM: both instructions and addresses are 32 bits, but the instruction also specifies operation so it can't contain every possible address.

Solution: allow a register to contain an address, use the address in the register to do loads and stores.

This is Register Indirect Addressing

### 7.2 Register Indirect Addressing

The address is held in the register

It takes only a few bits to select a register (4 bits in the case of ARM R0-R15)

A register can (typically) hold an arbitrary address (32 bits in the case of ARM)

ARM has register indirect addressing

**Example** loading a register from a memory location: LDR R0, b

Could be done using register indirect addressing:

```
ADR R2, b move the address of b into R2
LDR R0, [R2] use address in R2 to fetch the value of b
```

This is still a bit limited - addresses are:

- range limited (within ADR 'instruction')
- fixed

but:

- ADRL pseudo-op allows larger range (at a price)
- having addresses a variable once it is often used again
- variable are usually 'near' each other

#### 7.2.1 Address Arithmetic

We can operate on registers, so we can:

- store/load/move addresses
- do arithmetic to calculate addresses

Rather than use e.g. extra ADD instructions, we often use **Base + Offset Addressing** - address addition done within the operand.

We have actually been using this all along: Base = PC register.

# 8 Offset Addressing

In offset addressing the address is calculated from a register value and a number.

The register specifier is just a few bits, The offset can be 'fairly small'.

With one register 'pointer' any of several variables in nearby addresses may be addressed.

ARM allows offsets of 12 bits in LDR/STR

These bits can be added or subtracted, for example:

 $\begin{array}{lll} \mbox{LDR} & R0, & [R1, \, \#8] \\ \mbox{STR} & R3, & [R6, \, \#\text{-}0x240] \\ \mbox{LDR} & R7, & [R2, \, \#\text{short-constant}] \end{array}$ 

This provides a range of  $\pm~4$  kilobytes around a 'base' register. In practice this method is adequate for most purposes.

- 9 Lecture 8: Case study
- 10 Lecture 9: Stacks
- 11 Lecture 10: Methods, parameters, variables and stacks