### hessio 2018-01-03

Generated by Doxygen 1.8.13

# **Contents**

1	Intro	duction		1
	1.1	Introdu	action to the eventio/hessio libraries.	1
	1.2	Evention	o format documentation	2
	1.3	Utility a	and test programs in the hessio module	2
2	Mod	lule Inde	•x	3
	2.1	Module	es	3
3	Data	Structu	ure Index	5
	3.1	Data S	tructures	5
4	File	Index		9
	4.1	File Lis	st	9
5	Mod	lule Doc	eumentation	13
	5.1	The ad	ld_histograms program	13
		5.1.1	Detailed Description	13
		5.1.2	Function Documentation	13
			5.1.2.1 main()	13
	5.2	The be	est_of program	14
		5.2.1	Detailed Description	15
	5.3	The fca	at program	16
		5.3.1	Detailed Description	16
	5.4	The list	t_histogram program	17
		5.4.1	Detailed Description	17

ii CONTENTS

	5.4.2	Function Documentation	17
		5.4.2.1 main()	17
5.5	The ch	eck_trgmask program	18
	5.5.1	Detailed Description	18
5.6	The ex	tract_hess program	19
	5.6.1	Detailed Description	19
	5.6.2	Function Documentation	19
		5.6.2.1 main()	19
5.7	The ex	tract_simtel program	20
	5.7.1	Detailed Description	21
	5.7.2	Function Documentation	21
		5.7.2.1 check_autoload_trgmask()	21
	5.7.3	Variable Documentation	22
		5.7.3.1 map_to	22
		5.7.3.2 tel_idx	22
		5.7.3.3 tel_idx_out	22
5.8	The ge	en_trgmask program	23
	5.8.1	Detailed Description	23
5.9	The me	erge_simtel program	24
	5.9.1	Detailed Description	25
	5.9.2	Function Documentation	25
		5.9.2.1 check_autoload_trgmask()	25
		5.9.2.2 stop_signal_function()	26
	5.9.3	Variable Documentation	26
		5.9.3.1 map_to	26
		5.9.3.2 tel_idx	26
		5.9.3.3 tel_idx_out	26
5.10	The rea	ad_hess (aka read_simtel, read_cta) program	27
	5.10.1	Detailed Description	28
	5.10.2	Macro Definition Documentation	28

CONTENTS

		5.10.2.1 CALIB_SCALE [1/2]	28
		5.10.2.2 CALIB_SCALE [2/2]	28
	5.10.3	Function Documentation	28
		5.10.3.1 main()	28
		5.10.3.2 stop_signal_function()	28
5.11	The rea	ad_hess_nr program	30
	5.11.1	Detailed Description	30
	5.11.2	Macro Definition Documentation	30
		5.11.2.1 CALIB_SCALE	30
	5.11.3	Function Documentation	30
		5.11.3.1 calibrate_pixel_amplitude()	31
		5.11.3.2 main()	31
		5.11.3.3 stop_signal_function()	31
5.12	The sp	lit_hessio program	32
	5.12.1	Detailed Description	32
	5.12.2	Function Documentation	32
		5.12.2.1 main()	32
		5.12.2.2 stop_signal_function()	32
5.13	The hd	ata2hbook program (cvt2)	34
	5.13.1	Detailed Description	34
	5.13.2	Function Documentation	34
		5.13.2.1 main()	34
5.14	The hd	lata2root program (cvt3)	35
	5.14.1	Detailed Description	35

iv CONTENTS

6	Data	Structi	ire Docum	nentation	37
	6.1	basic_i	ntuple Stru	ct Reference	37
		6.1.1	Detailed I	Description	38
		6.1.2	Field Doo	eumentation	39
			6.1.2.1	acceptance	39
			6.1.2.2	alt	39
			6.1.2.3	alt_true	39
			6.1.2.4	az	39
			6.1.2.5	az_true	39
			6.1.2.6	chi2_e	40
			6.1.2.7	lg_e	40
			6.1.2.8	lg_e_true	40
			6.1.2.9	mdisp	40
			6.1.2.10	mscrl	40
			6.1.2.11	mscrw	41
			6.1.2.12	n_fail	41
			6.1.2.13	n_img	41
			6.1.2.14	n_pix	41
			6.1.2.15	n_trg	41
			6.1.2.16	n_tsl0	41
			6.1.2.17	primary	42
			6.1.2.18	rcm	42
			6.1.2.19	run	42
			6.1.2.20	sig_e	42
			6.1.2.21	sig_mscrl	42
			6.1.2.22	sig_mscrw	42
			6.1.2.23	sig_theta	43
			6.1.2.24	sig_xmax	43
			6.1.2.25	theta	43
			6.1.2.26	tslope	43

CONTENTS

		6.1.2.27	tsphere	 . 43
		6.1.2.28	weight	 . 43
		6.1.2.29	xc	 . 44
		6.1.2.30	xc_true	 . 44
		6.1.2.31	xfirst_true	 . 44
		6.1.2.32	xmax	 . 44
		6.1.2.33	xmax_true	 . 44
		6.1.2.34	yc	 . 44
		6.1.2.35	yc_true	 . 45
6.2	best_v	alue Struc	ct Reference	 . 45
6.3	Binary	_Interface	e_Chain Struct Reference	 . 46
6.4	FloatC	ompresso	pr::Bits Union Reference	 . 46
6.5	Float1	6Compres	ssor::Bits Union Reference	 . 47
6.6	bunch	Struct Ref	ference	 . 47
	6.6.1	Detailed	Description	 . 47
6.7	camera	a_nb_list S	Struct Reference	 . 48
6.8	compa	ct_bunch	Struct Reference	 . 48
	6.8.1	Detailed	Description	 . 49
6.9	Config	_Binary_It	tem_Interface Struct Reference	 . 49
	6.9.1	Detailed	Description	 . 49
	6.9.2	Field Do	ocumentation	 . 50
		6.9.2.1	copy_func	 . 50
		6.9.2.2	delete_func	 . 50
		6.9.2.3	elem_size	 . 50
		6.9.2.4	io_item_type	 . 50
		6.9.2.5	list_func	 . 50
		6.9.2.6	new_func	 . 51
		6.9.2.7	read_func	 . 51
		6.9.2.8	readtext_func	 . 51
		6.9.2.9	write_func	 . 51

vi

6.10	config_	specific_d	data	Struct	Refe	eren	се	 	51							
6.11	Configl	BlockStruc	ct Str	ruct Re	efere	ence		 	52							
	6.11.1	Detailed	Des	criptio	n .			 	52							
6.12	Configl	Boundary	Unio	n Ref	eren	се		 	53							
	6.12.1	Detailed	Des	criptio	n .			 	53							
6.13	Configl	DataPointe	er Ur	nion R	efere	ence		 	53							
	6.13.1	Detailed	Des	criptio	n.			 	53							
6.14	ConfigI	ntern Stru	uct R	eferer	ice.			 	54							
	6.14.1	Detailed	Des	criptio	n .			 	54							
	6.14.2	Field Doo	cume	entatio	n .			 	55							
		6.14.2.1	boı	und .				 	55							
		6.14.2.2	ele	m_siz	œ.			 	55							
		6.14.2.3	ityp	эе .				 	55							
		6.14.2.4	lbo	und_h	nard			 	55							
		6.14.2.5	lbo	ound_s	soft .			 	55							
		6.14.2.6	loc	ked .				 	56							
		6.14.2.7	ubo	ound_	hard	١		 	56							
		6.14.2.8	ubo	ound_	soft			 	56							
		6.14.2.9	val	ues .				 	56							
6.15	ConfigI	temStruct	t Stru	ıct Re	ferer	nce		 	57							
	6.15.1	Detailed	Des	criptio	n .			 	58							
	6.15.2	Field Doo	cume	entatio	n .			 	58							
		6.15.2.1	dat	ta .				 	58							
		6.15.2.2	flag	gs .				 	58							
		6.15.2.3	fun	iction .				 	58							
		6.15.2.4	init	ial .				 	59							
		6.15.2.5	inte	ernal .				 	59							
		6.15.2.6	lbo	und				 	59							
		6.15.2.7	naı	me				 	59							
		6.15.2.8	res	s <b>1</b>				 	59							

CONTENTS vii

6.15.2.9 res2	59
6.15.2.10 size	60
6.15.2.11 type	60
6.15.2.12 ubound	60
6.15.2.13 validate	60
6.16 ConfigValues Struct Reference	60
6.16.1 Detailed Description	61
6.16.2 Field Documentation	61
6.16.2.1 binary_config	61
6.16.2.2 data_changed	61
6.16.2.3 data_saved	62
6.16.2.4 elem_size	62
6.16.2.5 elements	62
6.16.2.6 itype	62
6.16.2.7 list_mod	62
6.16.2.8 max_mod	62
6.16.2.9 mod_flag	63
6.16.2.10 name	63
6.16.2.11 nmod	63
6.16.2.12 section	63
6.17 ebias_cor_data Struct Reference	63
6.18 ev_reg_chain Struct Reference	64
6.18.1 Detailed Description	64
6.19 Float16Compressor Class Reference	64
6.20 FloatCompressor Class Reference	65
6.21 hess_all_data_struct Struct Reference	66
6.21.1 Detailed Description	67
6.22 hess_aux_analog_trace Struct Reference	67
6.23 hess_aux_digital_trace Struct Reference	68
6.24 hess_camera_organisation_struct Struct Reference	68

viii CONTENTS

6.24.1 Detailed Description	69
6.25 hess_camera_settings_struct Struct Reference	69
6.25.1 Detailed Description	70
6.25.2 Field Documentation	70
6.25.2.1 mirror_area	70
6.26 hess_camera_software_setting_struct Struct Reference	70
6.26.1 Detailed Description	71
6.26.2 Field Documentation	71
6.26.2.1 zero_sup_mode	71
6.27 hess_central_event_data_struct Struct Reference	72
6.27.1 Detailed Description	73
6.27.2 Field Documentation	73
6.27.2.1 teldata_pattern	73
6.27.2.2 teltrg_pattern	73
6.27.2.3 teltrg_time	73
6.28 hess_event_data_struct Struct Reference	74
6.28.1 Detailed Description	74
6.29 hess_laser_calib_data_struct Struct Reference	75
6.29.1 Detailed Description	75
6.29.2 Field Documentation	75
6.29.2.1 calib	75
6.29.2.2 max_int_frac	75
6.29.2.3 max_pixtm_frac	76
6.30 hess_mc_event_struct Struct Reference	76
6.30.1 Detailed Description	77
6.30.2 Field Documentation	77
6.30.2.1 aweight	77
6.31 hess_mc_pe_list Struct Reference	77
6.31.1 Detailed Description	78
6.32 hess_mc_pe_sum_struct Struct Reference	78

CONTENTS

	6.32.1	Detailed Description	. 78
	6.32.2	Field Documentation	. 78
		6.32.2.1 photons_atm_qe	. 79
6.33	hess_n	mc_photons Struct Reference	. 79
	6.33.1	Detailed Description	. 79
6.34	hess_n	mc_run_header_struct Struct Reference	. 80
	6.34.1	Detailed Description	. 81
	6.34.2	Field Documentation	. 81
		6.34.2.1 shower_prog_id	. 81
6.35	hess_n	mc_shower_profile_struct Struct Reference	. 81
	6.35.1	Detailed Description	. 82
	6.35.2	Field Documentation	. 82
		6.35.2.1 id	. 82
6.36	hess_n	mc_shower_struct Struct Reference	. 83
	6.36.1	Detailed Description	. 84
	6.36.2	Field Documentation	. 84
		6.36.2.1 primary_id	. 84
		6.36.2.2 xmax	. 84
6.37	hess_p	pixel_calibrated_struct Struct Reference	. 84
6.38	hess_p	pixel_disabled_struct Struct Reference	. 85
	6.38.1	Detailed Description	. 85
6.39	hess_p	pixel_list Struct Reference	. 85
	6.39.1	Detailed Description	. 85
	6.39.2	Field Documentation	. 85
		6.39.2.1 code	. 86
6.40	hess_p	pixel_setting_struct Struct Reference	. 86
	6.40.1	Detailed Description	. 87
6.41	hess_p	pixel_timing_struct Struct Reference	. 87
	6.41.1	Field Documentation	. 88
		6.41.1.1 granularity	. 88

CONTENTS

6.41.1.2 pulse_sum_glob	88
6.41.1.3 pulse_sum_loc	88
6.41.1.4 threshold	88
6.41.1.5 time_level	88
6.41.1.6 timval	89
6.42 hess_pointing_correction_struct Struct Reference	89
6.42.1 Detailed Description	89
6.43 hess_run_end_mc_statistics_struct Struct Reference	89
6.43.1 Detailed Description	90
6.44 hess_run_end_statistics_struct Struct Reference	90
6.44.1 Detailed Description	90
6.45 hess_run_header_struct Struct Reference	91
6.45.1 Detailed Description	91
6.45.2 Field Documentation	92
6.45.2.1 conv_depth	92
6.45.2.2 conv_ref_pos	92
6.45.2.3 direction	92
6.45.2.4 offset_fov	92
6.45.2.5 reverse_flag	92
6.45.2.6 run	93
6.45.2.7 run_type	93
6.45.2.8 tel_pos	93
6.45.2.9 tracking_mode	93
6.46 hess_shower_parameter Struct Reference	93
6.46.1 Detailed Description	95
6.47 hess_tel_event_adc_struct Struct Reference	95
6.47.1 Detailed Description	96
6.48 hess_tel_event_data_struct Struct Reference	96
6.48.1 Detailed Description	97
6.49 hess_tel_image_struct Struct Reference	98

CONTENTS xi

	6.49.1	Detailed Description	99
	6.49.2	Field Documentation	99
		6.49.2.1	99
		6.49.2.2 num_hot	99
		6.49.2.3 phi	00
		6.49.2.4 tm_slope	00
		6.49.2.5 x	00
6.50	hess_te	el_monitor_struct Struct Reference	01
	6.50.1	Detailed Description	03
	6.50.2	Field Documentation	03
		6.50.2.1 coinc_count	03
		6.50.2.2 current	03
		6.50.2.3 drawer_temp	03
6.51	hess_ti	me_struct Struct Reference	04
	6.51.1	Detailed Description	04
6.52	hess_tr	racking_event_data_struct Struct Reference	04
	6.52.1	Detailed Description	05
6.53	hess_tr	racking_setup_struct Struct Reference	05
	6.53.1	Detailed Description	05
	6.53.2	Field Documentation	06
		6.53.2.1 range_low_az	06
6.54	histogra	am Struct Reference	06
	6.54.1	Detailed Description	07
	6.54.2	Field Documentation	07
		6.54.2.1 entries	07
		6.54.2.2 next	80
		6.54.2.3 overflow	80
		6.54.2.4 overflow_2d	80
		6.54.2.5 tentries	80
		6.54.2.6 type	09

xii CONTENTS

|         | 6.54          | .2.7              | und    | erflow  |       |       |      | <br> | . 109 |
|---------|---------------|-------------------|--------|---------|-------|-------|------|------|------|------|------|------|------|------|------|-------|
|         | 6.54          | .2.8              | und    | erflow_ | _2d   |       |      | <br> | . 109 |
| 6.55 H  | Histogram_l   | Extens            | sion   | Struct  | Refe  | eren  | ce . | <br> | . 109 |
| 6       | 6.55.1 Deta   | ailed [           | Desc   | ription | 1 .   |       |      | <br> | . 110 |
| 6       | 6.55.2 Field  | d Doc             | umei   | ntation | ı     |       |      | <br> | . 110 |
|         | 6.55          | 5.2.1             | ddat   | ta      |       |       |      | <br> | . 110 |
| 6.56 H  | Histogram_l   | <sup>2</sup> aram | neters | s Unio  | n Re  | efere | ence | <br> | . 110 |
| 6       | 6.56.1 Deta   | ailed [           | Desc   | ription | 1 .   |       |      | <br> | . 111 |
| 6       | 6.56.2 Field  | d Doc             | umei   | ntation | ı     |       |      | <br> | . 111 |
|         | 6.56          | 3.2.1             | inte   | ger .   |       |       |      | <br> | . 111 |
|         | 6.56          | 5.2.2             | inve   | rse_bi  | inwic | dth . |      | <br> | . 112 |
|         | 6.56          | 3.2.3             | real   |         |       |       |      | <br> | . 112 |
| 6.57 h  | nistory_stru  | ct Stru           | uct R  | eferen  | ice . |       |      | <br> | . 112 |
| 6       | 6.57.1 Deta   | ailed [           | Desc   | ription | 1 .   |       |      | <br> | . 113 |
| 6.58 h  | niststat Stru | ct Ref            | feren  | ce .    |       |       |      | <br> | . 113 |
| 6       | 6.58.1 Deta   | ailed [           | Desc   | ription | 1 .   |       |      | <br> | . 113 |
| 6.59 ir | ncpath Stru   | ct Ref            | feren  | ice .   |       |       |      | <br> | . 113 |
| 6       | 6.59.1 Deta   | ailed [           | Desc   | ription | i .   |       |      | <br> | . 114 |
| 6.60 li | inked_string  | y Stru            | ct Re  | eferenc | ce    |       |      | <br> | . 114 |
| 6       | 6.60.1 Deta   | ailed [           | Desc   | ription | ı .   |       |      | <br> | . 114 |
| 6.61 n  | map_tel_str   | uct St            | truct  | Refere  | ence  |       |      | <br> | . 115 |
| 6       | 6.61.1 Deta   | ailed [           | Desc   | ription | ı .   |       |      | <br> | . 115 |
| 6       | 6.61.2 Field  | d Doc             | umer   | ntation | ١.,   |       |      | <br> | . 115 |
|         | 6.61          | .2.1              | ifn    |         |       |       |      | <br> | . 115 |
| 6.62 n  | noments St    | ruct F            | Refere | ence    |       |       |      | <br> | . 116 |
| 6       | 6.62.1 Deta   | ailed [           | Desc   | ription |       |       |      | <br> | . 116 |
| 6.63 n  | nomstat Str   | uct R             | efere  | ence.   |       |       |      | <br> | . 116 |
| 6       | 6.63.1 Deta   | ailed [           | Desc   | ription |       |       |      | <br> | . 117 |
| 6.64 n  | next_file_str | uct St            | truct  | Refere  | ence  | )     |      | <br> | . 117 |
| 6.65 p  | ohoto_electi  | ron St            | truct  | Refere  | ence  |       |      | <br> | . 117 |

CONTENTS xiii

6.65.1 Detailed Description
6.65.2 Field Documentation
6.65.2.1 atime
6.65.2.2 lambda
6.65.2.3 pixel
6.66 range_list_struct Struct Reference
6.67 select_struct Struct Reference
6.68 shower_extra_parameters Struct Reference
6.68.1 Detailed Description
6.68.2 Field Documentation
6.68.2.1 fparam
6.68.2.2 id
6.68.2.3 iparam
6.68.2.4 is_set
6.68.2.5 nfparam
6.68.2.6 niparam
6.68.2.7 weight
6.69 tel_type_param Struct Reference
6.70 telescope_list Struct Reference
6.71 trgmask_entry Struct Reference
6.72 trgmask_hash_set Struct Reference
6.73 trgmask_set Struct Reference
6.74 user_parameters Struct Reference
6.74.1 Field Documentation
6.74.1.1 calib_scale
6.74.1.2 camera_clipping_deg
6.74.1.3 clip_amp
6.74.1.4 d_integ_param
6.74.1.5 d_sp_idx
6.74.1.6 impact_range

xiv CONTENTS

			6.74.1.7 integ_no_rescale	27
			6.74.1.8 integ_param	28
			6.74.1.9 integrator	28
			6.74.1.10 min_amp	28
			6.74.1.11 min_pix	28
			6.74.1.12 min_tel_img	28
			6.74.1.13 r_nb	29
			6.74.1.14 tailcut_low	29
			6.74.1.15 theta_escale	29
			6.74.1.16 user_flags	29
	6.75	warn_s	pecific_data Struct Reference	29
		6.75.1	Detailed Description	30
		6.75.2	Field Documentation	30
			6.75.2.1 logfname	30
7	Eile I	Doouma	entation 1	31
•	7.1		stograms.c File Reference	
	7.1			
		7.1.1	Detailed Description	
	7.2	•	f.c File Reference	32
	7.2	7.2.1	f.c File Reference	32 33
	7.2	•	f.c File Reference	32 33 34
	7.2	7.2.1	f.c File Reference       1         Detailed Description       1         Function Documentation       1         7.2.2.1 heighx()       1	32 33 34 34
	7.2	7.2.1	f.c File Reference	32 33 34 34
	7.2	7.2.1	f.c File Reference       1         Detailed Description       1         Function Documentation       1         7.2.2.1 heighx()       1         7.2.2.2 init_atmprof()       1	32 33 34 34
	7.2	7.2.1	f.c File Reference       1         Detailed Description       1         Function Documentation       1         7.2.2.1 heighx()       1         7.2.2.2 init_atmprof()       1         7.2.2.3 interp()       1	32 33 34 34 34
	7.2	7.2.1	f.c File Reference       1         Detailed Description       1         Function Documentation       1         7.2.2.1 heighx()       1         7.2.2.2 init_atmprof()       1         7.2.2.3 interp()       1         7.2.2.4 refidx()       1	32 33 34 34 34
	7.2	7.2.1	f.c File Reference       1         Detailed Description       1         Function Documentation       1         7.2.2.1 heighx()       1         7.2.2.2 init_atmprof()       1         7.2.2.3 interp()       1         7.2.2.4 refidx()       1         7.2.2.5 rhofx()       1	32 33 34 34 34 35
	7.2	7.2.1	f.c File Reference       1         Detailed Description       1         Function Documentation       1         7.2.2.1 heighx()       1         7.2.2.2 init_atmprof()       1         7.2.2.3 interp()       1         7.2.2.4 refidx()       1         7.2.2.5 rhofx()       1	32 33 34 34 34 35 35
	7.2	7.2.1 7.2.2	f.c File Reference       1         Detailed Description       1         Function Documentation       1         7.2.2.1 heighx()       1         7.2.2.2 init_atmprof()       1         7.2.2.3 interp()       1         7.2.2.4 refidx()       1         7.2.2.5 rhofx()       1         7.2.2.6 rpol()       1	32 33 34 34 34 35 35 36
		7.2.1 7.2.2	f.c File Reference	32 33 34 34 34 35 35 36 36 37

CONTENTS xv

		7.3.2.1	list_ntuple()	 138
7.4	best_o	f.cc File R	Reference	 138
	7.4.1	Detailed	Description	 140
7.5	camera	a_image.c	File Reference	 140
	7.5.1	Detailed	Description	 142
	7.5.2	Function	Documentation	 142
		7.5.2.1	find_neighbours()	 142
		7.5.2.2	hesscam_ps_plot()	 142
		7.5.2.3	print_pix_col()	 143
	7.5.3	Variable	Documentation	 143
		7.5.3.1	alt_az_arrow	 143
		7.5.3.2	ps_begin_page1	 144
		7.5.3.3	ps_begin_page2	 144
		7.5.3.4	ps_end_page	 144
		7.5.3.5	ps_head1a	 144
		7.5.3.6	ps_head1b	 145
		7.5.3.7	ps_trailer	 145
7.6	check_	_trgmask.c	c File Reference	 145
	7.6.1	Detailed	Description	 146
7.7	current	t.c File Re	eference	 146
	7.7.1	Detailed	Description	 147
	7.7.2	Function	Documentation	 147
		7.7.2.1	current_localtime()	 147
		7.7.2.2	current_time()	 148
		7.7.2.3	mkgmtime()	 148
		7.7.2.4	reset_local_offset()	 148
		7.7.2.5	set_current_offset()	 149
		7.7.2.6	set_local_offset()	 149
		7.7.2.7	time_string()	 149
7.8	current	t.h File Re	eference	 150

xvi CONTENTS

	7.8.1	Detailed Description	51
	7.8.2	Function Documentation	51
		7.8.2.1 current_localtime()	51
		7.8.2.2 current_time()	51
		7.8.2.3 mkgmtime()	51
		7.8.2.4 reset_local_offset()	52
		7.8.2.5 set_current_offset()	52
		7.8.2.6 set_local_offset()	53
		7.8.2.7 time_string()	53
7.9	cvt2.c F	File Reference	53
	7.9.1	Detailed Description	54
7.10	cvt3.cc	File Reference	55
	7.10.1	Detailed Description	55
7.11	dhsort.	c File Reference	56
	7.11.1	Detailed Description	56
	7.11.2	Function Documentation	57
		7.11.2.1 dhsort()	57
7.12	eventio	_registry.c File Reference	57
	7.12.1	Detailed Description	59
	7.12.2	Function Documentation	59
		7.12.2.1 find_ev_reg_std()	59
		7.12.2.2 read_eventio_registry()	59
		7.12.2.3 set_ev_reg_std()	30
7.13	eventio	_registry.h File Reference	30
	7.13.1	Detailed Description	31
	7.13.2	Function Documentation	31
		7.13.2.1 find_ev_reg_std()	31
		7.13.2.2 read_eventio_registry()	32
		7.13.2.3 set_ev_reg_std()	32
7.14	extract_	_hess.c File Reference	32

CONTENTS xvii

7.14.1	Detailed Description	163
7.15 extract	simtel.c File Reference	163
7.15.1	Detailed Description	165
7.16 fcat.c F	File Reference	166
7.16.1	Detailed Description	166
7.17 fileope	n.c File Reference	166
7.17.1	Detailed Description	168
7.17.2	Function Documentation	169
	7.17.2.1 addexepath()	169
	7.17.2.2 addpath()	169
	7.17.2.3 cmp_popen()	169
	7.17.2.4 disable_permissive_pipes()	170
	7.17.2.5 enable_permissive_pipes()	170
	7.17.2.6 exe_popen()	170
	7.17.2.7 fileclose()	170
	7.17.2.8 fileopen()	171
	7.17.2.9 freeexepath()	171
	7.17.2.10 freepath()	171
	7.17.2.11 initpath()	171
	7.17.2.12 listpath()	172
	7.17.2.13 set_permissive_pipes()	172
	7.17.2.14 uri_popen()	172
7.17.3	Variable Documentation	172
	7.17.3.1 permissive_pipes	172
	7.17.3.2 root_exe_path	173
	7.17.3.3 root_path	173
7.18 fileope	n.h File Reference	173
7.18.1	Detailed Description	174
7.18.2	Function Documentation	174
	7.18.2.1 addexepath()	174

xviii CONTENTS

	7.18.2.2 addpath()	174
	7.18.2.3 disable_permissive_pipes()	175
	7.18.2.4 enable_permissive_pipes()	175
	7.18.2.5 fileclose()	175
	7.18.2.6 fileopen()	175
	7.18.2.7 initpath()	176
	7.18.2.8 listpath()	176
	7.18.2.9 set_permissive_pipes()	176
7.19 ge	ookup.c File Reference	176
7.1	1 Detailed Description	178
7.1	2 Function Documentation	178
	7.19.2.1 fill_gaps()	179
7.20 ge	rgmask.c File Reference	179
7.2	1 Detailed Description	179
7.21 hc	ig.c File Reference	180
7.2	1 Detailed Description	182
7.2	2 Function Documentation	184
	7.21.2.1 build_config()	184
	7.21.2.2 find_config_item()	185
	7.21.2.3 get_config_filename()	185
	7.21.2.4 get_config_preprocessor()	186
	7.21.2.5 init_config()	186
	7.21.2.6 read_config_lines()	186
	7.21.2.7 read_config_status()	187
	7.21.2.8 reconfig()	187
	7.21.2.9 reload_config()	187
	7.21.2.10 set_config_filename()	188
	7.21.2.11 set_config_history()	188
	7.21.2.12 set_config_preprocessor()	189
	7.21.2.13 set_config_stack()	189

CONTENTS xix

	7.21.3	Variable [	Document	ation .			 	 	 	 		 	. 189
		7.21.3.1	config_d	efaults .			 	 	 	 		 	. 189
		7.21.3.2	default_d	config .			 	 	 	 		 	. 190
		7.21.3.3	first_con	fig_block	k		 	 	 	 		 	. 190
7.22	hconfig	.h File Ref	erence				 	 	 	 		 	. 190
	7.22.1	Detailed I	Descriptio	n			 	 	 	 		 	. 193
	7.22.2	Macro De	efinition D	ocument	tation		 	 	 	 		 	. 194
		7.22.2.1	_STR_				 	 	 	 		 	. 194
		7.22.2.2	CFG_MI	JTEX .			 	 	 	 		 	. 194
	7.22.3	Function	Documen	tation .			 	 	 	 		 	. 194
		7.22.3.1	abbrev()				 	 	 	 		 	. 194
		7.22.3.2	build_co	nfig()			 	 	 	 		 	. 195
		7.22.3.3	config_b	inary_co	onvert_c	data()	 	 	 	 		 	. 195
		7.22.3.4	config_b	inary_re	ad_text	t()	 	 	 	 		 	. 195
		7.22.3.5	config_b	inary_te	xt_leng	gth() .	 	 	 	 		 	. 196
		7.22.3.6	config_b	inary_w	rite_naı	me() .	 	 	 	 		 	. 196
		7.22.3.7	config_b	inary_w	rite_tex	ct()	 	 	 	 		 	. 196
		7.22.3.8	find_con	fig_item	()		 	 	 	 		 	. 196
		7.22.3.9	get_conf	ig_filena	ame()		 	 	 	 		 	. 197
		7.22.3.10	get_conf	ig_prep	rocesso	or()	 	 	 	 		 	. 197
		7.22.3.11	getword(	)			 	 	 	 		 	. 197
		7.22.3.12	init_conf	ig()			 	 	 	 		 	. 198
		7.22.3.13	read_co	nfig_line	s()		 	 	 	 		 	. 199
		7.22.3.14	read_co	nfig_stat	us().		 	 	 	 		 	. 199
		7.22.3.15	reconfig	<u>)</u>			 	 	 	 		 	. 199
		7.22.3.16	reload_c	onfig() .			 	 	 	 		 	. 200
		7.22.3.17	set_conf	ig_filena	ıme()		 	 	 	 		 	. 200
		7.22.3.18	set_conf	ig_histo	r <b>y</b> () .		 	 	 	 		 	. 200
		7.22.3.19	set_conf	ig_prepr	ocesso	or()	 	 	 	 		 	. 201
		7.22.3.20	set_conf	ig_stack	a()		 	 	 	 		 	. 201

CONTENTS

7.23	hessio_	doc.h File Reference	)2
	7.23.1	Detailed Description	)2
7.24	histogra	um.c File Reference	)2
	7.24.1	Detailed Description	)5
	7.24.2	Macro Definition Documentation	)5
		7.24.2.1 HistOutput	)5
	7.24.3	Function Documentation	)5
		7.24.3.1 add_histogram()	)5
		7.24.3.2 alloc_2d_int_histogram()	)6
		7.24.3.3 alloc_2d_real_histogram()	)6
		7.24.3.4 alloc_int_histogram()	)7
		7.24.3.5 alloc_real_histogram()	)8
		7.24.3.6 allocate_histogram()	)8
		7.24.3.7 book_1d_histogram()	)9
		7.24.3.8 book_histogram()	)9
		7.24.3.9 book_int_histogram()	10
		7.24.3.10 clear_histogram()	10
		7.24.3.11 describe_histogram()	11
		7.24.3.12 display_2d_histogram()	11
		7.24.3.13 display_all_histograms()	12
		7.24.3.14 display_histogram()	12
		7.24.3.15 fast_stat_histogram()	12
		7.24.3.16 fill_2d_int_histogram()	13
		7.24.3.17 fill_2d_real_histogram()	13
		7.24.3.18 fill_2d_weighted_histogram()	14
		7.24.3.19 fill_histogram()	14
		7.24.3.20 fill_histogram_by_ident()	15
		7.24.3.21 fill_int_histogram()	16
		7.24.3.22 fill_real_histogram()	16
		7.24.3.23 fill_weighted_histogram()	17

CONTENTS xxi

	7.24.3.24 free_all_histograms()
	7.24.3.25 free_histo_contents()
	7.24.3.26 free_histogram()
	7.24.3.27 get_first_histogram()
	7.24.3.28 get_histogram_by_ident()
	7.24.3.29 histogram_hashing()
	7.24.3.30 histogram_matching()
	7.24.3.31 histogram_to_lookup()
	7.24.3.32 list_histograms()
	7.24.3.33 locate_histogram_fraction()
	7.24.3.34 lookup_int()
	7.24.3.35 lookup_real()
	7.24.3.36 print_histogram()
	7.24.3.37 set_first_histogram()
	7.24.3.38 sort_histograms()
	7.24.3.39 stat_histogram()
	7.24.3.40 unlink_histogram()
7.24.4	Variable Documentation
	7.24.4.1 primetab
7.25 histog	ram.h File Reference
7.25.1	Detailed Description
7.25.2	2 Typedef Documentation
	7.25.2.1 HISTCOUNT
	7.25.2.2 HISTVALUE_REAL
7.25.3	Function Documentation
	7.25.3.1 add_histogram()
	7.25.3.2 alloc_2d_int_histogram()
	7.25.3.3 alloc_2d_real_histogram()
	7.25.3.4 alloc_int_histogram()
	7.25.3.5 alloc_moments()

xxii CONTENTS

7.25.3.6 alloc_real_histogram()
7.25.3.7 allocate_histogram()
7.25.3.8 book_1d_histogram()
7.25.3.9 book_histogram()
7.25.3.10 book_int_histogram()
7.25.3.11 clear_histogram()
7.25.3.12 clear_moments()
7.25.3.13 describe_histogram()
7.25.3.14 display_all_histograms()
7.25.3.15 display_histogram()
7.25.3.16 fast_stat_histogram()
7.25.3.17 fill_2d_int_histogram()
7.25.3.18 fill_2d_real_histogram()
7.25.3.19 fill_2d_weighted_histogram()
7.25.3.20 fill_histogram()
7.25.3.21 fill_histogram_by_ident()
7.25.3.22 fill_int_histogram()
7.25.3.23 fill_mean()
7.25.3.24 fill_mean_and_sigma()
7.25.3.25 fill_moments()
7.25.3.26 fill_real_histogram()
7.25.3.27 fill_real_mean()
7.25.3.28 fill_real_mean_and_sigma()
7.25.3.29 fill_real_moments()
7.25.3.30 fill_weighted_histogram()
7.25.3.31 free_all_histograms()
7.25.3.32 free_histogram()
7.25.3.33 free_moments()
7.25.3.34 get_first_histogram()
7.25.3.35 get_histogram_by_ident()

CONTENTS xxiii

	7.25.3.36 histogram_hashing()
	7.25.3.37 histogram_matching()
	7.25.3.38 histogram_to_lookup()
	7.25.3.39 list_histograms()
	7.25.3.40 locate_histogram_fraction()
	7.25.3.41 lookup_int()
	7.25.3.42 lookup_real()
	7.25.3.43 print_histogram()
	7.25.3.44 set_first_histogram()
	7.25.3.45 sort_histograms()
	7.25.3.46 stat_histogram()
	7.25.3.47 stat_moments()
	7.25.3.48 unlink_histogram()
7.26 history	,h File Reference
7.26.1	Detailed Description
7.27 initial.	n File Reference
7.27.1	Detailed Description
7.28 io_he	ss.c File Reference
7.28.1	Detailed Description
7.28.2	Function Documentation
	7.28.2.1 check_hessio_max()
	7.28.2.2 find_tel_idx()
	7.28.2.3 print_hess_aux_trace_analog()
	7.28.2.4 print_hess_aux_trace_digital()
	7.28.2.5 print_hess_pixcalib()
	7.28.2.6 read_hess_pixcalib()
	7.28.2.7 set_tel_idx()
	7.28.2.8 set_tel_idx_ref()
	7.28.2.9 write_hess_aux_trace_digital()
	7.28.2.10 write_hess_event()

xxiv CONTENTS

	7.28.2.11 write_hess_laser_calib()	262
	7.28.2.12 write_hess_mc_event()	262
	7.28.2.13 write_hess_mc_pe_sum()	263
	7.28.2.14 write_hess_mc_shower()	263
	7.28.2.15 write_hess_pixcalib()	263
	7.28.2.16 write_hess_run_stat()	263
	7.28.2.17 write_hess_shower()	263
	7.28.2.18 write_hess_tel_monitor()	264
	7.28.2.19 write_hess_teladc_samples()	264
	7.28.2.20 write_hess_teladc_sums()	264
	7.28.2.21 write_hess_televent()	265
7.28.3	Variable Documentation	265
	7.28.3.1 hs_verbose	265
7.29 io_hes	s.h File Reference	265
7.29.1	Detailed Description	270
7.29.2	Macro Definition Documentation	270
	7.29.2.1 H_CHECK_MAX	270
	7.29.2.2 H_MAX_FSHAPE	271
	7.29.2.3 H_MAX_HOTPIX	271
	7.29.2.4 H_MAX_PIX_TIMES	271
	7.29.2.5 H_MAX_PROFILE	271
	7.29.2.6 H_MAX_SLICES	271
	7.29.2.7 HI_GAIN	272
	7.29.2.8 LO_GAIN	272
	7.29.2.9 PIX_TIME_PEAKPOS_TYPE	272
	7.29.2.10 PIX_TIME_STARTPOS_ABS_TYPE	272
	7.29.2.11 PIX_TIME_STARTPOS_REL_TYPE	272
	7.29.2.12 PIX_TIME_WIDTH_ABS_TYPE	273
	7.29.2.13 PIX_TIME_WIDTH_REL_TYPE	273
7.29.3	Function Documentation	273

CONTENTS xxv

		7.29.3.1	ch	neck_	hessi	o_ma	ax()					 	 		 	 		. 273
7.30	io_histo	ogram.c Fi	ile F	Refere	ence .							 	 	 	 	 		. 274
	7.30.1	Detailed	De	scripti	ion .							 	 	 	 	 		. 275
	7.30.2	Function	Do	cume	ntatio	n .						 	 	 	 	 		. 275
		7.30.2.1	pr	rint_hi	istogr	ams(	() -					 	 	 	 	 		. 275
		7.30.2.2	re	ad_hi	istogr	ams(	() -					 	 	 	 	 		. 275
		7.30.2.3	re	ad_hi	istogr	ams_	_x()					 	 	 	 	 		. 276
		7.30.2.4	W	rite_h	istogr	ams	() -					 	 	 	 	 		. 276
7.31	io_histo	ogram.h Fi	ile I	Refere	ence							 	 	 	 	 		. 277
	7.31.1	Detailed	De	scripti	ion .							 	 	 	 	 		. 278
	7.31.2	Function	n Do	cume	ntatio	n .						 	 	 	 	 		. 278
		7.31.2.1	pr	rint_hi	istogr	ams(	() -					 	 	 	 	 		. 278
		7.31.2.2	re	ad_hi	istogr	ams	() -					 	 	 	 	 		. 279
		7.31.2.3	re	ad_hi	istogr	ams <sub>.</sub>	_x()					 	 	 	 	 		. 279
		7.31.2.4	W	rite_h	istogr	ams	() -					 	 	 	 	 		. 280
7.32	io_histo	ory.c File F	Refe	erence	е.							 	 	 	 	 		. 280
	7.32.1	Detailed	Des	scripti	ion .							 	 	 	 	 		. 282
	7.32.2	Variable I	Dod	cumer	ntatio	n .						 	 	 	 	 		. 282
		7.32.2.1	cr	ndline	<b>)</b> .							 	 	 	 	 		. 282
		7.32.2.2	cr	ndtim	е							 	 	 	 	 		. 282
		7.32.2.3	CC	onfigs	,							 	 	 	 	 		. 282
7.33	io_histo	ory.h File F	Refe	erenc	е							 	 	 	 	 		. 283
	7.33.1	Detailed	De	scripti	ion .							 	 	 	 	 		. 283
7.34	io_simt	el.c File R	Refe	rence	)							 	 	 	 	 		. 284
	7.34.1	Detailed	De	scripti	ion .							 	 	 	 	 		. 286
	7.34.2	Function	n Do	cume	ntatio	on .						 	 	 	 	 		. 286
		7.34.2.1	be	egin_r	read_	tel_a	ırray(	() .				 	 	 	 	 		. 286
		7.34.2.2	be	egin_\	write_	_tel_a	array(	()				 	 	 	 	 		. 287
		7.34.2.3	cl	ear_s	howe	r_ex	tra_p	ara	met	ers(	) .	 	 	 	 	 		. 287
		7.34.2.4	er	nd_re	ad_te	l_arr	ay()					 	 	 	 	 		. 287

xxvi CONTENTS

7.34.2.5 end_write_tel_array()
7.34.2.6 init_shower_extra_parameters()
7.34.2.7 print_camera_layout()
7.34.2.8 print_photo_electrons()
7.34.2.9 print_tel_block()
7.34.2.10 print_tel_offset()
7.34.2.11 print_tel_pos()
7.34.2.12 read_camera_layout()
7.34.2.13 read_input_lines()
7.34.2.14 read_photo_electrons()
7.34.2.15 read_shower_longitudinal()
7.34.2.16 read_tel_array_end()
7.34.2.17 read_tel_array_head()
7.34.2.18 read_tel_block()
7.34.2.19 read_tel_offset()
7.34.2.20 read_tel_offset_w()
7.34.2.21 read_tel_photons()
7.34.2.22 read_tel_pos()
7.34.2.23 write_camera_layout()
7.34.2.24 write_input_lines()
7.34.2.25 write_photo_electrons()
7.34.2.26 write_shower_longitudinal()
7.34.2.27 write_tel_array_end()
7.34.2.28 write_tel_array_head()
7.34.2.29 write_tel_block()
7.34.2.30 write_tel_compact_photons()
7.34.2.31 write_tel_offset()
7.34.2.32 write_tel_offset_w()
7.34.2.33 write_tel_photons()
7.34.2.34 write_tel_pos()

CONTENTS xxvii

	7.34.3	Variable Documentation	04
		7.34.3.1 max_print	04
		7.34.3.2 private_shower_extra_parameters	05
7.35	io_trgm	ask.c File Reference	05
	7.35.1	Detailed Description	06
	7.35.2	Function Documentation	06
		7.35.2.1 find_trgmask()	06
		7.35.2.2 print_hashed_trgmasks()	07
		7.35.2.3 trgmask_fill_hashed()	07
		7.35.2.4 trgmask_scan_log()	07
7.36	io_trgm	ask.h File Reference	07
	7.36.1	Detailed Description	80
	7.36.2	Macro Definition Documentation	80
		7.36.2.1 IO_TYPE_HESS_XTRGMASK	80
	7.36.3	Function Documentation	09
		7.36.3.1 find_trgmask()	09
		7.36.3.2 print_hashed_trgmasks()	09
		7.36.3.3 trgmask_fill_hashed()	09
		7.36.3.4 trgmask_scan_log()	09
7.37	list_his	ograms.c File Reference	10
	7.37.1	Detailed Description	10
7.38	mc_tel.	h File Reference	11
	7.38.1	Detailed Description	14
	7.38.2	Function Documentation	14
		7.38.2.1 begin_read_tel_array()	14
		7.38.2.2 begin_write_tel_array()	15
		7.38.2.3 clear_shower_extra_parameters()	15
		7.38.2.4 end_read_tel_array()	16
		7.38.2.5 end_write_tel_array()	16
		7.38.2.6 init_shower_extra_parameters()	16
		- $    -$	

xxviii CONTENTS

	7.38.2.7 print_camera_layout()
	7.38.2.8 print_photo_electrons()
	7.38.2.9 print_tel_block()
	7.38.2.10 print_tel_offset()
	7.38.2.11 print_tel_pos()
	7.38.2.12 read_camera_layout()
	7.38.2.13 read_input_lines()
	7.38.2.14 read_photo_electrons()
	7.38.2.15 read_shower_longitudinal()
	7.38.2.16 read_tel_array_end()
	7.38.2.17 read_tel_array_head()
	7.38.2.18 read_tel_block()
	7.38.2.19 read_tel_offset()
	7.38.2.20 read_tel_offset_w()
	7.38.2.21 read_tel_photons()
	7.38.2.22 read_tel_pos()
	7.38.2.23 write_camera_layout()
	7.38.2.24 write_input_lines()
	7.38.2.25 write_photo_electrons()
	7.38.2.26 write_shower_longitudinal()
	7.38.2.27 write_tel_array_end()
	7.38.2.28 write_tel_array_head()
	7.38.2.29 write_tel_block()
	7.38.2.30 write_tel_compact_photons()
	7.38.2.31 write_tel_offset()
	7.38.2.32 write_tel_offset_w()
	7.38.2.33 write_tel_photons()
	7.38.2.34 write_tel_pos()
7.39 merge	_simtel.c File Reference
7.39.1	Detailed Description

CONTENTS xxix

7.40 moments.c File Reference	34
7.40.1 Detailed Description	36
7.40.2 Function Documentation	36
7.40.2.1 alloc_moments()	36
7.40.2.2 clear_moments()	37
7.40.2.3 fill_mean()	38
7.40.2.4 fill_mean_and_sigma()	38
7.40.2.5 fill_moments()	38
7.40.2.6 fill_real_mean()	39
7.40.2.7 fill_real_mean_and_sigma()	39
7.40.2.8 fill_real_moments()	39
7.40.2.9 free_moments()	10
7.40.2.10 stat_moments()	10
7.41 read_hess.c File Reference	11
7.41.1 Detailed Description	12
7.42 read_hess_nr.c File Reference	16
7.42.1 Detailed Description	17
7.43 rec_tools.h File Reference	17
7.43.1 Detailed Description	18
7.43.2 Function Documentation	18
7.43.2.1 angle_between()	19
7.43.2.2 angles_to_offset()	19
7.43.2.3 cam_to_ref()	19
7.43.2.4 get_shower_trans_matrix()	50
7.43.2.5 intersect_lines()	50
7.43.2.6 line_point_distance()	50
7.43.2.7 offset_to_angles()	51
7.43.2.8 shower_geometric_reconstruction()	51
7.44 reconstruct.c File Reference	52
7.44.1 Detailed Description	55

CONTENTS

7.44.2	2 Macro Definition Documentation
	7.44.2.1 CALIB_SCALE
7.44.3	355 Function Documentation
	7.44.3.1 calibrate_amplitude()
	7.44.3.2 calibrate_pixel_amplitude()
	7.44.3.3 clean_image_tailcut()
	7.44.3.4 find_neighbours()
	7.44.3.5 global_peak_integration()
	7.44.3.6 gradient_integration()
	7.44.3.7 image_reconstruct()
	7.44.3.8 local_peak_integration()
	7.44.3.9 nb_fc_shaped_peak_integration()
	7.44.3.10 nb_peak_integration()
	7.44.3.11 pixel_integration()
	7.44.3.12 pixel_timing_analysis()
	7.44.3.13 PzpsaPeakProperty()
	7.44.3.14 PzpsaSmoothUpsampleU16()
	7.44.3.15 reconstruct()
	7.44.3.16 second_moments()
	7.44.3.17 select_calibration_channel()
	7.44.3.18 set_disabled_pixels()
	7.44.3.19 set_integration_correction()
	7.44.3.20 simple_integration()
7.45 rndm2	2.h File Reference
7.45.1	Detailed Description
7.46 split_l	nessio.c File Reference
7.46.1	Detailed Description
7.47 straux	c.c File Reference
7.47.1	Detailed Description
7.47.2	2 Function Documentation

CONTENTS xxxi

		7.47.2.1	abbrev()			 	 	 	 	 370
		7.47.2.2	getword()			 	 	 	 	 370
		7.47.2.3	stricmp()			 	 	 	 	 371
7.48	straux.l	n File Refe	ence			 	 	 	 	 371
	7.48.1	Detailed I	escription			 	 	 	 	 372
	7.48.2	Function	Documentation			 	 	 	 	 372
		7.48.2.1	abbrev()			 	 	 	 	 372
		7.48.2.2	getword()			 	 	 	 	 373
		7.48.2.3	stricmp()			 	 	 	 	 373
7.49	tohbool	k.c File Re	erence			 	 	 	 	 374
	7.49.1	Detailed I	escription			 	 	 	 	 374
7.50	toroot.c	c File Refe	rence			 	 	 	 	 375
	7.50.1	Detailed I	escription			 	 	 	 	 375
	7.50.2	Function	Documentation			 	 	 	 	 376
		7.50.2.1	convert_histog	rams_to_r	root() .	 	 	 	 	 376
		7.50.2.2	histogram_to_	root()		 	 	 	 	 376
7.51	user_a	nalysis.c F	le Reference			 	 	 	 	 377
	7.51.1	Detailed I	escription			 	 	 	 	 380
	7.51.2	Function	Documentation			 	 	 	 	 381
		7.51.2.1	ebias_correction	on()		 	 	 	 	 381
		7.51.2.2	eval_cut_para	m()		 	 	 	 	 381
		7.51.2.3	expected_max	_distance(	()	 	 	 	 	 382
		7.51.2.4	expected_max	_height()		 	 	 	 	 382
		7.51.2.5	img_norm()			 	 	 	 	 383
		7.51.2.6	init_telescope_	_types() .		 	 	 	 	 383
		7.51.2.7	interp()			 	 	 	 	 384
		7.51.2.8	prog_path().			 	 	 	 	 384
		7.51.2.9	rpol()			 	 	 	 	 385
		7.51.2.10	user_done()			 	 	 	 	 385
		7.51.2.11	user_event_fill	()		 	 	 	 	 386

xxxii CONTENTS

		7.52.2.3 7.52.2.4	set_log_file()	
		7.52.2.5	set_output_function()	
		7.52.2.6	set_warning()	393
			warn_f_output_text()	
			warn_f_warning()	
		7.52.2.9	warning_status()	394
	7.52.3	Variable [	Documentation	395
		7.52.3.1	warn_defaults	395
7.53	warning	g.h File Re	ference	395
		-	Description	
			Documentation	
			flush_output()	
			set_aux_warning_function()	
		7.53.2.3	set_log_file()	
		7.53.2.4	set_logging_function()	
		7.53.2.5	set_output_function()	
		7.53.2.6	set_warning()	
		7.53.2.7	warn_f_output_text()	
		7.53.2.8	warn_f_warning()	399
		7.53.2.9	warning_status()	400

## **Chapter 1**

### Introduction

#### 1.1 Introduction to the eventio/hessio libraries.

The hessio libraries include a number of components which are heavily used in CORSIKA/sim\_telarray (sim\_\circ
hessarray) simulations but also in some of the H.E.S.S. DAQ components. The basic components go back much
further in history and were used for the DAQ of the CRT (Cosmic Ray Tracking) experiment, starting in 1991, and
the HEGRA stereoscopic system of Cherenkov telescopes, starting in 1996. The library is thus also known under
its orignal name: eventio library. The major components of the package include:

- The eventio data storage method with programming interfaces in C and C++.
- The eventio based high-level interfaces for shower simulations in the IACT interface to CORSIKA.
- The eventio based high-level interfaces for H.E.S.S. raw data and H.E.S.S./CTA simulations, as used by the sim\_telarray program.
- A memory and speed efficient package for 1-D and 2-D histograms with full multi-threading support.
- The eventio based storage of the above histograms and conversion programs from the eventio format to PAW (HBOOK) and ROOT formats.
- A software run-time configuration interface named hconfig with a cpp-like preprocessor, also with full multithreading support.

The hessic libraries are normally built in several variants:

- libhessio The variant optimised for single-threaded C programs. It has no multi-threading support and should not be used in multi-threaded DAQ environments. For simulations performed in a single thread, this variant provides optimum performance because no time is wasted in protecting critical sections by mutexes etc.
- libhessio\_r The variant with full multi-threading support. Because of the overhead of protecting critical sections, it is not the optimal variant for single-threaded programs but (if linked with the POSIX threading library), will work for both multi-threaded and single-threaded programs. Linking: -lhessio\_cr\_lpthread
- libhessio++ Like libhessio it offers no multi-threading support. In addition to libhessio it offers also the C++ interfaces to the eventio data format. As such, it requires linking with the C++ Standard Library. Single-threaded C++ programs would normally be linked against this variant: -lhessio++

2 Introduction

• libhessio++\_r offers everything of libhessio\_r plus the C++ interfaces to the eventio data format. Multi-threaded C++ programs would normally be linked against this variant:  $-lhessio++\_\leftarrow r$  -lpthread

All of these libraries can be built as shared libraries and as static libraries, thus adding up to a total of eight libraries installed. Depending on definitions in the Makefile, the building of static libraries may be skipped by default.

The main documentation web page for this module can be found at

http://www.mpi-hd.mpq.de/hfm/~bernlohr/HESS/Software/hessio/

#### 1.2 Eventio format documentation

The underlying eventio data format and the C and C++ programming interfaces are documented separately. See http://www.mpi-hd.mpg.de/hfm/~bernlohr/HESS/Software/hessio/eventio\_en.pdf

### 1.3 Utility and test programs in the hessio module

A make install in the hessio module will, apart from the different variants of the library, install a number of programs. These include

- testio: A test program for the C programming interface. Should be run once if you go to a new platform or compiler.
- TestIO: A test program for the C++ programming interface. Should be run once if you go to a new platform or compiler. The output file generated should also be bitwise identical to that from the C interface test program.
- listio: Lists eventio data blocks in a data file or stream. Can also show the sub-block hierarchy.
- statio: Count the number of eventio top-level data blocks of each type and the total amount of (uncompressed) data for each block type. Also showing the version numbers involved.
- filterio: Select or deselect given types of eventio top-level data blocks between input or output, not requiring any support for the structure of the data block types.
- fcat: Like the standard 'cat' program but accepting any file type known by the fileopen() function as input, with decompression as implied by the filetype extension.
- read\_hess: Reads output files generated by sim\_hessarray and may optionally redo the image cleaning and shower reconstruction. It may be most useful to quickly visualize the images in the data file. Also called read\_cta or read\_simtel.
- gen\_lookup: Process the histograms generated by read\_hess to obtain lookup tables for width, length, energy, angular resolution, etc., which are used for further processing with read\_hess.
- list\_histograms: Show histograms embedded into an eventio file which can be either a dedicated histogram file or a general data file with any number of histogram blocks.
- add\_histograms: Add up multiple occurences of matching histograms (in ID, type, limits, and size) from one or multiple files into a new histogram file, independent of any format conversion.
- hdata2hbook: Converts from the eventio histogram format to the HBOOK/Paw format. Histogram blocks
  can be anywhere in a data file. You can also add up identical histograms from different input files before
  exporting.
- hdata2root: Converts from the eventio histogram format to the ROOT format. Like hdata2hbook.
- gen\_trgmask: Fixing a problem with 2012/13 versions of sim\_telarray for camera configurations with multiple types of triggers where the information on which type of trigger fired got lost. This tool recovers this information from the log files. Not needed for new simulations (nor for old ones which could only have one type of trigger).
- check\_trgmask: Check the camera trigger type bit patterns generated by the gen\_trgmask tool for consistency.

# Chapter 2

# **Module Index**

## 2.1 Modules

## Here is a list of all modules:

The add_histograms program
The best_of program
The fcat program
The list_histogram program
The check_trgmask program
The extract_hess program
The extract_simtel program
The gen_trgmask program
The merge_simtel program
The read_hess (aka read_simtel, read_cta) program
The read_hess_nr program
The split_hessio program
The hdata2hbook program (cvt2)
The hdata2root program (cvt3)

4 Module Index

# **Chapter 3**

# **Data Structure Index**

## 3.1 Data Structures

Here are the data structures with brief descriptions:

basic_ntuple	
A struct with basic per-shower parameters, to be used as an n-tuple in the event selection	37
best_value	45
Binary_Interface_Chain	46
FloatCompressor::Bits	46
Float16Compressor::Bits	47
bunch	
Photons collected in bunches of identical direction, position, time, and wavelength	47
camera_nb_list	48
compact_bunch	
The compact_bunch struct is equivalent to the bunch struct except that we try to use less memory	48
Config_Binary_Item_Interface	
Interface definitions for binary-only items	49
config_specific_data	51
ConfigBlockStruct	
Configuration is organized in sections	52
ConfigBoundary	
Configuration value may have optional lower and/or upper bounds	53
ConfigDataPointer	
This union of pointers allows convenient access of various types of data	53
ConfigIntern	
Configuration elements used only internally	54
ConfigItemStruct	
Configuration as used in definitions of configuration blocks	57
ConfigValues	
Configuration values and supporting data passed to user functions	60
ebias_cor_data	63
ev_reg_chain	
Use a double-linked list for the registry	64
Float16Compressor	64
FloatCompressor	65
hess_all_data_struct	
Container for all H.E.S.S	66
hess_aux_analog_trace	67
hess_aux_digital_trace	68

6 Data Structure Index

hess_camera_organisation_struct	
Logical organisation of camera electronics channels	68
hess_camera_settings_struct	
Definition of camera optics settings	69
hess_camera_software_setting_struct	
Software settings used in camera process	70
hess_central_event_data_struct	
Central trigger event data	72
hess_event_data_struct	
All data for one event	74
hess_laser_calib_data_struct	
Laser calibration data	75
hess_mc_event_struct	
Monte Carlo event-specific data	76
hess_mc_pe_list	
Photo-electrons from Monte Carlo individually	77
hess_mc_pe_sum_struct	70
Sums of photo-electrons in MC (total and per pixel)	78
hess_mc_photons	70
Photons from Monte Carlo	79
hess_mc_run_header_struct  MC run header	80
hess_mc_shower_profile_struct	00
Monte Carlo shower profile (sort of histogram)	81
hess_mc_shower_struct	01
Shower specific data	83
hess_pixel_calibrated_struct	84
hess_pixel_disabled_struct	٠.
Pixels disabled in HV and/or trigger	85
hess_pixel_list	
Lists of pixels (triggered, selected, etc.)	85
hess_pixel_setting_struct	
Settings of pixel HV and thresholds	86
hess_pixel_timing_struct	87
hess_pointing_correction_struct	
Pointing correction parameters	89
hess_run_end_mc_statistics_struct	
MC end-of-run statistics	89
hess_run_end_statistics_struct	
End-of-run statistics	90
hess_run_header_struct	
Run header common to measured and simulated data	91
hess_shower_parameter	
Reconstructed shower parameters	93
hess_tel_event_adc_struct	
ADC data (either sampled or sum mode)	95
hess_tel_event_data_struct	00
Event raw and image data from one telescope	96
hess_tel_image_struct	00
Image parameters	98
hess_tel_monitor_struct  Manitoring data	101
Monitoring data	101
hess_time_struct  Breakdown of time into seconds since 1970.0 and nanoseconds	104
hess_tracking_event_data_struct	104
Tracking data interpolated for one event and one telescope	104
hess_tracking_setup_struct	
Definition of tracking parameters	105

3.1 Data Structures 7

histogram	
A complete 1-D or 2-D histogram with control and data elements	)6
Histogram_Extension	
A histogram extension only allocated for weighted histograms	)9
Histogram_Parameters	
Parameters defining the usable range of coordinates	0
history_struct	
Use to build a linked list of configuration history	12
histstat	
Statistics element for histogram analysis	13
incpath	
An element in a linked list of include paths	13
linked_string	
The linked_string is mainly used to keep CORSIKA input	4
map_tel_struct	
Structure with per output telescope information keeping track of prerequisites	15
moments	
Numbers to be summed up to obtain the moments	6
momstat	
First, second, and higher moments of a 1-D histogram	
next_file_struct	17
A photo-electron produced by a photon hitting a pixel	17
range list struct	
select struct	
shower_extra_parameters	0
Extra shower parameters of unspecified nature	19
tel_type_param	-
telescope list	
trgmask entry	
trgmask hash set	
trgmask set	
user parameters	
warn specific data	
A struct used to store thread-specific data	29

8 Data Structure Index

# **Chapter 4**

# File Index

## 4.1 File List

Here is a list of all documented files with brief descriptions:

add_histograms.c	
Utility program for adding up matching histograms	131
atmprof.c	
A stripped-down version of the interpolation of atmospheric profiles from the atmo.c file of the CORSIKA IACT/ATMO package	132
atmprof.h	??
basic_ntuple.h	
Desclaration of the basic_ntuple struct	137
best_of.cc	
Tool for extracting best values from listings of 'rh3' sensitivity evaluations	138
camera_image.c	
Plot a camera image from H.E.S.S	
camera_image.h	??
check_trgmask.c	
Check consistency of 'trgmask' files produced with gen_trgmask for the CTA prod-2 data sets	
produced in 2013	145
current.c	4.40
Code to insert current time string into warnings	146
current.h  Header file for optional current time add-on to warning.c	150
cvt2.c	150
Utility program for converting histograms to HBOOK format	153
cvt3.cc	100
Conversion of eventio histograms to ROOT format	155
dhsort.c	
Dhsort - double type number heapsort	156
dhsort.h	??
eventio_registry.c	
Register and enquire about well-known I/O block types	157
eventio_registry.h	
Register and enquire about well-known I/O block types	160
eventio_version.h	??
extract_hess.c	
Extract part of the H.E.S.S	162
extract_simtel.c	
A program for extracting data for a subset of simulated telescopes	163

10 File Index

fcat.c	
Trivial test and utility program for the fileopen/fileclose functions	166
Allow searching of files in declared include paths (fopen replacement)	166
fileopen.h  Function prototypes for fileopen.c	173
gen_lookup.c  Generate image shape and energy lookups for user analysis in read_hess	176
gen_trgmask.c	
A utility program for fixing problems with simulation data which does not have the correct bit pattern of telescope triggers but the correct pattern can be extracted from the log files	
hconfig.c Configuration control and procedure call interface	180
hconfig.h  Declare hconfig structures and functions	190
hessio_doc.h  Add an introduction to doxygen-generated documentation	202
histogram.c	
Manage, fill, and display one- and two-dimensional histograms	202
Declarations for handling one- and two-dimensional histograms	224
Keep blocks of history in the data (like command line of programs operating on the data,)	250
initial.h  Indentification of the system and including some basic include file	251
io_hess.c  Writing and reading of H.E.S.S	254
io_hess.h	
Definition and structures for H.E.S.S	265
This file implements I/O for 1-D and 2-D histograms	274
Declarations for eventio I/O of histograms	277
io_history.c  Record history of configuration settings/commands	280
io_history.h  Record history of configuration settings/commands	283
io_simtel.c  Write and read CORSIKA blocks and simulated Cherenkov photon bunches	284
io_trgmask.c	
EventIO plus helper functions for trigger type bit patterns extracted from sim_telarray log files (only relevant for simulations with multiple trigger types using sim_telarray versions before mid-	
2013)	305
EventIO plus helper functions for trigger type bit patterns extracted from sim_telarray log files (only relevant for simulations with multiple trigger types using sim_telarray versions before mid-	
2013)	
Utility program for listing histograms	310
Definitions and structures for CORSIKA Cherenkov light interface	311
merge_simtel.c  A program for merging events from separate telescope simulations of the same showers	332
moments.c Calculate mean, rms, skewness, and kurtosis of data	334
read_hess.c	
A program reading simulated data, optionally analysing the data, and also optionally also writing summary ("DST") data	

4.1 File List

read_hess_nr.c	
A skeleton program reading H.E.S.S	346
rec_tools.h	
Tools for shower geometric reconstruction	347
reconstruct.c	
Second moments type image analysis	352
reconstruct.h	??
Prototypes for random number generators adapted from HEP Random C++ code	366
split_hessio.c	
Rip out data for each telescope into individual files	368
straux.c	
Check for abbreviations of strings and get words from strings	369
straux.h	
Check for abbreviations of strings and get words from strings	371
tohbook.c	
Convert my histograms to HBOOK (PAW) histograms	374
tohbook.h	??
toroot.cc	
Functions for conversion of eventio histograms to ROOT format	375
toroot.hh	??
user_analysis.c	
Code for analysis of simulated (and reconstructed) showers within the framework of the read $_{\leftarrow}$	
hess program	377
user_analysis.h	??
warning.c	
Pass warning messages to the screen or a usr function as set up	389
warning.h	
Pass warning messages to the screen or a usr function as set up	
$\sim$ user_analysis.h $\ldots$	

12 File Index

# **Chapter 5**

# **Module Documentation**

## 5.1 The add\_histograms program

## **Functions**

- void **syntax** (const char \*prgm)
- int main (int argc, char \*\*argv)

  Main program.
- 5.1.1 Detailed Description
- 5.1.2 Function Documentation

## 5.1.2.1 main()

```
int main (
          int argc,
          char ** argv )
```

Main program.

References verbose.

Referenced by dhsort(), line\_point\_distance(), and set\_ev\_reg\_std().

## 5.2 The best\_of program

One type is before the addition of 68% and 80% angular resolution values.

#### **Data Structures**

· struct best\_value

#### **Enumerations**

```
enum SpecType {
    SPEC_NONE = -1, SPEC_GAMMA = 0, SPEC_ELECTRON = 1, SPEC_PROTON = 101,
    SPEC_HE = 402, SPEC_CNO = 1407, SPEC_SI = 2814, SPEC_IRON = 5626,
    SPEC_NONE = -1, SPEC_GAMMA = 0, SPEC_ELECTRON = 1, SPEC_PROTON = 101,
    SPEC_HE = 402, SPEC_CNO = 1407, SPEC_SI = 2814, SPEC_IRON = 5626 }

enum espec_t {
    OLD_E_POWERLAW = 1, NEW_E_POWERLAW = 2, NEW_E_PL_LGN1 = 3, NEW_E_PL_LGN2 = 4,
    OLD_E_POWERLAW = 1, NEW_E_POWERLAW = 2, NEW_E_PL_LGN1 = 3, NEW_E_PL_LGN2 = 4 }

enum BestChoice {
    BestDiff = 1, BestIntegral = 2, BestAngle = 3, BestEres = 4,
    BestRate = 5, BestCombined = 6, BestAll = 7 }
```

#### **Functions**

- string particle\_type (SpecType sp)
- double Crab Unit (double E)
- static double **cu** (double x)
- · double Crab Unit int (double E)
- double **ergs** (double E)
- static double f50 (double x)
- static double **fsp50** (double x)
- double Flux\_req50\_south (double E)
- double Flux\_req50\_E2erg\_south (double E)
- double Flux\_req50\_CU\_south (double E)
- static double fn50 (double x)
- static double fnsp50 (double x)
- double Flux\_req50\_north (double E)
- double Flux\_req50\_E2erg\_north (double E)
- double Flux\_req50\_CU\_north (double E)
- static double **f5** (double x)
- static double **fsp5** (double x)
- double Flux req5 south (double E)
- double Flux req5 E2erg south (double E)
- double Flux\_req5\_CU\_south (double E)
- static double fn5 (double x)
- static double fnsp5 (double x)
- double Flux\_req5\_north (double E)
- double Flux\_req5\_E2erg\_north (double E)
- double Flux\_req5\_CU\_north (double E)
- static double f05 (double x)
- static double fsp05 (double x)

- double Flux\_req05\_south (double E)
- double Flux\_req05\_E2erg\_south (double E)
- double Flux req05 CU south (double E)
- static double **fn05** (double x)
- static double **fnsp05** (double x)
- double Flux\_req05\_north (double E)
- double Flux\_req05\_E2erg\_north (double E)
- double Flux req05 CU north (double E)
- static double fd50 (double x)
- static double **fdes50** (double x)
- double Flux goal50 south (double E)
- double Flux\_goal50\_E2erg\_south (double E)
- double Flux\_goal50\_CU\_south (double E)
- static double fnd50 (double x)
- static double fndes50 (double x)
- double Flux goal50 north (double E)
- double Flux\_goal50\_E2erg\_north (double E)
- double Flux\_goal50\_CU\_north (double E)
- double Angular\_resolution\_req (double E)
- double Angular\_resolution\_goal (double E)
- static double eresb (double E)
- double Energy\_resolution\_req (double E)
- static double **eresdb** (double E)
- double Energy\_resolution\_goal (double E)
- double flux\_int (SpecType sp, double E1, double E2)
- double lima17 (double on, double off, double alpha)
- bool matching\_required\_diffsens (int calc\_pput, bool with\_flux, double E, double diff\_sens)
- bool matching\_required\_performance (int calc\_pput, bool with\_flux, double E, double diff\_sens, double angres, double eres)
- bool matching\_required\_angres (double E, double angres)
- bool matching\_required\_eres (double E, double eres)
- int main (int argc, char \*\*argv)

#### **Variables**

- static double **sce** = 1.6022
- static double **sca** = 1e-4
- static double **sc** = sce\*sca
- espec\_t espec\_type = OLD\_E\_POWERLAW

#### 5.2.1 Detailed Description

One type is before the addition of 68% and 80% angular resolution values.

Another one is after addition of angular resolution but before addition of the energy resolution, and the third one is after the energy resolution got added to the output. The different formats are recognized by the presence and position of the histogram number (12056 to 12064 normally) on which the sensitivity evaluation is mainly based.

## 5.3 The fcat program

## Macros

• #define **BSIZE** 8192

## **Functions**

• int main (int argc, char \*\*argv)

## 5.3.1 Detailed Description

## 5.4 The list\_histogram program

## **Functions**

```
• int main (int argc, char **argv)

Main program.
```

- 5.4.1 Detailed Description
- 5.4.2 Function Documentation

## 5.4.2.1 main()

```
int main (
          int argc,
          char ** argv )
```

Main program.

References verbose.

# 5.5 The check\_trgmask program

## **Functions**

• int main (int argc, char \*\*argv)

## 5.5.1 Detailed Description

## 5.6 The extract\_hess program

## **Functions**

```
    static void syntax (char *program)
        Show program syntax.

    int main (int argc, char **argv)
```

## **Variables**

· static int interrupted

Main program.

- 5.6.1 Detailed Description
- 5.6.2 Function Documentation

## 5.6.2.1 main()


```
int main (
          int argc,
          char ** argv )
```

Main program.

Main program function of extract\_hess.c program.

## 5.7 The extract\_simtel program

Collaboration diagram for The extract\_simtel program:



#### **Data Structures**

• struct map\_tel\_struct

Structure with per output telescope information keeping track of prerequisites.

#### **Functions**

static void syntax (const char \*program)

Show program syntax.

• int find in tel idx (int tel id, int ifile)

Offset of an input telescope of given ID within the input structures.

• int find\_out\_tel\_idx (int tel\_id, int ifile)

Offset of an input telescope of given ID within the output structures.

• int find\_mapped\_telescope (int tel\_id, int ifile)

Mapping from telescope ID on input to telescope ID on output, with check.

• int write\_io\_block\_to\_file (IO\_BUFFER \*iobuf, FILE \*f)

Write an I/O block as-is to another file than foreseen for the I/O buffer.

- int check\_for\_delayed\_write (IO\_ITEM\_HEADER \*item\_header, int ifile, AllHessData \*hsdata\_out, IO\_←
  BUFFER \*iobuf out)
- int merge\_data\_from\_io\_block (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*item\_header, int ifile, AllHessData \*hsdata, AllHessData \*hsdata out, IO BUFFER \*iobuf out)

Processing of I/O blocks from the input file.

• int check\_autoload\_trgmask (const char \*input\_fname, IO\_BUFFER \*iobuf, int ifile)

Check for a 'trgmask.gz' file matching the given input data file name and, if it exists, extract the corrected trigger bit patterns from it.

- void print process status (int prev type1, int this type1)
- int read\_map (const char \*map\_fname)
- int main (int argc, char \*\*argv)

Main program.

#### **Variables**

```
    static int interrupted
    static int verbose = 0
    struct map tel struct
```

• struct map\_tel\_struct map\_tel [H\_MAX\_TEL]

```
• int map_to [2][H_MAX_TEL+1]
```

Mapping structures from input telescope ID to output telescope ID.

int tel\_idx [2][H\_MAX\_TEL+1]

Mapping from telescope IDs to offsets in the data structures, first for input telescope IDs.

int tel\_idx\_out [H\_MAX\_TEL+1]

Mapping from output telescope ID to offset in output data structures.

- int ntel1
- int ntel2
- int **ntel**
- · int nrtel1
- · int nrtel2
- long **event1** = -1
- long **event2** = 0
- long ev\_hess\_event = 0
- long ev\_pe\_sum = 0

For delayed writing.

- int run1 = -1
- int run2 = -1
- int min\_trg = 2
- static struct trgmask\_set \* tms [2] = { NULL, NULL }
- static struct trgmask\_hash\_set \* ths [2] = { NULL, NULL }
- static int **events** [2] = { 0, 0 }
- static int **mcshowers** [2] = { 0, 0 }
- static int **mcevents** [2] = { 0, 0 }
- static int max\_list = 999

#### 5.7.1 Detailed Description

#### 5.7.2 Function Documentation

#### 5.7.2.1 check\_autoload\_trgmask()

Check for a 'trgmask.gz' file matching the given input data file name and, if it exists, extract the corrected trigger bit patterns from it.

(Note: this is only relevant for multi-trigger data produced with a bug in recording the trigger bit pattern.)

We do not need to merge the contents of this file since the trigger bit patterns are corrected after reading the data.

References fileopen().

## 5.7.3 Variable Documentation

```
5.7.3.1 map_to
```

```
int map_to[2][H_MAX_TEL+1]
```

Mapping structures from input telescope ID to output telescope ID.

Not mapped telescopes are defined by output telescope ID of -1. The telescope ID to which a given input telescope ID should get mapped.

Referenced by find\_mapped\_telescope(), and find\_out\_tel\_idx().

```
5.7.3.2 tel_idx
```

```
int tel_idx[2][H_MAX_TEL+1]
```

Mapping from telescope IDs to offsets in the data structures, first for input telescope IDs.

We restrict the ID/index mapping here to well behaved cases (0<ID<=H\_MAX\_TEL). An index value of -1 indicates a non-existant/ignored telescope. Where is a telescope of given ID in the input data structures?

Referenced by find\_in\_tel\_idx(), and find\_out\_tel\_idx().

```
5.7.3.3 tel_idx_out
```

```
int tel_idx_out[H_MAX_TEL+1]
```

Mapping from output telescope ID to offset in output data structures.

Where is a telescope of given ID in the output data structures?

Referenced by find\_out\_tel\_idx().

## 5.8 The gen\_trgmask program


## **Functions**

- void **syntax** (char \*prgname)
- int main (int argc, char \*\*argv)

## 5.8.1 Detailed Description

## 5.9 The merge\_simtel program

Collaboration diagram for The merge\_simtel program:



#### **Data Structures**

struct map\_tel\_struct

Structure with per output telescope information keeping track of prerequisites.

#### **Functions**

void stop\_signal\_function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

• int find\_in\_tel\_idx (int tel\_id, int ifile)

Offset of an input telescope of given ID within the input structures.

int find\_out\_tel\_idx (int tel\_id, int ifile)

Offset of an input telescope of given ID within the output structures.

• int find\_mapped\_telescope (int tel\_id, int ifile)

Mapping from telescope ID on input to telescope ID on output, with check.

int write\_io\_block\_to\_file (IO\_BUFFER \*iobuf, FILE \*f)

Write an I/O block as-is to another file than foreseen for the I/O buffer.

- int has min\_trg\_tel (AllHessData \*hsdata out, int mtrg, double rtm)
- int check\_for\_delayed\_write (IO\_ITEM\_HEADER \*item\_header, int ifile, AllHessData \*hsdata\_out, IO\_←
  BUFFER \*iobuf out)
- int merge\_data\_from\_io\_block (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*item\_header, int ifile, AllHessData \*hsdata, AllHessData \*hsdata\_out, IO\_BUFFER \*iobuf\_out)

Processing and merging of I/O blocks from the two input files, hopefully presented in the right order.

• int check autoload trgmask (const char \*input fname, IO BUFFER \*iobuf, int ifile)

Check for a 'trgmask.gz' file matching the given input data file name and, if it exists, extract the corrected trigger bit patterns from it.

- void print\_process\_status (int prev\_type1, int this\_type1, int prev\_type2, int this\_type2)
- int read\_map (const char \*map\_fname)
- static void syntax (const char \*program)

Show program syntax.

• int main (int argc, char \*\*argv)

Main program.

#### **Variables**

```
static int interrupted
static int verbose = 0
struct map_tel_struct map_tel [H_MAX_TEL]
int map_to [2][H_MAX_TEL+1]
Mapping structures from input telescope ID to output telescope ID.
int tel_idx [2][H_MAX_TEL+1]
Mapping from telescope IDs to offsets in the data structures, first for input telescope IDs.
int tel_idx_out [H_MAX_TEL+1]
Mapping from output telescope ID to offset in output data structures.
```

- · int ntel1
- int ntel2
- int ntel
- int nrtel1
- · int nrtel2
- long **event1** = -1
- long **event2** = 0
- long ev\_hess\_event = 0
- long ev\_pe\_sum = 0

For delayed writing.

- int run1 = -1
- int run2 = -1
- int min\_trg = 2
- double distinct\_sep = 1.0
- static struct trgmask\_set \* tms [2] = { NULL, NULL }
- static struct trgmask hash set \* ths [2] = { NULL, NULL }
- static int **events** [2] = { 0, 0 }
- static int **mcshowers** [2] = { 0, 0 }
- static int **mcevents** [2] = { 0, 0 }
- static int max\_list = 999

#### 5.9.1 Detailed Description

#### 5.9.2 Function Documentation

## 5.9.2.1 check\_autoload\_trgmask()

Check for a 'trgmask.gz' file matching the given input data file name and, if it exists, extract the corrected trigger bit patterns from it.

(Note: this is only relevant for multi-trigger data produced with a bug in recording the trigger bit pattern.)

We do not need to merge the contents of this file since the trigger bit patterns are corrected after reading the data.

References fileopen().

#### 5.9.2.2 stop\_signal\_function()

```
void stop_signal_function ( int \ isig \ )
```

Stop the program gracefully when it catches an INT or TERM signal.

#### **Parameters**

```
isig Signal number.
```

#### Returns

(none)

### 5.9.3 Variable Documentation

```
5.9.3.1 map_to
```

```
int map_to[2][H_MAX_TEL+1]
```

Mapping structures from input telescope ID to output telescope ID.

Not mapped telescopes are defined by output telescope ID of -1. The telescope ID to which a given input telescope ID should get mapped.

Referenced by find\_mapped\_telescope(), and find\_out\_tel\_idx().

```
5.9.3.2 tel_idx
```

```
int tel_idx[2][H_MAX_TEL+1]
```

Mapping from telescope IDs to offsets in the data structures, first for input telescope IDs.

We restrict the ID/index mapping here to well behaved cases (0<ID<=H\_MAX\_TEL). An index value of -1 indicates a non-existant/ignored telescope. Where is a telescope of given ID in the input data structures?

Referenced by find\_in\_tel\_idx(), and find\_out\_tel\_idx().

```
5.9.3.3 tel_idx_out
```

```
int tel_idx_out[H_MAX_TEL+1]
```

Mapping from output telescope ID to offset in output data structures.

Where is a telescope of given ID in the output data structures?

Referenced by find\_out\_tel\_idx().

## 5.10 The read\_hess (aka read\_simtel, read\_cta) program

#### **Data Structures**

- · struct next file struct
- · struct range\_list\_struct

#### **Macros**

• #define CALIB SCALE 0.92

The factor needed to transform from mean p.e.

• #define CALIB SCALE 0.92

The factor needed to transform from mean p.e.

## **Typedefs**

- typedef struct next file struct NextFile
- typedef struct range\_list\_struct RangeList
- typedef struct next\_file\_struct NextFile

#### **Functions**

• void stop\_signal\_function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

- static void init\_rand (int is)
- double grand48 (double mean, double sigma)

Like RandFlat() from rndm2.c but using the drand48 engine.

static void mc\_event\_fill (AllHessData \*hsdata, double d\_sp\_idx)

Fill histogram(s) for DST writing which require all MC shower and event data and which cannot be filled from DST level >= 2 data.

• static int write\_dst\_histos (IO\_BUFFER \*iobuf2)

Write histograms for DST book-keeping and clear them afterwards.

- static void **show\_run\_summary** (AllHessData \*hsdata, int nev, int ntrg, double plidx, double wsum\_all, double wsum\_trg, double rmax\_x, double rmax\_y, double rmax\_r)
- static void syntax (char \*program)

Show program syntax.

- NextFile \* add next\_file (const char \*fn, NextFile \*nxt)
- RangeList \* add\_range (long f, long t, RangeList \*rl)
- int is\_in\_range (long n, RangeList \*rl)
- int main (int argc, char \*\*argv)

Main program.

#### **Variables**

- struct basic\_ntuple bnt
- static int interrupted
- · static int dst\_processing
- · static int g48 set
- static double g48\_next
- struct basic\_ntuple bnt
- · static int interrupted
- · static int dst\_processing

## 5.10.1 Detailed Description

#### 5.10.2 Macro Definition Documentation

```
5.10.2.1 CALIB_SCALE [1/2] #define CALIB_SCALE 0.92
```

The factor needed to transform from mean p.e.

units to units of the single-p.e. peak: Depends on the collection efficiency, the asymmetry of the single p.e. amplitude distribution and the electronic noise added to the signals.

```
5.10.2.2 CALIB_SCALE [2/2]
#define CALIB_SCALE 0.92
```

The factor needed to transform from mean p.e.

units to units of the single-p.e. peak: Depends on the collection efficiency, the asymmetry of the single p.e. amplitude distribution and the electronic noise added to the signals.

#### 5.10.3 Function Documentation

```
5.10.3.1 main()
```

```
int main (
          int argc,
          char ** argv )
```

Main program.

Main program function of read\_hess.c program.

References verbose.

## 5.10.3.2 stop\_signal\_function()

Stop the program gracefully when it catches an INT or TERM signal.

## **Parameters**

isig Signal number.

## Returns

(none)

## 5.11 The read\_hess\_nr program

#### **Macros**

- #define UNUSED
- #define CALIB\_SCALE 0.92

The factor needed to transform from mean p.e.

#### **Functions**

- double calibrate\_pixel\_amplitude (AllHessData \*hsdata, int itel, int ipix, int dummy, double cdummy)
   Calibrate a single pixel amplitude, for cameras with two gains per pixel.
- double calibrate\_pixel\_amplitude (AllHessData \*hsdata, int itel, int ipix, \_UNUSED\_ int dummy, \_UNUS
   ED\_ double cdummy)
- void stop\_signal\_function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

- static void **show\_run\_summary** (AllHessData \*hsdata, int nev, int ntrg, double plidx, double wsum\_all, double wsum\_trg, double rmax\_x, double rmax\_y, double rmax\_r)
- static void syntax (char \*program)

Show program syntax.

• int main (int argc, char \*\*argv)

Main program.

#### **Variables**

- · static int interrupted
- 5.11.1 Detailed Description
- 5.11.2 Macro Definition Documentation

#### 5.11.2.1 CALIB\_SCALE

```
#define CALIB_SCALE 0.92
```

The factor needed to transform from mean p.e.

units to units of the single-p.e. peak: Depends on the collection efficiency, the asymmetry of the single p.e. amplitude distribution and the electronic noise added to the signals.

#### 5.11.3 Function Documentation

#### 5.11.3.1 calibrate\_pixel\_amplitude()

Calibrate a single pixel amplitude, for cameras with two gains per pixel.

This version does not include amplitude clipping nor obtaining amplitudes from the pixel timing data structure.

#### Returns

Pixel amplitude in peak p.e. units.

## 5.11.3.2 main()

```
int main (
          int argc,
          char ** argv )
```

Main program.

Main program function of read\_hess.c program.

References user\_parameters::reco\_flag, and verbose.

#### 5.11.3.3 stop\_signal\_function()

Stop the program gracefully when it catches an INT or TERM signal.

#### **Parameters**

```
isig Signal number.
```

#### Returns

(none)

## 5.12 The split\_hessio program

## **Functions**

```
    void stop_signal_function (int isig)
    Stop the program gracefully when it catches an INT or TERM signal.
```

```
• static void syntax (char *program)

Show program syntax.
```

```
• int main (int argc, char **argv)
```

Main program.

#### **Variables**

· static int interrupted

## 5.12.1 Detailed Description

#### 5.12.2 Function Documentation

#### 5.12.2.1 main()

```
int main (
          int argc,
          char ** argv )
```

Main program.

Main program function of read\_hess.c program.

References verbose.

## 5.12.2.2 stop\_signal\_function()

Stop the program gracefully when it catches an INT or TERM signal.

#### **Parameters**

isig Signal number.

Returns

(none)

## 5.13 The hdata2hbook program (cvt2)

## **Functions**

```
• int main (int argc, char **argv)

Main program.
```

- 5.13.1 Detailed Description
- 5.13.2 Function Documentation

```
5.13.2.1 main()
```

```
int main (
          int argc,
          char ** argv )
```

Main program.

References verbose.

## 5.14 The hdata2root program (cvt3)

## **Functions**

- int read\_file (IO\_BUFFER \*iobuf, const char \*fname, int add\_flag, int list\_flag)
- int main (int argc, char \*\*argv)

## 5.14.1 Detailed Description

# **Chapter 6**

# **Data Structure Documentation**

## 6.1 basic\_ntuple Struct Reference

A struct with basic per-shower parameters, to be used as an n-tuple in the event selection.

```
#include <basic_ntuple.h>
```

#### **Data Fields**

· int primary

Primary particle ID.

• int run

Simulation run number.

· int event

Event number (100\*shower number + array number)

· double weight

Event weight, not to be used for selection (based on true energy).

• double lg\_e\_true

log10(true energy of primary).

double xfirst\_true

Atmospheric depth of first interaction.

· double xmax\_true

True shower maximum atmospheric depth (not well defined with few particles).

• double xc\_true

True core position at detection level (x coordinate).

· double yc\_true

True core position at detection level (y coordinate).

• double az\_true

True shower direction (Azimuth).

double alt true

True shower direction (Altitude).

· double xc

Reconstructed core position at detection level (x coordinate).

double yc

Reconstructed core position at detection level (y coordinate).

· double az

Reconstructed shower direction (Azimuth).

· double alt

Reconstructed shower direction (Altitude).

· double rcm

Mean core distance of telescopes used in reconstruction.

double mdisp

Mean DISP (1.

· double theta

Angle between source position and rec.

• double sig\_theta

R.m.s.

double mscrw

Mean scaled reduced width.

· double sig\_mscrw

R.m.s.

· double mscrl

Mean scaled reduced length.

· double sig\_mscrl

R.m.s.

· double xmax

Depth of shower maximum.

· double sig\_xmax

R.m.s.

• double lg e

Log10 of reconstructed energy.

• double sig\_e

Relative error estimate on E (NOT the r.m.s.

• double chi2 e

Consistency of individual energy estimates as reduced chi\*\*2 value.

double tslope

Core distance corrected mean time slope (deg/ns/100 m).

· double tsphere

R.m.s.

size\_t n\_img

Number of used images.

• size\_t n\_trg

Number of triggered telescopes.

• size\_t n\_fail

Number of failed triggers (telescopes expected to trigger).

size\_t n\_tsl0

Number of images with zero time slope well outside light pool.

size\_t n\_pix

Total number of used pixels in all used images.

· size\_t acceptance

Event acceptance level by standard selection scheme (0: no; 1: shape cuts; 2: +angular cut; 3: +dE cut; 4: +dE2 cut; 5: +Hmax cut.

## 6.1.1 Detailed Description

A struct with basic per-shower parameters, to be used as an n-tuple in the event selection.

#### 6.1.2 Field Documentation

#### 6.1.2.1 acceptance

```
size_t basic_ntuple::acceptance
```

Event acceptance level by standard selection scheme (0: no; 1: shape cuts; 2: +angular cut; 3: +dE cut; 4: +dE2 cut; 5: +Hmax cut.

#### 6.1.2.2 alt

double basic\_ntuple::alt

Reconstructed shower direction (Altitude).

#### 6.1.2.3 alt\_true

double basic\_ntuple::alt\_true

True shower direction (Altitude).

#### 6.1.2.4 az

double basic\_ntuple::az

Reconstructed shower direction (Azimuth).

#### 6.1.2.5 az\_true

double basic\_ntuple::az\_true

True shower direction (Azimuth).

Mean scaled reduced length.

```
6.1.2.6 chi2_e
double basic_ntuple::chi2_e
Consistency of individual energy estimates as reduced chi**2 value.
6.1.2.7 lg_e
double basic_ntuple::lg_e
Log10 of reconstructed energy.
Referenced by list_ntuple().
6.1.2.8 lg_e_true
double basic_ntuple::lg_e_true
log10(true energy of primary).
6.1.2.9 mdisp
double basic_ntuple::mdisp
Mean DISP (1.
-width/length) of usable images.
Referenced by list_ntuple().
6.1.2.10 mscrl
double basic_ntuple::mscrl
```

```
6.1.2.11 mscrw
```

double basic\_ntuple::mscrw

Mean scaled reduced width.

```
6.1.2.12 n_fail
```

```
size_t basic_ntuple::n_fail
```

Number of failed triggers (telescopes expected to trigger).

```
6.1.2.13 n_img
```

```
size_t basic_ntuple::n_img
```

Number of used images.

```
6.1.2.14 n_pix
```

```
size_t basic_ntuple::n_pix
```

Total number of used pixels in all used images.

#### 6.1.2.15 n\_trg

```
size_t basic_ntuple::n_trg
```

Number of triggered telescopes.

#### 6.1.2.16 n\_tsl0

```
size_t basic_ntuple::n_tsl0
```

Number of images with zero time slope well outside light pool.

R.m.s.

of scaled reduced widths of individual images.

```
6.1.2.17 primary
int basic_ntuple::primary
Primary particle ID.
6.1.2.18 rcm
double basic_ntuple::rcm
Mean core distance of telescopes used in reconstruction.
Referenced by list_ntuple().
6.1.2.19 run
int basic_ntuple::run
Simulation run number.
6.1.2.20 sig_e
double basic_ntuple::sig_e
Relative error estimate on E (NOT the r.m.s.
of individual estimates).
6.1.2.21 sig_mscrl
double basic_ntuple::sig_mscrl
R.m.s.
of scaled reduced lengths of indvidual images.
6.1.2.22 sig_mscrw
double basic_ntuple::sig_mscrw
```

```
6.1.2.23 sig_theta
double basic_ntuple::sig_theta
R.m.s.
of theta of telescopes pairs (if > 2 tel.).
6.1.2.24 sig_xmax
double basic_ntuple::sig_xmax
R.m.s.
of Xmax from individual telescopes/images.
6.1.2.25 theta
double basic_ntuple::theta
Angle between source position and rec.
shower direction.
Referenced by list_ntuple().
6.1.2.26 tslope
double basic_ntuple::tslope
Core distance corrected mean time slope (deg/ns/100 m).
6.1.2.27 tsphere
double basic_ntuple::tsphere
R.m.s.
of trigger times from spherical propagation from shower max.
6.1.2.28 weight
double basic_ntuple::weight
Event weight, not to be used for selection (based on true energy).
```

```
6.1.2.29 xc
double basic_ntuple::xc
Reconstructed core position at detection level (x coordinate).
Referenced by user_event_fill().
6.1.2.30 xc_true
double basic_ntuple::xc_true
True core position at detection level (x coordinate).
Referenced by user_event_fill().
6.1.2.31 xfirst_true
double basic_ntuple::xfirst_true
Atmospheric depth of first interaction.
6.1.2.32 xmax
double basic_ntuple::xmax
Depth of shower maximum.
6.1.2.33 xmax_true
double basic_ntuple::xmax_true
```

True shower maximum atmospheric depth (not well defined with few particles).

#### 6.1.2.34 yc

double basic\_ntuple::yc

Reconstructed core position at detection level (y coordinate).

Referenced by user\_event\_fill().

6.1.2.35 yc\_true

double basic\_ntuple::yc\_true

True core position at detection level (y coordinate).


Referenced by user\_event\_fill().

The documentation for this struct was generated from the following file:

• basic\_ntuple.h

## 6.2 best\_value Struct Reference

Collaboration diagram for best\_value:



#### **Public Member Functions**

• **best\_value** (int k, double v, int qtr, const string &t, double aeff, double vlgE, double vlgE1, double vlgE2, double vds, double vbr=0., double vgr=0., double var=0., double veb=0., double ng=0., double nb=0.)

#### **Data Fields**

- int kbin
- double best
- int q
- string text
- double A

effective area (for gammas)

- double IgE
- · double IgE1
- double IgE2
- · double diff\_sens
- double bg\_rate


- double gamma\_rate
- · double angres
- · double eres
- double ebias
- double n gamma cu
- double nint\_gamma\_cu
- double n\_bg
- double nint\_bg

The documentation for this struct was generated from the following file:

· best\_of.cc

## 6.3 Binary\_Interface\_Chain Struct Reference

Collaboration diagram for Binary\_Interface\_Chain:



#### **Data Fields**

- struct Config\_Binary\_Item\_Interface \* interface
- struct Binary\_Interface\_Chain \* next

The documentation for this struct was generated from the following file:

· hconfig.c

## 6.4 FloatCompressor::Bits Union Reference

#### **Data Fields**

- float f
- int32 t si
- uint32 t ui

The documentation for this union was generated from the following file:

• f16.cc

## 6.5 Float16Compressor::Bits Union Reference

#### **Data Fields**

- · float f
- int32\_t si
- uint32\_t ui

The documentation for this union was generated from the following file:

• f16.cc

#### 6.6 bunch Struct Reference

Photons collected in bunches of identical direction, position, time, and wavelength.

```
#include <mc_tel.h>
```

#### **Data Fields**

· float photons

Number of photons in bunch.

- float x
- float y

Arrival position relative to telescope (cm)

- float cx
- float cy

Direction cosines of photon direction.

· float ctime

Arrival time (ns)

float zem

Height of emission point above sea level (cm)

· float lambda

Wavelength in nanometers or 0.

#### 6.6.1 Detailed Description

Photons collected in bunches of identical direction, position, time, and wavelength.

The wavelength will normally be unspecified as produced by CORSIKA (lambda=0).

The documentation for this struct was generated from the following file:

• mc\_tel.h

## 6.7 camera\_nb\_list Struct Reference

#### **Data Fields**

int npix

Number of pixels in camera.

• int nbsize

Number of neighbours in list (elements in nblist).

• int \* pix\_num\_nb

Number of neighbours for each pixel.

• int \* pix\_first\_nb

Where in list is the first of the neighbours for each pixel.

int \* nblist

The actual packed list of all neighbours for all pixels.

The documentation for this struct was generated from the following file:

· reconstruct.c

## 6.8 compact\_bunch Struct Reference

The compact\_bunch struct is equivalent to the bunch struct except that we try to use less memory.

```
#include <mc_tel.h>
```

#### **Data Fields**

· short photons

ph\*100

- short x
- short y

x,y\*10 (mm)

- short cx
- short cy

cx,cy\*30000

· short ctime

ctime\*10 (0.1ns) after subtracting offset

• short log\_zem

log10(zem)\*1000

short lambda

(nm) or 0

#### 6.8.1 Detailed Description

The compact\_bunch struct is equivalent to the bunch struct except that we try to use less memory.

And that has a number of limitations: 1) Bunch sizes must be less than 327. 2) photon impact points in a horizontal plane through the centre of each detector sphere must be less than 32.7 m from the detector centre in both x and y coordinates. Thus,  $\sec(z) * R < 32.7$  m is required, with 'z' being the zenith angle and 'R' the radius of the detecor sphere. When accounting for multiple scattering and Cherenkov emission angles, the actual limit is reached even earlier than that. 3) Only times within 3.27 microseconds from the time, when the primary particle propagated with the speed of light would cross the altitude of the sphere centre, can be treated. For large zenith angle observations this limits horizontal core distances to about 1000 m. For efficiency reasons, no checks are made on these limits.

The documentation for this struct was generated from the following file:

· mc tel.h

## 6.9 Config\_Binary\_Item\_Interface Struct Reference

Interface definitions for binary-only items.

```
#include <hconfig.h>
```

#### **Data Fields**

· int io\_item\_type

The eventio item type.

· int elem\_size

The size of the elements.

void \*(\* new\_func )(int nelem, int item\_type)

The function to be called for allocating elements.

int(\* delete\_func )(void \*ptr, int nelem, int item\_type)

The function to be called for deleting elements.

int(\* read\_func )(void \*bin\_item, IO\_BUFFER \*iobuf, int item\_type)

The function to be called for reading elements from buffer.

int(\* write\_func )(void \*bin\_item, IO\_BUFFER \*iobuf, int item\_type)

The function to be called for writing elements to buffer.

• int(\* readtext func )(void \*bin item, char \*text, int item type)

The function to be called for reading elements from text line.

• int(\* list\_func )(void \*bin\_item, int item\_type)

The optional function for listing element contents.

int(\* copy\_func )(void \*bin\_item\_to, void \*bin\_item\_from, int io\_type)

The optional function for copying elements.

#### 6.9.1 Detailed Description

Interface definitions for binary-only items.

Binary-only items are structures, classes, or unions which can only be filled via dedicated functions (methods) and not via the standard text-input.

This structure defines available interface methods. The item type is always passed to the functions, in case that a function can handle more than one type.

#### 6.9.2 Field Documentation

#### 6.9.2.1 copy\_func

int(\* Config\_Binary\_Item\_Interface::copy\_func) (void \*bin\_item\_to, void \*bin\_item\_from, int
io\_type)

The optional function for copying elements.

This is only needed if the element includes pointers to external or dynamically allocated material.

#### 6.9.2.2 delete\_func

```
int(* Config_Binary_Item_Interface::delete_func) (void *ptr, int nelem, int item_type)
```

The function to be called for deleting elements.

#### 6.9.2.3 elem\_size

```
int Config_Binary_Item_Interface::elem_size
```

The size of the elements.

#### 6.9.2.4 io\_item\_type

```
int Config_Binary_Item_Interface::io_item_type
```

The eventio item type.

Referenced by find\_config\_binary\_interface().

#### 6.9.2.5 list func

```
int(* Config_Binary_Item_Interface::list_func) (void *bin_item, int item_type)
```

The optional function for listing element contents.

#### 6.9.2.6 new\_func

```
void*(* Config_Binary_Item_Interface::new_func) (int nelem, int item_type)
```

The function to be called for allocating elements.

#### 6.9.2.7 read func

```
int (* Config\_Binary\_Item\_Interface::read\_func) (void *bin\_item, IO\_BUFFER *iobuf, int item\_ \leftrightarrow type)
```

The function to be called for reading elements from buffer.

#### 6.9.2.8 readtext\_func

```
int(* Config_Binary_Item_Interface::readtext_func) (void *bin_item, char *text, int item_type)
```

The function to be called for reading elements from text line.

Referenced by define\_config\_binary\_interface().

#### 6.9.2.9 write\_func

```
int (* Config_Binary_Item_Interface::write_func) (void *bin_item, IO_BUFFER *iobuf, int item\_ \leftrightarrow type)
```

The function to be called for writing elements to buffer.

The documentation for this struct was generated from the following file:

· hconfig.h

## 6.10 config\_specific\_data Struct Reference

#### **Data Fields**

• char default\_section [65]


The documentation for this struct was generated from the following file:

hconfig.c

## 6.11 ConfigBlockStruct Struct Reference

Configuration is organized in sections.

Collaboration diagram for ConfigBlockStruct:



#### **Data Fields**

- const char \* section
- struct ConfigItemStruct \* items
- struct ConfigBlockStruct \* next
- int flag

#### 6.11.1 Detailed Description

Configuration is organized in sections.

CONFIG\_BLOCK used for bookkeeping of that.

The documentation for this struct was generated from the following file:

hconfig.c

## 6.12 ConfigBoundary Union Reference

Configuration value may have optional lower and/or upper bounds.

```
#include <hconfig.h>
```

#### **Data Fields**

- · long Ival
- · unsigned long ulval
- double \* rval

#### 6.12.1 Detailed Description

Configuration value may have optional lower and/or upper bounds.

The documentation for this union was generated from the following file:

· hconfig.h

## 6.13 ConfigDataPointer Union Reference

This union of pointers allows convenient access of various types of data.

```
#include <hconfig.h>
```

#### **Data Fields**

- void \* anything
- char \* cdata
- unsigned char \* ucdata
- short \* sdata
- unsigned short \* usdata
- int \* idata
- unsigned int \* uidata
- long \* Idata
- unsigned long \* uldata
- float \* fdata
- double \* ddata

#### 6.13.1 Detailed Description

This union of pointers allows convenient access of various types of data.

The documentation for this union was generated from the following file:


· hconfig.h

## 6.14 ConfigIntern Struct Reference

Configuration elements used only internally.

#include <hconfig.h>

Collaboration diagram for ConfigIntern:



#### **Data Fields**

· int itype

Parameter type code.

• int elem\_size

Size of elements in bytes.

int locked

Set to 1 if locked.

• int bound

Bits 0-3 set if lower soft, upper soft,.

union ConfigBoundary Ibound\_soft

Used for checking new values.

• union ConfigBoundary ubound\_soft

Used for checking new values.

union ConfigBoundary Ibound\_hard

Used for checking new values.

union ConfigBoundary ubound\_hard

Used for checking new values.

struct ConfigValues values

Passed to user function.

- struct Config\_Binary\_Item\_Interface \* bin\_interface
- int bin\_alloc\_elements

#### 6.14.1 Detailed Description

Configuration elements used only internally.

#### 6.14.2 Field Documentation

```
6.14.2.1 bound
int ConfigIntern::bound
Bits 0-3 set if lower soft, upper soft,.
lower hard, or upper hard bound present.
6.14.2.2 elem_size
int ConfigIntern::elem_size
Size of elements in bytes.
6.14.2.3 itype
int ConfigIntern::itype
Parameter type code.
Referenced by display_config_current().
6.14.2.4 lbound_hard
union ConfigBoundary ConfigIntern::lbound_hard
Used for checking new values.
6.14.2.5 lbound_soft
union ConfigBoundary ConfigIntern::lbound_soft
```

Used for checking new values.

· hconfig.h


# 6.14.2.6 locked int ConfigIntern::locked Set to 1 if locked. Referenced by display\_config\_item(). 6.14.2.7 ubound\_hard union ConfigBoundary ConfigIntern::ubound\_hard Used for checking new values. 6.14.2.8 ubound\_soft union ConfigBoundary ConfigIntern::ubound\_soft Used for checking new values. 6.14.2.9 values struct ConfigValues ConfigIntern::values Passed to user function. The documentation for this struct was generated from the following file:

## 6.15 ConfigItemStruct Struct Reference

Configuration as used in definitions of configuration blocks.

#include <hconfig.h>

Collaboration diagram for ConfigItemStruct:



#### **Data Fields**

• const char \* name

Parameter/function name.

const char \* type

Data/function type.

int size

Number of elements.

void \* data

Data pointer or NULL.

PFIX function

Associated function or NULL.

const char \* initial

Initial values/argument or NULL.

• const char \* lbound

Lower bound (soft,hard) on values or NULL.

const char \* ubound

Upper bound (soft,hard) on values or NULL.

· int flags

Additional flag bits.

· PFISS validate

Function to validate if change is possible or NULL.

void \* res1

Placeholder to keep structure size the same.

void \* res2

Not used.

· struct ConfigIntern internal

Internal data.

## 6.15.1 Detailed Description

Configuration as used in definitions of configuration blocks.

#### 6.15.2 Field Documentation

#### 6.15.2.1 data

void\* ConfigItemStruct::data

Data pointer or NULL.

Referenced by display\_config\_current().

#### 6.15.2.2 flags

int ConfigItemStruct::flags

Additional flag bits.

Referenced by set\_config\_values().

#### 6.15.2.3 function

PFIX ConfigItemStruct::function

Associated function or NULL.

## 6.15 ConfigltemStruct Struct Reference 6.15.2.4 initial const char\* ConfigItemStruct::initial Initial values/argument or NULL. 6.15.2.5 internal struct ConfigIntern ConfigItemStruct::internal Internal data. Referenced by display\_config\_current(), and display\_config\_item(). 6.15.2.6 Ibound const char\* ConfigItemStruct::lbound Lower bound (soft,hard) on values or NULL. 6.15.2.7 name const char\* ConfigItemStruct::name Parameter/function name. Referenced by display\_config\_item(). 6.15.2.8 res1 void\* ConfigItemStruct::res1 Placeholder to keep structure size the same.

#### void\* ConfigItemStruct::res2

6.15.2.9 res2

Not used.

#### 6.15.2.10 size

int ConfigItemStruct::size

Number of elements.

Referenced by display\_config\_current().

#### 6.15.2.11 type

const char\* ConfigItemStruct::type

Data/function type.

Referenced by display\_config\_item().

#### 6.15.2.12 ubound

const char\* ConfigItemStruct::ubound

Upper bound (soft,hard) on values or NULL.

#### 6.15.2.13 validate

PFISS ConfigItemStruct::validate

Function to validate if change is possible or NULL.

The documentation for this struct was generated from the following file:

· hconfig.h

## 6.16 ConfigValues Struct Reference

Configuration values and supporting data passed to user functions.

#include <hconfig.h>

#### **Data Fields**

void \* data\_changed

Pointer to the updated values.

void \* data\_saved

Pointer to the saved values.

int max mod

How many elements can, at most, be modified.

• int nmod

How many have been modified.

int \* list\_mod

List of indices to modified elements.

• unsigned char \* mod flag

Vector of size max\_mod indicating modified elements.

int itype

Internal item type representation.

• const char \* name

The name of the element.

• const char \* section

The section to which it belongs.

· int elements

The number of elements it has.

• int elem\_size

The size of one element in bytes.

· int binary\_config

Set to one if binary configuration was used.

#### 6.16.1 Detailed Description

Configuration values and supporting data passed to user functions.

#### 6.16.2 Field Documentation

#### 6.16.2.1 binary\_config

```
int ConfigValues::binary_config
```

Set to one if binary configuration was used.

#### 6.16.2.2 data\_changed

```
void* ConfigValues::data_changed
```

Pointer to the updated values.

#### 6.16.2.3 data\_saved

void\* ConfigValues::data\_saved

Pointer to the saved values.

#### 6.16.2.4 elem\_size

int ConfigValues::elem\_size

The size of one element in bytes.

#### 6.16.2.5 elements

int ConfigValues::elements

The number of elements it has.

## 6.16.2.6 itype

int ConfigValues::itype

Internal item type representation.

#### 6.16.2.7 list\_mod

int\* ConfigValues::list\_mod

List of indices to modified elements.

#### 6.16.2.8 max\_mod

int ConfigValues::max\_mod

How many elements can, at most, be modified.

#### 6.16.2.9 mod\_flag

```
unsigned char* ConfigValues::mod_flag
```

Vector of size max\_mod indicating modified elements.

#### 6.16.2.10 name

```
const char* ConfigValues::name
```

The name of the element.

#### 6.16.2.11 nmod

int ConfigValues::nmod

How many have been modified.

#### 6.16.2.12 section

```
const char* ConfigValues::section
```

The section to which it belongs.

The documentation for this struct was generated from the following file:

· hconfig.h

## 6.17 ebias\_cor\_data Struct Reference

#### **Data Fields**

- int ndat
- double \* IgE
- double \* IgDE

The documentation for this struct was generated from the following file:

user\_analysis.c

## 6.18 ev\_reg\_chain Struct Reference

Use a double-linked list for the registry.

Collaboration diagram for ev\_reg\_chain:



#### **Data Fields**

- struct ev\_reg\_entry \* entry

  The current entry.
- struct ev\_reg\_chain \* prev
- struct ev\_reg\_chain \* next

#### 6.18.1 Detailed Description

Use a double-linked list for the registry.

The documentation for this struct was generated from the following file:

• eventio\_registry.c

## 6.19 Float16Compressor Class Reference

#### **Data Structures**

• union Bits

#### **Static Public Member Functions**

- static uint16\_t compress (float value)
- static float decompress (uint16\_t value)

#### **Static Private Attributes**

- static int const shift = 13
- static int const shiftSign = 16
- static int32 t const infN = 0x7F800000
- static int32 t const maxN = 0x477FE000
- static int32\_t const **minN** = 0x38800000
- static int32\_t const signN = 0x80000000
- static int32 t const infC = infN >> shift
- static int32 t const nanN = (infC + 1) << shift
- static int32 t const maxC = maxN >> shift
- static int32\_t const **minC** = minN >> shift
- static int32\_t const signC = signN >> shiftSign
- static int32 t const **mulN** = 0x52000000
- static int32\_t const **mulC** = 0x33800000
- static int32 t const subC = 0x003FF
- static int32\_t const **norC** = 0x00400
- static int32 t const maxD = infC maxC 1
- static int32\_t const minD = minC subC 1

The documentation for this class was generated from the following file:

• f16.cc

## 6.20 FloatCompressor Class Reference

#### **Data Structures**

• union Bits

#### **Public Member Functions**

- FloatCompressor (float min, float epsilon, float max, int precision)
- float clamp (float value)
- uint32\_t compress (float value)
- float **decompress** (uint32 t value)

#### **Private Attributes**

- bool hasNegatives
- · bool noLoss
- int32\_t \_maxF
- int32\_t \_minF
- int32\_t \_epsF
- int32\_t \_maxC
- int32\_t \_zeroC
- int32\_t \_pDelta
- int32 t\_nDelta
- int \_shift

#### **Static Private Attributes**

- static int32\_t const **signF** = 0x80000000
- static int32\_t const  $absF = \sim signF$

The documentation for this class was generated from the following file:


• f16.cc

## 6.21 hess\_all\_data\_struct Struct Reference

Container for all H.E.S.S.

#include <io\_hess.h>

Collaboration diagram for hess\_all\_data\_struct:



#### **Data Fields**

- RunHeader run\_header
- MCRunHeader mc\_run\_header
- CameraSettings camera\_set [H\_MAX\_TEL]
- CameraOrganisation camera org [H MAX TEL]
- PixelSetting pixel\_set [H\_MAX\_TEL]
- PixelDisabled pixel\_disabled [H\_MAX\_TEL]
- CameraSoftSet cam\_soft\_set [H\_MAX\_TEL]
- TrackingSetup tracking\_set [H\_MAX\_TEL]
- PointingCorrection point\_cor [H\_MAX\_TEL]
- FullEvent event
- MCShower mc shower
- · MCEvent mc event
- TelMoniData tel\_moni [H\_MAX\_TEL]
- LasCalData tel\_lascal [H\_MAX\_TEL]
- RunStat run\_stat
- MCRunStat mc\_run\_stat

#### 6.21.1 Detailed Description

Container for all H.E.S.S.

data

The documentation for this struct was generated from the following file:

• io\_hess.h

## 6.22 hess\_aux\_analog\_trace Struct Reference

#### **Data Fields**

· int known

Must be set to 1 if and only if corresponding data is available.

int tel\_id

Must match the expected telescope ID when reading.

· int trace\_type

Indicate what type of trace we have (1: pixel input, 2: analog sum, 3: disc/comp. output, 4: majority input)

· float time scale

Time per auxilliary sample over time per normal FADC sample (typ.: 0.25)

size\_t num\_traces

The number of traces coming from the camera.

size\_t len\_traces

The length of each trace in FADC samples.

float \* trace\_data

Allocated on first use with num\_traces\*len\_traces elements.

The documentation for this struct was generated from the following file:

io\_hess.h

## 6.23 hess\_aux\_digital\_trace Struct Reference

#### **Data Fields**

· int known

Must be set to 1 if and only if corresponding data is available.

· int tel id

Must match the expected telescope ID when reading.

· int trace\_type

Indicate what type of trace we have (1: DigitalSum trigger trace)

float time\_scale

Time per auxilliary sample over time per normal FADC sample (typ.: 1.0)

size\_t num\_traces

The number of traces coming from the camera.

· size\_t len\_traces

The length of each trace in FADC samples.

• uint16\_t \* trace\_data

Allocated on first use with num\_traces\*len\_traces elements.

The documentation for this struct was generated from the following file:

· io\_hess.h

## 6.24 hess\_camera\_organisation\_struct Struct Reference

Logical organisation of camera electronics channels.

```
#include <io_hess.h>
```

#### **Data Fields**

• int tel id

Telescope ID.

• int num\_pixels

Number of pixels in camera.

· int num\_drawers

Number of drawers (mechanical units) in camera.

• int num\_gains

Number of gains per PM.

· int num\_sectors

Number of sectors (trigger groups).

• int drawer [H\_MAX\_PIX]

Drawer assignment for each pixel.

- int card [H\_MAX\_PIX][H\_MAX\_GAINS]
- int chip [H\_MAX\_PIX][H\_MAX\_GAINS]
- int channel [H\_MAX\_PIX][H\_MAX\_GAINS]
- int nsect [H MAX PIX]

Number of sectors (trigger groups) for trigger(s).

• int sectors [H\_MAX\_PIX][H\_MAX\_PIXSECTORS]

Pixels in sectors (trigger groups).

int sector\_type [H\_MAX\_SECTORS]

0: majority, 1: analog sum, 2: digital sum

double sector\_threshold [H\_MAX\_SECTORS]

Multiplicity or sum threshold applied to sector. [mV ?].

double sector\_pixthresh [H\_MAX\_SECTORS]

Pixel threshold for majority or clipping limit for sum triggers. [mV ?].

#### 6.24.1 Detailed Description

Logical organisation of camera electronics channels.

The documentation for this struct was generated from the following file:

· io hess.h

## 6.25 hess\_camera\_settings\_struct Struct Reference

Definition of camera optics settings.

```
#include <io_hess.h>
```

#### **Data Fields**

· int tel id

Telescope ID.

int num\_pixels

Number of pixels in camera.

• double xpix [H\_MAX\_PIX]

Pixel x position in camera [m].

double ypix [H\_MAX\_PIX]

Pixel y position in camera [m].

double zpix [H\_MAX\_PIX]

Pixel z position w.r.t. focal plane in camera center [m]. {new}.

• double <a href="mailto:nxpix">nxpix</a> [H\_MAX\_PIX]

Pixel pointing direction (nx,ny,1) x component. {new}.

double nypix [H\_MAX\_PIX]

Pixel pointing direction (nx,ny,1) y component. {new}.

• double area [H\_MAX\_PIX]

Pixel active area ([ $m^{\wedge}2$ ]).

• double size [H\_MAX\_PIX]

Pixel diameter (flat-to-flat, [m]).

int pixel\_shape [H\_MAX\_PIX]

Pixel shape type (0: circ., 1,3: hex, 2: square, -1: unknown). {new}.

double cam\_rot

Rotation angle of camera (counter-clock-wise from back side for prime focus camera).

· double flen

Focal length of optics (geometric or nominal) [m].

• double eff\_flen

Suggested effective focal length for image scale (can be zero). [m].

• int num\_mirrors

Number of mirror tiles.

· double mirror\_area

Total area of individual mirrors corrected for inclination  $[m^2]$ .

• int curved\_surface

0 for flat surface, 1 for curved surface. {new}

int pixels\_parallel

0 if (some) pixels are inclined, 1 if all pixels are parallel {new}

• int common\_pixel\_shape

instead of individual pixel shape if al pixels are the same. {new}

#### 6.25.1 Detailed Description

Definition of camera optics settings.

#### 6.25.2 Field Documentation

```
6.25.2.1 mirror_area
```

```
double hess_camera_settings_struct::mirror_area
```

Total area of individual mirrors corrected for inclination  $[m^{\wedge}2]$ .

The documentation for this struct was generated from the following file:

• io\_hess.h

## 6.26 hess\_camera\_software\_setting\_struct Struct Reference

Software settings used in camera process.

```
#include <io_hess.h>
```

#### **Data Fields**

· int tel id

The telescope ID number (1 ... n)

- int dyn\_trig\_mode
- int dyn\_trig\_threshold
- int dyn\_HV\_mode
- int dyn\_HV\_threshold
- · int data\_red\_mode

The desired data reduction mode.

• int zero\_sup\_mode

The desired zero suppression mode.

• int zero\_sup\_num\_thr

The number of thresholds to be used by z.s.

• int zero\_sup\_thresholds [10]

Threshold values to be used by z.s.

- · int unbiased\_scale
- int dyn\_ped\_mode
- int dyn\_ped\_events
- int dyn\_ped\_period

[ms]

• int monitor\_cur\_period

[ms]

int report\_cur\_period

[ms]

int monitor\_HV\_period

[ms]

int report\_HV\_period

[ms]

#### 6.26.1 Detailed Description

Software settings used in camera process.

#### 6.26.2 Field Documentation

```
6.26.2.1 zero_sup_mode
```

```
\verb|int hess_camera_software_setting_struct::zero_sup_mode|\\
```

The desired zero suppression mode.

The mode actually used may depend on the data.

The documentation for this struct was generated from the following file:


• io\_hess.h

## 6.27 hess\_central\_event\_data\_struct Struct Reference

Central trigger event data.

```
#include <io_hess.h>
```

Collaboration diagram for hess\_central\_event\_data\_struct:



#### **Data Fields**

· int glob\_count

Global event count.

HTime cpu\_time

CPU time at central trigger station.

· HTime gps\_time

GPS time at central trigger station.

int teltrg\_pattern

Bit pattern of telescopes having sent a trigger signal to the central station.

int teldata\_pattern

Bit pattern of telescopes having sent event data that could be merged.

• int num\_teltrg

How many telescopes triggered.

int teltrg\_list [H\_MAX\_TEL]

List of IDs of triggered telescopes.

float teltrg\_time [H\_MAX\_TEL]

Relative time of trigger signal.

• int teltrg\_type\_mask [H\_MAX\_TEL]

Bit mask which type of trigger fired.

float teltrg\_time\_by\_type [H\_MAX\_TEL][H\_MAX\_TRG\_TYPES]

Time of trigger separate for each type.

• int num\_teldata

Number of telescopes expected to have data.

• int teldata\_list [H\_MAX\_TEL]

List of IDs of telescopes with data.

#### 6.27.1 Detailed Description

Central trigger event data.

#### 6.27.2 Field Documentation

#### 6.27.2.1 teldata\_pattern

```
int hess_central_event_data_struct::teldata_pattern
```

Bit pattern of telescopes having sent event data that could be merged.

(Historical; only useful for small no. of telescopes.)

#### 6.27.2.2 teltrg\_pattern

```
int hess_central_event_data_struct::teltrg_pattern
```

Bit pattern of telescopes having sent a trigger signal to the central station.

(Historical; only useful for small no. of telescopes.)

#### 6.27.2.3 teltrg\_time

```
\verb|float hess_central_event_data_struct::teltrg_time[H\_MAX\_TEL]|\\
```

Relative time of trigger signal.

after correction for nominal delay [ns].

The documentation for this struct was generated from the following file:


• io\_hess.h

## 6.28 hess\_event\_data\_struct Struct Reference

All data for one event.

#include <io\_hess.h>

Collaboration diagram for hess\_event\_data\_struct:



#### **Data Fields**

· int num tel

Number of telescopes in run.

· CentralEvent central

Central trigger data and data pattern.

TelEvent teldata [H\_MAX\_TEL]

Raw and/or image data.

TrackEvent trackdata [H\_MAX\_TEL]

Interpolated tracking data.

· ShowerParameters shower

Reconstructed shower parameters.

· int num\_teldata

Number of telescopes for which we actually have data.

• int teldata\_list [H\_MAX\_TEL]

List of IDs of telescopes with data.

#### 6.28.1 Detailed Description

All data for one event.

The documentation for this struct was generated from the following file:

io\_hess.h

# 6.29 hess\_laser\_calib\_data\_struct Struct Reference

Laser calibration data.

```
#include <io_hess.h>
```

#### **Data Fields**

· int known

Are the calibration values known?

· int tel id

Telescope ID.

• int num\_pixels

Number of pixels.

• int num\_gains

Number of gains.

· int lascal id

Laser calibration ID.

double calib [H\_MAX\_GAINS][H\_MAX\_PIX]

ADC to laser/LED p.e.

double max\_int\_frac [H\_MAX\_GAINS]

Maximum fraction of the signal which can be in the fixed integration window.

double max\_pixtm\_frac [H\_MAX\_GAINS]

Maximum fraction of the signal which can be in the pixel timing integration.

double tm\_calib [H\_MAX\_GAINS][H\_MAX\_PIX]

## 6.29.1 Detailed Description

Laser calibration data.

### 6.29.2 Field Documentation

```
6.29.2.1 calib
```

```
double hess_laser_calib_data_struct::calib[H_MAX_GAINS][H_MAX_PIX]
```

ADC to laser/LED p.e.

conversion, in [mean p.e.], details depending on calibration procedure.

```
6.29.2.2 max_int_frac
```

```
double hess_laser_calib_data_struct::max_int_frac[H_MAX_GAINS]
```

Maximum fraction of the signal which can be in the fixed integration window.

#### 6.29.2.3 max\_pixtm\_frac

```
double hess_laser_calib_data_struct::max_pixtm_frac[H_MAX_GAINS]
```

Maximum fraction of the signal which can be in the pixel timing integration.

The documentation for this struct was generated from the following file:


• io\_hess.h

# 6.30 hess mc event struct Struct Reference

Monte Carlo event-specific data.

#include <io\_hess.h>

Collaboration diagram for hess\_mc\_event\_struct:



## **Data Fields**

· int event

Event number -> global counter.

· int shower num

Shower number as in shower structure.

· double xcore

Core position w.r.t. array reference point [m],.

double ycore

$$x \rightarrow N, y \rightarrow W.$$

· double aweight

Area weight (units: [m\*\*2]) in case of non-uniform sampling, normally counted in the shower plane and normalized such that the sum over all events for a shower should, on average, be the area over which core offsets are thrown (see also num\_use and core\_range in MCRunHeader).

• double photons [H MAX TEL]

The CORSIKA photon sum into fiducial volume.

• struct hess\_mc\_pe\_sum\_struct mc\_pesum

Numbers of / sums of photo-electrons.

• struct hess\_mc\_photons mc\_photons [H\_MAX\_TEL]

Raw simulated photons.

• struct hess\_mc\_pe\_list mc\_pe\_list [H\_MAX\_TEL]

List of detected photo-electrons.

### 6.30.1 Detailed Description

Monte Carlo event-specific data.

#### 6.30.2 Field Documentation

### 6.30.2.1 aweight

```
double hess_mc_event_struct::aweight
```

Area weight (units: [m\*\*2]) in case of non-uniform sampling, normally counted in the shower plane and normalized such that the sum over all events for a shower should, on average, be the area over which core offsets are thrown (see also num use and core range in MCRunHeader).

It may be zero for uniform sampling.

The documentation for this struct was generated from the following file:

· io hess.h

# 6.31 hess\_mc\_pe\_list Struct Reference

Photo-electrons from Monte Carlo individually.

```
#include <io_hess.h>
```

## **Data Fields**

int npe

The number of all photo-electrons in the telescope.

· int pixels

The number of pixels in the camera.

int flags

Bit 0: with amplitudes, bit 1: includes NSB.

int pe\_count [H\_MAX\_PIX]

The numbers of p.e. at each pixel.

int itstart [H\_MAX\_PIX]

The start index for each pixel in the sequential atimes vector.

double \* atimes

The list of start times of all photo-eletrons.

• double \* amplitudes

Optional list of matching amplitudes [mean p.e.].

int max\_npe

How many p.e. we can store in the atimes (+amplitudes) vector(s).

# 6.31.1 Detailed Description

Photo-electrons from Monte Carlo individually.

The documentation for this struct was generated from the following file:

• io\_hess.h

# 6.32 hess\_mc\_pe\_sum\_struct Struct Reference

Sums of photo-electrons in MC (total and per pixel).

```
#include <io_hess.h>
```

#### **Data Fields**

· int event

Event number -> global counter.

• int shower\_num

Shower number as in shower structure.

• int num\_tel

Number of telescopes simulated.

int num\_pe [H\_MAX\_TEL]

Number of photo-electrons per telescope.

• int num\_pixels [H\_MAX\_TEL]

Pixels per telescope or 0.

int pix\_pe [H\_MAX\_TEL][H\_MAX\_PIX]

Photo-electrons per pixel (without NSB).

• double photons [H\_MAX\_TEL]

The sum of the photon content of all bunches.

double photons\_atm [H\_MAX\_TEL]

Photons surviving atmospheric transmission.

double photons\_atm\_3\_6 [H\_MAX\_TEL]

Photons surv. atm. tr. in the 300 to 600 nm range.

double photons\_atm\_400 [H\_MAX\_TEL]

Photons surv. atm. tr. in the 350 to 450 nm range.

double photons\_atm\_qe [H\_MAX\_TEL]

Photons surviving atmospheric transmission, mirror reflectivity (except funnel), and Q.E.

### 6.32.1 Detailed Description

Sums of photo-electrons in MC (total and per pixel).

# 6.32.2 Field Documentation

#### 6.32.2.1 photons\_atm\_qe

```
double hess_mc_pe_sum_struct::photons_atm_qe[H_MAX_TEL]
```

Photons surviving atmospheric transmission, mirror reflectivity (except funnel), and Q.E.

The documentation for this struct was generated from the following file:


· io\_hess.h

# 6.33 hess\_mc\_photons Struct Reference

Photons from Monte Carlo.

```
#include <io_hess.h>
```

Collaboration diagram for hess\_mc\_photons:



### **Data Fields**

struct bunch \* bunches

Bunches of photons.

· int nbunches

How many photon bunches we have at this telescope.

• int max\_bunches

How many we can store in 'bunches' vector above.

· double photons

The sum of the photon content of all bunches.

### 6.33.1 Detailed Description

Photons from Monte Carlo.

The documentation for this struct was generated from the following file:

io\_hess.h

# 6.34 hess\_mc\_run\_header\_struct Struct Reference

```
MC run header.
```

```
#include <io_hess.h>
```

### **Data Fields**

· int shower\_prog\_id

Recorded data:

int shower\_prog\_vers

version \* 1000

· time\_t shower\_prog\_start

Time when shower simulation of run started (CORSIKA: only date)

int detector\_prog\_id

sim\_telarray=1, ...

int detector\_prog\_vers

version \* 1000

time\_t detector\_prog\_start

Time when detector simulation of run started.

· double obsheight

Height of simulated observation level.

· int num showers

Number of showers (intended to be) simulated.

· int num\_use

Number of uses of each shower.

· int core\_pos\_mode

Core position fixed/circular/rectangular/...

• double core\_range [2]

rmin+rmax or dx+dy [m].

• double az\_range [2]

Range of shower azimuth [rad, N->E].

• double alt\_range [2]

Range of shower altitude [rad].

· int diffuse

Diffuse mode off/on.

• double viewcone [2]

Min.+max. opening angle for diffuse mode [degrees] (was always in degrees despite earlier '[rad]' comment).

double E\_range [2]

Energy range [TeV] of simulated showers.

• double spectral\_index

Power-law spectral index of spectrum (<0).

• double B\_total

Total geomagnetic field assumed [microT].

double B inclination

Inclination of geomagnetic field [rad].

double B declination

Declination of geomagnetic field [rad].

double injection\_height

Height of particle injection [m].

• double fixed\_int\_depth

Fixed depth of first interaction or 0 [g/cm<sup>2</sup>].

· int atmosphere

Atmospheric model number.

- int corsika\_iact\_options
- int corsika\_low\_E\_model
- · int corsika\_high\_E\_model
- · double corsika bunchsize
- double corsika\_wlen\_min
- double corsika\_wlen\_max
- int corsika\_low\_E\_detail
- int corsika\_high\_E\_detail

# 6.34.1 Detailed Description

MC run header.

#### 6.34.2 Field Documentation

#### 6.34.2.1 shower\_prog\_id

```
int hess_mc_run_header_struct::shower_prog_id
```

Recorded data:

CORSIKA=1, ALTAI=2, KASCADE=3, MOCCA=4.

The documentation for this struct was generated from the following file:

• io\_hess.h

# 6.35 hess\_mc\_shower\_profile\_struct Struct Reference

Monte Carlo shower profile (sort of histogram).

```
#include <io_hess.h>
```

# **Data Fields**

int id

Type of profile (also determines units below).

• int num\_steps

Number of histogram steps.

· int max\_steps

Number of allowed steps as allocated for content.

· double start

Start of ordinate ([m] or [g/cm<sup>2</sup>])

· double end

End of it.

• double binsize

(End-Start)/num\_steps; not saved

double \* content

Histogram contents (allocated on demand).

### 6.35.1 Detailed Description

Monte Carlo shower profile (sort of histogram).

#### 6.35.2 Field Documentation

#### 6.35.2.1 id

```
int hess_mc_shower_profile_struct::id
```

Type of profile (also determines units below).

Temptative definitions:

- 1000\*k + 1: Profile of all charged particles.
- 1000\*k + 2: Profile of electrons+positrons.
- 1000\*k + 3: Profile of muons.
- 1000\*k + 4: Profile of hadrons.
- 1000\*k + 10: Profile of Cherenkov photon emission [1/m].

The value of k specifies the binning:

- k = 0: The profile is in terms of atmospheric depth along the shower axis.
- k = 1: in terms of vertical atmospheric depth.
- k = 2: in terms of altitude [m] above sea level.

The documentation for this struct was generated from the following file:


io\_hess.h

# 6.36 hess\_mc\_shower\_struct Struct Reference

Shower specific data.

#include <io\_hess.h>

Collaboration diagram for hess\_mc\_shower\_struct:



#### **Data Fields**

- int shower\_num
- · int primary\_id

Particle ID of primary.

• double energy

primary energy [TeV]

· double azimuth

Azimuth (N->E) [rad].

· double altitude

Altitude [rad].

double depth\_start

Atmospheric depth where particle started [g/cm<sup>2</sup>].

· double h\_first\_int

height of first interaction a.s.l. [m]

double xmax

Atmospheric depth of shower maximum [g/cm<sup>2</sup>], derived from all charged particles.

· double hmax

Height of shower maximum [m] in xmax.

· double emax

Atm. depth of maximum in electron number.

double cmax

Atm. depth of max. in Cherenkov photon emission.

· int num\_profiles

Number of profiles filled.

- ShowerProfile profile [H\_MAX\_PROFILE]
- struct shower\_extra\_parameters extra\_parameters

# 6.36.1 Detailed Description

Shower specific data.

# 6.36.2 Field Documentation

#### 6.36.2.1 primary\_id

```
int hess_mc_shower_struct::primary_id
```

# Particle ID of primary.

Was in CORSIKA convention where detector\_prog\_vers in MC run header was 0, and is now 0 (gamma), 1(e-), 2(mu-), 100\*A+Z for nucleons and nuclei, negative for antimatter.

### 6.36.2.2 xmax

```
double hess_mc_shower_struct::xmax
```

Atmospheric depth of shower maximum [g/cm<sup>2</sup>], derived from all charged particles.

The documentation for this struct was generated from the following file:

· io\_hess.h

# 6.37 hess\_pixel\_calibrated\_struct Struct Reference

#### **Data Fields**

· int known

is calibrated pixel data known?

int tel\_id

Telescope ID.

int num\_pixels

Pixels in camera: list should be in this range.

· int int method

-2 (timing local peak), -1 (timing global peak), >=0 (integration scheme, if known)

int list\_known

Was list of significant pixels filled in? 1: use list, 2: all pixels significant.

int list\_size

Size of the list of available pixels (with list mode).

int pixel\_list [H\_MAX\_PIX]

List of available pixels (with list mode).

uint8\_t significant [H\_MAX\_PIX]

Was amplitude large enough to record it?

float pixel\_pe [H\_MAX\_PIX]

Calibrated & flat-fielded pixel intensity [p.e.].

The documentation for this struct was generated from the following file:

io\_hess.h

# 6.38 hess\_pixel\_disabled\_struct Struct Reference

Pixels disabled in HV and/or trigger.

```
#include <io_hess.h>
```

#### **Data Fields**

· int tel id

The telescope ID number (1 ... n)

- int num\_trig\_disabled
- int trigger\_disabled [H\_MAX\_PIX]
- · int num HV\_disabled
- int HV\_disabled [H\_MAX\_PIX]

### 6.38.1 Detailed Description

Pixels disabled in HV and/or trigger.

The documentation for this struct was generated from the following file:

· io hess.h

# 6.39 hess\_pixel\_list Struct Reference

Lists of pixels (triggered, selected, etc.)

```
#include <io_hess.h>
```

# **Data Fields**

• int code

Indicates what sort of list this is: 0 (triggered pixel), 1 (selected pixel), ...

• int pixels

The size of the pixels in this list.

int pixel\_list [H\_MAX\_PIX]

The actual list of pixel numbers.

# 6.39.1 Detailed Description

Lists of pixels (triggered, selected, etc.)

### 6.39.2 Field Documentation

#### 6.39.2.1 code

```
int hess_pixel_list::code
```

Indicates what sort of list this is: 0 (triggered pixel), 1 (selected pixel), ...

The documentation for this struct was generated from the following file:

· io\_hess.h

# 6.40 hess\_pixel\_setting\_struct Struct Reference

Settings of pixel HV and thresholds.

```
#include <io_hess.h>
```

#### **Data Fields**

· int tel id

The telescope ID number (1 ... n)

- · int setup\_id
- int trigger\_mode
- int min\_pixel\_mult

The minimum number of pixels in a camera.

· int num pixels

Local copy of the number of pixels.

int pixel\_HV\_DAC [H\_MAX\_PIX]

High voltage DAC values set.

· int num\_drawers

Local copy of the number of drawers in the camera.

int threshold\_DAC [H\_MAX\_DRAWERS]

Threshold DAC values set.

- int ADC\_start [H\_MAX\_DRAWERS]
- int **ADC\_count** [H\_MAX\_DRAWERS]
- · double time slice

Width of readout time slice (i.e. one sample) [ns].

· int sum\_bins

Standard integration over so many time slices.

· int nrefshape

Number of following reference pulse shapes (num\_gains or 0)

· int Irefshape

Length of following reference pulse shape(s).

double refshape [H\_MAX\_GAINS][H\_MAX\_FSHAPE]

Reference pulse shape(s).

double ref\_step

Time step between refshape entries [ns].

### 6.40.1 Detailed Description

Settings of pixel HV and thresholds.

The documentation for this struct was generated from the following file:

· io\_hess.h

# 6.41 hess\_pixel\_timing\_struct Struct Reference

#### **Data Fields**

· int known

is pixel timing data known?

· int tel id

Telescope ID.

int num\_pixels

Pixels in camera: list should be in this range.

· int num gains

Number of different gains per pixel.

· int list type

0: not set; 1: individual pixels; 2: pixel ranges.

int list\_size

The size of the pixels in this list.

• int pixel list [2 \*H MAX PIX]

The actual list of pixel numbers.

· int threshold

Minimum base-to-peak raw amplitude difference applied in pixel selection.

int before\_peak

Number of bins before peak being summed up.

· int after\_peak

Number of bins after peak being summed up.

• int num\_types

How many different types of times can we store?

int time\_type [H\_MAX\_PIX\_TIMES]

Which types come in which order.

float time\_level [H\_MAX\_PIX\_TIMES]

The width and startpos types apply.

float granularity

Actually stored are the following timvals divided by granularity, as 16-bit integers.

· float peak\_global

Camera-wide (mean) peak position [time slices].

float timval [H\_MAX\_PIX][H\_MAX\_PIX\_TIMES]

Only the first 'pixels'.

• int pulse\_sum\_loc [H\_MAX\_GAINS][H\_MAX\_PIX]

Amplitude sum around.

int pulse\_sum\_glob [H\_MAX\_GAINS][H\_MAX\_PIX]

Amplitude sum around.

#### 6.41.1 Field Documentation

#### 6.41.1.1 granularity

```
float hess_pixel_timing_struct::granularity
```

Actually stored are the following timvals divided by granularity, as 16-bit integers.

Set this to e.g. 0.25 for a 0.25 time slice stepping.

### 6.41.1.2 pulse\_sum\_glob

```
int hess_pixel_timing_struct::pulse_sum_glob[H_MAX_GAINS][H_MAX_PIX]
```

Amplitude sum around.

global peak; for all pixels. Ped. subtracted. Only present if before&after\_peak>=0 and if list is of size>0 (otherwise no peak).

#### 6.41.1.3 pulse sum loc

```
int hess_pixel_timing_struct::pulse_sum_loc[H_MAX_GAINS][H_MAX_PIX]
```

Amplitude sum around.

local peak, for pixels in list. Ped. subtr. Only present if before&after\_peak>=0.

## 6.41.1.4 threshold

```
int hess_pixel_timing_struct::threshold
```

Minimum base-to-peak raw amplitude difference applied in pixel selection.

Referenced by nb\_fc\_shaped\_peak\_integration().

### 6.41.1.5 time\_level

```
float hess_pixel_timing_struct::time_level[H_MAX_PIX_TIMES]
```

The width and startpos types apply.

above some fraction from base to peak.

 $Referenced\ by\ nb\_fc\_shaped\_peak\_integration(),\ and\ pixel\_timing\_analysis().$ 

# 6.41.1.6 timval

```
float hess_pixel_timing_struct::timval[H_MAX_PIX][H_MAX_PIX_TIMES]
```

Only the first 'pixels'.

elements are actually filled and stored. Others are undefined.

Referenced by pixel\_timing\_analysis().

The documentation for this struct was generated from the following file:

· io hess.h

# 6.42 hess\_pointing\_correction\_struct Struct Reference

Pointing correction parameters.

```
#include <io_hess.h>
```

### **Data Fields**

• int tel\_id

The telescope ID number (1  $\dots$  n)

- int function\_type
- int num\_param
- double pointing\_param [20]

# 6.42.1 Detailed Description

Pointing correction parameters.

The documentation for this struct was generated from the following file:

• io\_hess.h

# 6.43 hess\_run\_end\_mc\_statistics\_struct Struct Reference

MC end-of-run statistics.

```
#include <io_hess.h>
```

# **Data Fields**

· int run\_num

Run number.

· int num showers

Number of simulated showers found.

· int num\_events

Number of MC events found.

# 6.43.1 Detailed Description

MC end-of-run statistics.

The documentation for this struct was generated from the following file:

· io\_hess.h

# 6.44 hess\_run\_end\_statistics\_struct Struct Reference

End-of-run statistics.

```
#include <io_hess.h>
```

# **Data Fields**

• int run\_num

Run number.

· int num tel

Number of telescopes used.

int tel\_ids [H\_MAX\_TEL]

IDs of all telescopes.

· int num\_central\_trig

Number of system triggers.

• int num\_local\_trig [H\_MAX\_TEL]

Number of local telescope triggers.

int num\_local\_sys\_trig [H\_MAX\_TEL]

Number of valid telescope triggers.

• int num\_events [H\_MAX\_TEL]

Number of events read out.

# 6.44.1 Detailed Description

End-of-run statistics.

The documentation for this struct was generated from the following file:

• io\_hess.h

# 6.45 hess\_run\_header\_struct Struct Reference

Run header common to measured and simulated data.

```
#include <io_hess.h>
```

#### **Data Fields**

• int run

Recorded data:

· time t time

Time of run start [UTC sec since 1970.0].

• int run\_type

Data/pedestal/laser/muon run or MC run: MC run: -1, Data run: 1, Pedestal run: 2, Laser run: 3, Muon run: 4.

· int tracking\_mode

Tracking/pointing mode: 0: Az/Alt, 1: R.A.

· int reverse\_flag

Normal or reverse tracking: 0: Normal, 1: reverse.

• double direction [2]

Tracking/pointing direction in [radians]: [0]=Azimuth, [1]=Altitude in mode 0, [0]=R.A., [1]=Declination in mode 1.

• double offset\_fov [2]

Offset of pointing dir.

double conv\_depth

Atmospheric depth of convergence point.

double conv\_ref\_pos [2]

Reference position for convergent pointing.

· int ntel

Number of telescopes involved.

int tel\_id [H\_MAX\_TEL]

ID numbers of telescopes used in this run.

double tel\_pos [H\_MAX\_TEL][3]

x,y,z positions of the telescopes [m].

· int min\_tel\_trig

Minimum number of tel. in system trigger.

· int duration

Nominal duration of run [s].

char \* target

Primary target object name.

· char \* observer

Observer(s) starting or supervising run.

int max\_len\_target

For internal data handling only:

• int max\_len\_observer

## 6.45.1 Detailed Description

Run header common to measured and simulated data.

### 6.45.2 Field Documentation

### 6.45.2.1 conv\_depth

```
double hess_run_header_struct::conv_depth
```

Atmospheric depth of convergence point.

#### 6.45.2.2 conv\_ref\_pos

```
double hess_run_header_struct::conv_ref_pos[2]
```

Reference position for convergent pointing.

X,y in [m] at the telescope reference height.

#### 6.45.2.3 direction

```
double hess_run_header_struct::direction[2]
```

Tracking/pointing direction in [radians]: [0]=Azimuth, [1]=Altitude in mode 0, [0]=R.A., [1]=Declination in mode 1.

Referenced by mc\_event\_fill().

#### 6.45.2.4 offset\_fov

```
double hess_run_header_struct::offset_fov[2]
```

Offset of pointing dir.

in camera f.o.v. divided by focal length, i.e. converted to [radians]: [0]=Camera x (downwards in normal pointing, i.e. increasing Alt, [1]=Camera y -> Az).

# 6.45.2.5 reverse\_flag

```
int hess_run_header_struct::reverse_flag
```

Normal or reverse tracking: 0: Normal, 1: reverse.

6.45.2.6 run

int hess\_run\_header\_struct::run

Recorded data:

Run number.

Referenced by hesscam\_ps\_plot().

6.45.2.7 run\_type

int hess\_run\_header\_struct::run\_type

Data/pedestal/laser/muon run or MC run: MC run: -1, Data run: 1, Pedestal run: 2, Laser run: 3, Muon run: 4.

6.45.2.8 tel\_pos

double hess\_run\_header\_struct::tel\_pos[H\_MAX\_TEL][3]

x,y,z positions of the telescopes [m].

x is counted from array reference position towards North, y towards West, z upwards.

6.45.2.9 tracking\_mode

 $\verb|int hess_run_header_struct::tracking_mode|\\$ 

Tracking/pointing mode: 0: Az/Alt, 1: R.A.

/Dec. 2000

The documentation for this struct was generated from the following file:

• io\_hess.h

# 6.46 hess\_shower\_parameter Struct Reference

Reconstructed shower parameters.

#include <io\_hess.h>

#### **Data Fields**

- · int known
- · int num\_trg

Number of telescopes contributing to central trigger.

· int num read

Number of telescopes read out.

· int num\_img

Number of images used for shower parameters.

· int img\_pattern

Bit pattern of which telescopes were used (for small no. of telescopes only).

int img\_list [H\_MAX\_TEL]

With more than 16 or 32 telescopes, we can only use the list.

· int result bits

Bit pattern of what results are available: Bits 0 + 1: direction + errors Bits 2 + 3: core position + errors Bits 4 + 5: mean scaled image shape + errors Bits 6 + 7: energy + error Bits 8 + 9: shower maximum + error.

double Az

Azimuth angle [radians from N-> E].

· double Alt

Altitude [radians].

· double err\_dir1

Error estimate in nominal plane X direction (|| Alt) [rad].

double err\_dir2

Error estimate in nominal plane Y direction (|| Az) [rad].

double err\_dir3

?

• double xc

X core position [m].

• double yc

Y core position [m].

• double err\_core1

Error estimate in X coordinate [m].

double err\_core2

Error estimate in Y coordinate [m].

• double err\_core3

?

• double mscl

Mean scaled image length [gammas  $\sim$ 1 (HEGRA-style) or  $\sim$ 0 (HESS-style)].

- double err\_mscl
- double mscw

Mean scaled image width [gammas  $\sim$ 1 (HEGRA-style) or  $\sim$ 0 (HESS-style)].

- · double err\_mscw
- · double energy

Primary energy [TeV], assuming a gamma.

- double err\_energy
- double xmax

Atmospheric depth of shower maximum [g/cm<sup>2</sup>].

· double err\_xmax

### 6.46.1 Detailed Description

Reconstructed shower parameters.

The documentation for this struct was generated from the following file:

· io hess.h

# 6.47 hess\_tel\_event\_adc\_struct Struct Reference

ADC data (either sampled or sum mode)

```
#include <io_hess.h>
```

#### **Data Fields**

· int known

Must be set to 1 if and only if raw data is available.

· int tel\_id

Must match the expected telescope ID when reading.

int num\_pixels

The number of pixels in the camera (as in configuration)

• int num\_gains

The number of different gains per pixel (2 for HESS).

· int num\_samples

The number of samples (time slices) recorded.

· int zero\_sup\_mode

The desired or used zero suppression mode.

int data\_red\_mode

The desired or used data reduction mode.

int offset\_hg8

The offset to be used in shrinking high-gain data.

int scale\_hg8

The scale factor (denominator) in shrinking h-g data.

· int threshold

Threshold (in high gain) for recording low-gain data.

· int list known

Was list of significant pixels filled in?

int list\_size

Size of the list of available pixels (with list mode).

int adc\_list [H\_MAX\_PIX]

List of available pixels (with list mode).

uint8\_t significant [H\_MAX\_PIX]

Was amplitude large enough to record it? Bit 0: sum, 1: samples.

uint8\_t adc\_known [H\_MAX\_GAINS][H\_MAX\_PIX]

Was individual channel recorded? Bit 0: sum, 1: samples, 2: ADC was in saturation.

uint32\_t adc\_sum [H\_MAX\_GAINS][H\_MAX\_PIX]

Sum of ADC values.

uint16\_t adc\_sample [H\_MAX\_GAINS][H\_MAX\_PIX][H\_MAX\_SLICES]

Pulses sampled.

# 6.47.1 Detailed Description

ADC data (either sampled or sum mode)

The documentation for this struct was generated from the following file:


• io\_hess.h

# 6.48 hess\_tel\_event\_data\_struct Struct Reference

Event raw and image data from one telescope.

#include <io\_hess.h>

Collaboration diagram for hess\_tel\_event\_data\_struct:



# **Data Fields**

- int known
- int tel id

The telescope ID number (1 ... n)

int loc\_count

The counter for local triggers.

int glob\_count

The counter for system triggers.

· HTime cpu time

Camera CPU system time of event.

HTime gps\_time

GPS time of event, if any.

• int trg\_source

1=internal (event data) or 2=external (calib data).

int num\_list\_trgsect

Number of trigger groups (sectors) listed.

int list\_trgsect [H\_MAX\_SECTORS]

List of triggered groups (sectors).

· int known\_time\_trgsect

Are the trigger times known? (0/1)

double time\_trgsect [H\_MAX\_SECTORS]

Times when trigger groups (as in list) fired.

int readout\_mode

Sum mode (0) or sample mode only (1) or both (>=2)

int num\_image\_sets

how many 'img' sets are available.

· int max\_image\_sets

how many 'img' sets were allocated.

AdcData \* raw

Pointer to raw data, if any.

PixelTiming \* pixtm

Optional pixel (pulse shape) timing.

ImgData \* img

Pointer to second moments, if any.

• PixelCalibrated \* pixcal

Pointer to calibrated pixel intensities, if available.

int num\_phys\_addr

(not used)

int phys\_addr [4 \*H\_MAX\_DRAWERS]

(not used)

· PixelList trigger\_pixels

List of triggered pixels.

· PixelList image\_pixels

Pixels included in (first) image.

AuxTraceD aux\_trace\_d [MAX\_AUX\_TRACE\_D]

Optional auxilliary digital traces.

AuxTraceA aux\_trace\_a [MAX\_AUX\_TRACE\_A]

Optional auxilliary analog traces.

### 6.48.1 Detailed Description

Event raw and image data from one telescope.

The documentation for this struct was generated from the following file:

• io\_hess.h

# 6.49 hess\_tel\_image\_struct Struct Reference

```
#include <io_hess.h>
```

```
Data Fields
```

int known

Image parameters.

is image data known?

· int tel id

Telescope ID.

· int pixels

number of pixels used for image

· int cut id

For which set of tail-cuts was used.

· double amplitude

Image amplitude (="SIZE") [mean p.e.].

· double clip\_amp

Pixel amplitude clipping level [mean p.e.] or zero for no clipping.

· int num\_sat

Number of pixels in saturation (ADC saturation or dedicated clipping).

double x

Position.

• double x\_err

Error on x (0: error not known, <0: x not known) [rad].

double y

Y position (c.o.g.) [rad], corrected for any camera rotation.

double y\_err

Error on y (0: error not known, <0: y not known) [rad].

double phi

Orientation.

· double phi\_err

Error on phi (0: error not known, <0: phi not known) [rad].

double I

Shape.

· double I err

Error on length (0: error not known, <0: I not known) [rad].

• double w

Width (minor axis) [rad].

· double w err

Error on width (0: error not known, <0: w not known) [rad].

· double skewness

Skewness, indicating asymmetry of image.

· double skewness\_err

Error (0: error not known, <0: skewness not known)

· double kurtosis

Kurtosis, indicating sharpness of peak of image.

· double kurtosis err

Error (0: error not known, <0: kurtosis not known)

· int num\_conc

Number of hottest pixels used for concentration.

· double concentration

Fraction of total amplitude in num\_conc hottest pixels.

• double tm\_slope

Timing.

· double tm\_residual

R.m.s. average residual time after slope correction. [ns].

· double tm\_width1

Average pulse width (50% of peak or time over threshold) [ns].

double tm\_width2

Average pulse width (20% of peak or 0) [ns].

• double tm\_rise

Average pixel rise time (or 0) [ns].

• int num\_hot

Individual pixels.

int hot\_pixel [H\_MAX\_HOTPIX]

Pixel IDs of hotest pixels.

double hot\_amp [H\_MAX\_HOTPIX]

Amplitudes of hotest pixels [mean p.e.].

## 6.49.1 Detailed Description

Image parameters.

#### 6.49.2 Field Documentation

```
6.49.2.1 I
```

double hess\_tel\_image\_struct::1

Shape.

Length (major axis) [rad]

6.49.2.2 num\_hot

int hess\_tel\_image\_struct::num\_hot

Individual pixels.

Number of hottest pixels individually saved

```
6.49.2.3 phi
double hess_tel_image_struct::phi
Orientation.
Angle of major axis w.r.t. x axis [rad], corrected for any camera rotation.
Referenced by pixel_timing_analysis().
6.49.2.4 tm_slope
double hess_tel_image_struct::tm_slope
Timing.
Slope in peak times along major axis as given by phi. [ns/rad]
Referenced by pixel_timing_analysis().
6.49.2.5 x
double hess_tel_image_struct::x
Position.
X position (c.o.g.) [rad], corrected for any camera rotation.
Referenced by pixel_timing_analysis().
```

• io\_hess.h


The documentation for this struct was generated from the following file:

# 6.50 hess\_tel\_monitor\_struct Struct Reference

Monitoring data.

```
#include <io_hess.h>
```

Collaboration diagram for hess\_tel\_monitor\_struct:



## **Data Fields**

· int known

Status etc., pedestals, DC, HV.

int new\_parts

What of that is new.

• int tel\_id

Telescope ID number.

· int num\_sectors

Number of sector available for trigger (default trigger).

• int num\_pixels

Number of pixels in camera.

· int num drawers

Number of drawers in camera.

- int num\_gains
- int num\_ped\_slices

How many slices have been added for pedestal.

int num\_drawer\_temp

Number of temperatures per drawer.

· int num\_camera\_temp

Number of other temperatures monitored.

· int monitor id

Incremented with each update.

· HTime moni\_time

Time when last monitoring data was sent.

- · HTime status time
- · HTime trig time

Time when last trigger monitor data was read.

· HTime ped noise time

Time when pedestals + noise were determined.

HTime hv\_temp\_time

Time when hv+currents+temp. were all read out.

HTime dc\_rate\_time

Time when DC current + pixels scalers were read.

• HTime set\_hv\_thr\_time

Time when HV + thresholds where set.

• HTime set\_daq\_time

Time when DAQ parameters where set.

· int status bits

Lid, HV, trigger, readout, drawers, fans.

· long coinc\_count

These have to be obtained from the camera trigger electronics (first trigger type only)

· long event count

Count of events read out.

· double event\_rate

Average event rate [Hz].

· double data\_rate

Average rate of packed data [MB/s].

· double trigger\_rate

Camera average local trigger rate [Hz].

double sector\_rate [H\_MAX\_SECTORS]

Sector trigger rate [Hz].

· double mean significant

These are computed by the readout software:

double pedestal [H\_MAX\_GAINS][H\_MAX\_PIX]

Average pedestal on ADC sums.

double noise [H\_MAX\_GAINS][H\_MAX\_PIX]

Average noise on ADC sums.

uint16\_t current [H\_MAX\_PIX]

These numbers need mapping from drawers+channel to pixel id:

• uint16\_t scaler [H\_MAX\_PIX]

ADC values of pixel trigger rate.

uint16\_t hv\_v\_mon [H\_MAX\_PIX]

ADC values of HV voltage monitor.

• uint16\_t hv\_i\_mon [H\_MAX\_PIX]

ADC values of HV current monitor.

uint16\_t hv\_dac [H\_MAX\_PIX]

DAC values of HV settings.

uint16\_t thresh\_dac [H\_MAX\_DRAWERS]

Thresholds set in each drawer.

uint8\_t trig\_set [H\_MAX\_PIX]

Set if pixel excluded from trigger.

uint8\_t hv\_set [H\_MAX\_PIX]

Set if HV switched off for pixel.

uint8\_t hv\_stat [H\_MAX\_PIX]

Set if HV switched off for pixel.

short drawer\_temp [H\_MAX\_DRAWERS][H\_MAX\_D\_TEMP]

That is left in its raw order:

• short camera\_temp [H\_MAX\_C\_TEMP]

ADC values.

· uint16\_t daq\_conf

As set by CNTRLDaq message.

- uint16\_t daq\_scaler\_win
- uint16\_t daq\_nd
- uint16\_t daq\_acc
- uint16\_t daq\_nl

### 6.50.1 Detailed Description

Monitoring data.

#### 6.50.2 Field Documentation

```
6.50.2.1 coinc_count
```

```
long hess_tel_monitor_struct::coinc_count
```

These have to be obtained from the camera trigger electronics (first trigger type only)

Count of pixel coincidences (local triggers).

```
6.50.2.2 current
```

```
uint16_t hess_tel_monitor_struct::current[H_MAX_PIX]
```

These numbers need mapping from drawers+channel to pixel id:

ADC values of DC current.

### 6.50.2.3 drawer\_temp

```
short hess_tel_monitor_struct::drawer_temp[H_MAX_DRAWERS][H_MAX_D_TEMP]
```

That is left in its raw order:

ADC values.

The documentation for this struct was generated from the following file:

• io\_hess.h

# 6.51 hess\_time\_struct Struct Reference

Breakdown of time into seconds since 1970.0 and nanoseconds.

```
#include <io_hess.h>
```

### **Data Fields**

- · long seconds
- long nanoseconds

### 6.51.1 Detailed Description

Breakdown of time into seconds since 1970.0 and nanoseconds.

The documentation for this struct was generated from the following file:

· io hess.h

# 6.52 hess\_tracking\_event\_data\_struct Struct Reference

Tracking data interpolated for one event and one telescope.

```
#include <io_hess.h>
```

#### **Data Fields**

· int tel id

The telescope ID number (1 ... n)

· double azimuth\_raw

Raw azimuth angle [radians from N->E].

· double altitude\_raw

Raw altitude angle [radians].

· double azimuth\_cor

Azimuth corrected for pointing errors.

• double altitude\_cor

Azimuth corrected for pointing errors.

int raw\_known

Set if raw angles are known.

• int cor\_known

Set if corrected angles are known.

### 6.52.1 Detailed Description

Tracking data interpolated for one event and one telescope.

The documentation for this struct was generated from the following file:

· io hess.h

# 6.53 hess\_tracking\_setup\_struct Struct Reference

Definition of tracking parameters.

```
#include <io_hess.h>
```

### **Data Fields**

· int tel id

Telescope ID.

- int known
- · int drive\_type\_az

0 for now.

· int drive\_type\_alt

0 for now.

double zeropoint\_az

Offsets subtracted from the values reported.

double zeropoint\_alt

by hardware before calculating 'raw' angles [rad].

double sign\_az

This is -1 if hardware counts the other way than.

double sign\_alt

we do, and +1 otherwise.

double resolution\_az

Typical resolution expected [rad].

double resolution\_alt

Typical resolution expected [rad].

double range\_low\_az

Note: The values may be outside the [0...2\*pi[ range.

- double range\_low\_alt
- double range\_high\_az
- double range\_high\_alt
- double park\_pos\_az
- double park\_pos\_alt

## 6.53.1 Detailed Description

Definition of tracking parameters.

This is a copy of the configuration given to the tracking computers. Note: all angles are in radians. This block should not be needed for event analysis.

### 6.53.2 Field Documentation

```
6.53.2.1 range_low_az
```

```
double hess_tracking_setup_struct::range_low_az
```

Note: The values may be outside the [0...2\*pi[ range.

The documentation for this struct was generated from the following file:


• io\_hess.h

# 6.54 histogram Struct Reference

A complete 1-D or 2-D histogram with control and data elements.

```
#include <histogram.h>
```

Collaboration diagram for histogram:



# **Data Fields**

- char \* title
  - Histogram title (optional)
- long ident

Histogram ID number (optional)

- union Histogram\_Parameters specific
- union Histogram\_Parameters specific\_2d
- int nbins

Number of histogram bins.

int nbins\_2d

Same for 2nd coordinate of 2-D.

• unsigned long entries

No.

• unsigned long tentries

No

• unsigned long underflow

No.

• unsigned long underflow\_2d

Same in 2nd coord of 2-D histo.

· unsigned long overflow

No.

• unsigned long overflow\_2d

Same in 2nd coord of 2-D histo.

• unsigned long \* counts

Pointer to histogram data.

char type

'I' for integer histogram,

• struct histogram \* previous

References to neighbours in.

struct histogram \* next

linked list of histograms.

• struct Histogram\_Extension \* extension

Extension for weighted histos.

## 6.54.1 Detailed Description

A complete 1-D or 2-D histogram with control and data elements.

## 6.54.2 Field Documentation

## 6.54.2.1 entries

unsigned long histogram::entries

No.

of entries, incl. u.f./o.f.

Referenced by histogram\_to\_root(), and write\_dst\_histos().

```
6.54.2.2 next
struct histogram* histogram::next
linked list of histograms.
Referenced by convert_histograms_to_root(), and write_histograms().
6.54.2.3 overflow
unsigned long histogram::overflow
No.
of entries above range
Referenced by histogram_to_root().
6.54.2.4 overflow_2d
unsigned long histogram::overflow_2d
Same in 2nd coord of 2-D histo.
Referenced by histogram_to_root().
6.54.2.5 tentries
unsigned long histogram::tentries
No.
of entries, without """
Referenced by display_histogram(), fast_stat_histogram(), lookup_int(), lookup_real(), and print_histogram().
```

#### 6.54.2.6 type

char histogram::type

'I' for integer histogram,

'i' for int. lookup table, 'R' for floating point histogr. 'r' for fl. p. lookup table, 'F'/'D' for single/double pre-cision weighted histograms.

Referenced by aux\_alloc\_histogram(), display\_2d\_histogram(), display\_histogram(), fast\_stat\_histogram(), fill\_2d — \_int\_histogram(), fill\_2d\_weighted\_histogram(), fill\_histogram(), fill\_int\_histogram(), fill\_ereal\_histogram(), fill\_weighted\_histogram(), histogram\_matching(), histogram\_to\_root(), lookup\_int(), lookup\_real(), print\_histogram(), and set\_ebias\_correction().

#### 6.54.2.7 underflow

unsigned long histogram::underflow

No.

of entries below range

Referenced by histogram\_to\_root().

### 6.54.2.8 underflow\_2d

unsigned long histogram::underflow\_2d

Same in 2nd coord of 2-D histo.

Referenced by histogram to root().

The documentation for this struct was generated from the following file:

· histogram.h

# 6.55 Histogram\_Extension Struct Reference

A histogram extension only allocated for weighted histograms.

#include <histogram.h>

# **Data Fields**

· double content all

Sum of all contents.

· double content inside

Sum of contents within range.

• double content\_outside [8]

Contents outside range.

float \* fdata

Data of each bin (ix+nx\*iy)

double \* ddata

in one of two precisions.

# 6.55.1 Detailed Description

A histogram extension only allocated for weighted histograms.

### 6.55.2 Field Documentation

## 6.55.2.1 ddata

double\* Histogram\_Extension::ddata

in one of two precisions.

Referenced by aux\_alloc\_histogram(), display\_2d\_histogram(), fill\_gaps(), free\_histo\_contents(), gen\_image\_ lookups(), histogram\_to\_root(), and set\_ebias\_correction().

The documentation for this struct was generated from the following file:

· histogram.h

# 6.56 Histogram\_Parameters Union Reference

Parameters defining the usable range of coordinates.

#include <histogram.h>

### **Data Fields**

```
struct {
    double lower limit
      Lower limit of histogram range.
    double upper limit
      Upper limit of histogram range.
    double sum
      Sum of all values.
    double tsum
      Sum of values within range.
    double inverse_binwidth
      1.
 } real
     Histogram parameters if it is some sort of 'F' or 'D' type.
• struct {
    long lower_limit
      Lower limit of histogram range.
    long upper_limit
      Upper limit of histogram range.
    long sum
      Sum of all values.
    long tsum
      Sum of values within range.
    long width
      Width of histogram range.
 } integer
```

Histogram parameters if it is some sort of 'I' (int) type.

### 6.56.1 Detailed Description

Parameters defining the usable range of coordinates.

### 6.56.2 Field Documentation

```
6.56.2.1 integer

struct { ... } Histogram_Parameters::integer
```

Histogram parameters if it is some sort of 'I' (int) type.

Needed for integer-type limits.

Referenced by histogram\_matching(), histogram\_to\_root(), lookup\_int(), and print\_histogram().

1.

### 6.56.2.2 inverse\_binwidth

```
double Histogram_Parameters::inverse_binwidth
```

/(width\_of\_one\_bin)

Referenced by lookup\_real().

### 6.56.2.3 real

```
struct { ... } Histogram_Parameters::real
```

Histogram parameters if it is some sort of 'F' or 'D' type.

Needed for real-type limits.

Referenced by fill\_gaps(), gen\_image\_lookups(), histogram\_matching(), histogram\_to\_root(), lookup\_real(), print ← \_histogram(), and set\_ebias\_correction().


The documentation for this union was generated from the following file:

· histogram.h

# 6.57 history\_struct Struct Reference

Use to build a linked list of configuration history.

Collaboration diagram for history\_struct:



### **Data Fields**

- char \* text
- time\_t time

Configuration test.

struct history\_struct \* next

Time when the configuration was entered.

### 6.57.1 Detailed Description

Use to build a linked list of configuration history.

The documentation for this struct was generated from the following file:

· io\_history.c

# 6.58 histstat Struct Reference

Statistics element for histogram analysis.

#include <histogram.h>

### **Data Fields**

- · double mean
- · double mean 2d
- · double tmean
- double tmean\_2d
- · double hmean
- · double hmean 2d
- double sigma
- · double sigma\_2d
- double median
- · double median\_2d

### 6.58.1 Detailed Description

Statistics element for histogram analysis.

The documentation for this struct was generated from the following file:

· histogram.h

# 6.59 incpath Struct Reference

An element in a linked list of include paths.

Collaboration diagram for incpath:



### **Data Fields**

• char \* path

The path name.

struct incpath \* next

The next element.

# 6.59.1 Detailed Description

An element in a linked list of include paths.

The documentation for this struct was generated from the following file:


• fileopen.c

# 6.60 linked\_string Struct Reference

The linked\_string is mainly used to keep CORSIKA input.

```
#include <mc_tel.h>
```

Collaboration diagram for linked\_string:



### **Data Fields**

- char \* text
- struct linked\_string \* next

### 6.60.1 Detailed Description

The linked\_string is mainly used to keep CORSIKA input.

The documentation for this struct was generated from the following file:

mc\_tel.h

# 6.61 map\_tel\_struct Struct Reference

Structure with per output telescope information keeping track of prerequisites.

### **Data Fields**

· int tel id

Telescope ID on output.

int ifn

Input file number (1 only in this program)

• int inp\_id

Telescope ID on input.

• int inp\_itel

Sequential telescope count on input.

· int have camset

Have camera\_settings for this telescope.

int have\_camorg

Have camera organisation for this telescope.

· int have\_pixset

Have pixel settings for this telescope.

int have\_pixdis

Have pixels disabled for this telescope (optional)

· int have camsoft

Have camera software settings for this telescope.

int have\_pointcor

Have pointing correction for this telescope.

· int have\_trackset

Have tracking settings for this telescope.

### 6.61.1 Detailed Description

Structure with per output telescope information keeping track of prerequisites.

### 6.61.2 Field Documentation

### 6.61.2.1 ifn

```
int map_tel_struct::ifn
```

Input file number (1 only in this program)

Input file number (1 or 2)

The documentation for this struct was generated from the following files:

- extract\_simtel.c
- merge\_simtel.c

# 6.62 moments Struct Reference

Numbers to be summed up to obtain the moments.

```
#include <histogram.h>
```

### **Data Fields**

- · double lower\_limit
- · double upper\_limit
- double sum
- · double tsum
- · double sum2
- double tsum2
- · double sum3
- double tsum3
- double sum4
- · double tsum4
- unsigned long entries
- unsigned long tentries
- · int level

### 6.62.1 Detailed Description

Numbers to be summed up to obtain the moments.

The documentation for this struct was generated from the following file:

· histogram.h

### 6.63 momstat Struct Reference

First, second, and higher moments of a 1-D histogram.

```
#include <histogram.h>
```

# **Data Fields**

- double mean
- double sigma
- double skewness
- · double kurtosis
- double tmean
- · double tsigma
- · double tskewness
- · double tkurtosis

### 6.63.1 Detailed Description

First, second, and higher moments of a 1-D histogram.

The documentation for this struct was generated from the following file:

· histogram.h

# 6.64 next\_file\_struct Struct Reference

Collaboration diagram for next\_file\_struct:



### **Data Fields**

- char \* fname
- struct next\_file\_struct \* next

The documentation for this struct was generated from the following files:

- · read hess.c
- · read\_hess\_cc.cc

# 6.65 photo\_electron Struct Reference

A photo-electron produced by a photon hitting a pixel.

```
#include <mc_tel.h>
```

### **Data Fields**

int pixel

The pixel that was hit.

• int lambda

The wavelength of the photon.

· double atime

The time [ns] when the photon hit the pixel.

# 6.65.1 Detailed Description

A photo-electron produced by a photon hitting a pixel.

### 6.65.2 Field Documentation

### 6.65.2.1 atime

double photo\_electron::atime

The time [ns] when the photon hit the pixel.

### 6.65.2.2 lambda

int photo\_electron::lambda

The wavelength of the photon.

# 6.65.2.3 pixel

int photo\_electron::pixel


The pixel that was hit.

The documentation for this struct was generated from the following file:

• mc\_tel.h

# 6.66 range\_list\_struct Struct Reference

Collaboration diagram for range\_list\_struct:



### **Data Fields**

- long from
- long to
- struct range\_list\_struct \* next

The documentation for this struct was generated from the following file:

· read hess.c

# 6.67 select\_struct Struct Reference

### **Data Fields**

- · int event
- · int tel id
- · int pixel
- int gain

The documentation for this struct was generated from the following file:

· rh\_dl0\_test.c

# 6.68 shower\_extra\_parameters Struct Reference

Extra shower parameters of unspecified nature.

```
#include <mc tel.h>
```

### **Data Fields**

· long id

May identify to the user what the parameters should mean.

int is set

May be reset after writing the parameter block and must thus be set to 1 for each shower for which the extra parameters should get recorded.

· double weight

To be used if the weight of a shower may change during processing, e.g.

size\_t niparam

Number of extra integer parameters.

• int \* iparam

Space for extra integer parameters, at least of size niparam.

size\_t nfparam

Number of extra floating-point parameters.

float \* fparam

Space for extra floats, at least of size nfparam.

### 6.68.1 Detailed Description

Extra shower parameters of unspecified nature.

Useful for things to be used like in the event header but which may only become available while processing a shower. Should be initialized with the init\_shower\_extra\_parameters(int ni\_max, int nf\_max) function.

### 6.68.2 Field Documentation

### 6.68.2.1 fparam

float\* shower\_extra\_parameters::fparam

Space for extra floats, at least of size nfparam.

### 6.68.2.2 id

long shower\_extra\_parameters::id

May identify to the user what the parameters should mean.

### 6.68.2.3 iparam

int\* shower\_extra\_parameters::iparam

Space for extra integer parameters, at least of size niparam.

### 6.68.2.4 is\_set

int shower\_extra\_parameters::is\_set

May be reset after writing the parameter block and must thus be set to 1 for each shower for which the extra parameters should get recorded.

### 6.68.2.5 nfparam

```
\verb|size_t| shower_extra_parameters:: nfparam|
```

Number of extra floating-point parameters.

### 6.68.2.6 niparam

```
size_t shower_extra_parameters::niparam
```

Number of extra integer parameters.

### 6.68.2.7 weight

```
double shower_extra_parameters::weight
```

To be used if the weight of a shower may change during processing, e.g.

when shower processing can be aborted depending on how quickly the electromagnetic component builds up and the remaining showers may have a larger weight to compensate for that. For backwards compatibility this should be set to 1.0 when no additional weight is needed.

The documentation for this struct was generated from the following file:

• mc\_tel.h

# 6.69 tel\_type\_param Struct Reference

### **Data Fields**

- int min\_tel\_id
- int max\_tel\_id
- · double mirror\_area
- double flen
- int num\_pixels

The documentation for this struct was generated from the following file:

user\_analysis.c

# 6.70 telescope\_list Struct Reference

### **Data Fields**


- size\_t min\_tel
- · size\_t ntel
- int \* tel\_id

The documentation for this struct was generated from the following file:

user\_analysis.c

# 6.71 trgmask\_entry Struct Reference

Collaboration diagram for trgmask\_entry:



### **Data Fields**

· long event

The event number.

• int tel\_id

The telescope ID number.

• int trg\_mask

The trigger mask bit pattern which got messed up in data files.

struct trgmask\_entry \* next


Can be used in arrays but also in linked lists.

The documentation for this struct was generated from the following file:

io\_trgmask.h

# 6.72 trgmask\_hash\_set Struct Reference

Collaboration diagram for trgmask\_hash\_set:



### **Data Fields**

- long run
- struct trgmask\_entry \* h\_e [TRGMASK\_PRIME]


  Start of linked list for each possible hash value.

The documentation for this struct was generated from the following file:

• io\_trgmask.h

# 6.73 trgmask\_set Struct Reference

Collaboration diagram for trgmask\_set:



### **Data Fields**

- · long run
- size\_t num\_entries
- struct trgmask entry \* mask

The documentation for this struct was generated from the following file:

· io\_trgmask.h

# 6.74 user\_parameters Struct Reference

### **Data Fields**

```
struct {
  int user_flags
     1: HESS-style analysis standard cuts; 2: hard cuts; 3: loose cuts.
    The minimum number of significant pixels in usable images.
  int reco_flag
    Reconstruction level flag.
  int min tel img
    Minimum and maximum number of usable images for events used in analysis.
  int max_tel_img
  int Iref
    Which pixel's amplitude is used as reference.
  int integrator
    The type of pixel intensity integration scheme.
  int integ param [3]
    Integration-scheme-specific integer parameters, typically:
  int integ_thresh [2]
    Integer type thresholds for significance in ADC units (one per gain)
  int integ no rescale
    Set to 1 if integration over small window should not rescale for fraction of single p.e.
  int trg_req
    Required trigger type (bit pattern: bit 0 = majo, 1=asum, 2=dsum)
} i
struct {
  double source_offset_deg
  double d sp idx
    Difference between generated MC spectrum (e.g.
  double min_amp
     The minimum amplitude [ peak p.e.
  double tailcut low
     The lower and upper tail cuts for the standard two-level tail-cut scheme.
  double tailcut high
  double minfrac
    Minimum fraction of reference amplitude is needed.
  double max_theta_deg
  double theta_scale
```

```
double de2_cut_param [4]
  double mscrw min [4]
  double mscrw_max [4]
  double mscrl_min [4]
  double mscrl_max [4]
  double eres cut param [4]
  double hmax cut param
  double min theta deg
  double camera clipping deg
    Pixel outside this radius (if > 0) should be ignored in image reconstruction.
  double theta_escale [4]
    If the angular acceptance deviates from the 80% containment.
  double clip_amp
    Pixel intensity clipped to this value after calibration, if this param is not zero.
  double d_integ_param [2][4]
    Integration-scheme- and gain-specific floating-point parameters.
  double calib scale
    Calibration scale from mean-p.e.
  double r_nb [3]
    Radii for initial neighbour pixel search.
  double r ne
    Radius for extending significant pixels in image cleaning [pixel diameter].
  double impact_range [3]
    [0]: maximum distance of array center from shower axis, [1],[2]: max.
  double true_impact_range [3]
    As for impact_ranhe.
  double max_core_distance
  double focal length
} d
struct {
  int user_flags
     1: HESS-style analysis standard cuts; 2: hard cuts; 3: loose cuts.
  int min pix
    The minimum number of significant pixels in usable images.
  int reco flag
    Reconstruction level flag.
  int min tel img
    Minimum and maximum number of usable images for events used in analysis.
  int max_tel_img
  int Iref
    Which pixel's amplitude is used as reference.
  int integrator
    The type of pixel intensity integration scheme.
  int integ param [3]
    Integration-scheme-specific integer parameters, typically:
  int integ_thresh [2]
    Integer type thresholds for significance in ADC units (one per gain)
  int integ no rescale
    Set to 1 if integration over small window should not rescale for fraction of single p.e.
  int trg_req
    Required trigger type (bit pattern: bit 0 = majo, 1=asum, 2=dsum)
} i
struct {
  double source_offset_deg
```

```
double d_sp_idx
          Difference between generated MC spectrum (e.g.
        double min amp
          The minimum amplitude [ peak p.e.
        double tailcut_low
           The lower and upper tail cuts for the standard two-level tail-cut scheme.
        double tailcut high
        double minfrac
          Minimum fraction of reference amplitude is needed.
        double max theta deg
        double theta_scale
        double de2_cut_param [4]
        double mscrw_min [4]
        double mscrw max [4]
        double mscrl_min [4]
        double mscrl_max [4]
        double eres cut param [4]
        double hmax cut param
        double min_theta_deg
        double camera_clipping_deg
          Pixel outside this radius (if > 0) should be ignored in image reconstruction.
        double theta escale [4]
          If the angular acceptance deviates from the 80% containment.
        double clip_amp
          Pixel intensity clipped to this value after calibration, if this param is not zero.
        double d_integ_param [2][4]
          Integration-scheme- and gain-specific floating-point parameters.
        double calib scale
          Calibration scale from mean-p.e.
        double r nb [3]
          Radii for initial neighbour pixel search.
        double r ne
          Radius for extending significant pixels in image cleaning [pixel diameter].
        double impact_range [3]
          [0]: maximum distance of array center from shower axis, [1],[2]: max.
        double true_impact_range [3]
          As for impact_ranhe.
        double max_core_distance
        double focal_length
      } d
6.74.1 Field Documentation
```

```
6.74.1.1 calib scale
double user_parameters::calib_scale
Calibration scale from mean-p.e.
units to experimental units (0.0: like HESS).
```

```
6.74.1.2 camera_clipping_deg
```

```
double user_parameters::camera_clipping_deg
```

Pixel outside this radius (if > 0) should be ignored in image reconstruction.

### 6.74.1.3 clip\_amp

```
double user_parameters::clip_amp
```

Pixel intensity clipped to this value after calibration, if this param is not zero.

### 6.74.1.4 d\_integ\_param

```
double user_parameters::d_integ_param[2][4]
```

Integration-scheme- and gain-specific floating-point parameters.

### 6.74.1.5 d\_sp\_idx

```
double user_parameters::d_sp_idx
```

Difference between generated MC spectrum (e.g.

 $E^{-2.0}$ ) and assumed source spectrum (e.g.  $E^{-2.5}$ ), e.g. case  $d_{sp_idx} = -0.5$ .

Referenced by user\_event\_fill(), and user\_mc\_event\_fill().

### 6.74.1.6 impact\_range

```
double user_parameters::impact_range[3]
```

[0]: maximum distance of array center from shower axis, [1],[2]: max.

|x|,|y| of core in ground plane.

### 6.74.1.7 integ\_no\_rescale

```
int user_parameters::integ_no_rescale
```

Set to 1 if integration over small window should not rescale for fraction of single p.e.

trace.

### 6.74.1.8 integ\_param

```
int user_parameters::integ_param[3]
```

Integration-scheme-specific integer parameters, typically:

number of bins to integrate and some offset value from start or back from detected peak.

Referenced by pixel\_integration().

### 6.74.1.9 integrator

```
int user_parameters::integrator
```

The type of pixel intensity integration scheme.

0: none (implicitly all samples), 1: simple, 2: around global peak, 3: around local peak, 4: around peak in neighbour pixels.

Referenced by pixel\_integration().

### 6.74.1.10 min\_amp

```
double user_parameters::min_amp
```

The minimum amplitude [ peak p.e.

] of images usable for the analysis.

### 6.74.1.11 min\_pix

```
int user_parameters::min_pix
```

The minimum number of significant pixels in usable images.

### 6.74.1.12 min\_tel\_img

```
int user_parameters::min_tel_img
```

Minimum and maximum number of usable images for events used in analysis.

```
6.74.1.13 r_nb
```

```
double user_parameters::r_nb[3]
```

Radii for initial neighbour pixel search.

Maximum search radii for neighbours [pixel diameter]

### 6.74.1.14 tailcut\_low

```
double user_parameters::tailcut_low
```

The lower and upper tail cuts for the standard two-level tail-cut scheme.

### 6.74.1.15 theta\_escale

```
double user_parameters::theta_escale[4]
```

If the angular acceptance deviates from the 80% containment.

### 6.74.1.16 user\_flags

```
int user_parameters::user_flags
```

1: HESS-style analysis standard cuts; 2: hard cuts; 3: loose cuts.

The documentation for this struct was generated from the following files:

- · user\_analysis.h
- ∼user\_analysis.h

# 6.75 warn\_specific\_data Struct Reference

A struct used to store thread-specific data.

# **Data Fields**

- · int warninglevel
- · int warningmode
- char output\_buffer [2048]
- const char \* logfname

The name of the log file.

- char saved\_logfname [256]
- · int buffered
- FILE \* logfile
- void(\* log\_function )(const char \*, const char \*, int, int)
- void(\* output\_function )(const char \*)
- char \*(\* aux\_function )(void)
- · int recursive

# 6.75.1 Detailed Description

A struct used to store thread-specific data.

# 6.75.2 Field Documentation

# 6.75.2.1 logfname

```
const char* warn_specific_data::logfname
```

The name of the log file.

Used only when opening the file.

The documentation for this struct was generated from the following file:

• warning.c

# **Chapter 7**


# **File Documentation**

# 7.1 add\_histograms.c File Reference

Utility program for adding up matching histograms.

```
#include "initial.h"
#include "histogram.h"
#include "io_basic.h"
#include "io_histogram.h"
#include "fileopen.h"
#include "straux.h"
```

Include dependency graph for add\_histograms.c:



# **Functions**

- void syntax (const char \*prgm)
- int main (int argc, char \*\*argv)
   Main program.

### 7.1.1 Detailed Description

Utility program for adding up matching histograms.

```
Syntax: add_histograms [ -x id1,...] input_files ... -o output_file
```

The histograms may be within multiple I/O blocks of the input file. Matching histograms will be added up, unless set to be excluded with the '-x' option. Only non-empty histograms are written to output.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2014/06/24 14:29:40 $
```

Version


```
CVS $Revision: 1.2 $
```

# 7.2 atmprof.c File Reference

A stripped-down version of the interpolation of atmospheric profiles from the atmo.c file of the CORSIKA IACT/A← TMO package.

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <math.h>
#include <unistd.h>
#include "atmprof.h"
#include "fileopen.h"
```

Include dependency graph for atmprof.c:



### **Macros**

• #define MAX\_PROFILE 50

### **Functions**

static void interp (double x, double \*v, int n, int \*ipl, double \*rpl)

Linear interpolation with binary search algorithm.

• static double rpol (double \*x, double \*y, int n, double xp)

Linear interpolation with binary search algorithm.

static char \* find\_elsewhere (const char \*fname, char \*bf, size\_t sz)

Find the atmospheric profiles elsewhere (in the sim\_telarray configuration).

• int init atmprof (int atmosphere)

Initialize atmospheric profiles.

double rhofx (double height)

Density of the atmosphere as a function of altitude.

• double thickx (double height)

Atmospheric thickness [g/cm\*\*2] as a function of altitude.

double refidx (double height)

Index of refraction as a function of altitude [cm].

• double heighx (double thick)

Altitude [m] as a function of atmospheric thickness [g/cm\*\*2].

### **Variables**

- · static int current\_atmosphere
- · static int num prof
- static double p\_alt [MAX\_PROFILE]
- static double p log alt [MAX PROFILE]
- static double **p\_log\_rho** [MAX\_PROFILE]
- static double p\_rho [MAX\_PROFILE]
- static double p\_log\_thick [MAX\_PROFILE]
- static double p log n1 [MAX PROFILE]
- static double top\_of\_atmosphere = 112.83e3
- static double **bottom\_of\_atmosphere** = 0.

### 7.2.1 Detailed Description

A stripped-down version of the interpolation of atmospheric profiles from the atmo.c file of the CORSIKA IACT/A← TMO package.

The main differences are a) parameters are passed by value instead of FORTRAN by-reference way, b) the height is measured in meters.

The CORSIKA built-in profiles are not handled here.

### **Author**

Konrad Bernloehr

### Date

```
CVS $Date: 2010/07/20 13:37:47 $
```

### Version

```
CVS $Revision: 1.6 $
```

### 7.2.2 Function Documentation

### 7.2.2.1 heighx()

```
double heighx ( \label{eq:double_thick} \mbox{double } thick \mbox{ )}
```

Altitude [m] as a function of atmospheric thickness [g/cm\*\*2].

### **Parameters**

```
thick atmospheric thickness [g/cm**2]
```

### Returns

altitude [m]

### 7.2.2.2 init\_atmprof()

Initialize atmospheric profiles.

Atmospheric models are read in from text-format tables. For the interpolation of relevant parameters (density, thickness, index of refraction, ...) all parameters are transformed such that linear interpolation can be easily used.

### **Parameters**

### Returns

```
0 (OK) or -1 (error, e.g. table available)
```

References fileopen(), and find\_elsewhere().

### 7.2.2.3 interp()

```
static void interp ( double x,
```

```
double * v,
int n,
int * ipl,
double * rpl ) [static]
```

Linear interpolation with binary search algorithm.

Linear interpolation between data point in sorted (i.e. monotonic ascending or descending) order. This function determines between which two data points the requested coordinate is and where between them. If the given coordinate is outside the covered range, the value for the corresponding edge is returned.

A binary search algorithm is used for fast interpolation.

### **Parameters**

X	Input: the requested coordinate
V	Input: tabulated coordinates at data points
n	Input: number of data points
ipl	Output: the number of the data point following the requested coordinate in the given sorting (1 <= ipl <= n-1)
rpl	Output: the fraction $(x-v[ipl-1])/(v[ipl]-v[ipl-1])$ with $0 \le rpl \le 1$

References rpol().

Referenced by rpol().

### 7.2.2.4 refidx()

```
double refidx ( \mbox{double } \mbox{\it height } \mbox{\it )}
```

Index of refraction as a function of altitude [cm].

### **Parameters**

```
height altitude [m]
```

### Returns

index of refraction

### 7.2.2.5 rhofx()

Density of the atmosphere as a function of altitude.

### **Parameters**

```
height altitude [m]
```

### Returns

```
density [g/cm**3]
```

### 7.2.2.6 rpol()

Linear interpolation with binary search algorithm.

Linear interpolation between data point in sorted (i.e. monotonic ascending or descending) order. The resulting interpolated value is returned as a return value.

This function calls interp() to find out where to interpolate.

### **Parameters**

X	Input: Coordinates for data table	
У	Input: Corresponding values for data table	
n	Input: Number of data points	
хр	Input: Coordinate of requested value	

### Returns

Interpolated value

References find\_elsewhere(), and interp().

Referenced by interp().

# 7.2.2.7 thickx()

```
double thickx (

double height)
```

Atmospheric thickness [g/cm\*\*2] as a function of altitude.

### **Parameters**

height	altitude [m]
--------	--------------


### Returns

thickness [g/cm\*\*2]

# 7.3 basic\_ntuple.h File Reference

Desclaration of the <a href="basic\_ntuple">basic\_ntuple</a> struct.

This graph shows which files directly or indirectly include this file:



### **Data Structures**

struct basic\_ntuple

A struct with basic per-shower parameters, to be used as an n-tuple in the event selection.

### **Functions**

• int list\_ntuple (FILE \*f, const struct basic\_ntuple \*b, int wtr)

List the parameters useful for event selection plus some more parameters which should not be used for event selection.

### 7.3.1 Detailed Description

Desclaration of the <a href="basic\_ntuple">basic\_ntuple</a> struct.

### 7.3.2 Function Documentation

### 7.3.2.1 list\_ntuple()

```
int list_ntuple (
          FILE * f,
          const struct basic_ntuple * b,
          int wtr )
```

List the parameters useful for event selection plus some more parameters which should not be used for event selection.

### **Parameters**

f	Output file, to be opened beforehand.
b	Pointer to the struct containing all the relevant numbers.
wtr	Non-zero on first call to write also true MC parameters.


References basic\_ntuple::lg\_e, basic\_ntuple::mdisp, basic\_ntuple::rcm, and basic\_ntuple::theta.

# 7.4 best\_of.cc File Reference

Tool for extracting best values from listings of 'rh3' sensitivity evaluations.

```
#include "initial.h"
#include "straux.h"
#include "fileopen.h"
#include <vector>
#include <map>
#include <iostream>
#include <cstdio>
#include <cstring>
```

Include dependency graph for best\_of.cc:



### **Data Structures**

struct best\_value

### **Enumerations**

```
enum SpecType {
    SPEC_NONE = -1, SPEC_GAMMA = 0, SPEC_ELECTRON = 1, SPEC_PROTON = 101,
    SPEC_HE = 402, SPEC_CNO = 1407, SPEC_SI = 2814, SPEC_IRON = 5626,
    SPEC_NONE = -1, SPEC_GAMMA = 0, SPEC_ELECTRON = 1, SPEC_PROTON = 101,
    SPEC_HE = 402, SPEC_CNO = 1407, SPEC_SI = 2814, SPEC_IRON = 5626 }

enum espec_t {
    OLD_E_POWERLAW = 1, NEW_E_POWERLAW = 2, NEW_E_PL_LGN1 = 3, NEW_E_PL_LGN2 = 4,
    OLD_E_POWERLAW = 1, NEW_E_POWERLAW = 2, NEW_E_PL_LGN1 = 3, NEW_E_PL_LGN2 = 4 }

enum BestChoice {
    BestDiff = 1, BestIntegral = 2, BestAngle = 3, BestEres = 4,
    BestRate = 5, BestCombined = 6, BestAll = 7 }
```

### **Functions**

- string particle\_type (SpecType sp)
- · double Crab Unit (double E)
- static double **cu** (double x)
- double Crab Unit int (double E)
- double ergs (double E)
- static double **f50** (double x)
- static double fsp50 (double x)
- double Flux req50 south (double E)
- double Flux req50 E2erg south (double E)
- double Flux\_req50\_CU\_south (double E)
- static double fn50 (double x)
- static double fnsp50 (double x)
- double Flux req50 north (double E)
- double Flux req50 E2erg north (double E)
- double Flux\_req50\_CU\_north (double E)
- static double **f5** (double x)
- static double fsp5 (double x)
- double Flux req5\_south (double E)
- double Flux\_req5\_E2erg\_south (double E)
- double Flux\_req5\_CU\_south (double E)
- static double fn5 (double x)
- static double fnsp5 (double x)
- double Flux\_req5\_north (double E)
- double Flux\_req5\_E2erg\_north (double E)
- double Flux req5 CU north (double E)
- static double f05 (double x)
- static double fsp05 (double x)
- double Flux\_req05\_south (double E)
- double Flux req05 E2erg south (double E)
- double Flux req05 CU south (double E)
- static double fn05 (double x)
- static double fnsp05 (double x)
- double Flux\_req05\_north (double E)
- double Flux\_req05\_E2erg\_north (double E)
- double Flux\_req05\_CU\_north (double E)
- static double fd50 (double x)
- static double fdes50 (double x)
- double Flux\_goal50\_south (double E)

- double Flux\_goal50\_E2erg\_south (double E)
- double Flux\_goal50\_CU\_south (double E)
- static double **fnd50** (double x)
- static double fndes50 (double x)
- double Flux\_goal50\_north (double E)
- double Flux\_goal50\_E2erg\_north (double E)
- double Flux\_goal50\_CU\_north (double E)
- double Angular\_resolution\_req (double E)
- double Angular\_resolution\_goal (double E)
- static double eresb (double E)
- double Energy\_resolution\_req (double E)
- · static double eresdb (double E)
- double Energy\_resolution\_goal (double E)
- double flux\_int (SpecType sp, double E1, double E2)
- double lima17 (double on, double off, double alpha)
- bool matching\_required\_diffsens (int calc\_pput, bool with\_flux, double E, double diff\_sens)
- bool matching\_required\_performance (int calc\_pput, bool with\_flux, double E, double diff\_sens, double angres, double eres)
- bool matching\_required\_angres (double E, double angres)
- bool matching\_required\_eres (double E, double eres)
- int main (int argc, char \*\*argv)

### **Variables**

```
• static double sce = 1.6022
```

- static double sca = 1e-4
- static double sc = sce\*sca
- espec\_t espec\_type = OLD\_E\_POWERLAW

### 7.4.1 Detailed Description

Tool for extracting best values from listings of 'rh3' sensitivity evaluations.

Three versions of the 'rh3' output format are supported. All of the input (from standard input) should be in the same format type.


# 7.5 camera\_image.c File Reference

Plot a camera image from H.E.S.S.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "history.h"
#include "io_hess.h"
#include "fileopen.h"
#include "rec_tools.h"
#include "reconstruct.h"
```

#include "camera\_image.h"

Include dependency graph for camera\_image.c:



### **Macros**

- #define H\_MAX\_NB1 8
- #define H\_MAX\_NB2 24

### **Functions**

- static int guessed\_pixel\_shape\_type (CameraSettings \*camset, int itel)
- static double **dist2** (double x, double y)
- static void print\_pix\_col (double n\_o\_r, FILE \*psfile, double gamma\_coeff)

Print a false-colour RGB value for a pixel intensity.

• void hesscam\_ps\_plot (const char \*image\_fname, AllHessData \*hsdata, int itel, int type, int amp\_tm, double clip\_amp)

Write PostScript of camera sum image or sample image to a dedicated file.

• static int find\_neighbours (CameraSettings \*camset, int itel)

Find the list of neighbours for each pixel.

### **Variables**

- static char ps\_head1a[]
- static char ps\_head1b []
- static char ps\_head2 []
- static char ps\_head3 []
- static char ps begin page1 []
- static char ps\_begin\_page2 []
- static char ps\_end\_page []
- static char ps\_trailer []
- static char alt\_az\_arrow []
- static int **ps\_num\_page** = 0
- static int neighbours1 [H\_MAX\_TEL][H\_MAX\_PIX][H\_MAX\_NB1]
- static int nnb1 [H\_MAX\_TEL][H\_MAX\_PIX]
- static int has\_nblist [H\_MAX\_TEL]
- static int px\_shape\_type [H\_MAX\_TEL]

### 7.5.1 Detailed Description

Plot a camera image from H.E.S.S.

/CTA data.

This code is derived from sim\_conv2hess.c but now getting the relevant data from the data structure filled after reading the eventio based data, rather than from the internal data structures of sim\_hessarray. As a consequence not all information available in the sim\_hessarray generated plots is available in the plots generated here. Also some flexibility is lost, concerning for example the pixel shape which is not included in the data.

**Author** 

Konrad Bernloehr

Date

```
CVS $Date: 2017/08/21 16:48:14 $
```

Version

```
CVS $Revision: 1.40 $
```

### 7.5.2 Function Documentation

### 7.5.2.1 find\_neighbours()

Find the list of neighbours for each pixel.

 $References\ hess\_camera\_settings\_struct::num\_pixels.$ 

### 7.5.2.2 hesscam\_ps\_plot()

Write PostScript of camera sum image or sample image to a dedicated file.

Also controlled via environment variables GAMMA\_COEFF, GRAY\_IMAGE, IMAGE\_RANGE, IMAGE\_OFFSET for image colors, PLOT\_WITH\_PIXEL\_ID, PLOT\_WITH\_PIXEL\_AMP, PLOT\_WITH\_PIXEL\_PE for overlay text, SH←OW\_TRUE\_PE for showing color for true p.e. number in place of calibrated amplitude.

#### **Parameters**

image_fname	The name of the postscript image file. Opened for appending new images.
hsdata	Pointer to the structure containing all data.
itel	The telescope index number.
type	Event type (<0: MC events, >=0: various type of calib data).
amp_tm	0: Use normal integrated amplitude. 1: Use integration around global peak position from pulse shape analysis. May include all pixels or only selected. 2: Use integration around local peak position from pulse shape analysis. Return 0 for pixels without a fairly significant peak. 3: Show only true p.e. content as amplitude (no samples).
clip_amp	if >0, any calibrated amplitude is clipped not to exceed this value [mean p.e.].

References hess\_event\_data\_struct::central, hess\_camera\_settings\_struct::flen, hess\_central\_event\_data\_
struct::glob\_count, hess\_tel\_event\_data\_struct::loc\_count, hess\_camera\_settings\_struct::num\_pixels, hess\_camera\_settings\_struct::run, hess\_camera\_settings\_struct::tel\_id, hess\_event\_data\_struct::teldata, hess\_camera\_camera\_camera\_settings\_struct::ypix.

### 7.5.2.3 print\_pix\_col()

Print a false-colour RGB value for a pixel intensity.

### 7.5.3 Variable Documentation

### 7.5.3.1 alt\_az\_arrow

```
char alt_az_arrow[] [static]
```

### Initial value:

```
"n 18000 26000 m "
"0 100 rl 200 -100 rl -200 -100 rl 0 100 rl -1000 0 rl "
"cp gs 20 slw black s gr\n"
"txt5 18700 26100 mtxt (Az) tblack\n"
"n 17000 25000 m "
"100 0 rl -100 -200 rl -100 200 rl 100 0 rl 0 1000 rl "
"cp gs 20 slw black s gr\n"
"txt5 17000 24600 mtxt (Alt) tblack\n"
"gs 17800 25500 tr %f rot -17800 -25500 tr\n"
"n 17800 25500 m"
"0 100 rl 200 -100 rl -200 -100 rl 0 100 rl -300 0 rl "
"cp gs 10 slw black s gr\n"
"txt2 17950 25350 mtxt (y) tblack\n"
"n 17500 25200 m"
"100 0 rl -100 -200 rl -100 200 rl 100 0 rl 0 300 rl "
"cp gs 10 slw black s gr\n"
"txt2 177700 25200 mtxt (x) tblack\n"
"txt2 177700 25200 mtxt (x) tblack\n"
"txt2 177700 25200 mtxt (x) tblack\n"
"gr\n"
```

```
7.5.3.2 ps_begin_page1
char ps_begin_page1[] [static]
Initial value:
"%%Page: "
7.5.3.3 ps_begin_page2
char ps_begin_page2[] [static]
Initial value:
=
"save\n"
"save\n"
"10 setmiterlimit\n"
"n -1000 31000 m -1000 -1000 1 22000 -1000 1 22000 31000 1 cp clip\n"
" 0.02835 0.02835 sc\n"
"gs\n"
"7.500 slw\n"
"black\n"
7.5.3.4 ps_end_page
char ps_end_page[] [static]
Initial value:
"gr\n"
"showpage\n"
7.5.3.5 ps_head1a
char ps_headla[] [static]
Initial value:
"%!PS-Adobe-2.0\n"
"%%Title: H.E.S.S. Telescope Simulation"
```

```
7.5.3.6 ps_head1b
```

```
char ps_headlb[] [static]
```

### Initial value:

```
=
"\n%%Creator:"
```

### 7.5.3.7 ps\_trailer

```
char ps_trailer[] [static]
```

### Initial value:


```
=
"rs\n"
```

# 7.6 check\_trgmask.c File Reference

Check consistency of 'trgmask' files produced with gen\_trgmask for the CTA prod-2 data sets produced in 2013.

```
#include "initial.h"
#include "io_basic.h"
#include "fileopen.h"
#include "io_trgmask.h"
```

Include dependency graph for check\_trgmask.c:



### **Functions**

int main (int argc, char \*\*argv)

### 7.6.1 Detailed Description


Check consistency of 'trgmask' files produced with gen\_trgmask for the CTA prod-2 data sets produced in 2013.

```
Syntax: bin/check_trgmask trgmask-file
@author Konrad Bernloehr
```

### 7.7 current.c File Reference

Code to insert current time string into warnings.

```
#include "initial.h"
#include "current.h"
Include dependency graph for current.c:
```



### **Macros**

• #define \_\_Current\_Module\_\_ 1

### **Functions**

- static long time\_correction (time\_t now)
- time\_t current\_time ()

Get the current time in seconds since 1970.0 GMT.

• time\_t current\_localtime ()

Like current\_time() but should return time in the local time zone.

• void set\_current\_offset (long off)

Set current time offset.

• void set\_local\_offset (long off)

Set offset of local time zone.

void reset\_local\_offset ()

Reset any previous local time offset.

• char \* time\_string ()

Return a pointer to a formatted time-and-date string.

• time\_t mkgmtime (struct tm \*tms)

Inverse to gmtime() library function.

7.7 current.c File Reference 147

### **Variables**

- static long tcor\_parm [3]
- static long local\_offset = DEFAULT\_LOCAL\_OFFSET
- static int local\_set =0

### 7.7.1 Detailed Description

Code to insert current time string into warnings.

This code is meant for inserting time strings into warnings passed through the code of warning.c. It is not currently used in my code and is not yet multi-threading safe. It is here mainly for improved backward-compatibility with config.c.

Author

Konrad Bernloehr

Date

1995, 2000, 2007

**Date** 

2018/05/11 11:54:29

Version

Revision

1.8

### 7.7.2 Function Documentation

## 7.7.2.1 current\_localtime()

Like current time() but should return time in the local time zone.

The offset of the time zone to GMT must be set by set\_local\_offset() or it is derived from the machine's internal time zone setup.

Referenced by time\_string().

### 7.7.2.2 current\_time()

Get the current time in seconds since 1970.0 GMT.

The resulting time includes the last time correction with respect to the server. Therefore, as long as the clock on the local computer is not much slower or faster than the clock on the I/O server, it is the current Greenwich Mean Time on the I/O server.

### Returns

Time in seconds since 0h UT on January 1, 1970.

### 7.7.2.3 mkgmtime()

```
time_t mkgmtime ( struct \ tm * \ tms \ )
```

Inverse to gmtime() library function.

Inverse to gmtime() library function without correction for timezone and daylight saving time.

### **Parameters**

```
tms Pointer to time structure as filled by gmtime().
```

### Returns

Time in seconds since 1970.0

## 7.7.2.4 reset\_local\_offset()

Reset any previous local time offset.

Reset any previously set local time offset. The next call to <a href="mailto:current\_localtime">current\_localtime</a>() will therefore set the offset to present system value.

Note: in a multi-threaded program this function should be called only at program startup.

### Returns

(none)

7.7 current.c File Reference 149

### 7.7.2.5 set\_current\_offset()

Set current time offset.

Set the offset between the time on the time server and the local time (in seconds in the sense 'remote-local').

Note: in a multi-threaded program this function should be called only at program startup.

### **Parameters**

```
off Time offset in seconds
```

### Returns

(none)

### 7.7.2.6 set\_local\_offset()

Set offset of local time zone.

Set the offset between the local time zone and GMT (in seconds in the sense 'local zone - GMT').

Note: in a multi-threaded program this function should be called only at program startup.

### **Parameters**

```
off Time offset in seconds
```

### Returns

(none)

## 7.7.2.7 time\_string()

```
char* time_string (
     void )
```

Return a pointer to a formatted time-and-date string.

This string is reused (changed) on the next call.

### Returns


Time/date character string pointer.

References current\_localtime().

## 7.8 current.h File Reference

Header file for optional current time add-on to warning.c.

This graph shows which files directly or indirectly include this file:



### **Macros**

• #define DEFAULT\_LOCAL\_OFFSET 3600

### **Functions**

• time\_t current\_time (void)

Get the current time in seconds since 1970.0 GMT.

time\_t current\_localtime (void)

Like current\_time() but should return time in the local time zone.

void set\_current\_offset (long \_toffset)

Set current time offset.

• void set\_local\_offset (long \_local\_offset)

Set offset of local time zone.

void reset\_local\_offset (void)

Reset any previous local time offset.

• char \* time\_string (void)

Return a pointer to a formatted time-and-date string.

• time\_t mkgmtime (struct tm \*tms)

Inverse to gmtime() library function.

### **Variables**

time\_t last\_data\_time

7.8 current.h File Reference 151

## 7.8.1 Detailed Description

Header file for optional current time add-on to warning.c.

**Author** 

Konrad Bernloehr

Date

1993 (original version)

Date

2010/07/20 13:37:45

Revision

1.4

### 7.8.2 Function Documentation

## 7.8.2.1 current\_localtime()

Like current\_time() but should return time in the local time zone.

The offset of the time zone to GMT must be set by set\_local\_offset() or it is derived from the machine's internal time zone setup.

Referenced by time\_string().

## 7.8.2.2 current\_time()

```
time_t current_time (
     void )
```

Get the current time in seconds since 1970.0 GMT.

The resulting time includes the last time correction with respect to the server. Therefore, as long as the clock on the local computer is not much slower or faster than the clock on the I/O server, it is the current Greenwich Mean Time on the I/O server.

Returns

Time in seconds since 0h UT on January 1, 1970.

### 7.8.2.3 mkgmtime()

```
time_t mkgmtime (
          struct tm * tms )
```

Inverse to gmtime() library function.

Inverse to gmtime() library function without correction for timezone and daylight saving time.

### **Parameters**

tms Pointer to time structure as filled by gmtime().

### Returns

Time in seconds since 1970.0

### 7.8.2.4 reset\_local\_offset()

Reset any previous local time offset.

Reset any previously set local time offset. The next call to <a href="mailto:current\_localtime">current\_localtime</a>() will therefore set the offset to present system value.

Note: in a multi-threaded program this function should be called only at program startup.

### Returns

(none)

### 7.8.2.5 set\_current\_offset()

Set current time offset.

Set the offset between the time on the time server and the local time (in seconds in the sense 'remote-local').

Note: in a multi-threaded program this function should be called only at program startup.

### **Parameters**

off   Time offset in se	econds
-------------------------	--------

## Returns

(none)

7.9 cvt2.c File Reference 153

### 7.8.2.6 set\_local\_offset()

Set offset of local time zone.

Set the offset between the local time zone and GMT (in seconds in the sense 'local zone - GMT').

Note: in a multi-threaded program this function should be called only at program startup.

### **Parameters**

```
off Time offset in seconds
```

### Returns

(none)

## 7.8.2.7 time\_string()

```
char* time_string (
     void )
```

Return a pointer to a formatted time-and-date string.

This string is reused (changed) on the next call.

## Returns

Time/date character string pointer.


References current\_localtime().

## 7.9 cvt2.c File Reference

Utility program for converting histograms to HBOOK format.

```
#include "initial.h"
#include "histogram.h"
#include "io_basic.h"
#include "tohbook.h"
#include "io_histogram.h"
```

#include "fileopen.h"
Include dependency graph for cvt2.c:



## **Functions**

int main (int argc, char \*\*argv)
 Main program.

### 7.9.1 Detailed Description

Utility program for converting histograms to HBOOK format.

```
Syntax: hdata2hbook [ input_file [ output_file ] ]
    or: hdata2hbook -a input_files ... -o output_file
```

The program was originally called cvt2. The default input file name is 'testpattern.hdata', the default output file name is 'testpattern.hbook' or the input file name with extension '.hbook' (instead of '.hdata'). The histograms may be within multiple I/O blocks of the input file. Only non-empty histograms are written to output.

With the '-a' option, all identical histograms in the input files will be added up before writing them to output.

### **Author**

Konrad Bernloehr

## Date

```
CVS $Date: 2014/02/20 10:53:06 $
```

### Version

```
CVS Revision: 1.23 $
```


7.10 cvt3.cc File Reference 155

### 7.10 cvt3.cc File Reference

Conversion of eventio histograms to ROOT format.

```
#include "initial.h"
#include "histogram.h"
#include "io_basic.h"
#include "io_histogram.h"
#include "warning.h"
#include "fileopen.h"
#include "straux.h"
#include "toroot.hh"
#include <vector>
```

Include dependency graph for cvt3.cc:



### **Functions**

- int read\_file (IO\_BUFFER \*iobuf, const char \*fname, int add\_flag, int list\_flag)
- int main (int argc, char \*\*argv)

### 7.10.1 Detailed Description

Conversion of eventio histograms to ROOT format.

```
Syntax: hdata2root [ input_file [ output_file ] ]
    or: hdata2root -a input_files ... -o output_file
```

The program was originally called cvt3. The default input file name is 'testpattern.hdata', the default output file name is 'testpattern.root' or the input file name with extension '.root' (instead of '.hdata'). The histograms may be within multiple I/O blocks of the input file. Only non-empty histograms are written to output. Take care not to replace any ROOT data format you wanted to keep.

With the '-a' option, all identical histograms in the input files will be added up before writing them to output.

### **Author**

Konrad Bernloehr

### Date

```
CVS $Date: 2016/10/21 12:37:05 $
```

### Version


```
CVS Revision: 1.19 $
```

## 7.11 dhsort.c File Reference

dhsort - double type number heapsort

```
#include "initial.h"
#include "dhsort.h"
```

Include dependency graph for dhsort.c:



## **Functions**

void dhsort (double \*dnum, int nel)
 Perform a heap sort on a double array starting at dnum.

## 7.11.1 Detailed Description

dhsort - double type number heapsort

Author

Konrad Bernloehr

Date

Date

2010/07/20 13:37:45

Version

Revision

1.6

```
Based on algorithms by Jon Bentley [Communications of the ACM v 28\ n\ 3\ p\ 245 (Mar 85) and v 28\ n\ 5\ p\ 456 (May 85)], and the sort interface routines by Allen I. Holub [Dr. Dobb's Journal \#102 (Apr 85)].
```

Notes...

This routine sorts N doubles in worst-case time proportional to  $N*\log(N)$ . The heapsort was discovered by J. W. J. Williams [Communications of the ACM v 7 p 347-348 (1964)] and is discussed by D. E. Knuth [The Art of Computer Programming, Volume 3: Sorting and Searching, Addison-Wesley, Reading, Mass., 1973, section 5.2.3].

This algorithm depends on a portion of an array having the "heap" property. The array X has the property heap[L,U] if:

```
for all L, i, and U such that 2L \le i \le U we have X[i \text{ div } 2] \le X[i]
```

### 7.11.2 Function Documentation

### 7.11.2.1 dhsort()

Perform a heap sort on a double array starting at dnum.

References main().


## 7.12 eventio\_registry.c File Reference

Register and enquire about well-known I/O block types.

```
#include "initial.h"
#include "eventio_registry.h"
```

```
#include "fileopen.h"
```

Include dependency graph for eventio\_registry.c:



## **Data Structures**

• struct ev\_reg\_chain

Use a double-linked list for the registry.

## **Functions**

- struct ev\_reg\_entry \* new\_reg\_entry (unsigned long t, const char \*n, const char \*d)

  Allocate a new entry for the registry.
- int read\_eventio\_registry (const char \*fname)

Read the type names and descriptions into the registry.

• static void read\_default\_registry (void)

By default the registry contents will be searched in a few places.

• struct ev\_reg\_entry \* find\_ev\_reg\_std (unsigned long t)

Find an entry for a given type number in the registry.

• void set\_ev\_reg\_std ()

Set the default registry search function.

### **Variables**

• static struct ev\_reg\_chain \* ev\_reg\_start = NULL

## 7.12.1 Detailed Description

Register and enquire about well-known I/O block types.

**Author** 

Konrad Bernloehr

Date

2014

CVS

Date

2017/05/16 12:31:51

Version

**CVS** 

Revision

1.4

### 7.12.2 Function Documentation

```
7.12.2.1 find_ev_reg_std()
```

Find an entry for a given type number in the registry.

This is the standard implementation being used by default where available.

References ev\_reg\_chain::entry, and read\_default\_registry().

Referenced by set\_ev\_reg\_std().

## 7.12.2.2 read\_eventio\_registry()

Read the type names and descriptions into the registry.

Note: this will only be done once.

References ev\_reg\_chain::entry, fileclose(), fileopen(), new\_reg\_entry(), and read\_default\_registry().

Referenced by read\_default\_registry().

### 7.12.2.3 set\_ev\_reg\_std()

```
void set_ev_reg_std (
     void )
```

Set the default registry search function.

At least with GCC we can do this without explicitly calling it.


References ev\_reg\_chain::entry, find\_ev\_reg\_std(), main(), and read\_default\_registry().

# 7.13 eventio\_registry.h File Reference


Register and enquire about well-known I/O block types.

```
#include "initial.h"
#include "io_basic.h"
```

Include dependency graph for eventio\_registry.h:



This graph shows which files directly or indirectly include this file:



### **Functions**

```
    int read_eventio_registry (const char *fname)
```

Read the type names and descriptions into the registry.

struct ev\_reg\_entry \* find\_ev\_reg\_std (unsigned long t)

Find an entry for a given type number in the registry.

void set\_ev\_reg\_std (void)

Set the default registry search function.

## 7.13.1 Detailed Description

Register and enquire about well-known I/O block types.

Author

Konrad Bernloehr

Date

2014

CVS

Date

2014/06/01 11:33:04

Version

CVS

Revision

1.2

## 7.13.2 Function Documentation

Find an entry for a given type number in the registry.

This is the standard implementation being used by default where available.

References ev\_reg\_chain::entry, and read\_default\_registry().

Referenced by set\_ev\_reg\_std().

### 7.13.2.2 read\_eventio\_registry()

Read the type names and descriptions into the registry.

Note: this will only be done once.

References ev\_reg\_chain::entry, fileclose(), fileopen(), new\_reg\_entry(), and read\_default\_registry().

Referenced by read\_default\_registry().

### 7.13.2.3 set\_ev\_reg\_std()

Set the default registry search function.

At least with GCC we can do this without explicitly calling it.


References ev\_reg\_chain::entry, find\_ev\_reg\_std(), main(), and read\_default\_registry().

## 7.14 extract\_hess.c File Reference

### Extract part of the H.E.S.S.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "history.h"
#include "io_hess.h"
#include "histogram.h"
#include "io_histogram.h"
#include "fileopen.h"
#include <signal.h>
```

Include dependency graph for extract\_hess.c:



### **Functions**

```
    static void syntax (char *program)
        Show program syntax.
    int main (int argc, char **argv)
        Main program.
```

### **Variables**

· static int interrupted

### 7.14.1 Detailed Description

```
Extract part of the H.E.S.S. data from sim_hessarray.
```

Author

Konrad Bernloehr

```
Date
```

```
CVS $Date: 2014/10/28 14:23:47 $
```

### Version


```
CVS $Revision: 1.7 $
```

## 7.15 extract\_simtel.c File Reference

A program for extracting data for a subset of simulated telescopes.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "history.h"
#include "io_hess.h"
#include "histogram.h"
#include "fileopen.h"
#include "straux.h"
#include "warning.h"
#include "io_trgmask.h"
#include "eventio_version.h"
#include <signal.h>
```

Include dependency graph for extract\_simtel.c:



### **Data Structures**

• struct map\_tel\_struct

Structure with per output telescope information keeping track of prerequisites.

### **Functions**

· void stop signal function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

static void syntax (const char \*program)

Show program syntax.

• int find\_in\_tel\_idx (int tel\_id, int ifile)

Offset of an input telescope of given ID within the input structures.

• int find\_out\_tel\_idx (int tel\_id, int ifile)

Offset of an input telescope of given ID within the output structures.

• int find mapped telescope (int tel id, int ifile)

Mapping from telescope ID on input to telescope ID on output, with check.

• int write\_io\_block\_to\_file (IO\_BUFFER \*iobuf, FILE \*f)

Write an I/O block as-is to another file than foreseen for the I/O buffer.

- int check\_for\_delayed\_write (IO\_ITEM\_HEADER \*item\_header, int ifile, AllHessData \*hsdata\_out, IO\_B 
   UFFER \*iobuf out)
- int merge\_data\_from\_io\_block (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*item\_header, int ifile, AllHessData \*hsdata, AllHessData \*hsdata\_out, IO\_BUFFER \*iobuf\_out)

Processing of I/O blocks from the input file.

• int check\_autoload\_trgmask (const char \*input\_fname, IO\_BUFFER \*iobuf, int ifile)

Check for a 'trgmask.gz' file matching the given input data file name and, if it exists, extract the corrected trigger bit patterns from it.

- void print\_process\_status (int prev\_type1, int this\_type1)
- int read\_map (const char \*map\_fname)
- int main (int argc, char \*\*argv)

Main program.

### **Variables**

- · static int interrupted
- static int verbose = 0
- struct map\_tel\_struct map\_tel [H\_MAX\_TEL]
- int map\_to [2][H\_MAX\_TEL+1]

Mapping structures from input telescope ID to output telescope ID.

• int tel idx [2][H MAX TEL+1]

Mapping from telescope IDs to offsets in the data structures, first for input telescope IDs.

int tel\_idx\_out [H\_MAX\_TEL+1]

Mapping from output telescope ID to offset in output data structures.

- int ntel1
- · int ntel2
- · int ntel
- int nrtel1
- · int nrtel2
- long **event1** = -1
- long **event2** = 0
- long ev\_hess\_event = 0

```
long ev_pe_sum = 0
    For delayed writing.
int run1 = -1
int run2 = -1
int min_trg = 2
static struct trgmask_set * tms [2] = { NULL, NULL }
static struct trgmask_hash_set * ths [2] = { NULL, NULL }
static int events [2] = { 0, 0 }
static int mcshowers [2] = { 0, 0 }
static int mcevents [2] = { 0, 0 }
static int max list = 999
```

### 7.15.1 Detailed Description

A program for extracting data for a subset of simulated telescopes.

The program will read sim\_telarray raw or DST data from one input file, map telescope ID according to how they appear in the list of selected telescopes and write the re-mapped blocks to an output file. It behaves basically like 'merge simtel' with only one input file.

Inputs expected - and the action to be performed: Type Once per run: 70 (history) - Write as-is, no attempt to identify which part is relevant for which telescope 2000 (run\_header) - Re-write as needed for telescope list and positions 2001 (MC run header) - Write as-is, nothing telescope-specific 1212 (input config = CORSIKA inputs) - Write as-is, nothing telescope-specific Once per telescope (and per run for raw & DST levels 0-2; just once for DST level 3): 2002 (camera settings) - Write after mapping of telescope ID (if mapped) 2003 (camera organization) - Write after mapping of telescope ID (if mapped) 2004 (pixel settings) - Write after mapping of telescope ID (if mapped) 2006 (camera software settings) - Write after mapping of telescope ID (if mapped) 2008 (tracking settings) - Write after mapping of telescope ID (if mapped) 2007 (pointing corrections) - Write after mapping of telescope ID (if mapped) 2022 (telescope monitoring) - Write after mapping of telescope ID (if mapped) 2023 (Laser calibration) - Write after mapping of telescope ID (if mapped) Per shower: once: 2020 (MC shower) - Write as-is, nothing telescope-specific per array: 2021 (MC event) - Write as-is, nothing telescope-specific Optional per event; not immediately written but delayed until next MC etc. block: 2026 (MC pe sum) - ??? 1204 (photo-electrons individually) - ??? 2010 (event) - Needs remapping at all levels At end of run: 2024 (run statistics - usually not present) 2025 (MC run statistics - usually not present) 100 (histograms) - Cannot be remapped properly (but few histograms are telescope-specific)


FIXME: Ignoring 'trgmask' files initially - include them later on.

CVS \$Revision: 1.4 \$

## 7.16 fcat.c File Reference

Trivial test and utility program for the fileopen/fileclose functions.

```
#include <stdlib.h>
#include <stdio.h>
#include <errno.h>
#include "fileopen.h"
Include dependency graph for fcat.c:
```



### **Macros**

• #define **BSIZE** 8192

### **Functions**

• int main (int argc, char \*\*argv)

## 7.16.1 Detailed Description

Trivial test and utility program for the fileopen/fileclose functions.


## 7.17 fileopen.c File Reference

Allow searching of files in declared include paths (fopen replacement).

```
#include "initial.h"
#include "straux.h"
#include "fileopen.h"
#include <string.h>
#include <strings.h>
#include <errno.h>
#include <sys/types.h>
```

#include <sys/stat.h>

Include dependency graph for fileopen.c:



### **Data Structures**

· struct incpath

An element in a linked list of include paths.

### **Functions**

- static FILE \* popenx (const char \*fname, const char \*mode)
- static FILE \* fopenx (const char \*fname, const char \*mode)
- void set\_permissive\_pipes (int p)

Enable or disable the permissive execution of pipes.

• void enable\_permissive\_pipes ()

Enable the permissive execution of pipes.

void disable\_permissive\_pipes ()

Disable the permissive execution of pipes.

• static void freepath ()

Free a whole list of include path elements.

static void freeexepath ()

Free a whole list of execution path elements.

void initpath (const char \*default\_path)

Init the path list, with default\_path as the only entry.

- void initexepath (const char \*default\_exe\_path)
- void listpath (char \*buffer, size\_t bufsize)

Show the list of include paths.

void addpath (const char \*name)

Add a path to the list of include paths, if not already there.

void addexepath (const char \*name)

Add a path to the list of execution paths, if not already there.

• static FILE \* exe\_popen (const char \*fname, const char \*mode)

Helper function for opening a pipe from or to a given program.

static FILE \* cmp\_popen (const char \*fname, const char \*mode, int compression)

Helper function for opening a compressed file through a fifo.

• static FILE \* uri popen (const char \*fname, const char \*mode, int compression)

Helper function for opening a file with a URI (http://etc.).

static FILE \* ssh\_popen (const char \*fname, const char \*mode, int compression)

Helper function for opening a file on a remote SSH server.

• FILE \* fileopen (const char \*fname, const char \*mode)

Search for a file in the include path list and open it if possible.

• int fileclose (FILE \*f)

Close a file or fifo but not if it is one of the standard streams.

### **Variables**

• static int verbose = 0

Use to decide if open/close success/failure is reported.

- static int parallel = 0
- static struct incpath \* root path = NULL

The starting element of include paths.

static struct incpath \* root exe path = NULL

The starting element for execution paths.

• static int permissive\_pipes = 0

Allow any execution pipe command if this variable is non-zero.

### 7.17.1 Detailed Description

Allow searching of files in declared include paths (fopen replacement).

The functions provided in this file provide an enhanced replacement fileopen() for the C standard library's fopen() function. The enhancements are in several areas:

- Where possible files are opened such that more than 2 gigabytes of data can be accessed on 32-bit systems when suitably compiled. This also works with software where a '-D\_FILE\_OFFSET\_BITS=64' at compile-time cannot be used (of which ROOT is an infamous example).
- For reading files, a list of paths can be configured before the the first fileopen() call and all files without absolute paths will be searched in these paths. Writing always strictly follows the given file name and will not search in the path list.
- Files compressed with gzip or bzip2 can be handled on the fly. Files with corresponding file name extensions ( .gz and .bz2 ) will be automatically decompressed when reading or compressed when writing (in a pipe, i.e. without producing temporary copies).
- In the same way, files compressed with 1zop (for extension .lzo ), 1zma (for extension .lzma ) as well as xz (for extension @ .xz ) and 1z4 (for extension .lz4 ) are handled on the fly. No check is made if these programs are installed.
- URIs (uniform resource identifiers) starting with <a href="https:">https:</a>, or ftp: will also be opened in a pipe, with optional decompression, depending on the ending of the URI name. You can therefore easily process files located on a web or ftp server. Access is limited to reading.
- Files on any SSH server where you can login without a password can be read as 'ssh://user:filepath' where filepath can be an absolute path (starting with '/') or one relative to the users home directory.
- Input and output can also be from/to a user-defined program. Restrictions apply there which prevent execution of any program by default. Either a list of accepted execution paths has to be set up beforehand with initexepath()/addexepath() or permissive mode can be enabled, allowing execution of any given program.

### Author

Konrad Bernloehr

### Date

```
Nov. 2000
```

```
CVS $Date: 2018/05/04 13:32:58 $
```

### Version

```
CVS $Revision: 1.27 $
```

### 7.17.2 Function Documentation

### 7.17.2.1 addexepath()

Add a path to the list of execution paths, if not already there.

The path name is always copied to a newly allocated memory location. This path name can actually be a colon-separated list, as for initexepath().

References addpath(), root\_exe\_path, and root\_path.

### 7.17.2.2 addpath()

Add a path to the list of include paths, if not already there.

The path name is always copied to a newly allocated memory location. This path name can actually be a colon-separated list, as for initpath(). Also environment variables (indicated by starting with '\$', e.g. "\$HOME") are accepted (and may expand into colon-separated list) but no mixed expansion (like "\$HOME/bin").

References getword(), incpath::next, incpath::path, root\_path, and verbose.

Referenced by addexepath().

### 7.17.2.3 cmp\_popen()

Helper function for opening a compressed file through a fifo.

### 7.17.2.4 disable\_permissive\_pipes()

Disable the permissive execution of pipes.

References freeexepath(), and freepath().

Referenced by set\_permissive\_pipes().

### 7.17.2.5 enable\_permissive\_pipes()

Enable the permissive execution of pipes.

Referenced by set permissive pipes().

## 7.17.2.6 exe\_popen()

Helper function for opening a pipe from or to a given program.

References incpath::path, and verbose.

Referenced by fileopen().

### 7.17.2.7 fileclose()

Close a file or fifo but not if it is one of the standard streams.

References verbose.

Referenced by read\_eventio\_registry(), and write\_all\_histograms().

### 7.17.2.8 fileopen()

Search for a file in the include path list and open it if possible.

References exe\_popen(), initpath(), incpath::path, root\_path, ssh\_popen(), uri\_popen(), and verbose.

Referenced by check\_autoload\_trgmask(), init\_atmprof(), read\_eventio\_registry(), and write\_all\_histograms().

### 7.17.2.9 freeexepath()

```
static void freeexepath ( ) [static]
```

Free a whole list of execution path elements.

References incpath::next, and incpath::path.

Referenced by disable\_permissive\_pipes().

## 7.17.2.10 freepath()

```
static void freepath ( ) [static]
```

Free a whole list of include path elements.

References incpath::next, and incpath::path.

Referenced by disable\_permissive\_pipes(), and initpath().

### 7.17.2.11 initpath()

Init the path list, with default\_path as the only entry.

References freepath(), and verbose.

Referenced by fileopen().

### 7.17.2.12 listpath()

Show the list of include paths.

References incpath::next, and incpath::path.

### 7.17.2.13 set\_permissive\_pipes()

```
void set_permissive_pipes ( \quad \text{ int } p \ )
```

Enable or disable the permissive execution of pipes.

References disable\_permissive\_pipes(), and enable\_permissive\_pipes().

### 7.17.2.14 uri\_popen()

Helper function for opening a file with a URI (http://etc.).

Referenced by fileopen().

## 7.17.3 Variable Documentation

## 7.17.3.1 permissive\_pipes

```
int permissive_pipes = 0 [static]
```

Allow any execution pipe command if this variable is non-zero.

7.17.3.2 root\_exe\_path

```
struct incpath* root_exe_path = NULL [static]
```

The starting element for execution paths.

Referenced by addexepath().

7.17.3.3 root\_path

```
struct incpath* root_path = NULL [static]
```

The starting element of include paths.

Referenced by addexepath(), addpath(), and fileopen().

## 7.18 fileopen.h File Reference

Function prototypes for fileopen.c.

This graph shows which files directly or indirectly include this file:



### **Functions**

- void initpath (const char \*default\_path)
  - Init the path list, with default\_path as the only entry.
- void initexepath (const char \*default\_path)
- void listpath (char \*buffer, size\_t bufsize)

Show the list of include paths.

void addpath (const char \*name)

Add a path to the list of include paths, if not already there.

void addexepath (const char \*name)

Add a path to the list of execution paths, if not already there.

• FILE \* fileopen (const char \*fname, const char \*mode)

Search for a file in the include path list and open it if possible.

int fileclose (FILE \*f)

Close a file or fifo but not if it is one of the standard streams.

void set\_permissive\_pipes (int p)

Enable or disable the permissive execution of pipes.

• void enable\_permissive\_pipes (void)

Enable the permissive execution of pipes.

void disable\_permissive\_pipes (void)

Disable the permissive execution of pipes.

## 7.18.1 Detailed Description

Function prototypes for fileopen.c.

**Author** 

Konrad Bernloehr

Date

```
CVS $Date: 2014/06/23 09:34:45 $
```

Version

```
CVS $Revision: 1.7 $
```

### 7.18.2 Function Documentation

### 7.18.2.1 addexepath()

Add a path to the list of execution paths, if not already there.

The path name is always copied to a newly allocated memory location. This path name can actually be a colon-separated list, as for initexepath().

References addpath(), root\_exe\_path, and root\_path.

### 7.18.2.2 addpath()

Add a path to the list of include paths, if not already there.

The path name is always copied to a newly allocated memory location. This path name can actually be a colon-separated list, as for initpath(). Also environment variables (indicated by starting with '\$', e.g. "\$HOME") are accepted (and may expand into colon-separated list) but no mixed expansion (like "\$HOME/bin").

References getword(), incpath::next, incpath::path, root\_path, and verbose.

Referenced by addexepath().

### 7.18.2.3 disable\_permissive\_pipes()

Disable the permissive execution of pipes.

References freeexepath(), and freepath().

Referenced by set\_permissive\_pipes().

### 7.18.2.4 enable\_permissive\_pipes()

Enable the permissive execution of pipes.

Referenced by set permissive pipes().

### 7.18.2.5 fileclose()

```
int fileclose ( FILE * f )
```

Close a file or fifo but not if it is one of the standard streams.

References verbose.

Referenced by read\_eventio\_registry(), and write\_all\_histograms().

## 7.18.2.6 fileopen()

```
FILE* fileopen (  \mbox{const char} \ * \ fname, \\ \mbox{const char} \ * \ mode \ )
```

Search for a file in the include path list and open it if possible.

References exe\_popen(), initpath(), incpath::path, root\_path, ssh\_popen(), uri\_popen(), and verbose.

Referenced by check\_autoload\_trgmask(), init\_atmprof(), read\_eventio\_registry(), and write\_all\_histograms().

## 7.18.2.7 initpath()

Init the path list, with default\_path as the only entry.

References freepath(), and verbose.

Referenced by fileopen().

### 7.18.2.8 listpath()

Show the list of include paths.

References incpath::next, and incpath::path.

## 7.18.2.9 set\_permissive\_pipes()

```
void set_permissive_pipes ( \quad \text{ int } p \ )
```

Enable or disable the permissive execution of pipes.

References disable\_permissive\_pipes(), and enable\_permissive\_pipes().


## 7.19 gen\_lookup.c File Reference

Generate image shape and energy lookups for user analysis in read\_hess.

```
#include "initial.h"
#include "io_basic.h"
#include "histogram.h"
#include "io_histogram.h"
```

#include "fileopen.h"

Include dependency graph for gen\_lookup.c:



### **Functions**

- · void fill\_gaps ()
  - Fill gaps in those histograms used for generating the lookups.
- void gen\_image\_lookups ()

Generate the lookups for image shape parameters and energy.

- void fill\_ebias\_correction (void)
- void syntax (char \*prgm)
- int main (int argc, char \*\*argv)

### **Variables**

- HISTOGRAM \* h18000
- HISTOGRAM \* h18001
- HISTOGRAM \* h18011
- HISTOGRAM \* h18012
- HISTOGRAM \* h18021
- HISTOGRAM \* h18022
- HISTOGRAM \* h18051
- HISTOGRAM \* h18052
- HISTOGRAM \* h18100
- HISTOGRAM \* h18101
- HISTOGRAM \* h18111
- HISTOGRAM \* **h18112**
- HISTOGRAM \* h18121
- HISTOGRAM \* h18122
- HISTOGRAM \* h18151
   HISTOGRAM \* h18152
- HISTOGRAM \* h18113
- HISTOGRAM \* h18114

- HISTOGRAM \* h18123
- HISTOGRAM \* h18124
- HISTOGRAM \* h18140
- HISTOGRAM \* h18141
- HISTOGRAM \* h18153
- HISTOGRAM \* h18154
- HISTOGRAM \* h18005
- HISTOGRAM \* h18006
- HISTOGRAM \* h18071
- HISTOGRAM \* h18072
- HISTOGRAM \* h18081
- HISTOGRAM \* h18082
- HISTOGRAM \* h18105
- HISTOGRAM \* h18106
- HISTOGRAM \* h18171
- · IIIOTOGITAW \* IIIOT7 I
- HISTOGRAM \* h18172
   HISTOGRAM \* h18181
- .....
- HISTOGRAM \* h18182
- HISTOGRAM \* **h18173**
- HISTOGRAM \* h18174
- HISTOGRAM \* h18183
- HISTOGRAM \* h18184
   HISTOGRAM \* h18200
- \* 111010011AW \* 1110200
- HISTOGRAM \* h18201
   HISTOGRAM \* h18211
- HISTOGRAM \* h18212
- HISTOGRAM \* h18301
- HISTOGRAM \* h18311
- HISTOGRAM \* h18321
- HISTOGRAM \* h18322

### 7.19.1 Detailed Description

Generate image shape and energy lookups for user analysis in read\_hess.

Read\_hess must be run with user analysis once and the generated histogram file is used by this program to generate the lookups. The lookup file is used in the next round of read\_hess user analysis, if found under the desired name. Look at the last lines of output from read\_hess (or at the beginning, right after the history) to see how the lookup file should be called (depends on tail cut parameters, and so on).

## Date

```
CVS $Revision: 1.21 $
```

## Version

```
CVS $Date: 2012/05/11 13:18:48 $
```

## 7.19.2 Function Documentation

```
7.19.2.1 fill_gaps()
```

```
void fill_gaps ( )
```

Fill gaps in those histograms used for generating the lookups.


Depending on the physical quantities we have different strategies for interpolation/extrapolation/smoothing.

References Histogram\_Extension::ddata, histogram::extension, fill\_histogram(), gen\_image\_lookups(), Histogram — Parameters::lower\_limit, histogram::nbins, histogram::nbins\_2d, Histogram\_Parameters::real, and Histogram\_ Parameters::upper\_limit.

## 7.20 gen\_trgmask.c File Reference

A utility program for fixing problems with simulation data which does not have the correct bit pattern of telescope triggers but the correct pattern can be extracted from the log files.

```
#include "initial.h"
#include "io_basic.h"
#include "fileopen.h"
#include "io_trgmask.h"
Include dependency graph for gen_trgmask.c:
```



### **Functions**

- void syntax (char \*prgname)
- int main (int argc, char \*\*argv)

### 7.20.1 Detailed Description

A utility program for fixing problems with simulation data which does not have the correct bit pattern of telescope triggers but the correct pattern can be extracted from the log files.

```
Syntax: bin/gen_trgmask log-file [ trgmask-file ] or: bin/gen_trgmask -1 trgmask-file

The first variant will create a file with a single data block for the trigger mask patterns recovered from the log file.

The default file name is derived with extension .trgmask.gz

Note that only data for one run per file is supported.

The second variant will list the contents of such a file.
```


@author Konrad Bernloehr

## 7.21 hconfig.c File Reference

Configuration control and procedure call interface.

```
#include "initial.h"
#include "io_basic.h"
#include <ctype.h>
#include "warning.h"
#include <errno.h>
#include <strings.h>
#include "hconfig.h"
#include "history.h"
```

Include dependency graph for hconfig.c:



### **Data Structures**

- struct ConfigBlockStruct

  Configuration is organized in sections.
- · struct config\_specific\_data
- struct Binary\_Interface\_Chain

### **Macros**

- #define **get\_config\_specific**() (&config\_defaults)
- #define TMP\_FORMAT "cfg%d.tmp"

## **Typedefs**

typedef struct ConfigBlockStruct CONFIG\_BLOCK

### **Functions**

static int do\_config (CONFIG\_ITEM \*item, CONST char \*line)

Internal configuration function.

- static void config syntax error (const char \*name, const char \*text)
- static void config\_info (const char \*name, const char \*text)
- static int set\_config\_values (CONFIG\_ITEM \*item, int first, int last, char \*text)

Set configuration values (internal usage only).

static void display config current (CONFIG ITEM \*item)

Display current values of a single configuration item (internal usage only).

static void display\_config\_item (CONFIG\_ITEM \*item)

Display a single configuration item (internal usage only).

- static int do reset func (const char \*text)
- static int signed\_config\_val (const char \*name, const char \*text, const char \*lbound, const char \*ubound, int strict, long \*ival)
- static int unsigned\_config\_val (const char \*name, const char \*text, const char \*lbound, const char \*ubound, int strict, unsigned long \*uval)
- static int **hex\_config\_val** (const char \*name, const char \*text, const char \*lbound, const char \*ubound, int strict, unsigned long \*uval)
- static int **real\_config\_val** (const char \*name, const char \*text, const char \*lbound, const char \*ubound, int strict, double \*rval)
- static int f\_show\_config (const char \*name, CONFIG\_VALUES \*val)

Display the current configuration status (internal usage only).

- static int f lock config (const char \*name, CONFIG VALUES \*val)
- static int f unlock config (const char \*name, CONFIG VALUES \*val)
- static int f\_limit\_config (const char \*name, CONFIG\_VALUES \*val)
- static int f\_status\_config (const char \*name, CONFIG\_VALUES \*val)
- static int f\_list\_config (const char \*name, CONFIG\_VALUES \*val)
- static int f\_get\_config (const char \*name, CONFIG\_VALUES \*val)
- static int f\_echo (const char \*name, CONFIG\_VALUES \*val)
- static int f\_warning (const char \*name, CONFIG\_VALUES \*val)
- static int f\_error (const char \*name, CONFIG\_VALUES \*val)
- static int save\_config\_values (CONFIG\_ITEM \*item, int first, int last)
- static int restore\_config\_values (CONFIG\_ITEM \*item, int first, int last)
- int build\_config (CONFIG\_ITEM \*items, const char \*section)

Build up the configuration by adding another section of configuration definitions.

int init\_config (char \*(\*fptr)(void))

Initialize the configuration after all build\_config() calls.

void unhook internal ()

Disable access to internal functions via configuration.

void rehook\_internal ()

Enable access again to internal functions via configuration.

int reload\_config (char \*(\*fptr)(void))

Reload some configuration using the file name/preprocessor as set up for init\_config() or with different file etc.

CONFIG\_ITEM \* find\_config\_item (const char \*name)

Find a configuration item by its name (mainly for internal usage).

- int verify\_config\_section (char \*section)
- int set\_config\_history (PFITI fptr)

Set a function for recording the history of the configuration settings.

• int reconfig (char \*text)

Modify the configuration after init\_config() has been called.

- static int lock unlock status (const char \*name, int lock)
- int is\_signed\_number (const char \*text)

- int is\_unsigned\_number (const char \*text)
- int is\_hex\_number (const char \*text)
- int is\_bin\_number (const char \*text)
- unsigned long decode bin number (const char \*text)
- int is real number (const char \*text)
- void set\_config\_filename (const char \*fname)

Set the name of the configuration file to be read by the function read\_config\_lines().

• char \* get\_config\_filename ()

Return the current value of the configuration file name.

void set\_config\_preprocessor (char \*preproc)

Set the command name and options of a preprocessor for configuration files to be read by function read\_config\_clines().

char \* get\_config\_preprocessor ()

Return the current value of the configuration preprocessor.

void set\_config\_stack (char \*\*stack)

Set a list of configuration lines to be processed before any lines from a file are read by read\_config\_lines().

char \* read\_config\_lines ()

Read configuration data from a file and return it line by line to the calling function (one line per call).

int read config status ()

Return the status of reading a configuration file with read\_config\_lines() in a preceding call to init\_config().

int define\_config\_binary\_interface (int item\_type, size\_t elem\_size, void \*(\*new\_func)(int nelem, int item type), int(\*delete\_func)(void \*ptr, int nelem, int item\_type), int(\*read\_func)(void \*bin\_item, IO\_BUFFER \*iobuf, int item\_type), int(\*write\_func)(void \*bin\_item, IO\_BUFFER \*iobuf, int item\_type), int(\*readtext\_tofunc)(void \*bin\_item, char \*text, int item\_type), int(\*list\_func)(void \*bin\_item, int item\_type), int(\*copy\_tofunc)(void \*bin\_item\_to, void \*bin\_item\_from, int io\_type))

Define a binary interface for an I/O type.

• struct Config\_Binary\_Item\_Interface \* find\_config\_binary\_interface (int item\_type)

Find the matching binary interface for given item type.

### **Variables**

static CONFIG ITEM default config []

Internal functions of the hoonfig package.

- static CONFIG\_BLOCK first\_config\_block
- static int internal\_unhooked = 0
- static PFITI history\_function
- · int config level
- static struct config\_specific\_data config\_defaults
- static struct Binary\_Interface\_Chain \* bin\_chain\_root
- static char cfg\_fname [1024]
- static char preprocessor [4096] = ""
- static char \*\* cfg\_stack
- · static int read status

### 7.21.1 Detailed Description

Configuration control and procedure call interface.

**Author** 

Konrad Bernloehr

Date

Date

2018/05/11 11:54:29

Version

Revision

1.21

This is the module controlling all configuration except that a function has to be supplied that collects input line for line. Most functions in this file are for internal use only and are given a 'static' modifier. The only functions to be called by the user are

```
build_config()
init_config()
reconfig().
```

In order to set up the configuration, one or several calls to build\_config() should be done, each with a list of 'configuration items' ('CONFIG\_ITEM \*items') terminated by a NULL\_CONFIG\_ITEM as an end marker. The list must be of 'static' or global/'extern' type and none of its entries must be modified by the user in any way, once they have been passed to build\_config.

Such a list might look like the following example:

The components of each item are:

- 1) The name, consisting of letters, digits, and '\_'. In external data the items are referenced by their name which may be abbreviated and is case-insensitive. However, the name used for the definition is case-sensitive in the current implementation. The first lowercase letter indicates the minimum length of accepted abbrevations. In the example above "ANY\_Numbers" may be abbreviated as "any\_n", "any\_nu", and so on, "DYnAllocArray" as "dy", "dyn", and so on. It is the user's responsibility the avoid conflicts of the accepted abbreviations of any two items.
- 2) The type which may be an abbreviation of one of the following:
   "Character", "Short", "Integer", "Long" (signed integer types),
   "UCharacter", "UShort", "UInteger, "ULong" (unsigned types)
   "FLoat", "Real", "Double" (floating point, "Real" == "Double"),
   "Text" (simple text, character string),
   "FUnction" (a function reference, not a data reference).

```
3) The number of data element. Must be -1 for "FUnction" type.
    The terminating ' \setminus 0' in characters strings should be included.
 4) A data pointer of any type. Must be NULL for "FUnction type.
    If the data should be dynamically allocated by the configuration
    software it should be a pointer to the pointer that should
    be set. Allocated data is initialized with '0's.
 5) A function pointer. Must not be NULL except for "FUnction" type
    and is optional (may be NULL) for data type entries.
    For the "Function" type, the data (normally a character string)
    is passed as the only argument. For data type entries,
    the associated functions are called with an extended
    calling syntax.
 6) A pointer to a character string with the default initialization
    values or NULL.
 7) A pointer to a character string with a lower bound value or NULL.
 8) A pointer to a character string with an upper bound value or NULL.
 9) An integer where any of the following flags may be combined
    by a bitwise OR '|':
       CFG_REQUIRE_DATA
       CFG_REQUIRE_ALL_DATA
       CFG_REJECT_MODIFICATION
10) Reserved. In multi_threaded mode, use
       CFG_MUTEX(&some_pthread_mutex)
    if the associated function is not fully reentrant or
    if a set of functions should only be called one at a time.
11) Reserved. Do not modify. Is 1 if reconfigured.
```

Components not specified are automatically initialized to NULL or 0.

The reason why build\_config may be called several times (with different configuration items each time) is that this way the configuration items for each more or less independent part of a program may be defined separately and there is no need for global data sharing. You only need to call a 'configuration definition function' for each part which has its items defined and only calls build\_config().

Once the whole configuration items from all parts have been passed to build\_config(), a single call to init\_config() is required to make the configuration effective. init\_config() first sets those initial values declared in the items (if any) and then tries to get external data line by line from a function passed to init\_config(), unless a NULL pointer is passed instead of a function pointer. This user-defined function (declared 'char \*user\_function(void);') should return the address of the first character of each line read from a configuration file, the command line, or anywhere else, until the end of input which the function must indicate by returning a NULL pointer. Input lines can be of any length up to 10240 bytes and may include a linefeed character as read by fgets(). Note that there used to be a problem with semicolons in comments, which should be fixed now - but beware of possible side-effects.

Later, configuration data can be changed by calling reconfig() with a line of input passed as argument. Configuration data marked as 'not to be modified' will not be changed. If a configuration item is of 'function' type that function will be called with the remaining line (after extracting the item name and processing special characters) passed as argument.

#### 7.21.2 Function Documentation

#### 7.21.2.1 build\_config()

Build up the configuration by adding another section of configuration definitions.

### **Parameters**

items	Vector of configuration items, which is terminated by a NULL_CONFIG_ITEM
section	Name of this configuration section.

### Returns

0 (O.k.), -1 (memory allocation failed), -2 (other error)

# 7.21.2.2 find\_config\_item()

Find a configuration item by its name (mainly for internal usage).

### **Parameters**

name	Item name or block:name
------	-------------------------

### Returns

Pointer to (first) configuration item found or NULL.

# 7.21.2.3 get\_config\_filename()

Return the current value of the configuration file name.

# **Parameters**



# Returns

pointer to static file name string

### 7.21.2.4 get\_config\_preprocessor()

Return the current value of the configuration preprocessor.

#### **Parameters**

```
- (none)
```

#### Returns

pointer to static command string

# 7.21.2.5 init\_config()

Initialize the configuration after all build\_config() calls.

Initialize the configuration after all sections have been supplied via <a href="build\_config">build\_config</a>(). A function may be specified for reading external configuration data after the internal specifications have been processed. This function may be called only once.

#### **Parameters**

fptr

Pointer to function that returns a string pointer as long as external configuration data is available, and NULL when no more data is available. fptr may be NULL if no such function should be called.

#### Returns

0 (O.k.), -1 (called a second time or invalid configuration data)

# 7.21.2.6 read\_config\_lines()

Read configuration data from a file and return it line by line to the calling function (one line per call).

A NULL pointer is returned on end-of-file. This function is intended to be used as the usual 'fptr' argument for init\_config().

### **Parameters**

_	(none)
---	--------

# Returns

Pointer to character string or NULL.

### 7.21.2.7 read\_config\_status()

Return the status of reading a configuration file with read\_config\_lines() in a preceding call to init\_config().

# **Parameters**

```
- (none)
```

#### Returns

0 (o.k.), -1 (no config file set), -2 (config file open failed), -3 (preprocessing failed), -4 (read error).

# 7.21.2.8 reconfig()

Modify the configuration after init\_config() has been called.

### **Parameters**

text

String consisting of configuration keyword (separated by a blank or '=' from the rest) and the corresponding data.

# Returns

0 (O.k.), -1 (invalid or undefined configuration keyword or error in the data)

# 7.21.2.9 reload\_config()

Reload some configuration using the file name/preprocessor as set up for init\_config() or with different file etc.

#### **Parameters**

fptr

Pointer to function that returns a string pointer as long as external configuration data is available, and NULL when no more data is available.

#### Returns

0 (O.k.), -1 (invalid configuration data)

# 7.21.2.10 set\_config\_filename()

Set the name of the configuration file to be read by the function read\_config\_lines().

#### **Parameters**

fname Name of file to be used.
--------------------------------

#### Returns

(none)

# 7.21.2.11 set\_config\_history()

Set a function for recording the history of the configuration settings.

### **Parameters**

fpti

 Pointer to function of type 'int fptr(char \*text,int flag)' where 'text' is the configuration line and flag is 0 for configuration file processing and 1 for latre reconfiguration.

### Returns

0

# 7.21.2.12 set\_config\_preprocessor()

Set the command name and options of a preprocessor for configuration files to be read by function read\_config\_ lines().

The input and output file names will be appended to the command string set by this function.

### **Parameters**

```
preproc Command string
```

### Returns

(none)

# 7.21.2.13 set\_config\_stack()

Set a list of configuration lines to be processed before any lines from a file are read by read\_config\_lines().

# **Parameters**

stack	Pointer to NULL terminated vector of strings.
-------	---

### Returns

(none)

# 7.21.3 Variable Documentation

# 7.21.3.1 config\_defaults

```
struct config_specific_data config_defaults [static]
```

### Initial value:

```
=
{
    "_internal_"
```

### 7.21.3.2 default\_config

```
CONFIG_ITEM default_config[] [static]
```

#### Initial value:

```
{ "SHOW", "FUN", -1, NULL, f_show_config, NULL, NULL, 0, NULL, CFG_MUTEX(mlock_hconfig) },
{ "LOCK",
           "FUN", -1, NULL, f_lock_config, NULL, NULL, NULL, O, NULL,
{ "LIMITS", "FUN", -1, NULL, f_limit_config, NULL, NULL, NULL, 0, NULL,
"FUN", -1, NULL, f_list_config, NULL, NULL, NULL, 0, NULL,
   CFG_MUTEX(mlock_hconfig) },
{ "GET", "FUN", -1, NULL, I
CFG_MUTEX(mlock_hconfig) },
           "FUN", -1, NULL, f_get_config, NULL, NULL, NULL, 0, NULL,
{ "ECHO", "FUN", -1, NULL, f_echo, CFG_MUTEX(mlock_hconfig) }, 
{ "WARNING", "FUN", -1, NULL, f_warning,
                                            NULL, NULL, NULL, 0, NULL,
                                            NULL, NULL, NULL, 0, NULL,
   CFG_MUTEX(mlock_hconfig) },
{ "ERROR", "FUN", -1, NULL, f_error,
    CFG_MUTEX(mlock_hconfig) },
                                          NULL, NULL, NULL, 0, NULL,
{ NULL_CONFIG_ITEM }
```

Internal functions of the hconfig package.

### 7.21.3.3 first\_config\_block

```
CONFIG_BLOCK first_config_block [static]
```

### Initial value:


```
= 
{ "_internal_", default_config, (CONFIG_BLOCK *) NULL, 0 }
```

# 7.22 hconfig.h File Reference


Declare hoonfig structures and functions.

```
#include "initial.h"
#include "io_basic.h"
```

Include dependency graph for hconfig.h:



This graph shows which files directly or indirectly include this file:



# **Data Structures**

· union ConfigDataPointer

This union of pointers allows convenient access of various types of data.

· union ConfigBoundary

Configuration value may have optional lower and/or upper bounds.

struct ConfigValues

Configuration values and supporting data passed to user functions.

struct Config\_Binary\_Item\_Interface

Interface definitions for binary-only items.

struct ConfigIntern

Configuration elements used only internally.

struct ConfigItemStruct

Configuration as used in definitions of configuration blocks.

### **Macros**

- #define NO INITIAL MACROS 1
- #define \_XSTR\_(s) \_STR\_(s)

Expand a macro first and then enclose in string.

#define \_STR\_(s) #s

Enclose in string without macro expansion.

- #define CONST const
- #define IO\_TYPE\_HCONFIG\_ENVELOPE 900
- #define IO TYPE HCONFIG NAME 901
- #define IO\_TYPE\_HCONFIG\_TEXT 902
- #define IO\_TYPE\_HCONFIG\_INDEX 903
- #define IO\_TYPE\_HCONFIG\_NUMBERS 904
- #define CFG\_REQUIRE\_DATA 1
- #define CFG\_REQUIRE\_ALL\_DATA 2
- #define CFG\_REJECT\_MODIFICATION 4
- #define CFG\_HARD\_BOUND 8
- #define CFG STRICT BOUND 16
- #define CFG\_INITIALIZED 32
- #define CFG ALL INITIALIZED 64
- #define CFG NOT INITIAL 128
- #define NULL\_CONFIG\_ITEM (char \*) NULL, (char \*) NULL, 0, NULL, NULL, (char \*) NULL, (char \*) NULL, (char \*) NULL, 0, NULL, NULL, NULL, {0}
- #define CFG\_MUTEX(mutex) (NULL)

Mutexes are only inserted when pthreads are used.

# **Typedefs**

- typedef void \*(\* PFVP) (char \*, char \*, int)
- typedef int(\* PFISI) (char \*, int)
- typedef int(\* PFITI) (const char \*, int)
- typedef int(\* PFISS) (char \*, char \*)
- typedef struct ConfigValues CONFIG VALUES
- typedef int(\* PFIX) (const char \*name, CONFIG VALUES \*val)
- typedef struct ConfigItemStruct CONFIG\_ITEM

#### **Functions**

int build\_config (CONFIG\_ITEM \*items, const char \*section)

Build up the configuration by adding another section of configuration definitions.

int init config (char \*(\*fptr)(void))

Initialize the configuration after all build\_config() calls.

· void unhook internal (void)

Disable access to internal functions via configuration.

void rehook internal (void)

Enable access again to internal functions via configuration.

int reload\_config (char \*(\*fptr)(void))

Reload some configuration using the file name/preprocessor as set up for init config() or with different file etc.

- void \* config\_alloc\_data (char \*name, char \*type, int size)
- int reconfig (char \*text)

Modify the configuration after init\_config() has been called.

- int verify\_config\_section (char \*section)
- int set\_config\_history (PFITI fptr)

Set a function for recording the history of the configuration settings.

void set\_config\_filename (const char \*fname)

Set the name of the configuration file to be read by the function read\_config\_lines().

char \* get config filename (void)

Return the current value of the configuration file name.

void set\_config\_preprocessor (char \*preproc)

Set the command name and options of a preprocessor for configuration files to be read by function read\_config\_
lines().

• char \* get\_config\_preprocessor (void)

Return the current value of the configuration preprocessor.

void set\_config\_stack (char \*\*stack)

Set a list of configuration lines to be processed before any lines from a file are read by read\_config\_lines().

• char \* read config lines (void)

Read configuration data from a file and return it line by line to the calling function (one line per call).

int read\_config\_status (void)

Return the status of reading a configuration file with read\_config\_lines() in a preceding call to init\_config().

CONFIG ITEM \* find config item (const char \*name)

Find a configuration item by its name (mainly for internal usage).

int define\_config\_binary\_interface (int item\_type, size\_t elem\_size, void \*(\*new\_func)(int nelem, int item type), int(\*delete\_func)(void \*ptr, int nelem, int item\_type), int(\*read\_func)(void \*bin\_item, IO\_BUFFER \*iobuf, int item\_type), int(\*write\_func)(void \*bin\_item, IO\_BUFFER \*iobuf, int item\_type), int(\*readtext\_content func)(void \*bin\_item, char \*text, int item\_type), int(\*list\_func)(void \*bin\_item, int item\_type), int(\*copy\_content func)(void \*bin\_item\_to, void \*bin\_item\_from, int io\_type))

Define a binary interface for an I/O type.

struct Config\_Binary\_Item\_Interface \* find\_config\_binary\_interface (int item\_type)

Find the matching binary interface for given item type.

- int reconfig binary (char \*buffer, size t buflen)
- int config\_binary\_read\_text (IO\_BUFFER \*iobuf, char \*name, int maxlen)

Get a hoonfig name or text item from an I/O buffer.

- int is\_signed\_number (const char \*text)
- int is\_unsigned\_number (const char \*text)
- int is\_hex\_number (const char \*text)
- int is\_bin\_number (const char \*text)
- int is\_real\_number (const char \*text)
- unsigned long decode bin number (const char \*text)
- int abbrev (CONST char \*s, CONST char \*t)

Compare strings s and t.

• int getword (CONST char \*s, int \*spos, char \*word, int maxlen, char blank, char endchar)

Copies a blank or '\0' or < endchar > delimeted word from position \*spos of the string s to the string word and increment \*spos to the position of the first non-blank character after the word.

int config binary read index (IO BUFFER \*iobuf, int \*nidx, int \*idx low, int \*idx high, int max idx)

Get a list of index ranges for binary hconfig data following.

• int config binary write name (IO BUFFER \*iobuf, char \*name)

Write the name of a hoonfig item for which binary data should follow.

int config binary write text (IO BUFFER \*iobuf, char \*text)

Write 'binary' hconfig data as text (for 'string' or 'function' types).

• int config\_binary\_text\_length (IO\_BUFFER \*iobuf)

If the next item is of the text type, get the length of the text.

int config binary read name (IO BUFFER \*iobuf, char \*name, int maxlen)

Is the same as config\_binary\_read\_text().

int config\_binary\_write\_index (IO\_BUFFER \*iobuf, int nidx, int \*idx\_low, int \*idx\_high)

Put a list of index ranges for binary hconfig data following.

• int config\_binary\_envelope\_begin (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*item\_header)

Begin with the envelope for a binary configuration item.

int config\_binary\_envelope\_end (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*item\_header)

Close the envelope for a binary configuration item.

int config\_binary\_inquire\_numbers (IO\_BUFFER \*iobuf, int \*ntype, int \*nsize, int32\_t \*num, int \*nopt)

Tell me what kind of binary numbers follow in the next I/O item.

• int config binary read numbers (IO BUFFER \*iobuf, void \*data, size t max size)

Get the binary numbers from the next I/O item.

• int config\_binary\_convert\_data (void \*out, int out\_type, int out\_size, void \*in, int in\_type, int in\_size)

Concert binary numbers of one type to numbers of another type.

# 7.22.1 Detailed Description

Declare hconfig structures and functions.

**Author** 

Konrad Bernloehr

Date

**CVS** 

Date

2017/08/02 13:29:04

Version

CVS

Revision

1.8

# 7.22.2 Macro Definition Documentation

```
7.22.2.1 _STR_
```

```
#define _STR_( s ) #s
```

Enclose in string without macro expansion.

# 7.22.2.2 CFG\_MUTEX

Mutexes are only inserted when pthreads are used.

In the multi-threaded variant: the address of the given mutex. In the single-threaded variant: a null pointer.

# 7.22.3 Function Documentation

# 7.22.3.1 abbrev()

```
int abbrev (  {\tt CONST\ char\ *\ s,}   {\tt CONST\ char\ *\ t\ )}
```

Compare strings s and t.

s may be an abbreviation of t. Upper/lower case in s is ignored. s has to be at least as long as the leading upper case, digit, and '\_' part of t.

#### **Parameters**

s	The string to be checked.
t	The test string with minimum part in upper case.

#### Returns

1 if s is an abbreviation of t, 0 if not.

### 7.22.3.2 build\_config()

Build up the configuration by adding another section of configuration definitions.

#### **Parameters**

items	Vector of configuration items, which is terminated by a NULL_CONFIG_ITEM
section	Name of this configuration section.

### Returns

```
0 (O.k.), -1 (memory allocation failed), -2 (other error)
```

# 7.22.3.3 config\_binary\_convert\_data()

```
int config_binary_convert_data (
    void * out,
    int out_type,
    int out_size,
    void * in,
    int in_type,
    int in_size )
```

Concert binary numbers of one type to numbers of another type.

Supported types are signed integers of various lengths, unsigned integers of various lengths, float and double. The signed and unsigned integers can be 1, 2, 4 or perhaps 8 bytes long. Float should be 4 bytes long, double 8 bytes.

### 7.22.3.4 config\_binary\_read\_text()

Get a hconfig name or text item from an I/O buffer.

Both the IO\_TYPE\_HCONFIG\_NAME and IO\_TYPE\_HCONFIG\_TEXT eventio item types are simple text strings enclosed in an I/O item. Because either of them can appear at the beginning of binary configuration data (with different interpretations) they are distinguished by different item type numbers. Otherwise they are the same.

Referenced by config\_binary\_read\_name().

### 7.22.3.5 config\_binary\_text\_length()

If the next item is of the text type, get the length of the text.

This allows finding out the length of the text first, allocating enough memory to read it and then start reading the text.

### Returns

The length of the string not including the trailing '\0' which has to be appended.

### 7.22.3.6 config\_binary\_write\_name()

Write the name of a hoonfig item for which binary data should follow.

Calls config\_binary\_write\_as\_text().

# 7.22.3.7 config\_binary\_write\_text()

Write 'binary' hconfig data as text (for 'string' or 'function' types).

Calls config\_binary\_write\_as\_text().

# 7.22.3.8 find\_config\_item()

Find a configuration item by its name (mainly for internal usage).

# **Parameters**

### Returns

Pointer to (first) configuration item found or NULL.

# 7.22.3.9 get\_config\_filename()

Return the current value of the configuration file name.

### **Parameters**

```
- (none)
```

# Returns

pointer to static file name string

# 7.22.3.10 get\_config\_preprocessor()

Return the current value of the configuration preprocessor.

### **Parameters**

```
- (none)
```

### Returns

pointer to static command string

### 7.22.3.11 getword()

```
char blank,
char endchar )
```

Copies a blank or '\0' or < endchar > delimeted word from position \*spos of the string s to the string word and increment \*spos to the position of the first non-blank character after the word.

The word must have a length less than or equal to maxlen.

#### **Parameters**

s	string with any number of words.
spos	position in the string where we start and end.
word	the extracted word.
maxlen	the maximum allowed length of word.
blank	has the same effect as ' ', i.e. end-of-word.
endchar	his terminates the whole string ( as '\0' ).

#### Returns

-2: Invalid string or NULL -1: The word was longer than maxlen (without the terminating '\0'); 0: There were no more words in the string s. 1: ok, we have a word and there are still more of them in the string s. 2: ok, but this was the last word

Referenced by addpath(), and user\_set\_tel\_type\_param\_by\_str().

# 7.22.3.12 init\_config()

Initialize the configuration after all build\_config() calls.

Initialize the configuration after all sections have been supplied via <a href="build\_config">build\_config</a>(). A function may be specified for reading external configuration data after the internal specifications have been processed. This function may be called only once.

#### **Parameters**

fptr Pointer to function that returns a string pointer as long as external configuration data is available, and NULL when no more data is available. fptr may be NULL if no such function should be called.

#### Returns

0 (O.k.), -1 (called a second time or invalid configuration data)

### 7.22.3.13 read\_config\_lines()

Read configuration data from a file and return it line by line to the calling function (one line per call).

A NULL pointer is returned on end-of-file. This function is intended to be used as the usual 'fptr' argument for init\_config().

### **Parameters**



### Returns

Pointer to character string or NULL.

### 7.22.3.14 read\_config\_status()

Return the status of reading a configuration file with read\_config\_lines() in a preceding call to init\_config().

# **Parameters**

```
- (none)
```

#### Returns

0 (o.k.), -1 (no config file set), -2 (config file open failed), -3 (preprocessing failed), -4 (read error).

# 7.22.3.15 reconfig()

Modify the configuration after init config() has been called.

# **Parameters**

text String consisting of configuration keyword (separated by a blank or '=' from the rest) and the corresponding data.

#### Returns

0 (O.k.), -1 (invalid or undefined configuration keyword or error in the data)

# 7.22.3.16 reload\_config()

```
int reload_config ( {\tt char \ *(*)\ (void)\ } \ fptr\ )
```

Reload some configuration using the file name/preprocessor as set up for init config() or with different file etc.

### **Parameters**

fptr

Pointer to function that returns a string pointer as long as external configuration data is available, and NULL when no more data is available.

### Returns

0 (O.k.), -1 (invalid configuration data)

# 7.22.3.17 set\_config\_filename()

Set the name of the configuration file to be read by the function read\_config\_lines().

# **Parameters**

fname	Name of file to be used.
-------	--------------------------

# Returns

(none)

# 7.22.3.18 set\_config\_history()

Set a function for recording the history of the configuration settings.

### **Parameters**

fptr

– Pointer to function of type 'int fptr(char \*text,int flag)' where 'text' is the configuration line and flag is 0 for configuration file processing and 1 for latre reconfiguration.

#### Returns

0

# 7.22.3.19 set\_config\_preprocessor()

Set the command name and options of a preprocessor for configuration files to be read by function read\_config\_clines().

The input and output file names will be appended to the command string set by this function.

#### **Parameters**

preproc	Command string
---------	----------------

# Returns

(none)

### 7.22.3.20 set\_config\_stack()

Set a list of configuration lines to be processed before any lines from a file are read by read\_config\_lines().

# **Parameters**

stack Pointer to NULL terminated vector of strings.

# Returns

(none)

# 7.23 hessio\_doc.h File Reference

Add an introduction to doxygen-generated documentation.

# 7.23.1 Detailed Description

Add an introduction to doxygen-generated documentation.


This file is not included during compilation.

# 7.24 histogram.c File Reference

Manage, fill, and display one- and two-dimensional histograms.

```
#include "initial.h"
#include "histogram.h"
#include "warning.h"
```

Include dependency graph for histogram.c:



# **Macros**

- #define \_HLOCK\_
- #define \_HUNLOCK\_
- #define \_WAIT\_IF\_BUSY\_(histo)
- #define \_CLEAR\_BUSY\_(histo)
- #define **HistOutput**(a)

#### **Functions**

static void initialize\_histogram (HISTOGRAM \*histo)

For internal purpose only.

• static HISTOGRAM \* aux\_alloc\_histogram (int ncounts, const char \*type)

For internal purpose only.

static void free\_histo\_contents (HISTOGRAM \*histo)

Free the contents (data pointers) of a histogram to be released or removed.

static void display\_2d\_histogram (HISTOGRAM \*histo)

Display contents of a 2D histogram.

- void histogram lock (HISTOGRAM \*histo)
- void histogram unlock (HISTOGRAM \*histo)
- HISTOGRAM \* get\_first\_histogram ()

Get a pointer to the first histogram.

void sort\_histograms ()

Sort histograms in linked list by idents.

void set first histogram (HISTOGRAM \*new first histogram)

Set a new histogram as the first element (context switching).

HISTOGRAM \* get histogram by ident (long ident)

Get a histogram with the given ID.

void list\_histograms (long ident)

List all available histograms using the 'Output()' function.

 HISTOGRAM \* book\_histogram (long id, const char \*title, const char \*type, int dimension, double \*low, double \*high, int \*nbins)

General histogram booking function, assigning ID and title.

HISTOGRAM \* book\_1d\_histogram (long id, const char \*title, const char \*type, double low, double high, int nbins)

Simplified histogram booking function for one-dimensional histograms, assigning ID and title.

- HISTOGRAM \* book\_int\_histogram (long id, const char \*title, int dimension, long \*low, long \*high, int \*nbins)

  Book and integer-type histogram (content incremented by one per entry).
- HISTOGRAM \* allocate\_histogram (const char \*type, int dimension, double \*low, double \*high, int \*nbins)

  \*\*Allocate any histogram without ID and title.
- HISTOGRAM \* alloc\_int\_histogram (long low, long high, int nbins)

Allocate memory for a 1-D 'int' histogram and initialize it.

• HISTOGRAM \* alloc real histogram (double low, double high, int nbins)

Allocate memory for a 1-D 'real' histogram and initialize it.

• HISTOGRAM \* alloc\_2d\_int\_histogram (long xlow, long xhigh, int nxbins, long ylow, long yhigh, int nybins)

Allocate memory for a 2-D 'int' histogram and initialize it.

HISTOGRAM \* alloc\_2d\_real\_histogram (double xlow, double xhigh, int nxbins, double ylow, double yhigh, int nybins)

Allocate memory for a 2-D 'int' histogram and initialize it.

void describe\_histogram (HISTOGRAM \*histo, const char \*title, long ident)

Add a describing title to a histogram previously allocated.

void clear\_histogram (HISTOGRAM \*histo)

Initialize an existing histogram.

void free histogram (HISTOGRAM \*histo)

Free a histogram completely (both data and control structure).

· void free\_all\_histograms ()

Deletes all histograms which are included in the linked list of histograms.

void unlink\_histogram (HISTOGRAM \*histo)

Remove a histogram from the list without destroying it.

int fill\_int\_histogram (HISTOGRAM \*histo, long value)

Increment a bin of a 1-D 'int' histogram by one.

• int fill real histogram (HISTOGRAM \*histo, double value)

Increment a bin of a 1-D 'real' histogram by one.

int fill\_weighted\_histogram (HISTOGRAM \*histo, double value, double weight)

Add an entry to a weighted 1-D histogram.

int fill\_2d\_int\_histogram (HISTOGRAM \*histo, long xvalue, long yvalue)

Increment a bin of a 2-D 'int' histogram by one.

• int fill\_2d\_real\_histogram (HISTOGRAM \*histo, double xvalue, double yvalue)

Increment a bin of a 2-D 'real' histogram by one.

int fill\_2d\_weighted\_histogram (HISTOGRAM \*histo, double xvalue, double yvalue, double weight)

Add an entry to a weighted 2-D histogram.

• int fill\_histogram (HISTOGRAM \*histo, double xvalue, double yvalue, double weight)

Fill any type of 1-D or 2-D histogram known by its pointer.

• int fill\_histogram\_by\_ident (long id, double xvalue, double yvalue, double weight)

Fill any type of 1-D or 2-D histogram known by its ID number.

• int histogram\_matching (HISTOGRAM \*histo1, HISTOGRAM \*histo2)

Check if two histograms have exactly matching definitions (same type, dimension, size, ranges).

HISTOGRAM \* add\_histogram (HISTOGRAM \*histo1, HISTOGRAM \*histo2)

Add a second histogram to a first one.

int stat histogram (HISTOGRAM \*histo, struct histstat \*stbuf)

Statistical analysis of a histogram.

double locate histogram fraction (HISTOGRAM \*histo, double fraction)

Locate point of arbitrary fraction of entries (quantile).

• int fast stat histogram (HISTOGRAM \*histo, struct histstat \*stbuf)

Fast and basic histogram statistics.

void print\_histogram (HISTOGRAM \*histo)

Print contents of a histogram on the terminal.

void display\_histogram (HISTOGRAM \*histo)

Display contents of a histogram on the terminal.

void display\_all\_histograms ()

Display all histograms in list of histograms.

• int histogram to lookup (HISTOGRAM \*histo, HISTOGRAM \*lookup)

Convert a histogram to a lookup table by integrating the histogram.

long lookup\_int (HISTOGRAM \*lookup, long value, long factor)

Look up a table created from an integer histogram.

• double lookup\_real (HISTOGRAM \*lookup, double value, double factor)

Look up a table created from an 'real' histogram.

int histogram\_hashing (int tabsize)

Turn hashing of histograms (using their ident as key) on or off.

#### **Variables**

- static HISTOGRAM \* first\_histogram = (HISTOGRAM \*) NULL
- static HISTOGRAM \* last\_histogram = (HISTOGRAM \*) NULL
- FILE \* histogram\_file
- static HISTOGRAM \*\* hash\_table
- static long hash size = 0
- static CONST QUAL short primetab []
- static CONST QUAL int zero = 0

# 7.24.1 Detailed Description

Manage, fill, and display one- and two-dimensional histograms.

Eventio routines for these types of histograms are available in io\_histogram.c. Conversion to HBOOK format is available through the hdata2hbook (was cvt2) program. Conversion to ROOT format is available through the hdata2root (was cvt3) program.

Note: multi-threading safety of functions provided in this file has not been tested extensively. Threads must not delete histograms shared with other threads when referenced by pointers.

**Author** 

Konrad Bernloehr

Date

1991 - 2010 CVS

Date

2014/02/20 10:53:06

Version

**CVS** 

Revision

1.21

### 7.24.2 Macro Definition Documentation

#### 7.24.2.1 HistOutput

```
#define HistOutput( a )
```

### Value:

```
do { if ( histogram_file == (FILE *) NULL ) \
    Output(a); \
    else \
        fputs(a, histogram_file); } while(zero)
```

# 7.24.3 Function Documentation

### 7.24.3.1 add\_histogram()

Add a second histogram to a first one.

The histograms must exactly match in their definitions. The first histogram will be modified, the second is unchanged.

### **Parameters**

histo1	pointer to first histogram
histo2	pointer to second histogram

# Returns

NULL pointer indicates failure.

# 7.24.3.2 alloc\_2d\_int\_histogram()

Allocate memory for a 2-D 'int' histogram and initialize it.

Resulting histogram has integer range limits and integer contents (incremented by one per entry).

### **Parameters**

xlow	lower limit of values in X to be covered by histogram
xhigh	upper limit
nxbins	the number of bins to be allocated in X
ylow	lower limit of values in Y to be covered by histogram
yhigh	upper limit
nybins	the number of bins to be allocated in Y

# Returns

pointer to allocated histogram or NULL

References aux\_alloc\_histogram().

# 7.24.3.3 alloc\_2d\_real\_histogram()

```
double yhigh,
int nybins )
```

Allocate memory for a 2-D 'int' histogram and initialize it.

Resulting histogram has floating point range limits and integer contents (incremented by one per entry).

### **Parameters**

xlow	lower limit of values in X to be covered by histogram
xhigh	upper limit
nxbins	the number of bins to be allocated in X
ylow	lower limit of values in Y to be covered by histogram
yhigh	upper limit
nybins	the number of bins to be allocated in Y

### Returns

pointer to allocated histogram or NULL

References allocate\_histogram().

# 7.24.3.4 alloc\_int\_histogram()

Allocate memory for a 1-D 'int' histogram and initialize it.

Resulting histogram has integer range limits and integer contents (incremented by one per entry).

# **Parameters**

low	lower limit of values to be covered by histogram
high	upper limit
nbins	the number of bins to be allocated

# Returns

pointer to allocated histogram or NULL

References aux\_alloc\_histogram().

### 7.24.3.5 alloc\_real\_histogram()

Allocate memory for a 1-D 'real' histogram and initialize it.

Resulting histogram has floating point range limits and integer contents (incremented by one per entry).

### **Parameters**

low	lower limit of values to be covered by histogram	
high	upper limit	
nbins	the number of bins to be allocated	

#### Returns

pointer to allocated histogram or NULL

References allocate\_histogram().

### 7.24.3.6 allocate\_histogram()

Allocate any histogram without ID and title.

Allocate a histogram of 1 or 2 dimensions, 'I', 'R', 'F' or 'D' type, without assigning an ID number and title string to it. To avoid the (long) <-> (double) typecasts, the direct calls to alloc\_int\_histogram() and alloc\_2d\_int\_histogram() are recommended for integer-limits histograms (type 'I').

### **Parameters**

type	"I" (int, no weights), "R" (real, no weights), "F" (float, with weights), "D" (double, w.w.)
dimension	1 or 2 for 1-D or 2-D histogram
low	Pointer to lower limits (x or x,y for 1-D or 2-D)
high	Pointer to upper limits
nbins	Pointer to no. of bins per dimension (nx or nx, ny)

# Returns

Pointer to new histogram or NULL

Referenced by alloc\_2d\_real\_histogram(), alloc\_real\_histogram(), book\_1d\_histogram(), and book\_histogram().

#### 7.24.3.7 book\_1d\_histogram()

```
HISTOGRAM* book_ld_histogram (

long id,

const char * title,

const char * type,

double low,

double high,

int nbins )
```

Simplified histogram booking function for one-dimensional histograms, assigning ID and title.

Book a histogram of one dimension, 'I', 'R', 'F', or 'D' type. The histogram is allocated (if possible) and the supplied ID number and title string are assigned.

#### **Parameters**

id	ID number
title	Histogram title string
type	"I" (int, no weights), "R" (real, no weights), "F" (float, with weights), "D" (double, w.w.)
low	Lower limit (x)
high	Upper limit (x)
nbins	No. of bins (nx)

#### Returns

Pointer to new histogram or NULL

References allocate\_histogram(), and describe\_histogram().

# 7.24.3.8 book\_histogram()

General histogram booking function, assigning ID and title.

Book a histogram of 1 or 2 dimensions, 'I', 'R', 'F', or 'D' type. The histogram is allocated (if possible) and the supplied ID number and title string are assigned.

### **Parameters**

id	ID number
title	Histogram title string
type	"I" (int, no weights), "R" (real, no weights), "F" (float, with weights), "D" (double, w.w.)
dimension	1 or 2 for 1-D or 2-D histogram
low	Pointer to lower limits (x or x,y for 1-D or 2-D)
high	Pointer to upper limits
nbins	Pointer to no. of bins per dimension (nx or nx, ny)

# Returns

Pointer to new histogram or NULL

References allocate\_histogram(), and describe\_histogram().

# 7.24.3.9 book\_int\_histogram()

Book and integer-type histogram (content incremented by one per entry).

Like book\_histogram() but for 'I' type histograms only (1-D or 2-D)

# **Parameters**

id	ID number
title	Histogram title string
dimension	1 or 2 for 1-D or 2-D histogram
low	Pointer to lower limits (x or x,y for 1-D or 2-D)
high	Pointer to upper limits
nbins	Pointer to no. of bins per dimension (nx or nx, ny)

# Returns

Pointer to new histogram or NULL

# 7.24.3.10 clear\_histogram()

```
void clear_histogram (
          HISTOGRAM * histo )
```

Initialize an existing histogram.

#### **Parameters**

```
histo – pointer to histogram
```

### Returns

(none)

Referenced by gen\_image\_lookups(), and write\_dst\_histos().

# 7.24.3.11 describe\_histogram()

```
void describe_histogram (
          HISTOGRAM * histo,
          const char * title,
          long ident )
```

Add a describing title to a histogram previously allocated.

#### **Parameters**

histo	Histogram to which the title should be added
title	The title string. This is ignored if the histogram already has a title.
ident	Identification number, must be unique (or 0) if any I/O is intended, because read_histogram() deletes a pre-existing histogram with the same ID.

# Returns

none

Referenced by book\_1d\_histogram(), and book\_histogram().

# 7.24.3.12 display\_2d\_histogram()

```
static void display_2d_histogram ( {\tt HISTOGRAM * histo} \;) \; \; [{\tt static}]
```

Display contents of a 2D histogram.

Called by display\_histogram().

The histogram has already been checked by display\_histogram() and its title has been printed.

### **Parameters**

```
histo - Pointer to histogram
```

# Returns

(none)

References histogram::counts, Histogram\_Extension::ddata, histogram::extension, Histogram\_Extension::fdata, histogram::nbins, histogram::nbins\_2d, and histogram::type.

# 7.24.3.13 display\_all\_histograms()

Display all histograms in list of histograms.

Arguments: none

Return value: none

# 7.24.3.14 display\_histogram()

```
void display_histogram ( {\tt HISTOGRAM * histo} \ )
```

Display contents of a histogram on the terminal.

This is a simple 'HPRINT' type display on one screen.

### **Parameters**

histo	Pointer to histogram

### Returns

(none)

References histogram::counts, histogram::extension, histogram::nbins, histogram::tentries, and histogram::type.

# 7.24.3.15 fast\_stat\_histogram()

```
int fast_stat_histogram (
          HISTOGRAM * histo,
          struct histstat * stbuf )
```

Fast and basic histogram statistics.

Compute mean and truncated mean for histogram. For this kind of histogram analysis actually no histogram is required. A 'moments' structure would be sufficient.

### **Parameters**

histo	pointer to histogram (1-D)
stbuf	pointer to histogram statistics structure

### Returns

Nonzero result indicates failure

References histogram::nbins 2d, histogram::tentries, and histogram::type.

# 7.24.3.16 fill\_2d\_int\_histogram()

Increment a bin of a 2-D 'int' histogram by one.

Increment a bin of a 2-D histogram by one. Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

Arguments: histo – pointer to histogram xvalue, yvalue – X and Y positions where an entry is to be to the histogram (they may be outside the given ranges)

Return value: 0 (o.k.), -1 (no histogram that can be filled)

References fill\_2d\_real\_histogram(), fill\_int\_histogram(), histogram::nbins\_2d, and histogram::type.

# 7.24.3.17 fill\_2d\_real\_histogram()

Increment a bin of a 2-D 'real' histogram by one.

Increment a bin of a 2-D histogram by one. Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

### **Parameters**

histo	Pointer to histogram
xvalue	X position where an entry is to be to the histogram (may be outside the given ranges)
yvalue	Y position where an entry is to be to the histogram (may be outside the given ranges)

### Returns

```
0 (o.k.), -1 (no histogram that can be filled)
```

References fill\_2d\_weighted\_histogram(), fill\_real\_histogram(), histogram::nbins\_2d, and histogram::type.

Referenced by fill\_2d\_int\_histogram().

### 7.24.3.18 fill\_2d\_weighted\_histogram()

Add an entry to a weighted 2-D histogram.

Increment a bin of a 2-D histogram by a given weight rather than by 1. This requires a suitable histogram type 'F' or 'D'.

# **Parameters**

histo	Pointer to histogram.
xvalue	X posistion where an entry is to be added.
yvalue	Y posistion where an entry is to be added.
weight	The weight of that entry.

### Returns

```
0 (o.k.), -1 (no histogram that can be filled with weights)
```

References histogram::ident, and histogram::type.

Referenced by fill\_2d\_real\_histogram().

# 7.24.3.19 fill\_histogram()

```
double xvalue,
double yvalue,
double weight )
```

Fill any type of 1-D or 2-D histogram known by its pointer.

Generic histogram fill function that can be used for type 'I', 'R', 'F', and 'D' histograms, although it is not recommended for type 'I' histograms, due to type conversions.

#### **Parameters**

histo	Pointer to histogram.
xvalue	X posistion where an entry is to be added.
yvalue	Y posistion (ignored for 1-D histograms)
weight	The weight of that entry (must be 1.0 for 'I' and 'R' type histograms).

# Returns

```
0 (o.k.), -1 (no histogram that can be filled)
```

References histogram::ident, and histogram::type.

Referenced by fill gaps(), and gen image lookups().

# 7.24.3.20 fill\_histogram\_by\_ident()

Fill any type of 1-D or 2-D histogram known by its ID number.

Generic histogram fill function that can be used for type 'I', 'R', 'F', and 'D' histograms, although it is not recommended for type 'I' histograms, due to type conversions.

### **Parameters**

id	Identifier number of the histogram.
xvalue	X posistion where an entry is to be added.
yvalue	Y posistion (ignored for 1-D histograms)
weight	The weight of that entry (must be 1.0 for 'I' and 'R' type histograms).

# Returns

```
0 (o.k.), -1 (no histogram that can be filled)
```

Referenced by user\_mc\_event\_fill().

### 7.24.3.21 fill\_int\_histogram()

Increment a bin of a 1-D 'int' histogram by one.

Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

#### **Parameters**

histo	Pointer to histogram
value	Position where an entry is to be added (may be outside the given range)

### Returns

```
0 (o.k.), -1 (no histogram that can be filled)
```

References fill\_real\_histogram(), and histogram::type.

Referenced by fill\_2d\_int\_histogram().

# 7.24.3.22 fill\_real\_histogram()

Increment a bin of a 1-D 'real' histogram by one.

Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

# Parameters

histo	Pointer to histogram
value	Position where an entry is to be added (may be outside the given range)

#### Returns

```
0 (o.k.), -1 (no histogram that can be filled)
```

References fill\_weighted\_histogram(), and histogram::type.

Referenced by fill\_2d\_real\_histogram(), and fill\_int\_histogram().

### 7.24.3.23 fill\_weighted\_histogram()

Add an entry to a weighted 1-D histogram.

Increment a bin of a histogram by a given weight rather than by 1. This requires a suitable histogram type 'F' or 'D'.

#### **Parameters**

histo	Pointer to histogram.
value	Position where an entry is to be added.
weight	The weight of that entry.

### Returns

```
0 (o.k.), -1 (no histogram that can be filled with weights)
```

References histogram::ident, and histogram::type.

Referenced by fill\_real\_histogram().

# 7.24.3.24 free\_all\_histograms()

Deletes all histograms which are included in the linked list of histograms.

# Returns

(none)

# 7.24.3.25 free\_histo\_contents()

Free the contents (data pointers) of a histogram to be released or removed.

#### **Parameters**

Pointer	to histogram that should be 'cleaned'.

#### Returns

(none)

References histogram::counts, Histogram\_Extension::ddata, histogram::extension, Histogram\_Extension::fdata, and histogram::title.

### 7.24.3.26 free\_histogram()

```
void free_histogram (
          HISTOGRAM * histo )
```

Free a histogram completely (both data and control structure).

Deallocates memory previously allocated to a histogram. If release\_histogram was applied to that histogram before, it cannot be reallocated.

#### **Parameters**

```
histo – pointer to previously allocated histogram
```

#### Returns

(none)

# 7.24.3.27 get\_first\_histogram()

Get a pointer to the first histogram.

Get a pointer to the first histogram in the linked list of available histograms without making the corresponding variable global.

# Returns

Pointer to the first histogram in the linked list.

Referenced by convert\_histograms\_to\_root(), write\_all\_histograms(), and write\_histograms().

# 7.24.3.28 get\_histogram\_by\_ident()

Get a histogram with the given ID.

Get the first histogram with a given ident (different from 0) or return NULL pointer if none exists.

#### **Parameters**

```
ident – The histogram ident to be searched for.
```

#### Returns

Histogram pointer or NULL

Referenced by histogram\_to\_root(), and write\_dst\_histos().

### 7.24.3.29 histogram\_hashing()

```
int histogram_hashing ( int \ tabsize \ )
```

Turn hashing of histograms (using their ident as key) on or off.

#### **Parameters**

tabsize Minimum number of elements in hashing table or 0 if hash table should be released (max: 15000).

### Returns

```
0 (o.k.), -1 (error)
```

## 7.24.3.30 histogram\_matching()

Check if two histograms have exactly matching definitions (same type, dimension, size, ranges).

#### **Parameters**

histo1	pointer to first histogram
histo2	pointer to second histogram

## Returns

```
0 (not matching) or 1 (matching)
```

References histogram::counts, histogram::extension, Histogram\_Parameters::integer, Histogram\_Parameters::lower\_limit, histogram::nbins, histogram::nbins\_2d, Histogram\_Parameters::real, histogram::type, and Histogram:\_Parameters::upper\_limit.

### 7.24.3.31 histogram\_to\_lookup()

Convert a histogram to a lookup table by integrating the histogram.

#### **Parameters**

histo	input histogram
lookup	output lookup table

### Returns

0 if ok or -1 for failure

## 7.24.3.32 list\_histograms()

List all available histograms using the 'Output()' function.

#### **Parameters**

ident	- histogram ident to search or 0
-------	----------------------------------

## Returns

(none)

### 7.24.3.33 locate\_histogram\_fraction()

Locate point of arbitrary fraction of entries (quantile).

Locate the place in a 1-D histogram where a given fraction of the entries is to the 'left' of this place ('I' and 'R' type only).

#### **Parameters**

histo	Pointer to histogram
fraction	Fraction of entries to the left.

### Returns

x-coordinate of given fraction or 0. for error.

### 7.24.3.34 lookup\_int()

```
long lookup_int (
            HISTOGRAM * lookup,
             long value,
             long factor )
```

Look up a table created from an integer histogram.

#### **Parameters**

lookup	the lookup table
value	the value at which to look up
factor	the scaling factor of the lookup result or 0

### Returns

If 'value' is inside the range of the lookup table (that is the range of the histogram from which the lookup table was created), a value between 0 and 'factor' (or the number of entries in the range, if factor==0) is returned.

References histogram::counts, Histogram\_Parameters::integer, Histogram\_Parameters::lower\_limit, histogram ← ::nbins, histogram::nbins\_2d, histogram::tentries, histogram::type, Histogram\_Parameters::upper\_limit, and Histogram\_Parameters::width.

## 7.24.3.35 lookup\_real()

```
double lookup_real (
             HISTOGRAM * lookup,
             double value,
             double factor )
```

Look up a table created from an 'real' histogram.

## **Parameters**

lookup	the lookup table
value	the value at which to look up
factor	the scaling factor of the lookup result or 0

ienerated by Doxygen

#### Returns

If 'value' is inside the range of the lookup table (that is the range of the histogram from which the lookup table was created), a value between 0 and 'factor' (or the number of entries in the range, if factor==0) is returned.

References histogram::counts, Histogram\_Parameters::inverse\_binwidth, Histogram\_Parameters::lower\_limit, histogram::nbins, histogram::nbins\_2d, Histogram\_Parameters::real, histogram::tentries, histogram::type, and Histogram\_Parameters::upper\_limit.

#### 7.24.3.36 print\_histogram()

Print contents of a histogram on the terminal.

Showing the actual content of each bin.

#### **Parameters**

histo	Pointer to histogram
-------	----------------------

#### Returns

(none)

References histogram::counts, histogram::extension, Histogram\_Parameters::integer, Histogram\_Parameters::lower\_limit, histogram::nbins, Histogram\_Parameters::real, histogram::tentries, histogram::type, and Histogram:-Parameters::upper\_limit.

### 7.24.3.37 set\_first\_histogram()

Set a new histogram as the first element (context switching).

To allow 'context switching' of histograms the first element of the linked list of histograms can be changed by this function. Before that, the old value should be obtained with <a href="mailto:get\_first\_histogram">get\_first\_histogram</a>() and saved. Note: For context switching it is not necessary to specify the actually first member of a linked list but any member of a list can be specifed to activate that list.

new_first_histogram	A histogram in the new list (may be NULL pointer).
---------------------	--

Returns

none

### 7.24.3.38 sort\_histograms()

```
void sort_histograms (
     void )
```

Sort histograms in linked list by idents.

Returns

(none)

### 7.24.3.39 stat\_histogram()

```
int stat_histogram (
          HISTOGRAM * histo,
          struct histstat * stbuf )
```

Statistical analysis of a histogram.

The median calculation is implemented for 1-D 'I' and 'R' types histograms only.

### **Parameters**

histo	pointer to histogram
stbuf	pointer to histogram statistics structure

### Returns

Nonzero result indicates failure

## 7.24.3.40 unlink\_histogram()

Remove a histogram from the list without destroying it.

Remove a histogram from the linked list of histograms. That histogram will therefore not be found by any subsequent call to 'free\_all\_histograms()', display\_all\_histograms()', and 'get\_histogram\_by\_ident()'.

#### **Parameters**

histo	Pointer to histogram.
-------	-----------------------

### Returns

(none)

### 7.24.4 Variable Documentation

## 7.24.4.1 primetab

```
CONST_QUAL short primetab[] [static]
```


#### Initial value:

```
= { 131, 233, 353, 541, 751, 1051, 1367, 1511, 1723, 1931, 2393, 3163, 3907, 5261, 6143, 7187, 8623, 9749, 11321, 15031 }
```


# 7.25 histogram.h File Reference

Declarations for handling one- and two-dimensional histograms.

```
#include "initial.h"
Include dependency graph for histogram.h:
```



This graph shows which files directly or indirectly include this file:



#### **Data Structures**

· union Histogram\_Parameters

Parameters defining the usable range of coordinates.

• struct Histogram\_Extension

A histogram extension only allocated for weighted histograms.

· struct histogram

A complete 1-D or 2-D histogram with control and data elements.

· struct histstat

Statistics element for histogram analysis.

· struct momstat

First, second, and higher moments of a 1-D histogram.

· struct moments

Numbers to be summed up to obtain the moments.

#### **Macros**

- #define MAX\_HISTCOUNT 4294967295UL /\* or ULONG\_MAX from <limits.h>\*/

### **Typedefs**

• typedef double HISTVALUE\_REAL

May be 'float' for ANSI C compiler.

typedef long HISTVALUE\_INT

Short int is not recommended.

typedef unsigned long HISTCOUNT

The histogram counts may be unsigned short or unsigned long.

typedef double HISTSUM REAL

To avoid loss of precision for adding many numbers, sums are of double type if 'real' type HISTVALUEs are used.

- · typedef long HISTSUM INT
- typedef double HISTSTATVALUE
- · typedef struct histogram HISTOGRAM
- · typedef struct moments MOMENTS

### **Functions**

- void histogram\_lock (HISTOGRAM \*histo)
- void histogram\_unlock (HISTOGRAM \*histo)
- HISTOGRAM \* get\_first\_histogram (void)

Get a pointer to the first histogram.

void set\_first\_histogram (HISTOGRAM \*new\_first\_histogram)

Set a new histogram as the first element (context switching).

HISTOGRAM \* get\_histogram\_by\_ident (long ident)

Get a histogram with the given ID.

void list\_histograms (long ident)

List all available histograms using the 'Output()' function.

 HISTOGRAM \* book\_histogram (long id, const char \*title, const char \*type, int dimension, double \*low, double \*high, int \*nbins)

General histogram booking function, assigning ID and title.

• HISTOGRAM \* book\_int\_histogram (long id, const char \*title, int dimension, long \*low, long \*high, int \*nbins)

Book and integer-type histogram (content incremented by one per entry).

 HISTOGRAM \* book\_1d\_histogram (long id, const char \*title, const char \*type, double low, double high, int nbins)

Simplified histogram booking function for one-dimensional histograms, assigning ID and title.

• HISTOGRAM \* allocate\_histogram (const char \*type, int dimension, double \*low, double \*high, int \*nbins)

\*\*Allocate any histogram without ID and title.

• HISTOGRAM \* alloc\_int\_histogram (long low, long high, int nbins)

Allocate memory for a 1-D 'int' histogram and initialize it.

HISTOGRAM \* alloc\_real\_histogram (double low, double high, int nbins)

Allocate memory for a 1-D 'real' histogram and initialize it.

• HISTOGRAM \* alloc\_2d\_int\_histogram (long xlow, long xhigh, int nxbins, long ylow, long yhigh, int nybins)

Allocate memory for a 2-D 'int' histogram and initialize it.

HISTOGRAM \* alloc\_2d\_real\_histogram (double xlow, double xhigh, int nxbins, double ylow, double yhigh, int nybins)

Allocate memory for a 2-D 'int' histogram and initialize it.

void describe\_histogram (HISTOGRAM \*histo, const char \*title, long ident)

Add a describing title to a histogram previously allocated.

void clear histogram (HISTOGRAM \*histo)

Initialize an existing histogram.

void free\_histogram (HISTOGRAM \*histo)

Free a histogram completely (both data and control structure).

void free\_all\_histograms (void)

Deletes all histograms which are included in the linked list of histograms.

void unlink histogram (HISTOGRAM \*histo)

Remove a histogram from the list without destroying it.

• int fill int histogram (HISTOGRAM \*histo, long value)

Increment a bin of a 1-D 'int' histogram by one.

int fill\_real\_histogram (HISTOGRAM \*histo, double value)

Increment a bin of a 1-D 'real' histogram by one.

int fill weighted histogram (HISTOGRAM \*histo, double value, double weight)

Add an entry to a weighted 1-D histogram.

• int fill\_2d\_int\_histogram (HISTOGRAM \*histo, long xvalue, long yvalue)

Increment a bin of a 2-D 'int' histogram by one.

• int fill\_2d\_real\_histogram (HISTOGRAM \*histo, double xvalue, double yvalue)

Increment a bin of a 2-D 'real' histogram by one.

• int fill\_2d\_weighted\_histogram (HISTOGRAM \*histo, double xvalue, double yvalue, double weight)

Add an entry to a weighted 2-D histogram.

int fill\_histogram (HISTOGRAM \*histo, double xvalue, double yvalue, double weight)

Fill any type of 1-D or 2-D histogram known by its pointer.

• int fill histogram by ident (long id, double xvalue, double yvalue, double weight)

Fill any type of 1-D or 2-D histogram known by its ID number.

int stat\_histogram (HISTOGRAM \*histo, struct histstat \*stbuf)

Statistical analysis of a histogram.

• double locate histogram fraction (HISTOGRAM \*histo, double fraction)

Locate point of arbitrary fraction of entries (quantile).

int fast\_stat\_histogram (HISTOGRAM \*histo, struct histstat \*stbuf)

Fast and basic histogram statistics.

int histogram matching (HISTOGRAM \*histo1, HISTOGRAM \*histo2)

Check if two histograms have exactly matching definitions (same type, dimension, size, ranges).

HISTOGRAM \* add\_histogram (HISTOGRAM \*histo1, HISTOGRAM \*histo2)

Add a second histogram to a first one.

void print\_histogram (HISTOGRAM \*histo)

Print contents of a histogram on the terminal.

void display histogram (HISTOGRAM \*histo)

Display contents of a histogram on the terminal.

void display\_all\_histograms (void)

Display all histograms in list of histograms.

int histogram\_to\_lookup (HISTOGRAM \*histo, HISTOGRAM \*lookup)

Convert a histogram to a lookup table by integrating the histogram.

long lookup\_int (HISTOGRAM \*lookup, long value, long factor)

Look up a table created from an integer histogram.

double lookup real (HISTOGRAM \*lookup, double value, double factor)

Look up a table created from an 'real' histogram.

int histogram\_hashing (int tabsize)

Turn hashing of histograms (using their ident as key) on or off.

void sort histograms (void)

Sort histograms in linked list by idents.

- void release\_histogram (HISTOGRAM \*histo)
- MOMENTS \* alloc moments (double low, double high)

Allocate a structure for sums of powers of data.

void clear\_moments (MOMENTS \*mom)

Initialize an existing moments structure (except for its range limits).

void free\_moments (MOMENTS \*mom)

Deallocates memory previously allocated to a moments structure.

void fill\_moments (MOMENTS \*mom, double value)

Add up those things needed to compute mean, standard deviation, skewness, and kurtosis (both for all data and separately for data in a range defined in alloc\_moments().

• void fill\_mean (MOMENTS \*mom, double value)

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc moments().

• void fill\_mean\_and\_sigma (MOMENTS \*mom, double value)

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc\_moments().

• void fill\_real\_moments (MOMENTS \*mom, double value, double weight)

Add up those things needed to compute – mean, – standard deviation, – skewness, and – kurtosis (both for all data and separately for data in a range defined in alloc\_moments().

void fill\_real\_mean (MOMENTS \*mom, double value, double weight)

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc moments().

• void fill\_real\_mean\_and\_sigma (MOMENTS \*mom, double value, double weight)

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc\_moments().

• int stat\_moments (MOMENTS \*mom, struct momstat \*stmom)

Calculate moments (mean, rms, skewness, kurtosis) from the sums of powers of data values.

### 7.25.1 Detailed Description

Declarations for handling one- and two-dimensional histograms.

The functions to work with these histograms is found in histogram.c . Eventio routines are available in io\_ histogram.c and conversion to HBOOK format is available through the 'cvt2' program. Handling of moments of a 1-D distribution is implemented in moments.c .

**Author** 

Konrad Bernloehr

Date

1991 - 2010 CVS

Date

2013/10/21 12:53:31

Version

CVS

Revision

1.12

## 7.25.2 Typedef Documentation

## 7.25.2.1 HISTCOUNT

```
typedef unsigned long HISTCOUNT
```

The histogram counts may be unsigned short or unsigned long.

With a unsigned short the overflow of a bin might easily happen.

7.25.2.2 HISTVALUE\_REAL

```
typedef double HISTVALUE_REAL
```

May be 'float' for ANSI C compiler.

HISTVALUE may be either an 'integer' type (recommended: long int) or a 'real' type (recommended: double). The method of calculating the array index corresponding to a given value is somewhat different for these two alternatives. Using a float for the 'real' type instead of a double would make no difference. However, a short int or an unsigned short int as 'integer' type requires more care for the calculation of the array index compared to a long or a unsigned long (frequent overflows unless a type cast of intermediate values to a long type is used).

### 7.25.3 Function Documentation

## 7.25.3.1 add\_histogram()

Add a second histogram to a first one.

The histograms must exactly match in their definitions. The first histogram will be modified, the second is unchanged.

### **Parameters**

histo1	pointer to first histogram
histo2	pointer to second histogram

#### Returns

NULL pointer indicates failure.

### 7.25.3.2 alloc\_2d\_int\_histogram()

Allocate memory for a 2-D 'int' histogram and initialize it.

Resulting histogram has integer range limits and integer contents (incremented by one per entry).

xlow	lower limit of values in X to be covered by histogram
xhigh	upper limit
nxbins	the number of bins to be allocated in X
ylow	lower limit of values in Y to be covered by histogram
yhigh	upper limit
nybins	the number of bins to be allocated in Y

#### Returns

pointer to allocated histogram or NULL

References aux\_alloc\_histogram().

### 7.25.3.3 alloc\_2d\_real\_histogram()

Allocate memory for a 2-D 'int' histogram and initialize it.

Resulting histogram has floating point range limits and integer contents (incremented by one per entry).

#### **Parameters**

xlow	lower limit of values in X to be covered by histogram
xhigh	upper limit
nxbins	the number of bins to be allocated in X
ylow	lower limit of values in Y to be covered by histogram
yhigh	upper limit
nybins	the number of bins to be allocated in Y

#### Returns

pointer to allocated histogram or NULL

References allocate histogram().

### 7.25.3.4 alloc\_int\_histogram()

Allocate memory for a 1-D 'int' histogram and initialize it.

Resulting histogram has integer range limits and integer contents (incremented by one per entry).

#### **Parameters**

low	,	lower limit of values to be covered by histogram
higi	h	upper limit
nbii	ns	the number of bins to be allocated

### Returns

pointer to allocated histogram or NULL

References aux\_alloc\_histogram().

### 7.25.3.5 alloc\_moments()

Allocate a structure for sums of powers of data.

Returns NULL if no structure could be allocated.

### **Parameters**

low	Lower limit of range for truncation
high	Upper limit of range for truncation

### Returns

Pointer to allocated structure or NULL.

References clear\_moments().

## 7.25.3.6 alloc\_real\_histogram()

Allocate memory for a 1-D 'real' histogram and initialize it.

Resulting histogram has floating point range limits and integer contents (incremented by one per entry).

#### **Parameters**

	low	lower limit of values to be covered by histogram
	high	upper limit
	nbins	the number of bins to be allocated

### Returns

pointer to allocated histogram or NULL

References allocate\_histogram().

### 7.25.3.7 allocate\_histogram()

Allocate any histogram without ID and title.

Allocate a histogram of 1 or 2 dimensions, 'I', 'R', 'F' or 'D' type, without assigning an ID number and title string to it. To avoid the (long) <-> (double) typecasts, the direct calls to alloc\_int\_histogram() and alloc\_2d\_int\_histogram() are recommended for integer-limits histograms (type 'I').

## **Parameters**

type	"I" (int, no weights), "R" (real, no weights), "F" (float, with weights), "D" (double, w.w.)
dimension	1 or 2 for 1-D or 2-D histogram
low	Pointer to lower limits (x or x,y for 1-D or 2-D)
high	Pointer to upper limits
nbins	Pointer to no. of bins per dimension (nx or nx, ny)

#### Returns

Pointer to new histogram or NULL

Referenced by alloc\_2d\_real\_histogram(), alloc\_real\_histogram(), book\_1d\_histogram(), and book\_histogram().

## 7.25.3.8 book\_1d\_histogram()

```
const char * title,
const char * type,
double low,
double high,
int nbins )
```

Simplified histogram booking function for one-dimensional histograms, assigning ID and title.

Book a histogram of one dimension, 'I', 'R', 'F', or 'D' type. The histogram is allocated (if possible) and the supplied ID number and title string are assigned.

#### **Parameters**

id	ID number
title	Histogram title string
type	"I" (int, no weights), "R" (real, no weights), "F" (float, with weights), "D" (double, w.w.)
low	Lower limit (x)
high	Upper limit (x)
nbins	No. of bins (nx)

#### Returns

Pointer to new histogram or NULL

References allocate\_histogram(), and describe\_histogram().

#### 7.25.3.9 book\_histogram()

```
HISTOGRAM* book_histogram (
long id,
const char * title,
const char * type,
int dimension,
double * low,
double * high,
int * nbins )
```

General histogram booking function, assigning ID and title.

Book a histogram of 1 or 2 dimensions, 'I', 'R', 'F', or 'D' type. The histogram is allocated (if possible) and the supplied ID number and title string are assigned.

id	ID number
title	Histogram title string
type	"I" (int, no weights), "R" (real, no weights), "F" (float, with weights), "D" (double, w.w.)
dimension	1 or 2 for 1-D or 2-D histogram
low	Pointer to lower limits (x or x,y for 1-D or 2-D)
high	Pointer to upper limits
nbins	Pointer to no. of bins per dimension (nx or nx, ny)

#### Returns

Pointer to new histogram or NULL

References allocate\_histogram(), and describe\_histogram().

## 7.25.3.10 book\_int\_histogram()

Book and integer-type histogram (content incremented by one per entry).

Like book\_histogram() but for 'I' type histograms only (1-D or 2-D)

#### **Parameters**

id	ID number
title	Histogram title string
dimension	1 or 2 for 1-D or 2-D histogram
low	Pointer to lower limits (x or x,y for 1-D or 2-D)
high	Pointer to upper limits
nbins	Pointer to no. of bins per dimension (nx or nx, ny)

#### Returns

Pointer to new histogram or NULL

## 7.25.3.11 clear\_histogram()

Initialize an existing histogram.

ı

#### Returns

(none)

Referenced by gen\_image\_lookups(), and write\_dst\_histos().

### 7.25.3.12 clear\_moments()

Initialize an existing moments structure (except for its range limits).

### **Parameters**

```
mom Pointer to moments structure
```

Referenced by alloc\_moments().

## 7.25.3.13 describe\_histogram()

```
void describe_histogram (
     HISTOGRAM * histo,
     const char * title,
     long ident )
```

Add a describing title to a histogram previously allocated.

### **Parameters**

histo	Histogram to which the title should be added
title	The title string. This is ignored if the histogram already has a title.
ident	Identification number, must be unique (or 0) if any I/O is intended, because read_histogram() deletes a
	pre-existing histogram with the same ID.

### Returns

none

Referenced by book\_1d\_histogram(), and book\_histogram().

### 7.25.3.14 display\_all\_histograms()

Display all histograms in list of histograms.

Arguments: none

Return value: none

### 7.25.3.15 display\_histogram()

Display contents of a histogram on the terminal.

This is a simple 'HPRINT' type display on one screen.

#### **Parameters**

histo	Pointer to histogram
-------	----------------------

### Returns

(none)

References histogram::counts, histogram::extension, histogram::nbins, histogram::tentries, and histogram::type.

## 7.25.3.16 fast\_stat\_histogram()

```
int fast_stat_histogram (
     HISTOGRAM * histo,
     struct histstat * stbuf )
```

Fast and basic histogram statistics.

Compute mean and truncated mean for histogram. For this kind of histogram analysis actually no histogram is required. A 'moments' structure would be sufficient.

histo	pointer to histogram (1-D)
stbuf	pointer to histogram statistics structure

#### Returns

Nonzero result indicates failure

References histogram::nbins\_2d, histogram::tentries, and histogram::type.

## 7.25.3.17 fill\_2d\_int\_histogram()

Increment a bin of a 2-D 'int' histogram by one.

Increment a bin of a 2-D histogram by one. Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

Arguments: histo – pointer to histogram xvalue, yvalue – X and Y positions where an entry is to be to the histogram (they may be outside the given ranges)

Return value: 0 (o.k.), -1 (no histogram that can be filled)

References fill\_2d\_real\_histogram(), fill\_int\_histogram(), histogram::nbins\_2d, and histogram::type.

### 7.25.3.18 fill\_2d\_real\_histogram()

Increment a bin of a 2-D 'real' histogram by one.

Increment a bin of a 2-D histogram by one. Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

#### **Parameters**

histo	Pointer to histogram
xvalue	X position where an entry is to be to the histogram (may be outside the given ranges)
yvalue	Y position where an entry is to be to the histogram (may be outside the given ranges)

### Returns

0 (o.k.), -1 (no histogram that can be filled)

References fill\_2d\_weighted\_histogram(), fill\_real\_histogram(), histogram::nbins\_2d, and histogram::type.

Referenced by fill\_2d\_int\_histogram().

#### 7.25.3.19 fill\_2d\_weighted\_histogram()

Add an entry to a weighted 2-D histogram.

Increment a bin of a 2-D histogram by a given weight rather than by 1. This requires a suitable histogram type 'F' or 'D'.

#### **Parameters**

histo	Pointer to histogram.
xvalue	X posistion where an entry is to be added.
yvalue	Y posistion where an entry is to be added.
weight	The weight of that entry.

### Returns

```
0 (o.k.), -1 (no histogram that can be filled with weights)
```

References histogram::ident, and histogram::type.

Referenced by fill\_2d\_real\_histogram().

### 7.25.3.20 fill\_histogram()

```
int fill_histogram (
          HISTOGRAM * histo,
          double xvalue,
          double yvalue,
          double weight )
```

Fill any type of 1-D or 2-D histogram known by its pointer.

Generic histogram fill function that can be used for type 'I', 'R', 'F', and 'D' histograms, although it is not recommended for type 'I' histograms, due to type conversions.

## **Parameters**

histo	Pointer to histogram.	
xvalue	X posistion where an entry is to be added.	<del> </del>
yvalue	Y posistion (ignored for 1-D histograms)	]
weight	The weight of that entry (must be 1.0 for 'I' and 'R' type histograms).	

Generated by Doxygen

#### Returns

```
0 (o.k.), -1 (no histogram that can be filled)
```

References histogram::ident, and histogram::type.

Referenced by fill\_gaps(), and gen\_image\_lookups().

### 7.25.3.21 fill\_histogram\_by\_ident()

Fill any type of 1-D or 2-D histogram known by its ID number.

Generic histogram fill function that can be used for type 'I', 'R', 'F', and 'D' histograms, although it is not recommended for type 'I' histograms, due to type conversions.

#### **Parameters**

id	Identifier number of the histogram.
xvalue	X posistion where an entry is to be added.
yvalue	Y posistion (ignored for 1-D histograms)
weight	The weight of that entry (must be 1.0 for 'I' and 'R' type histograms).

### Returns

```
0 (o.k.), -1 (no histogram that can be filled)
```

Referenced by user\_mc\_event\_fill().

### 7.25.3.22 fill\_int\_histogram()

Increment a bin of a 1-D 'int' histogram by one.

Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

#### **Parameters**

histo Pointer to histogram	
value	Position where an entry is to be added (may be outside the given range)

#### Returns

```
0 (o.k.), -1 (no histogram that can be filled)
```

References fill\_real\_histogram(), and histogram::type.

Referenced by fill\_2d\_int\_histogram().

#### 7.25.3.23 fill\_mean()

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc\_moments().

### **Parameters**

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value

## 7.25.3.24 fill\_mean\_and\_sigma()

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc\_moments().

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value

### 7.25.3.25 fill\_moments()

Add up those things needed to compute mean, standard deviation, skewness, and kurtosis (both for all data and separately for data in a range defined in alloc moments().

#### **Parameters**

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value

#### 7.25.3.26 fill\_real\_histogram()

```
int fill_real_histogram (
          HISTOGRAM * histo,
          double value )
```

Increment a bin of a 1-D 'real' histogram by one.

Either a count for one of the bins in the histogram range is incremented or an underflow or overflow count. For the calculation of the mean value and truncated mean value sums of values and number of histogram entries are updated as well.

### **Parameters**

histo	Pointer to histogram
value	Position where an entry is to be added (may be outside the given range)

## Returns

```
0 (o.k.), -1 (no histogram that can be filled)
```

References fill weighted histogram(), and histogram::type.

Referenced by fill\_2d\_real\_histogram(), and fill\_int\_histogram().

### 7.25.3.27 fill\_real\_mean()

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc\_moments().

#### **Parameters**

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value
weight	Weighting factor of this value

## 7.25.3.28 fill\_real\_mean\_and\_sigma()

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc\_moments().

#### **Parameters**

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value
weight	Weighting factor of this value

## 7.25.3.29 fill\_real\_moments()

Add up those things needed to compute – mean, – standard deviation, – skewness, and – kurtosis (both for all data and separately for data in a range defined in alloc\_moments().

### **Parameters**

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value
weight	Weighting factor of this value

## 7.25.3.30 fill\_weighted\_histogram()

```
double value,
double weight )
```

Add an entry to a weighted 1-D histogram.

Increment a bin of a histogram by a given weight rather than by 1. This requires a suitable histogram type 'F' or 'D'.

#### **Parameters**

histo	sto Pointer to histogram.	
value	Position where an entry is to be added.	
weight	The weight of that entry.	

### Returns

```
0 (o.k.), -1 (no histogram that can be filled with weights)
```

References histogram::ident, and histogram::type.

Referenced by fill\_real\_histogram().

### 7.25.3.31 free\_all\_histograms()

Deletes all histograms which are included in the linked list of histograms.

## Returns

(none)

### 7.25.3.32 free\_histogram()

Free a histogram completely (both data and control structure).

Deallocates memory previously allocated to a histogram. If release\_histogram was applied to that histogram before, it cannot be reallocated.

	histo	<ul> <li>pointer to previously allocated histogram</li> </ul>
--	-------	---

#### Returns

(none)

### 7.25.3.33 free\_moments()

Deallocates memory previously allocated to a moments structure.

#### **Parameters**

mom Pointer to previously allocated structure

### 7.25.3.34 get\_first\_histogram()

Get a pointer to the first histogram.

Get a pointer to the first histogram in the linked list of available histograms without making the corresponding variable global.

### Returns

Pointer to the first histogram in the linked list.

Referenced by convert\_histograms\_to\_root(), write\_all\_histograms(), and write\_histograms().

### 7.25.3.35 get\_histogram\_by\_ident()

Get a histogram with the given ID.

Get the first histogram with a given ident (different from 0) or return NULL pointer if none exists.

#### **Parameters**

ident - The histogram ident to be searched for.

#### Returns

Histogram pointer or NULL

Referenced by histogram\_to\_root(), and write\_dst\_histos().

### 7.25.3.36 histogram\_hashing()

Turn hashing of histograms (using their ident as key) on or off.

#### **Parameters**

bsize Minimum number of elements in hashing table or 0 if hash table should be released (max: 15000).
---

### Returns

```
0 (o.k.), -1 (error)
```

## 7.25.3.37 histogram\_matching()

```
int histogram_matching ( {\tt HISTOGRAM * histo1,} \\ {\tt HISTOGRAM * histo2} \ )
```

Check if two histograms have exactly matching definitions (same type, dimension, size, ranges).

## **Parameters**

histo1	pointer to first histogram
histo2	pointer to second histogram

## Returns

0 (not matching) or 1 (matching)

References histogram::counts, histogram::extension, Histogram\_Parameters::integer, Histogram\_Parameters ::lower\_limit, histogram::nbins, histogram::nbins\_2d, Histogram\_Parameters::real, histogram::type, and Histogram -- Parameters::upper\_limit.

#### 7.25.3.38 histogram\_to\_lookup()

Convert a histogram to a lookup table by integrating the histogram.

### **Parameters**

histo	input histogram
lookup	output lookup table

#### Returns

0 if ok or -1 for failure

### 7.25.3.39 list\_histograms()

List all available histograms using the 'Output()' function.

#### **Parameters**

ident	- histogram ident to search or 0
-------	----------------------------------

## Returns

(none)

## 7.25.3.40 locate\_histogram\_fraction()

Locate point of arbitrary fraction of entries (quantile).

Locate the place in a 1-D histogram where a given fraction of the entries is to the 'left' of this place ('I' and 'R' type only).

#### **Parameters**

histo	Pointer to histogram
fraction	Fraction of entries to the left.

### Returns

x-coordinate of given fraction or 0. for error.

### 7.25.3.41 lookup\_int()

```
long lookup_int (
            HISTOGRAM * lookup,
             long value,
             long factor )
```

Look up a table created from an integer histogram.

#### **Parameters**

lookup	the lookup table
value	the value at which to look up
factor	the scaling factor of the lookup result or 0

## Returns

If 'value' is inside the range of the lookup table (that is the range of the histogram from which the lookup table was created), a value between 0 and 'factor' (or the number of entries in the range, if factor==0) is returned.

References histogram::counts, Histogram\_Parameters::integer, Histogram\_Parameters::lower\_limit, histogram ← ::nbins, histogram::nbins\_2d, histogram::tentries, histogram::type, Histogram\_Parameters::upper\_limit, and Histogram\_Parameters::width.

## 7.25.3.42 lookup\_real()

```
double lookup_real (
             HISTOGRAM * lookup,
             double value,
             double factor )
```

Look up a table created from an 'real' histogram.

## **Parameters**

lookup	the lookup table
value	the value at which to look up
factor	the scaling factor of the lookup result or 0

ienerated by Doxygen

#### Returns

If 'value' is inside the range of the lookup table (that is the range of the histogram from which the lookup table was created), a value between 0 and 'factor' (or the number of entries in the range, if factor==0) is returned.

References histogram::counts, Histogram\_Parameters::inverse\_binwidth, Histogram\_Parameters::lower\_limit, histogram::nbins, histogram::nbins\_2d, Histogram\_Parameters::real, histogram::tentries, histogram::type, and Histogram\_Parameters::upper\_limit.

#### 7.25.3.43 print\_histogram()

Print contents of a histogram on the terminal.

Showing the actual content of each bin.

#### **Parameters**

histo	Pointer to histogram
-------	----------------------

### Returns

(none)

References histogram::counts, histogram::extension, Histogram\_Parameters::integer, Histogram\_Parameters::lower\_limit, histogram::nbins, Histogram\_Parameters::real, histogram::tentries, histogram::type, and Histogram:-Parameters::upper\_limit.

### 7.25.3.44 set\_first\_histogram()

Set a new histogram as the first element (context switching).

To allow 'context switching' of histograms the first element of the linked list of histograms can be changed by this function. Before that, the old value should be obtained with <a href="mailto:get\_first\_histogram">get\_first\_histogram</a>() and saved. Note: For context switching it is not necessary to specify the actually first member of a linked list but any member of a list can be specifed to activate that list.

new_first_histogram   A histogram in the new list (ma	ay be NULL pointer).
---	----------------------

#### Returns

none

### 7.25.3.45 sort\_histograms()

```
void sort_histograms (
     void )
```

Sort histograms in linked list by idents.

## Returns

(none)

### 7.25.3.46 stat\_histogram()

```
int stat_histogram (
          HISTOGRAM * histo,
          struct histstat * stbuf )
```

Statistical analysis of a histogram.

The median calculation is implemented for 1-D 'I' and 'R' types histograms only.

### **Parameters**

histo	pointer to histogram
stbuf	pointer to histogram statistics structure

### Returns

Nonzero result indicates failure

### 7.25.3.47 stat\_moments()

Calculate moments (mean, rms, skewness, kurtosis) from the sums of powers of data values.

#### **Parameters**

mom	'moments' structure with the sums of the powers of data values (only 1st power if only mean to be calculated, also 2nd power if r.m.s. to be calculated, and also 3rd and 4th if skewness and kurtosis wanted.
stmom	Pointer to structure for computed moments

#### Returns

```
0 (o.k.), -1 and -2 (invalid data)
```

### 7.25.3.48 unlink\_histogram()

```
void unlink_histogram ( {\tt HISTOGRAM * histo} \ )
```

Remove a histogram from the list without destroying it.

Remove a histogram from the linked list of histograms. That histogram will therefore not be found by any subsequent call to 'free\_all\_histograms()', display\_all\_histograms()', and 'get\_histogram\_by\_ident()'.

#### **Parameters**

histo Pointer to histogran	n.
----------------------------	----


## Returns

(none)

# 7.26 history.h File Reference


Keep blocks of history in the data (like command line of programs operating on the data, ...)

```
#include "initial.h"
Include dependency graph for history.h:
```



7.27 initial.h File Reference 251

This graph shows which files directly or indirectly include this file:



### **Functions**

- int push\_command\_history (int argc, char \*\*argv)
- int push\_config\_history (const char \*line, int replace)
- int write\_history (long id, IO\_BUFFER \*iobuf)
- int write\_config\_history (const char \*htext, long htime, long id, IO\_BUFFER \*iobuf)
- int list\_history (IO\_BUFFER \*iobuf, FILE \*file)

### 7.26.1 Detailed Description

Keep blocks of history in the data (like command line of programs operating on the data, ...)

Author

Konrad Bernloehr

Date

1997 to 2010

```
$Date: 2014/02/20 11:40:42 $
```

Version


\$Revision: 1.5 \$

## 7.27 initial.h File Reference

Indentification of the system and including some basic include file.

```
#include <string.h>
#include <stdio.h>
#include <math.h>
#include <time.h>
#include <stdlib.h>
```

#include <sys/types.h>
Include dependency graph for initial.h:



This graph shows which files directly or indirectly include this file:



#### **Macros**

- #define IEEE FLOAT FORMAT 1
- #define **M\_PI** 3.14159265358979323846
- #define ARGLIST(a) a
- #define SEEK\_CUR 1
- #define WRITE\_TEXT "w"
- #define WRITE BINARY "w"
- #define READ\_TEXT "r"
- #define READ\_BINARY "r"
- #define APPEND\_TEXT "a"
- #define APPEND\_BINARY "a"
- #define Nint(a) (((a)>=0.)?((long)(a+0.5)):((long)(a-0.5)))
- #define **Abs**(a) (((a)>=0)?(a):(-1\*(a)))
- #define **Min**(a, b) ((a)<(b)?(a):(b))
- #define **Max**(a, b) ((a)>(b)?(a):(b))
- #define **min**(a, b) ((a)<(b)?(a):(b))
- #define **max**(a, b) ((a)>(b)?(a):(b))
- #define REGISTER register
- #define CONST QUAL

## **Typedefs**

- · typedef char int8\_t
- · typedef unsigned char uint8 t
- typedef short int16\_t
- typedef unsigned short uint16\_t
- typedef int int32 t
- typedef unsigned int uint32\_t
- typedef long intmax t
- typedef unsigned long uintmax\_t

7.27 initial.h File Reference 253

## 7.27.1 Detailed Description

Indentification of the system and including some basic include file.

**Author** 

Konrad Bernloehr

Date

1991 to 2010

```
$Date: 2016/11/24 13:07:43 $
```

Version

```
$Revision: 1.19 $
```

This file identifies a range of supported operating systems and processor types. As a result, some preprocessor definitions are made. A basic set of system include files (which may vary from one system to another) are included. In addition, compatibility between different systems is improved, for example between K&R compiler systems and ANSI C compilers of various flavours.


```
Identification of the host operating system (not CPU):
Supported identifiers are
OS_MSDOS
OS_VAXVMS
OS_UNIX
    + variant identifiers like
   OS_ULTRIX, OS_LYNX, OS_LINUX, OS_DECUNIX, OS_AIX, OS_HPUX,
   OS_DARWIN (Mac OS X).
   Note: ULTRIX may be on VAX or MIPS, LINUX on Intel or Alpha,
   OS_LYNX on 68K or PowerPC.
OS_OS9
You might first reset all identifiers here.
Then set one or more identifiers according to the system.
Identification of the CPU architecture:
Supported CPU identifiers are
   CPU_I86
   CPU_X86_64
   CPU_VAX
   CPU_MIPS
   CPU_ALPHA
   CPU_68K
   CPU_RS6000
   CPU_PowerPC
   CPU_HPPA
```

## 7.28 io\_hess.c File Reference

### Writing and reading of H.E.S.S.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "io_hess.h"
#include <assert.h>
#include <sys/time.h>
```

Include dependency graph for io\_hess.c:



#### **Functions**

- void check\_hessio\_max (int ncheck, int max\_tel, int max\_pix, int max\_sectors, int max\_drawers, int max\_
   pixsectors, int max\_slices, int max\_hotpix, int max\_profile, int max\_d\_temp, int max\_c\_temp, int max\_gains)
  - Support for checking if user functions are compiled with the same limits as the library.
- void show\_hessio\_max ()
- void hs\_reset\_env ()

Allow user to override MAX\_PRINT\_ARRAY and PRINT\_VERBOSE settings at a later time.

static void hs\_check\_env ()

Get settings on how much information to print from environment.

• static void put time blob (HTime \*t, IO BUFFER \*iobuf)

Put the time (seconds since 1970.0, nanoseconds) into an eventio block already started.

• static void get\_time\_blob (HTime \*t, IO\_BUFFER \*iobuf)

Get the time (seconds since 1970.0, nanoseconds) from an eventio block already started.

• void set tel idx ref (int iref)

Switch between multiple telescope lookup tables.

void set\_tel\_idx (int ntel, int \*idx)

Setup of telescope index lookup table.

• int find tel idx (int tel id)

Lookup from telescope ID to offset number (index) in structures.

int write\_hess\_runheader (IO\_BUFFER \*iobuf, RunHeader \*rh)

Write the run header in eventio format.

• int read\_hess\_runheader (IO\_BUFFER \*iobuf, RunHeader \*rh)

Read the run header in eventio format.

• int print\_hess\_runheader (IO\_BUFFER \*iobuf)

Read the run header in eventio format.

• int write\_hess\_mcrunheader (IO\_BUFFER \*iobuf, MCRunHeader \*mcrh)

Write the Monte Carlo run header in eventio format.

 $\bullet \quad \text{int read\_hess\_mcrunheader (IO\_BUFFER *iobuf, MCRunHeader *mcrh)} \\$ 

Read the Monte Carlo run header in eventio format.

int print hess mcrunheader (IO BUFFER \*iobuf)

Print the Monte Carlo run header data.

• int write\_hess\_camsettings (IO\_BUFFER \*iobuf, CameraSettings \*cs)

Write the camera definition (pixel positions) in eventio format.

int read hess camsettings (IO BUFFER \*iobuf, CameraSettings \*cs)

Read the camera definition (pixel positions) in eventio format.

int print hess camsettings (IO BUFFER \*iobuf)

Print the camera definition (pixel positions) in eventio format.

int write hess camorgan (IO BUFFER \*iobuf, CameraOrganisation \*co)

Write the logical organisation of camera electronics in eventio format.

int read\_hess\_camorgan (IO\_BUFFER \*iobuf, CameraOrganisation \*co)

Read the logical organisation of camera electronics in eventio format.

int print hess camorgan (IO BUFFER \*iobuf)

Read the logical organisation of camera electronics in eventio format.

int write\_hess\_pixelset (IO\_BUFFER \*iobuf, PixelSetting \*ps)

Write the settings of pixel parameters (HV, thresholds, ...) in eventio format.

int read hess pixelset (IO BUFFER \*iobuf, PixelSetting \*ps)

Read the settings of pixel parameters (HV, thresholds, ...) in eventio format.

int print\_hess\_pixelset (IO\_BUFFER \*iobuf)

Show the settings of pixel parameters (HV, thresholds, ...) in eventio format.

int write hess pixeldis (IO BUFFER \*iobuf, PixelDisabled \*pd)

Write which pixels are disabled in HV and/or trigger in eventio format.

int read\_hess\_pixeldis (IO\_BUFFER \*iobuf, PixelDisabled \*pd)

Read which pixels are disabled in HV and/or trigger in eventio format.

int print\_hess\_pixeldis (IO\_BUFFER \*iobuf)

Print which pixels are disabled in HV and/or trigger in eventio format.

int write\_hess\_camsoftset (IO\_BUFFER \*iobuf, CameraSoftSet \*cs)

Write camera software parameters relevant for data recording in eventio format.

int read\_hess\_camsoftset (IO\_BUFFER \*iobuf, CameraSoftSet \*cs)

Read camera software parameters relevant for data recording in eventio format.

int write\_hess\_trackset (IO\_BUFFER \*iobuf, TrackingSetup \*ts)

Write the settings for tracking of a telescope in eventio format.

int read\_hess\_trackset (IO\_BUFFER \*iobuf, TrackingSetup \*ts)

Read the settings for tracking of a telescope in eventio format.

int print\_hess\_trackset (IO\_BUFFER \*iobuf)

Print the settings for tracking of a telescope in eventio format.

int write hess pointingcor (IO BUFFER \*iobuf, PointingCorrection \*pc)

Write the parameters of a telescope's pointing correction in eventio format.

int read\_hess\_pointingcor (IO\_BUFFER \*iobuf, PointingCorrection \*pc)

Read the parameters of a telescope's pointing correction in eventio format.

int print\_hess\_pointingcor (IO\_BUFFER \*iobuf)

Print the parameters of a telescope's pointing correction in eventio format.

int write hess centralevent (IO BUFFER \*iobuf, CentralEvent \*ce)

Write the trigger data of the central trigger in eventio format.

int read\_hess\_centralevent (IO\_BUFFER \*iobuf, CentralEvent \*ce)

Read the trigger data of the central trigger in eventio format.

· int print\_hess\_centralevent (IO\_BUFFER \*iobuf)

Print the trigger data of the central trigger in eventio format.

int write\_hess\_trackevent (IO\_BUFFER \*iobuf, TrackEvent \*tke)

Write a tracking position in eventio format.

int read\_hess\_trackevent (IO\_BUFFER \*iobuf, TrackEvent \*tke)

Read a tracking position in eventio format.

• int print hess trackevent (IO BUFFER \*iobuf)

Print the tracking data in eventio format.

• int write\_hess\_televt\_head (IO\_BUFFER \*iobuf, TelEvent \*te)

Write the event header for data from one camera in eventio format.

int read hess televt head (IO BUFFER \*iobuf, TelEvent \*te)

Read the event header for data from one camera in eventio format.

int print\_hess\_televt\_head (IO\_BUFFER \*iobuf)

Print the event header for data from one camera in eventio format.

- void put adcsum as uint16 (uint32 t \*adc sum, int n, IO BUFFER \*iobuf)
- void get adcsum as uint16 (uint32 t \*adc sum, int n, IO BUFFER \*iobuf)
- void put\_adcsum\_differential (uint32\_t \*adc\_sum, int n, IO\_BUFFER \*iobuf)
- void get adcsum differential (uint32 t \*adc sum, int n, IO BUFFER \*iobuf)
- void put\_adcsample\_differential (uint16\_t \*adc\_sample, int n, IO\_BUFFER \*iobuf)
- void get adcsample differential (uint16 t \*adc sample, int n, IO BUFFER \*iobuf)
- int write\_hess\_teladc\_sums (IO\_BUFFER \*iobuf, AdcData \*raw)

Write ADC sum data for one camera in eventio format.

int read hess teladc sums (IO BUFFER \*iobuf, AdcData \*raw)

Write ADC sum data for one camera in eventio format.

• int print\_hess\_teladc\_sums (IO\_BUFFER \*iobuf)

Print summed ADC data in eventio format.

int write hess teladc samples (IO BUFFER \*iobuf, AdcData \*raw)

Write sampled ADC data in eventio format.

int read\_hess\_teladc\_samples (IO\_BUFFER \*iobuf, AdcData \*raw, int what)

Read sampled ADC data in eventio format.

int print hess teladc samples (IO BUFFER \*iobuf)

Print sampled ADC data in eventio format.

- static void adc\_reset (AdcData \*raw)
- int write hess aux trace digital (IO BUFFER \*iobuf, AuxTraceD \*auxd)

Write auxilliary digitized traces.

int read\_hess\_aux\_trace\_digital (IO\_BUFFER \*iobuf, AuxTraceD \*auxd)

Read auxilliary digitized traces.

int print\_hess\_aux\_trace\_digital (IO\_BUFFER \*iobuf)

Print auxilliary digitized traces.

int write hess aux trace analog (IO BUFFER \*iobuf, AuxTraceA \*auxa)

Write auxilliary analog traces.

int read\_hess\_aux\_trace\_analog (IO\_BUFFER \*iobuf, AuxTraceA \*auxa)

Read auxilliary analog traces.

int print\_hess\_aux\_trace\_analog (IO\_BUFFER \*iobuf)

Print auxilliary analog traces.

static void build list for hess pixtime (PixelTiming \*pixtm)

A helper function finding the shorter of two possible formats for the list of pixels with any timing information.

int write hess pixtime (IO BUFFER \*iobuf, PixelTiming \*pixtm)

Write pixel timing parameters for selected pixels.

int read\_hess\_pixtime (IO\_BUFFER \*iobuf, PixelTiming \*pixtm)

Read pixel timing parameters for selected pixels.

int print\_hess\_pixtime (IO\_BUFFER \*iobuf)

Print sampled ADC data in eventio format.

int write\_hess\_pixcalib (IO\_BUFFER \*iobuf, PixelCalibrated \*pixcal)

Write pixel intensities calibrated to (mean?) p.e.

int read\_hess\_pixcalib (IO\_BUFFER \*iobuf, PixelCalibrated \*pixcal)

Read pixel intensities calibrated to (mean?) p.e.

int print hess pixcalib (IO BUFFER \*iobuf)

Print pixel intensities calibrated to (mean?) p.e.

int write hess telimage (IO BUFFER \*iobuf, ImgData \*img, int what)

Write image parameters for one telescope in eventio format.

int read hess telimage (IO BUFFER \*iobuf, ImgData \*img)

Read image parameters for one telescope in eventio format.

int print\_hess\_telimage (IO\_BUFFER \*iobuf)

Print image parameters for one telescope in eventio format.

int write\_hess\_televent (IO\_BUFFER \*iobuf, TelEvent \*te, int what)

Write data for one telescope camera in eventio format.

• int read\_hess\_televent (IO\_BUFFER \*iobuf, TelEvent \*te, int what)

Read data for one telescope camera in eventio format.

int print hess televent (IO BUFFER \*iobuf)

Print data for one telescope camera in eventio format.

• int write\_hess\_shower (IO\_BUFFER \*iobuf, ShowerParameters \*sp)

Write reconstructed shower parameters in eventio format.

int read hess shower (IO BUFFER \*iobuf, ShowerParameters \*sp)

Read reconstructed shower parameters in eventio format.

• int print\_hess\_shower (IO\_BUFFER \*iobuf)

Print reconstructed shower parameters in eventio format.

int write\_hess\_event (IO\_BUFFER \*iobuf, FullEvent \*ev, int what)

Write the full array data of one event in eventio format.

• int read hess event (IO BUFFER \*iobuf, FullEvent \*ev, int what)

Read the full array data of one event in eventio format.

int print\_hess\_event (IO\_BUFFER \*iobuf)

Print the full array data of one event in eventio format.

int write hess calib event (IO BUFFER \*iobuf, FullEvent \*ev, int what, int type)

Write a calibration event (pedestal, laser, led, ...) as an encapsulated raw data event.

int read\_hess\_calib\_event (IO\_BUFFER \*iobuf, FullEvent \*ev, int what, int \*ptype)

Read a calibration event (pedestal, laser, led, ...) as an encapsulated raw data event.

int print\_hess\_calib\_event (IO\_BUFFER \*iobuf)

Print a calibration event (pedestal, laser, led, ...) as an encapsulated raw data event.

int write\_hess\_mc\_shower (IO\_BUFFER \*iobuf, MCShower \*mcs)

Write MC data for one simulated shower in eventio format.

int read\_hess\_mc\_shower (IO\_BUFFER \*iobuf, MCShower \*mcs)

Read MC data for one simulated shower in eventio format.

int print\_hess\_mc\_shower (IO\_BUFFER \*iobuf)

Print MC data for one simulated shower in eventio format.

• int write hess mc event (IO BUFFER \*iobuf, MCEvent \*mce)

Write MC data for one use of a simulated shower in eventio format.

int read\_hess\_mc\_event (IO\_BUFFER \*iobuf, MCEvent \*mce)

Read MC data for one use of a simulated shower in eventio format.

• int print\_hess\_mc\_event (IO\_BUFFER \*iobuf)

Print MC data for one use of a simulated shower in eventio format.

int write\_hess\_mc\_pe\_sum (IO\_BUFFER \*iobuf, MCpeSum \*mcpes)

Write the numbers of photo-electrons detected from Cherenkov light in eventio format.

int read\_hess\_mc\_pe\_sum (IO\_BUFFER \*iobuf, MCpeSum \*mcpes)

Read the numbers of photo-electrons detected from Cherenkov light in eventio format.

 int print\_hess\_mc\_pe\_sum (IO\_BUFFER \*iobuf) Print the numbers of photo-electrons detected from Cherenkov light in eventio format. void reset htime (HTime \*t) void fill htime now (HTime \*now) Fill the current time into a HTime structure. void copy htime (HTime \*t2, HTime \*t1) Copy a time from one HTime structure into another one. • int write\_hess\_tel\_monitor (IO\_BUFFER \*iobuf, TelMoniData \*mon, int what) Write telescope camera monitoring information in eventio format. int read hess tel monitor (IO BUFFER \*iobuf, TelMoniData \*mon) Read telescope camera monitoring information in eventio format. • int print\_hess\_tel\_monitor (IO\_BUFFER \*iobuf) Print telescope camera monitoring information in eventio format. int write hess laser calib (IO BUFFER \*iobuf, LasCalData \*lcd) Write a set of laser calibration data in eventio format. int read\_hess\_laser\_calib (IO\_BUFFER \*iobuf, LasCalData \*lcd) Read a set of laser calibration data in eventio format. int print hess laser calib (IO BUFFER \*iobuf) Print a set of laser calibration data in eventio format. int write\_hess\_run\_stat (IO\_BUFFER \*iobuf, RunStat \*rs) Write run statistics in eventio format. int read\_hess\_run\_stat (IO\_BUFFER \*iobuf, RunStat \*rs) Read run statistics in eventio format. int print\_hess\_run\_stat (IO\_BUFFER \*iobuf) Print run statistics in eventio format. int write\_hess\_mc\_run\_stat (IO\_BUFFER \*iobuf, MCRunStat \*mcrs) Write Monte Carlo run statistics in eventio format. int read hess mc run stat (IO BUFFER \*iobuf, MCRunStat \*mcrs) Read Monte Carlo run statistics in eventio format. int print\_hess\_mc\_run\_stat (IO\_BUFFER \*iobuf) Print Monte Carlo run statistics in eventio format. • int read\_hess\_mc\_phot (IO\_BUFFER \*iobuf, MCEvent \*mce) Read Monte Carlo photons and photo-electrons. int print\_hess\_mc\_phot (IO\_BUFFER \*iobuf) Print Monte Carlo photons and photo-electrons. • int write hess pixel list (IO BUFFER \*iobuf, PixelList \*pl, int telescope) Write lists of pixels (triggered, selected in image analysis, ...) int read\_hess\_pixel\_list (IO\_BUFFER \*iobuf, PixelList \*pl, int \*telescope) Read lists of pixels (triggered, selected in image analysis, ...) • int print hess pixel list (IO BUFFER \*iobuf) Print lists of pixels (triggered, selected in image analysis, ...)

## **Variables**

static int hs verbose = -1

Should hessio print\_...

static int hs\_maxprt = -1

What is the maximum number of per pixel outputs?

static int hs dynamic = -1

Should be check environment variables each time?

- static int g tel idx [3][H MAX TEL+1]
- static int g\_tel\_idx\_init [3]
- static int g\_tel\_idx\_ref

## 7.28.1 Detailed Description

Writing and reading of H.E.S.S.

/CTA data (or other simulation data produced by sim\_telarray/sim\_hessarray) in eventio format.

This file provides functions for writing and reading of H.E.S.S./CTA related data blocks or similar data for other telescope arrays. This software will attempt to be backward-compatible, i.e. to be able to read older data in slightly different formats - but we cannot guarantee that it really works. There is no attempt to write data in older formats. As always: use at your own risc.

**Author** 

Konrad Bernlöhr

Date

## 7.28.2 Function Documentation

### 7.28.2.1 check\_hessio\_max()

```
void check_hessio_max (
    int ncheck,
    int max_tel,
    int max_pix,
    int max_sectors,
    int max_drawers,
    int max_pixsectors,
    int max_pixsectors,
    int max_lices,
    int max_hotpix,
    int max_profile,
    int max_d_temp,
    int max_c_temp,
    int max_gains )
```

Support for checking if user functions are compiled with the same limits as the library.

References H MAX TEL.

# 7.28.2.2 find\_tel\_idx()

Lookup from telescope ID to offset number (index) in structures.

The lookup table must have been filled before with set\_tel\_idx(). When dealing with multiple lookups, use set\_tel ← \_idx\_ref() first to select the lookup table to be used.

#### **Parameters**

tel⊷	A telescope ID for which we want the index count.
_id	

### Returns

>= 0 (index in the original list passed to set\_tel\_idx), -1 (not found in index, -2 (index not initialized).

#### 7.28.2.3 print\_hess\_aux\_trace\_analog()

Print auxilliary analog traces.

- < Must match the expected telescope ID when reading.
- < Indicate what type of trace we have
- < Time per auxilliary sample over time per normal FADC sample (typ.: 0.25)
- < The number of traces coming from the camera.
- < The length of each trace in FADC samples.

# 7.28.2.4 print\_hess\_aux\_trace\_digital()

Print auxilliary digitized traces.

- < Must match the expected telescope ID when reading.
- < Indicate what type of trace we have (1: DigitalSum trigger trace)
- < Time per auxilliary sample over time per normal FADC sample (typ.: 1.0)
- < The number of traces coming from the camera.
- < The length of each trace in FADC samples.

## 7.28.2.5 print\_hess\_pixcalib()

Print pixel intensities calibrated to (mean?) p.e.

units.

## 7.28.2.6 read\_hess\_pixcalib()

Read pixel intensities calibrated to (mean?) p.e.

units.

References hess\_pixel\_calibrated\_struct::known.

### 7.28.2.7 set\_tel\_idx()

```
void set_tel_idx (
          int ntel,
          int * idx )
```

Setup of telescope index lookup table.

Must be filled before first use of find\_tel\_idx() - which is automatically done when reading a run header data block. When dealing with multiple lookups, use set\_tel\_idx\_ref() first to select the one to fill.

### **Parameters**

ntel	The number of telescope following.
idx	The list of telescope IDs mapped to indices 0, 1,

## 7.28.2.8 set\_tel\_idx\_ref()

Switch between multiple telescope lookup tables.

Use this function when dealing simultaneously with multiple data streams for different array configurations. Both the set\_tel\_idx and the find\_tel\_idx will then work wit the selected choice of lookup table.

## **Parameters**

*iref* Which lookup table to use from now on (0<=iref<=2). Not switching lookup if iref is out of range.

Referenced by merge\_data\_from\_io\_block().

### 7.28.2.9 write\_hess\_aux\_trace\_digital()

Write auxilliary digitized traces.

There is no data reduction for auxilliary traces.

References hess\_aux\_digital\_trace::known, and hess\_aux\_digital\_trace::trace\_data.

# 7.28.2.10 write\_hess\_event()

Write the full array data of one event in eventio format.

This can include raw data, tracking data, and central trigger data as gathered from the individual computers, as well as reconstructed parameters (image parameters, shower parameters).

# 7.28.2.11 write\_hess\_laser\_calib()

Write a set of laser calibration data in eventio format.

This may well change in a future revision (when more details are known how the real laser calibration should work).

#### 7.28.2.12 write hess mc event()

Write MC data for one use of a simulated shower in eventio format.

This includes the core position shift with respect to the telescope array and the cross reference to the simulated shower.

#### 7.28.2.13 write\_hess\_mc\_pe\_sum()

Write the numbers of photo-electrons detected from Cherenkov light in eventio format.

These are the 'true' numbers registered, not including photo-electrons from nightsky background.

### 7.28.2.14 write\_hess\_mc\_shower()

Write MC data for one simulated shower in eventio format.

This includes data from the shower simulation itself, independent of how many times a shower is used and where the core position is shifted to with respect to the telescope array.

## 7.28.2.15 write\_hess\_pixcalib()

Write pixel intensities calibrated to (mean?) p.e.

units.

References hess\_pixel\_calibrated\_struct::known.

## 7.28.2.16 write\_hess\_run\_stat()

Write run statistics in eventio format.

This is pretty much dummy at this moment. Once we get closer to the real experiment, this data will certainly increase by a considerable amount.

# 7.28.2.17 write\_hess\_shower()

Write reconstructed shower parameters in eventio format.

Note that the actual amount of data stored depends on what is actually available (as indicated in the 'result\_bits').

## 7.28.2.18 write\_hess\_tel\_monitor()

Write telescope camera monitoring information in eventio format.

What actually is written depends on the 'what' parameter. The general idea is to write only those things which have changed. Only when a target farm CPU becomes the target of the data stream, the full set of monitoring data is written.

References copy\_htime(), fill\_htime\_now(), hess\_tel\_monitor\_struct::known, hess\_tel\_monitor\_struct::moni\_time, and hess\_tel\_monitor\_struct::new\_parts.

#### 7.28.2.19 write\_hess\_teladc\_samples()

Write sampled ADC data in eventio format.

In contrast to sum data, no data reduction is applied so far. It is assumed that sampled data would be taken only for hardware tests, where the full information has to be maintained. If large amounts of sampled data are taken, a suitable data reduction method should be inserted here.

References hess\_tel\_event\_adc\_struct::data\_red\_mode, and hess\_tel\_event\_adc\_struct::zero\_sup\_mode.

## 7.28.2.20 write\_hess\_teladc\_sums()

Write ADC sum data for one camera in eventio format.

The data can be optionally reduced (like writing only high-gain channels for pixels with low signals etc.) and zero-suppressed (not writing anything for pixels with very low signals).

References hess\_tel\_event\_adc\_struct::data\_red\_mode, hess\_tel\_event\_adc\_struct::known, hess\_tel\_event\_cadc struct::list known, and hess tel event adc struct::zero sup mode.

## 7.28.2.21 write\_hess\_televent()

Write data for one telescope camera in eventio format.

Depending on the 'what' parameter, either sampled or summed pixel values are expected to be in the 'te' structure. Writing of image paramaters is another option.

### 7.28.3 Variable Documentation

### 7.28.3.1 hs\_verbose

```
int hs_verbose = -1 [static]
```

Should hessio print\_...


functions be verbose?

Referenced by hs\_check\_env(), and hs\_reset\_env().

# 7.29 io\_hess.h File Reference

Definition and structures for H.E.S.S.

```
#include "mc_tel.h"
Include dependency graph for io_hess.h:
```



This graph shows which files directly or indirectly include this file:



### **Data Structures**

· struct hess\_run\_header\_struct

Run header common to measured and simulated data.

• struct hess\_mc\_run\_header\_struct

MC run header.

struct hess\_camera\_settings\_struct

Definition of camera optics settings.

· struct hess\_camera\_organisation\_struct

Logical organisation of camera electronics channels.

struct hess\_pixel\_setting\_struct

Settings of pixel HV and thresholds.

· struct hess\_pixel\_disabled\_struct

Pixels disabled in HV and/or trigger.

struct hess\_camera\_software\_setting\_struct

Software settings used in camera process.

• struct hess\_tracking\_setup\_struct

Definition of tracking parameters.

struct hess\_pointing\_correction\_struct

Pointing correction parameters.

struct hess time struct

Breakdown of time into seconds since 1970.0 and nanoseconds.

· struct hess\_tel\_event\_adc\_struct

ADC data (either sampled or sum mode)

- · struct hess\_aux\_digital\_trace
- struct hess\_aux\_analog\_trace
- struct hess\_pixel\_timing\_struct
- struct hess\_pixel\_calibrated\_struct
- struct hess\_pixel\_list

Lists of pixels (triggered, selected, etc.)

· struct hess\_tel\_image\_struct

Image parameters.

• struct hess\_tel\_event\_data\_struct

Event raw and image data from one telescope.

struct hess\_central\_event\_data\_struct

Central trigger event data.

• struct hess\_tracking\_event\_data\_struct

Tracking data interpolated for one event and one telescope.

· struct hess\_shower\_parameter

Reconstructed shower parameters.

· struct hess event data struct

All data for one event.

struct hess\_mc\_shower\_profile\_struct

Monte Carlo shower profile (sort of histogram).

struct hess\_mc\_shower\_struct

Shower specific data.

struct hess\_mc\_pe\_sum\_struct

Sums of photo-electrons in MC (total and per pixel).

· struct hess mc photons

Photons from Monte Carlo.

struct hess\_mc\_pe\_list

Photo-electrons from Monte Carlo individually.

struct hess\_mc\_event\_struct

Monte Carlo event-specific data.

· struct hess\_tel\_monitor\_struct

Monitoring data.

• struct hess\_laser\_calib\_data\_struct

Laser calibration data.

· struct hess\_run\_end\_statistics\_struct

End-of-run statistics.

• struct hess\_run\_end\_mc\_statistics\_struct

MC end-of-run statistics.

struct hess\_all\_data\_struct

Container for all H.E.S.S.

#### **Macros**

- #define IO\_HESS\_VERSION 2
- #define HI\_GAIN 0

Which index refers to which type of channel:

• #define LO GAIN 1

Index to low-gain channels in adc\_sum, adc\_sample, pedestal, ...

• #define LARGE TELESCOPE 1

Maximum sizes for various arrays:

- #define SMARTPIXEL 1
- #define H\_MAX\_TEL 16

Maximum number of telescopes handled.

- #define H MAX TRG PER SECTOR 1
- #define H MAX PIX 4095
- #define **H\_MAX\_SECTORS** (H\_MAX\_PIX\*H\_MAX\_TRG\_PER\_SECTOR)
- #define H\_MAX\_DRAWERS H\_MAX\_PIX
- #define H\_MAX\_GAINS 2

Maximum number of different gains per PM.

- #define H MAX PIXSECTORS 4
- #define H\_MAX\_SLICES 128

Maximum number of time slices handled.

• #define H\_MAX\_HOTPIX 5

The max.

• #define H\_MAX\_PROFILE 10

The max.

- #define **H\_MAX\_D\_TEMP** 8
- #define H MAX C TEMP 10
- #define H\_MAX\_FSHAPE 1000

Мах.

- #define H MAX TRG TYPES 4
- #define H\_CHECK\_MAX()

Compile-time override of the most relevant limits:

#define RAWDATA FLAG 0x01

Flags used for saving and restoring event data:

- #define RAWSUM FLAG 0x02
- #define TRACKRAW\_FLAG 0x04
- #define TRACKCOR FLAG 0x08
- #define TRACKDATA FLAG (TRACKRAW FLAG|TRACKCOR FLAG)
- #define IMG BASE FLAG 0x10
- #define IMG\_ERR\_FLAG 0x20
- #define IMG 34M FLAG 0x40
- #define IMG HOT FLAG 0x80
- #define IMG PIXTM FLAG 0x100
- #define IMAGE FLAG (IMG BASE FLAG IMG ERR FLAG IMG 34M FLAG IMG HOT FLAG IMG PI ← XTM FLAG)
- #define TIME\_FLAG 0x200
- #define SHOWER FLAG 0x400
- #define CALSUM FLAG 0x800
- #define IO TYPE HESS BASE 2000

Never change the following numbers after MC data is created:

- #define IO\_TYPE\_HESS\_RUNHEADER (IO\_TYPE\_HESS\_BASE+0)
- #define IO TYPE HESS MCRUNHEADER (IO TYPE HESS BASE+1)
- #define IO\_TYPE\_HESS\_CAMSETTINGS (IO\_TYPE\_HESS\_BASE+2)
- #define IO TYPE HESS CAMORGAN (IO TYPE HESS BASE+3)
- #define IO\_TYPE\_HESS\_PIXELSET (IO\_TYPE\_HESS\_BASE+4)
- #define IO\_TYPE\_HESS\_PIXELDISABLE (IO\_TYPE\_HESS\_BASE+5)
- #define IO\_TYPE\_HESS\_CAMSOFTSET (IO\_TYPE\_HESS\_BASE+6)
- #define IO\_TYPE\_HESS\_POINTINGCOR (IO\_TYPE\_HESS\_BASE+7)
- #define IO TYPE HESS TRACKSET (IO TYPE HESS BASE+8)
- #define IO\_TYPE\_HESS\_CENTEVENT (IO\_TYPE\_HESS\_BASE+9)
- #define IO\_TYPE\_HESS\_TRACKEVENT (IO\_TYPE\_HESS\_BASE+100)
- #define IO\_TYPE\_HESS\_TELEVENT (IO\_TYPE\_HESS\_BASE+200)
- #define IO TYPE HESS EVENT (IO TYPE HESS BASE+10)
- #define IO TYPE HESS TELEVTHEAD (IO TYPE HESS BASE+11)
- #define IO TYPE HESS TELADCSUM (IO TYPE HESS BASE+12)
- #define IO\_TYPE\_HESS\_TELADCSAMP (IO\_TYPE\_HESS\_BASE+13)
- #define IO TYPE HESS TELIMAGE (IO TYPE HESS BASE+14)
- #define IO\_TYPE\_HESS\_SHOWER (IO\_TYPE\_HESS\_BASE+15)
- #define IO TYPE HESS PIXELTIMING (IO TYPE HESS BASE+16)
- #define IO\_TYPE\_HESS\_PIXELCALIB (IO\_TYPE\_HESS\_BASE+17)
- #define IO TYPE HESS MC SHOWER (IO TYPE HESS BASE+20)
- #define IO TYPE HESS MC EVENT (IO TYPE HESS BASE+21) #define IO\_TYPE\_HESS\_TEL\_MONI (IO\_TYPE\_HESS\_BASE+22)
- #define IO TYPE HESS LASCAL (IO TYPE HESS BASE+23)
- #define IO TYPE HESS RUNSTAT (IO TYPE HESS BASE+24)
- #define IO\_TYPE\_HESS\_MC\_RUNSTAT (IO\_TYPE\_HESS\_BASE+25) #define IO TYPE HESS MC PE SUM (IO TYPE HESS BASE+26)
- #define IO\_TYPE\_HESS\_PIXELLIST (IO\_TYPE\_HESS\_BASE+27)
- #define IO TYPE HESS CALIBEVENT (IO TYPE HESS BASE+28)
- #define IO TYPE HESS AUX DIGITAL TRACE (IO TYPE HESS BASE+29)
- #define IO TYPE HESS AUX ANALOG TRACE (IO TYPE HESS BASE+30)
- #define HAS CORSIKA INTERACTION DETAIL 1
- #define MAX AUX TRACE D 1

Only one auxilliary digital trace.

#define MAX\_AUX\_TRACE\_A 4

Up to four auxilliary analog traces.

#define H MAX PIX TIMES 7

In addition to ADC we may (optionally) also have timing data.

• #define PIX TIME PEAKPOS TYPE 1

Position of peak in time (slices since readout).

• #define PIX TIME STARTPOS REL TYPE 2

Position of first rise above fraction of peak ampl.

#define PIX\_TIME\_STARTPOS\_ABS\_TYPE 3

Position of first rise above absolute threshold.

• #define PIX TIME WIDTH REL TYPE 4

Width of pulse over fraction of peak ampl.

• #define PIX\_TIME\_WIDTH\_ABS\_TYPE 5

Width of pulse over absolute threshold (time over threshold).

## **Typedefs**

- · typedef struct hess run header struct RunHeader
- typedef struct hess\_mc\_run\_header\_struct MCRunHeader
- typedef struct hess\_camera\_settings\_struct CameraSettings
- typedef struct hess\_camera\_organisation\_struct CameraOrganisation
- · typedef struct hess\_pixel\_setting\_struct PixelSetting
- typedef struct hess\_pixel\_disabled\_struct PixelDisabled
- typedef struct hess\_camera\_software\_setting\_struct CameraSoftSet
- typedef struct hess\_tracking\_setup\_struct TrackingSetup
- typedef struct hess pointing correction struct PointingCorrection
- typedef struct hess\_time\_struct HTime
- typedef struct hess\_tel\_event\_adc\_struct AdcData
- typedef struct hess\_aux\_digital\_trace AuxTraceD
- typedef struct hess\_aux\_analog\_trace AuxTraceA
- typedef struct hess\_pixel\_timing\_struct PixelTiming
- typedef struct hess\_pixel\_calibrated\_struct PixelCalibrated
- typedef struct hess\_pixel\_list PixelList
- · typedef struct hess\_tel\_image\_struct ImgData
- typedef struct hess\_tel\_event\_data\_struct TelEvent
- typedef struct hess\_central\_event\_data\_struct CentralEvent
- typedef struct hess\_tracking\_event\_data\_struct TrackEvent
- typedef struct hess\_shower\_parameter ShowerParameters
- · typedef struct hess event data struct FullEvent
- typedef struct hess\_mc\_shower\_profile\_struct ShowerProfile
- typedef struct hess\_mc\_shower\_struct MCShower
- typedef struct hess\_mc\_pe\_sum\_struct MCpeSum
- typedef struct hess\_mc\_event\_struct MCEvent
- typedef struct hess\_tel\_monitor\_struct TelMoniData
- typedef struct hess\_laser\_calib\_data\_struct LasCalData
- · typedef struct hess run end statistics struct RunStat
- typedef struct hess\_run\_end\_mc\_statistics\_struct MCRunStat
- typedef struct hess\_all\_data\_struct AllHessData

### **Functions**

void check\_hessio\_max (int ncheck, int max\_tel, int max\_pix, int max\_sectors, int max\_drawers, int max\_pixsectors, int max\_slices, int max\_hotpix, int max\_profile, int max\_d\_temp, int max\_c\_temp, int max\_gains)
 Support for checking if user functions are compiled with the same limits as the library.

void show\_hessio\_max (void)

## 7.29.1 Detailed Description

Definition and structures for H.E.S.S.

/CTA data in eventio format.

This file contains definitions and data structures used for writing and reading HESS data (both Monte Carlo and real data) in the eventio format. It was then extended to include potential additional CTA data.

### **Author**

Konrad Bernlöhr

### Date

```
initial version: July 2000

CVS $Date: 2018/08/03 16:20:21 $
```

## Version

```
CVS $Revision: 1.103 $
```

# 7.29.2 Macro Definition Documentation

## 7.29.2.1 H\_CHECK\_MAX

```
#define H_CHECK_MAX( )
```

### Value:

```
check_hessio_max(11,H_MAX_TEL,H_MAX_PIX,H_MAX_SECTORS,\
    H_MAX_DRAWERS,H_MAX_PIXSECTORS,H_MAX_SLICES,H_MAX_HOTPIX,
    H_MAX_PROFILE,\
    H_MAX_D_TEMP,H_MAX_C_TEMP,H_MAX_GAINS);
```

Compile-time override of the most relevant limits:

Macro expanding into a function call checking if user function is taking the same maximum array sizes as the library.

Referenced by main().

### 7.29.2.2 H\_MAX\_FSHAPE

#define H\_MAX\_FSHAPE 1000

Max.

number of (sub-) samples of reference pulse shapes.

## 7.29.2.3 **H\_MAX\_HOTPIX**

#define H\_MAX\_HOTPIX 5

The max.

size of the list of hottest pix.

# 7.29.2.4 H\_MAX\_PIX\_TIMES

#define H\_MAX\_PIX\_TIMES 7

In addition to ADC we may (optionally) also have timing data.

Referenced by pixel\_timing\_analysis().

## 7.29.2.5 H\_MAX\_PROFILE

#define H\_MAX\_PROFILE 10

The max.

number of MC shower profiles.

# 7.29.2.6 H\_MAX\_SLICES

#define H\_MAX\_SLICES 128

Maximum number of time slices handled.

Referenced by nb\_fc\_shaped\_peak\_integration(), nb\_peak\_integration(), and set\_integration\_correction().

## 7.29.2.7 HI\_GAIN

```
#define HI_GAIN 0
```

Which index refers to which type of channel:

Index to high-gain channels in adc\_sum, adc\_sample, pedestal, ...

Referenced by local\_peak\_integration(), and nb\_peak\_integration().

## 7.29.2.8 LO\_GAIN

```
#define LO_GAIN 1
```

Index to low-gain channels in adc\_sum, adc\_sample, pedestal, ...

Referenced by local\_peak\_integration(), and nb\_peak\_integration().

## 7.29.2.9 PIX\_TIME\_PEAKPOS\_TYPE

```
#define PIX_TIME_PEAKPOS_TYPE 1
```

Position of peak in time (slices since readout).

Referenced by pixel\_timing\_analysis().

# 7.29.2.10 PIX\_TIME\_STARTPOS\_ABS\_TYPE

```
#define PIX_TIME_STARTPOS_ABS_TYPE 3
```

Position of first rise above absolute threshold.

## 7.29.2.11 PIX\_TIME\_STARTPOS\_REL\_TYPE

```
#define PIX_TIME_STARTPOS_REL_TYPE 2
```

Position of first rise above fraction of peak ampl.

Referenced by pixel\_timing\_analysis().

## 7.29.2.12 PIX\_TIME\_WIDTH\_ABS\_TYPE

```
#define PIX_TIME_WIDTH_ABS_TYPE 5
```

Width of pulse over absolute threshold (time over threshold).

Referenced by pixel\_timing\_analysis().

# 7.29.2.13 PIX\_TIME\_WIDTH\_REL\_TYPE

```
#define PIX_TIME_WIDTH_REL_TYPE 4
```

Width of pulse over fraction of peak ampl.

Referenced by pixel\_timing\_analysis().

## 7.29.3 Function Documentation

## 7.29.3.1 check\_hessio\_max()

```
void check_hessio_max (
    int ncheck,
    int max_tel,
    int max_pix,
    int max_sectors,
    int max_drawers,
    int max_pixsectors,
    int max_slices,
    int max_hotpix,
    int max_profile,
    int max_d_temp,
    int max_c_temp,
    int max_gains )
```

Support for checking if user functions are compiled with the same limits as the library.


References H\_MAX\_TEL.

# 7.30 io\_histogram.c File Reference

This file implements I/O for 1-D and 2-D histograms.

```
#include "initial.h"
#include "io_basic.h"
#include "histogram.h"
#include "io_histogram.h"
#include "fileopen.h"
```

Include dependency graph for io\_histogram.c:



## Macros

• #define \_\_attribute \_\_(a) /\* Ignore gcc specials with other compilers \*/

## **Functions**

- int write\_all\_histograms (const char \*fname)
  - Save all available histograms into the file with the given name.
- int read\_histogram\_file (const char \*fname, int add\_flag)
- int read\_histogram\_file\_x (const char \*fname, int add\_flag, const long \*xcld\_ids, int nxcld)
- int write\_histograms (HISTOGRAM \*\*phisto, int nhisto, IO\_BUFFER \*iobuf)
  - Save specific histograms or all allocated histograms.
- int read\_histograms (HISTOGRAM \*\*phisto, int nhisto, IO\_BUFFER \*iobuf)
  - Read and allocate histograms and optionally return histogram pointers to caller.
- int read\_histograms\_x (HISTOGRAM \*\*phisto, int nhisto, const long \*xcld\_ids, int nxcld, IO\_BUFFER \*iobuf)
  - Read and allocate histograms and optionally return histogram pointers to caller.
- int print\_histograms (IO\_BUFFER \*iobuf)

Print out some basics about histogram data as we read it.

# 7.30.1 Detailed Description

This file implements I/O for 1-D and 2-D histograms.

Author

Konrad Bernloehr

Date

```
1993 to 2010
```

```
CVS $Date: 2018/02/28 16:36:53 $
```

Version

```
CVS $Revision: 1.22 $
```

## 7.30.2 Function Documentation

## 7.30.2.1 print\_histograms()

Print out some basics about histogram data as we read it.

## **Parameters**

```
iobuf The input iobuf descriptor.
```

Returns

```
>= 0 (O.k., no. of histograms read), -1 (error), -2 (e.o.d.)
```

# 7.30.2.2 read\_histograms()

Read and allocate histograms and optionally return histogram pointers to caller.

### **Parameters**

phisto	Pointer to vector of histogram pointers or NULL.
nhisto	The no. of elements in the phisto vector, i.e. the max. no. of histograms of which the histogram pointer can be returned to the caller. If negative, histograms contents are added to existing histograms of the same ID.
iobuf	The input iobuf descriptor.

### Returns

```
>= 0 (O.k., no. of histograms read), -1 (error), -2 (e.o.d.)
```

References read\_histograms\_x().

## 7.30.2.3 read\_histograms\_x()

```
int read_histograms_x (
    HISTOGRAM ** phisto,
    int nhisto,
    const long * xcld_ids,
    int nxcld,
    IO_BUFFER * iobuf )
```

Read and allocate histograms and optionally return histogram pointers to caller.

This extended version allows to exclude a list of histogram IDs from being kept or added.

## **Parameters**

phisto	Pointer to vector of histogram pointers or NULL.
nhisto	The no. of elements in the phisto vector, i.e. the max. no. of histograms of which the histogram pointer can be returned to the caller. If negative, histograms contents are added to existing histograms of the same ID.
xcld_ids	Pointer to vector of histogram IDs to be excluded.
ncxld	Number of histogram IDs to be excluded.
iobuf	The input iobuf descriptor.

## Returns

```
>= 0 (O.k., no. of histograms read), -1 (error), -2 (e.o.d.)
```

Referenced by read\_histograms().

# 7.30.2.4 write\_histograms()

```
int nhisto,
IO_BUFFER * iobuf )
```

Save specific histograms or all allocated histograms.

### **Parameters**

phisto	Pointer to vector of histogram pointers or NULL.
nhisto	The no. of histograms to be saved or -1. If phisto==NULL and nhisto==-1 then all allocated histograms
	(in the linked list of histograms) are saved.
iobuf	The output iobuf descriptor.

### Returns


References get\_first\_histogram(), histogram::ident, and histogram::next.

Referenced by write\_all\_histograms(), and write\_dst\_histos().


# 7.31 io\_histogram.h File Reference

Declarations for eventio I/O of histograms.

```
#include "histogram.h"
Include dependency graph for io_histogram.h:
```



This graph shows which files directly or indirectly include this file:



### **Functions**

• int write\_histograms (HISTOGRAM \*\*phisto, int nhisto, IO\_BUFFER \*iobuf)

Save specific histograms or all allocated histograms.

• int read\_histograms (HISTOGRAM \*\*phisto, int nhisto, IO\_BUFFER \*iobuf)

Read and allocate histograms and optionally return histogram pointers to caller.

• int read\_histograms\_x (HISTOGRAM \*\*phisto, int nhisto, const long \*xcld\_ids, int nxcld, IO\_BUFFER \*iobuf)

Read and allocate histograms and optionally return histogram pointers to caller.

• int print\_histograms (IO\_BUFFER \*iobuf)

Print out some basics about histogram data as we read it.

• int write\_all\_histograms (const char \*fname)

Save all available histograms into the file with the given name.

- int read\_histogram\_file (const char \*fname, int add\_flag)
- int read\_histogram\_file\_x (const char \*fname, int add\_flag, const long \*xcld\_ids, int nxcld)

## 7.31.1 Detailed Description

Declarations for eventio I/O of histograms.

**Author** 

Konrad Bernloehr

Date

```
CVS $Date: 2013/10/21 12:53:31 $
```

Version

```
CVS $Revision: 1.11 $
```

# 7.31.2 Function Documentation

## 7.31.2.1 print\_histograms()

Print out some basics about histogram data as we read it.

**Parameters** 

*iobuf* The input iobuf descriptor.

#### Returns

```
>= 0 (O.k., no. of histograms read), -1 (error), -2 (e.o.d.)
```

# 7.31.2.2 read\_histograms()

```
int read_histograms (
          HISTOGRAM ** phisto,
          int nhisto,
          IO_BUFFER * iobuf )
```

Read and allocate histograms and optionally return histogram pointers to caller.

### **Parameters**

phisto	Pointer to vector of histogram pointers or NULL.
nhisto	The no. of elements in the phisto vector, i.e. the max. no. of histograms of which the histogram pointer can be returned to the caller. If negative, histograms contents are added to existing histograms of the same ID.
iobuf	The input iobuf descriptor.

### Returns

```
>= 0 (O.k., no. of histograms read), -1 (error), -2 (e.o.d.)
```

References read\_histograms\_x().

## 7.31.2.3 read\_histograms\_x()

Read and allocate histograms and optionally return histogram pointers to caller.

This extended version allows to exclude a list of histogram IDs from being kept or added.

#### **Parameters**

phisto	Pointer to vector of histogram pointers or NULL.
nhisto	The no. of elements in the phisto vector, i.e. the max. no. of histograms of which the histogram pointer can be returned to the caller. If negative, histograms contents are added to existing histograms of the same ID.
xcld_ids	Pointer to vector of histogram IDs to be excluded.
ncxld	Number of histogram IDs to be excluded.
iobuf Generated by D	The input iobuf descriptor.

### Returns

```
>= 0 (O.k., no. of histograms read), -1 (error), -2 (e.o.d.)
```

Referenced by read\_histograms().

# 7.31.2.4 write\_histograms()

```
int write_histograms (
          HISTOGRAM ** phisto,
          int nhisto,
          IO_BUFFER * iobuf )
```

Save specific histograms or all allocated histograms.

### **Parameters**

phisto Pointer to vector of histogram pointers or NULL.	
nhisto	The no. of histograms to be saved or -1. If phisto==NULL and nhisto==-1 then all allocated histograms
	(in the linked list of histograms) are saved.
iobuf	The output iobuf descriptor.

## Returns

```
0 (O.k.) or -1 (error)
```

References get\_first\_histogram(), histogram::ident, and histogram::next.


Referenced by write\_all\_histograms(), and write\_dst\_histos().

# 7.32 io\_history.c File Reference

Record history of configuration settings/commands.

```
#include "initial.h"
#include "io_basic.h"
#include "history.h"
#include "current.h"
#include "hconfig.h"
```

Include dependency graph for io\_history.c:



## **Data Structures**

struct history\_struct

Use to build a linked list of configuration history.

# **Typedefs**

typedef struct history\_struct HSTRUCT

## **Functions**

- static void listtime (time\_t t, FILE \*f)
- int push\_command\_history (int argc, char \*\*argv)
- int push\_config\_history (const char \*line, int noreplace)
- int write\_history (long id, IO\_BUFFER \*iobuf)
- int write\_config\_history (const char \*htext, long htime, long id, IO\_BUFFER \*iobuf)
- int list\_history (IO\_BUFFER \*iobuf, FILE \*file)

# **Variables**

• static char \* cmdline = NULL

A copy of the program's command line.

static time\_t cmdtime

The time when the program was started.

• static HSTRUCT \* configs = NULL

Start of configuration history.

# 7.32.1 Detailed Description

Record history of configuration settings/commands.

This code has not been adapted for multi-threading.

Author

Konrad Bernloehr

Date

```
1997 to 2010
```

```
CVS $Date: 2014/02/20 11:40:42 $
```

Version

```
CVS $Revision: 1.8 $
```

## 7.32.2 Variable Documentation

### 7.32.2.1 cmdline

```
char* cmdline = NULL [static]
```

A copy of the program's command line.

## 7.32.2.2 cmdtime

```
time_t cmdtime [static]
```

The time when the program was started.

# 7.32.2.3 configs


```
HSTRUCT* configs = NULL [static]
```

Start of configuration history.

# 7.33 io\_history.h File Reference

Record history of configuration settings/commands.

#include "initial.h"
Include dependency graph for io\_history.h:



# **Functions**

- int push\_command\_history (int argc, char \*\*argv)
- int push\_config\_history (const char \*line, int noreplace)
- int write\_history (long id, IO\_BUFFER \*iobuf)
- int write\_config\_history (const char \*htext, long htime, long id, IO\_BUFFER \*iobuf)
- int list\_history (IO\_BUFFER \*iobuf, FILE \*file)

## 7.33.1 Detailed Description

Record history of configuration settings/commands.

**Author** 

Konrad Bernloehr

Date

1997 to 2010

CVS \$Date: 2014/02/20 11:40:42 \$

Version


CVS Revision: 1.5\$

# 7.34 io simtel.c File Reference

Write and read CORSIKA blocks and simulated Cherenkov photon bunches.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "fileopen.h"
```

Include dependency graph for io\_simtel.c:



#### **Functions**

• int write\_tel\_block (IO\_BUFFER \*iobuf, int type, int num, real \*data, int len)

Write a CORSIKA block as given type number (see mc\_tel.h).

• int read\_tel\_block (IO\_BUFFER \*iobuf, int type, real \*data, int maxlen)

Read a CORSIKA header/trailer block of given type (see mc tel.h)

• int print\_tel\_block (IO\_BUFFER \*iobuf)

Print a CORSIKA header/trailer block of any type (see mc\_tel.h)

int write\_input\_lines (IO\_BUFFER \*iobuf, struct linked\_string \*list)

Write a linked list of character strings (normally containing the text of the CORSIKA inputs file) as a dedicated block.

int read\_input\_lines (IO\_BUFFER \*iobuf, struct linked\_string \*list)

Read a block with several character strings (normally containing the text of the CORSIKA inputs file) into a linked list.

• int write\_tel\_pos (IO\_BUFFER \*iobuf, int ntel, double \*x, double \*y, double \*z, double \*r)

Write positions of telescopes/detectors within a system or array.

• int read\_tel\_pos (IO\_BUFFER \*iobuf, int max\_tel, int \*ntel, double \*x, double \*y, double \*z, double \*r)

Read positions of telescopes/detectors within a system or array.

• int print tel pos (IO BUFFER \*iobuf)

Print positions of telescopes/detectors within a system or array.

• int write\_tel\_offset (IO\_BUFFER \*iobuf, int narray, double toff, double \*xoff, double \*yoff)

Write offsets of randomly scattered arrays with respect to shower core.

• int write\_tel\_offset\_w (IO\_BUFFER \*iobuf, int narray, double toff, double \*xoff, double \*yoff, double \*weight)

Write offsets and weights of randomly scattered arrays with respect to shower core.

• int read\_tel\_offset (IO\_BUFFER \*iobuf, int max\_array, int \*narray, double \*toff, double \*xoff, double \*yoff)

Read offsets of randomly scattered arrays with respect to shower core.

• int read\_tel\_offset\_w (IO\_BUFFER \*iobuf, int max\_array, int \*narray, double \*toff, double \*xoff, double \*yoff, double \*weight)

Read offsets and weights of randomly scattered arrays with respect to shower core.

int print tel offset (IO BUFFER \*iobuf)

Print offsets and weights of randomly scattered arrays with respect to shower core.

int begin\_write\_tel\_array (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*ih, int array)

Begin writing data for one array of telescopes/detectors.

int end\_write\_tel\_array (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*ih)

End writing data for one array of telescopes/detectors.

int begin\_read\_tel\_array (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*ih, int \*array)

Begin reading data for one array of telescopes/detectors.

int end read tel array (IO BUFFER \*iobuf, IO ITEM HEADER \*ih)

End reading data for one array of telescopes/detectors.

• int write\_tel\_array\_head (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*ih, int array)

Begin writing data for one array of telescopes/detectors.

• int write tel array end (IO BUFFER \*iobuf, IO ITEM HEADER \*ih, int array)

End writing data for one array of telescopes/detectors.

• int read\_tel\_array\_head (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*ih, int \*array)

Begin reading data for one array of telescopes/detectors.

int read\_tel\_array\_end (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*ih, int \*array)

End reading data for one array of telescopes/detectors.

• int write\_tel\_photons (IO\_BUFFER \*iobuf, int array, int tel, double photons, struct bunch \*bunches, int nbunches, int ext\_bunches, char \*ext\_fname)

Write all the photon bunches for one telescope to an I/O buffer.

• int write\_tel\_compact\_photons (IO\_BUFFER \*iobuf, int array, int tel, double photons, struct compact\_bunch \*cbunches, int nbunches, int ext bunches, char \*ext fname)

Write all the photon bunches for one telescope to an I/O buffer.

• int read\_tel\_photons (IO\_BUFFER \*iobuf, int max\_bunches, int \*array, int \*tel, double \*photons, struct bunch \*bunches, int \*nbunches)

Read bunches of Cherenkov photons for one telescope/detector.

- int print\_tel\_photons (IO BUFFER \*iobuf)
- int write\_shower\_longitudinal (IO\_BUFFER \*iobuf, int event, int type, double \*data, int ndim, int np, int nthick, double thickstep)

Write CORSIKA shower longitudinal distributions.

• int read\_shower\_longitudinal (IO\_BUFFER \*iobuf, int \*event, int \*type, double \*data, int ndim, int \*np, int \*nthick, double \*thickstep, int max np)

Read CORSIKA shower longitudinal distributions.

• int write\_camera\_layout (IO\_BUFFER \*iobuf, int itel, int type, int pixels, double \*xp, double \*yp)

Write the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

int read\_camera\_layout (IO\_BUFFER \*iobuf, int max\_pixels, int \*itel, int \*type, int \*pixels, double \*xp, double \*yp)

Read the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

int print\_camera\_layout (IO\_BUFFER \*iobuf)

Print the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

• int write\_photo\_electrons (IO\_BUFFER \*iobuf, int array, int tel, int npe, int flags, int pixels, int \*pe\_counts, int \*tstart, double \*t, double \*a, int \*photon counts)

Write the photo-electrons registered in a Cherenkov telescope camera.

• int read\_photo\_electrons (IO\_BUFFER \*iobuf, int max\_pixels, int max\_pe, int \*array, int \*tel, int \*npe, int \*pixels, int \*flags, int \*pe\_counts, int \*tstart, double \*t, double \*a, int \*photon\_counts)

Read the photoelectrons registered in a Cherenkov telescope camera.

int print\_photo\_electrons (IO\_BUFFER \*iobuf)

List the the photoelectrons registered in a Cherenkov telescope camera.

- int write\_shower\_extra\_parameters (IO\_BUFFER \*iobuf, struct shower\_extra\_parameters \*ep)
- int read\_shower\_extra\_parameters (IO\_BUFFER \*iobuf, struct shower\_extra\_parameters \*ep)
- int print\_shower\_extra\_parameters (IO\_BUFFER \*iobuf)
- int init\_shower\_extra\_parameters (struct shower\_extra\_parameters \*ep, size\_t ni\_max, size\_t nf\_max)

Initialize, resize, clear shower extra parameters.

• int clear\_shower\_extra\_parameters (struct shower\_extra\_parameters \*ep)

Similar to init\_shower\_extra\_parameters() but without any attempts to re-allocate or resize buffers.

• struct shower\_extra\_parameters \* get\_shower\_extra\_parameters ()

### **Variables**

• static int max\_print = 0

Print bunches of Cherenkov photons for one telescope/detector.

• static struct shower\_extra\_parameters private\_shower\_extra\_parameters

There is one global (more precisely: static) block of extra shower parameters as, for example, used in the CORSIKA IACT interface.

# 7.34.1 Detailed Description

Write and read CORSIKA blocks and simulated Cherenkov photon bunches.

This file provides functions for writing and reading of CORSIKA header and trailer blocks, positions of telescopes/detectors, lists of simulated Cherenkov photon bunches before any detector simulation for the telescopes as well as of photoelectrons after absorption, telescope ray-tracing and quantum efficiency applied.

### **Author**

Konrad Bernloehr

#### Date

```
1997 to 2010
```

```
CVS $Date: 2018/08/03 16:19:36 $
```

#### Version

```
CVS $Revision: 1.36 $
```

## 7.34.2 Function Documentation

## 7.34.2.1 begin\_read\_tel\_array()

Begin reading data for one array of telescopes/detectors.

Note: this function does not finish reading from the I/O block but after reading of the photons a call to end\_read\_\to tel array() is needed.

## **Parameters**

iobuf	- I/O buffer descriptor
ih	- I/O item header (for item opened here)
arrav	- Number of array

#### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

Referenced by print\_hess\_mc\_phot(), and read\_hess\_mc\_phot().

## 7.34.2.2 begin\_write\_tel\_array()

Begin writing data for one array of telescopes/detectors.

Note: this function does not finish writing to the I/O block but after writing of the photons a call to end\_write\_tel\_\(\to\) array() is needed.

### **Parameters**

iobuf	I/O buffer descriptor
ih	I/O item header (for item opened here)
array	Number of array

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.3 clear\_shower\_extra\_parameters()

Similar to init\_shower\_extra\_parameters() but without any attempts to re-allocate or resize buffers.

Just clear contents.

### **Parameters**

```
ep Pointer to parameter block. A NULL value indicates that the static block is meant.
```

# 7.34.2.4 end\_read\_tel\_array()

```
int end_read_tel_array (
```

```
IO_BUFFER * iobuf,
IO_ITEM_HEADER * ih )
```

End reading data for one array of telescopes/detectors.

## **Parameters**

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array() )

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.34.2.5 end\_write\_tel\_array()

End writing data for one array of telescopes/detectors.

### **Parameters**

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.6 init\_shower\_extra\_parameters()

Initialize, resize, clear shower extra parameters.

## **Parameters**

ер	Pointer to parameter block. A NULL value indicates that the static block is meant.	
ni_max	The number of integer parameters to be used.	
nf_max	The number of float parameters to be used.	

### 7.34.2.7 print\_camera\_layout()

Print the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

#### **Parameters**

```
iobuf I/O buffer descriptor
```

#### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.8 print\_photo\_electrons()

List the the photoelectrons registered in a Cherenkov telescope camera.

## **Parameters**

```
iobuf I/O buffer descriptor
```

#### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.34.2.9 print\_tel\_block()

Print a CORSIKA header/trailer block of any type (see mc\_tel.h)

#### **Parameters**

iobuf	I/O buffer descriptor

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.10 print\_tel\_offset()

Print offsets and weights of randomly scattered arrays with respect to shower core.

### **Parameters**

iobuf	I/O buffer descriptor
-------	-----------------------

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.11 print\_tel\_pos()

Print positions of telescopes/detectors within a system or array.

#### **Parameters**

```
iobuf I/O buffer descriptor
```

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.34.2.12 read\_camera\_layout()

```
double * xp,
double * yp )
```

Read the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

### **Parameters**

iobuf	I/O buffer descriptor
max_pixels	The maximum number of pixels that can be stored in xp, yp.
itel	telescope number
type	camera type (hex/square)
pixels	number of pixels
хр	X positions of pixels
ур	Y position of pixels

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.34.2.13 read\_input\_lines()

Read a block with several character strings (normally containing the text of the CORSIKA inputs file) into a linked list.

### **Parameters**

iobuf	I/O buffer descriptor
list	starting point of linked list (on first call this should be a link to an empty list, i.e. the first element has
	text=NULL and next=NULL; on additional calls the new lines will be appended.)

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.14 read\_photo\_electrons()

```
int * tstart,
double * t,
double * a,
int * photon_counts )
```

Read the photoelectrons registered in a Cherenkov telescope camera.

## **Parameters**

iobuf	I/O buffer descriptor
max_pixels	Maximum number of pixels which can be treated
max_pe	Maximum number of photo-electrons
array	Array number
tel	Telescope number
npe	The total number of photo-electrons read.
pixels	Number of pixels read.
flags	Bit 0: amplitudes available, bit 1: includes NSB p.e.
pe_counts	Numbers of photo-electrons in each pixel
tstart	Offsets in 't' at which data for each pixel starts
t	Time of arrival of photons at the camera.
а	Amplitudes of p.e. signals [mean p.e.] (optional, may be NULL).
photon_counts	Optional number of photons arriving at a pixel.

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.15 read\_shower\_longitudinal()

Read CORSIKA shower longitudinal distributions.

See tellng\_() in iact.c for more detailed parameter description.

iobuf	I/O buffer descriptor
event	return event number
type	return 1 = particle numbers, 2 = energy, 3 = energy deposits
data	return set of (usually 9) distributions

### **Parameters**

ndim	maximum number of entries per distribution	
np	return number of distributions (usually 9)	
nthick	return number of entries actually filled per distribution (is 1 if called without LONGI being enabled).	
thickstep	return step size in g/cm**2	
max_np	maximum number of distributions for which we have space.	

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.34.2.16 read\_tel\_array\_end()

End reading data for one array of telescopes/detectors.

### **Parameters**

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.34.2.17 read\_tel\_array\_head()

Begin reading data for one array of telescopes/detectors.

Note: this function does not finish reading from the I/O block but after reading of the photons a call to end\_read\_\cdot
tel\_array() is needed.

iobuf	– I/O buffer descriptor	
ih	<ul> <li>I/O item header (for item opened here)</li> </ul>	
array	- Number of array	

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.18 read\_tel\_block()

Read a CORSIKA header/trailer block of given type (see mc\_tel.h)

#### **Parameters**

iob	uf	I/O buffer descriptor
typ	e	block type (see mc_tel.h)
dai	'a	area for data to be read
ma	xlen	maximum number of elements to be read

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.19 read\_tel\_offset()

Read offsets of randomly scattered arrays with respect to shower core.

iobuf	I/O buffer descriptor
max_array	Maximum number of arrays that can be treated
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

References read\_tel\_offset\_w().

## 7.34.2.20 read\_tel\_offset\_w()

Read offsets and weights of randomly scattered arrays with respect to shower core.

## **Parameters**

iobuf	I/O buffer descriptor
max_array	Maximum number of arrays that can be treated
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays
weight	Area weight for uniform or importance sampled core offset. For old version data (uniformly sampled), 0.0 is returned.

#### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

Referenced by read\_tel\_offset().

## 7.34.2.21 read\_tel\_photons()

Read bunches of Cherenkov photons for one telescope/detector.

The data format may be either the more or less compact one.

## **Parameters**

iobuf	I/O buffer descriptor
max_bunches	maximum number of bunches that can be treated
array	array number
tel	telescope number
photons	sum of photons (and fractions) in this device
bunches	list of photon bunches
nbunches	number of elements in bunch list

#### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.22 read\_tel\_pos()

Read positions of telescopes/detectors within a system or array.

## Parameters

iobuf	I/O buffer descriptor
max_tel	maximum number of telescopes allowed
ntel	number of telescopes/detectors
X	X positions
У	Y positions
Z	Z positions
r	radius of spheres including the whole devices

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.23 write\_camera\_layout()

```
int itel,
int type,
int pixels,
double * xp,
double * yp )
```

Write the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

### **Parameters**

iobuf	I/O buffer descriptor
itel	telescope number
type	camera type (hex/square)
pixels	number of pixels
хр	X positions of pixels
ур	Y position of pixels

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.24 write\_input\_lines()

Write a linked list of character strings (normally containing the text of the CORSIKA inputs file) as a dedicated block.

#### **Parameters**

iobuf	I/O buffer descriptor
list	starting point of linked list

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.25 write\_photo\_electrons()

```
int flags,
int pixels,
int * pe_counts,
int * tstart,
double * t,
double * a,
int * photon_counts )
```

Write the photo-electrons registered in a Cherenkov telescope camera.

### **Parameters**

iobuf	I/O buffer descriptor
array	array number
tel	telescope number
npe	Total number of photo-electrons in the camera.
pixels	No. of pixels to be written
flags	Bit 0: amplitudes available, bit 1: includes NSB p.e., bit 2: also including no. of photons hitting each pixel.
pe_counts	Numbers of photo-electrons in each pixel
tstart	Offsets in 't' at which data for each pixel starts
t	Time of arrival of photons at the camera.
а	Amplitudes of p.e. signals [mean p.e.] (optional, may be NULL).
photon_counts	Optional number of photons arriving at a pixel (with flags bit 2 set)

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.34.2.26 write\_shower\_longitudinal()

Write CORSIKA shower longitudinal distributions.

See tellng\_() in iact.c for more detailed parameter description.

iobuf	I/O buffer descriptor
event	event number
type	1 = particle numbers, 2 = energy, 3 = energy deposits

### **Parameters**

data	set of (usually 9) distributions
ndim	maximum number of entries per distribution
np	number of distributions (usually 9)
nthick	number of entries actually filled per distribution (is 1 if called without LONGI being enabled).
thickstep	step size in g/cm**2

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.34.2.27 write\_tel\_array\_end()

End writing data for one array of telescopes/detectors.

### **Parameters**

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.28 write\_tel\_array\_head()

Begin writing data for one array of telescopes/detectors.

Note: this function does not finish writing to the I/O block but after writing of the photons a call to end\_write\_tel\_← array() is needed.

iobuf	I/O buffer descriptor	
ih	I/O item header (for item opened here)	
array	Number of array	

#### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.34.2.29 write\_tel\_block()

Write a CORSIKA block as given type number (see mc\_tel.h).

#### **Parameters**

iobuf	I/O buffer descriptor
type	block type (see mc_tel.h)
num	Run or event number depending on type
data	Data as passed from CORSIKA
len	Number of elements to be written

#### Returns

```
0 (OK), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.30 write\_tel\_compact\_photons()

Write all the photon bunches for one telescope to an I/O buffer.

Usually, calls to this function for each telescope in an array should be enclosed within calls to <a href="mailto:begin\_write\_tel\_array">begin\_write\_tel\_array</a>(). This routine writes the more compact format (16 bytes per bunch). The more compact format should usually be used to save memory and disk space.

iobuf	I/O buffer descriptor
-------	-----------------------

## **Parameters**

array	array number
tel	telescope number
photons	sum of photons (and fractions) in this device
cbunches	list of photon bunches
nbunches	number of elements in bunch list
ext_bunches	number of elements in external file
ext_fname	name of external (temporary) file

#### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.2.31 write\_tel\_offset()

Write offsets of randomly scattered arrays with respect to shower core.

# **Parameters**

iobuf	I/O buffer descriptor
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

References write\_tel\_offset\_w().

# 7.34.2.32 write\_tel\_offset\_w()

```
double toff,
double * xoff,
double * yoff,
double * weight )
```

Write offsets and weights of randomly scattered arrays with respect to shower core.

With respect to the backwards-compatible non-weights version write\_tel\_offset(), this version adds a weight to each offset position which should be normalized in such a way that with uniform sampling it should be the area over which showers are thrown divided by the number of array in each shower. With importance sampling the same relation should hold on average. So in either case, the average sum of weights for the different offsets in one shower equals just the area over which cores are randomized. This leaves the possibility to change the number of offsets from shower to shower.

#### **Parameters**

iobuf	I/O buffer descriptor
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays
weight	Area weight for uniform or importance sampled core offset.

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

Referenced by write\_tel\_offset().

### 7.34.2.33 write\_tel\_photons()

Write all the photon bunches for one telescope to an I/O buffer.

Usually, calls to this function for each telescope in an array should be enclosed within calls to begin\_write\_tel\_array() and end\_write\_tel\_array(). This routine writes the less compact format (32 bytes per bunch).

iobuf	I/O buffer descriptor
array	array number
tel	telescope number
photons	sum of photons (and fractions) in this device
Gebenated &s Doxygen list of photon bunches	
nbunches	number of elements in bunch list
ext_bunches	number of elements in external file
ext_fname	name of external (temporary) file

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.34.2.34 write\_tel\_pos()

Write positions of telescopes/detectors within a system or array.

### **Parameters**

iobuf	I/O buffer descriptor
ntel	number of telescopes/detectors
X	X positions
У	Y positions
Z	Z positions
r	radius of spheres including the whole devices

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.34.3 Variable Documentation

# 7.34.3.1 max\_print

```
int max_print = 0 [static]
```

Print bunches of Cherenkov photons for one telescope/detector.

The data format may be either the more or less compact one.

iobuf	I/O buffer descriptor
-------	-----------------------

Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

7.34.3.2 private\_shower\_extra\_parameters

```
struct shower_extra_parameters private_shower_extra_parameters [static]
```

There is one global (more precisely: static) block of extra shower parameters as, for example, used in the CORSIKA IACT interface.


Get a pointer to this block.

# 7.35 io\_trgmask.c File Reference

EventIO plus helper functions for trigger type bit patterns extracted from sim\_telarray log files (only relevant for simulations with multiple trigger types using sim\_telarray versions before mid-2013).

```
#include "initial.h"
#include "io_basic.h"
#include "fileopen.h"
#include "io_trgmask.h"
```

Include dependency graph for io\_trgmask.c:



## **Macros**

• #define TMS\_ALLOCS 100

### **Functions**

int trgmask\_scan\_log (struct trgmask\_set \*tms, const char \*fname)

Scan a sim\_telarray log file for lines related to trigger type mask bit patterns.

int write\_trgmask (IO\_BUFFER \*iobuf, struct trgmask\_set \*tms)

Write the accumulated trigger mask bit patterns as an I/O block.

• int print\_trgmask (IO\_BUFFER \*iobuf)

Print the trigger mask bit patterns contained in an I/O block.

int read\_trgmask (IO\_BUFFER \*iobuf, struct trgmask\_set \*tms)

Read the trigger mask bit patterns contained in an I/O block.

• int trgmask\_fill\_hashed (struct trgmask\_set \*tms, struct trgmask\_hash\_set \*ths)

Fill an array of linked lists of trgmask entries, suitable for hashing.

struct trgmask\_entry \* find\_trgmask (struct trgmask\_hash\_set \*ths, long event, int tel\_id)

Find the trgmask entry for a given event and telescope in the hashed list.

void print\_hashed\_trgmasks (struct trgmask\_hash\_set \*ths)

Print the collected trgmask entries in the order as hashed.

# 7.35.1 Detailed Description

EventIO plus helper functions for trigger type bit patterns extracted from sim\_telarray log files (only relevant for simulations with multiple trigger types using sim\_telarray versions before mid-2013).

#### 7.35.2 Function Documentation

## 7.35.2.1 find\_trgmask()

Find the trgmask entry for a given event and telescope in the hashed list.

Hash collisions are handled by linear search through the linked list at each hash entry.

#### **Parameters**

ths	The trgmask hash set.
event	The event number in the search.
tel←	The telescope ID in the search.
_id	

#### **Returns**

A pointer to the trgmask entry searched for, or NULL for not found.

### 7.35.2.2 print\_hashed\_trgmasks()

Print the collected trgmask entries in the order as hashed.

Also show the maximum number of colliding entries under one hash value.

## 7.35.2.3 trgmask\_fill\_hashed()

Fill an array of linked lists of trgmask entries, suitable for hashing.

Hash collisions are handled by linear search through the linked list at each hash entry.

### 7.35.2.4 trgmask\_scan\_log()

Scan a sim telarray log file for lines related to trigger type mask bit patterns.

### **Parameters**

tms	The trigger mask structure into which results should be filled in.
fname	The name of the log file to be opened.


### Returns

0 (OK), -1 (invalid parameters or file not found), -2 (allocation error, partially filled)

# 7.36 io\_trgmask.h File Reference

EventIO plus helper functions for trigger type bit patterns extracted from sim\_telarray log files (only relevant for simulations with multiple trigger types using sim\_telarray versions before mid-2013).

This graph shows which files directly or indirectly include this file:



### **Data Structures**

- struct trgmask\_entry
- · struct trgmask set
- struct trgmask\_hash\_set

## **Macros**

• #define IO\_TYPE\_HESS\_XTRGMASK 2090

Extra (or external - not in normal data file) trigger mask data block type.

- #define TRGMASK\_PRIME 15269
- #define TRGMASK\_HASH(ev, ti) (((ti)\*10000+(ev))%TRGMASK\_PRIME)

### **Functions**

• int trgmask\_scan\_log (struct trgmask\_set \*tms, const char \*fname)

Scan a sim\_telarray log file for lines related to trigger type mask bit patterns.

int write\_trgmask (IO\_BUFFER \*iobuf, struct trgmask\_set \*tms)

Write the accumulated trigger mask bit patterns as an I/O block.

int print\_trgmask (IO\_BUFFER \*iobuf)

Print the trigger mask bit patterns contained in an I/O block.

int read\_trgmask (IO\_BUFFER \*iobuf, struct trgmask\_set \*tms)

Read the trigger mask bit patterns contained in an I/O block.

int trgmask\_fill\_hashed (struct trgmask\_set \*tms, struct trgmask\_hash\_set \*ths)

Fill an array of linked lists of trgmask entries, suitable for hashing.

struct trgmask\_entry \* find\_trgmask (struct trgmask\_hash\_set \*ths, long event, int tel\_id)

Find the trgmask entry for a given event and telescope in the hashed list.

void print hashed trgmasks (struct trgmask hash set \*ths)

Print the collected trgmask entries in the order as hashed.

## 7.36.1 Detailed Description

EventIO plus helper functions for trigger type bit patterns extracted from sim\_telarray log files (only relevant for simulations with multiple trigger types using sim\_telarray versions before mid-2013).

## 7.36.2 Macro Definition Documentation

## 7.36.2.1 IO\_TYPE\_HESS\_XTRGMASK

```
#define IO_TYPE_HESS_XTRGMASK 2090
```

Extra (or external - not in normal data file) trigger mask data block type.

Referenced by print\_trgmask().

## 7.36.3 Function Documentation

## 7.36.3.1 find\_trgmask()

Find the trgmask entry for a given event and telescope in the hashed list.

Hash collisions are handled by linear search through the linked list at each hash entry.

#### **Parameters**

ths	The trgmask hash set.
event	The event number in the search.
tel⊷	The telescope ID in the search.
_id	

### Returns

A pointer to the trgmask entry searched for, or NULL for not found.

### 7.36.3.2 print\_hashed\_trgmasks()

Print the collected trgmask entries in the order as hashed.

Also show the maximum number of colliding entries under one hash value.

## 7.36.3.3 trgmask\_fill\_hashed()

Fill an array of linked lists of trgmask entries, suitable for hashing.

Hash collisions are handled by linear search through the linked list at each hash entry.

## 7.36.3.4 trgmask\_scan\_log()

Scan a sim\_telarray log file for lines related to trigger type mask bit patterns.

### **Parameters**

tms	The trigger mask structure into which results should be filled in.
fname	The name of the log file to be opened.

#### Returns


0 (OK), -1 (invalid parameters or file not found), -2 (allocation error, partially filled)

# 7.37 list\_histograms.c File Reference

Utility program for listing histograms.

```
#include "initial.h"
#include "histogram.h"
#include "io_basic.h"
#include "io_histogram.h"
#include "fileopen.h"
```

Include dependency graph for list\_histograms.c:



### **Functions**

int main (int argc, char \*\*argv)
 Main program.

# 7.37.1 Detailed Description

Utility program for listing histograms.

```
Syntax: list_histograms [ input_file ... ]
```

The default input file name is 'testpattern.hdata'. The histograms may be within multiple I/O blocks of the input file.

Author

Konrad Bernloehr

Date

CVS \$Date: 2018/02/28 16:36:52 \$


Version

CVS \$Revision: 1.3 \$


# 7.38 mc\_tel.h File Reference

Definitions and structures for CORSIKA Cherenkov light interface.

#include "io\_basic.h"
Include dependency graph for mc\_tel.h:



This graph shows which files directly or indirectly include this file:



# **Data Structures**

struct bunch

Photons collected in bunches of identical direction, position, time, and wavelength.

struct compact\_bunch

The compact\_bunch struct is equivalent to the bunch struct except that we try to use less memory.

struct photo\_electron

A photo-electron produced by a photon hitting a pixel.

struct linked\_string

The linked\_string is mainly used to keep CORSIKA input.

• struct shower\_extra\_parameters

Extra shower parameters of unspecified nature.

### **Macros**

- #define \_MC\_TEL\_LOADED 2
- #define IO\_TYPE\_MC\_BASE 1200
- #define IO\_TYPE\_MC\_RUNH (IO\_TYPE\_MC\_BASE+0)
- #define IO TYPE MC TELPOS (IO TYPE MC BASE+1)
- #define IO TYPE MC EVTH (IO TYPE MC BASE+2)
- #define IO\_TYPE\_MC\_TELOFF (IO\_TYPE\_MC\_BASE+3)
- #define IO\_TYPE\_MC\_TELARRAY (IO\_TYPE\_MC\_BASE+4)
- #define IO\_TYPE\_MC\_PHOTONS (IO\_TYPE\_MC\_BASE+5)
- #define IO TYPE MC LAYOUT (IO TYPE MC BASE+6)
- #define IO\_TYPE\_MC\_TRIGTIME (IO\_TYPE\_MC\_BASE+7)
- #define IO TYPE MC PE (IO TYPE MC BASE+8)
- #define IO\_TYPE\_MC\_EVTE (IO\_TYPE\_MC\_BASE+9)
- #define IO\_TYPE\_MC\_RUNE (IO\_TYPE\_MC\_BASE+10)
- #define IO\_TYPE\_MC\_LONGI (IO\_TYPE\_MC\_BASE+11)
- #define IO TYPE MC INPUTCFG (IO TYPE MC BASE+12)
- #define IO\_TYPE\_MC\_TELARRAY\_HEAD (IO\_TYPE\_MC\_BASE+13)
- #define IO\_TYPE\_MC\_TELARRAY\_END (IO\_TYPE\_MC\_BASE+14)
- #define IO\_TYPE\_MC\_EXTRA\_PARAM (IO\_TYPE\_MC\_BASE+15)

### **Typedefs**

- · typedef float real
- · typedef short INT16
- · typedef unsigned short UINT16
- · typedef int INT32
- · typedef unsigned int UINT32

### **Functions**

• int write tel block (IO BUFFER \*iobuf, int type, int num, real \*data, int len)

Write a CORSIKA block as given type number (see mc\_tel.h).

• int read\_tel\_block (IO\_BUFFER \*iobuf, int type, real \*data, int maxlen)

Read a CORSIKA header/trailer block of given type (see mc\_tel.h)

• int print tel block (IO BUFFER \*iobuf)

Print a CORSIKA header/trailer block of any type (see mc\_tel.h)

• int write\_input\_lines (IO\_BUFFER \*iobuf, struct linked\_string \*list)

Write a linked list of character strings (normally containing the text of the CORSIKA inputs file) as a dedicated block.

• int read\_input\_lines (IO\_BUFFER \*iobuf, struct linked\_string \*list)

Read a block with several character strings (normally containing the text of the CORSIKA inputs file) into a linked list.

• int write\_tel\_pos (IO\_BUFFER \*iobuf, int ntel, double \*x, double \*y, double \*z, double \*r)

Write positions of telescopes/detectors within a system or array.

• int read\_tel\_pos (IO\_BUFFER \*iobuf, int max\_tel, int \*ntel, double \*x, double \*y, double \*z, double \*r)

Read positions of telescopes/detectors within a system or array.

• int print tel pos (IO BUFFER \*iobuf)

Print positions of telescopes/detectors within a system or array.

int write tel offset (IO BUFFER \*iobuf, int narray, double toff, double \*xoff, double \*yoff)

Write offsets of randomly scattered arrays with respect to shower core.

• int write\_tel\_offset\_w (IO\_BUFFER \*iobuf, int narray, double toff, double \*xoff, double \*yoff, double \*weight)

Write offsets and weights of randomly scattered arrays with respect to shower core.

• int read\_tel\_offset (IO\_BUFFER \*iobuf, int max\_array, int \*narray, double \*toff, double \*xoff, double \*yoff)

Read offsets of randomly scattered arrays with respect to shower core.

• int read\_tel\_offset\_w (IO\_BUFFER \*iobuf, int max\_array, int \*narray, double \*toff, double \*xoff, double \*yoff, double \*weight)

Read offsets and weights of randomly scattered arrays with respect to shower core.

int print tel offset (IO BUFFER \*iobuf)

Print offsets and weights of randomly scattered arrays with respect to shower core.

int begin\_write\_tel\_array (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*ih, int array)

Begin writing data for one array of telescopes/detectors.

int end\_write\_tel\_array (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*ih)

End writing data for one array of telescopes/detectors.

• int begin read tel array (IO BUFFER \*iobuf, IO ITEM HEADER \*ih, int \*array)

Begin reading data for one array of telescopes/detectors.

int end\_read\_tel\_array (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*ih)

End reading data for one array of telescopes/detectors.

• int write tel array head (IO BUFFER \*iobuf, IO ITEM HEADER \*ih, int array)

Begin writing data for one array of telescopes/detectors.

• int write\_tel\_array\_end (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*ih, int array)

End writing data for one array of telescopes/detectors.

int read\_tel\_array\_head (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*ih, int \*array)

Begin reading data for one array of telescopes/detectors.

• int read\_tel\_array\_end (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*ih, int \*array)

End reading data for one array of telescopes/detectors.

• int write\_tel\_photons (IO\_BUFFER \*iobuf, int array, int tel, double photons, struct bunch \*bunches, int nbunches, int ext\_bunches, char \*ext\_fname)

Write all the photon bunches for one telescope to an I/O buffer.

• int write\_tel\_compact\_photons (IO\_BUFFER \*iobuf, int array, int tel, double photons, struct compact\_bunch \*cbunches, int nbunches, int ext\_bunches, char \*ext\_fname)

Write all the photon bunches for one telescope to an I/O buffer.

• int read\_tel\_photons (IO\_BUFFER \*iobuf, int max\_bunches, int \*array, int \*tel, double \*photons, struct bunch \*bunches, int \*nbunches)

Read bunches of Cherenkov photons for one telescope/detector.

- int print\_tel\_photons (IO\_BUFFER \*iobuf)
- int write\_shower\_longitudinal (IO\_BUFFER \*iobuf, int event, int type, double \*data, int ndim, int np, int nthick, double thickstep)

Write CORSIKA shower longitudinal distributions.

• int read\_shower\_longitudinal (IO\_BUFFER \*iobuf, int \*event, int \*type, double \*data, int ndim, int \*np, int \*nthick, double \*thickstep, int max\_np)

Read CORSIKA shower longitudinal distributions.

int write\_camera\_layout (IO\_BUFFER \*iobuf, int itel, int type, int pixels, double \*xp, double \*yp)

Write the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

int read\_camera\_layout (IO\_BUFFER \*iobuf, int max\_pixels, int \*itel, int \*type, int \*pixels, double \*xp, double \*yp)

Read the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

• int print\_camera\_layout (IO\_BUFFER \*iobuf)

Print the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

• int write\_photo\_electrons (IO\_BUFFER \*iobuf, int array, int tel, int npe, int pixels, int flags, int \*pe\_counts, int \*tstart, double \*t, double \*a, int \*photon\_counts)

Write the photo-electrons registered in a Cherenkov telescope camera.

• int read\_photo\_electrons (IO\_BUFFER \*iobuf, int max\_pixel, int max\_pe, int \*array, int \*tel, int \*npe, int \*pixels, int \*flags, int \*pe\_counts, int \*tstart, double \*t, double \*a, int \*photon\_counts)

Read the photoelectrons registered in a Cherenkov telescope camera.

```
    int print_photo_electrons (IO_BUFFER *iobuf)
```

List the the photoelectrons registered in a Cherenkov telescope camera.

- int write\_shower\_extra\_parameters (IO\_BUFFER \*iobuf, struct shower\_extra\_parameters \*ep)
- int read\_shower\_extra\_parameters (IO\_BUFFER \*iobuf, struct shower\_extra\_parameters \*ep)
- int print\_shower\_extra\_parameters (IO\_BUFFER \*iobuf)
- int init\_shower\_extra\_parameters (struct shower\_extra\_parameters \*ep, size\_t ni\_max, size\_t nf\_max)

  Initialize, resize, clear shower extra parameters.
- int clear\_shower\_extra\_parameters (struct shower\_extra\_parameters \*ep)

Similar to init\_shower\_extra\_parameters() but without any attempts to re-allocate or resize buffers.

struct shower\_extra\_parameters \* get\_shower\_extra\_parameters (void)

## 7.38.1 Detailed Description

Definitions and structures for CORSIKA Cherenkov light interface.

This file contains definitions of data structures and of function prototypes as needed for the Cherenkov light extraction interfaced to the modified CORSIKA code.

**Author** 

Konrad Bernloehr

Date

```
1997 to 2010
```

```
CVS $Date: 2016/03/08 16:07:50 $
```

Version

```
CVS $Revision: 1.16 $
```

# 7.38.2 Function Documentation

## 7.38.2.1 begin\_read\_tel\_array()

Begin reading data for one array of telescopes/detectors.

Note: this function does not finish reading from the I/O block but after reading of the photons a call to end\_read\_← tel\_array() is needed.

#### **Parameters**

iobuf	<ul> <li>I/O buffer descriptor</li> </ul>
ih	- I/O item header (for item opened here)
array	- Number of array

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

Referenced by print\_hess\_mc\_phot(), and read\_hess\_mc\_phot().

# 7.38.2.2 begin\_write\_tel\_array()

Begin writing data for one array of telescopes/detectors.

Note: this function does not finish writing to the I/O block but after writing of the photons a call to end\_write\_tel\_\(\to\) array() is needed.

## Parameters

iobuf	I/O buffer descriptor
ih	I/O item header (for item opened here)
array	Number of array

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.38.2.3 clear\_shower\_extra\_parameters()

Similar to init\_shower\_extra\_parameters() but without any attempts to re-allocate or resize buffers.

Just clear contents.

### **Parameters**

ep Pointer to parameter block. A NULL value indicates that the static block is meant.

## 7.38.2.4 end\_read\_tel\_array()

End reading data for one array of telescopes/detectors.

#### **Parameters**

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.38.2.5 end\_write\_tel\_array()

End writing data for one array of telescopes/detectors.

### **Parameters**

	iobuf	I/O buffer descriptor
Ī	ih	I/O item header (as opened in begin_write_tel_array() )

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.38.2.6 init\_shower\_extra\_parameters()

```
size_t ni_max,
size_t nf_max )
```

Initialize, resize, clear shower extra parameters.

### **Parameters**

ер	Pointer to parameter block. A NULL value indicates that the static block is meant.
ni_max	The number of integer parameters to be used.
nf_max	The number of float parameters to be used.

## 7.38.2.7 print\_camera\_layout()

Print the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

### **Parameters**

iobuf	I/O buffer descriptor
-------	-----------------------

### Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

# 7.38.2.8 print\_photo\_electrons()

List the the photoelectrons registered in a Cherenkov telescope camera.

### **Parameters**

iobuf I/O buffer	descriptor
------------------	------------

## Returns

0 (o.k.), -1, -2, -3 (error, as usual in eventio)

### 7.38.2.9 print\_tel\_block()

Print a CORSIKA header/trailer block of any type (see mc\_tel.h)

## **Parameters**

```
iobuf I/O buffer descriptor
```

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.38.2.10 print\_tel\_offset()

Print offsets and weights of randomly scattered arrays with respect to shower core.

### **Parameters**

```
iobuf I/O buffer descriptor
```

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.38.2.11 print\_tel\_pos()

Print positions of telescopes/detectors within a system or array.

### **Parameters**

iobuf	I/O buffer descriptor

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

### 7.38.2.12 read\_camera\_layout()

Read the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

### **Parameters**

iobuf	I/O buffer descriptor
max_pixels	The maximum number of pixels that can be stored in xp, yp.
itel	telescope number
type	camera type (hex/square)
pixels	number of pixels
хр	X positions of pixels
ур	Y position of pixels

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

### 7.38.2.13 read\_input\_lines()

Read a block with several character strings (normally containing the text of the CORSIKA inputs file) into a linked list.

# **Parameters**

t (on first call this should be a link to an empty list, i.e. the first element has L; on additional calls the new lines will be appended.)

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

### 7.38.2.14 read\_photo\_electrons()

```
int read_photo_electrons (
    IO_BUFFER * iobuf,
    int max_pixels,
    int max_pe,
    int * array,
    int * tel,
    int * npe,
    int * pixels,
    int * flags,
    int * pe_counts,
    int * tstart,
    double * t,
    double * a,
    int * photon_counts )
```

Read the photoelectrons registered in a Cherenkov telescope camera.

### **Parameters**

iobuf	I/O buffer descriptor
max_pixels	Maximum number of pixels which can be treated
max_pe	Maximum number of photo-electrons
array	Array number
tel	Telescope number
npe	The total number of photo-electrons read.
pixels	Number of pixels read.
flags	Bit 0: amplitudes available, bit 1: includes NSB p.e.
pe_counts	Numbers of photo-electrons in each pixel
tstart	Offsets in 't' at which data for each pixel starts
t	Time of arrival of photons at the camera.
а	Amplitudes of p.e. signals [mean p.e.] (optional, may be NULL).
photon_counts	Optional number of photons arriving at a pixel.

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.38.2.15 read\_shower\_longitudinal()

```
int read_shower_longitudinal (
    IO_BUFFER * iobuf,
    int * event,
    int * type,
    double * data,
    int ndim,
    int * np,
    int * nthick,
```

```
double * thickstep,
int max_np )
```

Read CORSIKA shower longitudinal distributions.

See tellng\_() in iact.c for more detailed parameter description.

### **Parameters**

iobuf	I/O buffer descriptor
event	return event number
type	return 1 = particle numbers, 2 = energy, 3 = energy deposits
data	return set of (usually 9) distributions
ndim	maximum number of entries per distribution
np	return number of distributions (usually 9)
nthick	return number of entries actually filled per distribution (is 1 if called without LONGI being enabled).
thickstep	return step size in g/cm**2
max_np	maximum number of distributions for which we have space.

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.38.2.16 read\_tel\_array\_end()

End reading data for one array of telescopes/detectors.

### **Parameters**

iobu	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.38.2.17 read\_tel\_array\_head()

```
IO_ITEM_HEADER * ih,
int * array )
```

Begin reading data for one array of telescopes/detectors.

Note: this function does not finish reading from the I/O block but after reading of the photons a call to end\_read\_ tel\_array() is needed.

#### **Parameters**

iobuf	- I/O buffer descriptor
ih	- I/O item header (for item opened here)
array	- Number of array

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

### 7.38.2.18 read\_tel\_block()

Read a CORSIKA header/trailer block of given type (see mc\_tel.h)

## **Parameters**

iobuf	I/O buffer descriptor
type	block type (see mc_tel.h)
data	area for data to be read
maxlen	maximum number of elements to be read

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.38.2.19 read\_tel\_offset()

```
double * toff,
double * xoff,
double * yoff )
```

Read offsets of randomly scattered arrays with respect to shower core.

### **Parameters**

iobuf	I/O buffer descriptor
max_array	Maximum number of arrays that can be treated
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

References read\_tel\_offset\_w().

## 7.38.2.20 read\_tel\_offset\_w()

Read offsets and weights of randomly scattered arrays with respect to shower core.

## **Parameters**

iobuf	I/O buffer descriptor
max_array	Maximum number of arrays that can be treated
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays
weight	Area weight for uniform or importance sampled core offset. For old version data (uniformly sampled), 0.0 is returned.

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

Referenced by read\_tel\_offset().

## 7.38.2.21 read\_tel\_photons()

Read bunches of Cherenkov photons for one telescope/detector.

The data format may be either the more or less compact one.

#### **Parameters**

iobuf	I/O buffer descriptor
max_bunches	maximum number of bunches that can be treated
array	array number
tel	telescope number
photons	sum of photons (and fractions) in this device
bunches	list of photon bunches
nbunches	number of elements in bunch list

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.38.2.22 read\_tel\_pos()

Read positions of telescopes/detectors within a system or array.

iobuf I/O buffer descriptor
-----------------------------

### **Parameters**

max_tel	maximum number of telescopes allowed
ntel	number of telescopes/detectors
Х	X positions
У	Y positions
Z	Z positions
r	radius of spheres including the whole devices

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.38.2.23 write\_camera\_layout()

Write the layout (pixel positions) of a camera used for converting from photons to photo-electrons in a pixel.

### **Parameters**

iobuf	I/O buffer descriptor
itel	telescope number
type	camera type (hex/square)
pixels	number of pixels
хр	X positions of pixels
ур	Y position of pixels

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.38.2.24 write\_input\_lines()

Write a linked list of character strings (normally containing the text of the CORSIKA inputs file) as a dedicated block.

## **Parameters**

iobuf	I/O buffer descriptor
list	starting point of linked list

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.38.2.25 write\_photo\_electrons()

Write the photo-electrons registered in a Cherenkov telescope camera.

## **Parameters**

iobuf	I/O buffer descriptor
array	array number
tel	telescope number
npe	Total number of photo-electrons in the camera.
pixels	No. of pixels to be written
flags	Bit 0: amplitudes available, bit 1: includes NSB p.e., bit 2: also including no. of photons hitting
	each pixel.
pe_counts	Numbers of photo-electrons in each pixel
tstart	Offsets in 't' at which data for each pixel starts
t	Time of arrival of photons at the camera.
а	Amplitudes of p.e. signals [mean p.e.] (optional, may be NULL).
photon_counts	Optional number of photons arriving at a pixel (with flags bit 2 set)

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.38.2.26 write\_shower\_longitudinal()

Write CORSIKA shower longitudinal distributions.

See tellng\_() in iact.c for more detailed parameter description.

## **Parameters**

iobuf	I/O buffer descriptor
event	event number
type	1 = particle numbers, 2 = energy, 3 = energy deposits
data	set of (usually 9) distributions
ndim	maximum number of entries per distribution
np	number of distributions (usually 9)
nthick	number of entries actually filled per distribution (is 1 if called without LONGI being enabled).
thickstep	step size in g/cm**2

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.38.2.27 write\_tel\_array\_end()

End writing data for one array of telescopes/detectors.

### **Parameters**

iobuf	I/O buffer descriptor
ih	I/O item header (as opened in begin_write_tel_array())

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

## 7.38.2.28 write\_tel\_array\_head()

Begin writing data for one array of telescopes/detectors.

Note: this function does not finish writing to the I/O block but after writing of the photons a call to end\_write\_tel\_carray() is needed.

## **Parameters**

iobuf	I/O buffer descriptor
ih	I/O item header (for item opened here)
array	Number of array

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.38.2.29 write\_tel\_block()

Write a CORSIKA block as given type number (see mc\_tel.h).

# **Parameters**

iobuf	I/O buffer descriptor
type	block type (see mc_tel.h)
num	Run or event number depending on type
data	Data as passed from CORSIKA
len	Number of elements to be written

# Returns

```
0 (OK), -1, -2, -3 (error, as usual in eventio)
```

## 7.38.2.30 write\_tel\_compact\_photons()

```
int write_tel_compact_photons (
    IO_BUFFER * iobuf,
    int array,
    int tel,
    double photons,
    struct compact_bunch * cbunches,
    int nbunches,
    int ext_bunches,
    char * ext_fname )
```

Write all the photon bunches for one telescope to an I/O buffer.

Usually, calls to this function for each telescope in an array should be enclosed within calls to begin\_write\_tel\_array() and end\_write\_tel\_array(). This routine writes the more compact format (16 bytes per bunch). The more compact format should usually be used to save memory and disk space.

## **Parameters**

iobuf	I/O buffer descriptor
array	array number
tel	telescope number
photons	sum of photons (and fractions) in this device
cbunches	list of photon bunches
nbunches	number of elements in bunch list
ext_bunches	number of elements in external file
ext_fname	name of external (temporary) file

# Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.38.2.31 write\_tel\_offset()

Write offsets of randomly scattered arrays with respect to shower core.

## **Parameters**

iobuf	I/O buffer descriptor
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays

Generated by Doxygen

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

References write\_tel\_offset\_w().

# 7.38.2.32 write\_tel\_offset\_w()

Write offsets and weights of randomly scattered arrays with respect to shower core.

With respect to the backwards-compatible non-weights version write\_tel\_offset(), this version adds a weight to each offset position which should be normalized in such a way that with uniform sampling it should be the area over which showers are thrown divided by the number of array in each shower. With importance sampling the same relation should hold on average. So in either case, the average sum of weights for the different offsets in one shower equals just the area over which cores are randomized. This leaves the possibility to change the number of offsets from shower to shower.

## **Parameters**

iobuf	I/O buffer descriptor
narray	Number of arrays of telescopes/detectors
toff	Time offset (ns, from first interaction to ground)
xoff	X offsets of arrays
yoff	Y offsets of arrays
weight	Area weight for uniform or importance sampled core offset.

### Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

Referenced by write tel offset().

## 7.38.2.33 write\_tel\_photons()

```
struct bunch * bunches,
int nbunches,
int ext_bunches,
char * ext_fname )
```

Write all the photon bunches for one telescope to an I/O buffer.

Usually, calls to this function for each telescope in an array should be enclosed within calls to begin\_write\_tel\_array() and end\_write\_tel\_array(). This routine writes the less compact format (32 bytes per bunch).

## **Parameters**

iobuf	I/O buffer descriptor
array	array number
tel	telescope number
photons	sum of photons (and fractions) in this device
bunches	list of photon bunches
nbunches	number of elements in bunch list
ext_bunches	number of elements in external file
ext_fname	name of external (temporary) file

## Returns

```
0 (o.k.), -1, -2, -3 (error, as usual in eventio)
```

# 7.38.2.34 write\_tel\_pos()

Write positions of telescopes/detectors within a system or array.

# **Parameters**

iobuf	I/O buffer descriptor
ntel	number of telescopes/detectors
X	X positions
У	Y positions
Z	Z positions
r	radius of spheres including the whole devices

#### Returns


0 (o.k.), -1, -2, -3 (error, as usual in eventio)

# 7.39 merge\_simtel.c File Reference

A program for merging events from separate telescope simulations of the same showers.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "history.h"
#include "io_hess.h"
#include "histogram.h"
#include "io_histogram.h"
#include "fileopen.h"
#include "straux.h"
#include "warning.h"
#include "io_trgmask.h"
#include "eventio_version.h"
#include <signal.h>
```

Include dependency graph for merge\_simtel.c:



## **Data Structures**

· struct map tel struct

Structure with per output telescope information keeping track of prerequisites.

# **Functions**

· void stop signal function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

int find\_in\_tel\_idx (int tel\_id, int ifile)

Offset of an input telescope of given ID within the input structures.

• int find\_out\_tel\_idx (int tel\_id, int ifile)

Offset of an input telescope of given ID within the output structures.

• int find\_mapped\_telescope (int tel\_id, int ifile)

Mapping from telescope ID on input to telescope ID on output, with check.

• int write\_io\_block\_to\_file (IO\_BUFFER \*iobuf, FILE \*f)

Write an I/O block as-is to another file than foreseen for the I/O buffer.

- int has\_min\_trg\_tel (AllHessData \*hsdata\_out, int mtrg, double rtm)
- int check\_for\_delayed\_write (IO\_ITEM\_HEADER \*item\_header, int ifile, AllHessData \*hsdata\_out, IO\_B
   UFFER \*iobuf out)
- int merge\_data\_from\_io\_block (IO\_BUFFER \*iobuf, IO\_ITEM\_HEADER \*item\_header, int ifile, AllHessData \*hsdata, AllHessData \*hsdata\_out, IO\_BUFFER \*iobuf\_out)

Processing and merging of I/O blocks from the two input files, hopefully presented in the right order.

• int check\_autoload\_trgmask (const char \*input\_fname, IO\_BUFFER \*iobuf, int ifile)

Check for a 'trgmask.gz' file matching the given input data file name and, if it exists, extract the corrected trigger bit patterns from it.

- void **print\_process\_status** (int prev\_type1, int this\_type1, int prev\_type2, int this\_type2)
- int read\_map (const char \*map\_fname)
- static void syntax (const char \*program)

Show program syntax.

int main (int argc, char \*\*argv)

Main program.

### **Variables**

- · static int interrupted
- static int verbose = 0
- struct map\_tel\_struct map\_tel [H\_MAX\_TEL]
- int map\_to [2][H\_MAX\_TEL+1]

Mapping structures from input telescope ID to output telescope ID.

int tel\_idx [2][H\_MAX\_TEL+1]

Mapping from telescope IDs to offsets in the data structures, first for input telescope IDs.

int tel\_idx\_out [H\_MAX\_TEL+1]

Mapping from output telescope ID to offset in output data structures.

- int ntel1
- int ntel2
- int ntel
- int nrtel1
- int nrtel2
- long event1 = -1
- long **event2** = 0
- long ev\_hess\_event = 0
- long ev pe sum = 0

For delayed writing.

- int run1 = -1
- int run2 = -1
- int min\_trg = 2
- double distinct\_sep = 1.0
- static struct trgmask\_set \* tms [2] = { NULL, NULL }
- static struct trgmask\_hash\_set \* ths [2] = { NULL, NULL }
- static int **events** [2] = { 0, 0 }
- static int **mcshowers** [2] = { 0, 0 }
- static int **mcevents** [2] = { 0, 0 }
- static int max\_list = 999

# 7.39.1 Detailed Description

A program for merging events from separate telescope simulations of the same showers.

The program will read sim\_telarray raw or DST data on two input files, map telescope ID according to a mapping file and write the merged blocks to an output file.

Inputs expected - and the action to be performed: Type Once per run: 70 (history) - Write as-is, impossible to merge 2000 (run header) - Merging needed for telescope list and positions 2001 (MC run header) - Only one of two MC run-headers needed (should be identical) 1212 (input config = CORSIKA inputs) - Only one needed (should be identical, duplicate) Once per telescope (and per run for raw & DST levels 0-2; just once for DST level 3) ← : 2002 (camera settings) - Write after mapping of telescope ID (if mapped) 2003 (camera organization) - Write after mapping of telescope ID (if mapped) 2004 (pixel settings) - Write after mapping of telescope ID (if mapped) 2005 (pixel disable) - Write after mapping of telescope ID (if mapped) 2006 (camera software settings) - Write after mapping of telescope ID (if mapped) 2008 (tracking settings) - Write after mapping of telescope ID (if mapped) 2007 (pointing corrections) - Write after mapping of telescope ID (if mapped) 2022 (telescope monitoring) - Write after mapping of telescope ID (if mapped) 2023 (Laser calibration) - Write after mapping of telescope ID (if mapped) Per shower: once: 2020 (MC shower) - Only one of two MC run-headers needed (should be identical) per array: 2021 (MC event) - Only one of two blocks needed (anything to get merged?) Optional per event; not immediately written but delayed until next MC etc. block: 2026 (MC pe sum) - ??? 1204 (photo-electrons individually) - ??? 2010 (event) - Needs remapping and merging at all levels At end of run: 2024 (run statistics - usually not present) 2025 (MC run statistics - usually not present) 100 (histograms) - Cannot be merged properly. Histograms of generated showers should agree, but for triggered showers we cannot tell how many are common.

FIXME: Ignoring 'trgmask' files initially - include them later on.

```
Syntax: merge_simtel [ options ] map-file input1 input2 output
Options:
    --auto-trgmask : Load trgmask.gz files for each input file where available.
    --min-trg-tel n : Require at least n telescopes in merged event (default: 2).
    --verbose : Show events being merged.

@author Konrad Bernloehr
@date @verbatim CVS $Date: 2017/05/16 12:31:52 $
```

## Version


```
CVS $Revision: 1.11 $
```

# 7.40 moments.c File Reference

Calculate mean, rms, skewness, and kurtosis of data.

#include "histogram.h"

Include dependency graph for moments.c:



### **Functions**

• MOMENTS \* alloc moments (HISTVALUE REAL low, HISTVALUE REAL high)

Allocate a structure for sums of powers of data.

void clear moments (MOMENTS \*mom)

Initialize an existing moments structure (except for its range limits).

void free\_moments (MOMENTS \*mom)

Deallocates memory previously allocated to a moments structure.

• void fill moments (MOMENTS \*mom, HISTVALUE REAL value)

Add up those things needed to compute mean, standard deviation, skewness, and kurtosis (both for all data and separately for data in a range defined in alloc\_moments().

• void fill\_mean\_and\_sigma (MOMENTS \*mom, HISTVALUE\_REAL value)

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc\_moments().

void fill\_mean (MOMENTS \*mom, HISTVALUE\_REAL value)

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc\_moments().

void fill\_real\_moments (MOMENTS \*mom, HISTVALUE\_REAL value, double weight)

Add up those things needed to compute – mean, – standard deviation, – skewness, and – kurtosis (both for all data and separately for data in a range defined in alloc\_moments().

void fill\_real\_mean\_and\_sigma (MOMENTS \*mom, HISTVALUE\_REAL value, double weight)

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc\_moments().

void fill\_real\_mean (MOMENTS \*mom, HISTVALUE\_REAL value, double weight)

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc\_moments().

• int stat moments (MOMENTS \*mom, struct momstat \*stmom)

Calculate moments (mean, rms, skewness, kurtosis) from the sums of powers of data values.

# 7.40.1 Detailed Description

Calculate mean, rms, skewness, and kurtosis of data.

**Author** 

Konrad Bernloehr

Date

1995 to 2010

Date

2011/02/28 09:56:42

Revision

1.3

# 7.40.2 Function Documentation

# 7.40.2.1 alloc\_moments()

Allocate a structure for sums of powers of data.

Returns NULL if no structure could be allocated.

# **Parameters**

low	Lower limit of range for truncation
high	Upper limit of range for truncation

## Returns

Pointer to allocated structure or NULL.

References clear\_moments().

# 7.40.2.2 clear\_moments()

Initialize an existing moments structure (except for its range limits).

## **Parameters**

Referenced by alloc\_moments().

# 7.40.2.3 fill\_mean()

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc\_moments().

## **Parameters**

	mom	Pointer to previously allocated MOMENTS structure.
ĺ	value	One measurement value

# 7.40.2.4 fill\_mean\_and\_sigma()

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc\_moments().

### **Parameters**

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value

# 7.40.2.5 fill\_moments()

Add up those things needed to compute mean, standard deviation, skewness, and kurtosis (both for all data and separately for data in a range defined in alloc\_moments().

## **Parameters**

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value

# 7.40.2.6 fill\_real\_mean()

Add up those things needed to compute – mean, (both for all data and separately for data in a range defined in alloc\_moments().

## **Parameters**

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value
weight	Weighting factor of this value

# 7.40.2.7 fill\_real\_mean\_and\_sigma()

Add up those things needed to compute – mean, – standard deviation, (both for all data and separately for data in a range defined in alloc\_moments().

## **Parameters**

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value
weight	Weighting factor of this value

## 7.40.2.8 fill\_real\_moments()

```
HISTVALUE_REAL value,
double weight )
```

Add up those things needed to compute – mean, – standard deviation, – skewness, and – kurtosis (both for all data and separately for data in a range defined in alloc\_moments().

## **Parameters**

mom	Pointer to previously allocated MOMENTS structure.
value	One measurement value
weight	Weighting factor of this value

# 7.40.2.9 free\_moments()

Deallocates memory previously allocated to a moments structure.

## **Parameters**

	mom	Pointer to previously allocated structure
--	-----	---

# 7.40.2.10 stat\_moments()

Calculate moments (mean, rms, skewness, kurtosis) from the sums of powers of data values.

# **Parameters**

mom	'moments' structure with the sums of the powers of data values (only 1st power if only mean to be calculated, also 2nd power if r.m.s. to be calculated, and also 3rd and 4th if skewness and kurtosis wanted.
stmom	Pointer to structure for computed moments

# Returns


```
0 (o.k.), -1 and -2 (invalid data)
```

# 7.41 read\_hess.c File Reference

A program reading simulated data, optionally analysing the data, and also optionally also writing summary ("DST") data.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "history.h"
#include "io_hess.h"
#include "histogram.h"
#include "io_histogram.h"
#include "fileopen.h"
#include "straux.h"
#include "rec_tools.h"
#include "reconstruct.h"
#include "user_analysis.h"
#include "warning.h"
#include "camera_image.h"
#include "basic_ntuple.h"
#include "io_trgmask.h"
#include "eventio_version.h"
#include <sys/time.h>
#include <strings.h>
#include <signal.h>
```

Include dependency graph for read\_hess.c:



## **Data Structures**

- struct next\_file\_struct
- struct range\_list\_struct

### **Macros**

• #define CALIB\_SCALE 0.92

The factor needed to transform from mean p.e.

- #define **\_XSTR**\_(s) **\_STR**\_(s)
- #define \_STR\_(s) #s
- #define **SHOW**(s) if ( strcmp(#s,\_XSTR\_(s)) != 0 ) printf(" " #s " = " \_XSTR\_(s) "\n" )

# **Typedefs**

- typedef struct next\_file\_struct NextFile
- typedef struct range\_list\_struct RangeList

## **Functions**

· void stop\_signal\_function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

- static void init\_rand (int is)
- · double grand48 (double mean, double sigma)

Like RandFlat() from rndm2.c but using the drand48 engine.

static void mc event fill (AllHessData \*hsdata, double d sp idx)

Fill histogram(s) for DST writing which require all MC shower and event data and which cannot be filled from DST level >= 2 data.

• static int write\_dst\_histos (IO\_BUFFER \*iobuf2)

Write histograms for DST book-keeping and clear them afterwards.

- static void show\_run\_summary (AllHessData \*hsdata, int nev, int ntrg, double plidx, double wsum\_all, double wsum trg, double rmax x, double rmax y, double rmax r)
- static void syntax (char \*program)

Show program syntax.

- NextFile \* add\_next\_file (const char \*fn, NextFile \*nxt)
- RangeList \* add range (long f, long t, RangeList \*rl)
- int is in range (long n, RangeList \*rl)
- int main (int argc, char \*\*argv)

Main program.

### **Variables**

- struct basic\_ntuple bnt
- static int interrupted
- static int dst\_processing
- static int g48\_set
- static double g48 next

# 7.41.1 Detailed Description

A program reading simulated data, optionally analysing the data, and also optionally also writing summary ("DST") data.

This program started as a skeleton for reading H.E.S.S. data in eventio format (which is what the read\_hess\_nr program is now intended for). The read\_hess program reads the whole range of hessio item types into a single tree of data structures but normally does nothing with the data.

It can be instructed to create nice camera images similar to those generated in sim hessarray.

It can also be instructed to redo the image cleaning (with the simple 10/5 tail-cut algorithm) and the shower reconstruction, writing ASCII output of the results.

In addition, it includes an interface for a full-scale analysis which can optionally be activated.

And finally, it can be instructed to extract DST-level data in order to reduce the amount of data by a large factor. This depends on the dst-level flag: 1) Remove all raw data (you cannot redo image cleaning) afterwards. 2) Remove also all MC data from non-triggered event (you should better stay with the spectral index used for DST extraction because you have to rely on its histograms for MC energy distribution). 3) and 4) Keep only user-defined events (with or without raw data).

```
read_hess: A program for viewing and analyzing sim_telarray (sim_hessarray) data.
Syntax: read_hess [ options ] [ - | input_fname ... ]
Options:
  -p ps_filename (Write a PostScript file with camera images.)
   --plot-with-true-pe (If data available, include true p.e. plot in PS file.)
  --plot-with-sum-only (Show only sum image even if we have traces.)
  --plot-with-pixel-id (Show pixel ID number on top of pixel.)
   --plot-with-pixel-amp (Show pixel amplitude value on top of pixel.)
   --plot-with-pixel-pe (Show count of true Cherenkov p.e. on top of pixel.)
  --plot-without-reco (Do not show reconstructed image/shower parameters.)
   --plot-with-title text (User-defined title on top of page.)
                   (Use 10/5 tail-cut image cleaning and redo reconstruction.)
  -r level
                   level >= 1: show parameters from sim_hessarray.
                   level >= 2: redo shower reconstruction
                   level >= 3: redo image cleaning (and shower reconstruction
                               with new image parameters)
                   level >= 4: redo amplitude summation
                   level >= 5: PostScript file includes original and
                              new shower reconstruction.
   -v
                   (More verbose output)
                   (Much more quiet output)
   -q
   -8
                   (Show data explained)
                   (Show data explained, including raw data)
  -s
   --history (-h) (Show contents of history data block)
   --clean-history (Drop previous history data blocks)
  - i
                   (Ignore unknown data block types)
                   (Call user-defined analysis function)
   --global-peak
                   (For image analysis use amplitude sums around global peak
                    in 'on-line' pulse shape analysis.)
   --local-peak
                   (For image analysis use amplitude sums around local peaks
                    in 'on-line' pulse shape analysis.)
   --powerlaw x
                   (Use this spectral index for events weights in output.)
                   (Default spectral index is -2.7)
   --only-run run1[,run2-run3[,...]] (Select runs being processed.)
   --not-run run1[,run2-run3[,...]]
   --only-telescope id1[,id2-i3[,...]] (Select telescopes being used.)
   --not-telescope id1[,id2-id3[,...]]
   --auto-trgmask (Automatically load matching .trgmask.gz files.)
  --trgmask-path dir (Search the trgmask files in this path first.)
   --trg-required b *(Required trigger bits, e.g. 5=1|4 -> majo or asum)
   --type nt[,id1,id2,A,f,npix] (Set [requirements for] telescope type nt.)
  --focal-length f \star (Set telescope imaging effective focal length [m].)
   --min-tel tmn *(The minimum number of tel. images required in analysis.)
   --max-tel tmx (The maximum number of tel. images required in analysis.)
   --min-trg-tel n (Minimum number of telescopes in system trigger.)
   --hard-stereo id1,id2,.. (Telescope of ID id1 etc. only use if stereo.)
   --min-amp npe
                  *(Minimum image amplitude for shower reconstruction.)
                  *(Minimum number of pixels for shower reconstruction.)
   --min-pix npix
   --max-events n (Skip remaining data after so many triggered events.)
   --max-theta d
                  (Maximum angle between source and shower direction [deg].)
   --min-theta d
                   (Where cut angle is multiplicity dependent, use this
                   as the lower limit [deg].)
   --theta-scale f (Scale fixed and optimized theta cut by this factor.)
   --theta-E-scale t0,ts,min,max (Energy-dependent scaling beyond multiplicity.)
  --tail-cuts l,h[,n,f] \star (Low and high level tail cuts to be applied in analysis.)
   --nb-radius r1[,r2[,r3]] *(Maximum distance of neighbour pixels [px diam.])
   --ext-radius r \star (Radius to extend preserved pixels beyond cleaning [px diam.])
  --dE2-cut c
                  (Cut parameter for dE2 cut.)
   --hess-standard-cuts (Apply HESS-style selection with standard cuts.)
   --hess-hard-cuts (Apply HESS-style selection with hard cuts.)
  --hess-loose-cuts (Apply HESS-style selection with loose cuts.)
   --hess-style-cuts (No shape parameter rescaling as HESS-style.)
   --shape-cuts wmn, wmx, lmn, lmx (Shape cut parameters: mscrw/l min/max).
                  (Scale parameter for dE cut strictness, def=1.0).
   --hmax-cut c
                  (Scale parameter for hmax cut strictness, def=1.0).
   --\min-img-angle a (Only use image pairs intersecting at angle > a deg, def=0).
                 *(Do not use round images with disp = (1-w/1) < d, def=0).
   --max-core-distance r *(Only use images from telescope not further from core).
   --impact-range r,x,y (Accept only events with reconstructed core in range).
   --true-impact-range r,x,y (Accept only events with true core in range).
                   Note that r is in shower plane but x, y ranges are on surface.
   --min-true-energy e (Completely skip events below given true energy.
```

```
--clip-camera-radius r *(In image reconstruction clip camera at radius r deg.)
  --clip-camera-diameter d \star (Same as before but with diameter d deg.)
  --clip-pixel-amplitude a *(Calibrated pixel ampl. does not exceed a mean p.e.)
   --only-high-gain (Use only high-gain channel and ignore low gain.)
   --only-low-gain (Use only low-gain channel and ignore high gain.)
   --max-events (Stop after having processed this many events.)
   --pure-raw
                  (Discard any sub-items of TelescopeEvent which are not raw data.)
   --no-mc-data
                  (Discard MC shower and MC event data.)
   --broken-pixels-fraction (Add random broken/dead pixels on run-by-run basis.)
   --dead-time-fraction (Set telescopes randomly as dead from prior triggers.)
   --integration-scheme n *(Set the integration scheme for sample-mode data.
                   Use '--integration-scheme help' to show available schemes.)
   --integration-window w,o[,ps] *(Set integration window width and offset.)
                   For some integration schemes there is a pulse shaping option.
   --integration-treshold h[,1] *(Set significance thresholds for integration.)
   --integration-no-rescale *(Don't rescale pulse sum for integration with
                  windows narrower than a single-p.e. pulse.)
  --integration-rescale *(Rescale for single-p.e. fraction in window; default)
  --calib-scale f *(Rescale from mean p.e. to experiment units. Default: 0.92)
   --calib-error f (Random pixel relative calibration error. Default: 0.)
   --calibrate
                  (Store calibrated pixel intensities to DST file, if possible.)
   --only-calibrated (Like '--calibrate' but omit raw data from DST.)
   --diffuse-mode (True shower position assumed as source position.)
  --random-seed n|auto (Initialize random number generator.)
   --off-axis-range al,a2 (Only for diffuse mode, restricting range in deg.)
                  (Automatically generate lookup table (gammas only).)
   --aut.o-lookup
   --lookup-file name (Override automatic naming of lookup files.)
   --cleaning n (Imaging cleaning setting: 0=no, 1-5=yes, see '--cleaning help')
   --zero-suppression n (Zero suppression scheme; 0: off, 3=auto)
                   (Equivalent to '--zero-suppression auto')
   --dst-level n
                  (Level of data reduction when writing DST-type output.)
                   Valid levels: 0, 1, 2, 3, 10, 11, 12, 13.
                   Raw data is stripped off at all levels except 0 and 10.
                   Level 0 has any sample mode data reduced to sums,
                   Level 1 includes all MC shower/event blocks,
                   level 2 only for triggered events,
                   level 3 has many config/calib blocks only once, not per run.
                   Levels 10-13 include only selected gamma-like events.
   --raw-level n
                   (Re-write original raw data or processed data, with possible
                   selection or reduction of other data according to level.)
                   Level 0 has all data written as available.
                   Level 1 has MC data only for triggered events.
                   Level 2 has no MC data (--no-mc-data).
                   Level 3 has only raw data for telescopes and nothing else (--pure-raw).
                   Level 4 also cleans past history data (--clean-history).
   --dst-file name (Name of output file for DST-type output.)
                  A DST file is needed for cleaning > 0 or DST level >= 0.
   --output-file
                  (Synonym to --dst-file)
   --histogram-file name (Name of histogram file.)
                  (Get list of input file names from fname.)
Parameters followed by a '\star' can be type-specific if preceded by a
'--type' option. Their interpretation is thus position-dependent.
@author Konrad Bernloehr
        @verbatim CVS $Date: 2018/03/27 14:33:26 $
Version
```

This program started as a skeleton for reading H.E.S.S. data in eventio format (which is what the read\_hess\_nr program is now intended for). The read\_hess program reads the whole range of hessio item types into a single tree of data structures but normally does nothing with the data.

It can be instructed to create nice camera images similar to those generated in sim\_hessarray.

CVS \$Revision: 1.141 \$

It can also be instructed to redo the image cleaning (with the simple 10/5 tail-cut algorithm) and the shower reconstruction, writing ASCII output of the results.

In addition, it includes an interface for a full-scale analysis which can optionally be activated.

And finally, it can be instructed to extract DST-level data in order to reduce the amount of data by a large factor. This depends on the dst-level flag: 1) Remove all raw data (you cannot redo image cleaning) afterwards. 2) Remove also all MC data from non-triggered event (you should better stay with the spectral index used for DST extraction because you have to rely on its histograms for MC energy distribution). 3) and 4) Keep only user-defined events (with or without raw data).

```
Syntax: read_hess [ options ] [ - | input_fname ... ]
Options:
   -p ps_filename (Write a PostScript file with camera images.)
   -r level
                   (Use 10/5 tail-cut image cleaning and redo reconstruction.)
                   level >= 1: show parameters from sim_hessarray.
                   level >= 2: redo shower reconstruction
                   level >= 3: redo image cleaning (and shower reconstruction
                               with new image parameters)
                   level >= 4: redo amplitude summation
                   level >= 5: PostScript file includes original and
                               new shower reconstruction.
   -77
                   (More verbose output)
                   (Much more quiet output)
   -a
                   (Show data explained)
   -s
   -S
                   (Show data explained, including raw data)
   --history (-h) (Show contents of history data block)
   - i
                   (Ignore unknown data block types)
                   (Call user-defined analysis function)
   --global-peak
                  (For image analysis use amplitude sums around global peak
                    in 'on-line' pulse shape analysis.)
   --local-peak (For image analysis use amplitude sums around local peaks
                    in 'on-line' pulse shape analysis.)
   --powerlaw x
                   (Use this spectral index for events weights in output.)
                   (Default spectral index is -2.7)
   --only-telescope id1[,id2[,...]]
   --not-telescope id1[,id2[,...]]
   --min-tel tmn (The minimum number of tel. images required in analysis.)
   --max-tel tmx (The maximum number of tel. images required in analysis.)
   --min-trg-tel n (Minimum number of telescopes in system trigger.)
   --min-amp npe (Minimum image amplitude for shower reconstruction.)
   --min-pix npix (Minimum number of pixels for shower reconstruction.)
   --max-events n (Skip remaining data after so many triggered events.)
--max-theta d (Maximum angle between source and shower direction [d
                   (Maximum angle between source and shower direction [deg].)
   --theta-scale f (Scale fixed and optimized theta cut by this factor.)
   --theta-E-scale t0,ts,min,max (Energy-dependent scaling beyond multiplicity.)
   --tail-cuts l,h[,n,f] (Low and high level tail cuts to be applied in analysis.)
   --dE2-cut c (Cut parameter for dE2 cut.)
   --hess-standard-cuts (Apply HESS-style selection with standard cuts.)
   --hess-hard-cuts (Apply HESS-style selection with hard cuts.)
   --hess-loose-cuts (Apply HESS-style selection with loose cuts.)
   --hess-style-cuts (No shape parameter rescaling as HESS-style.)
   --shape-cuts wmn,wmx,lmn,lmx (Shape cut parameters: mscrw/l min/max).
   --dE-cut c
                  (Scale parameter for dE cut strictness, def=1.0).
   --hmax-cut c (Scale parameter for hmax cut strictness, def=1.0).
   --clip-camera-radius r \star (In image reconstruction clip camera at radius r deg.)
   --clip-camera-diameter d \star (Same as before but with diameter d deq.)
   --auto-lookup
                  (Automatically generate lookup table (gammas only).)
   --lookup-file name (Override automatic naming of lookup files.)
   --dst-level n
                  (Level of data reduction when writing DST-type output.)
                   Valid levels: 1, 2, 3, 10, 11, 12, 13.
                   Raw data is stripped off at all levels except 10.
                   Level 1 includes all MC shower/event blocks,
                   level 2 only for triggered events,
                   level 3 has many config/calib blocks only once, not per run.
                   Levels 10-13 include only selected gamma-like events.
   --dst-file name (Name of output file for DST-type output.)
   --dst-process (Telescope configuration etc. may appear only once.)
   -f fname
                   (Get list of input file names from fname.)
Parameters followed by a ' \, \star ' can be type-specific if preceded by a
'--type' option. Their interpretation is thus position-dependent.
```

```
@author Konrad Bernloehr
@date @verbatim CVS $Date: 2010/03/19 18:09:32 $
```

### Version


```
CVS $Revision: 1.76 $
```

# 7.42 read\_hess\_nr.c File Reference

# A skeleton program reading H.E.S.S.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "history.h"
#include "io_hess.h"
#include "histogram.h"
#include "io_histogram.h"
#include "fileopen.h"
#include "straux.h"
#include "rec_tools.h"
#include "warning.h"
#include "camera_image.h"
#include <signal.h>
```

Include dependency graph for read\_hess\_nr.c:



### **Macros**

- #define \_UNUSED\_
- #define CALIB\_SCALE 0.92

The factor needed to transform from mean p.e.

# **Functions**

- double calibrate\_pixel\_amplitude (AllHessData \*hsdata, int itel, int ipix, int dummy, double cdummy)

  Calibrate a single pixel amplitude, for cameras with two gains per pixel.

- void stop\_signal\_function (int isig)
  - Stop the program gracefully when it catches an INT or TERM signal.
- static void **show\_run\_summary** (AllHessData \*hsdata, int nev, int ntrg, double plidx, double wsum\_all, double wsum\_trg, double rmax\_x, double rmax\_y, double rmax\_r)
- static void syntax (char \*program)

Show program syntax.

int main (int argc, char \*\*argv)

Main program.

## **Variables**

· static int interrupted

# 7.42.1 Detailed Description

A skeleton program reading H.E.S.S.

data.

As a skeleton for programs reading H.E.S.S. data in eventio format, this program reads the whole range of hessio item types into a single tree of data structures but normally does nothing with the data.

It can be instructed, though, to create nice camera images similar to those generated in sim\_hessarray.


```
Syntax: read_hess_nr [ options ] [ - | input_fname ... ]
Options:
  -p ps_filename (Write a PostScript file with camera images.)
  -r level
                   (Reconstruction level not fully used in this program version.)
                   level >= 1: show parameters from sim_hessarray.
                   (More verbose output)
                   (Much more quiet output)
  -q
   -s
                   (Show data explained)
  -S
                   (Show data explained, including raw data)
   --history (-h) (Show contents of history data block)
  – i
                   (Ignore unknown data block types)
  -u
                   (Call user-defined analysis function)
   --powerlaw x
                   (Use this spectral index for events weights in output.)
                   (Default spectral index is -2.7)
   --max-events n (Skip remaining data after so many triggered events.)
@author Konrad Bernloehr
@date
        @verbatim CVS $Date: 2011/07/21 16:07:26 $
Version
```

# 7.43 rec\_tools.h File Reference

CVS \$Revision: 1.16 \$

Tools for shower geometric reconstruction.

This graph shows which files directly or indirectly include this file:



## **Functions**

void angles\_to\_offset (double obj\_azimuth, double obj\_altitude, double azimuth, double altitude, double focal length, double \*xoff, double \*yoff)

Transform telescope and object Alt/Az to offset in camera.

• void offset\_to\_angles (double xoff, double yoff, double azimuth, double altitude, double focal\_length, double \*obj\_azimuth, double \*obj\_altitude)

Transform from offset in camera to corresponding Az/Alt.

• void get\_shower\_trans\_matrix (double azimuth, double altitude, double trans[][3])

Calculate transformation matrix.

• void cam\_to\_ref (double ximg, double yimg, double phi, double ref\_azimuth, double ref\_altitude, double cam\_rot, double azimuth, double altitude, double focal\_length, double \*axref, double \*ayref, double \*phiref)

Transform from one camera to common reference frame.

• int intersect\_lines (double xp1, double yp1, double phi1, double xp2, double yp2, double phi2, double \*xs, double \*ys, double \*sang)

Intersect pairs of lines.

• int shower\_geometric\_reconstruction (int ntel, const double \*amp, const double \*ximg, const double \*yimg, const double \*phi, const double \*disp, const double \*xtel, const double \*ytel, const double \*ztel, const double \*ztel, const double \*at, const double \*flen, const double \*cam\_rot, double ref\_az, double ref\_alt, int flag, double \*shower\_az, double \*shower\_alt, double \*var\_dir, double \*xc, double \*yc, double \*var\_core)

Simple reconstruction by intersecting pairs of lines.

· double angle between (double azimuth1, double altitude1, double azimuth2, double altitude2)

Calculate the angle between two directions given in spherical coordinates.

double line\_point\_distance (double xp1, double yp1, double zp1, double cx, double cx, double cz, double x, double y, double z)

Distance between a straight line and a point in space.

# 7.43.1 Detailed Description

Tools for shower geometric reconstruction.

Shower geometric reconstruction based on the major axes of the telescope images. The image parameters from each telescope are transformed to a common reference frame first before the average intersection point of all images is calculated in plane coordinates.

### **Author**

Konrad Bernloehr

### Date

```
2000, 2009
```

```
CVS $Date: 2014/05/07 13:08:25 $
```

# Version

```
CVS $Revision: 1.17 $
```

### 7.43.2 Function Documentation

## 7.43.2.1 angle\_between()

Calculate the angle between two directions given in spherical coordinates.

### Returns

The angle between the two directions in units of radians.

## 7.43.2.2 angles\_to\_offset()

Transform telescope and object Alt/Az to offset in camera.

Transform from given telescope and object angles (Az/Alt) to the offset the object has in the camera plane.

Transform from given telescope and object angles (Az/Alt) to the offset the object has in the camera plane.

This does not account for any rotation of the camera and its pixels.

Referenced by cam\_to\_ref().

## 7.43.2.3 cam\_to\_ref()

Transform from one camera to common reference frame.

Transform from the camera plane coordinate system of a telescope looking to altitude/azimuth to a plane coordinate system of a potential telescope looking to a reference direction ref\_azimuth,ref\_altitude and having unit focal length. Rotation of image angles is accounted for but not imaging errors.

References angles\_to\_offset(), and offset\_to\_angles().

## 7.43.2.4 get\_shower\_trans\_matrix()

Calculate transformation matrix.

Calculate transformation matrix from horizontal reference frame to one z axis in the given Az/Alt direction and the x axis in the plane defined by Az/Alt and zenith.

# 7.43.2.5 intersect\_lines()

Intersect pairs of lines.

Intersect a pair of straight lines in a plane and return the intersection point and the angle at which the lines intersect.

# 7.43.2.6 line\_point\_distance()

Distance between a straight line and a point in space.

## **Parameters**

xp1,yp1,zp1	reference point on the line
cx,cy,cz	direction cosines of the line
x,y,z	point in space

Returns

distance

References main().

Referenced by mc\_event\_fill(), and user\_mc\_event\_fill().

# 7.43.2.7 offset\_to\_angles()

Transform from offset in camera to corresponding Az/Alt.

Transform from the offset an object or image has in the camera plane of a telescope to the corresponding Az/Alt.

Transform from the offset an object or image has in the camera plane of a telescope to the corresponding Az/Alt.

This does not account for any rotation of the camera and its pixels. (xoff and yoff are assumed to be corrected for camera rotation).

Referenced by cam\_to\_ref().

# 7.43.2.8 shower\_geometric\_reconstruction()

```
int shower_geometric_reconstruction (
             int ntel,
             const double * amp,
             const double * ximq,
             const double * yimg,
             const double * phi,
             const double * disp,
             const double * xtel,
             const double * ytel,
             const double * ztel,
             const double * az,
             const double * alt,
             const double * flen,
             const double * cam_rot,
             double ref_az,
             double ref_alt,
             int flag,
             double * shower_az,
             double * shower_alt,
```

```
double * var_dir,
double * xc,
double * yc,
double * var_core )
```

Simple reconstruction by intersecting pairs of lines.

Simple geometric shower reconstruction by intersecting pairs of straigh lines (from major axis of second moments ellipses after transformation to a common plane), first for the shower direction and then for the core position. No errors on reconstructed direction or core position are calculated. This should sooner or later be superceded by a fit procedure taking advantage of estimated errors on image positions and angles.

#### **Parameters**


ntel	The number of telescopes with suitable images.
amp	The image amplitudes in each suitable telescope [p.e.].
ximg	The image c.o.g. x positions in the local camera coordinate systems.
yimg	The image c.o.g. y positions in the local camera coordinate systems.
phi	The image major axis direction [rad].
disp	The DISP parameter (1width/length), used for giving preference to elongated images. Set all to 1.0 if unknown or no preference wanted. Can also be passed as a NULL pointer instead.
xtel	The x coordinate of the telescope positions within array [m].
ytel	The y coordinate of the telescope positions within array [m].
ztel	The z coordinate of the telescope positions within array [m].
az	The azimuth angles to which the telescopes are pointing (N->E->S->W) [rad].
alt	The altitude angles to which the telescopes are pointing [rad].
flen	The focal length to which ximg and yimg are scaled (1.0 if in units of radians, otherwise flen is in meters).
cam_rot	Camera rotation angle [rad].
ref_az	The reference azimuth angle (system nominal azimuth) [rad].
ref_alt	The reference altitude angle (system nominal altitude) [rad].
flag	Use the reconstructed direction to derive the core position (0) or use the nominal direction for that (1 or any other non-zero). The second version may sightly improve core distance and thus energy accuracy for well-defined point sources.
shower_az	Return the reconstructed shower azimuth angle (N->E->S->W) [rad].
shower_alt	Return the reconstructed shower altitude angle [rad].
var_dir	Variance (dx**2+dy**2)/ntel of reconstructed direction for more than two images. Can be NULL if you are not interested in it.
XC	Return the reconstructed core position x coordinate (at z=0) [m].
ус	Return the reconstructed core position y coordinate (at z=0) [m].
var_core	Variance (dx**2+dy**2)/ntel of reconstructed core position for more than two images. Can be NULL if you are not interested in it.

# 7.44 reconstruct.c File Reference

Second moments type image analysis.

```
#include "initial.h"
#include "io_hess.h"
#include "rec_tools.h"
```

#include "reconstruct.h"
#include "user\_analysis.h"
Include dependency graph for reconstruct.c:



### **Data Structures**

· struct camera\_nb\_list

### **Macros**

- #define CALIB SCALE 0.92
  - The factor needed to transform from mean p.e.
- #define H\_MAX\_NB 50
- #define WITH PZPSA 1

## **Functions**

- int allocate\_nb\_list (int itel, int npix, int shape\_type, int nnbs, int \*nbs)
- int deallocate\_nb\_list (int itel)
- int set disabled pixels (AllHessData \*hsdata, int itel, double broken pixels fraction)

Set up pixels to be ignored (regarded as zero amplitude) in the analysis if they either have HV disabled or the camera active radius is clipped.

- static int guess\_pixel\_shape (CameraSettings \*camset, int itel)
  - Guess the common pixel shape type from relative positions of neighbours.
- static int find\_neighbours (CameraSettings \*camset, int itel)

Find the list of neighbours for each pixel.

- int store\_camera\_radius (CameraSettings \*camset, int itel)
- double get\_camera\_radius (int itel, int maxflag)
- void select\_calibration\_channel (int chn)

Control if only low-gain or high-gain should get used instead of both.

- int calibrate\_amplitude (AllHessData \*hsdata, int itel, int flag\_amp\_tm, double clip\_amp)
  - Calibrate amplitudes in all pixels of a camera.
- double calibrate\_pixel\_amplitude (AllHessData \*hsdata, int itel, int ipix, int flag\_amp\_tm, int itime, double clip\_amp)

Calibrate a single pixel amplitude.

- static int simple\_integration (AllHessData \*hsdata, int itel, int nsum, int nskip)
  - Integrate sample-mode data (traces) over a common and fixed interval.
- static int global\_peak\_integration (AllHessData \*hsdata, int itel, int nsum, int nbefore, int \*sigamp)

Integrate sample-mode data (traces) over a common interval around a global signal peak.

• static int local\_peak\_integration (AllHessData \*hsdata, int itel, int nsum, int nbefore, int \*sigamp)

Integrate sample-mode data (traces) around a pixel-local signal peak.

• static int nb\_peak\_integration (AllHessData \*hsdata, int lwt, int itel, int nsum, int nbefore, int \*sigamp)

Integrate sample-mode data (traces) around a peak in the signal sum of neighbouring pixels.

static int gradient\_integration (AllHessData \*hsdata, int itel, int nsum, int nbefore, int \*sigamp)

Fit gradient of pixel pulse peak times along image and evaluate the fitted line for getting the time around which pulses get integrated.

static int PzpsaSmoothUpsampleU16 (int n, int us, uint16\_t \*ip, double bl, double pz, double \*op, double \*max, int \*at)

Upsample (expand the n input values to us samples each) Subtract baseline bl and correct for a single pole decay with the decay time pz and smooth the resulting trace with two moving averages with a width of us.

static double PzpsaPeakProperty (int n, double \*in, int pos, int w, double \*intsum, double \*cog)

Calculates the peak property of the signal in (n samples) at position pos.

static int nb\_fc\_shaped\_peak\_integration (AllHessData \*hsdata, int itel, int nsum, int nbefore, int \*sigamp, int psopt, int ithr)

Pulse integration based on peaks in neighbour pixel signals after FlashCam-style pulse shaping.

static double qpol (double x, int np, double \*yval)

Quick interpolation in array of points equidistant in x coordinate.

static int set integration correction (AllHessData \*hsdata, int itel, int integrator, int \*intpar)

With partial pulse integration we extract a correction factor from partial to full pulse area from the reference pulse shape provided by MC.

static int pixel\_integration (AllHessData \*hsdata, int itel, struct user\_parameters \*up)

Pixel integration steering function.

• static int clean image tailcut (AllHessData \*hsdata, int itel, double al, double ah, int Iref, double minfrac)

Use dual-level tail-cut image cleaning procedure to get pixel list.

static int second\_moments (AllHessData \*hsdata, int itel, int cut\_id, int nimg, double clip\_amp)

Reconstruction of second moments parameters from cleaned image.

• static int pixel\_timing\_analysis (AllHessData \*hsdata, int itel, int nimg)

Calculate summary results from pixel timing data.

• static int image\_reconstruct (AllHessData \*hsdata, int itel, int cut\_id, double tcl, double tch, int lref, double minfrac, int nimg, int flag\_amp\_tm, double clip\_amp)

Calibrate and clean image pixels and reconstruct second moments parameters from images.

- int clean\_raw\_data (AllHessData \*hsdata, int itel, int clean\_flag, int tcl, int tch, struct user\_parameters \*up)
- static int shower\_reconstruct (AllHessData \*hsdata, const double \*min\_amp\_tel, const size\_t \*min\_pix\_tel, int cut\_id)

Shower reconstruction (geometrical reconstruction only)

 int reconstruct (AllHessData \*hsdata, int reco\_flag, const double \*min\_amp, const size\_t \*min\_pix, const double \*tcl, const double \*tch, const int \*lref, const double \*minfrac, int nimg, int flag\_amp\_tm, int clean\_← flag)

Image/shower reconstruction function.

void set reco verbosity (int v)

## **Variables**

- static int px\_shape\_type [H\_MAX\_TEL]
- static struct camera\_nb\_list nb\_lists [H\_MAX\_TEL][3]

To be filled with up to 3 neighbour lists for each telescope.

• static struct camera\_nb\_list ext\_list [H\_MAX\_TEL]

Optional extension lists beyond image cleaning.

- static int image\_list [H\_MAX\_TEL][H\_MAX\_PIX]
- static int image\_numpix [H MAX TEL]
- static double pixel\_amp [H\_MAX\_TEL][H\_MAX\_PIX]

- static int show\_total\_amp = 0
- static int pixel\_sat [H\_MAX\_TEL]
- static char pixel\_disabled [H\_MAX\_TEL][H\_MAX\_PIX]
- static int any\_disabled [H MAX TEL]
- static double camera\_radius\_eff [H\_MAX\_TEL]
- static double camera\_radius\_max [H\_MAX\_TEL]
- static double integration\_correction [H\_MAX\_TEL][H\_MAX\_GAINS]
- static int verbosity = 0
- static int no low gain = 0
- static int **no\_high\_gain** = 0

## 7.44.1 Detailed Description

Second moments type image analysis.

Date

```
CVS $Revision: 1.70 $
```

Version

```
CVS $Date: 2017/06/07 14:33:27 $
```

## 7.44.2 Macro Definition Documentation

## 7.44.2.1 CALIB\_SCALE

```
#define CALIB_SCALE 0.92
```

The factor needed to transform from mean p.e.

units to units of the single-p.e. peak: Depends on the collection efficiency, the asymmetry of the single p.e. amplitude distribution and the electronic noise added to the signals. Default value is for HESS.

# 7.44.3 Function Documentation

# 7.44.3.1 calibrate\_amplitude()

Calibrate amplitudes in all pixels of a camera.

This function is operating only on pulse sums, either from normal raw data or from timing/pulse shape analysis. Use calibrate\_pixel\_amplitude() for calibration of individual samples.

## **Parameters**

hsdata	Pointer to all available data and configurations.
itel	Index of telescope in the relevant arrays (not the ID).
flag_amp_tm	0: Use normal integrated amplitude. 1: Use integration around global peak position from pulse shape analysis. May include all pixels or only selected. 2: Use integration around local peak position from pulse shape analysis. Return 0 for pixels without a fairly significant peak.
clip_amp	if >0, any calibrated amplitude is clipped not to exceed this value [mean p.e.].

References camera\_nb\_list::npix, and hess\_camera\_settings\_struct::num\_pixels.

Referenced by image\_reconstruct().

# 7.44.3.2 calibrate\_pixel\_amplitude()

Calibrate a single pixel amplitude.

## **Parameters**

hsdata	Pointer to all available data and configurations.
itel	Index of telescope in the relevant arrays (not the ID).
ipix	The pixel number (0 npix-1).
flag_amp_tm	0: Use normal integrated amplitude. 1: Use integration around global peak position from pulse shape analysis. May include all pixels or only selected. 2: Use integration around local peak position from pulse shape analysis. Return 0 for pixels without a fairly significant peak.
itime	-1: sum of samples of type as given in flag_amp_tm 0(nsamples-1): sample data (if available) for one time slice
clip_amp	if $>$ 0, any calibrated amplitude is clipped not to exceed this value [mean p.e.].

## Returns

Pixel amplitude in peak p.e. units (based on conversion factor from H.E.S.S.).

References camera\_nb\_list::npix.

# 7.44.3.3 clean\_image\_tailcut()

```
int itel,
double al,
double ah,
int lref,
double minfrac ) [static]
```

Use dual-level tail-cut image cleaning procedure to get pixel list.

In contrast to the classical dual-level tail-cuts this function has an optional restriction to only those pixels having an amplitude above a given fraction of the n-th hottest pixel. This should almost stop the increase of width and length with increasing intensity after some point.

### **Parameters**

hsdata	Pointer to all available data and configurations.
itel	Sequence number of the telescope being processed.
al	The lower of the two tail-cut thresholds.
ah	The higher of the two tail-cut thresholds.
Iref	Determines which pixel, after sorting by amplitude, will be used as providing the reference amplitude. Example: use 3 for the third hottest pixel. If this number is <= 0, the classical scheme is used.
minfrac	Which fraction of the reference amplitude is required for pixels to be included in the final image. If this number is $\leq 0.0$ , the classical scheme is used.

Referenced by image\_reconstruct(), and pixel\_integration().

# 7.44.3.4 find\_neighbours()

Find the list of neighbours for each pixel.

< Temporary neighbour lists for one telescope.

Referenced by image\_reconstruct(), and nb\_peak\_integration().

# 7.44.3.5 global\_peak\_integration()

Integrate sample-mode data (traces) over a common interval around a global signal peak.

The integration window can be anywhere in the available length of the traces. Since the calibration function subtracts a pedestal that corresponds to the total length of the traces we may also have to add a pedestal contribution for the samples not summed up. No weighting of individual samples is applied.

### **Parameters**

hsdata	Pointer to all available data and configurations.
itel	Sequence number of the telescope being processed.
nsum	Number of samples to sum up (is reduced if exceeding available length).
nbefore	Start the integration a number of samples before the peak, as long as it fits into the available data range. Note: for multiple gains, this results in identical integration regions.
sigamp	Amplitude in ADC counts above pedestal at which a signal is considered as significant (separate for high gain/low gain).

Referenced by pixel\_integration(), and simple\_integration().

# 7.44.3.6 gradient\_integration()

Fit gradient of pixel pulse peak times along image and evaluate the fitted line for getting the time around which pulses get integrated.

There are basically three problems: a) bootstrap problem for finding significant pixels, b) robustness of the fit in case of pixels that don't follow the time gradient, and c) what to do with pixels that have a large enough signal at a time not consistent with the fitted line.

References H\_MAX\_TEL, hess\_tel\_event\_adc\_struct::known, hess\_tel\_event\_adc\_struct::num\_samples, Pzpsa SmoothUpsampleU16(), hess\_tel\_event\_data\_struct::raw, and hess\_event\_data\_struct::teldata.

Referenced by nb\_peak\_integration(), and pixel\_integration().

## 7.44.3.7 image\_reconstruct()

Calibrate and clean image pixels and reconstruct second moments parameters from images.

References calibrate\_amplitude(), clean\_image\_tailcut(), hess\_tel\_image\_struct::cut\_id, find\_neighbours(), H \cdots MAX\_TEL, hess\_tel\_event\_data\_struct::img, hess\_tel\_event\_adc\_struct::known, hess\_tel\_image\_struct::known, nb\_lists, camera\_nb\_list::nblist, hess\_tel\_event\_data\_struct::num\_image\_sets, pixel\_timing\_analysis(), hess\_tel event\_data\_struct::raw, second\_moments(), and hess\_event\_data\_struct::teldata.

Referenced by pixel\_timing\_analysis().

## 7.44.3.8 local\_peak\_integration()

Integrate sample-mode data (traces) around a pixel-local signal peak.

The integration window can be anywhere in the available length of the traces. Since the calibration function subtracts a pedestal that corresponds to the total length of the traces we may also have to add a pedestal contribution for the samples not summed up. No weighting of individual samples is applied.

#### **Parameters**

hsdata	Pointer to all available data and configurations.
itel	Sequence number of the telescope being processed.
nsum	Number of samples to sum up (is reduced if exceeding available length).
nbefore	Start the integration a number of samples before the peak, as long as it fits into the available data range. Note: for multiple gains, this may result in identical integration regions (depending on signal).
sigamp	Amplitude in ADC counts above pedestal at which a signal is considered as significant (separate for high gain/low gain).

References hess\_tel\_event\_adc\_struct::adc\_known, hess\_tel\_event\_adc\_struct::adc\_sample, hess\_tel\_event = \_adc\_struct::adc\_sum, H\_MAX\_TEL, HI\_GAIN, hess\_tel\_event\_adc\_struct::known, LO\_GAIN, nb\_peak\_= integration(), hess\_tel\_event\_adc\_struct::num\_gains, hess\_tel\_event\_adc\_struct::num\_pixels, hess\_tel\_event = \_adc\_struct::num\_samples, hess\_tel\_event = \_adc\_struct::raw, hess\_tel\_event = \_adc\_struct::significant, hess\_event\_data\_struct::teldata, and hess\_tel\_event\_adc\_struct::zero\_sup\_mode.

Referenced by pixel\_integration().

# 7.44.3.9 nb\_fc\_shaped\_peak\_integration()

Pulse integration based on peaks in neighbour pixel signals after FlashCam-style pulse shaping.

Basically like nb\_peak\_integration for lwt=0 but pulses are all upscaled in sampling frequency by a factor of four and one several variants for FlashCam-style pulse shaping is applied first. Signal extraction = integration also allows for different variants. There are actually way more variants available than necessary, intended for evaluation and testing.

Note that the psopt parameter is specified with the '-integration-window' command line option as the third value. (Recommended values for the first two are 1,0 (=nsum,nbefore). Nsum=0 means nsum=1.) Interpret psopt as decimal MHTO (with M=psopt/1000, H=(psopt%1000)/100, T=(psopt%100)/10, O=psopt%10): O = -1: Full pzpsa shaping and peak finding over full readout range, no neighbours involved. This results in a significant bias for positive NSB fluctuations. 0: Full pzpsa shaping but peak finding in signal of neighbours, avoiding the beginning (first 7) and end (last 3) of the upsampled signal because these are noisier and result in artifacts. (OK to use) 9: Like '0' but include the beginning and end for peak finding. (better use 0 or 1) 1: Like '9' but do own differencing to have smooth start and end. (recommended) 2: Like '1' but do differencing between second-to-next original samples. 3: Like '1' but do pulse shaping with own, more explicit code (differs in the beginning and the end but otherwise the same). 4: Like '2' but do pulse shaping with own, more explicit code. T = 0: Use integration from nbefore the peak for nsum upsampled samples and determine the pixel timing as the peak position close to the peak times in the signal of neighbour pixels (except for O = -1). > 0: Use the PzpsaPeakProperty code for summation and center-of-gravity determination of peaks, with T as width parameter. Nsum and nbefore are ignored. H = 0: Summation region is entirely determined by the peak in the signal of neighbourin pixels, without any bias for NSB fluctuations. 1: Summation region allows for small adjustement in peak position in the signal of the pixel itself. Small NSB bias. M = 0: Not touching pixel timing structure. 1: Re-evaluate and refill pixel timing from shaped signals and peaks. Unless a new 'integration threshold' is given, the old threshold for significant pixel timings gets re-used (but pixel is list still new).

#### **Parameters**

hsdata	Pointer to all available data and configurations.
itel	Sequence number of the telescope being processed.
nsum	Number of samples to sum up (is reduced if exceeding available length).
nbefore	Start the integration a number of samples before the peak, as long as it fits into the available data range. Note: for multiple gains, this may result in identical integration regions (depending on signal).
sigamp	(not used)
psopt	Pulse shaping option as described
ithr	Integration threshold in ADC counts gets actually used for significance in pixel timing.

## Returns

0 (OK), -1 (error)

- < Pedestal in raw signal, per sample.
- < Extension of summation/cog region [peakpos-w : peakpos+w]

References hess\_tel\_event\_adc\_struct::adc\_sum, hess\_pixel\_timing\_struct::after\_peak, hess\_pixel\_timing\_ $\leftarrow$  struct::before\_peak, H\_MAX\_SLICES, H\_MAX\_TEL, hess\_tel\_event\_adc\_struct::known, hess\_pixel\_timing\_ $\leftarrow$  struct::known, hess\_pixel\_timing\_struct::list\_size, hess\_pixel\_timing\_struct::list\_type, hess\_tel\_event\_adc\_struct ::num\_gains, hess\_tel\_event\_adc\_struct::num\_pixels, hess\_tel\_event\_adc\_struct::num\_samples, hess\_pixel  $\leftarrow$  timing\_struct::num\_types, hess\_tel\_event\_data\_struct::pixtm, hess\_tel\_event\_data\_struct::raw, hess\_event\_ $\leftarrow$  data\_struct::teldata, hess\_pixel\_timing\_struct::time\_level, and hess\_pixel\_ $\leftarrow$  timing\_struct::time\_type.

Referenced by pixel\_integration().

## 7.44.3.10 nb\_peak\_integration()

Integrate sample-mode data (traces) around a peak in the signal sum of neighbouring pixels.

The integration window can be anywhere in the available length of the traces. Since the calibration function subtracts a pedestal that corresponds to the total length of the traces we may also have to add a pedestal contribution for the samples not summed up. No weighting of individual samples is applied.

## **Parameters**

hsdata	Pointer to all available data and configurations.
lwt	Weight of the local pixel (0: peak from neighbours only, 1: local pixel counts as much as any neighbour).
itel	Sequence number of the telescope being processed.
nsum	Number of samples to sum up (is reduced if exceeding available length).
nbefore	Start the integration a number of samples before the peak, as long as it fits into the available data range. Note: for multiple gains, this results in identical integration regions.
sigamp	Amplitude in ADC counts above pedestal at which a signal is considered as significant (separate for high gain/low gain).

References hess\_tel\_event\_adc\_struct::adc\_known, hess\_tel\_event\_adc\_struct::adc\_sample, hess\_tel\_event\_  $\leftarrow$  adc\_struct::adc\_sum, find\_neighbours(), gradient\_integration(), H\_MAX\_SLICES, H\_MAX\_TEL, HI\_GAIN, hess  $\leftarrow$  tel\_event\_adc\_struct::known, LO\_GAIN, nb\_lists, camera\_nb\_list::nblist, camera\_nb\_list::nbsize, hess\_tel\_  $\leftarrow$  event\_adc\_struct::num\_gains, hess\_tel\_event\_adc\_struct::num\_pixels, hess\_tel\_event\_adc\_struct::num\_samples, hess\_tel\_monitor\_struct::pedestal, camera\_nb\_list::pix\_first\_nb, camera\_nb\_list::pix\_num\_nb, hess\_tel\_event\_  $\leftarrow$  data\_struct::raw, hess\_tel\_event\_adc\_struct::significant, hess\_event\_data\_struct::teldata, and hess\_tel\_event\_  $\leftarrow$  adc\_struct::zero\_sup\_mode.

Referenced by local\_peak\_integration(), and pixel\_integration().

# 7.44.3.11 pixel\_integration()

Pixel integration steering function.

Work is done in selected integration function.

References clean\_image\_tailcut(), global\_peak\_integration(), gradient\_integration(), user\_parameters::integ\_ $\leftarrow$  param, user\_parameters::integ\_thresh, user\_parameters::integrator, local\_peak\_integration(), nb\_fc\_shaped\_ $\leftarrow$  peak\_integration(), nb\_peak\_integration(), set\_integration\_correction(), and simple\_integration().

## 7.44.3.12 pixel\_timing\_analysis()

Calculate summary results from pixel timing data.

References hess\_camera\_settings\_struct::flen, H\_MAX\_PIX\_TIMES, H\_MAX\_TEL, image\_reconstruct(), hess—tel\_event\_data\_struct::img, hess\_pixel\_timing\_struct::known, hess\_tel\_event\_data\_struct::num\_image\_sets, hess\_pixel\_timing\_struct::num\_pixels, hess\_pixel\_timing\_struct::num\_types, hess\_tel\_image\_struct::phi, PIX\_T IME\_PEAKPOS\_TYPE, PIX\_TIME\_STARTPOS\_REL\_TYPE, PIX\_TIME\_WIDTH\_ABS\_TYPE, PIX\_TIME\_WID TH\_REL\_TYPE, hess\_tel\_event\_data\_struct::pixtm, hess\_event\_data\_struct::teldata, hess\_pixel\_timing\_struct ::time\_level, hess\_pixel\_setting\_struct::time\_slice, hess\_pixel\_timing\_struct::time\_type, hess\_pixel\_timing\_struct ::timval, hess\_tel\_image\_struct::tm\_residual, hess\_tel\_image\_struct::tm\_rise, hess\_tel\_image\_struct::tm\_slope, hess\_tel\_image\_struct::tm\_width1, hess\_tel\_image\_struct::tm\_width2, hess\_tel\_image\_struct::x, hess\_camera\_c settings\_struct::xpix, hess\_tel\_image\_struct::ypix.

Referenced by image reconstruct().

### 7.44.3.13 PzpsaPeakProperty()

```
static double PzpsaPeakProperty (
    int n,
    double * in,
    int pos,
    int w,
    double * intsum,
    double * cog ) [static]
```

Calculates the peak property of the signal in (n samples) at position pos.

The signal is integrated from sample pos-w to pos+w and the result is stored in intsum.

The cog is the center of gravity calculated by the area above the minumum of the signal from pos-w to pos+w

Returns a quality value for the signal which is defined as in[pos]-(in[start]+in[stop])/2. Negativ values indicate that no positive signal was found.

Referenced by PzpsaSmoothUpsampleU16().

### 7.44.3.14 PzpsaSmoothUpsampleU16()

```
static int PzpsaSmoothUpsampleU16 (
    int n,
    int us,
    uint16_t * ip,
    double b1,
    double pz,
    double * op,
    double * max,
    int * at ) [static]
```

Upsample (expand the n input values to us samples each) Subtract baseline bl and correct for a single pole decay with the decay time pz and smooth the resulting trace with two moving averages with a width of us.

The output is placed in array op and returns the new number of samples (n\*us).

This function derived from code by T.Kihm, using uint16\_t for input array element type and double for output. Example: PzpsaSmoothUpsampleU16(50,4,tti,0.,mpz,tto,&mxop,&imxop);

#### **Parameters**

n	Number of elements in input array ip
us	Upsampling factor (use '4' to upsample from 250 MHZ to one GHz).
ip	Pointer to input array of ADC raw data of type uint16_t
bl	Baseline (pedestal) on input per sample
pz	Pole-zero compensation factor in differencing (0<=pz<=1)
ор	Pointer to output array of type double
max	Maximum content in output array (only filled if not NULL)
at	Position of maximum bin in output array (only filled if not NULL)

- < running indices
- < the next and prev. input samples
- < the running sum of 1.st and 2.nd average
- < a temp var for intermediate copy
- < the next and prev. pz corrected value
- < the out pointer of the first runsum
- < the out pointer of the second runsum
- < the multiplier to correct the two runsums
- < peak maximum
- < peak position

References PzpsaPeakProperty().

Referenced by gradient\_integration().

# 7.44.3.15 reconstruct()

```
int reconstruct (
    AllHessData * hsdata,
    int reco_flag,
    const double * min_amp,
    const size_t * min_pix,
    const double * tcl,
    const double * tch,
    const int * lref,
    const double * minfrac,
    int nimg,
    int flag_amp_tm,
    int clean_flag )
```

Image/shower reconstruction function.

#### **Parameters**

hsdata	Pointer to all available data and configurations.
reco_flag	If $>=$ 3 then redo image cleaning before shower reconstruction. If $>=$ 4 then the total image intensities are re-determined and that may change which images are used or not in the shower reconstruction.
min_amp	The minimum amplitude required in images (telescope-specific, that means requiring an array of at least size H_MAX_TEL).
min_pix	The minimum number of pixels required in images (telescope-specific).
tcl	The lower of the two tail-cut thresholds (telescope-specific).
tch	The higher of the two tail-cut thresholds (telescope-specific).
Iref	Determines which pixel, after sorting by amplitude, will be used as providing the reference amplitude (telescope-specific). Example: use 3 for the third hottest pixel. If this number is <= 0, the classical scheme is used.
minfrac	Which fraction of the reference amplitude is required for pixels to be included in the final image (telescope-specific). If this number is <= 0.0, the classical scheme is used.
nimg	Which of (sometimes) several images should be filled? Use -1 to replace an existing image of the same cut id (if such an image exists) or add another image (if there is free space for it) or replace the first image (if all else fails). Use -2 to indicate that image analysis from normal integrated amplitude should go into first image and (if available) that from pixel timing (around local peak position or otherwise global peak position) should go into the second image.
flag_amp_tm	0: Use normal integrated amplitude. 1: Use integration around global peak position from pulse shape analysis. May include all pixels or only selected. 2: Use integration around local peak position from pulse shape analysis. Return 0 for pixels without a fairly significant peak.

References hess\_tel\_event\_adc\_struct::known, hess\_run\_header\_struct::ntel, hess\_tel\_event\_data\_struct::raw, hess\_event\_data\_struct::teldata, and user\_get\_type().

# 7.44.3.16 second\_moments()

```
static int second_moments (
          AllHessData * hsdata,
          int itel,
          int cut_id,
          int nimg,
          double clip_amp ) [static]
```

Reconstruction of second moments parameters from cleaned image.

Referenced by image\_reconstruct().

# 7.44.3.17 select\_calibration\_channel()

Control if only low-gain or high-gain should get used instead of both.

#### **Parameters**

```
chn 0 (both channels), 1 (only high gain), 2 (only low gain)
```

#### 7.44.3.18 set\_disabled\_pixels()

Set up pixels to be ignored (regarded as zero amplitude) in the analysis if they either have HV disabled or the camera active radius is clipped.

#### **Parameters**

hsdata	Pointer to all available data and configurations.
itel	Telescope index where we set new values.
broken_pixels_fraction	Optional fraction of additional pixels to be set like dead pixels (not usable for analysis).

Disabled pixels are ignored in the evaluation of the camera radius.

References camera\_nb\_list::npix.

## 7.44.3.19 set\_integration\_correction()

With partial pulse integration we extract a correction factor from partial to full pulse area from the reference pulse shape provided by MC.

Since actual pulses may have an intrinsic width (and as a result are wider than the reference pulse) this can still lead to a bit underestimated p.e. values. But this is hard to fix without knowing the true width of light pulses.

References H\_MAX\_SLICES, H\_MAX\_TEL, hess\_pixel\_setting\_struct::lrefshape, hess\_pixel\_setting\_struct::nrefshape, hess\_camera\_organisation\_struct::num\_gains, hess\_tel\_event\_adc\_struct::num\_samples, hess\_tel event\_data\_struct::raw, hess\_pixel\_setting\_struct::ref\_step, hess\_pixel\_setting\_struct::refshape, hess\_event\_event\_data\_struct::teldata, and hess\_pixel\_setting\_struct::time\_slice.

Referenced by pixel\_integration(), and qpol().

## 7.44.3.20 simple\_integration()

Integrate sample-mode data (traces) over a common and fixed interval.

The integration window can be anywhere in the available length of the traces. Since the calibration function subtracts a pedestal that corresponds to the total length of the traces we may also have to add a pedestal contribution for the samples not summed up. No weighting of individual samples is applied.

#### **Parameters**

hsdata	Pointer to all available data and configurations.	
itel	Sequence number of the telescope being processed.	
nsum	Number of samples to sum up (is reduced if exceeding available length).	
nskip	Number of initial samples skipped (adapted such that interval fits into what is available). Note: for multiple gains, this results in identical integration regions.	

References hess\_tel\_event\_adc\_struct::adc\_known, hess\_tel\_event\_adc\_struct::adc\_sample, hess\_tel\_event = \_adc\_struct::adc\_sum, global\_peak\_integration(), H\_MAX\_TEL, hess\_tel\_event\_adc\_struct::known, hess\_tel\_event\_adc\_struct::num\_pixels, hess\_tel\_event\_adc\_struct::num = \_samples, hess\_tel\_event\_adc\_struct::pedestal, hess\_tel\_event\_adc\_struct::raw, hess\_tel\_event\_adc\_struct = :significant, hess\_event\_data\_struct::teldata, and hess\_tel\_event\_adc\_struct::zero\_sup\_mode.

Referenced by pixel\_integration().

# 7.45 rndm2.h File Reference

Prototypes for random number generators adapted from HEP Random C++ code.

#### **Macros**

- #define rndm(idummy) RandFlat()
  - Backwards compatibility with rndm.c.
- #define rannor(mean, sigma) RandGauss(mean, sigma)
- #define rdmin(iseed) Ranlux\_setSeed(iseed,3);
- #define rdmout(piseed) fprintf(stderr,"rdmout() not implemented; use Ranlux\_getStatus/Ranlux\_setStatus instead\n");
- #define irndm(idummy) ((long)(RandFlat()\*2147483648.))

# **Typedefs**

- · typedef int HepBoolean
- typedef double(\* PFVD\_t) (void)

#### **Functions**

- void SetRandomEngine (PFVD t f)
- void Ranlux\_setSeed (long seed, int lux)
- void Ranlux\_setSeeds (long \*seeds, int lux)
- void Ranlux\_getStatus (int \*pseed, int seed\_table[24], int \*pi\_lag, int \*pj\_lag, int \*pcount24, double \*pcarry)
- void Ranlux\_setStatus (int \*pseed, int seed\_table[24], int \*pi\_lag, int \*pj\_lag, int \*pcount24, double \*pcarry)
- void Ranlux\_saveStatus (const char \*fname)
- void Ranlux\_restoreStatus (const char \*fname)
- void Ranlux\_showStatus (void)
- double Ranlux\_RandFlat (void)
- void Ranlux\_RandFlatArray (int size, double \*vect)
- double RandFlat (void)
- void RandFlatArray (int size, double \*vect)
- void RandGauss\_setFlag (HepBoolean val)
- HepBoolean RandGauss\_getFlag (void)
- void RandGauss\_setVal (double nextVal)
- double RandGauss\_getVal (void)
- double RandGauss (double mean, double sigma)
- void RandPoisson\_setOldMean (double val)
- double RandPoisson\_getOldMean (void)
- double RandPoisson\_getMaxMean (void)
- void RandPoisson\_setPStatus (double sq, double alxm, double g)
- double \* RandPoisson\_getPStatus (void)
- long RandPoisson (double xm)
- double RandExponential (double mean)

# 7.45.1 Detailed Description

Prototypes for random number generators adapted from HEP Random C++ code.

#### Author

Konrad Bernloehr

#### Date

# 11 July 1997

```
CVS $Date: 2009/12/07 18:27:28 $


CVS $Revision: 1.5 $
```

# 7.46 split\_hessio.c File Reference

Rip out data for each telescope into individual files.

```
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "history.h"
#include "io_hess.h"
#include "histogram.h"
#include "io_histogram.h"
#include "fileopen.h"
#include "straux.h"
#include "rec_tools.h"
#include "warning.h"
#include "camera_image.h"
#include <signal.h>
```

Include dependency graph for split\_hessio.c:



# **Functions**

• void stop\_signal\_function (int isig)

Stop the program gracefully when it catches an INT or TERM signal.

• static void syntax (char \*program)

Show program syntax.

• int main (int argc, char \*\*argv)

Main program.

# **Variables**

· static int interrupted

# 7.46.1 Detailed Description

Rip out data for each telescope into individual files.

7.47 straux.c File Reference 369


```
Syntax: split_hessio [ options ] [ - | input_fname ... ]
Options:
  -x
                   (Extract TelescopeEvent data from Event.)
   -X
                   (Extract TelescopeEvent raw data (samples or sum).)
  -q|-quiet (More quiet on standard output.)
-v|--verbose (More verbose on standard)
                  (Ignore unknown data block types.)
                   (More verbose on standard output.)
   --max-events n (Skip remaining data after so many triggered events.)
                   (Discard any sub-items of TelescopeEvent which are not raw data.)
   --clean-history (Drop previous history data blocks)
   --output-path d (Create output files in given directory instead of current.)
   --only-telescope[s] (Only data for the given telescopes IDs is written.)
   --not-telescope[s] (No data for the given telescopes IDs is written.)
@author Konrad Bernloehr
         @verbatim CVS $Date: 2017/05/16 12:31:52 $
Version
    CVS $Revision: 1.8 $
```

# 7.47 straux.c File Reference

Check for abbreviations of strings and get words from strings.

```
#include "initial.h"
#include <ctype.h>
#include "straux.h"
```

Include dependency graph for straux.c:



#### **Macros**

#define NO\_INITIAL\_MACROS 1

# **Functions**

- int abbrev (CONST char \*s, CONST char \*t)

  Compare strings s and t.
- int getword (CONST char \*s, int \*spos, char \*word, int maxlen, char blank, char endchar)

Copies a blank or '\0' or < endchar > delimeted word from position \*spos of the string s to the string word and increment \*spos to the position of the first non-blank character after the word.

int stricmp (CONST char \*a, CONST char \*b)

Case independent comparison of character strings.

# 7.47.1 Detailed Description

Check for abbreviations of strings and get words from strings.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2010/07/20 13:37:45 $
```

Version

```
CVS $Revision: 1.4 $
```

# 7.47.2 Function Documentation

# 7.47.2.1 abbrev()

```
int abbrev ( \label{eq:const_char} \text{CONST char} \ * \ s, \text{CONST char} \ * \ t \ )
```

Compare strings s and t.

s may be an abbreviation of t. Upper/lower case in s is ignored. s has to be at least as long as the leading upper case, digit, and '\_' part of t.

# **Parameters**

s	The string to be checked.
t	The test string with minimum part in upper case.

# Returns

1 if s is an abbreviation of t, 0 if not.

# 7.47.2.2 getword()

```
char * word,
int maxlen,
char blank,
char endchar )
```

Copies a blank or '\0' or < endchar > delimeted word from position \*spos of the string s to the string word and increment \*spos to the position of the first non-blank character after the word.

The word must have a length less than or equal to maxlen.

#### **Parameters**

s	string with any number of words.
spos	position in the string where we start and end.
word	the extracted word.
maxlen	the maximum allowed length of word.
blank	has the same effect as ' ', i.e. end-of-word.
endchar	his terminates the whole string ( as '\0' ).

#### Returns

-2: Invalid string or NULL -1: The word was longer than maxlen (without the terminating '\0'); 0: There were no more words in the string s. 1: ok, we have a word and there are still more of them in the string s. 2: ok, but this was the last word

Referenced by addpath(), and user\_set\_tel\_type\_param\_by\_str().

# 7.47.2.3 stricmp()

```
int stricmp (  {\tt CONST~char~*~a,} \\ {\tt CONST~char~*~b~)}
```

Case independent comparison of character strings.

#### **Parameters**

```
a,b - strings to be compared.
```

# Returns

 $\bf 0$  : strings are equal (except perhaps for case)  $>\!0$  : a is lexically 'greater' than b  $<\!0$  : a is lexically 'smaller' than b

# 7.48 straux.h File Reference

Check for abbreviations of strings and get words from strings.

This graph shows which files directly or indirectly include this file:



# **Macros**

· #define CONST const

#### **Functions**

- int abbrev (CONST char \*s, CONST char \*t)
  - Compare strings s and t.
- int getword (CONST char \*s, int \*spos, char \*word, int maxlen, char blank, char endchar)

Copies a blank or '\0' or < endchar > delimeted word from position \*spos of the string s to the string word and increment \*spos to the position of the first non-blank character after the word.

• int stricmp (CONST char \*a, CONST char \*b)

Case independent comparison of character strings.

# 7.48.1 Detailed Description

Check for abbreviations of strings and get words from strings.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2018/02/23 15:51:53 $
```

## Version

```
CVS $Revision: 1.3 $
```

### 7.48.2 Function Documentation

## 7.48.2.1 abbrev()

```
int abbrev (  {\tt CONST\ char\ *\ s,}   {\tt CONST\ char\ *\ t\ )}
```

Compare strings s and t.

s may be an abbreviation of t. Upper/lower case in s is ignored. s has to be at least as long as the leading upper case, digit, and '\_' part of t.

7.48 straux.h File Reference 373

#### **Parameters**

s	The string to be checked.
t	The test string with minimum part in upper case.

#### Returns

1 if s is an abbreviation of t, 0 if not.

# 7.48.2.2 getword()

Copies a blank or '\0' or < endchar > delimeted word from position \*spos of the string s to the string word and increment \*spos to the position of the first non-blank character after the word.

The word must have a length less than or equal to maxlen.

# Parameters

s	string with any number of words.
spos	position in the string where we start and end.
word	the extracted word.
maxlen	the maximum allowed length of word.
blank	has the same effect as ' ', i.e. end-of-word.
endchar	his terminates the whole string ( as '\0' ).

# Returns

-2: Invalid string or NULL -1: The word was longer than maxlen (without the terminating '\0'); 0: There were no more words in the string s. 1: ok, we have a word and there are still more of them in the string s. 2: ok, but this was the last word

# 7.48.2.3 stricmp()

Case independent comparison of character strings.

#### **Parameters**

```
a,b – strings to be compared.
```

# Returns


0: strings are equal (except perhaps for case) > 0: a is lexically 'greater' than b < 0: a is lexically 'smaller' than b

# 7.49 tohbook.c File Reference

Convert my histograms to HBOOK (PAW) histograms.

```
#include "initial.h"
#include "histogram.h"
#include "tohbook.h"
```

Include dependency graph for tohbook.c:



# **Functions**

- void convert\_histograms\_to\_hbook (const char \*fname)
- int histogram\_to\_hbook (int ihisto, HISTOGRAM \*histo)

# 7.49.1 Detailed Description


Convert my histograms to HBOOK (PAW) histograms.

## 7.50 toroot.cc File Reference

Functions for conversion of eventio histograms to ROOT format.

```
#include <TFile.h>
#include <TH1.h>
#include <TH2.h>
#include <string>
#include <sstream>
#include "initial.h"
#include "histogram.h"
#include "toroot.hh"
```

Include dependency graph for toroot.cc:



# **Functions**

• string num2str (int i)

Convert an int to a string using the STL.

• string num2str (double d)

Convert a double to a string using the STL.

 template < class T > string num2str (T num)

Convert various sorts of numbers to a string.

void convert\_histograms\_to\_root (const char \*fname)

Open a ROOT file for output, convert all histograms known and write to file.

• int histogram\_to\_root (int ihisto, HISTOGRAM \*histo)

Create a ROOT histogram from the eventio histogram.

# 7.50.1 Detailed Description

Functions for conversion of eventio histograms to ROOT format.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2018/04/16 16:57:08 $
```

Version

```
CVS Revision: 1.13 $
```

# 7.50.2 Function Documentation

#### 7.50.2.1 convert\_histograms\_to\_root()

Open a ROOT file for output, convert all histograms known and write to file.

#### **Parameters**

Name of ROOT output file.	fname
---------------------------	-------

References get\_first\_histogram(), histogram\_to\_root(), and histogram::next.

#### 7.50.2.2 histogram\_to\_root()

Create a ROOT histogram from the eventio histogram.

Create a ROOT histogram and fill it with the contents of the given histogram, if it contains any entries. If the histogram has an ID number, it is booked with this Id. Otherwise, 90000 + a sequential number is used.

# Parameters

ihisto	Histogram sequential number
histo	Histogram pointer

# Returns

```
0 (ok), -1 (invalid histogram)
```

References histogram::counts, Histogram\_Extension::ddata, histogram::entries, histogram::extension, Histogram—
\_Extension::fdata, get\_histogram\_by\_ident(), histogram::ident, Histogram\_Parameters::integer, Histogram—
Parameters::lower\_limit, histogram::nbins, histogram::nbins\_2d, num2str(), histogram::overflow, histogram—
::overflow\_2d, Histogram\_Parameters::real, histogram::title, histogram::type, histogram::underflow, histogram—
::underflow\_2d, and Histogram\_Parameters::upper\_limit.


Referenced by convert\_histograms\_to\_root().

# 7.51 user\_analysis.c File Reference

Code for analysis of simulated (and reconstructed) showers within the framework of the read\_hess program.

```
#include <limits.h>
#include "initial.h"
#include "io_basic.h"
#include "mc_tel.h"
#include "io_hess.h"
#include "io_histogram.h"
#include "fileopen.h"
#include "rec_tools.h"
#include "reconstruct.h"
#include "user_analysis.h"
#include "atmprof.h"
#include "straux.h"
#include "basic_ntuple.h"
```

Include dependency graph for user analysis.c:



# **Data Structures**

- struct tel\_type\_param
- · struct telescope\_list
- struct ebias\_cor\_data

# **Macros**

- #define MAX\_TEL\_TYPES 10
- #define PATH\_MAX 4096

### **Functions**

• static void interp (double x, double \*v, int n, int \*ipl, double \*rpl)

Linear interpolation with binary search algorithm.

• static double rpol (double \*x, double \*y, int n, double xp)

Linear interpolation with binary search algorithm.

void user\_set\_lookup\_file (const char \*fname)

Override the automatic naming for lookup files.

void user set histogram file (const char \*fname)

Override the automatic naming for histogram files.

void user\_set\_telescope\_type (int itype)

Select a specific telescope type for setting user parameters.

int user\_set\_tel\_type\_param\_by\_str (const char \*str)

Set telescope type parameters from a string (e.g.

int which\_telescope\_type (const struct hess\_camera\_settings\_struct \*cam\_set)

Find out to which telescope type a telescope belongs, by best matching in the required parameters.

- struct user\_parameters \* user\_get\_parameters (int tp)
- int user get type (int itel)

Get the best matching telescope type for a given telescope index.

static double eval\_cut\_param (double \*cut, double lgE)

Evaluate energy-dependent cut parameters with.

- void <u>\_\_attribute\_\_</u> ((constructor))
- void user\_set\_flags (int uf)

Set user-defined flags: used to active HESS-style analysis.

• void user\_set\_spectrum (double di)

Set the difference between generated MC spectrum and the assumed source spectrum.

void user\_set\_impact\_range (double \*impact\_range)

Set the acceptable ranges for reconstructed impact positions.

void user\_set\_true\_impact\_range (double \*true\_impact\_range)

Set the acceptable ranges for true impact positions.

void user\_set\_max\_core\_distance (double rt)

Set the maximum core distance for telescopes if their images should be used beyond geometrical reconstruction.

void user set min amp (double a)

Set the minimum amplitude of images usable for the analysis.

void user\_set\_tail\_cuts (double tcl, double tch, int lref, double minfrac)

Set the lower and upper tail cuts for the standard two-level tail-cut scheme.

void user\_set\_min\_pix (int mpx)

Set the minimum number of significant pixels in usable images.

void user\_set\_reco\_flag (int rf)

Set the reconstruction level flag ('-r' option in read\_hess).

void user\_set\_tel\_img (int tmn, int tmx)

Set the minimum and maximum number of usable images for events used in analysis.

void user\_set\_tel\_list (size\_t min\_tel, size\_t ntel, int \*tel\_id)

You may have alternative selections of (fewer) telescopes.

void user\_set\_max\_theta (double thmax, double thscale, double thmin)

Set the maximum angle between source and reconstructed shower direction.

void user\_set\_theta\_escale (double \*thes)

By default the angular acceptance is the 80% containment radius.

void user\_set\_de\_cut (double \*dec)

The dE cut can be made more or less strict by a scale parameter which should be 1.0 by default and is below 1 for a stricter cut and above 1 for a looser cut.

void user\_set\_de2\_cut (double \*de2c)

Since the dE2 cut is not always of any help with default cut parameters, you can change the parameter to your needs.

void user\_set\_hmax\_cut (double hmaxc)

The hmax cut can be made or or less strict by a scale parameter which should be 1.0 by default and is below 1 for a stricter cut and above 1 for a looser cut.

void user set shape cuts (double wmin, double wmax, double lmin, double lmax)

Set shape cut parameters.

void user\_set\_width\_max\_cut (double \*wmax)

Set energy dependent scaled width limit.

• void user\_set\_length\_max\_cut (double \*Imax)

Set energy dependent scaled length limit.

void user\_set\_focal\_length (double f)

Set the telescope effective focal length.

void user set clipping (double dc)

Set the maximum radius to be used of a camera.

void user\_set\_clipamp (double cpa)

Set the maximum amplitude in a pixel.

void user set trg reg (int trg reg)

Set the required trigger type(s) as a bit pattern.

- void user\_set\_diffuse\_mode (int dm, double oar[])
- void user\_set\_verbosity (int v)
- · int user selected event ()
- void user\_set\_auto\_lookup (int al)
- void user set integrator (int scheme)
- void user\_set\_integ\_window (int nsum, int noff, int ps\_opt)
- void user\_set\_integ\_threshold (int ithg, int itlg)
- void user\_set\_integ\_no\_rescale (int no)
- void user\_set\_calib\_scale (double s)
- void user set nb radius (double \*r)
- void user\_set\_nxt\_radius (double r)
- static double expected max height (double E, double theta, double height)

Expected height of the shower maximum above the detector for gamma rays, based on simple analytical formula and exponential atmospheric profile.

• static double expected\_max\_distance (double E, double theta, double height)

Expected distance of the shower maximum from the detector for gamma rays, based on simple analytical formula and exponential atmospheric profile.

static int img\_norm (double w, double I, double A, double IgA, double rc, int tel\_type, double \*scrw, double \*scrl, double \*scw, double \*sce, double \*scer, double \*rco, double \*rcor, double \*dimgo, double \*dimgor)

Get scaled + reduced scaled image parameters (both HEGRA and HESS type scaling) as well as energy scaling from the lookups.

double ebias correction (double IgE)

Ask for a correction to log10(reconstructed energy), if available.

void set\_ebias\_correction (HISTOGRAM \*h)

Set correction to log10(reconstructed energy), if available.

static void init\_telescope\_types (AllHessData \*hsdata)

Initialize what of type each telescope is.

- static void book hist global (AllHessData \*hsdata)
- static void book\_hist\_for\_type (AllHessData \*hsdata, int itype)
- static void user\_init (AllHessData \*hsdata)

Initialisation of user analysis, booking of histograms etc.

• static void user mc shower fill (AllHessData \*hsdata)

Work to be done once per generated shower.

• static void user mc event fill (AllHessData \*hsdata)

Work to be done once per shower usage.

static void user\_event\_fill (AllHessData \*hsdata, int stage)

Fill (triggered) event specific histograms etc.

• static void user\_done (AllHessData \*hsdata)

After all data for a file (usually one run) was processed.

static char \* prog\_path (void)

Find the path from which the current program was started.

• static void user finish (AllHessData \*hsdata)

Final call before program terminates.

• int do\_user\_ana (AllHessData \*hsdata, unsigned long item\_type, int stage)

#### **Variables**

- static int verbosity = 0
- static int user init done = 0
- static int current\_tel\_type = 0
- static struct tel\_type\_param def\_tel\_type\_param [MAX\_TEL\_TYPES]
- static int saved tel type [H MAX TEL]
- static char user\_lookup\_fname [1024]
- static char hist fname [1024]
- static struct telescope\_list \* alt\_list = NULL
- static size t **n\_list** = 0
- static double max\_theta = 0.2 \* (M PI/180.)
- static double min\_theta = 0.2 \* (M\_PI/180.)
- static struct user\_parameters up [MAX\_TEL\_TYPES+2]
- · static int nparams

Number of parameters, including: the gamma-ray source offset plus d\_sp\_idx, min\_amp, tailcut\_low, tailcut\_high, min\_pix, reco\_flag, min\_tel\_img, max\_tel\_img, max\_theta, theta\_scale.

- static int nparams i
- · static int nparams d
- static double \* params
- static double opt\_theta\_cut [7][H\_MAX\_TEL]

Angular cut limit is multiplicity dependent.

- static int diffuse\_mode = 0
- static double diffuse\_off\_axis\_min = 0.
- static double diffuse\_off\_axis\_max = M\_PI/2.
- static int event\_selected = 0
- static int auto\_lookup = 0
- static int telescope\_type [H\_MAX\_TEL]

Declare local (static) data here ...

- static char lookup\_fname [1024]
- · static double Az\_src
- static double Alt\_src
- · static double Az nom
- · static double Alt\_nom
- · static double source\_offset
- static MOMENTS \* pixmom = NULL
- · static struct ebias\_cor\_data ebias
- static int tel\_types\_change = 0
- static int stat\_type [MAX\_TEL\_TYPES+2]
- static int init\_hist\_for\_type [MAX\_TEL\_TYPES+2]
- static int init\_hist\_global = 0
- struct basic\_ntuple bnt

# 7.51.1 Detailed Description

Code for analysis of simulated (and reconstructed) showers within the framework of the read\_hess program.

Users wanting to make use of such analysis should modify the user\_\* functions provided here or the do\_user\_ana() function. Except for the do\_user\_ana() function and the user\_set\_...() functions, all functions are declared as static to emphasize that their interfaces can be changed here to the user's desires.

Author

Konrad Bernloehr

Date

```
initial version: August 2006
```

```
CVS $Date: 2017/10/14 17:51:29 $
```

Version

```
CVS $Revision: 1.79 $
```

# 7.51.2 Function Documentation

# 7.51.2.1 ebias\_correction()

```
double ebias_correction ( \label{eq:correction} \mbox{double } lgE \mbox{ )}
```

Ask for a correction to log10(reconstructed energy), if available.

Returns

Bias in log10(energy), to be subtracted from log10(energy), or 0.

References rpol(), and set\_ebias\_correction().

# 7.51.2.2 eval\_cut\_param()

Evaluate energy-dependent cut parameters with.

#### **Parameters**

cut[0]	the cut parameter at 1 TeV (lgE=0),
cut[1]	the slope of the cut parameters versus IgE,
cut[2]	the minimum cut parameter,
cut[3]	the maximum cut parameter.

#### 7.51.2.3 expected\_max\_distance()

```
static double expected_max_distance ( \label{eq:constraint} \mbox{double $E$,} \\ \mbox{double $theta$,} \\ \mbox{double $height$ } ) \mbox{ [static]}
```

Expected distance of the shower maximum from the detector for gamma rays, based on simple analytical formula and exponential atmospheric profile.

#### **Parameters**

E	The energy of the shower [TeV].
theta	Then zenith angle of the shower [radians].
height	The height above sea level of the experiment [m].

#### Returns

Distance of shower maximum from detector [m]

References expected\_max\_height(), and img\_norm().

Referenced by expected\_max\_height().

## 7.51.2.4 expected\_max\_height()

Expected height of the shower maximum above the detector for gamma rays, based on simple analytical formula and exponential atmospheric profile.

## **Parameters**

E	The energy of the shower [TeV].
theta	Then zenith angle of the shower [radians].
height	The height above sea level of the experiment [m].

# Returns

Height of shower maximum above detector [m]

References expected\_max\_distance().

Referenced by expected\_max\_distance().

## 7.51.2.5 img\_norm()

```
static int img_norm (
            double w,
             double 1,
             double A,
             double 1gA,
             double rc,
             int tel_type,
             double * scrw,
             double * scrl,
             double * scw,
             double * scl,
             double * sce,
             double * scer,
             double * rco,
             double * rcor,
             double * dimgo,
             double * dimgor ) [static]
```

Get scaled + reduced scaled image parameters (both HEGRA and HESS type scaling) as well as energy scaling from the lookups.

All variables for the results are optional. For variables which are of no interest, pass a NULL pointer.

#### **Parameters**

W	Image width [rad].
1	Image length [rad].
Α	Image amplitude [ peak p.e. ].
lgA	log10(A)
rc	Reconstructed core distance.
tel_type	Telescope type (for multiple lookups).
scrw	Variable getting the scaled reduced width (HESS style).
scrl	Variable getting the scaled reduced length (HESS style).
scw	Variable getting the scaled width (HEGRA style).
scl	Variable getting the scaled length (HEGRA style).
sce	Variable getting the expected energy [TeV] for the given amplitude at the given core distance.
scer	Variable getting the relative fluctuation of energy/amplitude at this point.
rco	Variable getting the expected core distance based on width/length and amplitude.
rcor	Variable getting the relative error in the core distance estimate.
dimgo	Variable getting the expected distance in the image (as for rco).
dimgor	Variable getting the relative error in the image distance estimate.

Referenced by expected\_max\_distance().

# 7.51.2.6 init\_telescope\_types()

Initialize what of type each telescope is.

In normal simulation data this is only needed once but in complex merged (via merge\_simtel) data the necessary info may not be available for all of them when types for the first of them is needed.

References hess\_run\_header\_struct::ntel, hess\_camera\_settings\_struct::num\_mirrors, telescope\_type, and which\_telescope\_type().

Referenced by set\_ebias\_correction().

#### 7.51.2.7 interp()

Linear interpolation with binary search algorithm.

Linear interpolation between data point in sorted (i.e. monotonic ascending or descending) order. This function determines between which two data points the requested coordinate is and where between them. If the given coordinate is outside the covered range, the value for the corresponding edge is returned.

A binary search algorithm is used for fast interpolation.

#### **Parameters**

X	Input: the requested coordinate
V	Input: tabulated coordinates at data points
n	Input: number of data points
ipl	Output: the number of the data point following the requested coordinate in the given sorting (1 <= ipl <= n-1)
rpl	Output: the fraction $(x-v[ipl-1])/(v[ipl]-v[ipl-1])$ with $0 \le rpl \le 1$

References rpol().

Referenced by rpol().

# 7.51.2.8 prog\_path()

```
static char * prog_path (
void ) [static]
```

Find the path from which the current program was started.

Referenced by user\_done().

#### 7.51.2.9 rpol()

Linear interpolation with binary search algorithm.

Linear interpolation between data point in sorted (i.e. monotonic ascending or descending) order. The resulting interpolated value is returned as a return value.

This function calls interp() to find out where to interpolate.

#### **Parameters**

X	Input: Coordinates for data table
У	Input: Corresponding values for data table
n	Input: Number of data points
хр	Input: Coordinate of requested value

# Returns

Interpolated value

References interp().

Referenced by ebias\_correction(), and interp().

# 7.51.2.10 user\_done()

After all data for a file (usually one run) was processed.

References prog\_path().

## 7.51.2.11 user\_event\_fill()

Fill (triggered) event specific histograms etc.

- < true energy [TeV]
- < Event for desired spectral slope
- < true core distance [m]
- < reconstructed core distance [m]
- < image amplitude [peak p.e.]
- < image width [rad]
- < image length [rad]
- < radius of image c.o.g. in camera plane
- < distance of image c.o.g. to source [rad]
- < Amplitude and edge distance are ok

References hess\_mc\_shower\_struct::altitude, hess\_mc\_shower\_struct::azimuth, user\_parameters::d\_sp\_idx, hess\_mc\_shower\_struct::energy, H\_MAX\_TEL, basic\_ntuple::xc, basic\_ntuple::xc\_true, hess\_mc\_event\_struct::xcore, basic\_ntuple::yc, basic\_ntuple::yc, true, and hess\_mc\_event\_struct::ycore.

# 7.51.2.12 user\_finish()

Final call before program terminates.

### 7.51.2.13 user\_get\_type()

Get the best matching telescope type for a given telescope index.

If user analysis is not activated, this will always be type 0.

Referenced by reconstruct().

## 7.51.2.14 user\_mc\_event\_fill()

Work to be done once per shower usage.

Depending on sim\_hessarray flags this might be called only for triggered events or also for non-triggered events (default).

References hess\_mc\_shower\_struct::altitude, hess\_mc\_shower\_struct::azimuth, user\_parameters::d\_sp\_idx, hess\_mc\_shower\_struct::energy, fill\_histogram\_by\_ident(), line\_point\_distance(), hess\_mc\_event\_struct::xcore, and hess\_mc\_event\_struct::ycore.

#### 7.51.2.15 user\_mc\_shower\_fill()

Work to be done once per generated shower.

# 7.51.2.16 user\_set\_clipping()

```
void user_set_clipping ( double dc )
```

Set the maximum radius to be used of a camera.

# 7.51.2.17 user\_set\_flags()

```
void user_set_flags ( \inf \ uf \ )
```

Set user-defined flags: used to active HESS-style analysis.

#### **Parameters**

0: not exactly HESS-style analysis; 1: HESS-style standard cuts; 2: HESS-style hard cuts; 3: HESS-style loose cuts. >=4: HESS-style (no re-scaling) but user-defined cut parameters.

## 7.51.2.18 user\_set\_focal\_length()

```
void user_set_focal_length ( double f )
```

Set the telescope effective focal length.

#### 7.51.2.19 user\_set\_length\_max\_cut()

Set energy dependent scaled length limit.

#### 7.51.2.20 user\_set\_tel\_type\_param\_by\_str()

Set telescope type parameters from a string (e.g.

on the command line).

Can be used to set all relevant parameters (others set to 0) or just to switch the active type (no parameters other than the type number).

References getword().

## 7.51.2.21 user\_set\_theta\_escale()

By default the angular acceptance is the 80% containment radius.

Performance may improve by using a smaller radius at low energies (stricter cut) and a larger radius at high energies (looser cut). This sets an additional lg(E) dependent scaling factor.

#### 7.51.2.22 user\_set\_width\_max\_cut()

Set energy dependent scaled width limit.

# 7.51.3 Variable Documentation

# 7.51.3.1 opt\_theta\_cut

```
double opt_theta_cut[7][H_MAX_TEL] [static]
```

Angular cut limit is multiplicity dependent.

# 7.51.3.2 telescope\_type

```
int telescope_type[H_MAX_TEL] [static]
```

Declare local (static) data here ...


Referenced by init\_telescope\_types().

# 7.52 warning.c File Reference

Pass warning messages to the screen or a usr function as set up.

```
#include "initial.h"
#include "warning.h"
#include <errno.h>
```

Include dependency graph for warning.c:



# **Data Structures**

• struct warn\_specific\_data

A struct used to store thread-specific data.

#### **Macros**

- #define \_\_WARNING MODULE 1
- #define get\_warn\_specific() (&warn\_defaults)

#### **Functions**

 $\bullet \ \ void \ warn\_f\_warning \ (const \ char \ *msgtext, \ const \ char \ *msgorigin, \ int \ msglevel, \ int \ msgno)\\$ 

Issue a warning to screen or other configured target.

• int set\_warning (int level, int mode)

Set a specific warning level and mode.

- int set\_default\_warning (int level, int mode)
- void warning\_status (int \*plevel, int \*pmode)

Inquire status of warning settings.

void set\_logging\_function (void(\*user\_function)(const char \*, const char \*, int, int))

Set user-defined function for logging warnings and errors.

- void set\_default\_logging\_function (void(\*user\_function)(const char \*, const char \*, int, int))
- int set\_log\_file (const char \*fname)

Set a new log file name and save it in local storage.

void warn\_f\_output\_text (const char \*text)

Print a text string (without appending a newline etc.) on the screen or send it to a controlling process, depending on the setting of the output function.

• void flush\_output ()

Flush buffered output.

void set\_output\_function (void(\*user\_function)(const char \*))

Set a user-defined function as the function to be used for normal text output.

- void set\_default\_output\_function (void(\*user\_function)(const char \*))
- void set\_aux\_warning\_function (char \*(\*auxfunc)(void))

Set an auxilliary function for warnings.

void set\_default\_aux\_warning\_function (char \*(\*auxfunc)(void))

# **Variables**

• static struct warn\_specific\_data warn\_defaults

# 7.52.1 Detailed Description

Pass warning messages to the screen or a usr function as set up.

Author

Konrad Bernloehr

# Date

CVS \$Date: 2014/02/20 10:53:06 \$

#### Version

```
CVS $Revision: 1.9 $
```

One of the most import parameter for setting up the bevaviour is the warning level:

# 7.52.2 Function Documentation

# 7.52.2.1 flush\_output()

```
void flush_output (
     void )
```

Flush buffered output.

Output is flushed, no matter if it is standard output or a special output function;

# Returns

(none)

#### 7.52.2.2 set\_aux\_warning\_function()

Set an auxilliary function for warnings.

This function may be used to insert time and date or origin etc. at the beginning of the warning text.

# **Parameters**

#### Returns

(none)

# 7.52.2.3 set\_log\_file()

Set a new log file name and save it in local storage.

If there was a log file with a different name opened previously, close it.

#### **Parameters**

```
fname New name of log file for warnings
```

#### Returns

```
0 (o.k.), -1 (error)
```

# 7.52.2.4 set\_logging\_function()

Set user-defined function for logging warnings and errors.

Set a user-defined function as the function to be used for logging warnings and errors. To enable usage of this function, bit 2 of the warning mode must be set and other bits reset, if logging to screen and/or disk file is no longer wanted.

Parameter userfunc: Pointer to a function taking two strings (the message text and the origin text, which may be NULL) and two integers (message level and message number).

# Returns

(none)

## 7.52.2.5 set\_output\_function()

Set a user-defined function as the function to be used for normal text output.

Such a function may be used to send output back to a remote control process via network.

Parameter userfunc: Pointer to a function taking a string (the text to be displayed) as argument.

#### Returns

(none)

# 7.52.2.6 set\_warning()

```
int set_warning (
          int level,
          int mode )
```

Set a specific warning level and mode.

#### **Parameters**

level	Warnings with level below this are ignored.
mode	To screen, to file, with user function

#### Returns

0 if ok, -1 if level and/or mode could not be set.

# 7.52.2.7 warn\_f\_output\_text()

Print a text string (without appending a newline etc.) on the screen or send it to a controlling process, depending on the setting of the output function.

# **Parameters**

text	A text string to be displayed.

#### Returns

(none)

# 7.52.2.8 warn\_f\_warning()

Issue a warning to screen or other configured target.

Issue a warning to screen and/or file if the warning has a sufficiently large message 'level' (high enough severity). This function should best be called through the macros 'Information', 'Warning', and 'Error'. The name of this function has been changed from 'warning' to '\_warning' to avoid trouble if you call 'warning' instead of 'Warning'. Now such a typo causes an error in the link step.

#### **Parameters**

msgtext	Warning or error text.
msgorigin	Optional origin (e.g. function name) or NULL.
msglevel	Level of message importance: negative: debugging if needed, 0-9: informative, 10-19: warning,
	20-29: error.
msgno	Number of message or 0.

## Returns

(none)

# 7.52.2.9 warning\_status()

```
void warning_status (
          int * plevel,
          int * pmode )
```

Inquire status of warning settings.

# **Parameters**

plevel	Pointer to variable for storing current level.
pmode	Pointer to store the current warning mode.

Returns

(none)

# 7.52.3 Variable Documentation

#### 7.52.3.1 warn\_defaults

```
struct warn_specific_data warn_defaults [static]
```

#### Initial value:

# 7.53 warning.h File Reference

Pass warning messages to the screen or a usr function as set up.

This graph shows which files directly or indirectly include this file:



# **Macros**

- #define **WARNING\_ORIGIN** (char \*) NULL
- #define Information(string) warn\_f\_warning(string,WARNING\_ORIGIN,0,0)
- #define **Warning**(string) warn\_f\_warning(string,WARNING\_ORIGIN,10,0)
- #define **Error**(string) warn\_f\_warning(string,WARNING\_ORIGIN,20,0)
- #define Output(string) warn\_f\_output\_text(string)

#### **Functions**

• void warn\_f\_warning (const char \*text, const char \*origin, int level, int msgno)

Issue a warning to screen or other configured target.

int set\_warning (int level, int mode)

Set a specific warning level and mode.

- int set default warning (int level, int mode)
- void warning\_status (int \*plevel, int \*pmode)

Inquire status of warning settings.

void set logging function (void(\*user function)(const char \*, const char \*, int, int))

Set user-defined function for logging warnings and errors.

- void set\_default\_logging\_function (void(\*user\_function)(const char \*, const char \*, int, int))
- int set\_log\_file (const char \*fname)

Set a new log file name and save it in local storage.

void warn\_f\_output\_text (const char \*text)

Print a text string (without appending a newline etc.) on the screen or send it to a controlling process, depending on the setting of the output function.

void flush\_output (void)

Flush buffered output.

void set output function (void(\*user function)(const char \*))

Set a user-defined function as the function to be used for normal text output.

- void set\_default\_output\_function (void(\*user\_function)(const char \*))
- void set\_aux\_warning\_function (char \*(\*auxfunc)(void))

Set an auxilliary function for warnings.

- void set\_default\_aux\_warning\_function (char \*(\*auxfunc)(void))
- char \* warn\_f\_get\_message\_buffer (void)

# 7.53.1 Detailed Description

Pass warning messages to the screen or a usr function as set up.

Author

Konrad Bernloehr

Date

```
CVS $Date: 2010/07/20 13:37:45 $
```

Version

```
CVS $Revision: 1.5 $
```

# 7.53.2 Function Documentation

## 7.53.2.1 flush\_output()

```
void flush_output (
     void )
```

Flush buffered output.

Output is flushed, no matter if it is standard output or a special output function;

Returns

(none)

# 7.53.2.2 set\_aux\_warning\_function()

Set an auxilliary function for warnings.

This function may be used to insert time and date or origin etc. at the beginning of the warning text.

#### **Parameters**

```
auxfunc - Pointer to a function taking no argument and returning a character string.
```

# Returns

(none)

# 7.53.2.3 set\_log\_file()

Set a new log file name and save it in local storage.

If there was a log file with a different name opened previously, close it.

# **Parameters**

fname	New name of log file for warnings
mamo	Trow hand or log me for warrings

```
Returns
```

```
0 (o.k.), -1 (error)
```

## 7.53.2.4 set\_logging\_function()

Set user-defined function for logging warnings and errors.

Set a user-defined function as the function to be used for logging warnings and errors. To enable usage of this function, bit 2 of the warning mode must be set and other bits reset, if logging to screen and/or disk file is no longer wanted.

Parameter userfunc: Pointer to a function taking two strings (the message text and the origin text, which may be NULL) and two integers (message level and message number).

#### Returns

(none)

#### 7.53.2.5 set\_output\_function()

Set a user-defined function as the function to be used for normal text output.

Such a function may be used to send output back to a remote control process via network.

Parameter userfunc: Pointer to a function taking a string (the text to be displayed) as argument.

## Returns

(none)

# 7.53.2.6 set\_warning()

```
int set_warning (
          int level,
          int mode )
```

Set a specific warning level and mode.

#### **Parameters**

level	Warnings with level below this are ignored.	
mode	To screen, to file, with user function	

#### Returns

0 if ok, -1 if level and/or mode could not be set.

# 7.53.2.7 warn\_f\_output\_text()

Print a text string (without appending a newline etc.) on the screen or send it to a controlling process, depending on the setting of the output function.

#### **Parameters**

text	A text string to be displayed.
------	--------------------------------

### Returns

(none)

# 7.53.2.8 warn\_f\_warning()

Issue a warning to screen or other configured target.

Issue a warning to screen and/or file if the warning has a sufficiently large message 'level' (high enough severity). This function should best be called through the macros 'Information', 'Warning', and 'Error'. The name of this function has been changed from 'warning' to '\_warning' to avoid trouble if you call 'warning' instead of 'Warning'. Now such a typo causes an error in the link step.

#### **Parameters**

msgtext	Warning or error text.
msgorigin	Optional origin (e.g. function name) or NULL.
msglevel	Level of message importance: negative: debugging if needed, 0-9: informative, 10-19: warning,
	20-29: error.
msgno	Number of message or 0.

Generated by Doxygen

400 File Documentation

# Returns

(none)

# 7.53.2.9 warning\_status()

```
void warning_status (
    int * plevel,
    int * pmode )
```

Inquire status of warning settings.

# **Parameters**

plevel	Pointer to variable for storing current level.
pmode	Pointer to store the current warning mode.

# Returns

(none)

# Index

_STR_	heighx, 134
hconfig.h, 194	init_atmprof, 134
	interp, 134
abbrev	refidx, 135
hconfig.h, 194	rhofx, 135
straux.c, 370	rpol, 136
straux.h, 372	thickx, 136
acceptance	aweight
basic_ntuple, 39	hess mc event struct, 77
add_histogram	az
histogram.c, 205	basic_ntuple, 39
histogram.h, 229	az true
add_histograms.c, 131	basic_ntuple, 39
addexepath	ap.e, 00
fileopen.c, 169	basic_ntuple, 37
fileopen.h, 174	acceptance, 39
addpath	alt, 39
fileopen.c, 169	alt_true, 39
fileopen.h, 174	az, 39
alloc_2d_int_histogram	az_true, 39
histogram.c, 206	chi2_e, 39
histogram.h, 229	lg e, 40
alloc 2d real histogram	lg_e_true, 40
histogram.c, 206	mdisp, 40
histogram.h, 230	mscrl, 40
alloc_int_histogram	mscrw, 40
histogram.c, 207	n_fail, 41
histogram.h, 230	n_img, 41
alloc moments	n_pix, 41
histogram.h, 231	n_trg, 41
_	n_tsl0, 41
moments.c, 336	primary, 41
alloc_real_histogram	-
histogram.c, 207	rcm, 42
histogram.h, 231	run, 42
allocate_histogram	sig_e, 42
histogram.c, 208	sig_mscrl, 42
histogram.h, 232	sig_mscrw, 42
alt	sig_theta, 42
basic_ntuple, 39	sig_xmax, 43
alt_az_arrow	theta, 43
camera_image.c, 143	tslope, 43
alt_true	tsphere, 43
basic_ntuple, 39	weight, 43
angle_between	xc, 43
rec_tools.h, 348	xc_true, 44
angles_to_offset	xfirst_true, 44
rec_tools.h, 349	xmax, 44
atime	xmax_true, 44
photo_electron, 118	yc, 44
atmprof.c, 132	yc_true, 44

basic_ntuple.h, 137	ps_trailer, 145
list_ntuple, 137	camera_nb_list, 48
begin_read_tel_array	check_autoload_trgmask
io_simtel.c, 286	The extract_simtel program, 21
mc_tel.h, 314	The merge_simtel program, 25
begin_write_tel_array	check_hessio_max
io_simtel.c, 287	io_hess.c, 259
mc_tel.h, 315	io_hess.h, 273
best_of.cc, 138	check_trgmask.c, 145
best_value, 45	chi2_e
Binary_Interface_Chain, 46	basic_ntuple, 39
binary_config	clean_image_tailcut
ConfigValues, 61	reconstruct.c, 356
book_1d_histogram	clear_histogram
histogram.c, 209 histogram.h, 232	histogram.c, 210
book_histogram	histogram.h, 234
histogram.c, 209	clear_moments
histogram.h, 233	histogram.h, 235
book_int_histogram	moments.c, 336
histogram.c, 210	clear_shower_extra_parameters
histogram.h, 234	io_simtel.c, 287
bound	mc_tel.h, 315
ConfigIntern, 55	clip_amp
build_config	user_parameters, 127
hconfig.c, 184	cmdline
hconfig.h, 195	io_history.c, 282 cmdtime
bunch, 47	
	io_history.c, 282
CALIB_SCALE	cmp_popen fileopen.c, 169
reconstruct.c, 355	code
The read_hess (aka read_simtel, read_cta) pro-	hess_pixel_list, 85
gram, 28	coinc count
The read_hess_nr program, 30	hess_tel_monitor_struct, 103
CFG_MUTEX	compact bunch, 48
hconfig.h, 194	Config_Binary_Item_Interface, 49
calib	copy_func, 50
hess_laser_calib_data_struct, 75 calib_scale	delete_func, 50
user_parameters, 126	elem_size, 50
calibrate amplitude	io_item_type, 50
reconstruct.c, 355	list func, 50
calibrate_pixel_amplitude	new_func, 50
reconstruct.c, 356	read_func, 51
The read hess nr program, 30	readtext_func, 51
cam_to_ref	write_func, 51
rec_tools.h, 349	config_binary_convert_data
camera clipping deg	hconfig.h, 195
user_parameters, 126	config_binary_read_text
camera_image.c, 140	hconfig.h, 195
alt_az_arrow, 143	config_binary_text_length
find_neighbours, 142	hconfig.h, 195
hesscam_ps_plot, 142	config_binary_write_name
print_pix_col, 143	hconfig.h, 196
ps_begin_page1, 143	config_binary_write_text
ps_begin_page2, 144	hconfig.h, 196
ps_end_page, 144	config_defaults
ps_head1a, 144	hconfig.c, 189
ps_head1b, 144	config_specific_data, 51

ConfigBlockStruct, 52	set_local_offset, 149
ConfigBoundary, 53	time_string, 149
ConfigDataPointer, 53	current.h, 150
ConfigIntern, 54	current_localtime, 151
bound, 55	current_time, 151
elem_size, 55	mkgmtime, 151
itype, 55	reset_local_offset, 152
Ibound hard, 55	set_current_offset, 152
lbound_soft, 55	set_local_offset, 152
locked, 55	time_string, 153
ubound hard, 56	current_localtime
ubound_soft, 56	current.c, 147
values, 56	current.h, 151
ConfigltemStruct, 57	current_time
data, 58	current.c, 147
flags, 58	current.h, 151
function, 58	cvt2.c, 153
initial, 58	cvt3.cc, 155
internal, 59	
Ibound, 59	d_integ_param
name, 59	user_parameters, 127
res1, 59	d_sp_idx
res2, 59	user_parameters, 127
	data
size, 59	ConfigItemStruct, 58
type, 60	data_changed
ubound, 60	ConfigValues, 61
validate, 60	data_saved
ConfigValues, 60	ConfigValues, 61
binary_config, 61	ddata
data_changed, 61	Histogram_Extension, 110
data_saved, 61	default_config
elem_size, 62	hconfig.c, 189
elements, 62	delete func
itype, 62	Config Binary Item Interface, 50
list_mod, 62	describe histogram
max_mod, 62	histogram.c, 211
mod_flag, 62	histogram.h, 235
name, 63	dhsort
nmod, 63	dhsort.c, 157
section, 63	dhsort.c, 156
configs	dhsort, 157
io_history.c, 282	direction
conv_depth	hess_run_header_struct, 92
hess_run_header_struct, 92	disable_permissive_pipes
conv_ref_pos	fileopen.c, 169
hess_run_header_struct, 92	fileopen.h, 174
convert_histograms_to_root	display_2d_histogram
toroot.cc, 376	histogram.c, 211
copy_func	display_all_histograms
Config_Binary_Item_Interface, 50	histogram.c, 212
current	histogram.h, 235
hess_tel_monitor_struct, 103	display_histogram
current.c, 146	histogram.c, 212
current_localtime, 147	histogram.h, 236
current_time, 147	drawer_temp
mkgmtime, 148	hess_tel_monitor_struct, 103
reset_local_offset, 148	,
set_current_offset, 148	ebias_cor_data, 63

ebias_correction	freepath, 171
user_analysis.c, 381	initpath, 171
elem_size	listpath, 171
Config_Binary_Item_Interface, 50	permissive_pipes, 172
ConfigIntern, 55	root_exe_path, 172
ConfigValues, 62	root_path, 173
elements	set_permissive_pipes, 172
ConfigValues, 62	uri_popen, 172
enable_permissive_pipes	fileopen.h, 173
fileopen.c, 170	addexepath, 174
fileopen.h, 175	addpath, 174
end_read_tel_array	disable_permissive_pipes, 174
io_simtel.c, 287	enable_permissive_pipes, 175
mc_tel.h, 316	fileclose, 175
end_write_tel_array	fileopen, 175
io_simtel.c, 288	initpath, 175
mc tel.h, 316	listpath, 176
entries	•
histogram, 107	set_permissive_pipes, 176
ev_reg_chain, 64	fill_2d_int_histogram
eval_cut_param	histogram.c, 213
user_analysis.c, 381	histogram.h, 237
eventio_registry.c, 157	fill_2d_real_histogram
find_ev_reg_std, 159	histogram.c, 213
read_eventio_registry, 159	histogram.h, 237
set_ev_reg_std, 159	fill_2d_weighted_histogram
eventio_registry.h, 160	histogram.c, 214
	histogram.h, 238
find_ev_reg_std, 161	fill_gaps
read_eventio_registry, 161	gen_lookup.c, 178
set_ev_reg_std, 162	fill_histogram
exe_popen	histogram.c, 214
fileopen.c, 170	histogram.h, 238
expected_max_distance	fill_histogram_by_ident
user_analysis.c, 381	histogram.c, 215
expected_max_height	histogram.h, 239
user_analysis.c, 382	fill_int_histogram
extract_hess.c, 162	histogram.c, 215
extract_simtel.c, 163	histogram.h, 239
fast_stat_histogram	fill mean
histogram.c, 212	histogram.h, 240
histogram.h, 236	moments.c, 338
fcat.c, 166	fill mean and sigma
fileclose	histogram.h, 240
fileopen.c, 170	moments.c, 338
fileopen.h, 175	fill_moments
•	histogram.h, 240
fileopen	moments.c, 338
fileopen.c, 170	fill_real_histogram
fileopen.h, 175	histogram.c, 216
fileopen.c, 166	histogram.h, 241
addexepath, 169	fill real mean
addpath, 169	
cmp_popen, 169	histogram.h, 241
disable_permissive_pipes, 169	moments.c, 339
enable_permissive_pipes, 170	fill_real_mean_and_sigma
exe_popen, 170	histogram.h, 242
fileclose, 170	moments.c, 339
fileopen, 170	fill_real_moments
freeexepath, 171	histogram.h, 242

moments.c, 339	histogram.c, 218
fill_weighted_histogram	histogram.h, 244
histogram.c, 216	get_histogram_by_ident
histogram.h, 242	histogram.c, 218
find_config_item	histogram.h, 244
hconfig.c, 185	get_shower_trans_matrix
hconfig.h, 196	rec_tools.h, 349
find_ev_reg_std	getword
eventio_registry.c, 159	hconfig.h, 197
eventio_registry.h, 161	straux.c, 370
find_neighbours	straux.h, 373
camera_image.c, 142	global_peak_integration
reconstruct.c, 357	reconstruct.c, 357
find_tel_idx	gradient_integration
io_hess.c, 259	reconstruct.c, 358
find_trgmask	granularity
io_trgmask.c, 306	hess_pixel_timing_struct, 88
io_trgmask.h, 309	LL CUECK MAY
first_config_block	H_CHECK_MAX
hconfig.c, 190	io_hess.h, 270
flags	H_MAX_FSHAPE
ConfigItemStruct, 58	io_hess.h, 270
Float16Compressor, 64	H_MAX_HOTPIX
Float16Compressor::Bits, 47	io_hess.h, 271
FloatCompressor, 65	H_MAX_PIX_TIMES
FloatCompressor::Bits, 46	io_hess.h, 271
flush_output	H_MAX_PROFILE
warning.c, 391	io_hess.h, 271
warning.h, 396	H_MAX_SLICES
warring.ri, 590	
fparam	io_hess.h, 271
_	HI_GAIN
fparam	HI_GAIN io_hess.h, 271
fparam shower_extra_parameters, 120	HI_GAIN io_hess.h, 271 HISTCOUNT
fparam shower_extra_parameters, 120 free_all_histograms	HI_GAIN io_hess.h, 271 HISTCOUNT histogram.h, 228
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217	HI_GAIN io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243	HI_GAIN io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents	HI_GAIN io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217	HI_GAIN io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram	HI_GAIN io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218	HI_GAIN io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243	HI_GAIN io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189 find_config_item, 185
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments	HI_GAIN io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189 find_config_item, 185 first_config_block, 190
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244	HI_GAIN io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189 find_config_item, 185 first_config_block, 190 get_config_filename, 185
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340	HI_GAIN  io_hess.h, 271  HISTCOUNT  histogram.h, 228  HISTVALUE_REAL  histogram.h, 228  hconfig.c, 180  build_config, 184  config_defaults, 189  default_config, 189  find_config_item, 185  first_config_block, 190  get_config_filename, 185  get_config_preprocessor, 185
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath	HI_GAIN  io_hess.h, 271  HISTCOUNT  histogram.h, 228  HISTVALUE_REAL  histogram.h, 228  hconfig.c, 180  build_config, 184  config_defaults, 189  default_config, 189  find_config_item, 185  first_config_block, 190  get_config_filename, 185  get_config_preprocessor, 185  init_config, 186
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath fileopen.c, 171	HI_GAIN  io_hess.h, 271  HISTCOUNT  histogram.h, 228  HISTVALUE_REAL  histogram.h, 228  hconfig.c, 180  build_config, 184  config_defaults, 189  default_config, 189  find_config_item, 185  first_config_block, 190  get_config_filename, 185  get_config_preprocessor, 185  init_config, 186  read_config_lines, 186
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath fileopen.c, 171 freepath	HI_GAIN  io_hess.h, 271  HISTCOUNT  histogram.h, 228  HISTVALUE_REAL  histogram.h, 228  hconfig.c, 180  build_config, 184  config_defaults, 189  default_config, 189  find_config_item, 185  first_config_block, 190  get_config_filename, 185  get_config_preprocessor, 185  init_config, 186  read_config_lines, 186  read_config_status, 187
fparam shower_extra_parameters, 120  free_all_histograms histogram.c, 217 histogram.h, 243  free_histo_contents histogram.c, 217  free_histogram histogram.c, 218 histogram.h, 243  free_moments histogram.h, 244 moments.c, 340  freeexepath fileopen.c, 171  freepath fileopen.c, 171  function	HI_GAIN  io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189 find_config_item, 185 first_config_block, 190 get_config_filename, 185 get_config_preprocessor, 185 init_config, 186 read_config_lines, 186 read_config_status, 187 reconfig, 187
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath fileopen.c, 171 freepath fileopen.c, 171	HI_GAIN  io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189 find_config_item, 185 first_config_block, 190 get_config_filename, 185 get_config_preprocessor, 185 init_config, 186 read_config_lines, 186 read_config_status, 187 reconfig, 187 reload_config, 187
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath fileopen.c, 171 freepath fileopen.c, 171 function ConfigltemStruct, 58  gen_lookup.c, 176	HI_GAIN  io_hess.h, 271  HISTCOUNT  histogram.h, 228  HISTVALUE_REAL histogram.h, 228  hconfig.c, 180  build_config, 184  config_defaults, 189  default_config, 189  find_config_item, 185  first_config_block, 190  get_config_filename, 185  get_config_preprocessor, 185  init_config, 186  read_config_lines, 186  read_config_status, 187  reconfig, 187  reload_config, 187  set_config_filename, 188
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath fileopen.c, 171 freepath fileopen.c, 171 function ConfigltemStruct, 58  gen_lookup.c, 176 fill_gaps, 178	HI_GAIN  io_hess.h, 271  HISTCOUNT  histogram.h, 228  HISTVALUE_REAL  histogram.h, 228  hconfig.c, 180  build_config, 184  config_defaults, 189  default_config, 189  find_config_item, 185  first_config_block, 190  get_config_filename, 185  get_config_preprocessor, 185  init_config, 186  read_config_lines, 186  read_config_status, 187  reconfig, 187  reload_config, 187  set_config_history, 188
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath fileopen.c, 171 freepath fileopen.c, 171 function ConfightemStruct, 58  gen_lookup.c, 176 fill_gaps, 178 gen_trgmask.c, 179	HI_GAIN  io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189 find_config_item, 185 first_config_block, 190 get_config_filename, 185 get_config_preprocessor, 185 init_config, 186 read_config_lines, 186 read_config_status, 187 reconfig, 187 reload_config, 187 set_config_history, 188 set_config_preprocessor, 188
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath fileopen.c, 171 freepath fileopen.c, 171 function ConfightemStruct, 58  gen_lookup.c, 176 fill_gaps, 178 gen_trgmask.c, 179 get_config_filename	HI_GAIN  io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189 find_config_item, 185 first_config_block, 190 get_config_filename, 185 get_config_preprocessor, 185 init_config, 186 read_config_lines, 186 read_config_status, 187 reconfig, 187 reload_config, 187 set_config_filename, 188 set_config_preprocessor, 188 set_config_preprocessor, 188 set_config_preprocessor, 188
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath fileopen.c, 171 freepath fileopen.c, 171 function ConfigltemStruct, 58  gen_lookup.c, 176 fill_gaps, 178 gen_trgmask.c, 179 get_config_filename hconfig.c, 185	HI_GAIN  io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189 find_config_item, 185 first_config_block, 190 get_config_filename, 185 get_config_preprocessor, 185 init_config, 186 read_config_lines, 186 read_config_status, 187 reconfig, 187 reload_config_filename, 188 set_config_history, 188 set_config_preprocessor, 188 set_config_preprocessor, 188 set_config_preprocessor, 188 hconfig.h, 190
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath fileopen.c, 171 freepath fileopen.c, 171 function ConfigltemStruct, 58  gen_lookup.c, 176 fill_gaps, 178 gen_trgmask.c, 179 get_config_filename hconfig.c, 185 hconfig.h, 197	HI_GAIN  io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189 find_config_item, 185 first_config_block, 190 get_config_filename, 185 get_config_preprocessor, 185 init_config, 186 read_config_lines, 186 read_config_lines, 186 read_config_status, 187 reconfig, 187 reload_config, 187 set_config_filename, 188 set_config_history, 188 set_config_preprocessor, 188 set_config_preprocessor, 188 hconfig.h, 190 _STR_, 194
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath fileopen.c, 171 freepath fileopen.c, 171 function ConfigltemStruct, 58  gen_lookup.c, 176 fill_gaps, 178 gen_trgmask.c, 179 get_config_filename hconfig.c, 185	HI_GAIN  io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189 find_config_item, 185 first_config_block, 190 get_config_filename, 185 get_config_preprocessor, 185 init_config, 186 read_config_lines, 186 read_config_status, 187 reconfig, 187 reload_config, 187 set_config_filename, 188 set_config_history, 188 set_config_preprocessor, 188 set_config_stack, 189 hconfig.h, 190STR, 194 abbrev, 194
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath fileopen.c, 171 freepath fileopen.c, 171 function ConfigltemStruct, 58  gen_lookup.c, 176 fill_gaps, 178 gen_trgmask.c, 179 get_config_filename hconfig.c, 185 hconfig.h, 197 get_config_preprocessor hconfig.c, 185	HI_GAIN  io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189 find_config_item, 185 first_config_block, 190 get_config_filename, 185 get_config_preprocessor, 185 init_config, 186 read_config_lines, 186 read_config_status, 187 reconfig, 187 reload_config, 187 set_config_filename, 188 set_config_filename, 188 set_config_preprocessor, 188 set_config_preprocessor, 188 set_config_stack, 189 hconfig.h, 190STR_, 194 abbrev, 194 build_config, 195
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath fileopen.c, 171 freepath fileopen.c, 171 function ConfigltemStruct, 58  gen_lookup.c, 176 fill_gaps, 178 gen_trgmask.c, 179 get_config_filename hconfig.c, 185 hconfig.h, 197 get_config_preprocessor	HI_GAIN  io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189 find_config_item, 185 first_config_block, 190 get_config_filename, 185 get_config_preprocessor, 185 init_config, 186 read_config_lines, 186 read_config_status, 187 reconfig, 187 reload_config, 187 set_config_filename, 188 set_config_history, 188 set_config_preprocessor, 188 set_config_stack, 189 hconfig.h, 190STR, 194 abbrev, 194
fparam shower_extra_parameters, 120 free_all_histograms histogram.c, 217 histogram.h, 243 free_histo_contents histogram.c, 217 free_histogram histogram.c, 218 histogram.h, 243 free_moments histogram.h, 244 moments.c, 340 freeexepath fileopen.c, 171 freepath fileopen.c, 171 function ConfigltemStruct, 58  gen_lookup.c, 176 fill_gaps, 178 gen_trgmask.c, 179 get_config_filename hconfig.c, 185 hconfig.h, 197 get_config_preprocessor hconfig.c, 185	HI_GAIN  io_hess.h, 271 HISTCOUNT histogram.h, 228 HISTVALUE_REAL histogram.h, 228 hconfig.c, 180 build_config, 184 config_defaults, 189 default_config, 189 find_config_item, 185 first_config_block, 190 get_config_filename, 185 get_config_preprocessor, 185 init_config, 186 read_config_lines, 186 read_config_status, 187 reconfig, 187 reload_config, 187 set_config_filename, 188 set_config_filename, 188 set_config_preprocessor, 188 set_config_preprocessor, 188 set_config_stack, 189 hconfig.h, 190STR_, 194 abbrev, 194 build_config, 195

config_binary_read_text, 195	threshold, 88
config_binary_text_length, 195	time_level, 88
config_binary_write_name, 196	timval, 88
config_binary_write_text, 196	hess_pointing_correction_struct, 89
find_config_item, 196	hess_run_end_mc_statistics_struct, 89
get_config_filename, 197	hess_run_end_statistics_struct, 90
get_config_preprocessor, 197	hess_run_header_struct, 91
getword, 197	conv_depth, 92
init_config, 198	conv ref pos, 92
read_config_lines, 198	direction, 92
read_config_status, 199	offset_fov, 92
reconfig, 199	reverse_flag, 92
reload_config, 200	run, 92
set_config_filename, 200	run_type, 93
set_config_history, 200	tel_pos, 93
set config preprocessor, 201	tracking mode, 93
set_config_stack, 201	hess_shower_parameter, 93
heighx	hess_tel_event_adc_struct, 95
atmprof.c, 134	hess_tel_event_data_struct, 96
hess_all_data_struct, 66	hess_tel_image_struct, 98
hess_aux_analog_trace, 67	I, 99
<del>-</del>	
hess_aux_digital_trace, 68 hess_camera_organisation_struct, 68	num_hot, 99
	phi, 99
hess_camera_settings_struct, 69	tm_slope, 100
mirror_area, 70	x, 100
hess_camera_software_setting_struct, 70	hess_tel_monitor_struct, 101
zero_sup_mode, 71	coinc_count, 103
hess_central_event_data_struct, 72	current, 103
teldata_pattern, 73	drawer_temp, 103
teltrg_pattern, 73	hess_time_struct, 104
teltrg_time, 73	hess_tracking_event_data_struct, 104
hess_event_data_struct, 74	hess_tracking_setup_struct, 105
hess_laser_calib_data_struct, 75	range_low_az, 106
calib, 75	hesscam_ps_plot
max_int_frac, 75	camera_image.c, 142
max_pixtm_frac, 75	hessio_doc.h, 202
hess_mc_event_struct, 76	HistOutput
aweight, 77	histogram.c, 205
hess_mc_pe_list, 77	histogram, 106
hess_mc_pe_sum_struct, 78	entries, 107
photons_atm_qe, 78	next, 107
hess_mc_photons, 79	overflow, 108
hess_mc_run_header_struct, 80	overflow_2d, 108
shower_prog_id, 81	tentries, 108
hess_mc_shower_profile_struct, 81	type, 108
id, 82	underflow, 109
hess_mc_shower_struct, 83	underflow_2d, 109
primary_id, 84	histogram.c, 202
xmax, 84	add_histogram, 205
hess_pixel_calibrated_struct, 84	alloc_2d_int_histogram, 206
hess_pixel_disabled_struct, 85	alloc_2d_real_histogram, 206
hess_pixel_list, 85	alloc_int_histogram, 207
code, 85	alloc_real_histogram, 207
hess_pixel_setting_struct, 86	allocate_histogram, 208
hess_pixel_timing_struct, 87	book_1d_histogram, 209
granularity, 88	book_histogram, 209
pulse_sum_glob, 88	book_int_histogram, 210
pulse_sum_loc, 88	clear_histogram, 210

describe_histogram, 211	fill_real_histogram, 241
display_2d_histogram, 211	fill_real_mean, 241
display_all_histograms, 212	fill_real_mean_and_sigma, 242
display_histogram, 212	fill_real_moments, 242
fast_stat_histogram, 212	fill_weighted_histogram, 242
fill_2d_int_histogram, 213	free_all_histograms, 243
fill_2d_real_histogram, 213	free_histogram, 243
fill_2d_weighted_histogram, 214	free_moments, 244
fill_histogram, 214	get_first_histogram, 244
fill_histogram_by_ident, 215	get_histogram_by_ident, 244
fill_int_histogram, 215	HISTCOUNT, 228
fill_real_histogram, 216	HISTVALUE_REAL, 228
fill_weighted_histogram, 216	histogram_hashing, 245
free_all_histograms, 217	histogram_matching, 245
free_histo_contents, 217	histogram_to_lookup, 245
free_histogram, 218	list_histograms, 246
get_first_histogram, 218	locate_histogram_fraction, 246
get_histogram_by_ident, 218	lookup_int, 247
HistOutput, 205	lookup_real, 247
histogram_hashing, 219	print_histogram, 248
histogram_matching, 219	set_first_histogram, 248
histogram_to_lookup, 220	sort_histograms, 249
list_histograms, 220	stat_histogram, 249
locate_histogram_fraction, 220	stat_moments, 249
lookup_int, 221	unlink_histogram, 250
lookup_real, 221	Histogram_Extension, 109
primetab, 224	ddata, 110
print_histogram, 222	Histogram_Parameters, 110
set_first_histogram, 222	integer, 111
sort_histograms, 223	inverse_binwidth, 111 real, 112
stat_histogram, 223	histogram_hashing
unlink_histogram, 223	histogram.c, 219
histogram.h, 224	histogram.h, 245
add_histogram, 229	histogram_matching
alloc_2d_int_histogram, 229	histogram.c, 219
alloc_2d_real_histogram, 230	histogram.h, 245
alloc_int_histogram, 230	histogram_to_lookup
alloc_moments, 231	histogram.c, 220
alloc_real_histogram, 231	histogram.h, 245
allocate_histogram, 232	histogram to root
book_1d_histogram, 232	toroot.cc, 376
book_histogram, 233	history.h, 250
book_int_histogram, 234	history struct, 112
clear_histogram, 234	histstat, 113
clear_moments, 235	hs verbose
describe_histogram, 235	 io_hess.c, 265
display_all_histograms, 235	
display_histogram, 236	IO_TYPE_HESS_XTRGMASK
fast_stat_histogram, 236	io_trgmask.h, 308
fill_2d_int_histogram, 237	id
fill_2d_real_histogram, 237	hess_mc_shower_profile_struct, 82
fill_2d_weighted_histogram, 238	shower_extra_parameters, 120
fill_histogram, 238	ifn
fill_histogram_by_ident, 239	map_tel_struct, 115
fill_int_histogram, 239	image_reconstruct
fill_mean, 240	reconstruct.c, 358
fill_mean_and_sigma, 240	img_norm
fill_moments, 240	user_analysis.c, 382

impact_range	write_hess_televent, 264
user_parameters, 127	io_hess.h, 265
incpath, 113	check_hessio_max, 273
init_atmprof	H_CHECK_MAX, 270
atmprof.c, 134	H_MAX_FSHAPE, 270
init_config	H_MAX_HOTPIX, 271
hconfig.c, 186	H_MAX_PIX_TIMES, 271
hconfig.h, 198	H_MAX_PROFILE, 271
init_shower_extra_parameters	H_MAX_SLICES, 271
io_simtel.c, 288	HI_GAIN, 271
mc_tel.h, 316	LO_GAIN, 272
init_telescope_types	PIX_TIME_PEAKPOS_TYPE, 272
user_analysis.c, 383	PIX_TIME_STARTPOS_ABS_TYPE, 272
initial	PIX_TIME_STARTPOS_REL_TYPE, 272
ConfigItemStruct, 58	PIX_TIME_WIDTH_ABS_TYPE, 272
initial.h, 251	PIX_TIME_WIDTH_REL_TYPE, 273
initpath	io_histogram.c, 274
fileopen.c, 171	print_histograms, 275
fileopen.h, 175	read_histograms, 275
integ_no_rescale	read_histograms_x, 276
user_parameters, 127	write_histograms, 276
integ_param	io_histogram.h, 277
user parameters, 127	print_histograms, 278
integer	read_histograms, 279
Histogram_Parameters, 111	read_histograms_x, 279
integrator	write_histograms, 280
user parameters, 128	io_history.c, 280
internal	cmdline, 282
ConfigItemStruct, 59	cmdtime, 282
interp	configs, 282
atmprof.c, 134	io_history.h, 283
user_analysis.c, 384	io_item_type
intersect_lines	Config_Binary_Item_Interface, 50
rec tools.h, 350	io simtel.c, 284
inverse_binwidth	begin_read_tel_array, 286
Histogram_Parameters, 111	begin_write_tel_array, 287
io hess.c, 254	clear_shower_extra_parameters, 287
check_hessio_max, 259	end_read_tel_array, 287
find_tel_idx, 259	end_write_tel_array, 288
hs verbose, 265	init_shower_extra_parameters, 288
print_hess_aux_trace_analog, 260	max_print, 304
print_hess_aux_trace_digital, 260	print_camera_layout, 289
print hess pixcalib, 260	print_bhoto_electrons, 289
read_hess_pixcalib, 260	print_tel_block, 289
set_tel_idx, 261	print_tel_block, 290
set_tel_idx_ref, 261	print_tel_pos, 290
write_hess_aux_trace_digital, 261	private shower extra parameters, 305
write_hess_event, 262	read_camera_layout, 290
write_hess_laser_calib, 262	read_input_lines, 292
write hess mc event, 262	read_photo_electrons, 292
write_hess_mc_pe_sum, 262	read_shower_longitudinal, 293
write_hess_mc_shower, 263	read_snower_forigitudinal, 293
write_hess_pixcalib, 263	read_tel_array_head, 294
write_ness_pixcaiib, 263 write_hess_run_stat, 263	read_tel_block, 295
write_ness_run_stat, 263 write_hess_shower, 263	read_tel_offset, 295
write_hess_tel_monitor, 263	read_tel_offset_w, 296
write_hess_teladc_samples, 264	read_tel_photons, 296
write_hess_teladc_sums, 264	read_tel_pos, 297

write_camera_layout, 297	basic_ntuple.h, 137
write_input_lines, 298	listpath
write_photo_electrons, 298	fileopen.c, 171
write_shower_longitudinal, 299	fileopen.h, 176
write_tel_array_end, 300	local_peak_integration
write_tel_array_head, 300	reconstruct.c, 358
write_tel_block, 301	locate_histogram_fraction
write_tel_compact_photons, 301	histogram.c, 220
write_tel_offset, 302	histogram.h, 246
write_tel_offset_w, 302	locked
write_tel_photons, 303	ConfigIntern, 55
write_tel_pos, 304	logfname
io_trgmask.c, 305	warn_specific_data, 130
find_trgmask, 306	lookup_int
print_hashed_trgmasks, 306	histogram.c, 221
trgmask_fill_hashed, 307	histogram.h, 247
trgmask_scan_log, 307	lookup_real
io_trgmask.h, 307	histogram.c, 221
find_trgmask, 309	histogram.h, 247
IO_TYPE_HESS_XTRGMASK, 308	
print_hashed_trgmasks, 309	main
trgmask_fill_hashed, 309	The add_histograms program, 13
trgmask_scan_log, 309	The extract_hess program, 19
iparam	The hdata2hbook program (cvt2), 34
shower extra parameters, 120	The list_histogram program, 17
is set	The read_hess (aka read_simtel, read_cta) pro-
shower extra parameters, 120	gram, 28
itype	The read_hess_nr program, 31
ConfigIntern, 55	The split_hessio program, 32
	map_tel_struct, 115
ConfigValues, 62	map_tel_struct, 115 ifn, 115
	ifn, 115 map_to
ConfigValues, 62	ifn, 115
ConfigValues, 62	ifn, 115 map_to
ConfigValues, 62  I hess_tel_image_struct, 99	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard ConfigIntern, 55  lbound_soft	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard ConfigIntern, 55	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard ConfigIntern, 55  lbound_soft	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard ConfigIntern, 55  lbound_soft ConfigIntern, 55	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard ConfigIntern, 55  lbound_soft ConfigIntern, 55  lg_e	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard ConfigIntern, 55  lbound_soft ConfigIntern, 55  lg_e basic_ntuple, 40	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314 begin_write_tel_array, 315
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard ConfigIntern, 55  lbound_soft ConfigIntern, 55  lg_e basic_ntuple, 40  lg_e_true	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314 begin_write_tel_array, 315 clear_shower_extra_parameters, 315
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard ConfigIntern, 55  lbound_soft ConfigIntern, 55  lg_e basic_ntuple, 40  lg_e_true basic_ntuple, 40	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314 begin_write_tel_array, 315 clear_shower_extra_parameters, 315 end_read_tel_array, 316
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard ConfigIntern, 55  lbound_soft ConfigIntern, 55  lg_e basic_ntuple, 40  lg_e_true basic_ntuple, 40  line_point_distance	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314 begin_write_tel_array, 315 clear_shower_extra_parameters, 315 end_read_tel_array, 316 init_shower_extra_parameters, 316 print_camera_layout, 317
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigltemStruct, 59  lbound_hard Configlntern, 55  lbound_soft Configlntern, 55  lg_e basic_ntuple, 40  lg_e_true basic_ntuple, 40  line_point_distance rec_tools.h, 350  linked_string, 114  list_func	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314 begin_write_tel_array, 315 clear_shower_extra_parameters, 315 end_read_tel_array, 316 end_write_tel_array, 316 init_shower_extra_parameters, 316 print_camera_layout, 317 print_photo_electrons, 317
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard ConfigIntern, 55  lbound_soft ConfigIntern, 55  lg_e basic_ntuple, 40  lg_e_true basic_ntuple, 40  line_point_distance rec_tools.h, 350  linked_string, 114  list_func Config_Binary_Item_Interface, 50	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314 begin_write_tel_array, 315 clear_shower_extra_parameters, 315 end_read_tel_array, 316 end_write_tel_array, 316 init_shower_extra_parameters, 316 print_camera_layout, 317 print_photo_electrons, 317 print_tel_block, 317
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard ConfigIntern, 55  lbound_soft ConfigIntern, 55  lg_e basic_ntuple, 40  lg_e_true basic_ntuple, 40  line_point_distance rec_tools.h, 350  linked_string, 114  list_func Config_Binary_Item_Interface, 50  list_histograms	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314 begin_write_tel_array, 315 clear_shower_extra_parameters, 315 end_read_tel_array, 316 end_write_tel_array, 316 init_shower_extra_parameters, 316 print_camera_layout, 317 print_photo_electrons, 317 print_tel_block, 317 print_tel_offset, 318
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard ConfigIntern, 55  lbound_soft ConfigIntern, 55  lg_e basic_ntuple, 40  lg_e_true basic_ntuple, 40  line_point_distance rec_tools.h, 350  linked_string, 114  list_func Config_Binary_Item_Interface, 50  list_histograms histograms.c, 220	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314 begin_write_tel_array, 315 clear_shower_extra_parameters, 315 end_read_tel_array, 316 end_write_tel_array, 316 init_shower_extra_parameters, 316 print_camera_layout, 317 print_photo_electrons, 317 print_tel_block, 317 print_tel_offset, 318 print_tel_pos, 318
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigItemStruct, 59  lbound_hard ConfigIntern, 55  lbound_soft ConfigIntern, 55  lg_e basic_ntuple, 40  lg_e_true basic_ntuple, 40  line_point_distance rec_tools.h, 350  linked_string, 114  list_func Config_Binary_Item_Interface, 50  list_histograms histogram.c, 220  histogram.h, 246	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314 begin_write_tel_array, 315 clear_shower_extra_parameters, 315 end_read_tel_array, 316 end_write_tel_array, 316 init_shower_extra_parameters, 316 print_camera_layout, 317 print_photo_electrons, 317 print_tel_block, 317 print_tel_offset, 318 print_tel_pos, 318 read_camera_layout, 319
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigltemStruct, 59  lbound_hard Configlntern, 55  lbound_soft Configlntern, 55  lg_e basic_ntuple, 40  lg_e_true basic_ntuple, 40  line_point_distance rec_tools.h, 350  linked_string, 114  list_func Config_Binary_Item_Interface, 50  list_histograms histograms.c, 220     histograms.c, 310	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314 begin_write_tel_array, 315 clear_shower_extra_parameters, 315 end_read_tel_array, 316 end_write_tel_array, 316 init_shower_extra_parameters, 316 print_camera_layout, 317 print_photo_electrons, 317 print_tel_block, 317 print_tel_offset, 318 print_tel_pos, 318 read_camera_layout, 319 read_input_lines, 319
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigltemStruct, 59  lbound_hard Configlntern, 55  lbound_soft Configlntern, 55  lg_e basic_ntuple, 40  lg_e_true basic_ntuple, 40  line_point_distance rec_tools.h, 350  linked_string, 114  list_func Config_Binary_ltem_Interface, 50  list_histograms histograms.c, 220     histogram.c, 220     histograms.c, 310  list_mod	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314 begin_write_tel_array, 315 clear_shower_extra_parameters, 315 end_read_tel_array, 316 end_write_tel_array, 316 init_shower_extra_parameters, 316 print_camera_layout, 317 print_tel_block, 317 print_tel_block, 317 print_tel_offset, 318 print_tel_pos, 318 read_camera_layout, 319 read_input_lines, 319 read_photo_electrons, 319
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigltemStruct, 59  lbound_hard Configlntern, 55  lbound_soft Configlntern, 55  lg_e basic_ntuple, 40  lg_e_true basic_ntuple, 40  line_point_distance rec_tools.h, 350  linked_string, 114  list_func Config_Binary_Item_Interface, 50  list_histograms histograms.c, 220     histograms.c, 310	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314 begin_write_tel_array, 315 clear_shower_extra_parameters, 315 end_read_tel_array, 316 end_write_tel_array, 316 init_shower_extra_parameters, 316 print_camera_layout, 317 print_tel_block, 317 print_tel_block, 317 print_tel_offset, 318 print_tel_pos, 318 read_camera_layout, 319 read_input_lines, 319 read_photo_electrons, 319 read_shower_longitudinal, 320
ConfigValues, 62  I hess_tel_image_struct, 99  LO_GAIN io_hess.h, 272  lambda photo_electron, 118  lbound ConfigltemStruct, 59  lbound_hard Configlntern, 55  lbound_soft Configlntern, 55  lg_e basic_ntuple, 40  lg_e_true basic_ntuple, 40  line_point_distance rec_tools.h, 350  linked_string, 114  list_func Config_Binary_ltem_Interface, 50  list_histograms histograms.c, 220     histogram.c, 220     histograms.c, 310  list_mod	ifn, 115 map_to The extract_simtel program, 22 The merge_simtel program, 26 max_int_frac hess_laser_calib_data_struct, 75 max_mod ConfigValues, 62 max_pixtm_frac hess_laser_calib_data_struct, 75 max_print io_simtel.c, 304 mc_tel.h, 311 begin_read_tel_array, 314 begin_write_tel_array, 315 clear_shower_extra_parameters, 315 end_read_tel_array, 316 end_write_tel_array, 316 init_shower_extra_parameters, 316 print_camera_layout, 317 print_tel_block, 317 print_tel_offset, 318 print_tel_pos, 318 read_camera_layout, 319 read_input_lines, 319 read_photo_electrons, 319

read_tel_array_head, 321	basic_ntuple, 41
read_tel_block, 322	n_tsl0
read_tel_offset, 322	basic_ntuple, 41
read_tel_offset_w, 323	name
read_tel_photons, 324	ConfigItemStruct, 59
read_tel_pos, 324	ConfigValues, 63
write_camera_layout, 325	nb_fc_shaped_peak_integration
write_input_lines, 325	reconstruct.c, 359
write_photo_electrons, 326	nb_peak_integration
write_shower_longitudinal, 326	reconstruct.c, 360
write_tel_array_end, 327	new_func
write_tel_array_head, 327	Config_Binary_Item_Interface, 50
write_tel_block, 328 write_tel_compact_photons, 328	next histogram, 107
write_tel_offset, 329	next_file_struct, 117
write_tel_offset_w, 330	nfparam
write_tel_photons, 330	shower_extra_parameters, 120
write_tel_pos, 331	niparam
mdisp	shower_extra_parameters, 121
basic_ntuple, 40	nmod
merge simtel.c, 332	ConfigValues, 63
min_amp	num hot
user_parameters, 128	hess_tel_image_struct, 99
min pix	nood_tol_imago_otraot, oo
user_parameters, 128	offset fov
min_tel_img	hess_run_header_struct, 92
user_parameters, 128	offset_to_angles
mirror_area	rec_tools.h, 351
hess_camera_settings_struct, 70	opt_theta_cut
mkgmtime	user_analysis.c, 389
current.c, 148	overflow
current.h, 151	histogram, 108
mod_flag	overflow_2d
ConfigValues, 62	histogram, 108
moments, 116	
moments.c, 334	PIX_TIME_PEAKPOS_TYPE
alloc_moments, 336	io_hess.h, 272
clear_moments, 336	PIX_TIME_STARTPOS_ABS_TYPE
fill_mean, 338	io_hess.h, 272
fill_mean_and_sigma, 338	PIX_TIME_STARTPOS_REL_TYPE
fill_moments, 338	io_hess.h, 272
fill_real_mean, 339	PIX_TIME_WIDTH_ABS_TYPE
fill_real_mean_and_sigma, 339	io_hess.h, 272
fill_real_moments, 339	PIX_TIME_WIDTH_REL_TYPE
free_moments, 340	io_hess.h, 273 permissive pipes
stat_moments, 340	fileopen.c, 172
momstat, 116	•
mscrl	phi
basic_ntuple, 40	hess_tel_image_struct, 99 photo_electron, 117
mscrw	atime, 118
basic_ntuple, 40	lambda, 118
n fail	pixel, 118
basic_ntuple, 41	photons_atm_qe
n img	hess_mc_pe_sum_struct, 78
basic_ntuple, 41	pixel
n pix	photo_electron, 118
basic_ntuple, 41	pixel_integration
n_trg	reconstruct.c, 361
··_··ʊ	100011011001101, 001

pixel_timing_analysis	pulse_sum_loc
reconstruct.c, 361	hess_pixel_timing_struct, 88
primary	PzpsaPeakProperty
basic_ntuple, 41	reconstruct.c, 362
primary_id	PzpsaSmoothUpsampleU16
hess_mc_shower_struct, 84	reconstruct.c, 362
primetab	
histogram.c, 224	r_nb
print_camera_layout	user_parameters, 128
io_simtel.c, 289	range_list_struct, 118
mc_tel.h, 317	range_low_az
print_hashed_trgmasks	hess_tracking_setup_struct, 106
io_trgmask.c, 306	rcm
io_trgmask.h, 309	basic_ntuple, 42
print_hess_aux_trace_analog	read_camera_layout
io_hess.c, 260	io_simtel.c, 290
print_hess_aux_trace_digital	mc_tel.h, 319
io_hess.c, 260	read_config_lines
print_hess_pixcalib	hconfig.c, 186
io hess.c, 260	hconfig.h, 198
print_histogram	read_config_status
histogram.c, 222	hconfig.c, 187
histogram.h, 248	hconfig.h, 199
print histograms	read_eventio_registry
io_histogram.c, 275	eventio_registry.c, 159
io_histogram.h, 278	eventio_registry.h, 161
print_photo_electrons	read_func
io_simtel.c, 289	Config_Binary_Item_Interface, 51
mc_tel.h, 317	read_hess.c, 341
print_pix_col	read_hess_nr.c, 346
	read_hess_pixcalib
camera_image.c, 143	io_hess.c, 260
print_tel_block	read_histograms
io_simtel.c, 289	io_histogram.c, 275
mc_tel.h, 317	io_histogram.h, 279
print_tel_offset	read_histograms_x
io_simtel.c, 290	io_histogram.c, 276
mc_tel.h, 318	io_histogram.h, 279
print_tel_pos	read_input_lines
io_simtel.c, 290	io_simtel.c, 292
mc_tel.h, 318	mc_tel.h, 319
private_shower_extra_parameters	read_photo_electrons
io_simtel.c, 305	io_simtel.c, 292
prog_path	mc_tel.h, 319
user_analysis.c, 384	read_shower_longitudinal
ps_begin_page1	io_simtel.c, 293
camera_image.c, 143	mc_tel.h, 320
ps_begin_page2	read_tel_array_end
camera_image.c, 144	io_simtel.c, 294
ps_end_page	mc_tel.h, 321
camera_image.c, 144	read_tel_array_head
ps_head1a	io_simtel.c, 294
camera_image.c, 144	mc_tel.h, 321
ps_head1b	read_tel_block
camera_image.c, 144	io_simtel.c, 295
ps_trailer	mc_tel.h, 322
camera_image.c, 145	read_tel_offset
pulse_sum_glob	io_simtel.c, 295
hess_pixel_timing_struct, 88	mc_tel.h, 322
·	_

read_tel_offset_w	reset_local_offset
io_simtel.c, 296	current.c, 148
mc_tel.h, 323	current.h, 152
read_tel_photons	reverse_flag
io_simtel.c, 296	hess_run_header_struct, 92
mc_tel.h, 324	rhofx
read_tel_pos	atmprof.c, 135
io_simtel.c, 297	rndm2.h, 366
mc_tel.h, 324	root_exe_path
readtext_func	fileopen.c, 172
Config_Binary_Item_Interface, 51	root_path
real	fileopen.c, 173
Histogram_Parameters, 112	rpol
rec_tools.h, 347	atmprof.c, 136
angle_between, 348	user_analysis.c, 384
angles_to_offset, 349	run
cam_to_ref, 349	basic_ntuple, 42
get_shower_trans_matrix, 349	hess_run_header_struct, 92
intersect_lines, 350	run_type
line_point_distance, 350	hess_run_header_struct, 93
offset_to_angles, 351	second moments
shower_geometric_reconstruction, 351	reconstruct.c, 364
reconfig	section
hconfig.c, 187	ConfigValues, 63
hconfig.h, 199	select_calibration_channel
reconstruct	reconstruct.c, 364
reconstruct.c, 363	select_struct, 119
reconstruct.c, 352	set_aux_warning_function
CALIB_SCALE, 355	warning.c, 391
calibrate_amplitude, 355	warning.h, 397
calibrate_pixel_amplitude, 356	set_config_filename
clean_image_tailcut, 356	hconfig.c, 188
find_neighbours, 357	hconfig.h, 200
global_peak_integration, 357	set_config_history
gradient_integration, 358	hconfig.c, 188
image_reconstruct, 358	hconfig.h, 200
local_peak_integration, 358	set_config_preprocessor
nb_fc_shaped_peak_integration, 359	hconfig.c, 188
nb_peak_integration, 360	hconfig.h, 201
pixel_integration, 361	set_config_stack
pixel_timing_analysis, 361	hconfig.c, 189
PzpsaPeakProperty, 362 PzpsaSmoothUpsampleU16, 362	hconfig.h, 201
reconstruct, 363	set_current_offset
second_moments, 364	current.c, 148
select_calibration_channel, 364	current.h, 152
set_disabled_pixels, 365	set_disabled_pixels
set_integration_correction, 365	reconstruct.c, 365
simple_integration, 365	set_ev_reg_std
refidx	eventio_registry.c, 159
atmprof.c, 135	eventio_registry.h, 162
reload_config	set_first_histogram
hconfig.c, 187	histogram.c, 222 histogram.h, 248
hconfig.h, 200	set_integration_correction
res1	reconstruct.c, 365
ConfigItemStruct, 59	set_local_offset
res2	current.c, 149
ConfigItemStruct, 59	current.h, 152
Somgitom statis, ou	oanonan, rot

set_log_file	The read_hess (aka read_simtel, read_cta) pro-
warning.c, 392	gram, 28
warning.h, 397	The read_hess_nr program, 31
set_logging_function	The split_hessio program, 32
warning.c, 392	straux.c, 369
warning.h, 398	abbrev, 370
set_output_function	getword, 370
warning.c, 392	stricmp, 371
warning.h, 398	straux.h, 371
set_permissive_pipes	abbrev, 372
fileopen.c, 172	getword, 373
fileopen.h, 176	stricmp, 373
set_tel_idx	stricmp
io_hess.c, 261	straux.c, 371
set_tel_idx_ref	straux.h, 373
io_hess.c, 261	tailcut_low
set_warning	user_parameters, 129
warning.c, 393	tel_idx
warning.h, 398	The extract_simtel program, 22
shower_extra_parameters, 119	The merge_simtel program, 26
fparam, 120	tel_idx_out
id, 120	The extract_simtel program, 22
iparam, 120	The merge_simtel program, 26
is_set, 120	tel pos
nfparam, 120	hess_run_header_struct, 93
niparam, 121	tel_type_param, 121
weight, 121	teldata_pattern
shower_geometric_reconstruction	hess_central_event_data_struct, 73
rec_tools.h, 351	telescope_list, 122
	telescope_type
shower_prog_id	user_analysis.c, 389
hess_mc_run_header_struct, 81	teltrg_pattern
sig_e	hess_central_event_data_struct, 73
basic_ntuple, 42	teltrg_time
sig_mscrl	hess central event data struct, 73
basic_ntuple, 42	tentries
sig_mscrw	histogram, 108
basic_ntuple, 42	The add_histograms program, 13
sig_theta	main, 13
basic_ntuple, 42	The best_of program, 14
sig_xmax	The check_trgmask program, 18
basic_ntuple, 43	The extract_hess program, 19
simple_integration	main, 19
reconstruct.c, 365	The extract_simtel program, 20
size	check_autoload_trgmask, 21
ConfigItemStruct, 59	map_to, 22
sort_histograms	tel_idx, 22
histogram.c, 223	tel_idx_out, 22
histogram.h, 249	The fcat program, 16
split_hessio.c, 368	The gen_trgmask program, 23
stat_histogram	The hdata2hbook program (cvt2), 34
histogram.c, 223	main, 34
histogram.h, 249	The hdata2root program (cvt3), 35
stat_moments	The list_histogram program, 17
histogram.h, 249	main, 17
moments.c, 340	The merge_simtel program, 24
stop_signal_function	check_autoload_trgmask, 25
The merge_simtel program, 25	map_to, 26

stop_signal_function, 25	ubound_soft
. — • —	
tel_idx, 26	ConfigIntern, 56
tel_idx_out, 26	underflow
The read_hess (aka read_simtel, read_cta) program, 27	histogram, 109
CALIB_SCALE, 28	underflow_2d
main, 28	histogram, 109
stop_signal_function, 28	unlink_histogram
The read_hess_nr program, 30	histogram.c, 223
CALIB_SCALE, 30	histogram.h, 250
calibrate_pixel_amplitude, 30	uri_popen
main, 31	fileopen.c, 172
stop_signal_function, 31	user_analysis.c, 377
The split_hessio program, 32	ebias_correction, 381
main, 32	eval_cut_param, 381
stop_signal_function, 32	expected_max_distance, 381
theta	expected_max_height, 382
basic ntuple, 43	img_norm, 382
theta_escale	<u> </u>
user_parameters, 129	init_telescope_types, 383
thickx	interp, 384
atmprof.c, 136	opt_theta_cut, 389
threshold	prog_path, 384
	rpol, 384
hess_pixel_timing_struct, 88	telescope_type, 389
time_level	user_done, 385
hess_pixel_timing_struct, 88	user_event_fill, 385
time_string	user_finish, 386
current.c, 149	user_get_type, 386
current.h, 153	user_mc_event_fill, 386
timval	user_mc_shower_fill, 387
hess_pixel_timing_struct, 88	user_set_clipping, 387
tm_slope	user_set_flags, 387
hess_tel_image_struct, 100	user_set_focal_length, 387
tohbook.c, 374	user_set_length_max_cut, 388
toroot.cc, 375	user_set_tel_type_param_by_str, 388
convert_histograms_to_root, 376	user set theta escale, 388
histogram_to_root, 376	user_set_width_max_cut, 388
tracking_mode	
hess_run_header_struct, 93	user_done
trgmask_entry, 122	user_analysis.c, 385
trgmask fill hashed	user_event_fill
io_trgmask.c, 307	user_analysis.c, 385
io_trgmask.h, 309	user_finish
trgmask_hash_set, 123	user_analysis.c, 386
trgmask_scan_log	user_flags
io trgmask.c, 307	user_parameters, 129
io_trgmask.h, 309	user_get_type
trgmask set, 123	user_analysis.c, 386
tslope	user_mc_event_fill
·	user_analysis.c, 386
basic_ntuple, 43	user_mc_shower_fill
tsphere	user_analysis.c, 387
basic_ntuple, 43	user_parameters, 124
Confighter Struct 60	calib_scale, 126
ConfigltemStruct, 60	camera_clipping_deg, 126
histogram, 108	clip_amp, 127
ubound	d_integ_param, 127
ConfigItemStruct, 60	d_integ_param, 127 d_sp_idx, 127
-	
ubound_hard	impact_range, 127
ConfigIntern, 56	integ_no_rescale, 127

integ_param, 127	warning_status, 400
integrator, 128	warning_status
min_amp, 128	warning.c, 394
min_pix, 128	warning.h, 400
min_tel_img, 128	weight
r_nb, 128	basic_ntuple, 43
tailcut_low, 129	shower_extra_parameters, 121
theta_escale, 129	write_camera_layout
user_flags, 129	io simtel.c, 297
user_set_clipping	mc tel.h, 325
user_analysis.c, 387	write func
user_set_flags	Config_Binary_Item_Interface, 51
user_analysis.c, 387	write_hess_aux_trace_digital
user_set_focal_length	io hess.c, 261
user_analysis.c, 387	write_hess_event
user_set_length_max_cut	io hess.c, 262
user_analysis.c, 388	write_hess_laser_calib
user_set_tel_type_param_by_str	io_hess.c, 262
user_analysis.c, 388	write_hess_mc_event
user set theta escale	io_hess.c, 262
user_analysis.c, 388	write_hess_mc_pe_sum
user_set_width_max_cut	io_hess.c, 262
user_analysis.c, 388	
	write_hess_mc_shower
validate	io_hess.c, 263
ConfigItemStruct, 60	write_hess_pixcalib
values	io_hess.c, 263
ConfigIntern, 56	write_hess_run_stat
	io_hess.c, 263
warn_defaults	write_hess_shower
warning.c, 395	io_hess.c, 263
warn_f_output_text	write_hess_tel_monitor
warning.c, 393	io_hess.c, 263
warning.h, 399	write_hess_teladc_samples
warn_f_warning	io_hess.c, 264
warning.c, 394	write_hess_teladc_sums
warning.h, 399	io_hess.c, 264
warn_specific_data, 129	write_hess_televent
logfname, 130	io_hess.c, 264
warning.c, 389	write_histograms
flush_output, 391	io_histogram.c, 276
set_aux_warning_function, 391	io_histogram.h, 280
set_log_file, 392	write_input_lines
set_logging_function, 392	io_simtel.c, 298
set_output_function, 392	mc_tel.h, 325
set_warning, 393	write_photo_electrons
warn_defaults, 395	io_simtel.c, 298
warn_f_output_text, 393	mc_tel.h, 326
warn_f_warning, 394	write_shower_longitudinal
warning_status, 394	io_simtel.c, 299
warning.h, 395	mc_tel.h, 326
flush_output, 396	write_tel_array_end
set_aux_warning_function, 397	io_simtel.c, 300
set_log_file, 397	mc_tel.h, 327
set_logging_function, 398	write_tel_array_head
set_output_function, 398	io_simtel.c, 300
set_warning, 398	mc_tel.h, 327
warn_f_output_text, 399	write_tel_block
warn_f_warning, 399	io_simtel.c, 301
,	_ ,

```
mc_tel.h, 328
write_tel_compact_photons
    io_simtel.c, 301
     mc_tel.h, 328
write_tel_offset
     io simtel.c, 302
     mc_tel.h, 329
write_tel_offset_w
     io_simtel.c, 302
     mc_tel.h, 330
write_tel_photons
     io_simtel.c, 303
     mc_tel.h, 330
write_tel_pos
     io_simtel.c, 304
     mc_tel.h, 331
Χ
     hess_tel_image_struct, 100
хc
    basic_ntuple, 43
xc_true
    basic_ntuple, 44
xfirst_true
    basic_ntuple, 44
xmax
     basic_ntuple, 44
     hess_mc_shower_struct, 84
xmax_true
    basic_ntuple, 44
ус
     basic_ntuple, 44
yc_true
    basic_ntuple, 44
zero_sup_mode
     hess_camera_software_setting_struct, 71
```