
More PROCESSES!



Computer System Organization

- Computer-system operation
 - One or more CPUs, device controllers connect through common bus providing access to shared memory
 - Concurrent execution of CPUs and devices competing for memory cycles








Computer-System Operation

- I/O devices and the CPU can execute concurrently
- Each device controller is in charge of a particular device type
- Each device controller has a local buffer
- CPU moves data from/to main memory to/from local buffers
- I/O is from the device to local buffer of controller
- Device controller informs CPU that it has finished its operation by causing an interrupt






Interrupt Timeline







How a Modern Computer Works




A von Neumann architecture






Diagram of Process State







Ready Queue And Various I/O Device Queues








Representation of Process Scheduling

Queueing diagram represents queues, resources, flows







Schedulers


- Short-term scheduler (or CPU scheduler) selects which process should be executed next and allocates CPU
 - Sometimes the only scheduler in a system
 - Short-term scheduler is invoked frequently (milliseconds) ⇒ (must be fast)
- Long-term scheduler (or job scheduler) selects which processes should be brought into the ready queue
 - Long-term scheduler is invoked infrequently (seconds, minutes) ⇒
 (may be slow)
 - The long-term scheduler controls the degree of multiprogramming
- Processes can be described as either:
 - I/O-bound process spends more time doing I/O than computations, many short CPU bursts
 - CPU-bound process spends more time doing computations; few very long CPU bursts
- Long-term scheduler strives for good process mix






Addition of Medium Term Scheduling

- Medium-term scheduler can be added if degree of multiple programming needs to decrease
 - Remove process from memory, store on disk, bring back in from disk to continue execution: swapping







Context Switch

- When CPU switches to another process, the system must save the state of the old process and load the saved state for the new process via a context switch
- Context of a process represented in the PCB
- Context-switch time is overhead; the system does no useful work while switching
 - The more complex the OS and the PCB → the longer the context switch
- Time dependent on hardware support
 - Some hardware provides multiple sets of registers per CPU
 - → multiple contexts loaded at once






Process Creation

- Parent process create children processes, which, in turn create other processes, forming a tree of processes
- Generally, process identified and managed via a process identifier (pid)
- Resource sharing options
 - Parent and children share all resources
 - Children share subset of parent's resources
 - Parent and child share no resources
- Execution options
 - Parent and children execute concurrently
 - Parent waits until children terminate





A Tree of Processes in Linux








Process Creation (Cont.)

- Address space
 - Child duplicate of parent
 - Child has a program loaded into it
- UNIX examples
 - fork() system call creates new process
 - exec() system call used after a fork() to replace the process' memory space with a new program







C Program Forking Separate Process

```
#include <sys/types.h>
#include <stdio.h>
#include <unistd.h>
int main()
pid_t pid;
   /* fork a child process */
   pid = fork();
   if (pid < 0) { /* error occurred */
      fprintf(stderr, "Fork Failed");
      return 1;
   else if (pid == 0) { /* child process */
      execlp("/bin/ls", "ls", NULL);
   else { /* parent process */
      /* parent will wait for the child to complete */
      wait(NULL);
      printf("Child Complete");
   return 0;
```



Process Termination


- Process executes last statement and then asks the operating system to delete it using the exit() system call.
 - Returns status data from child to parent (via wait())
 - Process' resources are deallocated by operating system
- Parent may terminate the execution of children processes using the abort() system call. Some reasons for doing so:
 - Child has exceeded allocated resources
 - Task assigned to child is no longer required
 - The parent is exiting and the operating systems does not allow a child to continue if its parent terminates



UNIX shells

```
int main(int argc, char **argv)
{
 while (1) {
    printf ("$ ");
    char *cmd = get next command();
    int pid = fork();
    if (pid == 0) {
       exec(cmd);
       panic("exec failed!");
    } else {
       wait(pid);
```

States of a user process



The OS's process namespace

- (Like most things, the particulars depend on the specific OS, but the principles are general)
- The name for a process is called a process ID (PID)
 - An integer
- The PID namespace is global to the system
 - Only one process at a time has a particular PID
- Operations that create processes return a PID
 - E.g., fork()
- Operations on processes take PIDs as an argument
 - E.g., kill(), wait(), nice()

Representation of processes by the OS

- The OS maintains a data structure to keep track of a process's state
 - Called the process control block (PCB) or process descriptor
 - Identified by the PID
- OS keeps all of a process's execution state in (or linked from) the PCB when the process isn't running
 - PC, SP, registers, etc.
 - when a process is unscheduled, the execution state is transferred out of the hardware registers into the PCB
 - (when a process is running, its state is spread between the PCB and the CPU)
- Note: It's natural to think that there must be some esoteric techniques being used
 - fancy data structures that you'd never think of yourself
 Wrong! It's pretty much just what you'd think of!

The PCB

- The PCB is a data structure with many, many fields:
 - process ID (PID)
 - parent process ID
 - execution state
 - program counter, stack pointer, registers
 - address space info
 - UNIX user id, group id
 - scheduling priority
 - accounting info
 - pointers for state queues
- In Linux:
 - defined in task_struct (include/linux/sched.h)

PCBs and CPU state

- When a process is running, its CPU state is inside the CPU
 - PC, SP, registers
 - CPU contains current values
- When the OS gets control because of a ...
 - Trap: Program executes a syscall
 - Exception: Program does something unexpected (e.g., page fault)
 - Interrupt: A hardware device requests service
 the OS saves the CPU state of the running process in that process's PCB

- When the OS returns the process to the running state, it loads the hardware registers with values from that process's PCB – general purpose registers, stack pointer, instruction pointer
- The act of switching the CPU from one process to another is called a context switch
 - systems may do 100s or 1000s of switches/sec.
 - takes a few microseconds on today's hardware
- Choosing which process to run next is called scheduling


Process ID
Pointer to parent
List of children
Process state
Pointer to address space descriptor
Program counter stack pointer (all) register values
uid (user id) gid (group id) euid (effective user id)
Open file list
Scheduling priority
Accounting info
Pointers for state queues
Exit ("return") code value

This is (a simplification of) what each of those PCBs looks like inside!

Process execution states


- Each process has an execution state, which indicates what it's currently doing
 - ready: waiting to be assigned to a CPU
 - could run, but another process has the CPU
 - running: executing on a CPU
 - it's the process that currently controls the CPU
 - waiting (aka "blocked"): waiting for an event, e.g., I/O completion, or a message from (or the completion of) another process
 - cannot make progress until the event happens
- As a process executes, it moves from state to state
 - UNIX: run ps, STAT column shows current state
 - which state is a process in most of the time?

Process states and state transitions



State queues

- The OS maintains a collection of queues that represent the state of all processes in the system
 - typically one queue for each state
 - e.g., ready, waiting, ...
 - each PCB is queued onto a state queue according to the current state of the process it represents
 - as a process changes state, its PCB is unlinked from one queue, and linked onto another
- Once again, this is just as straightforward as it sounds! The PCBs are moved between queues, which are represented as linked lists. There is no magic!



• There may be many wait queues, one for each type of wait (particular device, timer, message, ...)

PCBs and state queues

- PCBs are data structures
 - dynamically allocated inside OS memory
- When a process is created:
 - OS allocates a PCB for it
 - OS initializes PCB
 - (OS does other things not related to the PCB)
 - OS puts PCB on the correct queue
- As a process computes:
 - OS moves its PCB from queue to queue
- When a process is terminated:
 - PCB may be retained for a while (to receive signals, etc.)
 - eventually, OS deallocates the PCB

Process creation

- New processes are created by existing processes
 - creator is called the parent
 - created process is called the child
 - UNIX: do ps, look for PPID field
 - what creates the first process, and when?

UNIX shells

```
int main(int argc, char **argv)
{
 while (1) {
    printf ("$ ");
    char *cmd = get next command();
    int pid = fork();
    if (pid == 0) {
       exec(cmd);
       panic("exec failed!");
    } else {
       wait(pid);
```