

# MC-BLOS (v1.0) User Manual

# **Terminology**

- B<sub>LOS</sub>: Line-of-sight component of magnetic field
- Reference Point: Points representing final selected "OFF positions"

• RM: Rotation Measure

#### 1 Introduction

The MC-BLOS software, described in Tahani et al. (2024), determines the line-of-sight component of magnetic fields ( $B_{LOS}$ ) associated with molecular clouds using the Faraday rotation-based technique developed by Tahani et al. (2018). The software is automated utilizing user input in configuration files and supplied data files to perform an analysis and output the results as output files for the user's review.

# 2 Installation

# 2.1 Minimum Python Version

The minimum Python version is 3.6.1. Due to library dependencies, the software will not work with any Python version below 3.6.1.

# 2.2 Quick Setup and Installation

Once Python has been installed, the remaining components can be quickly configured by running the Initialize.py script, either directly or in the terminal as follows:

python Initialize.py

The initialization script installs the required packages, sets up the configuration files, and downloads necessary data. Once this process is completed, the software is fully installed and ready for data analysis.

# 2.3 Obtaining the Data

In order for the analysis to be conducted on a given region, three pieces of data must be obtained:

Rotation Measure Catalog: A rotation measure catalog must be obtained and placed in the Data/RMCatalog directory, with the appropriate format specified by the example in the file RMCatalogueHeader.csv. Catalogs with the same format as the Van Eck et al. (2023) catalog can be converted utilizing the UserRMCatalog\_ifVanEckFormat.py script, via the instructions in its code documentation. The catalog must cover the region or cloud of interest; otherwise, there will be no data to analyze.

Region Fits File: A fits file, either Extinction or Hydrogen Column Density, which contains information for the region or cloud of interest. Place these files inside the Data directory.

Cloud Parameters: A .ini configuration file, which specifies information about the region of interest, including its distance from us, chemical code parameters, the rotation measure catalog's area of coverage, and image subsections of the fits file. This file ties all the data together. Place these files in Data/CloudParameters. Examples can be seen inside this directory. A template is automatically generated as part of the initialization process.

The initialization script downloads the Taylor et al. (2009) catalog, the Van Eck et al. (2023) catalog (converted into the Taylor et al. (2009) format), and Hydrogen Column Density fits files for a large number of regions. By default, the Taylor et al. (2009) catalog is selected. To use the Van Eck et al. (2023) consolidated catalog instead, follow the instructions at the bottom of configDirectoryAndNames.ini, replacing catalog.dat with van\_eck\_(taylor\_format).dat.

User's RM catalog: To utilize other catalogs with the Taylor et al. (2009) catalog format, simply place it into the Data/RMCatalog folder. To utilize other catalogs with the Van Eck et al. (2023) format, run the UserRMCatalog\_ifVanEckFormat.py script as per the instructions within that script and place its output file into the Data/RMCatalog folder. An example of how to do that is here:

python3 UserRMCatalog\_ifVanEckFormat.py [RM file path] [output complete path] [merge flag]

The current version of the software is optimized for catalogs with cross-matched RMs, if multiple observations exist. As the Van Eck et al. (2023) catalog does not currently include this cross-matching (contains multiple RM values for a single source from different catalogs), users may encounter some limitations when using it with the software. The merging of close datapoints according to their overlapping RA and Dec uncertainties is automatically provided while downloading the Van Eck et al. (2023) catalog—and as an option when utilizing user's own RM catalog—by averaging all cross-matched RMs and propagating their uncertainties to provide a final RM uncertainty for that point.

Default cloud parameters are provided in the Data/Cloud Parameters directory. Any data not provided by default must be placed in the appropriate location by the user. For Cloud Parameters, users must create files according to the template and specify them accordingly.

# 2.4 Configuration

Configuration files control the operation of the scripts and are the primary means by which user input or decision-making is taken into account before the analysis is conducted. The main configuration files are:

**configStartSettings:** Contains parameters involving human judgment or stylistic choices. This includes settings for cloud selection, reference point qualification, and plotting and logging styles. This is the primary file to adjust before each analysis.

**configDirectoryAndNames:** Specifies the names of directories and files utilized and produced by the scripts. Users can modify this file if they wish to rename files or directories, or relocate certain folders.

**configConstants:** Contains the values of constants used in the scripts' calculations. It is recommended to verify these values before proceeding with the analysis.

Further details on each configuration option are available within the configuration files themselves, via their naming or the preceding comments.

# 3 Conducting the analysis - Quick Overview

#### 3.1 Setting Up

Once the files have been installed, we can begin to prepare for conducting the analysis.

1. Check that the constants defined are correct in:

2. Check that the directory file naming scheme is to your satisfaction in:

3. Check that the various starting settings and judgment parameters are to your satisfaction in:

The following will need to be done for every given region of interest:

- Check that your region of interest is correctly defined in its Region.ini file (located in Data/CloudParameters).
  - If your region of interest is not defined, create a new region.ini data file and fill out the data accordingly. Then place it in the Data/CloudParameters directory.
  - An example template has been placed in the directory for you. It is called 0 template.ini

# 3.2 Running the analysis

Before conducting the analysis, user input is defined in configStartSettings.ini. Please review these settings before conducting the analysis.

Run-all scripts are provided, which automate the process of running each of the scripts in order. Different quick run scripts are provided for different use cases. Further details on the run-all scripts are as follows:

Run.py: Standard Run-all script which runs each of the seven steps of the analysis in sequence, utilizing the default configuration files. It can be run directly, or through the terminal via:

RunCloud.py: Meant to be run through the terminal only, and clouds to be analyzed are specified afterwards. Any number of clouds can be specified, so long as the data is available, separated by a space. Ex:

RunConfigCloud.py: If the user wishes to run the analysis on an alternatively specified starting configuration file, they can utilize this script. The user specifies the starting configuration file as the first argument in the terminal. It must be of the exact same format as the regular configStartSettings.ini file. Once it finishes, it will rename the output folder with the config file's name, to keep track of what configuration file was used. Ex:

python RunParamCloud.py altStartConfig.ini Oriona Orionb Taurus California Perseus

If permission issues are encountered, attempt deleting the original FileOutput folder entirely, and closing any other programs which may be utilizing the software's folder.

Each step of the analysis corresponds to the scripts numbered in the main directory, and are meant to be run one at a time in the order indicated by their name. Each step will produce output either in the form of a figure or a table of data. Output will be saved to a folder with the same name as the region of interest. It is strongly recommended that the output be critically examined after each analysis, and starting configuration parameters adjusted accordingly.

# 3.3 Input and Output Files

At a high level, the program takes in the data associated with a region, along with the information from the user's judgment, processes it, and then returns output in the form of the analyzed results. All of these are encoded within files. By default, unless changed in the directories configuration file (configDirectoryAndNames.ini), their names will be as outlined here.

#### 3.3.1 Input Files

The input files consist of the configuration files and the input data. The configuration files are located in the main directory, along with the main scripts, and more information on the parameters controlled by the configuration files can be found in this manual, in Tahani et al. (2024), or in the configuration files themselves. The input data are stored in the *Data* directory, which has the following structure:

- Fits files Extinction fits files should be stored directly within this directory, rather than any sub-directory.
- CloudParameters This directory contains the Region of Interest files which a user must create in order to analyze a given region. Examples for multiple regions come with the software. These files contain information on a region and point to the relevant fits file and chemical abundance information for the given region. An example template can be found with 0- cloudTemplate.ini. These files can be opened and edited with any text editor.
- Chemical Abundance This directory contains the results of the chemical evolution code which are utilized in the analysis. Each sub-directory corresponds to a given set of parameters, the files within which correspond to the results of those parameters.
- RMCatalog This directory contains the rotation measure catalogs.

# 3.3.2 Output Files

By default, the final results and data on the intermediate calculations by the program are output files, which are stored in the FileOutput folder within the program directory. Within this folder, the results of the analysis are stored in a folder corresponding to the name of the region analyzed. Within the output files folder for the given region, the files are further sorted into sub-folders:

- Logs Each file corresponds to human-readable logs for one of the scripts corresponding to
  the steps of the technique. Each log provides information on what the script is doing, why
  it is doing what it does, important values to be aware of, and where the files are being saved
  at each stage of the analysis. Reading these scripts is recommended for understanding the
  program's decisions.
- IntermediateData Each file corresponds to calculated values utilized between stages of the analysis which may not be of interest to the user except to verify the integrity of the analysis. The files are as follows:
  - AnomRej.csv Potential OFF points rejected for having anomalous RM values.

- FarHighExtRej.csv Potential OFF points rejected for being too far from a point of high extinction.
- NearHighExtRej.csv Potential OFF points rejected for being too near a point of high extinction.
- Rejected.csv Potential OFF points rejected for any reason.
- Remaining.csv Potential OFF points remaining after all the reasons to reject them.
- FilteredRMExtinction.csv Potential OFF points remaining after the policy on maximum fraction of OFF points is applied.
- QuadrantDivisionData.csv Data on the equations which split the extinction map of the region into four equally-weighted quadrants.
- RegionThresholdData.csv Data on the extinction thresholds utilized to judge the region.
- TrendDataTable.csv Data on the magnetic field stability trend's input.
- DensitySensitivity The results of density variation on magnetic field calculations are stored here. The name of the file corresponds to the variation B\_Av\_T0\_n[].csv, where [] corresponds to the percentage change. It is utilized for uncertainty calculations and assumes no temperature variation.
- TemperatureSensitivity The results of temperature variation on magnetic field calculations are stored here. The name of the file corresponds to the variation B\_Av\_T[]\_n0.csv, where [] corresponds to the percentage change. It is utilized for uncertainty calculations and assumes no density variation.
- Plots Informative plots meant to be utilized or examined by the user. These can be divided into two categories plots meant to provide feedback on the steps of the analysis, and plots which represent the final products of the analysis. Plots meant to provide feedback on the steps of the analysis are as follows:
  - RMMap.png A map of all the rotation measures and where they are in the extinction map of the region.
  - AllPotRefPts.png A map of all the potential OFF points, as filtered by the maximum extinction criteria.
  - ExtRefPts.png A map of the extinction thresholds defined in the config, and how they
    cut up the region.
  - Filter\_[].png The potential OFF points rejected for the reason in [], plotted against the extinction map. For example, Filter\_AnomRM.png plots the potential OFF points rejected for having an anomalous rotation measure.
  - AllRefPointSorted.png All the potential OFF points sorted, between those which have been rejected and those that remain.
  - QuadrantDivisionPlot.png The division of the region into four quadrants for the four-quadrant analysis.
  - ChosenRefPoints.png the reference points chosen as OFF positions for the region.
  - BLOS\_vs\_NRef\_AllPotentialRefPoints.png Stability trend graph with all potential OFF points.
  - BLOS\_vs\_NRef\_ChosenRefPoints.png Stability trend graph with only the chosen reference points.

The plots meant to represent the final products of the analysis are as follows:

- BDensitySensitivity.png - A figure of the density sensitivity of the region based off how much it changes relative to changes in density (part of the error analysis).

- BTemperatureSensitivity.png A figure of the temperature sensitivity of the region based off how much it changes relative to changes in temperature (part of the error analysis).
- BLOSPointMap.png The map of the line-of-sight magnetic field of the region.
- FinalData The final results of the analysis. The files are as follows:
  - MatchedRMExtinction.csv All rotation measure points in the region with their matched extinctions relative to the region.
  - AllPotentialRefPoints.csv All the rotation measure points which have sufficiently low extinction as to be a potential OFF point.
  - SelectedRefPoints.csv The reference points chosen to sample the Galactic contribution (non-cloud contribution).
  - ReferenceData.csv The reference value of the Galactic contribution as calculated utilizing the chosen OFF points (reference points).
  - BLOSPoints.csv The calculated magnetic field values for the given region.
  - FinalBLOSResults.csv The final magnetic field values with uncertainties calculated.

# 4 Installation Information and Troubleshooting

# 4.1 What Initialize.py Does

When run, the script runs the three setup 00 scripts in order:

- 00aInstallPackages.py Installs the python packages required for the program to work.
- 00bMakeConfig.py Creates or resets the three configuration files.
- OocDownloadExampleData.py Downloads the default example data set, consisting of the Taylor et al. (2009) catalog, and hydrogen column density data for many regions. It also downloads the Van Eck et al. (2023) catalog, merges overlapping RM measurements not accounted for by the catalog, and converts it into the Taylor et al. (2009) format for optional use.

These scripts can be run on their own, if only specific steps are needed. Further elaboration on those steps are given in the following subsections.

# 4.2 Installing Required Modules

The following packages are installed by *Initialize.py*, which invokes 00aInstallPackages.py.

astropy
matplotlib
pandas
requests
adjustText
numpy
scipy
sklearn

These packages can also be manually installed in case the script fails, by utilizing the terminal with the command:

pip install –upgrade [package]

Where [package] is to be replaced with the name of the package to be installed.

# 4.3 Initializing and Resetting Configuration Files

If the software fails to load due to configuration errors, or if a clean slate configuration is desired, the config files can be reset by simply rerunning OObMakeConfig.py. This will overwrite the three configuration files (or recreate them, if missing) with the default configuration and values.

# 5 MC-BLOS - Structure and Explanation

# 5.1 Overview of Steps

The MC-BLOS method is conducted over 7 steps. each of which may have several associated scripts.

- Step 1: Preparation: (01): The necessary output folders and sub-folders are created.
- Step 2: Rotation Measure-Extinction Matching: (02a): The rotation measure points are read from the defined catalog and matched to visual extinction values using a map of the region of interest. (02b): Optionally, the rotation measure points can be plotted over a map of the region of interest in order to get a sense of the rotation measure coverage.
- Step 3: The reference points are chosen. These points represent selected OFF positions, as defined in Tahani et al. (2024). (03a): First, candidate OFF points are identified, and filtered for disqualifying features. (03b): Next, the stability trend analysis is performed. (03c): Optionally, the results of this stage may be plotted for information on the decision making process conducted by the script.
- Step 4: (04): The  $B_{LOS}$  directions and values are determined and calculated for the rotation measure points in the region of interest using the reference points found in step 3.
- Steps 5 & 6: The  $B_{LOS}$  uncertainties that result from using different density (05a) and temperature (06a) values as input parameters to the chemical code are determined. (05b and 06b): The results are then plotted.
- Step 7: (07): The total uncertainty in B<sub>LOS</sub> values is calculated (resulted from RM, RM<sub>ref</sub>, extinction values, and input parameters to the chemical code).

# 5.2 Notes on Step 3: Selection of Reference Points

Step 3 requires the most input from the starting configuration file, as this is the step in which the reference points are chosen. Reference points are meant to estimate the Galactic contribution to the observed rotation measure.

The primary criterion for determining reference points is their visual extinction value. The program will identify all points with extinction values below a specified threshold and arrange them sequentially based on increasing extinction levels, as "potential OFF points". The Galactic coordinate of the cloud can help select this threshold value (see Tahani et al. (2024)).

The program will also flag and remove points that are too close to the cloud, and points that have odd anomalous rotation measure values. The program can also flag and remove points which are too far from the cloud to be considered for sampling the Galactic contribution. Points with these properties may require additional consideration from the user as to whether they are suitable reference points. The program will then recommend an optimal number of points to take as reference points using a stability trend analysis. Afterwards, it will ensure that sufficient points have been sampled from around the cloud. The OFF points chosen after these steps will go on to form the Galactic contribution to the RM.

Figures displaying the location of these points, and their relevant data, are produced for user review, in case parameters need to be changed for the next analysis. These final information and map of reference points should be reviewed to ensure proper Galactic contribution sampling and that all sides of the cloud are properly sampled.

# References

Tahani, M., Ngo, J. M., Glover, J., et al. 2024, arXiv e-prints, arXiv:2407.13005

Tahani, M., Plume, R., Brown, J. C., & Kainulainen, J. 2018, A&A, 614, A100

Taylor, A. R., Stil, J. M., & Sunstrum, C. 2009, ApJ, 702, 1230

Van Eck, C. L., Gaensler, B. M., Hutschenreuter, S., et al. 2023, ApJS, 267, 28