```
Minclude <string.h>
Fdefine MAXPAROLA 30
#define MAXRIGA 80
   int treq[MAXPAROLA]; /* vettore di contatoni
delle frequenze delle lunghazza delle pitrole
   char riga[MAXRIGA] ;
lint i, inizio, lunghezza
```

# **High Level Programming**

#### **Copy Control**

Stefano Quer
Dipartimento di Automatica e Informatica
Politecnico di Torino

#### **License Information**

#### This work is licensed under the license









(cc) (i) (S) (=) CC BY-NC-ND 4.0

#### Attribution-NonCommercial-NoDerivatives 4.0 International

This license requires that reusers give credit to the creator. It allows reusers to copy and distribute the material in any medium or format in unadapted form and for noncommercial purposes only.

- BY: Credit must be given to you, the creator.
- S NC: Only noncommercial use of your work is permitted. Noncommercial means not primarily intended for or directed towards commercial advantage or monetary compensation.
- ND: No derivatives or adaptations of your work are permitted.

To view a copy of the license, visit: https://creativecommons.org/licenses/by-nc-nd/4.0/?ref=chooser-v1

#### **Introduction**

- When a C++ class is defined, we implicitly or explicitly specify what happens when the class is
  - Copied, moved, assigned, and destroyed
- A class controls these operations with five special class member functions
  - > They are referred to as "copy control" functions
  - We can write them explicitly
  - If we do not write them, the compiler creates them **automatically** 
    - There are cases in which relying on the default definitions may lead to **disaster**
    - Thus, we need to learn how to define them

#### Introduction

- Copy control is performed by
  - Copy and Move constructors
    - Define the behavior when an object is initialized from another object
  - Copy and Move Assignment Operators
    - Define the behavior when we **assign** an object to another object
  - Destructor
    - Defines the behavior when an object ceases to exist

Beyond the standard constructor

Already analyzed in Unit 03

constructor.

#### **Copy Constructor**

A copy constructor is a special constructor that

Simple Example to understand what copy constructor is:
what copy constructor is:
For example, imagine you have allows the **definition** of an object **through** a

a class called Car, and you create an object car1 of type Car. Now, if you want to make another Car object that's exactly copy of an existing object of the same class like car1, you use the copy

> There may be multiple copy constructors

- Given a class C, copy constructors have
  - The same name of the class
  - An argument of type C& or const C& (preferred)
  - Possibly, additional parameters with default values

```
class Foo {
    When declaring a copy constructor, you typically want to pass the object to be copied by reference rather than by value. Passing by reference (Car&) is more efficient than passing by value (Car) because it avoids making a copy of the object being passed, especially for large objects.
    Passing by reference allows the copy constructor to access the original object directly, without the overhead of creating a new copy of the object.

Foo (); // Default constructor

Foo (const Foo&); // Copy constructor

In the copy constructor declaration, you might see const Car& instead of just Car&. Adding const indicates that the reference is to a constant object, meaning the copy constructor promises not to modify the original object.
```

## **Copy Constructor**

- The copy constructor
  - Is called by the compiler whenever an object is defined through a copy
  - By default copies all members of its argument into the object being created
  - Can refer directly to any private data of the object that must be copied into the current one

The arrow (->) is a C++ operator used to access members of a class or structure through a pointer. It is essentially a shorthand notation for dereferencing a pointer and accessing a member of the object being pointed to.

```
Rectangle::Rectangle (const Rectangle &to_copy) {
    this->m_width = to_copy.m_width; This line assigns the value of the m_width member variable of the to_copy object to the m_width member variable of the current object (referred to by this).

    this->m_length = to_copy.m_length; Similarly, this line assigns the value of the m_length member variable of the to_copy object to the m_length member variable of the current object.

    Pointer to the current instance

Parameter

Parameter

Private

data
```

```
class Class {
  public:
     Class (const char *str);
     ~Class();
  private:
                        Constructor
     char *str;
Class::Class (const char *s) {
  str = new char[strlen(s)+1];
  strcpy(str,s);
                        dynamic mem allocation
Class::~Class() {
                             Destructor
  delete[] str;
  dynamically alloc mem is
                     Destructors are denoted with ~
  deleted
```

Constructor & Destructor

**Synthesized** copy constructors

When implementing a copy constructor for a class that manages dynamically allocated resources, such as char\* in this case, it's crucial to perform a deep copy. This involves allocating new memory and copying the contents of the source object's dynamically allocated memory into the newly allocated memory.

#include <cstring>

The **synthetized** copy constructor copies each non static member from the given object to the created object. **Do we need to copy the pointer or duplicate the string?** 

Compiler-defined copy constructor

```
Class::Class (const Class &another) {
  str = another.str;
}
```

```
class Class {
                                                      Constructor
   public:
                                                     & Destructor
       Class (const char *str);
       ~Class();
   private:
                                 Constructor
       char *str;
Class::Class (const char *s) {
   str = new char[strlen(s)+1];
   strcpy(str,s);
Class::~Class() {
                                       Destructor
   delete[] str;
  The destructor deallocates the dynamically allocated memory to prevent memory leaks. It is
  responsible for releasing any resources acquired during the object's lifetime.
  The correct destructor implementation provided in your code snippet Class::~Class() is appropriate
  for deallocating the dynamically allocated memory pointed to by str.
```

**User-defined** copy constructors

#### #include <cstring>

Memory Allocation:

new char[strlen(str) + 1] dynamically allocates memory on the heap for storing a string. strlen(str) calculates the length of the input string str, and +1 is added to account for the null terminator ("\0') required at the end of the string.

The result is a pointer to the first character of the allocated memory block, which is assigned to the pointer variable m\_string.

String Copying:

stropy(m\_string, str) copies the content of the input string str to the dynamically allocated memory block pointed to by m\_string.

This function iterates through each character of the source string str and copies it to the destination string m\_string, including the null terminator.

We may want to duplicate the string

User-defined copy constructor

```
Class::Class (const Class &another) {
   str = new char[strlen(another.str)+1];
   strcpy(str,another.str);
```

When implementing a copy constructor for a class that manages dynamically allocated resources, such as char\* in this case, it's crucial to perform a deep copy. This involves allocating new memory and copying the contents of the source object's dynamically allocated memory into the newly allocated memory.

It is now possible to better

**Activation** of the copy constructors

Direct initialization involves calling and erstand the difference between constructor explicitly with a set of

Direct initialization and copy initialization

arguments enclosed in parentheses Example: string s1(10, '.'); In direct initialization, the compiler calls the constructor that best matches the provided arguments.

The copy constructor is pot typically

invoked during direct initialization, as it's called only when an object is

```
being created as a copy of another Direct initialization object.
                                                                  Copy initialization involves initializing
                string s1(10,'.');
                                                                  an object using the = operator with
                                                                  another object or a value of
                                                                  compatible type
                string s2(s1);
                                                                  Example: string s3 = s1;
                                                                  In copy initialization, the compiler
                                                                  invokes the copy constructor to create
                                                                  a new object by copying the contents
                                                                  of the right-hand operand into the
                // Copy initialization Copy initialization can also occur
                                                                  when creating a temporary object to
                string s3 = s1;
                                                                  initialize another object, such as string
                                                                  s5 = string(100, '9');
                string s4 = "1234567890";
                string s5 = string (100, '9');
```

#### **Standard** constructor:

The compiler calls the function that best matches the arguments

#### **Copy** constructor:

The compiler copies the righthand operand into the object being created

This is not a constructor (activated only when the object is created) but an assignment

The copy assignment operator is called when an already initialized object is assigned a new value from

string s6;

s6 = s1;

#### **Copy assignment operator**

Copy Assignment Operator:

The copy assignment operator (operator=) is a special member function in a class that defines how one object can be assigned the value of another object of the same type.

It is used when objects are assigned to each other using the assignment operator (=).

Example: c2 = c1; or myc1 = myc2;
The copy assignment operator is

The copy assignment operator is invoked when an object is already initialized, and its value is being replaced with the value of another object. It is used to perform a shallow copy or deep copy, depending on the requirements of the class and the semantics desired by the programmer.

- Copy control is called when object are copied at initialization
- Copy assignment operator is called when objects

are **assigned** 

The copy assignment operator is called when an already initialized object is assigned a new value from another existing object.

```
my_class c1, c2;
...
c2 = c1;

Use the my_class copy
assignment operator
Either the implicitly or the user-
defined one

class sales myc1, myc2;.
...
myc1 = myc2;
```

## **Copy assignment operator**

- The copy assignment operator controls how objects are assigned
  - > Given a class C, assignment operators have
    - The name operator=
    - An argument of type C& or const C& (preferred)
    - A return type (usually a C&)
  - The compiler generates a synthesized copy assignment constructor if the class does not define one

```
class Foo {
   public:
     Foo& operator= (const Foo&);
}
```

```
class sales {
  public:
     sales (const sales&);
     sales& operator= (const saless=&);
  private:
     std::string number;
     int sold = 0;
     double revenue = 0.0;
}
```

**Synthesized** copy assignment

Equivalent to the synthesized copy constructor

Empty body

Equivalent to the synthesized copy assignment

```
number(orig.number), from the sold(orig.sold), revenue(orig.revenue)

{    }
sales& sales::operator= (
    number = orig.number;
    sold = orig.sold;
    revenue = orig.revenue;
    return *this;
```

sales::sales (const sales &orig):

The copy constructor creates a new sales object by copying the data members from another sales object passed as a parameter.

It initializes the new object with the same values as the original object.

The member initialization list (number(orig.number), sold(orig.sold), revenue(orig.revenue)) initializes the data members number, sold and revenue of the new object with the corresponding values from the original object orig.

#### (const sales &orig) {

The copy assignment operator (operator=) defines how one sales object can be assigned the value of another sales object.

It copies the data members from the right-hand operand (orig) to the left-hand operand (\*this).

Each data member (number, sold, and revenue) of the current object (\*this) is assigned the corresponding value from the orig object.

The assignment operator returns a reference to the current object (\*this) to allow chaining of assignment operations (sales1 = sales2) = sales3;).

# Introduced in Unit 03

#### **Destructor**

- The destructor reverse the operations done by the constructors
  - Variables are destroyed when they go out of scope
  - Member of an object are destroyed when the object to which they belong to is destroyed
  - Elements is a container are destroyed when the container is detroyed
  - Dynamically allocated objects are destroyed when delete is called
  - ➤ Temporary objects are destroyed at the end of the expression in which they were temporary created

# Introduced in Unit 03

#### **Destructor**

- The destructor do whatever is need to reverse done by the constructors
  - > Given a class C, the destructor has
    - The name ~C
    - No argument (does it cannot be overloaded)
  - ➤ It is called automatically whenever an object is destroyed

```
class Foo {
  public:
    ~Foo ();
}
```

```
Activation of the
                                                                                                      destructor
// New scope
       This line is creating a new instance of my_class on the heap and storing the address of the newly created object in the pointer p1.
                                                                         // p1 is a standard ptr
my class *p1 = new my class;
auto p2 = make_shared<my_class>(); // p2 is a shared ptr This line is creating a new instance of auto p2 = make_shared
the ective class item (*p1); This line is creating a new instance of my_class on the stack by copying the object pointed to by p1. This is done using the // Constructor copy copy constructor of my_class.
                                                                                  pl into item
vector<my class> v; This line is creating a vector v that can store objects of type my_class.
                                                                         // Local object
v.push back (*p2); This line is adding a copy of the object pointed to by p2 to the end of the vector v. This is done using the copy constructor of my class. // Copy the object to which
                                                                               p2 points
delete p1; - This line is deleting the object pointed to by p1 from the heap. This calls the destructor of my_class for the object pointed to by p1.
                                                                         // Destrutor called on
                                                                                   the object pointed by p1
                               The destruction of p2 decrements its reference count, and if the reference count goes to zero (which it does in this case, as there are no other shared pointers to the object), the object it points to is destroyed. The
      Scope ends
      Destructor called on item, p2, and v
     Destroying p2 decrements its counter; if it goes to zero,
      the object is free
// Destroying v destroys the element in v
```

#### The "rule of three"

- If a class requires
  - A user-defined copy constructor
  - A user-defined copy assignment operator
  - A user-defined destructor
  - it almost certainly requires all three
- Explanation
  - A user-defined copy constructor (destructor) usually implies some custom setup (cleanup) logic which needs to be executed by copy assignment and vice-versa

#### **Move semantic**

- Copy constructor and copy assignment follow a copy semantics
  - There are cases in which the object is immediately destroyed after it is copied

Move semantics, introduced in C++11, are designed to efficiently transfer resources (like dynamically allocated memory) from one object to another, typically in cases where creating a copy is unnecessary or expensive.

 In those cases we incur in unnecessary and unwanted overhead

Before move semantics, C++ primarily relied on copy semantics. When you pass objects to functions or return them from functions, copies are often made.

In those cases **moving** instead of copying may enhance performance

- C++11 introduced the "move semantic"
- Move operators typically "steal" resources
  - They do not usually allocate resources
  - They do not ordinarily throw exceptions
- std::string func() {
   std::string str = "Hello";
   return str; // A copy of str is made
  }

std::string s = func();

// Here str is copied when returned from the function func(), which can be costly, especially for large strings.

#### Move semantic

- To support move C++11 introduced a new kind of reference, i.e., a rvalue reference
- Generally speaking
  - In C Ivalue stands on the left-hand side of assignments; rvalue could not Ivalue expressions

#### Lvalues:

An Ivalue refers to an object that has a name and can appear on the left-hand side of an assignment expression.

Lvalues represent objects that have a persistent identity and can be referenced or modified. Examples of Ivalues include variables, objects, and elements of arrays.

int x = 5: // 'x' is an Ivalue int arr[5]; // 'arr' is an Ivalue Can stand on the left-hand side of an expression

Refer to an object's identity

Have persistent state

#### rvalue expressions refer to an object's value

An rvalue refers to an object that does not have a name and typically appears on the right-hand side of an assignment expression. Rvalues represent temporary values or

temporary objects that are not persistently stored in memory.

Examples of rvalues include literal values, temporary objects created during expressions. and the results of function calls. Like the str in the previous slide example which is returned. Or these

int result = 3 + 4: // '3 + 4' is an rvalue int\* ptr = new int(10); // 'new int(10)' returns an rvalue

Are either literal or temporary objects create in the course of evaluating expressions

An rvalue reference is obtained by using && rather

than & The distinction between Ivalues and rvalues is based on the expression context.

Lyalues are objects that have a memory location and can be referenced or modified, while rvalues are temporary values or objects that don't have

Lyalues are typically used to represent variables, objects, or memory locations, while ryalues are used to represent temporary values or results of expressions.

persistent identities (Ivalues).

#### **Examples**

Rvalue references, denoted by &&, are a special type of reference introduced in C++11.

They can bind to temporary objects (rvalues) and are often used in move semantics to efficiently transfer resources from temporary objects.

Rvalue references are essential for enabling move semantics and improving performance in modern C++ code.

int&& rvref = 10; // '10' is an rvalue, 'rvref' is an rvalue reference // rvalue = i, lvalue = 42 int i = 5; // The rvalue is just another int i = 5:: Here, i is an Ivalue because it has a name and represents a memory location where the value 5 is stored. The value 5 itself is an rvalue because it's a // name for the object temporary value without a persistent identity. // bind an rvalue to a constant int &&r1 = 42;// OK, because the constant is int &&r1 = 42:: Here, r1 is an rvalue reference (denoted by &&) bound to the rvalue 42. Since 42 is an rvalue, it can be bound to an rvalue reference. // an rvalue int &&r2 = i \* 10;// OK as before // i\*10 is an rvalue int &&r2 = i \* 10;: The expression i \* 10 evaluates to a temporary value (an rvalue), which is then bound to the rvalue reference r2. The result of i \* 10 is an rvalue because it's a temporary value resulting from the expression. // Error: We cannot bind an int &&r3 = i; // rvalue to a variable i int &&r3 = i;: This line causes a compilation error because r3 is an rvalue reference, but i is an Ivalue. We cannot bind an rvalue // which is an lvalue reference to an Ivalue directly. Rvalue references are typically used to bind to temporary values (rvalues), not to objects with

#### **Move constructor**

Move constructors are special member functions in C++ that enable the efficient transfer of resources from one object to another.

- A move constructor is typically called when an object is initialized from an rvalue reference of the same type
  - > Given a class C, the move constructor has
    - The name C
    - An argument of type C&&
    - The **noexcept** keyword added to indicate that the constructor never throws an exception

noexcept is a C++ keyword used to specify that a function (including constructors, destructors, and assignment operators) does not throw exceptions.

```
class Foo {
   public:
      Foo (Foo&&) noexcept;
}
Foo::Foo (Foo&&) noexcept : { ... }
```

We cannot bind an rvalue to an Ivalue directly

```
int &&r = i;  // Error
```

However, we can cast an Ivalue to its corresponding rvalue

Although you cannot directly bind an Ivalue to an rvalue reference, you can use the std::move function to cast the Ivalue to an rvalue reference.

The std::move function is provided by the <utility> header and is used to convert an Ivalue to an ryalue reference.

- The utility header includes the function move
- ➤ The function move can be used to convert an Ivalue to an rvalue reference

```
String has its own
                                                                                       Activation of the
                              move constructor
struct X {
                                                                                          move operator
    int i;
                                                                              Move Constructor Activation:
    std::string s;
                                                                              When you use std::move on an object, you're signaling to the compiler that
                                                                              you're willing to move its resources elsewhere.
                                                                              Regular Variables (Ivalues):
                                                    Y has a
struct Y {
                                                                              Before std::move, x1 and y1 are regular variables, also known as Ivalues.
                                             synthesized move
                                                                              std::move Transforms Variables to rvalues:
    X mem;
                                                 constructor
                                                                              After std::move, although x1 and y1 were initially lvalues, std::move
                                                                              transforms them into rvalues. This transformation essentially says, "I'm okay
                                                                              with this object being moved from."
                                                                                                Once std::move is applied, it triggers the move
X x1;
                                                                                                constructors for X and Y. If not explicitly defined, the
                                                                                                compiler generates synthesized move constructors.
                                                           x1 and y1 are
Y y1;
                                                                                                Move Constructors Move Resources:
                                                        variable, i.e. Ivalue
                                                                                                The move constructors for X and Y move the
                                                                                                resources from the source object (the one being
                                                                                                moved from) to the destination object (the one being
X \times 2 = std::move(x1);
                                                                                                constructed or assigned to).
Y y2 = std::move(y1);
                                                          Calls the synthesized
                                                             move constructor
```

The move constructor for X is called with x1 as its argument. This means that the resources owned by x1 are transferred to x2, leaving x1 in a valid but unspecified state.

In summary, x2 and y2 are new objects that inherit the resources from x1 and y1, respectively, through the use of move constructors. After this operation, x1 and y1 may be left in a valid but unspecified state, ready for destruction or further assignment.

For a class type C and objects a, b, the move constructor is invoked on

```
Activation of the
                                                   move operator
                                  Direct
                               initialization
C a(std::move(b));
                              Argument passing to
f(std::move(a));
                                   a function
C f(C p) {
  return a;
                           Function return
```

```
Copy constructor
class A {
  A(const A& other);
  A(A&& other);
                                   Move constructor
};
int main() {
  A a1;
                           Calls copy constructor
  A a2(a1);
  A a3(std::move(a1));
                                      Calls move constructor
```

## **Move assignment**

- A move assignment is typically called if an object appears on the **left-hand** side of an assignment with a **rvalue reference** on the right-hand side
  - Given a class C, the destructor has
    - The name operator= of type C&
    - An argument of type C&&
    - The noexcept keyword added to indicate that the constructor never throws an exception

```
class Foo {
   public:
      Foo& operator=(Foo&&) noexcept;
}
this is the move constructor for transferring ownership of data
Foo& &Foo::operator=(Foo&& in) noexcept { . . . }
```

```
class A {
                                                                                        Copy operations (copy constructor and copy assignment operator) create a new object as a
                                                                                        copy of an existing object or assign the value of an existing object to another existing object.
                                                                                        This means that the same data exists in two places, which can be inefficient, especially for
                         constructor
       A();
                                                                                        large objects or when the object owns resources like dynamic memory or file handles.
       A (const A&); copy constructor
                                                                                        Move operations (move constructor and move assignment operator), bn the other hand,
                                                                                        transfer resources from one object (the source) to another (the target
       A(A&&) noexcept; move constructor
                                                                                        source object is in a valid but unspecified state, and the target object
                                                                                        the source object had before the operation. This can be more efficient than copying, especially
                                                                                        for large objects or when the object owns resources.
       A& operator=(const A&);
       A& operator=(A&&) noexcept;
                                                                             copy assignment with noexcept to indicate it never throws an exception
};
int main()
                                                 Calls copy constructor
       A a1; default constructor
                                                                                                 Calls move constructor
       A a2 = a1;
       Class a3 = std::move(a1);
       a3 = a2;
                                                                                     Calls copy assignment
       a2 = std::move(a3);
                                          Calls move assignment
                                                      operator
```

```
Constructor
class A {
  unsigned capacity;
  int* memory;
                                                     Move
  A(unsigned capacity): capacity(capacity),
                                                   constructor
  memory(new int[capacity]) { }
  A(A&& other) noexcept :capacity(other.capacity),
 memory(other.memory) {
    other.capacity = 0;
    other.memory = nullptr;
                                A& operator=(A&& other) noexcept
                                   if (this == &other)
                                     return *this;
  ~A() { delete[] memory; }
                                  delete[] memory;
                                   capacity = other.capacity;
  Destructor
                                  memory = other.memory;
                                   other.capacity = 0;
                                   other.memory = nullptr;
           Move assignment
                                   return *this;
               operator
```

#### The "rule of five"

- The presence of a user-defined copy constructor or copy assignment operator or destructor prevents the implicit definition of the move constructor and move assignment operator
- As a consequence, if a class follows the rule of three, it must define all five special member functions
  - Not adhering to the rule of five usually does not lead to incorrect code
  - However, many optimization opportunities may be inaccessible to the compiler if no move operations are defined

#### **Summary**

- The constructor is called when objects are created
- The copy constructor is called when objects are created (assigned) from existing objects
- The copy assignment operator is called when objects are assigned (it appearrs as Ivalue)
- The destructor is called to desrtroy the objects created by the constructors
- A move constructor is called when objects are initialized from an rvalue reference
- A move assignment operator is called when objects (Ivalue) are assigned from an rvalue reference

Which copy control functions are called in the following code snippet?

```
class C {
int main() {
   C e1, e2; default constructors 2 times
   e2 = e1; copy assignment operator
   C *e3 = new C; default constructor
   e2 = *e3; copy assignment operator
   return 0;
```

Which copy control functions are called in the following code snippet?

```
Destructor Calls
                      Why two destructor calls?
                      e1 and e2 are automatic (stack-allocated) variables.
                      When the program exits main(), the destructors for e1 and e2 are called automatically
                      e3 is a dynamic (heap-allocated) variable.
                      The destructor for e3 is not called automatically because e3 is allocated with new.
                      To properly manage the dynamic memory, you would need to delete e3 using delete e3; before returning from main().
class C {
                      Since delete e3; is not called, the destructor for the object pointed to by e3 is never called, leading to a memory leak
                      destructor is not called, which would result in a memory leak
int main() {
    C e1, e2;
                                     // Line 1: Constructor: 2 times
    e2 = e1;
                                    // Line 2: Copy Assignment Operator
    C *e3 = new C;
                                     // Line 3: Constructor (from new)
    e2 = *e3;
                                     // Line 4: Copy Assignment Operator
                                     // Line 5: Destructor: 2 times
    return 0;
```

e3 is not destroyed: Dynamically allocated objects are destroyed when delete is called

Which copy control functions are called in the following code snippet?

```
class C {
                          int main() {
            default constructor C e1, *e2;
                                                                      default constructor called once for e1, for *e2 nothing is called because it is just a pointer Instead, it simply declares a pointer to an object of type C without actually creating an instance of C.For the constructor to be called, you would need to create an instance of C and assign its address to the pointer p. For example, C *e2 = new C;
                                C e3 = *new C; Remember how C *e = new C means an instance of C is created and its address is assigned to the pointer.

*new C means instead of the address the value of the class is assigned. So default constructor is called once more.
default constructor and
copy constructor
     10 default constructors are C *e4 = new C[10];
                                e1 = e3; copy assignment operator
                                e2 = e4; nothing
                                e1 = (std::move(e3)); calls move assignment operator
                                e2 = (std::move(e4)); since e2 is pointer and so is e4 nothing is called
                                return 0;
```

Which copy control functions are called in the following code snippet?

```
class C {
                                                      Contructor for new
                                                   Copy constructor for e3
                int main()
                                                 perficiass C. The constructor for e// Line 1: Constructor e1 (e2=pointer)
                    C e1, *e2; a pointer e2 to is called here.
                    C = 3 = *new C;
                                                                  // Line 2: Constructor + Copy Con.
C e3 = *new C; - This line dynamically
allocates memory for a new object of
class C and then immediat
                    C *e4 = new C[10];
                                                                  // Line 3: Constructur: 10 times
dereferences it to initialize eB. This calls
the constructor for the new object and
                    e1 = e3;
                                                                  // Line 4: Copy Assignement Operator
                                                                  // Line 5: Nothing (e4=pointer)
                    e2 = e4;
 e1 = std::move(e3); - This line
 assigns the value of e3 to e1
                    e1 = (std::move(e3));
                                                                // Line 6: Move Assignement Operator
 using the move assignm
 operator. After this line, $3 is in a
 valid but unspecified state
                    e2 = (std::move(e4));
                                                                  // Line 7: Nothing (e4=pointer)
                                                                   // Line 8: Desctructor: 2 times
                    return 0;
                                 return 0; - At the end of the main function, all local objects are destroyed
                                 This calls the destructor for e1 and e3. The dynamically allocated
                                 memory for the objects pointed to by e2 and e4 is not automatically
                                 deallocated, which would result in a memory leak. To avoid this, you
                                 should manually delete dynamically allocated memory when you're done
```

e2 = std::move(e4); - This ine assigns the value of e4 (which is pointer to C) to e2 using move semantics. However, since e4 is pointer, this doesn't actually call any special functions like the move assignment operator. It just

the pointer value

e1 and e3 e2 and e4 are pointers