# Activity 1 - Run an idealized ocean basin

#### 1. Get the model

- Download from <a href="http://jgula.fr/ModNum/croco.tar.gz">http://jgula.fr/ModNum/croco.tar.gz</a> or from <a href="mailto://forums/public/pub/Data/croco.tar.gz">/forums/public/pub/Data/croco.tar.gz</a>
- Put it in a folder of your choice: [for example ~/ModNum/]
- untar it: tar xf croco.tar.gz
- the croco source code is in the folder ~/ModNum/croco/OCEAN

## 2. Compile the model

- Create a folder where you will run the model [for example ~/ModNum/case1]
- we need to edit the following files: jobcomp, cppdefs.h, param.h, croco.in so copy them into the folder you just created:

```
cp ~/ModNum/croco/OCEAN/jobcomp ~/ModNum/case1/
```

- cp ~/ModNum/croco/OCEAN/cppdefs.h ~/ModNum/case1/
- cp ~/ModNum/croco/OCEAN/param.h ~/ModNum/case1/
- $cp \sim /ModNum/croco/TEST\_CASES/croco.in. Basin \sim /ModNum/case1/croco.in$
- the model needs a fortran compiler and compatible netcdf libraries, so we will
  - 1. unload everything: module purge
  - 2. then load intel compilers and netcdf library

```
module load intel/12.1 netcdf/4.1.3-intel12
```

- edit the jobcomp to specify the location of the source code:

SOURCE=../croco/OCEAN

- edit the cppdefs.h and choose the predefined test case **Basin**:

```
#define BASIN
...
#undef REGIONAL
```

- Compile the code: ./jobcomp

#### 3. Run the model

- run the model: ./croco croco.in

- look at the output: neview basin his.ne

### 4. Modify the namelist (croco.in)

- Modify the namelist (croco.in) to:
- a. make the model run for 20 years (you can approximate 1 year = 360 days)
  - b. output of history files every 30 days
  - c. outputs of variables averaged over 5 years

## 5. Run the model using openMP

- we need to edit the file cppdefs.h,
- find the part of the file where the BASIN case is defined (#elif defined BASIN) and change # undef OPENMP into # define OPENMP

- edit the param.h file to choose the number of processors (NPP) you want to use:

#### 

- reCompile the code: ./jobcomp
- define the number of threads to use for your computer (the number should be the same than NPP defined in the param.h file), type in your terminal:
  - in bash: export OMP\_NUM\_THREADS=8in csh/tcsh: setenv OMP\_NUM\_THREADS 8
- run the model: ./croco croco.in
- What can you tell about the configuration? What is the forcing? What is the Coriolis parameter? What is the boundary condition? What is the bottom condition?
- What can you tell about the circulation? Is it similar to Stommel's gyre? (http://jgula.fr/ModNum/Stommel48.pdf)