HOME / GUIDES / CSS Flexbox Layout Guide Brought to you by DigitalOcean DigitalOcean has the cloud computing services you Chris Coyier on Aug 12, 2024 need to support your growth at any stage. Get Our comprehensive guide to CSS flexbox layout. This complete started with a free \$200 credit! guide explains everything about flexbox, focusing on all the different possible properties for the parent element (the flex container) and the child elements (the flex items). It also includes history, demos, patterns, and a browser support chart. **Table of contents ⊙** Get the poster! Part 1: Background Reference this guide a Part 2: Basics and terminology lot? Here's a high-res image you can print! Part 3: Flexbox properties Part 4: Prefixing Flexbox **DOWNLOAD FREE** Part 5: Examples Part 6: Flexbox tricks Part 7: Browser support Part 8: Bugs Part 9: Related properties Part 10: More information Part 11: More sources Background Basics and terminology ▼ Flexbox properties container Properties for the Parent **⋄** Properties for the Children (flex items) (flex container) ං display **⊘** order This defines a flex container; inline or block depending on the given value. It enables a flex context for all its direct children. .container { display: flex; /* or inline-flex */ Note that CSS columns have no effect on a flex container. By default, flex items are laid out in the source order. **[∞] flex-direction** However, the order property controls the order in which they appear in the flex container. .item { order: 5; /* default is 0 */ Items with the same order revert to source order. This establishes the main-axis, thus defining the direction flex items are placed in the flex container. Flexbox is (aside from optional wrapping) a single-∘ flex-grow direction layout concept. Think of flex items as primarily laying out either in horizontal rows or vertical columns. .container { flex-direction: row | row-reverse | column | column-• row (default): left to right in ltr; right to left in rtl This defines the ability for a flex item to grow if • row-reverse: right to left in ltr; left to right in rtl necessary. It accepts a unitless value that serves as a • column: same as row but top to bottom proportion. It dictates what amount of the available space • column-reverse: same as row-reverse but bottom inside the flex container the item should take up. to top If all items have flex-grow set to 1, the remaining space in the container will be distributed equally to all children. If one of the children has a value of 2, that child would ∘ flex-wrap take up twice as much of the space as either one of the others (or it will try, at least). .item { flex-grow: 4; /* default 0 */ By default, flex items will all try to fit onto one line. You Negative numbers are invalid. can change that and allow the items to wrap as needed with this property. **™** flex-shrink .container { flex-wrap: nowrap | wrap | wrap-reverse; This defines the ability for a flex item to shrink if necessary. • nowrap (default): all flex items will be on one line .item { • wrap: flex items will wrap onto multiple lines, from flex-shrink: 3; /* default 1 */ top to bottom. • wrap-reverse: flex items will wrap onto multiple lines from bottom to top. Negative numbers are invalid. There are some visual demos of flex-wrap here. flex-basis This defines the default size of an element before the ୃ flex-flow remaining space is distributed. It can be a length (e.g. This is a shorthand for the flex-direction and flex-20%, 5rem, etc.) or a keyword. The auto keyword means wrap properties, which together define the flex "look at my width or height property" (which was container's main and cross axes. The default value is row temporarily done by the main-size keyword until nowrap. deprecated). The content keyword means "size it based on the item's content" - this keyword isn't well supported .container { yet, so it's hard to test and harder to know what its flex-flow: column wrap; brethren max-content, min-content, and fit-content do. .item { flex-basis: | auto; /* default auto */ justify-content flex-start If set to 0, the extra space around content isn't factored in. If set to auto, the extra space is distributed based on flex-end its flex-grow value. See this graphic. center ⊕ flex space-between This is the shorthand for flex-grow, flex-shrink and flex-basis combined. The second and third parameters space-around (flex-shrink and flex-basis) are optional. The default is 0 1 auto, but if you set it with a single number value, like flex: 5;, that changes the flex-basis to space-evenly 0%, so it's like setting flex-grow: 5; flex-shrink: 1; flex-basis: 0%;. .item { flex: none | [<'flex-grow'> <'flex-shrink'>? || <'f</pre> This defines the alignment along the main axis. It helps distribute extra free space leftover when either all the flex items on a line are inflexible, or are flexible but have It is recommended that you use this shorthand reached their maximum size. It also exerts some control **property** rather than set the individual properties. The over the alignment of items when they overflow the line. shorthand sets the other values intelligently. .container { justify-content: flex-start | flex-end | center | sp align-self • flex-start (default): items are packed toward the flex-start start of the flex-direction. • flex-end: items are packed toward the end of the flex-direction. • start: items are packed toward the start of the flex-end writing-mode direction. • end: items are packed toward the end of the writing-This allows the default alignment (or the one specified by mode direction. align-items) to be overridden for individual flex items. • left: items are packed toward left edge of the container, unless that doesn't make sense with the Please see the align-items explanation to understand flex-direction, then it behaves like start. the available values. • right: items are packed toward right edge of the container, unless that doesn't make sense with the .item { flex-direction, then it behaves like end. align-self: auto | flex-start | flex-end | center | • center: items are centered along the line • space-between: items are evenly distributed in the Note that float, clear and vertical-align have no line; first item is on the start line, last item on the end effect on a flex item. line • space-around: items are evenly distributed in the line with equal space around them. Note that visually the spaces aren't equal, since all the items have equal space on both sides. The first item will have one unit of space against the container edge, but two units of space between the next item because that next item has its own spacing that applies. • space-evenly: items are distributed so that the spacing between any two items (and the space to the edges) is equal. Note that that browser support for these values is nuanced. For example, space-between never got support from some versions of Edge, and start/end/left/right aren't in Chrome yet. MDN has detailed charts. The safest values are flex-start, flexend, and center. There are also two additional keywords you can pair with these values: safe and unsafe. Using safe ensures that however you do this type of positioning, you can't push an element such that it renders off-screen (e.g. off the top) in such a way the content can't be scrolled too (called "data loss"). ∘ align-items flex-start flex-end center stretch baseline text text This defines the default behavior for how flex items are laid out along the **cross axis** on the current line. Think of it as the justify-content version for the cross-axis (perpendicular to the main-axis). .container { align-items: stretch | flex-start | flex-end | cente • stretch (default): stretch to fill the container (still respect min-width/max-width) • flex-start / start / self-start: items are placed at the start of the cross axis. The difference between these is subtle, and is about respecting the flexdirection rules or the writing-mode rules. • flex-end/end/self-end: items are placed at the end of the cross axis. The difference again is subtle and is about respecting flex-direction rules vs. writing-mode rules. • center: items are centered in the cross-axis • baseline: items are aligned such as their baselines align The safe and unsafe modifier keywords can be used in conjunction with all the rest of these keywords (although note browser support), and deal with helping you prevent aligning elements such that the content becomes inaccessible. □ align-content flex-start flex-end stretch center space-around space-between This aligns a flex container's lines within when there is extra space in the cross-axis, similar to how justifycontent aligns individual items within the main-axis. **Note:** This property only takes effect on multi-line flexible containers, where flex-wrap is set to either wrap or wrap-Hey! reverse). A single-line flexible container (i.e. where flex-wrap is set to its default value, no-wrap) will not reflect align-content. .container { align-content: flex-start | flex-end | center | spac • normal (default): items are packed in their default position as if no value was set. • flex-start / start: items packed to the start of the container. The (more supported) flex-start honors the flex-direction while start honors the writing-mode direction. • flex-end / end: items packed to the end of the container. The (more support) flex-end honors the flex-direction while end honors the writingmode direction. • center: items centered in the container • space-between: items evenly distributed; the first line is at the start of the container while the last one is at the end • space-around: items evenly distributed with equal space around each line • space-evenly: items are evenly distributed with equal space around them • stretch: lines stretch to take up the remaining space The safe and unsafe modifier keywords can be used in conjunction with all the rest of these keywords (although note browser support), and deal with helping you prevent aligning elements such that the content becomes inaccessible.

[∞] gap, row-gap, column-gap

The gap property explicitly controls the space between

flex items. It applies that spacing only between items not

gap: 10px 20px; /* row-gap column gap */

The behavior could be thought of as a *minimum* gutter, as

like justify-content: space-between;) then the gap

if the gutter is bigger somehow (because of something

will only take effect if that space would end up smaller.

It is not exclusively for flexbox, gap works in grid and

gap: 10px

gap: 30px

gap: 10px 30px

on the outer edges.

.container {

gap: 10px;

display: flex;

row-gap: 10px;

column-gap: 20px;

multi-column layout as well.