# Lecture 24 — Virtual Memory II

Jeff Zarnett jzarnett@uwaterloo.ca

Department of Electrical and Computer Engineering University of Waterloo

May 21, 2015

ECE 254 Spring 2015 1/39

#### **Allocation of Frames**

In a simple system with *n* frames free in the system, demand to page all of them.

Initially, all frames are empty, and as needed, pages are read into those frames.

Once all n frames are filled with pages, page n+1 must replace a page already in a frame (because there is no more space).

When a process terminates, all its frames are marked as free. In theory, one process could fill all the frames in the system.

This is as simple as it can be; from there we can build on it.

ECE 254 Spring 2015 2/3:

#### Make a Reservation

We might reserve a few pages to be free at all times for performance reasons.

When we want to move a page into a frame, if all of the frames are full, we select a victim and write that victim out to disk if necessary.

If we keep a few frames free, the newly-read page can be read into one of the free frames, and we can write the old page out to disk at a convenient time.

The read does not need to wait for the write.

Therefore the user process continues a bit sooner than it otherwise would.

ECE 254 Spring 2015 3/3

#### **How Many Frames?**

We might want to allocate different numbers of frames to different processes.

We are constrained in the number of pages we can allocate.

The maximum number of frames a process could have is the maximum number of frames in the system (obviously), but the minimum is more interesting.

ECE 254 Spring 2015 4/39

#### **Minimum Frames**

The motivation behind a minimum number of frames is ostensibly performance.

As long as our page replacement algorithm is sane (i.e., not FIFO), adding more frames reduces the page fault rate.

As we demonstrated earlier, a page fault is a huge performance decrease.

This is not the only reason.

ECE 254 Spring 2015 5/3

#### **Minimum Frames**

The absolute minimum number of frames is determined by the architecture.

Imagine a machine where a memory reference instruction may contain one memory address.

In the worst case, the instruction and the address are in different pages, so we will need two frames to be able to complete this instruction.

If the max frames for this process were 1, the instruction could never complete.

ECE 254 Spring 2015 6/3

#### Minimum Frames: IBM 370

The IBM 370 MVC instruction is an extreme example: it moves data from one storage location to another.

It takes six bytes, and the instruction itself can straddle two pages.

That requires six frames.

The worst case scenario is when the MVC instruction is the operand of an EXECUTE instruction that also straddles a page boundary.

So eight (!) frames are needed.

ECE 254 Spring 2015 7/3

#### **Minimum Fames: Infinite?**

In theory, the problem could be infinitely bad if the computer architecture allows referencing of an indirect address.

The address being referenced could be on another page.

That instruction could then reference another indirect address, and it's turtles all the way down.

The standard solution is to limit the levels of indirection to some manageable value,

If we limited the levels of indirection to 16, then the worst case scenario is a requirement of 17 pages.

ECE 254 Spring 2015 8/

# **Allocation Strategies**

Assuming we do not allocate every process the minimum or maximum, there are a few allocation algorithms we might follow.

We already got a glimpse at this when we talked about local vs. global cache replacement.

If there are m frames in the system and the operating system reserves k of them for its own use, there are m-k frames available for processes.

ECE 254 Spring 2015 9/3

#### **Equal Allocation**

If there are *n* processes, each process gets (m - k)/n frames.

If this division produces a remainder, the leftover frames can be kept as a pool of free frames for performance purposes as above.

But: why does a text editor get the same amount of frames as a web browser?

And the same amount of frames as a game (VERY demanding on memory)?

ECE 254 Spring 2015 10/3

# **Proportional Allocation**

Each process should get a share of the frames based on its needs.

Let the virtual memory size of a process  $p_i$  be defined as  $s_i$ .

Thus 
$$S = \sum s_i$$
.

Then we allocate  $a_i$  frames to a process  $p_i$  according to the formula:

$$a_i = s_i/S \times (m-k).$$

ECE 254 Spring 2015 11/3

### **Proportional Allocation**

This value of  $a_i$  is only an estimate.

It may not divide evenly.

We can only allocate an integer number of frames to each process.

So we will have to raise or lower  $a_i$  a bit to make it an integer.

If  $a_i$  is below the minimum number of frames, then it needs to get bumped up.

We also must respect the limits of the system: the sum of all  $a_i$  values may not exceed the total frames of memory (minus the OS reserve).

A few of the larger processes may need to have their allocations nudged down.

ECE 254 Spring 2015 12/

### **Proportional Allocation**

Note that with proportional allocation, as with equal allocation, there is no regard given to the priorities of the processes.

Normally, we would want to give more frames to higher priority processes so their page fault rates are lower and they can therefore execute more quickly.

So we could modify the  $a_i$  values according to process priority.

The subject of priority is something we have not yet examined much yet, but will do so soon when we get to talking about scheduling; the next major topic.

But, first, let's finish what we are doing with memory.

ECE 254 Spring 2015 13/39

### Local and Global Replacement

We already saw the idea of local and global replacement in the cache.

If we have chosen the LRU algorithm, in a global replacement policy, the least recently used page anywhere in the cache (memory) will be replaced.

If we chose a local page replacement policy, it is the least recently used page that belongs to the current process.

ECE 254 Spring 2015 14/39

#### Local and Global Replacement

Local is not affected much by our allocation concerns; leave that alone.

Suppose we choose global allocation.

We will see the number of pages allocated to each change over time.

Over time, a global replacement algorithm means processes that run more often will accumulate more pages in memory.

They will acquire more pages than get taken from them.

ECE 254 Spring 2015 15/39

### **Watching Frame Counts**

It might make sense to watch to see how many frames each process has.

It may be desirable to prevent a process from falling below the minimum number of pages.

Or we swap completely to disk a process that no longer meets that threshold.

ECE 254 Spring 2015 16/39

### Thrashing

This topic was previously introduced, and now we'll come back to it.

The quick definition of thrashing still applies.

Aside from intentionally depriving the system of RAM, how can we get into this state, and how can we get out of it?

ECE 254 Spring 2015 17/3

### Thrashing

In simple operating systems, the logic that controlled how many processes to run at a time would rely just on the CPU utilization.

If CPU utilization is low, the CPU needs more work to do!

Assign it more work by starting or bringing more processes into memory.

The global page replacement policy is used here, so when a process gets a page fault, it takes a frame from another process.

Under most circumstances, this works just fine.

ECE 254 Spring 2015 18/3:

#### **Downward Spiral**

This situation can run until one process starts to have a lot of page faults.

This is not unreasonable; a compiler might be finished with reading and parsing the input files and moving to generation of binary code.

This requires a whole bunch of new instructions pages, plus pages for output.

When this process does so, it starts taking pages from other processes.

ECE 254 Spring 2015 19 / 3:

#### **Downward Spiral**

The victim processes need the pages they had, so when they get a turn to run, they too start generating page faults.

So more and more requests are queued up for memory writes and reads, so the CPU is not very busy.

Here's the fatal mistake: seeing that the CPU is not very busy, the OS schedules **more** programs to run.

ECE 254 Spring 2015 20/39

### The Doom in Thrashing


A new process getting started will need at least the minimum number of pages.

These have to come from somewhere, so they will necessarily come from the pages currently belonging to other processes.

This causes more page faults, more time spent paging, lower CPU utilization... Prompting the OS to start more processes.

ECE 254 Spring 2015 21/39

No more work is getting done, because the system spends all its time moving pages into and out of memory, thrashing all around, acting like a maniac.



ECE 254 Spring 2015 22 / 39

#### **Breaking the Spiral**

To increase CPU utilization we need to stop the thrashing... which means we need **fewer** programs in memory at a time.

CPU usage alone is not a sufficient indicator of whether more or fewer processes need to be running right now.

It also matters why the CPU utilization is low. Another reason that might cause low CPU usage is, as you may recall, deadlock.

ECE 254 Spring 2015 23 / 3:

#### **Local Replacement Instead**

What if we stop using a global replacement policy and instead use local?

This limits some of the damage; If  $P_1$  is thrashing, it cannot steal pages from  $P_2$ . We do not get a cascade.

But  $P_2$  is still affected.

If  $P_1$  is spending all its time paging to and from disk, any other process that wants to use the disk is going to have to spend more time waiting for the disk.

ECE 254 Spring 2015 24/39

#### **Starting and Suspending Processes**

Decide whether to start or suspend programs not just based on CPU usage, but also on the number of page faults that occur in a given period of time.

If there are too many page faults, it indicates we have too much going on.

That is a reactive solution, however.

It would be better to be proactive and deal with this before thrashing has started.

ECE 254 Spring 2015 25/39

#### More Clairvoyance

As is typical, a bit of clairvoyance would help here: how many pages is the process going to need and when will it need them?

Unfortunately, there is no good way to know or to figure this out. So we will have to rely on (educated) guessing.

ECE 254 Spring 2015 26 / 39

You may hate the idea of guessing.

As a general engineering practice, "let's do an experiment and find out" is good, provided you can analyze the result and if things go wrong, no damage is done.

Those last conditions make it kind of infeasible to do medical experiments just to see what would happen, or for NASA to play around with satellites in orbit.

So in those cases, a simulation is probably the better approach.

Even so, sometimes we don't have (or can't get) the data we need and we will therefore need to "make our best guess".

ECE 254 Spring 2015 27/3

#### **Making Our Best Guess**

What do we know about process memory accesses?

They tend to obey the principle of locality, both temporal and spatial.


We could think of different parts of the program as different localities, as if they were areas on a map. And localities may overlap sometimes.

Give a process enough frames for its locality.

It can operate in this little area without encountering (too many) page faults.

ECE 254 Spring 2015 28/39

# **Check Assumptions**



ECE 254 Spring 2015 29 / 39

#### The Working-Set Model

A potential solution is the working-set model.

Retain the last *n* pages in memory as they represent the locale of the program.

Assuming that most memory accesses are local, the most recent n pages will be the most frequently used.

ECE 254 Spring 2015 30/39

#### The Working-Set Model

In the textbook descriptions, this n is usually called  $\Delta$ , the working set window.

Pages that have been recently used are in the working set.

If a page has not been accessed recently, it will drop out of the working set after  $\Delta$  time units since its last reference.

ECE 254 Spring 2015 31/39

### **Working Set Example**

Suppose the window is defined as being ten accesses.

Any page that was accessed in the last ten requests will then be considered part of the working set.

If the next ten memory accesses are all in page k, then after those further ten accesses, the working set will contain only k.

The size of the working set will change over time; can be from 1 to  $\Delta$  pages.

ECE 254 Spring 2015 32 / 39

#### **Choosing Delta**

If  $\Delta$  is too small, the working set will not encompass the entire locale.

If it is too large, it will cover multiple locales.

Underestimating the size of the locale is bad; it will mean more page faults.

Overestimating is also bad; it means fewer processes will be allowed to run.

ECE 254 Spring 2015 33/39

# Sum of the Working Sets

If the working set of every process is summed up, we will get the total number of frames each process would "like" to have.

If this sum exceeds the (m - k) available frames in the system, at least one process is going to be unhappy.

It does not have as many frames as it will need.

And like unhappy workers who go on strike, unhappy process start thrashing.

ECE 254 Spring 2015 34/39

# **Working Sets**

Once a value of  $\Delta$  is determined, the OS will monitor the working set of each process and use that to figure out if the system is currently overloaded.

If it is, the OS will pick a victim and suspend it to prevent thrashing.

If the system is underloaded (frame supply exceeds demand), more processes can be started to run.

ECE 254 Spring 2015 35 / 39

### **Working Set**

The page fault rate of a process tends to vary over time.


At the beginning, there will be a bunch of page faults as the program starts up.

Then once established in its first locale, the rate will drop.

When it come time to move to a new locale, the page fault rate rises until the program is "settled" in that new locale.

ECE 254 Spring 2015 36 / 39

# **Working Set**



ECE 254 Spring 2015 37/39

# **Working Set Analogy**

Imagine that you have moved to a new city for a co-op term.

When you have just moved, you will frequently rely on Google Maps to find what you are looking for and how to get there.

You need to buy groceries, so you ask Google for directions to the nearest grocery store of choice.

Once you've been there, you know the way so you don't have to ask again.

ECE 254 Spring 2015 38 / 39

# Working Set Analogy

Not knowing where the grocery store is equals a page fault, and asking Google is like asking the operating system to bring in that page from disk.

Once you know the way to the grocery store, it is part of your working set and you do not have to ask again.

... Until your next co-op term when you move somewhere else.

ECE 254 Spring 2015 39/39