

MuseScore Handbook

MuseScore 0.9.2 and 0.9.3

English handbook written by Werner Schweer and David Bolton. Contributions by Thomas Bonte, Toby Smithe, and others.

Copyright © 2002-2008. Licensed under the $\underline{\text{Creative Commons Attribution 3.0}}$ license

Getting started

This chapter helps you install and run MuseScore for the first time. The chapter will also show you how to create a new score.

Installation

Windows

You will find the Windows installer on the <u>Download</u> page of the MuseScore website. Click on the link to start the download. Your Internet browser will confirm that you want to download this file. Click "Save File".

When the download finishes double click on the file to start the installation. Windows may open a security window and ask you to confirm before running the software. Click "Run" to continue.



The installer recommends that you close all other applications before continuing. After you close the other applications click "Next" to continue.

The setup wizard displays the terms of the free software license which you may review. Click "I Agree" to continue.

Next it confirms the location for installing MuseScore. If you are installing a newer version of MuseScore but still want to keep the old version on your computer then you should change the folder. Otherwise click "Next" to continue.

Next it confirms the name for the MuseScore folder that appears in the Windows Start menu list of programs. Click "Install" to continue.


Give the setup wizard a few minutes to install the necessary files and configurations. When it is done click "Finish" to exit the installer. If you wish, you may now delete the installer file you downloaded.



Start MuseScore

To start MuseScore choose Start \rightarrow All Programs \rightarrow MuseScore 0.9 \rightarrow MuseScore.

After several seconds MuseScore will open up to the demo score. Feel free to experiment with the demo score and get the feel of the program. Next you may want to <u>create your own score</u>.



Create new score

From the main menu choose Score \rightarrow New. This opens the new score wizard.

Title, composer and other information




Enter the title, composer, or any other information as shown above. Notice the two options at the bottom:

- Create new score from template
- · Create new score from scratch

The first option allows you to selected from ready-made scores in the next screen. The second option gives you the full choice of instruments in the next screen. Templates are discussed in more detail <u>below</u>, but for now just leave it marked as "Create new score from scratch."

Click "Next" to continue.

Instruments and voice parts



The instrument window is divided into two columns. The first column lists instruments or voice parts to choose from. The second column is initially empty but will soon contain a list of the

instruments for your new score.


The instrument list in the first column is categorized into instrument families. Double click a category to show the full list of instruments in each family. Select an instrument and click "Add". The instrument you selected now appears in the second column. You can add more instruments or voice parts if needed.

The order of the instruments in the second column determines the order they appear in the score. To change the order click on an instrument name and use the "Up" or "Down" buttons to move it higher or lower. When you are done click "Next".

Key signature

If you are using version 0.9.3 of MuseScore the wizard asks for a key signature. Select the key signature you need and click "Next" to continue.

If you are using version 0.9.2 or earlier the wizard does not ask for a key signature so you may ignore this step.



Time signature, pickup, and number of measures

Set the time signature to the numbers you want. If your piece begins with a pickup then mark the "Pickup measure" checkbox and adjust pickup time signature to indicate the actual duration of the first measure.

If you know approximately how many measures you need you can specify that here. Otherwise you can add or delete measure later.

Click "Finish" to create your new score.

Adjustments to score after creation

Anything that you set up in the new score wizard can be changed and any time.

- To add or delete measures or create a pickup see <u>Measure operations</u>
- To change any text see <u>Text editing</u>. To add a missing Title (or other text item) use the menu
 Create → Text → Title (or other text item)

• To add, delete, or change the order of instruments use the menu Create \rightarrow Instruments....

See also: Key signature, time signature, clef.

Templates

When you create a new score using the wizard there is an option to "Create new score from template" on the first screen (see <u>Title and other text</u> above for details). Select the template option and click "Next" to continue.

Select a template and click Next to continue with the new score wizard as usual.

The template files are normal MuseScore files stored in the template folder. You can create your own templates by saving MuseScore files to the template folder. On Windows the template folder is usually located at C:\Program Files\MuseScore 0.9\templates. On Linux look under /usr/share/mscore-xxx if you installed from the package manager. If you compiled mscore on Linux then look under /usr/local/share/mscore-xxx.

Basics

The "Getting started" chapter above guides you through the <u>Installation</u> and process for <u>creating a new score</u>. The "Basics" chapter gives an overview of MuseScore and describes the general methods for interacting with the score.

Note entry

Notes are entered in Note entry mode. First select a note or rest as start position for note entry. When entering notes you are always replacing existing notes or rests. So the duration of a measure does not change.

- N: Enters Note entry mode.
- Escape: Leaves Note entry mode.

After entering Note entry mode you should select the duration of the note you want to enter by selecting a value from the note palette or by pressing:

- Alt+1: Quarter note (crochet)
- Alt+2: Eighth note (quaver)
- Alt+3: 16th note (semiquaver)
- Alt+4: 32nd note (demi-semiquaver)
- Alt+5: 64th note (semi-demi-semiquaver)
- Alt+6: Whole note (semibreve)
- Alt+7: Half note (minim)

In version 0.9.4 and later the keyboard shortcuts for selecting the note duration are reduced to a single keypress and ordered:

- 1: 64th note (semi-demi-semiquaver)
- 2: 32nd note (demi-semiquaver)
- 3: 16th note (semiquaver)
- 4: Eighth note (quaver)
- 5: Quarter note (crochet)
- 6: Half note (minim)
- 7: Whole note (semibreve)
- 8: Double whole note (breve)
- 9: Longa

Notes are entered by typing: CDEFGABC



Space creates a rest: C D Space E



Notes are added to chords by holding Shift and entering a note name: C D Shift+F Shift+A E F



Beams are created automatically: Alt+1 C D Alt+2 E F G A



To change octaves use the following key combinations:

- Ctrl+Up: Increase the pitch of a note by one octave.
- Ctrl+Down: Decrease the pitch of a note by one octave.

MIDI keyboard

You can also insert pitches using a MIDI keyboard on Linux. Support for MIDI keyboard on Windows is available in the prereleases for 0.9.4.

Copy and paste

Copy

- 1. Click on an empty part of a measure to select the entire measure (a blue rectangle highlights the selection)
- 2. If you want to extend the selection then Shift+click on the empty part of another measure
- 3. From the menu choose Edit \rightarrow Copy

Paste

- 1. Click on the empty part of the measure you want to paste into
- 2. From the menu choose Edit \rightarrow Paste

In versions 0.9.3 or earlier you can copy-paste measures, but not individual notes. The upcoming 0.9.4 release includes many improvements including support for shift-drag selections.

Edit mode

Many elements in the score can be edited in Edit Mode:

• Double Click: Starts Edit Mode

• Escape: Ends Edit Mode

Some elements show handles in edit mode which can be moved by mouse dragging or keyboard commands.

Slur in Edit Mode:



Available keyboard commands:

- Left: Moves handle left one Space
- Right: Moves handle right one Space
- Up: Moves handle up one Space
- Down: Moves handle down one Space
- Ctrl+Left: Moves handle left 0.1 Space
- Ctrl+Right: Moves handle right 0.1 Space
- Ctrl+Up: Moves handle up 0.1 Space
- Ctrl+Down: Moves handle down 0.1 Space
- Shift+Left: Moves handle's tick anchor left
- Shift+Right: Moves handle's tick anchor right
- Tab: Goes to next handle

See also: Text editing, Slur, Bracket, Lines

Measure operations

Append

To add a measure to the end of the piece press Ctr+B. To add multiple measures use the menu Create \rightarrow Measures \rightarrow Append Measures....

Insert


First select a measure then press *Ins* to insert a new empty measure before the selected one. To insert multiple measures use the menu Create \rightarrow Measures \rightarrow Insert Measures....

Delete

To delete a measure you have to first select in a special way. Press *Ctrl* on the keyboard as you click on an empty part of the measure with the mouse. The measure is marked with a dotted line indicating that you selected a "piece of time". Press *Shift+Click* to extend the selection. Pressing *Del* removes the selected measures.

Properties

To edit the properties of a measure right click on an empty part of the measure and select Measure Properties....



Duration

Normally the nominal and actual duration of a measure is identical. A pickup (upbeat) measure can have a different actual duration.

Irregular

An "irregular" measure is not counted in the measure numbering. Normally a pickup measure is marked as "irregular".

Repeat count

If the measure is the end of a <u>repeat</u> you can define how often the repeat should be played.

Palette

You can show or hide the palette using the menu Display \rightarrow Palette.

You can drag-and-drop palette symbols onto score elements.

Double clicking a palette symbol is equivalent to drag-and-dropping this symbol to each of the selected elements on the score.

For example you can easily put a tenuto on several notes at once:

- 1. Select notes
- 2. Double click on the tenuto symbol in the attributes palette

Undo and redo

MuseScore has unlimited undo/redo functions.

The standard shortcuts are:

- Undo Ctrl+Z
- Redo Ctrl+Shift+Z

Or use the toolbar buttons:



Export

A score can be exported via File \rightarrow Save As... to several different formats:

Compressed MuseScore format (* .mscz)

MSCZ is the standard *MuseScore* file format and recommended for most uses. A score saved in this format will not loose any information. The format is a ZIP-compressed version of .msc files.

MuseScore format (* .msc)

MSC is the uncompressed version of the *MuseScore* file format. A score saved in this format will not loose any information. However the file extension has file association conflicts on Microsoft Windows and is blocked by some email providers since <code>.msc</code> files can also be a type of Windows system file ("Management Saved Console"). This format is recommended if you need to manually edit the file format using a text editor.

MusicXML (*.xml)

<u>MusicXML</u> is the universal standard for sheet music and can be used by most of the currently available scorewriters including Sibelius, Finale, and more than 100 others. It is the recommended format for sharing your sheet music between different scorewriters.

Compressed MusicXML (* .mxl)

Compressed MusicXML creates smaller files than regular MusicXML. Compressed MusicXML is a newer standard and not as widely supported by other scorewriters at this time.

MIDI(*.mid)

Musical Instrument Digital Interface (MIDI) is a format widely supported by sequencers and music notation software. It is not a notation format so much of the information about the score is cannot be saved in a MIDI format. To sharing files between different music notation software use MusicXML.

PDF(*.pdf)

Portable Document Format (PDF) is ideal for sharing your sheet music with others who do not need to edit the music. Most computer users already have a PDF viewer on their computer so they will not need to install any extra software to see your score.

PostScript (*.ps)

PostScript (PS) is popular as a page description language used in printing.

PNG(*.png)

Portable Network Graphics (PNG) is a bitmap image format with native support on all major operating systems and image software and popular on the web. As of version 0.9.3 Multi-page scores export a PNG file for every page.

SVG(*.svg)

Scalable Vector Graphics (SVG) can be opened by most web browsers (expect Internet Explorer) and most vector graphics software. However most SVG software does not support embedded fonts so the appropriate MuseScore fonts must be install to view these files correctly.

LilyPond(*.ly)


LilyPond format can be opened by the <u>Lilypond</u> scrorewriter. However LilyPond export is incomplete and experimental in the current versions of *MuseScore*.

Notation

In the previous "Basics" chapter you learn how to <u>enter notes</u> and interact with the <u>palette</u>. The "Notation" chapter describes the different types of notation in more detail including more advanced music notation.

Accidental

Accidentals can be set or changed by dragging an accidental symbol from the accidental palette to a note in the score.



If you only want to change the pitch of a note you can also select the note and press:

- *Up*: Increase the pitch of a note by one semitone.
- Down: Decrease the pitch of a note by one semitone.
- Ctrl+Up: Increase the pitch of a note by one octave.
- Ctrl+Down: Decrease the pitch of a note by one octave.

MuseScore automatically tries to set an appropriate accidental for the changed pitch. If you need to manually correct an accidental or place an cautionary accidental (editorial accidental), then drag an accidental from the accidental palette to the note. If you later change the pitch with cursor keys, manual settings to the accidental are removed.

The menu function Notes \rightarrow Pitch spell tries to guess the right accidentals for the whole score.

Arpeggio


Arpeggios are set by dragging an arpeggio symbol from the arpeggio palette to a note of a chord.



Bar line


Change bar line type

Bar lines are changed by dragging a bar line symbol from the bar line palette to an bar line in the score.



Create grand staff

To extend bar lines over multiple staves double click on a bar line to edit it (see Edit mode).



Click and drag the blue square down to the next staff.

Display of all staff bar lines updates when you leave edit mode.



See also: Measure operations

Beam

Beams are set automatically but the automatic setting can be overridden manually. Drag a beam symbol from the beam palette to a note in order to change its beam behavior.



You can also first select a note and then double click the appropriate symbol in the beam palette.



Start a beam at this note.



Do not end a beam a this note.



Do not beam this note.



Start a second level beam at this note.

See also: Cross staff beaming


Bracket

Delete

Select the bracket and press Del

Add

Drag a bracket symbol from the bracket palette to an empty space in the first measure of a system.



Change

Drag a bracket symbol from the bracket palette to an bracket in the score.

Edit

Double click on a bracket to enter <u>edit mode</u>, In edit mode you can drag the height of a bracket to span arbitrary staves of a system.

Breath

To place a **breath** symbol drag it from the breath palette to a note in the score. The breath symbol is placed before the note.




Breath symbol in score:



Clef

Clefs are created or changed by dragging a clef symbol from the clef palette to a measure or another clef.

F9 toggles the palette window.



Change

Drag a clef from the palette onto a clef in the score. You can also drag a clef from the score to another clef of the score by using *Shift + leftMouseButton + Drag*.

Add

Drag a clef from the palette onto an empty part of a measure. This creates a clef at the beginning of the measure. Drag a clef to a particular note to create a mid-measure clef. If the measure is not the first measure in the staff it is drawn smaller.

Remove

Select a clef and press Del.

Note that changing a clef does not change the pitch of any note. Instead the notes are moved.

Cross staff beaming

In piano scores it is common to use both staves (bass and treble clef) to write a musical phrase. This can be entered in MuseScore as follows:

First enter all notes in one staff:




Shift+Ctrl+Down moves the selected note or chord to the next staff



See also: Bar line for cross-staff bar lines (i.e. grand staff).

Drum notation

Example drum notation:



Grace note

Short grace notes (Acciaccatura) are painted as a small notes with a stroke through the stem. **Long grace notes** (Appoggiatura) have no stroke. Both are placed before the normal-sized main note.

Create a grace note by dragging a grace note symbol from the notes palette to a main note.

See also:

- Palette
- Grace note at Wikipedia

Hairpin

Hairpins are <u>line</u> objects. To create a hairpin first select a note to mark the start point.

- H: Creates a crescendo hairpin
- Shift+H: Creates a diminuendo hairpin (decrescendo)

Hairpins could also be created by dragging a hairpin symbol from the line palette to a note head.

1. *H* creates a crescendo hairpin:



2. Double click switches to edit mode:




3. Shift+Right moves end anchor:



Key signature

Key signatures are created or changed by dragging a key symbol from the key palette to a measure or existing key signature.



F9 toggles the palette window.

Change

Drag a key from the palette onto a key in the score. You can also drag a key from the score to another key on the score by using *Shift+leftMouseButton+Drag*.

Add


Drag a key from the palette onto an empty part of a measure. This creates a key at the beginning of the measure.

Remove

Select a key and press Del.

Lines

The **lines palette** like other <u>palettes</u> works via "drag-and-drop". Use the mouse to drag the item from the palette and drop it onto the score.



Change length

- 1. If you are in note entry mode then press N to leave note entry
- 2. Double click the line that you want to change
- 3. Move the handles using the following shortcuts
 - Shift+Right to move the anchor right by one note (or measure)
 - Shift+Left to move the anchor left by one note (or measure)
- 4. If you need to change the length visually without changing the notes or measures that the line is anchored to then use the following shortcuts
 - Right to move the handle right by one unit
 - Left to move the anchor left by one unit

See also: Hairpin, Volta (1st and 2nd endings)

One-bar rest

When an entire measure is devoid of notes, a full measure (semibreve) rest is used.

A one-bar rest can be created by marking a measure and pressing Del.

All notes and rests on this measure are then replaced by a one-bar rest.

Repeat

The start and end of simple repeats can be defined by setting appropriate <u>bar lines</u>. For instructions on first and second ending measures see <u>volta</u>.

Playback

To hear repeats during playback make sure the "Play Repeats"

|: |

button on the toolbar is selected. Likewise you can turn off repeats during playback by deselecting the button.

In the last measure of a repeat you can set the <u>property</u> "Repeat Count" to define the number of played repeats.

TextRepeat text such as "D.C. al Fine" or "D.S. al Coda" is located in the repeats <u>palette</u>.

Repeats ▼	
*	%
•	Ó
ΦΦ	Fine
D.C.	D.C. al Fine
D.C. al Coda	D.S. al Coda
D.S. al Fine	D.S.
To Coda	

Slur


A **slur** is a curved line between two or more notes that indicates the notes are to be played without separation. If you mean to join two notes of the same pitch then see <u>Tie</u>

Instructions

1. Select first note:



2. S creates a slur in Edit mode:



3. *Shift+Right* moves the slur end to the next note:



4. X flips the slur direction:



5. Escape ends Edit mode:



The boxes or handles (displayed in the images for steps 2-4 above) can be adjusted with the mouse. The two outer handles adjust the start and end of the slur. The two inner handles adjust the contour of the slur.

A slur can span several systems and pages. Slur start and end is anchored to a note/chord or rest. This means that if the notes move in a relayout, the slur moves too.

See also: Tie, Edit mode.

Tie

A **tie** is a curved line between two notes of the same pitch. If you want a curved line that spans multiple pitches see <u>Slur</u>.

First method

Select first note:



Shift+S creates a tie:



Second method


Use the following method to create slurs during <u>note entry</u>:

Versions 0.9.3 or earlier: Press + *before* entering the first note to create a tie to the next note.

Versions 0.9.4 or later: Press + *after* entering the first note to create a tie to the next note.


Time signature

Time signatures are available in the main palette sidebar. You can drag and drop the times signatures onto the score (see <u>palette</u> for general information on working with palettes in MuseScore).



If you need a time signature not found in the sidebar palette then go to $Create \rightarrow Time...$ to create your own. You can edit the upper and lower numbers in the Create Time Signature pane.

In most cases you'll only need to edit the first of the upper numbers. The additional upper numbers are for <u>additive meters</u> which contain multiple upper numbers separated by a plus sign.



Pickup measures

There are occasions when the actual duration of a measure is different from the duration specified by the time signature. Pickup measures are a common example. To change the actual duration of a measure without displaying a different time signature see the Properties section of measure operations.

Tremolo

Tremolo is the rapid repetition of one note or a rapid alternation between two or more notes. It is indicated by strokes through the stems of the notes. If the tremolo is between two or more notes, the bars are drawn between them.

The tremolo palette contains separate symbols for one note tremolos (shown with stems below) and for two note tremolos (shown with no stem below).



In a two note tremolo every note has the value of the whole tremolo duration. To enter a tremolo with the duration of a half note (minum) first enter two normal quarter notes (quavers). After dragging a tremolo symbol to the first note the note values automatically double to half notes.

Tuplet

To create a **triplet** first create a note with a duration of the whole triplet. Then select the note and press *Ctrl+3* to change it to a triplet. Similarly *Ctrl+5* changes the note to a quintuplet.

First select a note:



Ctrl+3 creates a triplet:



which can be further edited



Voices

Note: The MuseScore implementation of voices in 0.9.3 is not yet complete and subject to change.

Enter multiple voices per staff:

- 1. First start by entering the top voice (all the up-stem notes).
- 2. When you enter the notes some may have down-stems. You can flip the stem direction by clicking the "Flip direction" button



2. on the toolbar or pressing X on the keyboard.



- 3. Now select the first note to move your cursor back to the begining of the line.
- 4. Click on "Voice 2" button



and start entering the bottom voice (all the down-stem notes).

5. Remember to flip the stems as to go along using *X* on the keyboard or the flip direction button



6. When you are done it should look like this:



When to use voices

- · If you need stems pointing in opposite directions within a chord on a single staff
- If you need notes of different durations within a single staff, played simultaneously

Hidden spacer rests

To hide a rest right-click on the rest and select Set Invisible. If you have Display \rightarrow Show Invisible marked then the rest still shows in gray on your screen. The rest does not appear when you print.

Volta

Volta brackets or **first and second ending** brackets are used to mark different endings for a repeat.



To place a volta bracket on the score drag-and-drop the item from the lines palette.

The brackets can span more than one measure. Double click the volta to enter edit mode and then move the handles with:

- one measure left Shift+Right
- one measure right Shift+Left

These commands move the "logical" start or end of the volta which determine the bracketed measures.

Other commands in edit mode also move the handles but do not change how the repeat is played.

If you move the handles, a dashed line from the logical position to the actual position is shown



Properties


Repeat list

This list determines which repeat the volta should be played.

If the volta is played in more than one repeat all repeat numbers must be listed and separated by a comma (",").

Text

You can set an arbitrary volta text. Of course the text should correspond with the repeat list.



Sound and playback

MuseScore has "Sound and playback" capabilities built in. This chapter covers the playback controls and ways to extend the instrument sounds beyond the built-in piano sound.

Play mode

MuseScore has an integrated sequencer and synthesizer to play your score. By pressing the Play



button you enter Play mode. In Play mode the following commands are available:

- · Toggle pause/play Space
- Seek to previous chord Left
- Seek to next chord Right
- Seek to previous measure Ctrl+Left
- Seek to next measure Ctrl+Right
- · Rewind to start of score Home
- Toggle show play panel F11

Or via the menu: Display \rightarrow Play Panel



Press the play button again to stop and exit Play mode.

If you want to play instruments other than piano you have to change the MuseScore integrated $\underline{SoundFont}$ with a more capable one in $\underline{Edit} \rightarrow \underline{Preferences...} \rightarrow \underline{I/O}$ tab.

SoundFont

MuseScore comes with a piano sound for play back. For more sounds, such as a violin or percussion, you need a General MIDI SoundFont.

Overview

A SoundFont file can store any number of instrument sounds. Many SoundFonts are available on the web. Look for one that covers the 128 sounds of <u>General MIDI</u> (GM).

The file size and sound quality of SoundFonts available on the web is varied. Larger SoundFonts often sound better but may be too large to run on your computer. If you find MuseScore runs slowly after installing a large SoundFont or your computer can't keep up during play back then look for a smaller SoundFont. Below are three popular GM SoundFonts of different sizes.

- FluidR3_GM.sf2 (141 MB uncompressed), download <u>Fluid-soundfont.tar.gz (129 MB)</u>
- MagicSF_ver2.sf2 (67.8 MB uncompressed), see Big SoundFonts
- Unison.sf2 (27.9 MB uncompressed), see <u>Big SoundFonts</u>

Compression

Since SoundFont files are large they often are compressed into a variety of formats including .zip, .sfArk, and .tar.gz. You need to decompress these files before they can be used.

- ZIP is standard compression format supported by most operating systems.
- sfArk is a compression format designed especially for compressing SoundFont files. Use the special <u>sfArk software</u> to decompress it.
- .tar.gz is a popular compression format for Linux. Windows users can use <u>7-zip</u> which supports a wide variety of compression formats. Note that you need apply decompression twice: once for GZip and once for TAR.

MuseScore settings

After finding and decompressing a SoundFont do not double click to open it since this does not set up MuseScore. Instead move the file to a folder of your choosing, start MuseScore, and follow the instructions below.

```
Go to Edit \rightarrow Preferences... \rightarrow I/O tab.
```

The initial Sound Font setting is :/data/piano1.sf2. Replace this with the location of your new SoundFont (.sf2) file. Click on the Open icon to browse for the file and open it.

To apply changes click OK to exit the preferences panel. Quit and and reopen MuseScore for the changes to take affect

Troubleshooting

If the toolbar play panel is greyed out or not visible follow the instructions below to get your sound working again:

- Make sure there is a check mark next to the Display → Transport menu item. You can add or remove the check mark by clicking on the corresponding menu item. If this step does not solve your problem continue with the next step below
- 2. If the play panel disappears after changing the SoundFont go to Edit → Preferences... → I/O tab and click OK without making any changes, After restarting MuseScore the play panel should reappear. This is a known bug with versions 0.9.3 or earlier.

Tempo

Play back tempo can be changed via the play panel or via tempo text in the score.

Play panel

- Display the play panel: Display \rightarrow Play Panel
- Change the Beats per Minute (bpm) using the Tempo (Tmp) slider

Tempo text

- Select a note to indicate where the tempo text should be created
- From the main menu: Create \rightarrow Text... \rightarrow Tempo...
- · Press OK to finish

Note that in versions 0.9.3 or earlier it is not possible to change the tempo text or BPM from the initial Tempo Text dialog. However you can change both of these after you add a tempo text to the score.

Existing tempo text can be changed by double clicking the text to enter edit mode. Beats per minute (BPM) on existing tempo text can be adjusted by right clicking on the text and selecting Tempo Properties...

Note: Tempo text in the score overrides a tempo setting in the play panel.

Text

The "Text" chapter covers lyrics, chord names, and other staff text. The previous chapter covers text that affects playback tempo

Text editing

Double click on text to enter edit mode:



In text edit mode the following commands are available:

- Ctrl+B toggles bold face
- Ctrl+1 toggles italic
- Ctrl+U toggles underline
- Up start superscript or end subscript if in subscript mode
- Down start subscript or end superscript if in superscript mode
- move cursor: Home End Left Right
- · Backspace remove character to the left of the cursor
- Delete remove character to the right of the cursor
- Return start new line
- F2 Show text palette. The text palette can be used to enter special characters and symbols.

Text palette:



See also: Chord name, Lyrics

Text style

Text elements are created from a *Text Style*. This style defines the initial properties of text.

Text properties:

• Font family: Name of the font such as "Times New Roman" or "Arial"

• Point size: the size of the font in points

• Italic, bold, underline: font properties

• Anchor: page, time, notehead, system, staff

• Alignment: horizontal: left, right, center; vertical: top, bottom, center

• Offset: an offset to the normal anchor position

• Offset type: mm, space, or percent of page size

Text types:

• Title, subtitle, composer, poet: anchored to page

• **Fingering**: Fingerings are anchored to note heads.

• Lyrics: Lyrics are anchored to a time position.

• **Chord name**: Chord names are also anchored to a time position.

Chord name

Chord names can be entered by first selecting a note and then pressing *Ctrl+K*. This creates a chord name text object for the selected chord.

- 1. Type Space to move to the next chord.
- 2. Shift+Space moves to the previous chord.
- 3. Ctrl+Space enters a space into the chord name text.

Chord names can be edited as normal text.

Fingering

Fingering can be added to notes by dragging a fingering character from the fingering palette to a note head in the score. Fingerings are normal text which can be <u>edited</u> like any other text.




Lyrics

1. First enter notes

- 2. Select first note
- 3. Type Ctrl+L and enter lyrics text for first note
- 4. Type Space at end of word to go next note
- 5. Type an hyphen at end of syllable to go to next note. The syllables are connected with a dash
- 6. Shift+Space moves to the previous note
- 7. Ctrl+Space enters a space into the lyrics text
- 8. Ctrl+- enters a hyphen (-) into the lyrics text



Syllables can be extended by an underline:



Entered with: soul, _ _ _ To Esc.


Lyrics can be edited as normal text.

See also: <u>Text</u>, <u>Chord name</u>.

Formatting

Break

Page breaks or **line breaks** (system breaks) can be applied by dragging a page break symbol or line break symbol from the breaks palette to an empty space of a measure in the score. The break happens after the marked measure. The green break symbols are visible on the screen but do not appear on printouts.



Frame

Frames provide empty space outside of normal measures. They can also contain text or pictures. MuseScore has two kinds of frames:

Horizontal

Horizontal frames break a system. The width is adjustable and the height equals the system height. Horizontal frames can be used to separate a coda.

Vertical

Vertical frames provide empty space between or before systems. The height is adjustable and the width equals the system width. Vertical frames are used to place title, subtitle or composer. If you create a title, a vertical frame is placed before the first measure automatically if it is not there already.

Create a frame

First select a measure. The command to insert a frame is found in the menu Create \rightarrow Measures . The frame is inserted before the selected measure.


Delete a frame

Select the frame and press Del.

Edit frame

Double click the frame to enter <u>edit mode</u>. A handle appears which can be used to drag the size of the frame.

Title frame in edit mode:



Support

How to report bug or ask for support

Before posting your support request:

- PLEASE, try to find a solution in support forum. Use <u>search</u> function.
- Try to find solution in the <u>user handbook</u>.
- If you are getting an error message, check list of common error messages.
- If you are posting error report, first try to reproduce the problem with <u>the latest release</u>. You may also see the version history to check whether it has been fixed already.

When posting your request for support or reporting bug, please include as much of the following information as you know:

- Version of MuseScore you are using and what operating system you are running it on.
- Try to describe precise steps that lead to the problem (where do you click, what keys do you press, what do you see, etc.). If you are not able to reproduce the problem with the steps, it is probably not worth reporting it as the developers will not be able to reproduce it (and solve) either.

Licensed under the <u>Creative Commons Attribution 3.0</u> license, 2002-2008 <u>Werner Schweer</u> and others.

Source URL: http://www.musescore.org/en/handbook/index