



CS 4001/7001 Cloud Computing Spring 2015

Lab # 2: Instrumentation and Measurement of a GENI Slice

Dr. Prasad Calyam (Contact: calyamp@missouri.edu)

1. Purpose of the lab

Install and configure a distributed measurement Web App viz., "OnTimeMeasure" within a slice. Configuration involves 'Node Beacons' at measurement points, and a 'Root Beacon' that acts as a central intelligence module. Schedule measurements from the Root Beacon and query/ visualize performance between two compute nodes that host Node Beacons. Performance data collection comprises of network health metrics such as round trip delay, loss, jitter and throughput.

2. References to guide lab work

- [1] Chapter 3 Distributed and Cloud Computing, Hwang, Fox & Dongarra
- [2] OnTimeMeasure Tutorial: http://groups.geni.net/geni/wiki/OnTimeMeasure
- [3] OnTimeControl: http://groups.geni.net/geni/wiki/OTM-Control
- [4] OnTimeMeasure Custom Metric Integration: http://groups.geni.net/geni/wiki/OTM-customMetric
- [5] OnTimeMeasure demo video on Graphite: http://ontime.rnet.missouri.edu/demo/dashboard.htm
- [6] Miscellaneous OnTimeMeasure demo videos: http://ontime.rnet.missouri.edu/demo

3. Lab Steps and output collection guidelines



Figure 1: Lab Steps Overview

Figure 1 shows the required steps to successfully complete the lab with OnTimeMeasure in GENI. You will need to install the OnTimeMeasure Node and Root Beacon software, and configure them with 'network path measurement tasks' between two compute nodes in your GENI slice. You will control and query active measurements as part of your experiment and monitor the network path status using common network health metrics such as round trip delay, loss, jitter and throughput. You will also experiment with adding a custom metric i.e., CPU usage and schedule 'host-based measurement tasks' with OnTimeMeasure and understand programmability and extensibility concepts in cloud monitoring.

The OnTimeMeasure-GENI architecture is shown in Figure 2, for details refer to [2].









Figure 2: OnTimeMeasure-GENI Architecture

Pre-work for OnTimeMeasure

Register and create an account on the OnTimeMeasure portal at: http://ontime.rnet.missouri.edu (OnTimeBeacon instance installed at University of Missouri-Columbia)



- 1. The 'Register' button will take you to the User Registration page. Provide your user information and give the project name as 'Calyam_UMissouri_Fall2013' and click 'Register'.
- 2. Once the Instructor approves your registration, you can login to the portal to perform OnTimeMeasure related experiments in GENI.

Note: You will start using the OnTimeMeasure portal functions from Step 3.2.2 of this manual.

3.1 Install OnTimeMeasure Software Packages

3.1.1 Create Slice

Create a slice Lab2<Pawprint> similar to Step 2 of Lab1.





3.1.2 Specify Topology

Download RSpec file from Blackboard (Assignments → GENI Lab-2 RSpec) and make sure it is saved as 'Lab2.rspec'. Upload this RSpec file in Flack using 'Import from file' to specify the slice topology and use the same aggregate manager (a.k.a. Flack nickname) assigned to you previously.

Note: The previous allocation of aggregate managers has changed. Following are the new allocations. Reserve your resources according to the new allocations.

Group Name	Aggregate manager	AM Nickname
A,B,C	instageni.nysernet.org	nysernet-ig
D,E,F,G	instageni.stanford.edu	stanford-ig
H,I,J	instageni.idre.ucla.edu	ucla-ig

This RSpec will reserve 3 compute nodes in your slice with 2 Node Beacons and 1 Root Beacon.

Modify the NODE1 information by clicking on the "i" button" on each of these nodes.

First, select '+ Add Install Service', and Flack will prompt you for an 'Archive URL' and a location for installation. For this experiment, enter the below URL:

```
http://babbage.cs.missouri.edu/~ar442/cc/OTCNodeInstall.tar.gz
```

and ask for this to be installed in:

```
/tmp
```

Similarly, use the '+ Add Execute Service' button to request that the appropriate command:

```
sudo sh /tmp/ontime_software_install.sh
```

be executed using

```
sh
```

Once both the "install" and "execute" services are specified, choose 'Apply'. Then repeat the procedure to add the same "install" and "execute" services on the 'NODE2' node;







Similarly, modify the 'ROOT' node information by providing the below URL for '+ Add Install Service'

```
http://babbage.cs.missouri.edu/~ar442/cc/OTCRootInstall.tar.gz
```

and ask for this to be installed in:

```
/tmp
```


Similarly, use the '+ Add Execute Service' button to request that the appropriate command:

```
sudo sh /tmp/ontime_software_install.sh otm_slice_password
```

be executed using


```
sh
```

Once both the "install" and "execute" services are specified, choose 'Apply'.



3.1.3 Create and Access your Sliver


Select the 'Submit' button in the left hand corner to create your sliver. *Wait for the canvas to turn green which confirms the reservation of resources*. Use "Get Status" to refresh asynchronously to see if the reservation is complete.








Once the nodes are reserved successfully, in the GENI portal the canvas turns green and each of the nodes have an address associated with them. Click on "i" symbol beside each of the nodes



Copy the address of each of the nodes as highlighted and save them where they are accessible.



Please note that the login information can be different for every student (and not necessarily the same as shown in the screenshot)

3.1.4 OnTimeMeasure Installation Confirmation

Confirm the installation of Root Beacon:

Note: Installation of the Root Beacon and Node Beacon can take more than 5 minutes.

For example, from the login information, if your ROOT login is xyz99@pcvm2-7.instageni.gpolab.bbn.com, open a browser and type, http://pcvm2-7.instageni.gpolab.bbn.com:17291). You should see your supervisor running as below -







Similarly, confirm the installation of Node Beacons in the web-browser URL of each Node Beacon as shown below:

As an example, http://pcvm2-5.instageni.gpolab.bbn.com:17291 and http://pcvm2-6.instageni.gpolab.bbn.com:17291)

The login information can be different for every student. Please change the URL accordingly and point the port to 17291.



3.2 Configure OnTimeMeasure

3.2.1 Identify the IP addresses of all 3 nodes

Open a terminal, Ping all the three nodes to see if they are accessible, and note down the IP addresses in the Ping tool output.

If your login for the Root and Node Beacons are pcvm2-7.instageni.gpolab.bbn.com, pcvm2-5.instageni.gpolab.bbn.com and pcvm2-6.instageni.gpolab.bbn.com, type for e.g.:

\$: ping pcvm2-7.instageni.gpolab.bbn.com

3.2.2 Resource Setup


Login to the portal at: http://ontime.rnet.missouri.edu




Once you login, click on the 'Setup resources' in your home page








This will take you to another page, 'Measurement Request Creation' page, please read the steps involved for measurement request creation, and then select the 'Setup Resources' button.




The 'Measurement Request Setup' page comes up. Retain the desired topology as 'Centralized'. Enter the Root and Node Beacon information and IP addresses noted down in the previous step. Also enter the database username and password as collector and otm_slice_password.







Once the information is entered, select the 'Specify Request' button. You should observe the status changing to 'Measurement Request Specification' as shown below:







3.3: Control (start/stop) measurement


You should be transferred to the 'Measurement Request Specification' page. In case you do not see the metric options in the drop down menu of Metric field, logout of the portal and login again and click the 'Manage Measurements' button in the home page.


Researcher Web-portal Home

OnTimeMeasure-GENI is a measurement service for the GENI facility users. The measurement service can be used to perform centralized and distributed orchestration and provisioning of measurements within experiment slices for purposes such as:

- · Network paths monitoring
- · Network weather forecasting
- · Network performance anomaly detection
- · Network-bottleneck fault-location diagnosis








Add the following tasks for network path measurement metrics: Round-trip Delay, Jitter, Loss and Throughput from Node2 to Node1 by selecting the metrics from the drop down menu of Metric field and click 'AddTask' button. Also retain the pattern as periodic. Do the same again with source as Node1 and Destination as Node 2.

Also, do 'Add Task' for the Memory Free metric on both Node1 and Node2 as shown below.



The tasks added to the measurement service are as follows:

Source	Destination	Metric	Pattern	Action
node2(155.98.38.97)	node1(155.98.38.99)	Loss	Periodic	Remove
node2(155.98.38.97)	node1(155.98.38.99)	Jitter	Periodic	Remove
node2(155.98.38.97)	node1(155.98.38.99)	Round-trip Delay	Periodic	Remove
node2(155.98.38.97)	node1(155.98.38.99)	Throughput	Periodic	Remove
node1(155.98.38.99)	node2(155.98.38.97)	Throughput	Periodic	Remove
node1(155.98.38.99)	node2(155.98.38.97)	Round-trip Delay	Periodic	Remove
node1(155.98.38.99)	node2(155.98.38.97)	Jitter	Periodic	Remove
node1(155.98.38.99)	node2(155.98.38.97)	Loss	Periodic	Remove

ı	Host	Metric	Pattern	Action
ı	node1(155.98.38.99)	Mem ory Free	Periodic	Remove
	node2(155.98.38.97)	Mem ory Free	Periodic	Remove








Once the above steps are complete, select the Step3 'Review Request' button.

This will take you to the Step 3 'Measurement Request Submission' page. Review the tasks information and select the 'Submit Request' button:



Measurement Request Submission

Please review and submit your measurement request to the OnTimeMeasure-GENI measure service:



The tasks added to the measurement service are as follows:

Source	Destination	Metric	Pattern
node2(155.98.38.97)	node1(155.98.38.99)	Loss	Periodic
node2(155.98.38.97)	node1(155.98.38.99)	Jitter	Periodic
node2(155.98.38.97)	node1(155.98.38.99)	Round-trip Delay	Periodic
node2(155.98.38.97)	node1(155.98.38.99)	Throughput	Periodic
node1(155.98.38.99)	node2(155.98.38.97)	Throughput	Periodic
node1(155.98.38.99)	node2(155.98.38.97)	Round-trip Delay	Periodic
node1(155.98.38.99)	node2(155.98.38.97)	Jitter	Periodic
node1(155.98.38.99)	node2(155.98.38.97)	Loss	Periodic

Host	Metric	Pattern
node1(155.98.38.99)	Mem ory Free	Periodic
node2(155.98.38.97)	Mem ory Free	Periodic

Request Submission

Status: Complete


Submit the request to initialize the measurement service.



Once, you select the 'Submit Request', the 'Service Control' page comes up, initiate the measurement collection by selecting the 'Start' button. The status changes to 'Running'.







3.4: Query Measurements


Select the 'Query Data' button to visualize the results. This will take you to the 'Measurement Query' page. Allow some time for the results to be generated (at least 30 minutes). Scroll down to the end of page and select the 'View Dashboard' button. You can also download the measurement data by selecting the 'Submit Query' button and clicking 'View Result' as shown below:






Measurement Query

Please select from the following query options:



Measurement graph:




The 'View Dashboard' button will take you to a new page called the Graphite Browser. You can visualize all the measurement metrics data by navigating the left hand folder structure. At any moment, in order to visualize a new metric, de-select the current metric and highlight the desired metric to view the results at any given time. You can also change the measurement data period by clicking third icon in the top left corner of the graph.

For more details, see the OnTimeMeasure demo video on Graphite: http://ontime.rnet.missouri.edu/demo/dashboard.htm







Note: Measurement graphs in Graphite can vary for every student.

3.5 Add Custom Metric

3.5.1 Configure IP address and database password

Login to your ROOT node using the ssh login information in the 'Details' page of GENI portal as shown previously.

```
$: ssh xyz99@pcvm2-35.instageni.gpolab.bbn.com
```

Enter OnTimeControl folder by entering the following command -

```
$: cd /opt/OnTimeMeasure/OnTimeControl
```

Copy the given config_example.yaml under the directory to config.yaml

```
$: sudo cp config_example.yaml config.yaml
```

Open the config.yaml file and edit the IP addresses of 'root_beacon', 'node1' and 'node2', change the 'root_hostname' to localhost and also change the 'db_pwd' to otm_slice_password and change http://ontime.oar.net/xmlrpc.php to http://ontime.rnet.missouri.edu/xmlrpc.php. Your config.yaml should look similar to below.

Note: Please make sure you do not give extra spaces or unnecessary quotes anywhere in the file.

```
$: sudo vi config.yaml
```





```
connection: direct
# Setup for direct connection
root beacon: 192.1.242.205
root hostname: localhost
db user: collector
db pwd: otm slice password
nodes:
- name: node1
IP: 192.1.242.206
- name: node2
IP: 192.1.242.207
# Setup for portal connection
portal: http://ontime.rnet.missouri.edu/xmlrpc.php
web_user: demo
web_pwd: password
```





3.5.2 Install custom metric CPU on to the OnTimeMeasure Framework

Run the following commands to download a custom CPU metric which gives CPU utilization of the nodes.

```
$: sudo wget http://ontime.rnet.missouri.edu/INSTALL/metric/CPU.tgz
$: sudo tar -xzf CPU.tgz
```

You will get custom metric specification file CPUSpecs.yaml and parser file CPUParser.pm

Add custom metric specifications file and parser file into your OnTimeMeasure framework instance.

```
$: python add_metric.py -c CPUSpecs.yaml -p CPUParser.pm
```

Edit the measurement configuration file (measurement.yaml) to add the new metric on both nodes

```
$: sudo vi measurement.yaml
```

Configure the two nodes CPU metric at the end of the file as shown below:

```
- source: node1

metric: [MemFree, Mycpu]

- source: node2

metric: [MemFree, Mycpu]
```

3.5.3 Restart the measurement service

Run command "task_manage.py" to manage the measurement tasks with custom metric (i.e., requests), which are configured in the measurement.yaml file and restart the measurements

```
$: python task_manage.py -c measurement.yaml
$: python service_control.py restart
```

Allow sometime for results to be generated (at least 30 minutes).

You can go back to your graphite page to visualize the new metric or download the results from the OnTimeBeacon portal page as shown previously. You can also download the results from command line. For example to download the data for the Throughput metric for a certain start and end time, run:

```
python query.py -f "2013-08-24 18:00:00" -t "2012-08-27 20:00:00" -s node2 -d node1 -m Throughput -r TimeSeries
```

You can change the -m, -f, -t and -r parameter accordingly.





4. What to turn in for Grading?

- 1. Provide screenshots of your OnTimeMeasure instance' Graphite page for 'RoundTripDelay' of node2 -> node1, node1-> node2, 'MemFree' and MyCPU of node1 and node2.
- Explain the role and functions of "Instrumentation and Measurement Tools" such as
 OnTimeMeasure
 (http://groups.geni.net/geni/attachment/wiki/OnTimeMeasure/OnTimeMeasure_Tutorial.pdf?format=raw), and GEMINI Tool Set

(http://groups.geni.net/geni/attachment/wiki/GEMINI/gemini-gec13.pptx?format=raw) in GENI infrastructure.

- 3. Briefly explain in your own words the architecture of the 'OnTimeControl' framework (see Reference [3]).
- 4. Describe the workflow that was involved when you added the custom metric feature to your OnTimeMeasure framework instance in the last step of your GENI experiment.

NOTE:

Release your resources after finishing your lab report by following below steps

The command to use is:

```
omni.py -a AM_NICKNAME deletesliver SLICENAME
```

where AM_NICKNAME is the aggregate manager nickname and SLICENAME is the name of your slice. A minute or so later, Omni should respond with:

```
INFO:omni: Completed deletesliver:
```

Or you can delete the resources by using flack by clicking delete button located bottom left of the canvas.

