# **Application Authenticity**

fork and edit tutorial (https://github.ibm.com/MFPSamples/DevCenter/tree/master/tutorials/en/foundation/8.0/authentication-and-security/application-authenticity/index.md) | report issue (https://github.ibm.com/MFPSamples/DevCenter/issues/new)

#### **Overview**

By issuing an HTTP request, an entity can access to corporate HTTP services (APIs) IBM MobileFirst Platform Foundation Server provides access to. The predefined application-authenticity security check (../authentication-concepts/) ensures that an application that tries to connect to a MobileFirst Server instance is the authentic one and was not tampered with or modified by a third-party attacker.

To enable Application Authenticity you can either follow the on-screen instructions in the **MobileFirst Operations Console** → **[your-application]** → **Authenticity**, or review the information below.

#### Availability

 Application Authenticity is available in all supported platforms (iOS, Android, Windows 8.1 Universal, Windows 10 UWP) in both Cordova and Native applications.

#### Limitations

- Application Authenticity is not available in the MobileFirst Development Server. To test, use a remote
  application server such as a QA, UAT or Production server.
- Application Authenticity does not support **Bitcode** in iOS. If using Application Authenticity, disable Bitcode in the Xcode project properties.


### Jump to:

- Authenticity flow (authenticity-flow)
- Enabling authenticity (enabling-application-authenticity)
- Disabling authenticity (disabling-application-authenticity)
- Configuring authenticity (configuring-application-authenticity)

### **Application Authenticity Flow**

By default, the application-authenticity security check is run during the application's runtime registration with MobileFirst Server, which occurs the first time an instance of the application attempts to connect to the server.

Once an application has passed the authenticity challenge, an authenticity scope is granted. For as long as the token is valid, the authenticity challenge will not occur again. See Configuring authenticity (configuring-authenticity) to learn how this can be customized.



The challenge token in the diagram is processed by compiled native code, so that third-party attackers cannot see the logic of this processing.

### **Enabling Application Authenticity**

To enable Application Authenticity in your Cordova or Native application, the application's binary file needs to be signed using the application-authenticity tool. Eligible binary files are: ipa for iOS, apk for Android and appx for Windows 8.1 Universal & Windows 10 UWP.

1. Open a **Command-line** window and run the command: java -jar path-to-application-authenticity-tool.jar path-to-binary-file


For example:

java -jar /Users/your-username/Desktop/application-authenticity-tool.jar /Users/your-username/Desktop/MyBankApp.ipa

The result of the command above is an authenticity\_data file generated next to the MyBankApp.ipa file, called MyBankApp.authenticity\_data.


- 2. Open the MobileFirst Operations Console in your browser of choice.
- 3. Select your application from the navigation sidebar and click on the Authenticiy menu item.
- 4. Click on "Upload Authenticity File" to upload the .authenticity data file.

When the .authenticity data file is uploaded, Application Authenticity is enabled.



### **Disabling Application Authenticity**

To disable Application Authenticity, click the "Delete Authenticity File" button.



## **Configuring Application Authenticity**

The predefined application-authenticity security check can be configured with the following property:

• expirationInSec: Defaults to 3600 seconds / 1 hour. Defines the duration until the Authenticity token expires.

Once an authenticity check has been performed, it will not be performed again until the token has expired based on the set value.

To configure the expirationInSec property:

- Load the MobileFirst Operations Console and navigate to [your application] → Security → Security
   Check Configurations and click on Create New.
- 2. Search for the "appAuthenticity" scope element.

3. Set a new value in seconds.

