

# C interfaces to GALAHAD UGO

Jari Fowkes and Nick Gould STFC Rutherford Appleton Laboratory Wed Mar 16 2022

1 GALAHAD C package ugo	1
1.1 Introduction	1
1.1.1 Purpose	1
1.1.2 Authors	1
1.1.3 Originally released	1
1.1.4 Method	1
1.1.5 References	2
1.2 Call order	2
2 File Index	3
2.1 File List	3
3 File Documentation	5
3.1 ugo.h File Reference	5
3.1.1 Data Structure Documentation	5
3.1.1.1 struct ugo_control_type	5
3.1.1.2 struct ugo_time_type	7
3.1.1.3 struct ugo_inform_type	7
3.1.2 Function Documentation	7
3.1.2.1 ugo_initialize()	7
3.1.2.2 ugo_read_specfile()	8
3.1.2.3 ugo_import()	8
3.1.2.4 ugo_reset_control()	9
3.1.2.5 ugo_solve_direct()	10
3.1.2.6 ugo_solve_reverse()	11
3.1.2.7 ugo_information()	13
3.1.2.8 ugo_terminate()	13
4 Example Documentation	15
4.1 ugos.c	15
4.2 ugot.c	16
Index	19

# GALAHAD C package ugo

#### 1.1 Introduction

#### 1.1.1 Purpose

The ugo package aims to find the global minimizer of a univariate twice-continuously differentiable function f(x) of a single variable over the finite interval  $x^l \le x \le x^u$ . Function and derivative values may be provided either via a subroutine call, or by a return to the calling program. Second derivatives may be used to advantage if they are available.

#### 1.1.2 Authors

N. I. M. Gould, STFC-Rutherford Appleton Laboratory, England.

C interface, additionally J. Fowkes, STFC-Rutherford Appleton Laboratory.

#### 1.1.3 Originally released

July 2016, C interface August 2021.

#### 1.1.4 Method

The algorithm starts by splitting the interval  $[x^l,x^u]$  into a specified number of subintervals  $[x_i,x_{i+1}]$  of equal length, and evaluating f and its derivatives at each  $x_i$ . A surrogate (approximating) lower bound function is constructed on each subinterval using the function and derivative values at each end, and an estimate of the first- and second-derivative Lipschitz constant. This surrogate is minimized, the true objective evaluated at the best predicted point, and the corresponding interval split again at this point. Any interval whose surrogate lower bound value exceeds an evaluated actual value is discarded. The method continues until only one interval of a maximum permitted width remains.

#### 1.1.5 References

Many ingredients in the algorithm are based on the paper

D. Lera and Ya. D. Sergeyev (2013), `'Acceleration of univariate global optimization algorithms working with Lipschitz functions and Lipschitz first derivatives'' SIAM J. Optimization Vol. 23, No. 1, pp. 508–529,

but adapted to use second derivatives.

#### 1.2 Call order

To solve a given problem, functions from the ugo package must be called in the following order:

- · ugo\_initialize provide default control parameters and set up initial data structures
- · ugo\_read\_specfile (optional) override control values by reading replacement values from a file
- ugo import set up problem data structures and fixed values
- ugo\_reset\_control (optional) possibly change control parameters if a sequence of problems are being solved
- · solve the problem by calling one of
  - ugo\_solve\_direct solve using function calls to evaluate function and derivative values, or
  - ugo solve reverse solve returning to the calling program to obtain function and derivative values
- ugo information (optional) recover information about the solution and solution process
- ugo terminate deallocate data structures

See Section 4.1 for examples of use.

# File Index

_				
2	1	Fil	ΔI	iet

Here is a list of all files with brief descriptions:	
ugo.h	5

4 File Index

# **File Documentation**

# 3.1 ugo.h File Reference

```
#include <stdbool.h>
#include "galahad_precision.h"
```

#### **Data Structures**

- struct ugo\_control\_type
- struct ugo\_time\_type
- struct ugo\_inform\_type

#### **Functions**

- void ugo\_initialize (void \*\*data, struct ugo\_control\_type \*control, int \*status)
- void ugo\_read\_specfile (struct ugo\_control\_type \*control, const char specfile[])
- void ugo\_import (struct ugo\_control\_type \*control, void \*\*data, int \*status, const real\_wp\_ \*x\_l, const real wp\_ \*x\_u)
- void ugo reset control (struct ugo control type \*control, void \*\*data, int \*status)
- void ugo\_solve\_direct (void \*\*data, void \*userdata, int \*status, real\_wp\_ \*x, real\_wp\_ \*f, real\_wp\_ \*g, real\_wp\_ \*h, int(\*eval\_fgh)(real\_wp\_, real\_wp\_ \*, real\_wp\_ \*, real\_wp\_ \*, const void \*))
- void ugo\_solve\_reverse (void \*\*data, int \*status, int \*eval\_status, real\_wp\_ \*x, real\_wp\_ \*f, real\_wp\_ \*g, real\_wp\_ \*h)
- void ugo information (void \*\*data, struct ugo inform type \*inform, int \*status)
- void ugo\_terminate (void \*\*data, struct ugo\_control\_type \*control, struct ugo\_inform\_type \*inform)

#### 3.1.1 Data Structure Documentation

#### 3.1.1.1 struct ugo\_control\_type

#### **Examples**

ugos.c, and ugot.c.

# Data Fields

int	error	error and warning diagnostics occur on stream error
int	out	general output occurs on stream out
int	print_level	the level of output required. Possible values are:
		• $\leq$ 0 no output,
		1 a one-line summary for every improvement
		2 a summary of each iteration
		• $\geq 3$ increasingly verbose (debugging) output
int	start_print	any printing will start on this iteration
int	stop_print	any printing will stop on this iteration
int	print_gap	the number of iterations between printing
int	maxit	the maximum number of iterations allowed
int	initial_points	the number of initial (uniformly-spaced) evaluation points (<2 reset to 2)
int	storage_increment	incremenets of storage allocated (less that 1000 will be reset to 1000)
int	buffer	unit for any out-of-core writing when expanding arrays
int	lipschitz_estimate_used	what sort of Lipschitz constant estimate will be used:
		• 1 = global contant provided
		• 2 = global contant estimated
		• 3 = local costants estimated
int	next_interval_selection	how is the next interval for examination chosen:
		• 1 = traditional
		• 2 = local_improvement
int	refine_with_newton	try refine_with_newton Newton steps from the vacinity of the global
		minimizer to try to improve the estimate
int	alive_unit	removal of the file alive_file from unit alive_unit terminates execution
char	alive_file[31]	see alive_unit
real_wp_	stop_length	overall convergence tolerances. The iteration will terminate when the step is less than .stop_length
real_wp_	small_g_for_newton	if the absolute value of the gradient is smaller than
		small_g_for_newton, the next evaluation point may be at a Newton
		estimate of a local minimizer
real_wp_	small_g	if the absolute value of the gradient at the end of the interval search is smaller than small_g, no Newton serach is necessary
real_wp_	obj_sufficient	stop if the objective function is smaller than a specified value
real_wp_	global_lipschitz_constant	the global Lipschitz constant for the gradient (-ve means unknown)
real_wp_	reliability_parameter	the reliability parameter that is used to boost insufficiently large estimates of the Lipschitz constant (-ve means that default values will be chosen depending on whether second derivatives are provided or not)
real_wp_	lipschitz_lower_bound	a lower bound on the Lipscitz constant for the gradient (not zero unless the function is constant)

#### **Data Fields**

real_wp_	cpu_time_limit	the maximum CPU time allowed (-ve means infinite)
real_wp_	clock_time_limit	the maximum elapsed clock time allowed (-ve means infinite)
bool	second_derivative_available	if .second_derivative_available is true, the user must provide them when requested. The package is generally more effective if second derivatives are available.
bool	space_critical	if .space_critical is true, every effort will be made to use as little space as possible. This may result in longer computation time
bool	deallocate_error_fatal	if .deallocate_error_fatal is true, any array/pointer deallocation error will terminate execution. Otherwise, computation will continue
char	prefix[31]	all output lines will be prefixed by .prefix(2:LEN(TRIM(.prefix))-1) where .prefix contains the required string enclosed in quotes, e.g. "string" or 'string'

# 3.1.1.2 struct ugo\_time\_type

#### **Data Fields**

real_sp_	total	the total CPU time spent in the package
real_wp_	clock_total	the total clock time spent in the package

# 3.1.1.3 struct ugo\_inform\_type

# Examples

ugos.c, and ugot.c.

# Data Fields

int	status	return status. See UGO_solve for details
int	eval_status	evaluation status for reverse communication interface
int	alloc_status	the status of the last attempted allocation/deallocation
char	bad_alloc[81]	the name of the array for which an allocation/deallocation error ocurred
int	iter	the total number of iterations performed
int	f_eval	the total number of evaluations of the objection function
int	g_eval	the total number of evaluations of the gradient of the objection function
int	h_eval	the total number of evaluations of the Hessian of the objection function
struct ugo_time_type	time	timings (see above)

# 3.1.2 Function Documentation

# 3.1.2.1 ugo\_initialize()

```
void ugo_initialize (
     void ** data,
```

```
struct ugo_control_type * control,
int * status )
```

Set default control values and initialize private data

#### **Parameters**

in,out	data	holds private internal data
out	control	is a struct containing control information (see ugo_control_type)
out	status	is a scalar variable of type int, that gives the exit status from the package. Possible values are (currently):
		0. The import was succesful.

#### Examples

ugos.c, and ugot.c.

#### 3.1.2.2 ugo\_read\_specfile()

Read the content of a specification file, and assign values associated with given keywords to the corresponding control parameters

#### **Parameters**

in,out	control	is a struct containing control information (see ugo_control_type)
in	specfile	is a character string containing the name of the specification file

### **Examples**

ugot.c.

#### 3.1.2.3 ugo\_import()

```
void ugo_import (
          struct ugo_control_type * control,
          void ** data,
          int * status,
          const real_wp_ * x_l,
          const real_wp_ * x_u )
```

Import problem data into internal storage prior to solution.

#### **Parameters**

in	control	is a struct whose members provide control paramters for the remaining prcedures (see
		ugo_control_type)
in,out	data	holds private internal data
in,out	status	<ul> <li>is a scalar variable of type int, that gives the exit status from the package. Possible values are:</li> <li>1. The import was successful, and the package is ready for the solve phase</li> <li>-1. An allocation error occurred. A message indicating the offending array is written on unit control.error, and the returned allocation status and a string containing the name of the offending array are held in inform.alloc_status and</li> </ul>
		<ul> <li>inform.bad_alloc respectively.</li> <li>-2. A deallocation error occurred. A message indicating the offending array is written on unit control.error and the returned allocation status and a string containing the name of the offending array are held in inform.alloc_status and inform.bad_alloc respectively.</li> </ul>
in	x_I	is a scalar variable of type double, that holds the value $x^l$ of the lower bound on the optimization variable $x$ .
in	x_u	is a scalar variable of type double, that holds the value $x^u$ of the upper bound on the optimization variable $x$ .

# Examples

ugos.c, and ugot.c.

# 3.1.2.4 ugo\_reset\_control()

Reset control parameters after import if required.

# Parameters

in	control	is a struct whose members provide control paramters for the remaining proedures (so ugo_control_type)	
in,out	data	holds private internal data	
in,out	status	is a scalar variable of type int, that gives the exit status from the package. Possible values are:	
		1. The import was succesful, and the package is ready for the solve phase	

#### 3.1.2.5 ugo\_solve\_direct()

Find an approximation to the global minimizer of a given univariate function with a Lipschitz gradient in an interval.

This version is for the case where all function/derivative information is available by function calls.

#### **Parameters**

in,out	data	holds private internal data
in	userdata	is a structure that allows data to be passed into the function and derivative evaluation programs (see below).
in,out	status	is a scalar variable of type int, that gives the entry and exit status from the package. On initial entry, status must be set to 1.  Possible exit are:  • 0. The run was succesful  • -1. An allocation error occurred. A message indicating the offending array is written on unit control.error, and the returned allocation status and a string containing the name of the offending array are held in inform.alloc_status and inform.bad_alloc respectively.  • -2. A deallocation error occurred. A message indicating the offending array is written on unit control.error and the returned allocation status and a string containing the name of the offending array are held in inform.alloc_status and inform.bad_alloc respectively.  • -7. The objective function appears to be unbounded from below  • -18. Too many iterations have been performed. This may happen if control.maxit is too small, but may also be symptomatic of a badly scaled problem.  • -19. The CPU time limit has been reached. This may happen if control.cpu_time_limit is too small, but may also be symptomatic of a badly
out	X	-40. The user has forced termination of solver by removing the file named control.alive_file from unit unit control.alive_unit.  is a scalar variable of type double, that holds the value of the approximate global
Out	, A	minimizer $x$ after a successful (status = 0) call.
out	f	is a scalar variable of type double, that holds the the value of the objective function $f(x)$ at the approximate global minimizer $x$ after a successful (status = 0) call.
out	g	is a scalar variable of type double, that holds the the value of the gradient of the objective function $f'(x)$ at the approximate global minimizer $x$ after a successful (status = 0) call.
out	h	is a scalar variable of type double, that holds the the value of the second derivative of the objective function $f''(x)$ at the approximate global minimizer $x$ after a successful (status = 0) call.

#### **Parameters**

eval_fgh	<pre>is a user-provided function that must have the following signature: int eval_fgh( double x,</pre>
	The value of the objective function $f(x)$ and its first derivative $f'(x)$ evaluated at $x=x$ must be assigned to f and g respectively, and the function return value set to 0. In addition, if control.second_derivatives_available has been set to true, when calling ugo_import, the user must also assign the value of the second derivative $f''(x)$ in h; it need not be assigned otherwise. If the evaluation is impossible at x, return should be set to a nonzero value.

#### **Examples**

ugos.c.

#### 3.1.2.6 ugo\_solve\_reverse()

Find an approximation to the global minimizer of a given univariate function with a Lipschitz gradient in an interval.

This version is for the case where function/derivative information is only available by returning to the calling procedure.

#### **Parameters**

in,out	data	holds private internal data
--------	------	-----------------------------

# **Parameters**

in,out	status	is a scalar variable of type int, that gives the entry and exit status from the package.
		On initial entry, status must be set to 1. Possible exit are:
		0. The run was succesful
		<ul> <li>-1. An allocation error occurred. A message indicating the offending array is written on unit control.error, and the returned allocation status and a string containing the name of the offending array are held in inform.alloc_status and inform.bad_alloc respectively.</li> </ul>
		<ul> <li>-2. A deallocation error occurred. A message indicating the offending array is written on unit control.error and the returned allocation status and a string containing the name of the offending array are held in inform.alloc_status and inform.bad_alloc respectively.</li> </ul>
		-7. The objective function appears to be unbounded from below
		<ul> <li>-18. Too many iterations have been performed. This may happen if control.maxit is too small, but may also be symptomatic of a badly scaled problem.</li> </ul>
		<ul> <li>-19. The CPU time limit has been reached. This may happen if control.cpu_time_limit is too small, but may also be symptomatic of a badly scaled problem.</li> </ul>
		<ul> <li>-40. The user has forced termination of solver by removing the file named control.alive_file from unit unit control.alive_unit.</li> </ul>
		• 3. The user should compute the objective function value $f(x)$ and its first derivative $f'(x)$ , and then re-enter the function. The required values should be set in f and g respectively, and eval_status (below) should be set to 0. If the user is unable to evaluate $f(x)$ or $f'(x)$ - for instance, if the function or its first derivative are undefined at x - the user need not set f or g, but should then set eval_status to a non-zero value. This value can only occur when control.second_derivatives_available = false.
		• 4. The user should compute the objective function value $f(x)$ and its first two derivatives $f'(x)$ and $f''(x)$ at $x=x$ , and then re-enter the function. The required values should be set in f, g and h respectively, and eval_status (below) should be set to 0. If the user is unable to evaluate $f(x)$ , $f'(x)$ or $f''(x)$ - for instance, if the function or its derivatives are undefined at x - the user need not set f, g or h, but should then set eval_status to a non-zero value. This value can only occur when control.second_derivatives_available = true.
in,out	eval_status	is a scalar variable of type int, that is used to indicate if objective function and its derivatives can be provided (see above).
out	X	is a scalar variable of type double, that holds the next value of $x$ at which the user is required to evaluate the objective (and its derivatives) when status $>$ 0, or the value of the approximate global minimizer when status $=$ 0
in,out	f	is a scalar variable of type double, that must be set by the user to hold the value of $f(x)$ if required by status $>$ 0 (see above), and will return the value of the approximate global minimum when status = 0
in,out	g	is a scalar variable of type double, that must be set by the user to hold the value of $f'(x)$ if required by status $>$ 0 (see above), and will return the value of the first derivative of $f$ at the approximate global minimizer when status = 0

#### **Parameters**

in,out	h	is a scalar variable of type double, that must be set by the user to hold the value of
		f''(x) if required by status $>$ 0 (see above), and will return the value of the second
		derivative of $f$ at the approximate global minimizer when status = 0

# Examples

ugot.c.

# 3.1.2.7 ugo\_information()

#### Provides output information

#### **Parameters**

in,out	data	holds private internal data	
out	inform	is a struct containing output information (see ugo_inform_type)	
out	status	is a scalar variable of type int, that gives the exit status from the package. Possible values are (currently):	
		0. The values were recorded succesfully	

### **Examples**

ugos.c, and ugot.c.

### 3.1.2.8 ugo\_terminate()

### Deallocate all internal private storage

#### **Parameters**

	in,out	data	holds private internal data
	out	control	is a struct containing control information (see ugo_control_type)
	out	inform	is a struct containing output information (see ugo_inform_type)

# Examples

ugos.c, and ugot.c.

# **Example Documentation**

# 4.1 ugos.c

This is an example of how to use the package to find an approximation to the global minimum of a given univariate function over an interval.

```
/\star Spec test for the UGO C interface \star/
#include <stdio.h>
#include <math.h>
#include "ugo.h'
struct userdata_type {
};
// Evaluate test problem objective, first and second derivatives
int fgh(double x, double *f, double *g, double *h, const void *userdata) {
   struct userdata_type *myuserdata = (struct userdata_type *) userdata;
}
    *f = x * x * cos(a*x);
    *g = - a * x * x * sin( a*x ) + 2.0 * x * cos( a*x );

*h = - a * a* x * x * cos( a*x ) - 4.0 * a * x * sin( a*x )
         + 2.0 * cos( a*x );
    return 0;
int main(void) {
     // Derived types
     void *data;
     struct ugo_control_type control;
struct ugo_inform_type inform;
     // Initialize UGO
     ugo_initialize( &data, &control, &inform );
      // Set user-defined control options
     control.print_level = 1;
     control.maxit = 100;
     control.lipschitz_estimate_used = 3;
     // User data
     struct userdata_type userdata;
     userdata.a = 10.0;
     // Test problem bounds
     double x_1 = -1.0;
double x_u = 2.0;
     // Test problem objective, gradient, Hessian values
     double x, f, g, h;
     // import problem data
ugo_import( &control, &data, &status, &x_l, &x_u );
     \ensuremath{//} Set for initial entry
     status = 1;
     // Call UGO_solve
     ugo_solve_direct( &data, &userdata, &status, &x, &f, &g, &h, fgh );
     // Record solution information
     ugo_information( &data, &inform, &status );
if(inform.status == 0){ // successful return
    printf("UGO successful solve\n");
           printf("iter: %d \n", inform.iter);
```

```
printf("x: %f \n", x);
  printf("f: %f \n", f);
  printf("g: %f \n", g);
  printf("h: %f \n", h);
  printf("f_eval: %d \n", inform.f_eval);
  printf("time: %f \n", inform.time.clock_total);
  printf("status: %d \n", inform.status);
}else{ // error returns
  printf("UGO error in solve\n");
  printf("status: %d \n", inform.status);
}
// Delete internal workspace
  ugo_terminate( &data, &control, &inform );
  return 0;
}
```

# 4.2 ugot.c

This is the same example, but now function and derivative information is found by reverse communication with the calling program.

```
/* ugo test.c */
/* Simple code to test the UGO reverse communication C interface */
#include <math.h>
#include "ugo.h"
// Test problem objective
double objf(double x) {
   double a = 10.0;
    return x * x * cos( a*x );
,
// Test problem first derivative
double gradf(double x) {
    double a = 10.0;
    return - a * x * x * sin( a*x ) + 2.0 * x * cos( a*x );
// Test problem second derivative
double hessf(double x) {
    double a = 10.0;
    return - a * a* x * x * cos( a*x ) - 4.0 * a * x * sin( a*x )
            + 2.0 * cos( a*x );
int main(void) {
    // Derived types
    void *data;
    struct ugo_control_type control;
    struct ugo_inform_type inform;
    // Initialize UGO
    int status, eval_status;
    ugo_initialize( &data, &control, &status );
    // Set user-defined control options
    //control.print_level = 1;
//control.maxit = 100;
    //control.lipschitz_estimate_used = 3;
    // Read options from specfile
    char specfile[] = "UGO.SPC";
    ugo_read_specfile(&control, specfile);
    // \ {\tt Test \ problem \ bounds}
    double x_1 = -1.0;
double x_u = 2.0;
    // Test problem objective, gradient, Hessian values
    double x, f, g, h;
    // import problem data
    ugo_import( &control, &data, &status, &x_l, &x_u );
    // Set for initial entry
status = 1;
    // Solve the problem: min f(x), x_1 <= x <= x_u
    while(true) {
         // Call UGO_solve
        ugo\_solve\_reverse(\&data, \&status, \&eval\_status, \&x, \&f, \&g, \&h);
        // Evaluate f(x) and its derivatives as required if(status >= 2){ // need objective
             f = objf(x);
             if(status >= 3){ // need first derivative
                 g = gradf(x);
                 if(status >= 4) { // need second derivative
                     h = hessf(x);
         } else { // the solution has been found (or an error has occured)
```

4.2 ugot.c 17

```
break;
}
}
// Record solution information
ugo_information( &data, &inform, &status );
// Print solution details
printf("iter: %d \n", inform.iter);
printf("x: %f \n", x);
printf("f: %f \n", f);
printf("g: %f \n", g);
printf("h: %f \n", h);
printf("f_eval: %d \n", inform.f_eval);
printf("time: %f \n", inform.status);
// Delete internal workspace
ugo_terminate( &data, &control, &inform );
return 0;
```

# Index

```
ugo.h, 5
    ugo_import, 8
    ugo_information, 13
    ugo_initialize, 7
    ugo_read_specfile, 8
    ugo_reset_control, 9
    ugo_solve_direct, 9
    ugo_solve_reverse, 11
    ugo_terminate, 13
ugo_control_type, 5
ugo_import
    ugo.h, 8
ugo_inform_type, 7
ugo_information
    ugo.h, 13
ugo_initialize
     ugo.h, 7
ugo_read_specfile
     ugo.h, 8
ugo_reset_control
    ugo.h, 9
ugo_solve_direct
    ugo.h, 9
ugo_solve_reverse
    ugo.h, 11
ugo_terminate
    ugo.h, 13
ugo_time_type, 7
```