How to Boot VHD + WIM from USB Portable SSD as FILEDISK and with Grub4dos from RAMDISK using SVBus driver

November 16, 2020

Download: VHD WIMBOOT and WinNTSetup and USB FORMAT and wimb GitHub - Info: VHD WIMBOOT and Win10XPE and UEFI MULTI

- 0. USB FORMAT Tool Option: Make Bootable USB Drive with MBR and 2 Partitions active FAT32 Boot Drive + NTFS System Drive
- 1. WinNTSetup do Fresh Install Compact 4K mode of Win10x64 in 25 GB VHD located on Internal System Drive C: use page 2 of this Manual
- 2. Boot with Win10XPE Or other Win10x64 and Switch off Defender Start VHD WIMBOOT select System Drive and the 25 GB VHD file
- 3. VHD WIMBOOT Capture with WimBoot mode and Copy the Captured WIM File to Wimboot folder on NTFS System Drive of Portable SSD
- 4. VHD_WIMBOOT Preset FILEDISK Apply WIM with Compact LZX mode in Fixed VHD 25 GB located on NTFS System Drive of USB SSD
- 5. VHD_WIMBOOT Preset RAMDISK Apply WIM with WimBoot mode in Expandable VHD 3.9 GB located on NTFS System Drive of USB SSD
- 6. Internet Off (disconnect LAN cable) Boot in MBR BIOS mode via F8 menu from USB Boot Manager Menu with 3.9 GB VHD as FILEDISK
- 7. Install of SVBus driver use R-mouse menu to Run as admin file instx64.exe of SVBus bin folder Driver for booting from RAMDISK
- 8. Reboot in MBR BIOS mode from USB and select in Grub4dos Menu your 3.9 GB VHD on USB for booting from RAMDISK
- 9. Reboot in UEFI Or MBR BIOS mode from USB and select in Boot Manager Menu 25 GB VHD on USB for booting as FILEDISK
- 10. Always use <u>Firewall App Blocker</u> and **Enable WhiteList** with Allow Internet Browser and Netsh Commands Allow Local Subnet (Printer)

 This is the easiest way to block unwanted internet traffic including Windows Update and prevents the growth of Used Size inside VHD
- 11. Option Boot with 10XPE Or other Win10x64 use Win Reduce Trusted in 30 seconds to Reduce Offline Windows e.g. use Mounted VHD
- 12. VHD_WIMBOOT Capture WimBoot LZX mode and Apply Compact LZX mode in 3.9 GB VHD to boot Mini10x64 as FILEDISK or as RAMDISK The Button **WIM Info** will give useful info about your WIM file wimboot compatible WIM File contains only Index 1

The Button **Upd WimBOOT** can be used after copy of VHD + WIM set to other NTFS drive to make the WimBoot set bootable again

The Button **Make Boot** and **Apply** will make the boot entries on Target Boot Drive - FAT32 partition of USB Portable SSD as described below

- VHD boot entry in Boot Manager Menu for booting VHD as FILEDISK in BIOS mode and in UEFI mode
- VHD boot entry in **Grub4dos** Menu for booting VHD from **RAMDISK** in BIOS mode only Make Boot needs installed <u>SVBus</u> driver
- Booting from USB with Portable SSD needs after BIOS beep to press F8 Or F11 to arrive at BIOS Boot Menu and then select your boot device After Install of SVBus driver then UEFI booting requires in Boot Manager Menu to press F8 where you can allow unsigned drivers When file **grldr.mbr** is Not found at Boot Drive, then **Make Boot** and **APPLY** will make Grub4dos entry in Boot Manager Menu on Boot Drive **WimBoot LZX** Compression can be used in CAPTURE to make WIM files of smaller size **Switch Defender Off** for Faster Capture An **Expandable** VHD will load much faster into RAMDISK, since only the space occupied by files of 600 MB needs to be loaded It Expands then to the maximum **VHD Size** of 3.9 GB and gives the RAMDISK of that size a lot of FREE Space

△ VHD WIMBOOT x64 - APPLY WIM to VHD file - wimlib X System Files - Version 3.0 - OS = WIN_10 X64 UEFI WIM File 4.3 GB WIM Info D:\Wimboot\W10x64 NL 1.wim APPLY WimBoot Upd WimBoot Mode CAPTURE WimBoot 4K ~ Mode VHD Info VHD Size VHD File D:\Min10x64.vhd 25.0 GB ~ Preset FILEDISK V VHD ~ FIXED ~ Target FAT32 8.7 GB Boot Drive Z: FREE = 8.7 GB NTFS 214 GB D:\Wimboot System Drive FREE = 111.1 GB Make Boot FXIT Select APPLY of WIM File to VHD Or Upd WimBoot

In VHD_WIMBOOT the First Selection is the **System Drive**. System Drive is NTFS partition for VHD + WIM Operating System files. VHD Capture WimBoot will make WIM file in Wimboot folder on System Drive. WIM Apply WimBoot Mode will use WIM file to Install Windows on VHD file. **Boot Drive** is FAT32 partition for Boot Manager and Grub4dos Boot files. On Internal Harddisk the System Drive is Drive C: and the Boot drive is Hidden. Run VHD_WIMBOOT_x64 so that Hidden Boot partition is mounted as drive Z: On USB Portable SSD the Boot and System Drive are made as described below. Win10XPE environment is advised for faster Capture of WIM file from VHD. **UEFI** MULTI is used to Add Win10XPE as Boot Option to your Internal SSD Or USB. wimlib is used for Capture and Apply of wimboot compatible WIM files. VHD Capture involves replacing Windows\System32\WimBootCompress.ini in Captured WIM file by the WimBootCompress.ini file supplied in makebt folder. [PrepopulateList] is used to Apply as real files in VHD instead of as WOF pointers. Entries \Boot\BCD and \bootmgr in the [PrepopulateList] section are needed to allow Grub4dos booting VHD from RAMDISK and so to avoid Error 13.

Extra Options: **APPLY** WIM File in Normal or <u>WimBoot Mode</u> or <u>Compact Mode</u> with XPRESS4K 8K 16K or LZX Compression Extra Options: **CAPTURE** WIM File in Normal Or WimBoot Mode with XPRESS4K or LZX Compression - See wimlib

USB Format Tool - Make Bootable USB Drive with MBR and 2 Partitions - active FAT32 Boot Drive + NTFS System Drive

- Use USB_FORMAT with SAMSUNG Portable SSD T5 500 GB Or USB-Stick gives UEFI/MBR Partitioning with active FAT32 + NTFS Partition
- 1st partition 20 GB FAT32 Set Active used for Boot Manager and Grub4dos Boot files and 2nd partition NTFS used for VHD + WIM System files BIOS mode booting requires Active partition with BOOTMGR bootsector


UEFI mode booting requires FAT32 partition with x64 file efi\boot\bootx64.efi Or x86 file efi\boot\bootia32.efi

Step 1 is use WinNTSetup to do Fresh Install of Win10x64 in VHD located on Internal System Drive C:

Download Win10_20xx_English_x64.iso Or Win10 x64 Setup ISO in your language from <u>TechBench</u> Or using <u>Windows-ISO-Downloader</u> Tool **Download** <u>WinNTSetup</u> and run WinNTSetup_x64.exe for the first time to collect some Tools - <u>BOOTICE</u> v1.3.3.2 is included already

Create W10x64_F.vhd using WinNTSetup x64 for Install of Win10 x64 in 25 GB Fixed VHD

- 1. Disconnect Internet LAN Ethernet cable Start up with Windows 10 x64 Or 10XPE and Start WinNTSetup x64
- 2. In WinNTSetup x64 location Windows Installation file sources\install.wim use R-mouse to select Win10x64 ISO file from TechBench
- 3. Select Boot drive (usually EFI drive Z:) and Select VHD to Create 25 GB VHD located on internal SSD harddisk VHD is mounted as Drive Y:
- 4. Choose Win10 Edition Select desired Tweaks Disable Hibernate use Compact:XPRESS4K Mode to reduce the Used Size of Windows
- 5. Select Unattended Install for Local Account Select unattend\Win7-10-Select.xml and fill in the form Option: select to Add Drivers folder
- 6. Select Setup and select Legacy Boot Menu Style and OK to Install Win10x64 in VHD choose OK and not Reboot
- 7. BOOTICEx64.exe from Upper Right Icon BCD of current system file Z:\efi\microsoft\boot Professional mode BootMenuPolicy = Legacy
- 8. Option needed for RAMDISK SVBus driver In BootIce Use R-mouse to create New element AllowPrereleaseSignatures Yes
- 9. Reboot and install Win10x64 in VHD with Offline Local Account Connect to LAN or WLAN for Install of missing Drivers and Activation
- 10. use Firewall App Blocker and Enable WhiteList with Allow Internet Browser to block Windows Update and prevent the growth of Used Size
- 11. Install <u>7-zip</u> <u>VLC player</u> and Office and <u>registry_backup_portable</u> and Reboot
- 12. Open Admin Command Window and use wmic UserAccount where Name='Vx64W' set PasswordExpires=False More Info
- 13. If not done with Tweaks set Hibernate Off in admin command window type: powercfg -h off
- 14. After Install 7-zip using file 7z1900-x64.exe In 7-zip File Manager menu Tools > Options select file associations, such as zip 7z rar wim
- 15. Firewall App Blocker File > Netsh Commands Allow Local Subnet Connect Printer and after auto Installation Set as Default Printer
- 16. Disable LAN Network Adapter and Disable Connect Automatically WiFi for protection and Reboot computer
- 17. Start > Windows System > Configuration > System > Advanced system > Settings > Startup Select as **Standardsystem** your normal Windows 10 and **Reboot** computer



Downloads: WinNTSetup and Windows 10 x64 ISO from TechBench and Firewall App Blocker and Option: WinSxS Reduce Trusted

Downloads: from wimb GitHub - USB FORMAT - UEFI MULTI - System Info - VHD WIMBOOT - WOF Compress - MBR Backup

More Info: VHD WIMBOOT and UEFI MULTI Win10XPE - WIMBOOT Topic - RAMBOOT Topic - Compact install - WinSxS Reduce Trusted

More Info: WinCmd and bcdedit and bcdboot and bootsect and DiskPart en DISM and Win10 Install.pdf and VHDX and Native Boot

VHD_WIMBOOT - Apply and Capture of WIM Files for OS in VHD - Background Info and Details

APPLY of WIM File in wimboot mode to VHD gives Operating System with only variable and boot essential files total about 1 GB in VHD. The VHD contains also pointers to the non variable files in the WIM archive, so that it seems that the complete OS is present in the VHD. The VHD content can be generated in 2 minutes from the WIM archive of about 9 GB, so that a backup of the system is always available. The VHD + WIM set can be copied to any drive so that we have a portable Operating System (needs to use supplied WimBootCompress.ini). The WIM file cannot be changed by viruses or other malware so that the system is reliable and if needed it is easy to generate new VHD. The VHD can boot as 25 GB FILEDISK from Portable SSD to allow changes, but also booting always Fresh from 3.9 GB RAMDISK is possible. Grub4dos booting from RAMDISK requires VHD file, since VHDX files are Not compatible with Grub4dos.

WIMBOOT and Compact needs wof.sys driver of Win 10 Or for 7/8 the wofadk.sys driver as installed by WinNTSetup mode Compact:NONE
Boot Manager files of Windows 7 cannot be used for booting VHD as WIMBOOT and VHDX files cannot be used in Windows PE Or 7 OS.

WinNTSetup 4.0 Menu > Local Windows Installations allows to Capture WIM of a running Windows System using WIMLIB Engine.

WimBootCompress.ini file cannot be modified in this case, which is needed for APPLY as Portable OS Or for Grub4dos booting from RAMDISK.

Microsoft WimGAPI tool cannot be used as Engine, since it will make mistakes in uncompressing drivers needed for Portable Operating System.

VHD WIMBOOT has support for Office and Printer and any program can be installed, which is all not possible in case of WinPE

In case of VHD WIMBOOT on each machine it takes extra boottime and space to adjust the drivers for that machine

The VHD WIMBOOT solution is Portable, but not as flexible as Win10XPE, where boottime is not dependant on machine hardware


File makebt\WimBootCompress-W10X.ini gives minimal used space for VHD, but Portable OS requires the supplied WimBootCompress.ini

In WimBoot Capture file WimBootCompress.ini is copied to System32 and in Normal Mode WimBootCompress-Normal.ini is used but Not copied

Add 50 GB Fixed VHD as personalised UEFI VHD WIMBOOT Operating System to your Internal SSD

- In Windows 10 x64 Or 10XPE run VHD_WIMBOOT_x64 so that Hidden EFI partition is in VHD_WIMBOOT Selectable as Boot drive Z:
- Or use R-mouse to open admin cmd window and mount the EFI partition using mountvol Z: /s
- You can use R-mouse menu to run as administrator Explorer-x64.exe of Explorer++ for file management on EFI partition
- Use VHD_WIMBOOT to APPLY Captured WIM File to New Created VHD Fixed Size 50 GB on NTFS System Drive of Internal SSD
- In case of UEFI VHD WIMBOOT it is better that SVBus driver is NOT installed, since otherwise F8 menu is needed to allow unsigned drivers
- Boot 50 GB VHD as Filedisk from UEFI Boot Manager Menu and Switch to Microsoft Account for personalisation
- Make Links for Documents, Downloads and Pictures to folders elsewhere on Harddisk partition

Final Result - Windows 10 x64 in VHD booting from RAMDISK by using Grub4dos menu and SVBus driver



How to make Win10XPE WIM file for booting from RAMDISK

Download: Win10XPE Builder Or Win10XPE at GitHub and Unpack with 7-Zip x64 - More Info: Win10XPE and Quick Guide

Download Win10_1909_English_x64.iso or newer from TechBench Or using Windows-ISO-Downloader Tool

Mount ISO with double-click and Copy the Content of the ISO to Folder Win10_1909_English_x64 on your Harddisk

In WinBuilder > Build Core > Select Run ALL Programs From RAM to get WIM file with all Programs integrated

In WinBuilder > Apps > System Tools DeSelect XPE Startup (when Selected build fails)


In WinBuilder Select the Folder Win10_1909_English_x64 on your Harddisk and Start building with Play button

Use Win10XPE\ISO\sources\boot.wim as your Boot Image file and use Win10XPE\ISO\Boot\boot.sdi for booting WIM file from RAMDISK


First copy both files to folder Win10XPE located on NTFS System Drive of Portable SSD and then use <u>UEFI_MULTI</u> to make Boot Manager entry

More Info: Win10_Install.pdf Manual in Forums MSFN and Reboot.pro and UEFI MULTI

Downloads: from wimb GitHub - USB FORMAT - UEFI MULTI - System Info - VHD WIMBOOT - WOF Compress - MBR Backup








Next 3 Pages is old description based on using wimlib-clc

wimlib-clc can be used to CAPTURE Wimboot Image File from Mounted VHD

Download wimlib-clc and wimlib 64-bit - Extract wimlib to x64 folder of wimlib-clc so that Program is auto recognized From Mounted W10x64_F.vhd file, browse to it's Windows\system32 folder and copy file WimBootCompress.ini to wimlib-clc folder. Rename WimBootCompress.ini as WimBootCompress_BCD.ini and Edit this new ini file as follows:

- Add entries \Boot\BCD and \bootmgr to the [PrepopulateList] so that these files are copied as file instead of as pointers
- Remove or disable with; the **[PinningFolderList]** since it will give wimlib WARNING Unrecognized Section, which is safe to ignore The modified WimBootCompress_BCD.ini file is needed to allow Grub4dos booting VHD from RAMDISK and so to avoid Error 13

In Win10 x64 OS Run **wimlib-clc** and Select Image file C:\sources\capt_f.wim using Mounted W10x64_F.vhd as Source Y:\ Select **--wimboot** and Select custom WimBootCompress_BCD.ini file Selected as **--config** Select **CAPTURE** to make sources\capt_f.wim Image file from Mounted W10x64_F.vhd



Download <u>UEFI_MULTI</u> Tool to make USB Bootable from Boot Manager menu with VHD file in BIOS and UEFI_Secure mode UEFI_MULTI can make Grub4dos menu entry for VHD booting with <u>SVBus driver</u> as FILEDISK or as RAMDISK UEFI_MULTI makes entry in Windows Boot Manager for booting VHD as FILEDISK using Microsoft vhdmp.sys driver

Make Portable SSD 250 GB - SAMSUNG Portable SSD T5 250 GB with UEFI/MBR Partitioning


- 1st partition 20 GB FAT32 Set Active for Boot Manager and Grub4dos Boot files and 2nd partition NTFS for VHD + WIM System files
- 1. In **Disk Management** remove existing exFat Volume and Create new partitions
- 2. MBR partitioning with 1st partition 20 GB FAT32 Set Active and 2nd partition NTFS
- 3. In admin command window run DiskPart
- 4. In DiskPart type list volume and select volume <FAT32 volume nr> and active and exit


BIOS mode booting requires Active partition with BOOTMGR bootsector

UEFI mode booting requires FAT32 partition with x64 file efi\boot\bootx64.efi Or x86 file efi\boot\bootia32.efi

Use WinNTSetup to Create 2GB VHD on NTFS drive of Portable SSD and Apply Captured WIM file with Setup


- 1. Copy file capt f.wim to folder sources on NTFS drive of Portable SSD connected to USB
- 2. Start WinNTSetup x64 and use VHD Create to make 2GB file W10x64_F2.vhd on NTFS partition of Portable SSD
- 3. Select USB Boot Drive and Installation Drive (X: Mounted VHD) for Win10x64 Installation
- 4. Select location Windows Installation files Select your **sources\capt_f.wim** file on USB
- 5. Select Mode Wimboot and Disable All Tweaks since the Capture contains them already
- 6. Select **Setup** and prepare VHD for installation of Win10x64 choose OK and not Reboot
- 7. Run BOOTICEx64.exe Choose Boot\BCD on USB Boot Drive
- 8. Professional mode Choose Windows 10 (WimBoot) entry use Description W10x64_F2.vhd and BootMenuPolicy set value Legacy
- 9. Use R-mouse to create New element AllowPrereleaseSignatures Yes needed for SVBus driver
- 10. Reboot from USB with W10x64_F2.vhd from Boot Manager Menu
- 11. After booting with VHD then use R-mouse menu to Run as admin file instx64.exe of SVBus bin folder to install the driver
- 12. Reboot with Win10 x64 OS and use UEFI MULTI to make Grub4dos menu entry for booting VHD WIMBOOT as RAMDISK
- 13. Reboot from USB and Select in Grub4dos menu your WIMBOOT VHD for booting from RAMDISK





After install of extra programs or after adding drivers of other machines, it will be needed to regain **FREE Size** in your VHD CAPTURE - Format - APPLY carried out on mounted VHD results quickly in the original free space, since all file data go in the WIM file

Reboot with Win10 x64 OS and use wimlib-clc to CAPTURE Image file capt_f2.wim from Mounted W10x64_F2.vhd Selected as Source



After Format of Mounted W10x64_F2.vhd as Selected Target, then APPLY capt_f2.wim Image file using --wimboot flag

