

# ADOBE® INDESIGN® CS4



## ADOBE INDESIGN CS4 SOLUTIONS



© 2008 Adobe Systems Incorporated. All rights reserved.

*Adobe InDesign CS4 Solutions*

If this guide is distributed with software that includes an end user agreement, this guide, as well as the software described in it, is furnished under license and may be used or copied only in accordance with the terms of such license. Except as permitted by any such license, no part of this guide may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, recording, or otherwise, without the prior written permission of Adobe Systems Incorporated. Please note that the content in this guide is protected under copyright law even if it is not distributed with software that includes an end user license agreement.

The content of this guide is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Adobe Systems Incorporated. Adobe Systems Incorporated assumes no responsibility or liability for any errors or inaccuracies that may appear in the informational content contained in this guide.

Please remember that existing artwork or images that you may want to include in your project may be protected under copyright law. The unauthorized incorporation of such material into your new work could be a violation of the rights of the copyright owner. Please be sure to obtain any permission required from the copyright owner.

Any references to company names in sample templates are for demonstration purposes only and are not intended to refer to any actual organization.

Adobe, the Adobe logo, Acrobat, Bridge, Creative Suite, Flex, Flex Builder, Illustrator, InCopy, InDesign, Photoshop, and Reader are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States and/or other countries. Microsoft and Windows are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries. Apple and Mac OS are trademarks of Apple Computer, Incorporated, registered in the United States and other countries. All other trademarks are the property of their respective owners.

Adobe Systems Incorporated, 345 Park Avenue, San Jose, California 95110, USA. Notice to U.S. Government End Users. The Software and Documentation are "Commercial Items," as that term is defined at 48 C.F.R. §2.101, consisting of "Commercial Computer Software" and "Commercial Computer Software Documentation," as such terms are used in 48 C.F.R. §12.212 or 48 C.F.R. §227.7202, as applicable. Consistent with 48 C.F.R. §12.212 or 48 C.F.R. §§227.7202-1 through 227.7202-4, as applicable, the Commercial Computer Software and Commercial Computer Software Documentation are being licensed to U.S. Government end users (a) only as Commercial Items and (b) with only those rights as are granted to all other end users pursuant to the terms and conditions herein. Unpublished-rights reserved under the copyright laws of the United States. Adobe Systems Incorporated, 345 Park Avenue, San Jose, CA 95110-2704, USA. For U.S. Government End Users, Adobe agrees to comply with all applicable equal opportunity laws including, if appropriate, the provisions of Executive Order 11246, as amended, Section 402 of the Vietnam Era Veterans Readjustment Assistance Act of 1974 (38 USC 4212), and Section 503 of the Rehabilitation Act of 1973, as amended, and the regulations at 41 CFR Parts 60-1 through 60-60, 60-250, and 60-741. The affirmative action clause and regulations contained in the preceding sentence shall be incorporated by reference.

# Contents

<b>Introduction</b>	7
<b>Layout</b>	9
Getting Started	9
Documents	11
Spreads and Pages	16
Layers	24
Master Spreads and Master Pages	29
Page Items	35
Guides and Grids	41
Layout Windows and Layout Views	45
<b>Text</b>	49
Getting Started	49
Stories	51
Story Text	55
Text Formatting	62
Text Containers	71
Rendered Text	84
Text Composition	87
Text Hyphenation	92
Fonts	96
Find/Change Text	100
<b>Tables</b>	105
Getting Started	105
Tables	107
Tables and Cells	109
Text in Tables	111
Table and Cell Styles	113

<b>Graphics</b>	<b>119</b>
Introduction	119
Paths	119
Graphic Page Items	122
Colors and Swatches	130
Graphic Attributes	133
Drawing	141
Frequently Asked Questions	143
<b>Selection</b>	<b>153</b>
Getting Started	153
Working with Selection Suites Provided by the API	154
Creating Selection Suites	160
<b>User Interfaces</b>	<b>169</b>
Getting Started	169
Menus	171
Alerts	174
Progress Bars	175
Dialogs	176
Palettes and Panels	181
Static Text Widgets	193
Check Boxes and Radio Buttons	196
Button Widgets	198
Edit Boxes	202
Image Widgets	206
Drop-Down Lists and Combo Boxes	208
Splitter Widgets	211
Scroll Bars	212
Sliders	213
Tree-view Widgets	216
The Quick Apply Dialog	225

<b>XML</b>	227
The XML User Interface . . . . .	227
XML Import . . . . .	229
XML Export. . . . .	236
Tags . . . . .	238
Elements and Content. . . . .	247
XSLT . . . . .	259
<b>Versioning Persistent Data</b> . . . . .	261
Getting Started . . . . .	261
Working with Data Conversion Strategies . . . . .	262
<b>Commands</b> . . . . .	269
Finding commands provided by the API . . . . .	269
Spying on command processing . . . . .	270
Processing a command . . . . .	271
Scheduling a command. . . . .	272
Processing a command sequence . . . . .	273
Processing an abortable command sequence. . . . .	274
Fixing assert "DataBase change outside of Begin/End Transaction!" . . . . .	275
<b>Notification</b> . . . . .	277
Finding responder events and their associated ServiceID . . . . .	277
Spying on observer notification broadcasts . . . . .	280
Accessing lazy notification data objects used by the application. . . . .	280
Using lazy notification data . . . . .	281
<b>Snippets</b> . . . . .	285
Working with snippet export . . . . .	285
Working with snippet import . . . . .	289
Working with snippets and libraries . . . . .	291

<b>InCopy: Assignments . . . . .</b>	<b>295</b>
Creating an assignment . . . . .	295
Adding content to an assignment . . . . .	296
Examining the content of an assignment . . . . .	296
Deleting an assignment . . . . .	297
<b>Flash/FlexUI . . . . .</b>	<b>299</b>
Getting Started . . . . .	299
Flash/Flex from a C++ plug-in . . . . .	300
Flash/Flex from ScriptUI . . . . .	304
Limitations . . . . .	307

# Introduction

This document offers step-by-step instructions to developers embarking on Adobe® InDesign® development tasks. It includes references to other SDK documentation, tools, and samples, and it helps developers determine which InDesign API to use for different tasks.

Before the information in this document is of much value, you will need to become familiar with the architecture. If you are new to InDesign development, we recommend approaching the documentation as follows:

1. *Getting Started With the Adobe InDesign CS4 Products SDK* provides an overview of the SDK, as well as a tutorial that takes you through the tools and steps to build your first plug-in.
2. *Learning Adobe InDesign CS4 Plug-in Development* introduces the most common programming constructs for InDesign development. This includes an introduction to the InDesign object model and basic information on user-interface options, scripting, localization, and best practices for structuring your plug-in.
3. The SDK itself includes several sample projects. All samples are described in the “Samples” section of the API reference. This is a great opportunity to find sample code that does something similar to what you want to do, and study it.
4. This manual provides step-by-step instructions (or “recipes”) for accomplishing various tasks. If your particular task is covered by this guide, reading it can save you a lot of time.
5. *Adobe InDesign CS4 Products Programming Guide* provides the most complete, in-depth information on plug-in development for InDesign CS4 products.



# Layout

---

## Getting Started

This chapter presents layout-related use cases. To solve a layout-related programming problem, like creating a spread or finding the frames in a spread, look for a use case that matches your needs.

To learn about how layout works and is organized under the hood, do the following:

- Run through the activities in “[Exploring Layout with SnippetRunner](#)” on page 9, to learn how to explore the layout-related objects in a document and familiarize yourself with layout-related sample code.
- Read the “Layout Fundamentals” chapter in *Adobe InDesign CS4 Programming Guide*.

## Exploring Layout with SnippetRunner

SnippetRunner is a plug-in that lets you run code snippets provided in the SDK. Several code snippets are provided that let you explore the layout-related objects in a document.

### Solution

1. Run Adobe® InDesign® with the SnippetRunner plug-in present. For instructions on using the plug-in, see the API documentation page for SnippetRunner.
2. Run the CreateDocument code snippet.
3. Run the InspectLayoutModel code snippet to create a textual report about the objects in the document’s layout hierarchy.
4. Run the CreateFrame code snippet.
5. Deselect the new frame and run the InspectLayoutModel code snippet, to see how the document’s layout hierarchy has changed. A new kSplineItemBoss is created.

**NOTE:** If an object is selected, InspectLayoutModel reports the hierarchy of only the selected object. If nothing is selected, it reports the hierarchy of the entire document.

6. Run the PlaceFile code snippet, and place an image file.
7. Make sure the placed frame is selected, and run the InspectLayoutModel code snippet to report the objects in the hierarchy of the graphic frame.

8. Create other objects in a document or open documents containing layouts you want to examine, and use `InspectLayoutModel` to examine the boss objects representing the layout hierarchy.
9. Browse the sample code in the snippets you have been running.

### Sample Code

- `SnpCreateDocument`
- `SnpInspectLayoutModel`
- `SnpCreateFrame`
- `SDKLayoutHelper`

### Related APIs

- `IDocument`
- `IDocumentLayer`
- `IHierarchy`
- `IMasterSpreadList`
- `ISpread`
- `ISpreadLayer`
- `ISpreadList`

## Finding Layout-related Resources in the SDK

You can locate assets in the SDK that will help you program with the layout subsystem.

### Solution

1. See *Adobe InDesign CS4 Programming Guide*, in the docs/guides folder. The “Layout Fundamentals” chapter covers the layout subsystem.
2. See the API documentation in docs/references/index.chm or in HTML format. There are documentation pages for boss classes and interfaces. Sample code related to layout is on the Layout Samples page.

---

# Documents

## Acquiring a Reference to a Document

### Solution

A document (kDocBoss) is characterized by the IDocument interface. A UIDRef that can instantiate an IDocument interface is a document.

To iterate through documents, use IDocumentList to list the documents the application has open. See “[Iterating through Documents](#)” on page 14.

If you have an IDataBase pointer, call IDataBase::GetRootUID. The document associated with a database (if any) can be discovered using code like the following:

```
InterfacePtr<IDocument> document (db, db->GetRootUID(), UseDefaultIID());  
if (document != nil) // use the document interface
```

If you have a UIDRef, follow these steps:

1. Call UIDRef::GetDataBase to discover the IDataBase pointer.
2. Use the pointer to acquire the document as described above.

If you have an interface pointer for any interface on a UID-based object (for example, an IHierarchy interface), follow these steps:

1. Call the PersistUtils function ::GetDataBase to discover the IDataBase pointer.
2. Use the pointer to acquire the document as described above.

If you have an IActiveContext interface, call IActiveContext::GetContextDocument. The document associated with this context (if any) can be found using code like the following:

```
IDocument* document = activeContext->GetContextDocument();  
if (document != nil) // use the document interface
```

If you have a layout view, call ILayoutControlData::GetDocument. For details, in the “Layout Fundamentals” chapter of *Adobe InDesign CS4 Programming Guide*, see “The Layout Window and View” section. This call often is used by trackers (ITracker).

To work with the document the user is editing, call ILayoutUIUtils::GetFrontDocument.

### Related API

IDocument

## Creating a Document

### Creating a Document with a Setup of your Own Choice

You can create a document and specify the number of pages, page size, and so on that the new document should have.

#### Solution

1. To create the command, call `IDocumentCommands::CreateNewCommand`.
2. Populate the command's `INewDocCmdData` data interface to describe the desired set-up.
3. Process the command.

#### Sample Code

- `SDKLayoutHelper::CreateDocument`
- `SnpCreateDocument`

### Creating a Document using the Default Document Setup

#### Solution

Call `IDocumentCommands::New` with the `syleToUse` parameter set to nil.

#### Related APIs

- `IDocument`
- `IDocumentCommands`
- `IPageSetupPrefs`

### Creating a Document from a Document Preset

#### Solution

1. Using `IDocStyleListMgr`, find the name of the preset style (`kDocStyleBoss`) on which you want to base your document.
2. Call `IDocumentCommands::New`, passing the name of the preset in the `syleToUse` parameter.

#### Related APIs

- `IDocument`
- `IDocumentCommands`

## Opening an Existing Document

### Solution

Use `IDocumentCommands::Open`.

### Sample Code

`SDKLayoutHelper::OpenDocument`

### Related APIs

- `IDocumentCommands`
- `IDocument`

## Saving a Document

### Saving a Document to a File

#### Solution

If you already know where the file to save into is located or you want full control over how the user is prompted for the file location, call `IDocumentCommands::SaveAs`.

If you want the user to be asked to identify the file to save to using the application's save file dialog, call `IDocFileHandler::SaveAs`.

#### Sample Code

`SDKLayoutHelper::SaveDocumentAs`

#### Related API

`IDocumentCommands`

### Saving a Document

You can save a document that was saved to a file at least once before (`IDocument::IsSaved` indicates this).

#### Solution

Call one of the following

- `IDocumentCommands::Save`
- `IDocFileHandler::Save`

#### Related APIs

- `IDocument`
- `IDocumentCommands`
- `IDocFileHandler`

## Closing a Document

### Solution

To close any layout windows that are open, then schedule a command to close the document, use IDocFileHandler::Close.

To process a command to close the document immediately, use IDocumentCommands::Close.

### Sample Code

SDKLayoutHelper::CloseDocument

### Related API

IDocument

## Iterating through Documents

You can examine all open documents.

### Solution

1. Use the session returned from GetExecutionContextSession() to call ISession::QueryApplication.
2. Call IApplication::QueryDocumentList.
3. Examine the documents using IDocumentList

### Sample Code

```
InterfacePtr<IAplication> application(GetExecutionContextSession() ->QueryApplication());  
InterfacePtr<IDocumentList> documentList(application->QueryDocumentList());  
for (int32 i = 0; i < documentList->GetDocCount(); i++) {  
    IDocument* document = documentList->GetNthDoc(i);  
    PMString name;  
    document->GetName(name);  
}
```

### Related API

IDocument

## Finding the Default InDesign Document Setup

You can find the properties displayed in the File > Document Setup and File > New Document dialogs.

### Solution

To get the defaults inherited by new documents, use IPageSetupPrefs on kWorkspaceBoss.

To get the settings for a document, use IPageSetupPrefs on kDocWorkspaceBoss.

### Sample Code

SnpModifyLayoutGrid

### Related API

IPageSetupPrefs

## Changing the Default InDesign Document Setup

### Solution

Use kSetPageSetupPrefsCmdBoss.

### Related Documentation

- See “[Finding the Default InDesign Document Setup](#)” on page 15.

### Related API

IPageSetupPrefs

## Getting Notified when Documents are Created, Opened, Saved, or Closed

### Solution

Implement a document signal responder service (IResponder).

### Sample Code

DocWatch

### Related APIs

- DocWchResponder::Respond catalogs the ServiceIDs.
- IK2ServiceProvider
- IResponder

---

# Spreads and Pages

## Acquiring a Reference to a Spread

### Solution

A spread (kSpreadBoss) is characterized by the ISpread interface. A UIDRef that can instantiate an ISpread interface is a spread.

To iterate through the spreads (kSpreadBoss) in a document (see “[Acquiring a Reference to a Document](#)” on page 11), use ISpreadList.

If you have an IHierarchy interface on a page item, use the following:

- IHierarchy::GetSpreadUID.
- IPasteboardUtils::QuerySpread. This utility gives you the ISpread interface of the spread that owns the object whose IHierarchy interface you already have.

**NOTE:** If you have another page item interface like IGeometry or ITransform, query that interface for IHierarchy, then call the method above to get a reference to the spread.

If you have a layout view and want to find the spread being edited, use ILayoutControlData::GetSpread.

If you have a document and want to find the spread being edited, use IID\_ICURRENTSPREAD on kDocBoss. This is an IPersistUIData interface that stores the current spread for a document.

To hit test for a spread, use IPasteboardUtils.

### Sample Code

- BscDNDCustomFlavorHelper::ProcessDragDropCommand
- CHMLFiltHelper::collectGraphicFrames
- SnapTracker::BeginTracking
- SnpInspectLayoutModel

### Related APIs

- ISpread
- kSpreadBoss

## Creating a Spread

### Solution

Use kNewSpreadCmdBoss.

### Related APIs

- ISpread
- kSpreadBoss

## Deleting a Spread

### Solution

Use kDeleteSpreadCmdBoss.

### Related APIs

- ISpread
- kSpreadBoss

## Iterating through Spreads

You can examine all spreads in a document.

### Solution

Use ISpreadList.

### Sample Code

- CHMLFiltHelper::collectGraphicFrames
- SnpInspectLayoutModel

### Related APIs

- ISpread
- kSpreadBoss

## Rearranging the Order of Spreads

You can rearrange the order of spreads in a document; for example, move the spread containing pages 2 and 3 so these pages precede the spread containing pages 6 and 7.

### Solution

Use kMoveSpreadCmdBoss.

### Related APIs

- ISpread
- ISpreadList

## Copying a Spread

You can duplicate a spread and the page items it contains.

### Solution

To append the duplicated spread to the spread list (ISpreadList) in the target document, process kCreateSpreadFromSpreadCmdBoss.

To control where in the spread list (ISpreadList) the spread is positioned, follow these steps:

1. Process kNewSpreadCmdBoss to create a new spread at a position of your choice in the target document's spread list.
2. Process kDuplicateSpreadCmdBoss to copy the source spread.

## Iterating through the Content of a Spread

### Solution

Use IHierarchy on kSpreadBoss.

### Related Documentation

- “[Iterating through Page Content](#)” on page 21.
- “[Iterating through Layer Content](#)” on page 27.

### Sample Code

- SnpInspectLayoutModel
- In the “Layout Fundamentals” chapter of *Adobe InDesign CS4 Programming Guide*, see two examples: “Code that Iterates through Spreads and Visits their Children via IHierarchy” and “Code that Iterates through Spreads and Filters Items by Page via ISpread”.

## Acquiring a Reference to a Page

### Solution

A page (kPageBoss) is characterized by the IMasterPage interface. A UIDRef that can instantiate an IMasterPage interface is a page.

If you have a document (see “[Acquiring a Reference to a Document](#)” on page 11) and want to iterate through its pages, use IPagedList. See “[Acquiring a Reference to a Page](#)” on page 19.

If you have a spread (see “[Acquiring a Reference to a Spread](#)” on page 16) and want to iterate through its pages, use the following:

- ISpread::GetNumPages and ISpread::GetNthPageUID provide easy access to the pages.
- ISpread::QueryPagesLayer provides access to the spread layer that stores the pages on its IHierarchy. The child boss objects of this spread layer are the pages owned by the spread.

If you have a page item and want to know the page, if any, on which it lies or is drawn, use the following:

- ILayoutUtils::GetOwnerPageUID
- ILayoutUtils::GetDrawingPageUID

If you have a layout view(kLayoutWidgetBoss), use ILayoutControlData::GetPage, to get the page being viewed by the user in layout view.

### Sample Code

- CHMLFiltImportProvider::LoadImage
- SnpCreateInddPreview::CreateFirstPagePreview

### Related API

kPageBoss

## Creating a Page

### Solution

Use kNewPageCmdBoss.

### Related API

kPageBoss

## Deleting a Page

You can delete a page and the page items on it.

### Solution

Use kDeletePageCmdBoss.

### Related API

kPageBoss

## Iterating through Pages

You can examine the pages in a document or the pages in a spread.

### Solution

To iterate through all pages in a document, use IPageList.

**NOTE:** IPageList does not list master pages (the pages owned by master spreads). It lists only pages owned by spreads (kSpreadBoss).

To iterate through all pages in a spread, use ISpread.

### Sample Code

CHMLFiltImportProvider::LoadImage

### Related APIs

- IPageList
- ISpread
- kPageBoss

## Rearranging Pages

You can rearrange the order of pages in a document.

### Solution

Use kMovePageCmdBoss.

### Related APIs

- IPageList
- kPageBoss

## Copying a Page

You can duplicate a page together with the page items on it.

### Solution

To append the duplicated page to the target document, use `kCreatePageFromPageCmdBoss`.

To control the spread in which the duplicate is made, do one of the following:

- Create a new spread for the page using `kNewSpreadCmdBoss`.
- Process `kDuplicatePageCmdBoss`.

### Related API

`kPageBoss`

## Iterating through Page Content

You can iterate through page items on a page.

### Solution

Use `ISpread::GetItemsOnPage`.

### Sample Code

- `CHMLFiltImportProvider::LoadImage`
- In the “Layout Fundamentals” chapter of *Adobe InDesign CS4 Programming Guide*, see the example entitled “Code that Iterates through Spreads and Filters Items by Page via `ISpread`.”

### Related APIs

- `ISpread`
- `kPageBoss`

## Finding Page Size

### Solution

If you have a reference to a page (`kPageBoss`), use `IGeometry::GetStrokeBoundingBox` to get the size of each page.

If you have a reference to the document’s workspace (`kDocWorkspaceBoss`), use `IPageSetupPrefs` to get the default page size inherited by new pages.

**NOTE:** The size of each page (`kPageBoss`) in a document is the same and always agrees with the default page size stored in `IPageSetupPrefs`.

### Sample Code

`SnpModifyLayoutGrid`

**Related API**

kPageBoss

## Changing Page Size

You can change the size of all pages in a document.

**Solution**

Use kSetPageSetupPrefsCmdBoss to change the default page size and the size of all pages.

**Related API**

kPageBoss

## Finding Page Margins

**Solution**

Use IMargins. Each page (kPageBoss) has its own margins.

**Sample Code**

- CHMLFiltHelper::addGraphicFrameDescription
- SDKLayoutHelper::PageToSpread
- SnpModifyLayoutGrid

**Related API**

kPageBoss

## Changing Page Margins

**Solution**

Use kSetPageMarginsCmdBoss.

**Sample Code**

SnpModifyLayoutGrid

**Related API**

kPageBoss

## Finding Page Column Guides

### Solution

Use IColumns. Each page (kPageBoss) has its own column guides.

### Sample Code

- SnpModifyLayoutGrid

### Related API

kPageBoss

## Changing Page Column Guides

### Solution

Use the following:

- kSetPageColumnsCmdBoss
- kSetColumnGutterCmdBoss

### Sample Code

SnpModifyLayoutGrid

### Related API

kPageBoss

## Getting Notified of Spread and Page Operations

### Solution

Implement a document observer interested in IID\_ISPREADLIST.

**NOTE:** This approach works for commands that create, delete, arrange, and copy spreads and pages but not for all spread and page manipulations. For details of the subject you need to observe, see the API documentation for the command used to perform the operation in which you are interested.

### Related APIs

- IDocument
- IObserver
- ISubject

---

## Layers

### Acquiring a Reference to a Layer

A layer comprises a document layer with two corresponding spread layers in each spread in the document. Spread layers own page items. If you want a boss object to act as a parent for a new page item, you will need a reference to a spread layer.

#### Acquiring a Reference to a Document Layer

##### Solution

A document layer (kDocumentLayerBoss) is characterized by the IDocumentLayer interface. A UIDRef that can instantiate an IDocumentLayer interface is a document layer.

If you have a document (see “[Acquiring a Reference to a Document](#)” on page 11) and want to examine all the document layers, use ILayerList.

If you have a document and want to find the document layer targeted for edit operations, use ILayerUtils::QueryDocumentActiveLayer.

If you have a spread layer and want to find its associated document layer, use ISpreadLayer::QueryDocLayer.

If you have a reference to a page item and want to find its associated document layer, Call ILayerUtils::GetLayerUID to get the spread layer that owns the page item, then call ISpreadLayer::QueryDocLayer.

If you have a layout view and want to find the document layer targeted for edit, use ILayoutControlData::QueryActiveDocLayer or ILayoutControlData::GetActiveDocLayerUID give the active document layer.

If you have an IActiveContext interface, use ILayerUIUtils::QueryContextActiveLayer.

##### Sample Code

- SdkLayoutHelper
- SnpInspectLayoutModel

##### Related API

kDocumentLayer

## Acquiring a Reference to a Spread Layer

### Solution

A spread layer (`kSpreadLayerBoss`) is characterized by the `ISpreadLayer` interface. A `UIDRef` that can instantiate an `ISpreadLayer` interface is a spread layer.

If you have a spread (see “[Acquiring a Reference to a Spread](#)” on page 16) and a document layer (see “[Acquiring a Reference to a Document Layer](#)” on page 24), use `ISpread::QueryLayer` to get the content or guide spread layer (`kSpreadLayerBoss`) associated with the document layer.

If you have a page item and want to know the spread layer that owns it, use `IHierarchy::GetLayerUID`.

**NOTE:** Some hierarchies, like those for an inline frame (`kInlineBoss`), return `kInvalidUID`. If you are working with inline frames, use `IPageItemUtils::QueryInlineParentPageItem` to find the page item in the layout hierarchy first, then find the spread layer.

If you have a layout view and want to find the spread layer targeted for edit operations, use `ILayoutControlData::QueryActiveLayer` or `ILayoutControlData::GetActiveLayerUID` to get the active spread layer. This is useful if you want to parent page items created by your plug-in on the same layer the user is editing.

### Sample Code

- `SDKLayoutHelper::GetActiveSpreadLayerRef`
- `SnpInspectLayoutModel`

### Related API

`kSpreadLayer`

## Creating a Layer

### Solution

Use `kNewLayerCmdBoss`.

### Sample Code

`SnpProcessDocumentLayerCmnds::CreateNewLayer`

### Related APIs

- `kDocumentLayer`
- `kSpreadLayer`

## Deleting a Layer

You can delete a layer and its associated content.

### Solution

Use kDeleteLayerCmdBoss.

### Related APIs

- kDocumentLayer
- kSpreadLayer

## Iterating through Layers

You can examine the layers in a document.

### Solution

- Use ILayerList to get the document layers(kDocumentLayerBoss).
- Use ISpread::QueryLayer to get the spread layers associated with a document layer.

### Sample Code

- SnpInspectLayoutModel
- In the “Layout Fundamentals” chapter of *Adobe InDesign CS4 Programming Guide*, see the example entitled “Code that Iterates through Spreads in a Document, then Iterates through Document Layers, to visit Items on the Spread Layer associated with each Document Layer.”

### Related APIs

- ILayerList
- ISpread
- kDocumentLayer
- kSpreadLayer

## Rearranging the Order of Layers

### Solution

Use kMoveLayerCmdBoss.

### Related APIs

- kDocumentLayer
- kSpreadLayer

## Copying a Layer

### Solution

To append the duplicated layer to the end of the layer list (ILayerList) in the target document, use kCreateLayerFromLayerCmdBoss.

To position the duplicate at a position of choice in the layer list (ILayerList), use the following:

1. kNewLayerCmdBoss creates a new layer.
2. kMoveLayerCmdBoss positions the new layer.
3. kDuplicateLayerCmdBoss copies the content.

### Related APIs

- [kDocumentLayer](#)
- [kSpreadLayer](#)

## Iterating through Layer Content

You can examine all page items assigned to a given layer on a spread.

### Solution

1. Iterate through document layers using ILayerList.
2. Iterate through spreads using ISpreadList.
3. Iterate through the spread layers using ISpread::QueryLayer.
4. Examine the page items on the IHierarchy of each spread layer.

### Sample Code

- [SnpInspectLayoutModel](#)
- In the “Layout Fundamentals” chapter of *Adobe InDesign CS4 Programming Guide*, see the example “Code that Iterates through Spreads in a Document, then Iterates through Document Layers, to visit Items on the Spread Layer associated with each Document Layer.”

## Locking and Unlocking a Layer

### Solution

Use kLockLayerCmdBoss.

### Related API

[kDocumentLayer](#)

## Showing and Hiding a Layer

### Solution

Use kShowLayerCmdBoss.

### Related API

kDocumentLayer

## Renaming a Layer

### Solution

Use kChangeLayerNameCmdBoss.

### Related API

kDocumentLayer

## Changing Layer Color

### Solution

Use kSetLayerColorCmdBoss.

### Related API

kDocumentLayer

## Merging Layers

You can merge two or more layers and the page items assigned to them into one layer.

### Solution

Use kMergeLayersCmdBoss.

### Related APIs

- kDocumentLayer
- kSpreadLayer

## Getting Notified of Layer Operations

### Solution

Implement a document observer that's interested in IID\_ILAYERLIST

### Related APIs

- IDocument
- kDocumentLayer
- IObserver
- ISubject

---

## Master Spreads and Master Pages

### Acquiring a Reference to a Master Spread

#### Solution

A master spread (kMasterpagesBoss) is characterized by the IMasterSpread interface. A UIDRef that can instantiate an IMasterSpread interface is a master spread.

If you have a document (see “[Acquiring a Reference to a Document](#)” on page 11) and want to examine all the master spreads, use IMasterSpreadList.

If you have a page (see “[Acquiring a Reference to a Page](#)” on page 19) and want to find its master spread, use IMasterPage::GetMasterPageUID.

### Related APIs

- IMasterPage
- IMasterSpread
- kMasterPagesBoss
- kPageBoss

## Creating a Master Spread

### Solution

Use `kNewMasterSpreadCmdBoss`.

### Related Documentation

- “[Copying a Master Spread](#)” on page 31

### Related APIs

- `IMasterPage`
- `kMasterPagesBoss`
- `IMasterSpread`
- `IMasterSpreadList`
- `kPageBoss`

## Deleting a Master Spread

### Solution

Use `kDeleteMasterSpreadCmdBoss`.

### Related APIs

- `IMasterPage`
- `IMasterSpreadList`
- `kMasterPagesBoss`
- `IMasterSpread`
- `kPageBoss`

## Rearranging the Order of Master Spreads

### Solution

The order of master spreads in the document is given by their index order in `IMasterSpreadList`. To re-arrange the order process, use `kMoveMasterSpread`.

### Related APIs

- `IMasterPage`
- `kMasterPagesBoss`
- `IMasterSpread`
- `kPageBoss`

## Copying a Master Spread

You can duplicate a master spread and the page items it contains.

### Solution

To append the duplicated master spread to the master spread list (IMasterSpreadList) in the target document, use kCreateMasterFromMasterCmdBoss.

To control where in the master spread list (IMasterSpreadList) the master spread is positioned, follow these steps:

1. Use kNewMasterSpreadCmdBoss to create a new master spread at a position of your choice in the target document's master spread list.
2. Use kDuplicateSpreadCmdBoss to copy the source spread.

## Saving a Spread as a Master Spread

You can create a master spread from a spread and the page items it contains.

### Solution

To append the duplicated spread to the master spread list (IMasterSpreadList) in the target document, use kCreateMasterFromSpreadCmdBoss.

To control where in the master spread list (IMasterSpreadList) the master spread is positioned, follow these steps:

1. Use kNewMasterSpreadCmdBoss to create a new master spread at a position of your choice in the target document's master spread list.
2. Use kDuplicateSpreadCmdBoss to copy the source spread.

### Related APIs

- IMasterPage
- IMasterSpread
- kMasterPagesBoss
- kPageBoss

## Renaming a Master Spread

You can change the name or prefix of a master spread.

### Solution

Use kRenameMasterSpreadCmdBoss.

### Related APIs

- IMasterPage
- IMasterSpread
- kMasterPagesBoss
- kPageBoss

## Acquiring a Page's Master Page

### Solution

To get hold of a page if you do not have one, see “[Acquiring a Reference to a Page](#)” on page 19.

Follow these steps:

1. Use IMasterPage::IsValid to determine whether the page has a master (if so, kTrue is returned).
2. Use IMasterPage::GetMasterPageUID to return the UID of the associated master spread (kMasterPagesBoss).
3. Use IMasterPage::GetMasterIndex to get the index of the master page in the master spread.
4. With the index, use ISpread::GetItemsOnPage to get the master spread's ISpread interface, and call it to collect a list of all page items on the master page.

### Sample Code

`SnpInspectLayoutModel::TracePageNode`

### Related APIs

- IMasterPage
- IMasterSpread
- kMasterPagesBoss
- kPageBoss

## Distinguishing a Master Page from a Page

### Solution

Both pages and master pages are represented by the same boss class kPageBoss (see “[Acquiring a Reference to a Page](#)” on page 19). To tell them apart, call ILayoutUtils::IsAMaster. A master page is a page owned by a master spread (kMasterPagesBoss). This utility encapsulates the tests that need to be made to determine this.

### Related APIs

- IMasterPage
- IMasterSpread
- kMasterPagesBoss
- kPageBoss

## Applying a Master Page to a Page

### Solution

Use kApplyMasterSpreadCmdBoss.

### Related APIs

- IMasterPage
- IMasterSpread
- kMasterPagesBoss
- kPageBoss

## Showing and Hiding Master Page Items

### Solution

Use kShowMasterItemsCmdBoss.

### Related API

kSpreadBoss

## Overriding Master Page Items

### Solution

To override master page items of your choice, use `kOverrideMasterPageItemCmdBoss`.

To override all the master page items associated with a range of spreads of pages, use `IMasterSpreadUtils::CreateOverrideMasterPageItemsCmd`.

### Related APIs

- `IMasterOverrideList`
- `IMasterPage`
- `IMasterSpread`
- `kMasterPagesBoss`
- `kPageBoss`

## Removing a Master Page Item Overrides

### Solution

To remove the master page item overrides of your choice, use `kRemoveMasterPageOverrideCmdBoss`.

To remove master page item overrides of objects that are selected, use `IMasterPageSuite`.

### Related APIs

- `IMasterOverrideList`
- `IMasterPage`
- `IMasterSpread`
- `kMasterPagesBoss`
- `kPageBoss`

## Getting Notified of Master Spread and Master Page Operations

### Solution

Implement a document observer interested in `IID_ISPREADLIST`.

**NOTE:** This approach works for commands that create, delete, arrange, and copy spreads and pages but not for all spread and page manipulations. For details of the subject you need to observe, see the API documentation for the command used to perform the operation in which you are interested.

## Related APIs

- IDocument
- IObserver
- ISubject

---

# Page Items

## Creating a Page Item

### Creating an Empty Graphic Frame

#### Solution

1. Determine the UIDRef of the parent. The parent is the object that will own the frame. Normally, it is a spread layer (see “[Acquiring a Reference to a Spread Layer](#)” on page 25).
2. Determine the bounding box for the frame to position and size it as desired. Normally, frames are positioned relative to a page (see “[Acquiring a Reference to a Page](#)” on page 19).
3. Create the frame by calling the IPPathUtils method that creates the path you want:
  - Use IPPathUtils::CreateRectangleSpline to create a rectangular path.
  - Use IPPathUtils::CreateOvalSpline to create an elliptical path.
  - Use IPPathUtils::CreateRegPolySpline to create a regular polygon path.
  - Use IPPathUtils::CreateSpline to get complete control of the path.
  - Use attrType= INewPageItemCmdData::kGraphicFrameAttributes to create a placeholder graphic frame (a frame with an X in it).

[Example 1](#) shows code that, given a UIDRef to a document (kDocBoss), creates a frame at the origin of the first page in the document. The parent for the frame is the spread layer associated with the first content layer in the first spread in the document.

#### **EXAMPLE 1 Create a 100\*100 Point Square Graphic Frame at the Origin of the First Page**

```
// 1. Determine the UIDRef of the parent.  
InterfacePtr<ISpreadList> spreadList(docUIDRef, UseDefaultIID());  
InterfacePtr<ISpread> spread(spreadList.GetDataBase(), spreadList->  
GetNthSpreadUID(0), UseDefaultIID());  
InterfacePtr<ILayerList> layerList(docUIDRef, UseDefaultIID());  
IDocumentLayer* documentLayer = layerList->GetLayer(1);  
InterfacePtr<ISpreadLayer> spreadLayer(spread->QueryLayer(documentLayer));  
UIDRef parentUIDRef = ::GetUIDRef(spreadLayer);
```

```
if (spreadLayer->IsLocked() == kFalse) {  
    // 2. Determine the bounding box of the frame.  
    PMRect boundingBox(0, 0, 100, 100);  
    InterfacePtr<IGeometry> pageGeometry(spread->QueryNthPage(0));  
    ::InnerToPasteboard(pageGeometry, &boundingBox);  
  
    // 3. Create the frame.  
    UIDRef frameUIDRef = Utils<IPathUtils>()->CreateRectangleSpline(parentUIDRef,  
    boundingBox,  
    INewPageItemCmdData::kGraphicFrameAttributes,  
    kTrue, Transform::PasteboardCoordinates());  
}
```

### Sample Code

- SDKLayoutHelper::CreateRectangleFrame
- SnpCreateFrame

### Related API

kSplineItemBoss

## Creating a Path

### Solution

1. See “[Creating an Empty Graphic Frame](#)” on page 35 for the basic approach. Frames and paths both create spline item boss objects, kSplineItemBoss. The significant difference is that a graphic frame is designated as being a container for a graphics page item.
2. On calling the IPPathUtils create spline method that creates the path you want, use attrType=INewPageItemCmdData::kGraphicAttribute to create a path.

### Related Documentation

See “[Creating an Empty Graphic Frame](#)” on page 35.

### Sample Code

- SDKLayoutHelper::CreateRectangleGraphic
- SDKLayoutHelper::CreateSplineGraphic
- SnpCreateFrame

### Related API

See [Example 1](#) in “[Creating an Empty Graphic Frame](#)” on page 35.

## Creating a Text Frame

### Solution

Use kCreateMultiColumnItemCmdBoss.

### Sample Code

- SDKLayoutHelper::CreatetextFrame
- SnpCreateFrame

### Related APIs

- kMultiColumnItemBoss
- kSplineItemBoss

## Deleting Page Items and their Contents

### Solution

Use kDeleteCmdBoss.

## Moving Page Items from one Spread to Another

### Solution

Use kMoveToSpreadCmdBoss.

## Moving Page Items from one Layer to Another

### Solution

To move page items of your choice between layers, use kMoveToLayerCmdBoss.

To move page items that are currently selected between layers, use ILayerSuite

## Copying Page Items within or across Documents

You can copy a page item and any nested page items it contains, either within the same document or into another document.

### Solution

Use kCopyCmdBoss.

## Copying Page Items to the Clipboard

### Solution

To copy page items of your own choice to the clipboard, use `kCopyCmdBoss`.

To copy page items that are currently selected to the clipboard, use `IScrapSuite::CanCopy` and `IScrapSuite::Copy`.

## Pasting Page Items from the Clipboard

### Solution

To paste page items from the clipboard into a document of your choice (the spread layer that will be the parent of the pasted objects is specified by you), use `kPasteCmdBoss`.

To paste page items on the clipboard into a document being edited in layout view (the spread and layer that will contain the pasted objects is designated by the view's `ILayoutControlData`), use `IScrapSuite::CanPaste` and `IScrapSuite::Paste`.

## Removing Page Items from a Hierarchy

### Solution

To remove one page item from its hierarchy, use `IHierarchyUtils::RemoveFromHierarchy`.

To more than one page item from its associated hierarchy, use `kRemoveFromHierarchyCmdBoss`.

### Related API

`IHierarchy`

## Adding Page Items to a Hierarchy

### Solution

To add one page item into a hierarchy, use `IHierarchyUtils::AddToHierarchy`.

To add more than one page items to a hierarchy, use `kAddToHierarchyCmdBoss`.

## Iterating through Frame Content

You can examine the content of a frame.

### Solution

Query the frame for `IFrameType` to find the type of frame you have

## Finding the Frames in a Spread

### Solution

1. Call ISpread::GetItemsOnPage to get the page items
2. Call IPageItemTypeUtils to find the type of each page item, or query the page items for an IFrameType interface.

### Sample Code

```
CHMLFiltHelper::collectGraphicFrames
```

### Related APIs

- IHierarchy
- ISpread

## Searching for Page Items (Objects) with Certain Attributes

You may want to search/replace page items with certain graphic attributes. This section describes how to set search/replace options and find page items (objects) according to object style, frame type, and graphic attributes.

### Solution

1. Set search mode to IFindChangeOptions::kObjectSearch, using kFindSearchModeCmdBoss.
2. In IFindChangeOptions, set object type to find, using kObjectSearchTypeCmdBoss. You can choose from all frame types, graphic frames, and unassigned frames.
3. Set search scope using kScopeCmdBoss. The scope can be current document, all open documents, or within current selection. Do not forget to explicitly set the IID\_IFINDCHANGEMODEDATA interface on the command bosses to IFindChangeOptions::kObjectSearch search mode.
4. Choose an object style to search, and prepare an attribute boss list to store graphic attributes your found page item should have. Then, set the find object style and find attribute list using kFindChangeFormatCmdBoss.
5. Perform a search by creating kFindChangeServiceBoss and calling IFindChangeService::SearchObject().

### Sample Code

```
SnpFindAndReplace::Do_FindObject
```

## Related APIs

- IFindChangeOptions on kWorkspaceBoss maintains all find/change options.
- IFindChangeService on kFindChangeServiceBoss provides find/change object services.
- Commands: kFindSearchModeCmdBoss, kScopeCmdBoss, kFindChangeFormatCmdBoss, and kFindObjectBoss.

## Replacing Page Items (Objects) with New Attributes

After finding an object, we may want to replace it with new attributes or replace and find the next object. You also may want to find objects with specific attributes and replace them with new attributes. This section describes how to set search/replace options and replace page items (objects) according to both search/replace object style and graphic attributes.

### Solution

Replacing shares most steps with searching. The following are the steps to set up options and perform search and replace.

1. Set search mode to IFindChangeOptions::kObjectSearch, using kFindSearchModeCmdBoss.
2. In IFindChangeOptions, set object type to find, using kObjectSearchTypeCmdBoss. You can choose from all frame types, graphic frames, and unassigned frames.
3. Set search scope using kScopeCmdBoss. The scope can be current document, all open documents, or within current selection. Do not forget to explicitly set the IID\_IFINDCHANGEMODEDEDATA interface on the command bosses to IFindChangeOptions::kObjectSearch search mode.
4. Choose an object style to search and prepare an attribute boss list to store graphic attributes your resulting page item should have. Then, set the find object style and find attribute list using kFindChangeFormatCmdBoss.
5. Choose an object style to replace, and prepare an attribute boss list to store graphic attributes your resulting page item should have. Then, set the change object style and change attribute list using kFindChangeFormatCmdBoss. You may combine this step with the previous step if the command is processed only once.
6. Perform a search by creating kFindChangeServiceBoss. Depending on what you want to do with the found object(s), call IFindChangeService::ReplaceObject(), ReplaceAndSearchObject(), or ReplaceAllObject().

### Sample Code

```
SnpFindAndReplace::Do_ReplaceObject
```

## Related APIs

- IFindChangeOptions on kWorkspaceBoss maintains all find/change options.
- IFindChangeService on kFindChangeServiceBoss provides find/change object services.
- Commands: kFindSearchModeCmdBoss, kScopeCmdBoss, kFindChangeFormatCmdBoss, kReplaceObjectCmdBoss, kReplaceFindObjectCmdBoss, and kReplaceAllObjectCmdBoss.

---

# Guides and Grids

## Acquiring a Reference to a Ruler Guide

### Solution

A ruler (kGuideItemBoss) is characterized by the IGuideData interface. A UIDRef that can instantiate an IGuideData interface is a ruler guide.

Follow these steps:

1. Acquire a reference to the spread containing the ruler guides (see “[Acquiring a Reference to a Spread](#)” on page 16). If you are starting from a page (kPageBoss), find the spread that owns the page, then examine the spread layers that store guides as described below
2. To get the guide spread layers, call ISpread::QueryLayer with wantGuideLayer set to kTrue.
3. Examine the child objects on the spread layer’s IHierarchy. These are ruler guides

### Sample Code

SnpInspectLayoutModel

### Related API

kGuideItemBoss

## Creating a Ruler Guide

### Solution

Use kNewGuideCmdBoss.

Ruler guide properties are given by the IGuideData interface on kGuideItemBoss. When you are creating a ruler guide, you specify the coordinates in their parent’s space, normally spread coordinate space.

## Sample Code

[Example 2](#) demonstrates how to create a vertical guide item on the first page of the active spread. For code simplicity, error checking is omitted.

### **EXAMPLE 2 Create a Vertical Ruler Guide**

```
InterfacePtr<ILayoutControlData> layoutData(Utils<ILayoutUtils>() ->QueryFrontLayoutData());
// Get the active document layer
InterfacePtr<IDocumentLayer> docLayer(layoutData->QueryActiveDocLayer());

InterfacePtr<ISpread> spread(layoutData->GetSpread(), IID_ISPREAD);
IDataBase* db = ::GetDataBase(spread);

// Get the guide spread layer for the active spread.
InterfacePtr<ISpreadLayer> spreadLayer(spread->QueryLayer(docLayer, nil, kTrue));

// The parent for the new guide is the guide spread layer.
UID parent = ::GetUID(spreadLayer);
UIDRef parentUIDRef(db, parent);

// Get the first page UID. ownerUID is a page for short guides.
UID ownerUID = spread->GetNthPageUID(0);

// Note: The parent for the guide we are to create is the spread. Each
// page owns its guides. We need to convert the guide coordinates
// to its parent space - spread space.

// Get the bounding box of the page in spread space.
InterfacePtr<IGeometry> geometry(db, ownerUID, IID_IGEOMETRY);
PBPMRect bBox = geometry->GetStrokeBoundingBox(::InnerToParentMatrix(geometry));

InterfacePtr< ICommand> newGuideCmd(CmdUtils::CreateCommand(kNewGuideCmdBoss)) ;

InterfacePtr<INewGuideCmdData> newGuideCmdData(newGuideCmd, IID_INEWGUIDECMDDATA) ;

// The distance the guide is located at.
PMReal distance = bBox.Left() + bBox.GetHCenter();

// Get the default guide preference
InterfacePtr<IGuidePrefs>
iGuideDefault((IGuidePrefs*)::QueryPreferences(IID_IGUIDEPREFERENCES,
kGetFrontmostPrefs));

// Get the guide threshold and the color index
PMReal guideThreshold = iGuideDefault->GetGuidesThreshold();
int32 guideColorIndex = iGuideDefault->GetGuidesColorIndex();

newGuideCmdData->Set(parentUIDRef, kFalse, distance, ownerUID, kTrue,
guideThreshold, guideColorIndex);
```

```
if (CmdUtils::ProcessCommand(newGuideCmd) != kSuccess)
// Report process command failure.
```

### Related APIs

- IGuideData
- IGuidePrefs
- kGuideItemBoss
- kNewGuideCmdBoss

## Deleting a Ruler Guide

### Solution

Use kDeleteCmdBoss.

## Moving a Ruler Guide

### Solution

To move the guide relative to its current position, use kMoveGuideRelativeCmdBoss.

To move the guide to an absolute position, use kMoveGuideAbsoluteCmdBoss.

### Related API

kGuideItemBoss

## Changing the Color, View Threshold, or Orientation of Ruler Guides

### Solution

To change the color of a ruler guide, process the command created by calling IGuideUtils::MakeChangeColorGuideCmd.

To change the view threshold of a ruler guide, use kSetGuideViewThresholdCmdBoss.

To change the horizontal or vertical orientation of a ruler guide, use kSetGuideOrientationCmdBoss.

### Related API

kGuideItemBoss

## Showing and Hiding Guides

### Solution

To show or hide all guides, use kSetGuidePrefsCmdBoss.

To show or hide ruler guides associated with a specific layer, use kShowGuideLayerCmdBoss.

### Related API

kGuideItemBoss

## Locking and Unlocking Guides

### Solution

To lock or unlock all guides, use kSetGuidePrefsCmdBoss.

To lock or unlock ruler guides associated with a specific layer, use kLockGuideLayerCmdBoss.

### Related API

kGuideItemBoss

## Turning Snap to Guides On and Off

### Solution

Use kSetSnapToPrefsCmdBoss.

### Related API

kGuideItemBoss

## Getting Notified of Guide and Grid Operations

### Solution

1. Determine the command that is making the change in which you are interested.
2. See the API documentation page for that command.
3. Attach an observer to the subject changed by that command.

### Related APIs

- IObserver
- ISubject

---

# Layout Windows and Layout Views

## Acquiring a Reference to a Layout Window

### Solution

If you have a reference to a document (kDocBoss), use IPresentationList on kDocBoss to get the windows (kLayoutPresentationBoss) open on a document (see “[Acquiring a Reference to a Document](#)” on page 11).

If you have an IActiveContext interface, use IActiveContext::GetContextView to get the layout view associated with the context. From there, code like that in [Example 3](#) gives the layout window:

**EXAMPLE 3 Navigating from Layout View to Layout Window via IWidgetParent**

```
// If you have a reference to a layout view (kLayoutWidgetBoss) the
// code below will find the associated layout window:
InterfacePtr<IWidgetParent> widgetParent(layoutView, UseDefaultIID());
InterfacePtr<IWindow> myWindow((IWindow*)widgetParent-
>QueryParentFor(IWindow::kDefaultIID));
```

To work with the window displaying the document the user is editing, use ILayoutUIUtils::QueryFrontView to get the layout view (kLayoutWidgetBoss) of the front document. See [Example 3](#) for the code that then gets the layout window.

To hit test for a layout window or iterate through windows on a document, use IDocumentUIUtils.

### Related API

kLayoutPresentationBoss

## Opening a Layout Window on a Document

### Solution

Use kOpenLayoutCmdBoss.

### Related Documentation

- “[Opening an Existing Document](#)” on page 13

### Sample Code

SDKLayoutHelper::OpenLayoutWindow

## Closing a Layout Window

### Solution

Use kCloseLayoutCmdBoss.

### Related Documentation

- “[Closing a Document](#)” on page 14

### Related API

kLayoutPresentationBoss

## Iterating through Open Layout Windows

### Solution

1. Use IDocumentList, to list the documents the application has open. See “[Iterating through Documents](#)” on page 14.
2. Use IPresentationList on each document, to list the windows open on it.

### Related API

kLayoutPresentationBoss

## Acquiring a Reference to a Layout View

### Solution

If you have an IActiveContext interface, use IActiveContext::GetContextMenu.

If you have a layout window (kLayoutPresentationBoss) reference, use IPanelControlData::FindWidget. Call with widgetId=kLayoutWidgetBoss to get the window’s layout view.

To work with the layout view that is editing the document, follow these steps:

1. Use ILayoutUIUtils::QueryFrontView to get the layout view of the front document.
2. Use ILayoutUIUtils::QueryFrontLayoutData to get the ILayoutControlData interface for the layout view of the front document.

### Related API

kLayoutWidgetBoss

## Setting the Spread Targeted for Edit Operations

### Solution

Use kSetSpreadCmdBoss.

### Sample Code

- BscDNDCustomFlavorHelper::ProcessDragDropCommand
- SnapTracker::CreateAndProcessSetSpreadCmd

### Related APIs

- ILayoutControlData::GetSpread
- IID\_ICURRENTSPREAD on kDocBoss

## Setting the Layer Targeted for Edit Operations

### Solution

Use kSetActiveLayerCmdBoss.

### Sample Code

SnpProcessCmds

### Related APIs

- ILayoutControlData::QueryActiveDocLayer
- ILayoutControlData::QueryActiveLayer returns the active spread layer (kSpreadLayerBoss).
- ILayerUtils::QueryDocumentActiveLayer

## Setting the Page viewed in a Layout Window

### Solution

1. Get the ILayoutControlData interface of the layout view (kLayoutWidgetBoss).
2. Process kSetPageCmdBoss.

**NOTE:** The page being viewed is not stored anywhere. It is calculated each time ILayoutControlData::GetPage is called, by finding the page whose center point is closest to the center of the view.

### Related APIs

- ILayoutControlData::GetPage
- ILayoutUIUtils::GetVisiblePageUID
- kLayoutWidgetBoss

## Fitting a Spread or Page in a Layout Window

### Solution

To fit a spread in a layout view, follow these steps:

1. Follow the steps described in “[Setting the Spread Targeted for Edit Operations](#)” on page 47.
2. Create a zoom command using ILayoutUIUtils::MakeZoomCmd with fit = ILayoutControlData::kFitSpread.
3. Run the zoom command.

To fit a page in a layout view, follow these steps:

1. Follow the steps described in “[Setting the Page viewed in a Layout Window](#)” on page 47.
2. Create a zoom command using ILayoutUIUtils::MakeZoomCmd with fit = ILayoutControlData::kFitPage.
3. Run the zoom command.

### Related APIs

- ILayoutControlData
- kLayoutWidgetBoss

## Setting the Zoom for the Layout Window

You can increase or decrease the magnification applied by the window.

### Solution

Process one of the zoom-related commands created by ILayoutUIUtils; for example, ILayoutUIUtils::MakeZoomCmd.

# Text

---

## Getting Started

This chapter presents table-related use cases. To learn about how text layout is organized, do the following:

- Run through the activities in “[Exploring Text with SnippetRunner](#)” on page 49, to learn how to explore text and familiarize yourself with fundamental text-Sample Code.
- Read the “Text Fundamentals” chapter in *Adobe InDesign® CS4 Programming Guide*.

To solve a text-related programming problem, do the following:

- Look in this document for a use case that matches your problem.
- As references, see the API reference documentation and the “Text Fundamentals” chapter mentioned above.

### Exploring Text with SnippetRunner

SnippetRunner is a plug-in that lets you run code snippets provided on the SDK. Several code snippets are provided that let you explore the text-related objects in a document.

#### Solution

1. Run InDesign with the SnippetRunner plug-in present. For instructions on using the plug-in, see the API documentation page for SnippetRunner.
2. Browse the sample code in the snippets you have been running.

#### Sample Code

- BscShpHandleShape::DrawLabelHandles in sample basic shape on the SDK
- CHMLFiltTextHelper in sample chmlfilter
- SingleLineComposer
- SnpApplyTextStyleAttributes
- SnpApplyTextStyleAttributes::ApplyFontVariant
- SnpCreateFrame
- SnpEstimateTextDepth
- SnpInsertGlyph
- SnpInspectFontMgr
- SnpInspectTextModel

- SnpInspectTextStyles
- SnpManipulateInline
- SnpManipulateTextFootnotes
- SnpManipulateTextModel
- SnpManipulateTextOnPath
- SnpManipulateTextStyle
- SnpManipulateTextFrame
- SnpManipulateTextPresentation
- SnpPerformCompFont
- SnpPerformFontGroupIterator
- SnpPerformTextAttr\*
- SnpTextAttrHelper

## Related APIs

- ICompositeFont represents a composite font.
- IDocFontMgr represents the persistent fonts in the session or document.
- IDocumentFontUsage provides a shell around IUsedFontList and IFontNames.
- HighLevelAPI::ITextWrapFacade provides functions to determine the word-wrap behavior a particular page item forces onto text.
- IFontFamily represents a group of related styles of fonts.
- IFontGroup (not derived from IPMUnknown) represents a font family within cooltype.
- IFontInstance (not derived from IPMUnknown) is an instance of a cooltype font, characterized by a particular font size.
- IFontMgr on the session that is the cooltype (font subsystem) wrapper.
- IFontNames allows access to the set of fonts on which a placed asset (PDF or EPS) depends
- IFrameContentSuite/IFrameContentFacade converts a page item to a container for text and manipulates the size of the page item relative to the text content.
- IFrameList provides a list of containers (frames) used to display the text from a single story.
- IHierarchy defines the relations of the containers within the document.
- IMissingFontSignalData provides the context for missing font responders.
- IMultiColumnTextFrame provides access to the associated story, frame list, and the range of text displayed.
- IParcel represents an area within a frame into which some sub-text for a story can flow; for example, a table cell or story footnote.
- IParcelList represents a set of parcels into which some sub-text for a story can flow; for example, footnotes that span multiple page items.

- IPMFont (not derived from IPMUnknown) represents a single font within cooltype.
- ITextAttrFont represents the text attribute defining the font applied to text.
- ITextAttributeSuite represents the capabilities and functionality that can be applied to the formatting of selected text.
- ITextFrameColumn represents a column within a text frame.
- ITextFrameOptionsSuite provides the ability to access and manipulate text frame options (like number of columns or gutter width) on the session workspace, document workspace, or a set of text containers.
- ITextModel represents a story within the document.
- ITextModelCmds provides prepackaged commands that modify a text story.
- ITextParcelList provides the relationship between the rendered text (known as the wax) in a parcel list and the parcel list.
- ITextSelectionSuite represents capabilities and functions that can be applied to selected text.
- ITextUtils provides higher level APIs to modify and access text content.
- IUsedFontList represents fonts used within text frames.
- IWaxStrand represents the final rendered text. It provides an iterator (IWaxStrand::NewWaxIterator) that allows the individual lines of rendered text (wax) to be accessed.

---

## Stories

A text story represents a single body of textual content within the application. It encompasses the raw text and formatting applied to this text; it can be viewed as a container for all this information. This section describes common use cases when working with text stories.

For more information see the “Text Fundamentals” chapter in *Adobe InDesign CS4 Programming Guide*.

### Accessing the Stories in a Document

A document can contain zero or more stories. You can access the set of stories contained in a single document.

#### Solution

A document is represented by the kDocBoss boss class.

IStoryList on kDocBoss maintains the stories contained within a document. A document can contain stories purely for internal use.

Use IStoryList::GetUserAccessibleStoryCount and IStoryList::GetNthUserAccessibleStoryUID to identify and access the user-accessible stories in a document.

Use `IStoryList::GetAllTextModelCount` and `IStoryList::GetNthTextModelUID` to access all stories in a document.

Use `IStoryList::GetNthTextModelAccess` to test whether a particular story is user accessible.

### Sample Code

```
SnpInspectTextModel::ReportStories
```

## Accessing the Stories under the Current Focus

You can get the story that maintains the current text focus.

### Solution

When dealing with a selection, you need to implement a selection extension pattern, which allows you to participate in the selection subsystem. As part of this extension pattern, you provide an add-in implementation of a concrete selection interface on the `kTextSuiteBoss` (and associated add-in implementation of an abstract selection interface on the `kIntegratorSuiteBoss`). For details on implementing this extension pattern, see the “Selection” chapter of *Adobe InDesign CS4 Products Programming Guide*.

Use `ISelectionUtils::GetActiveSelection` to obtain your abstract selection, which can then provide access to the concrete selection.

`ITextTarget` (on `kTextSuiteBoss`) resides on the same boss class as your selection.

Use `ITextTarget::QueryTextModel` to get the text model for the selection. This interface provides other information about the text selection, like its range.

To manipulate the model through the selection, add a new suite interface onto the `kTextSuiteBoss` class. This provides the mechanism required to keep actual selection types separate from the selection architecture. For an example, see the use of the interface `IDataUpdaterSuite` in the `XmlDataUpdater` plug-in.

## Accessing a Story, given a Page Item

You can get from a page item to (potentially) the text story representing the text it contains.

### Solution

Use `ITextUtils::GetSelectedTextItemsFromUIDList` on `kUtilsBoss` to extract text item entities from a list of UID items. Specifying a non-nil `UIDList` for either of the out parameters causes the associated `UIDList` to be populated with the set of page items containing text.

`IGraphicFrameData::GetTextContentUID` (the interface is on the page item) provides `kInvalidUID` if the page item is not a text container. This more direct approach is more effective if you are interested only in whether the page item contains text, rather than getting access to the text.

### Sample Code

```
SnpManipulateTextFrame
```

## Creating a Story

You can create a story programmatically.

### Solution

Stories are rarely created directly. Normally, they are created as a side effect of creating a text frame.

### Sample Code

SDKLayoutHelper::CreateTextFrame

### Related APIs

- The kNewStoryCmdBoss command creates a new story. It is unlikely you will have to use this command directly.
- The kCreateMultiColumnItemCmdBoss command creates a text frame (and the associated story).

## Deleting a Story

You can delete a story programmatically.

### Solution

Stories are rarely deleted directly. Normally, a story is deleted as a side effect of deleting the last text frame item that displays its text.

### Sample Code

SnpManipulateTextFrame::DeleteTextFrame

### Related API

kDeleteStoryCmdBoss deletes a text story. It is unlikely you will have to use this command directly.

## Detecting when Stories are Created

You can invoke your code on story creation.

### Solution

Implement a responder extension pattern. Specifically, a custom implementation of IResponder is required (indicating a service ID of kNewStorySignalResponderService). To implement the responder, use the CResponder helper implementation.

The extension pattern requires an implementation of IK2ServiceProvider. The API provides an implementation; the implementation ID is kNewStorySignalRespServiceImpl.

When the responder is called, query the ISignalMgr parameter for the INewStorySignalData interface. This interface provides access to the command that created the story and the underlying text model. Set the global error state from within the respond, to suppress story creation.

## Detecting when Stories are Deleted

You can get called when a story is deleted.

### Solution

Implement a responder extension pattern. Specifically, a custom implementation of IResponder is required (indicating a service ID of kDeleteStoryRespService). To implement the responder, use the CResponder helper implementation.

The extension pattern requires an implementation of IK2ServiceProvider. The API provides an implementation; the implementation ID being kDeleteStoryRespServiceImpl.

When the responder is called, query the ISignalMgr interface for the command (ICommand) invoked for the delete operation. Set the global error state, to suppress the story deletion.

## Navigating from the Story (Text Model) to a Strand

You can get from the text model (kTextStoryBoss, the main boss class that represents a story) to a particular strand. Strands are a low-level abstraction; there are higher level APIs that allow you to accomplish most tasks.

### Solution

You can get a particular strand from the text model (ITextModel) interface on the text story (kTextStoryBoss), using ITextModel::QueryStrand.

### Sample Code

- See SnpInspectTextModel::CountStoryOwnedItems for an example of moving from the story (kTextModelBoss) to the owned item strand (kOwnedItemStrandBoss).
- The SnpManipulateTextStyle::CreateParaStyle sample shows how to navigate from the story (kTextModelBoss) to the character (kParaAttrStrandBoss) and paragraph (kCharAttrStrandBoss) attribute strands.

### Related API

See IStrand, the signature interface for a story strand.

---

## Story Text

In many cases require working on the raw text in a story; for example, spell checking, find/replace, and word count. This section includes use cases that deal with purely the text of a story.

For details, see the “Text Fundamentals’ chapter of *Adobe InDesign CS4 Programming Guide*.

For related APIs, see the following:

- `ITextModel` on `kTextStoryBoss` is the signature interface for the story abstraction within the application.
- `IStoryList` on `kDocBoss` maintains all stories in the document.

### Accessing a Story’s Raw Text Content

You can access the raw content (the body of characters) of a text story.

#### Solution

Use text iterators to access the raw content of a story. For an example, see `SnpTextModelHelper::GetWideStringFromTextRange`.

The compose scanner (`IComposeScanner`) on the story (`kTextStoryBoss`) supports the `CopyText` method. For an example of its use, see `SnpManipulateTextFootnotes::GetStoryThreadContents`.

### Counting the Paragraphs in a Story

You can calculate the number of paragraphs in a story.

#### Solution

The `IComposeScanner` interface, available on `kTextStoryBoss`, has a method (`FindSurroundingParagraph`) that determines the extent of each paragraph in the story. It can be used to scan a story, counting the paragraphs.

You can use a similar technique with the low-level `IStrand` interface on the paragraph attribute stand (`kParaAttrStrandBoss`). For each paragraph, a run exists on the `IStrand` interface on the paragraph attribute strand (`kParaAttrStrandBoss`). The number of runs is equal to the number of paragraphs. Iterate using `IStrand::GetRunLength` on all runs in the strand.

#### Sample Code

`SnpInspectTextModel::ReportParagraphs`

## Counting the Words in a Story

You can calculate the number of words in a story.

### Solution

The IComposeScanner interface, available on kTextStoryBoss, has a method (FindSurroundingWord) that determine the extent of each word in the story. It can be used to scan across a story, counting the words.

## Inserting Text into a Story

You can insert text into a story, using text commands or via a text selection.

### Solution

If there is a valid text selection, use ITextEditSuite::InsertText (after testing ITextEditSuite::CanEditText to determine whether the operation is allowed).

To insert characters at an arbitrary position in a story, use the command generated by ITextModelCmds::InsertCmd. ITextModelCmds is available on the kTextStoryBoss. Use the ITextModel::IsModelLocked method to test whether a lock exists on the text model.

Put the inserted data into a reference counted K2::shared\_ptr with type WideString, and pass it into the InsertCmd, so the memory occupied by the data is purged when no one is referencing it. For more information, see K2SmartPtr.h.

### Sample Code

```
SnpManipulateTextModel::InsertText
```

## Deleting Text from a Story

You can delete a range of text from a story, using text commands or via a text selection.

### Solution

If there is a valid text selection, use ITextEditSuite::Delete to delete selected text (after testing ITextEditSuite::CanEditText to determine whether the operation is allowed).

To delete an arbitrary range of text, use the command generated by ITextModelCmds::DeleteCmd. ITextModelCmds is available on kTextStoryBoss.

Before performing the modification, check the model to ensure it is not locked (ITextModel::IsModelLocked).

### Sample Code

```
SnpManipulateTextModel::DeleteText
```

## Replacing Text in a Story

You can replace a range of text with alternative text.

### Solution

Use the command generated by ITextModelCmds::ReplaceCmd to replace text within a story.

Put the replaced data into a reference counted K2::shared\_ptr with type WideString, and pass it into the InsertCmd, so the memory occupied by the data is purged when no one is referencing it. For more information, see K2SmartPtr.h.

Before performing the modification, check the model to ensure it is not locked (ITextModel::IsModelLocked).

### Sample Code

```
SnpManipulateTextModel::ReplaceText
```

## Copying Text within and between Stories

You can programmatically copy text within or across text stories.

### Solution

To copy text within and between stories, use the command provided by the ITextUtils::QueryCopyStoryCommand utility facade. Variants of this API allow common use cases of text copy to be handled; for example, copying a range from source to a range in the destination and copying the complete source story to the end of the destination story.

To copy text within the same story, source and destination references should be the same. When specifying ranges for this operation, take care they do not overlap.

Before performing the modification, check the model to ensure it is not locked (ITextModel::IsModelLocked).

## Moving Text within and between Stories

You can programmatically move text within or across text stories.

### Solution

To move text within and between stories, use the command provided by the ITextUtils::QueryMoveStoryCommand utility facade. Variants of this API allow common use cases of text move to be handled; for example, moving a range from source to a range in the destination and moving the complete source story to the end of the destination story.

To move text within the same story, source and destination references should be the same. When specifying ranges for this operation, take care they do not overlap.

Before performing the modification, check the model to ensure it is not locked (ITextModel::IsModelLocked).

## Sample Code

SnpManipulateTextFootnotes::ConvertSelectionToFootnote shows how to move the contents of one story thread to another, which would be the case if you want to move text cell contents or footnotes.

## Iterating across Text Story Threads in a Story

Given a story comprises one or more text story threads, each of which represents a discrete subcomponent (like table cell text or a footnote), you may need to iterate or otherwise discover text story threads within a story.

### Solution

To be able to deal with distinct text units like table cell contents or footnotes, a hierarchy is built on top of the simple linear model maintained by the various strands. The nodes of this hierarchy are represented by text story thread dictionaries (ITextStoryThreadDict, maintained on boss classes representing the subcomponent, such as kFootnoteReferenceBoss). The root of the hierarchy is the primary story thread. (All stories have a primary story thread; see ITextModel::GetPrimaryStoryThreadSpan.). Story thread dictionaries maintain a mapping to a set of text story threads (ITextStoryThread). For example, the story thread dictionary for a table is on the table model (kTableModelBoss). It maintains the mapping to the actual text story threads for each cell (kTextCellContentBoss). The dictionary provides the mechanism required to iterate through all text story threads it manages.

The story (kTextModelBoss) models the inherent hierarchy using ITextStoryThreadDictHier. Using ITextStoryThreadDictHier::NextUID, you can access all story threads in the order in which they appear within the story.

With this background, the solution becomes apparent. For each text story thread dictionary obtained from ITextStoryThreadDictHier::NextUID, obtain the supported set of text story thread keys using ITextStoryThreadDict::GetFirstKey/GetNextKey before calling ITextStoryThreadDict::QueryThread.

## Sample Code

- SnpIterTableUseDictHier
- SnpInspectTextModel::InspectStoryThreadDicts

## Obtaining the Text Story Thread for the Current Selection

If you have a valid text selection, you can determine the text story thread that maintains the contents,

### Solution

When dealing with a selection, you need to implement a selection extension pattern, which allows you to participate in the selection subsystem. As part of this extension pattern, you provide an add-in implementation of a concrete selection interface on the kTextSuiteBoss (and associated add-in implementation of an abstract selection interface on the kIntegratorSuite-

Boss). For details on implementing this extension pattern, see the “Selection” chapter of *Adobe InDesign CS4 Products Programming Guide*.

Use `ISelectionUtils::GetActiveSelection` to obtain your abstract selection, which can then provide access to the concrete selection.

`ITextTarget` (on `kTextSuiteBoss`) resides on the same boss class as your concrete selection.

`ITextTarget::QueryTextModel` provides the text model for the current selection. This interface provides access to the text model as well as information on the range to which the selection applies.

Use `ITextModel::QueryStoryThread` along with the index provided by the `ITextTarget`, to obtain the text story thread.

## Inserting an Inline Graphic into a Story

You can insert an inline graphic into the story at a particular position.

### Solution

An inline graphic is represented within the text of a story using the special character `kTextChar_Inline`; known as the *anchor character*. This character indicates to the text subsystem that there is an inline item embedded at this position. The inline itself is represented on the owned item strand (`kOwnedItemStrandBoss`). The owned item strand maintains a (persistent/UID-based) reference to the actual inline item (`kInlineBoss`) through the `IItemStrand` interface.

Two actions are required to add an inline to a story:

- Add the anchor character to the story at the required text index. This is done using standard text content manipulation.
- Create and add the inline reference to the owned item strand, using the `kChangeILGCmd-Boss` command.

### Sample Code

`SnpManipulateInline::ChangeToInline`

## Modifying an Inline Object’s Position

### Solution

Positioning information for an inline object is maintained on the `IAncoredObjectData` interface for the inline. There are many options that define the placement of the inline relative to the anchor point within the text. You can modify the position of an inline using the `IAncoredObjectSuite` interface or the `kChangeAnchoredObjectDataCmdBoss` low level command.

### Sample Code

`SnpManipulateInline::ModifyAnchorPosition`

## Text

*Story Text*

## Deleting an Inline Object

### Solution

Delete the character that anchors the object into the story.

## Inserting a Footnote into a Story

You can create a footnote and insert it into an existing story.

### Solution

A footnote is maintained within the story as a special inline object. The character used in the story to indicate a footnote reference is kTextChar\_FootnoteMarker. The footnote is represented on the owned item strand by a reference to a kFootnoteReferenceBoss. The textual contents for the footnote reside in a distinct text story thread within the story.

Three actions are required to add a footnote to a story:

1. Add the anchor character to the story at the required text index. This is done using standard text content manipulation.
2. Create and add the footnote reference boss object to the owned item strand, using the kCreateFootnoteCmdBoss command.
3. After processing, the kCreateFootnoteCmdBoss command provides the text story thread (ITextStoryThread) for the newly created footnote in the IUIDData interface on the command boss object. Add text to this text story thread using standard text content manipulation.

### Sample Code

```
SnpManipulateTextFootnote::InsertFootnote
```

## Deleting a Footnote from a Story

### Solution

Delete the footnote's anchor character.

### Sample Code

```
SnpManipulateTextFootnote::DeleteAllStoryFootnotes
```

## Determining if a Text Range is within a Footnote

Given a range or selection within a text story, there are some operations that are invalid if that range is within a footnote. You can determine whether the range or selection is within the text of a footnote.

### Solution

Use `ISelectionUtils::QueryActiveTextSelectionSuite` on the `kUtilsBoss` to get the active text selection (`ITextSelectionSuite`).

`ITextSelectionSuite::IsTextSelectionInFootnote` indicates whether the selection is in a footnote.

To determine whether an arbitrary text range is within the text story thread of a footnote, use the `ITextUtils::IsFootnote` from the `kUtilsBoss` class. The API can be used to determine whether the range is within a footnote and to get the footnote reference (`kFootnoteReferenceBoss`) object through the parameter list.

## Determining if a Page Item can have Text along its Path

You can determine whether it is legal for a defined page item to have text along its path.

### Solution

A page item can have text flowed along its path if it has one path with at least one segment with at least two points (i.e., it cannot be a compound path or a single point). The page item cannot be an inline item.

### Sample Code

`SnpManipulateTextOnPath::CanAddTextOnPath`

## Determining if a Page Item has Text on its Path

### Solution

`IPageItemTypeUtils::IsTextOnAPath` on the `kUtilsBoss` has an API that returns true if the page item has text along its path.

## Adding Text along the Path of a Page Item

### Solution

Use the `kAddTextOnPathCmdBoss` API command to create the text model that supports the text on the path. This newly created text model is a candidate for traditional text content manipulation operations.

### Sample Code

`SnpManipulateTextOnPath::AddTextOnPath`

## Adding Text to Existing Text on a Path

### Solution

To navigate from a page item with associated text on its path, get the IMainTOPData interface from the spline object. You can get the text frame associated with the text on the path using IMainTOPData::QueryTOPFrameData. From the ITOPFrameData interface (on the kTOPFrameItemBoss object), you can get the ITextFrameColumn and call the QueryTextModel interface to get the text model interface. You can manipulate the text model using the mechanisms described above.

### Sample Code

```
SnpManipulateTextOnPath::InsertTextIntoTextOnPath
```

## Deleting the Text on a Path

### Solution

To delete the text on a path for a spline item, use the kTOPDeleteCmdBoss API command. Specify the spline to be processed on the item list.

### Sample Code

```
SnpManipulateTextOnPath::DeleteTextOnPath
```

## Inserting Page Numbering and Title Heading into a Story

### Solution

The text composition engine provided with the application automatically replaces special characters in the text stream with page numbering and/or section header text (the exact format defined by the preferences). For page numbering, insert the kTextChar\_PageNumber character into the text story. For headings, insert the kTextChar\_SectionName special character into the text model.

---

## Text Formatting

This document contains use cases related to formatting text and managing text styles within the application.

Text is formatted to give it a particular look, like underlined or in a particular font face. The desired look of text can be described by a set of attributes; for example, a point size or text color. Attributes are defined to be either character or paragraph based. Character attributes can be applied to text at any granularity, from a single character to the entire story. Paragraph attributes are settings that work at the granularity of a paragraph (for example, hyphenation behavior or horizontal justification).

Generally, attributes are grouped together to describe a common theme (for example, a heading or body text); these themes are called *styles*. Attributes also can be applied to text independently of any applied style. These attributes are said to be *overrides*, as they override the definition of that attribute in the style.

A style is a mechanism for identifying groups of attributes. In the application, character and paragraph styles are supported (along with table styles, which are not considered here). Character styles contain only character-based attributes. Paragraph styles can contain either character- or paragraph-based attributes. The style can be queried to determine its type (IStyleInfo::GetStyleType). All text has a character and paragraph style applied to it (represented on the character and paragraph attribute strands, respectively).

For more information, see the “Text Fundamentals” chapters of *Adobe InDesign CS4 Programming Guide*.

## Accessing the Set of Supported Styles

Styles can exist for all documents on a session or a particular document. They are accessed through the workspace and are modeled within the application using the persistent kStyleBoss. Session workspace styles are inherited into the document workspace (thus preventing the style not being available at a later date or on another machine).

You can access the set of styles available to a particular document.

### Solution

Styles can exist on either the session or document workspace. Session workspace styles are available for all documents; document workspace styles are available only for that document. The workspace boss classes support two implementations of the IStyleGroupManager interface, IID\_IPARASTYLEGROUPMANAGER for paragraph styles and IID\_ICHARSTYLEGROUPMANAGER for character styles. The interface provides the GetRootHierarchy() API, which returns a pointer to IStyleGroupHierarchy at the root level. Use IStyleGroupHierarchy to iterate across the supported styles.

### Sample Code

```
SnpInspectTextStyles::Inspect
```

## Accessing a Style using its Path

The IStyleGroupManager::FindByName(PMString fullPath) method returns the UID of a kStyleBoss in the style group hierarchy specified in the fullPath. The fullPath to pass into the method is the “internal” path name. Normally, you cannot construct an internal path name using a string literal, because the internal path uses a path delimiter that is not accessible by keyboard. This is necessary because a style name can include most of the common path delimiters (like “:” and “/”). A main reason for this is to provide backward compatibility for styles created before the style group concept was introduced in InDesign CS4. Previously, many users named styles with “:” to better organize their styles. Therefore, if you construct a PMString path with string literals and pass it into the IStyleGroupManager::FindByName(PMString full-

Path) method, you are asking IStyleGroupManager to find a style with the passed-in name at the root level. For example, if you pass “My Group:Style 1” (as PMString) into FindByName(), IStyleGroupManager still treats the whole string as the style name, not as the path (as you expect). This string literal is used to find the style with the name “My Group:Style 1” on the root level.

To use the IStyleGroupManager::FindByName(PMString fullPath) method, pass in a valid internal path for a style. To get the internal path, use the IStyleGroupHierarchy::GetFullPath() method. IStyleGroupHierarchy is aggregated on three bosses: kStyleGroupHierarchyBoss, kStyleGroupBoss, and kStyleBoss. This means to find a style by name using a internal full path, you need to have previously accessed the style or style group. For example, if you have a UID for a style, you can use the UID to query its IStyleGroupHierarchy and ask for its internal full path using GetFullPath(); later, you can use the path to find the style again.

### Solution

Use SnpApplyTextStyleAttributes::CreateParaStyle.

## Accessing a Style using its Name and Parent Style Group UID

As explained in “[Accessing a Style using its Path](#)” on page 63, there is no easy way to specify a path to find a style. IStyleGroupManager defines an overloaded FindByName(UID parent, const PMString& name), so if you have access to a style group UID and you know the name of style you are looking for, you can use this method to find the corresponding style. It returns the UID of the style whose name matches the passed name within the specified parent style group node.

### Solution

Use SnpApplyTextStyleAttributes::ApplyParaStyle.

## Determining a Style’s Type

You can determine the style a particular kStyleBoss represents.

### Solution

From the kStyleBoss, use the IStyleInfo::GetStyleType API.

## Determining a Style’s Parent Style

InDesign has the concept of a *root style*. All other styles inherit from the root style, maintaining within their definition only how they differ from their parent. For a particular style, you can determine its parent; i.e. the style on which it is based.

### Solution

IStyleInfo on kStyleBoss provides the API IStyleInfo::GetBasedOn. This provides either the parent style UID or kInvalidUID if the style is the root.

## Determining the Value of an Attribute within a Style

You can determine what a style means to a particular attribute; that is, what value for a particular attribute would be applied to text (as long as there are no local overrides).

### Solution

Since styles do not maintain a full set of attributes (they record only the differences from the style on which they are based), you can determine the setting for a particular attribute by obtaining the list of attributes supported by the style (ITextAttributes). Querying this interface for the particular attribute of interest (ITextAttributeList::QueryByClassID, say) returns either the attribute (if this style specifies it) or nil. In the latter case, the parent style needs to be interrogated to determine whether it specifies the attribute. Continue until the attribute is found.

For paragraph styles, the attribute is found at some point; the terminal case is the root style. For character styles, the root style is empty, deferring the attribute values to the paragraph style. In this case, if the attribute is not defined by any (parent) character style, the root paragraph style provides the value.

## Creating a New Style

You can create a new character or paragraph style.

### Solution

Use kCreateParaStyleCmdBoss or kCreateCharStyleCmdBoss. The item list for each of these commands identifies the workspace the style is to be added to (generally the session or document workspace). Beginning in InDesign CS4, a new Interface IStylePositionInfo is added to kCreateParaStyleCmdBoss and kCreateCharStyleCmdBoss. IStylePositionInfo allows the style to be created inside a style group, as explained in the “Text Fundamentals” chapter of *Adobe InDesign CS4 Programming Guide*. To create a style group, use kCreateStyleGroupCmdBoss.

### Sample Code

See SnpManipulateTextStyle::CreateParaStyle for an example of how to create a new paragraph style inside a style group. This sample provides its own implementation for generating a unique style name; however, the style utility interface on the utils boss class provides an API that provides this functionality (IStyleUtils::CreateUniqueName).

## Modifying an Existing Style

You can modify a style by either modifying the attributes the style represents or changing some aspect of the style, like its name.

### Solution

Changes to styles are handled through the kEditTextStyleCmdBoss command. The UIData interface on this boss class identifies the style being manipulated. The ITextAttributes interface identifies the list of attributes that will exist in the style after the command is processed (this is an absolute list, so to modify an existing attribute on the style, representing the attribute within

this list will update it in the style). The IStyleInfo interface defines the metadata (like style name), the style it is based on, and what the next style should be (for paragraph styles).

There are utility methods in IStyleUtils (on the UtilsBoss) that construct the kEditTextStyleCmdBoss commands. These methods allow the caller to determine sets of attributes that should be added or deleted from the style (rather than forcing them to define an absolute set that is left in the style once the command completes).

### **Related API**

IStyleUtils::CreateEditStyleCmd

## **Deleting a Style**

You can delete a style from a style name table. There are implications for text already formatted with the deleted style.

### **Solution**

Use the kDeleteParaStyleCmdBoss or kDeleteCharStyleCmdBoss command. The command boss supports IBoolData. Setting this interface indicates formatting should not be stripped from text using the style; the formatting is maintained by a set of local attribute overrides. The IUIDData interface (identified with the ID IID\_IREPLACEUIDDATA interface) allows an alternate style to be specified as a replacement style. The style to be deleted is identified through the IUIDData (default IID) interface. The item list identifies the workspace from which the style is deleted.

### **Sample Code**

SnpManipulateTextStyle::DeleteParaStyle

## **Applying a Style to Text**

You can apply a style to a range of text or the current selection.

### **Solution**

If you are dealing with a selection, use ISelectionUtils::QueryActiveTextSelectionSuite on the kUtilsBoss to get the active text selection (ITextSelectionSuite). The same boss class supports the ITextAttributeSuite interface.

Use ITextAttributeSuite::ApplyStyle to set the new style or revert the style back to the root style (in this case, with the option to leave the formatting intact as a set of attribute overrides).

To apply a style to an arbitrary range of text, use the command provided by ITextModelCmds::ApplyStyleCmd (the ITextModelCmds interface is available on the kTextStoryBoss class).

Before performing the modification, check the model to ensure it is not locked (ITextModel::IsModelLocked).

## Sample Code

See SnpApplyTextStyleAttributes::ApplyParaStyle for an example of using ITextAttributeSuite.

## Removing a Style from Text

You can remove a style from a text selection or an arbitrary text range.

### Solution

If you are dealing with a selection, use ISelectionUtils::QueryActiveTextSelectionSuite on the UtilsBoss to get the active text selection (ITextSelectionSuite). The same boss class supports the ITextAttributeSuite interface. This interface has the API ApplyStyle, which can be used to set the new style as the root style, in effect removing the style.

To remove a style from an arbitrary range of text, use the command provided by ITextModelCmds::UnapplyStyleCmd (the ITextModelCmds interface is available on the kTextStoryBoss class).

Before performing the modification, check the model to ensure it is not locked (ITextModel::IsModelLocked).

## Sample Code

See SnpApplyTextStyleAttributes::ApplyParaStyle for an example of using ITextAttributeSuite.

## Obtaining the Style of Text

You can determine the character or paragraph style for a particular text position (identified through a selection or arbitrary text index).

### Solution

If you have a selection, obtaining the text attribute suite interface (ITextAttributeSuite) from the text selection (ISelectionUtils::QueryActiveTextSelectionSuite) allows you to determine how many styles are in the selection (using ITextAttributeSuite::CountParagraphStyles and ITextAttributeSuite::CountCharacterStyles), and iterate through them (using ITextAttributeSuite::GetNthParagraphStyle and ITextAttributeSuite::GetNthCharacterStyle).

To get the style from an arbitrary position in the story, navigate to the appropriate strand—either the paragraph (kParaAttrStrandBoss) or character (kCharAttrStrandBoss) attribute strands. Obtain the IAttributeStrand interface, which supports the IAttributeStrand::GetStyleUID method, returning the style for a particular text position.

## Sample Code

See SnpManipulateTextStyle::UpdateParaStyle for an example of accessing the style at a given text index.

## Obtaining the Value of an Attribute applied to Text

You can access the single named attribute that applies to a text selection or a text index or range.

### Solution

If you have a selection, obtaining the text attribute suite interface (ITextAttributeSuite) from the same boss class as the text selection (ISelectionUtils::QueryActiveTextSelectionSuite) provides you with methods that expose the state of a particular attribute (see ITextAttributeSuite::FeatureState). For example, ITextAttributeSuite::GetCapsModeState indicates whether a certain mode applies to all the text, none of the text, or some of the text (if the attribute changes along the selection).

To determine whether there is an attribute override, use ITextAttributeSuite::CountAttributes, passing in the ClassID for the attribute of interest. An attribute is provided for each time the attribute value changes across the range of the selection. ITextAttributeSuite::QueryAttributeN provides the set of attributes that apply to the selection for a particular attribute class.

To get the attribute value from an arbitrary position in the story, use the IComposeScanner interface (on kTextStoryBoss). The method IComposeScanner::QueryAttributeAt provides the attribute that applies to the identified text index.

There is an iterator class (TextAttributeRunIterator) that allows the set of attributes that apply to a range of text to be accessed, dealing with the changes in attributes that can occur across ranges.

### Sample Code

- See SnpApplyTextStyleAttributes::CycleSmallAllCaps for an example.
- See SnpInspectTextModel::InspectStoryPointSizes for an example of using a TextAttributeRunIterator to access the attributes in a range of text.

## Modifying the Value of an Attribute for Text

You can modify an attribute applied to a text selection or text range.

### Solution

If you have a selection, obtaining the text attribute suite interface (ITextAttributeSuite) from the same boss class as the text selection (ISelectionUtils::QueryActiveTextSelectionSuite) provides you with methods that allow you to modify the format of the selection (for example, ITextAttributeSuite::ToggleItalic, or ITextAttributeSuite::IncrementPointSize). The suite also provides mechanisms for setting the value of attributes that have non-exotic data requirements. For example, use ITextAttributeSuite::SetInt16Attribute to specify that an override for an attribute of a particular type should be applied to the text, with a particular value. For attributes with more exotic data requirements, use ITextAttributeSuite::ApplyAttribute, though the onus for the creation of the attribute falls on the client.

Before manipulating the selection in this way, test that the operation is valid (ITextAttributeSuite::CanApplyAttributes).

To modify the attribute given an arbitrary range of text, use `ITextModelCmds` interface (on `kTextStoryBoss`), which provides a command through the `ITextModelCmds::ApplyCmd` API that modifies the attributes. This command expects a `K2::shared_ptr`. The `AttributeBossList` that defines the attributes to be applied should be allocated on the heap and wrapped in a `K2::shared_ptr`. This implements reference counting for the attribute list and automatically deletes it when it is no longer used.

It is important to apply attributes to the correct strand: paragraph attributes should be applied to the paragraph-attribute strand, and character attributes should be applied to the character-attribute strand. For example, it would make no sense to try to set the justification of text on the character-attribute strand, as justification is a paragraph attribute. Likewise, it would not make sense to set the point size of text on a paragraph strand.

Although you cannot apply character-attribute overrides directly to the paragraph-attribute strand, you can do so indirectly by defining a paragraph style with the character-attribute override defined, and applying this style to the paragraph-attribute strand.

Before performing the modification, check the model to ensure it is not locked (`ITextModel::IsModelLocked`).

### Sample Code

- See `SnpApplyTextStyleAttributes::ApplyFontVariant` for an example of using `ITextAttributeSuite::ApplyAttribute`.
- See `SnpTextModelHelper::ApplyOverrides` for an example of using `ITextModelCmds::ApplyCmd`.

## Clearing Attribute Overrides for Text

You can remove local formatting overrides for a text selection or text range (leaving the text formatted to the specification of whatever style is applied).

### Solution

If you have a selection, obtaining the text attribute suite interface (`ITextAttributeSuite`) from the same boss class as the text selection (`ISelectionUtils::QueryActiveTextSelectionSuite`) provides you with methods that allow you to remove character-attribute overrides (`ITextAttributeSuite::ClearCharacterOverrides`), paragraph-attribute overrides (`ITextAttributeSuite::ClearParagraphOverrides`), or both (`ITextAttributeSuite::ClearAllOverrides`).

Before removing the formatting information, test the capability using `ITextAttributeSuite::CanRemoveFormatting`.

To remove all the attributes that are overridden given an arbitrary range of text, use the `ITextModelCmds` interface (on `kTextStoryBoss`) which provides a command through the `ITextModelCmds::ClearOverridesCmd` API that removes all specified overrides for a particular strand. To specify all overrides, navigate to the stand of interest (`ITextModel::QueryStrand` on `kTextStoryBoss`), obtain the `IAttributeStrand` interface, and use `IAttributeStrand::GetLocalOverrides` to obtain a list of all attribute overrides that exist at a particular text index.

Before performing the modification, check the model to ensure it is not locked (ITextModel::IsModelLocked).

### Sample Code

See SnpTextModelHelper::ClearOverrides for an example of using ITextModelCmds::ClearOverridesCmd.

## Determining the Type of an Attribute

Paragraph attributes should be applied only to the paragraph-attribute strand; character attributes, to the character-attribute strand. You can determine the type of an attribute.

### Solution

The signature interface for an attribute boss class is IAttrReport. It supports a method, IsParagraphAttribute, that indicates whether the attribute is a paragraph attribute.

## Defining a Custom Text Attribute

Most attributes control some aspect of the final appearance of rendered text, like point size or font. The composition engines delivered with the application understand and interpret these attributes when rendering the text. You can add custom text attributes to the application using the text attribute extension pattern.

A text-adornment extension pattern can be used to decorate the text; it provides a hook into the drawing of the text. Custom text attributes are used to control the drawing behavior of the adornment for ranges of text.

Text attributes also can be used to give a range of text special meaning; that is, overlay use-specific information on the text story for ranges of characters. For example, imagine you want some text in a story to be variable and replaced with text from database records when doing a print run.

Sometimes, you want to add another attribute, something that can be applied to text to give the rendered appearance a specific effect. You need to add a custom attribute for this (in fact, you also need to define a custom composition engine, as there is no mechanism to direct the supplied composers to interpret custom attributes).

### Solution

Implement a custom text-attribute extension pattern. To do this, provide an implementation of the IAttrReport interface in a boss class. Further, if the attribute has some meaning for tagged text import/export, provide an implementation of IAttrImportExport.

### Sample Code

See the BasicTextAdornment sample from the SDK for an example of using a custom text attribute to control the behavior of a text adornment.

## Text Containers

Raw text content is presented to the user through a process known as *composition*. Raw text content is defined as the Unicode text along with some idea how it is to be displayed. The process of composition needs some notion of where to place the text. It works with *containers*, which are *parcels* into which the text can be placed. Several types of containers are supported:

- Text frames, like those created using the “Type Tool.”
- Text on the path of a spline (text on a path), such as you could create using the “Type on a Path Tool.”
- Text in a footnote.
- Text within a table cell (this is covered in the tables documentation).

A story (i.e., a discrete body of textual work) can be spread across multiple columns of a page element. The story can have embedded tables and footnote references, and it can be spread across several page elements (on different pages of the document).

This section presents use cases for interacting with text containers and controlling options that apply to them.

For more information, see *Adobe InDesign CS4 Programming Guide*.

### Creating a Text Frame

You can create a page item to hold text.

#### Solution

Use the kCreateMultiColumnItemCmdBoss command. To specify the characteristics of the new text item, use the IMultiColumnData and ICreateFrameData interfaces.

#### Sample Code

- SDKLayoutHelper::CreateTextFrame
- SnpCreateFrame::CreateTextFrame

### Converting a Page Item into a Text Frame

You can modify a page item so it can be a container for text.

#### Solution

Given a selection, follow these steps:

1. Obtain the IFrameContentSuite, using ISelectionUtils::QuerySuite on the kUtils boss class.
2. Check the capability by calling IFrameContentSuite::CanConvertItemToText

3. Use `IFrameContentSuite::ConvertItemToText` to convert selected items that are candidates for conversion.

Given an arbitrary set of page items, follow these steps:

1. Use `IFrameContentFacade::CanConvertItemToText` (an interface on the `kUtils` boss class) to test the capability
2. Use `IFrameContentFacade::ConvertItemToText` to convert items that are candidates for conversion.

### **Sample Code**

`SnpManipulateTextPresentation::ConvertToText`

## **Examining the Characteristics of a Text Frame**

### **Solution**

Given a selection, follow these steps:

1. Obtain the interface using `ISelectionUtils::QuerySuite` on the `kUtils` boss class.
2. Use `ITextFrameOptionsSuite::GetTextFrameOptionsData` to provide a reference to the `ITextFrameOptionsData` interface, which can be interrogated for the text frame options.

Given an arbitrary set of page items, do the following:

1. Navigate to the `kMultiColumnItemBoss` object (child of `kSplineItemBoss` via `IHierarchy`).
2. Use `ITextColumnSizer` to provide access to attributes of the frame (gutter width, inset, number of columns etc.).

### **Sample Code**

`SnpManipulateTextFrame::InspectTextFrame`

## **Modifying the Characteristics of a Text Frame**

### **Solution**

Given a selection, follow these steps:

1. Obtain the interface using `ISelectionUtils::QuerySuite` on the `kUtils` boss class.
2. Use `ITextFrameOptionsSuite::CanApplyTextFrameOptions` to test the capability to modify options on the selection.
3. Use `ITextFrameOptionsSuite::SetTextFrameOptionData` to manipulate the options on the frame. This API takes a reference to the `ITextFrameOptionsData` interface. The API provides a boss class (`kObjStylesTFOptionsCollectDataBoss`) that can be used to hold the text frame options for this API.

Given an arbitrary set of page items, there is no one way to manipulate text frame options. You can do the following:

- Change the number of columns with `kChangeNumberOfColumnsCmdBoss`.
- Manipulate the text inset with `kSetTextInsetCmdBoss`.
- Modify the column gutter with `kSetColumnGutterCmdBoss`.

### Sample Code

- `SnpManipulateTextFrame::IncrementTextInset`
- `SnpManipulateTextPresentation::IncrementFrameColumns`

## Deleting a Text Frame

### Solution

You delete page items holding text like any other page item. If the text is linked through other page items, it continues to exist (reflowing through linked items), and no text is deleted. If the text is contained only within the single page item, deleting the page item causes the associated text objects to be deleted.

To delete an arbitrary page item, use `kDeleteCmdBoss`.

### Sample Code

`SnpManipulateTextFrame::DeleteTextFrame`

## Detecting if a Page Element is a Text Frame

Arbitrary page items can contain text, and the relationship between container and text is maintained as an association between two sets of objects. You can determine whether a page item has this association.

### Solution

Call `IPageItemTypeUtils::IsTextFrame`.

### Sample Code

`SnpManipulateTextFrame::IsTextFrame` code snippet

## Navigating to the Text Frame for a Page Item

Suppose you have a reference to a page element (that could have been obtained through a selection, for instance). You can navigate to the associated text container object(s) for that page element, assuming they exist.

### Solution

1. Obtain the hierarchy (IHierarchy) interface from the page item object. The text container objects are maintained as part of the page item hierarchy.
2. Child 0 (zero) on the hierarchy is a column object (kMultiColumnItemBoss) that represents the set of text columns an individual page item can have.
3. With respect to the hierarchy (IHierarchy) on the multi-column object, each child is an individual frame (kFrameItemBoss), representing one column of text in the page item.
4. To get the parcel related to a particular frame, use the IParcel interface on the frame item boss object (kFrameItemBoss).
5. If you are interested in other parcels associated with the frame (for example, for a footnote), note the frame (kFrameItemBoss) object does not maintain the association. A list of all parcels used to display text for a particular story is provided through the frame list boss object (kFrameListBoss). You can obtain this interface from the frame item (kFrameItemBoss) using IParcel::QueryParcelList.

### Sample Code

SnpManipulateTextFrame::InspectTextFrame code snippet

## Navigating to the Text Frame for Text on a Path

Suppose you have a reference to a page element (that could have been obtained through a selection, for instance). You can navigate to the associated text container object(s) for text that might appear on the item's path.

### Solution

1. Obtain the hierarchy (IHierarchy) interface from the page item object (kTOPSplineItemBoss). The text container objects are maintained as part of the page item hierarchy.
2. Child 0 (zero) on the hierarchy is a column object (kMultiColumnItemBoss) that represents the set of text columns an individual page item can have.
3. With respect to the hierarchy (IHierarchy) on the multi-column object, there should be one frame item (kTOPFrameItemBoss) object.
4. To get the parcel related to a particular frame, use the IParcel interface on the frame item boss object (kFrameItemBoss).

## Sample Code

SnpManipulateTextFrame::InspectTextFrame code snippet

## Finding the Range of Characters displayed by a Text Frame

You can determine the range of the primary story thread displayed in a text frame. For details on accessing the raw text for a range, see “[Story Text](#)” on page 55.

### Solution

The text must be fully composed. Follow these steps:

1. Use IMultiColumnTextFrame::TextSpan to get the number of characters from the primary story thread that exist in the frame.
2. Use IMultiColumnTextFrame::TextStart to get the index within the primary story thread of the first character in the text frame.

The range is from the text start until the text start plus the text span. It may include the final terminating character of the primary story thread. The range of characters relates to all columns of text in the text frame. If the ITextFrame interface being queried is from a frame item (kFrameItemBoss), the range of characters relates to one column.

## Sample Code

SnpManipulateTextFrame::GetTextFrameTextRange

## Finding the Page Item that displays a given TextIndex

You can get the text frame (kFrameItemBoss) for a given text index within a story.

### Solution

The text must be fully composed. Follow these steps:

1. Use ITextModel::QueryFrameList to get the frame list (IFrameList) on the frame list boss object (kFrameListBoss).
2. Use IFrameList::QueryFrameContaining to get the text frame (ITextFrameColumn) for the frame boss object (kFrameItemBoss).
3. Use IHierarchy::QueryParent to get the multi-column frame item (kMultiColumnItemBoss). Use the equivalent call on the multi-column item to get the page item (kSplineItemBoss).

**NOTE:** The index need not belong to the primary story thread; it could reference text within another story thread, like a table cell or footnote.

## Sample Code

SnpManipulateTextFrame::QueryTextFrameContaining

## Finding the Story associated with a Parcel

Given a parcel (IParcel), you can determine the story with which it is associated.

### Solution

The text must be fully composed. Follow these steps:

1. Use IParcel::QueryFrame on the parcel object to get the text frame interface (ITextFrameColumn) on the text frame boss object (kFrameItemBoss) with which the parcel is associated.
2. Use ITextFrameColumn ::QueryTextModel to get the text model for the text that flows in the text frame.

Alternatively, navigate using the text parcel list (ITextParcelList), as follows:

1. Use IParcel::QueryParcelList on the parcel object to get the parcel list (IParcelList) that maintains the relationship for associated parcels.
2. Use ITextParcelList::GetTextModelRef to get the UIDRef for the text model (kTextModelRef) associated with the parcel. ITextParcelList is on the same boss object as the IParcelList interface.

### Sample Code

`SnpEstimateTextDepth::GetParcelTextRange` code snippet

## Finding the Range of Text displayed by a Parcel

You can determine the range of a particular text story displayed in a particular parcel (IParcel).

### Solution

The text must be fully composed. Follow these steps:

1. Use IParcel::GetParcelKey to obtain the parcel key.
2. Use IParcel::QueryParcelList on the parcel object to get the parcel list (IParcelList) that maintains the relationship between text story threads and associated parcels.
3. Get the text parcel list interface (ITextParcelList) from the same boss object.
4. ITextParcelList::GetTextRange returns the range of text in the specified parcel.

### Sample Code

- `SnpTextModelHelper::GetParcelTextRange` code snippet
- `SnpTextModelHelper::GetWideStringFromParcel` code snippet

For details on accessing the raw text for a particular range, see “[Story Text](#)” on page 55.

## Finding the Parcel that displays a TextIndex

Given a particular text story (ITextModel), you can find the parcel (IParcel) into which the text from a particular index in the text model is composed.

### Solution

The text must be fully composed. Follow these steps:

1. Use ITextModel::QueryTextParcelList to get the text parcel list (ITextParcelList).
2. ITextParcelList::GetParcelContaining returns the key for the parcel you need.
3. Get the parcel list interface (IParcelList) from the same boss object as ITextParcelList.
4. IParcelList::GetParcelContaining returns the required parcel (IParcel).


### Sample Code

SnpTextModelHelper::QueryParcelContaining code snippet

## Detecting Overset Stories

Figure 1 shows a story that is *overset*: the combined area of all linked frames associated with the story is not large enough to contain the text in the story. The figure shows a story associated with two linked frames. Both frames are overset, as is the story. You can determine whether a story is overset.

**FIGURE 1** An Overset Story with Two Frames



## Solution

The text must be fully composed. Follow these steps:

1. Navigate to the frame list boss (kFrameListBoss), in one of two ways. If dealing with a page item, you can use IHierarchy::QueryChild, then IMultiColumnTextFrame::QueryFrameList from the multi-column boss object (kMultiColumnItemBoss). If dealing with a text story (kTextStoryBoss), you can use ITextModel::QueryFrameList.
2. Use ITextUtils::IsOverset (the interface is available on the kUtilsBoss) to determine whether all the text is represented in a parcel. If only the final (required) carriage return is overset, the text is not defined to be overset.

## Sample Code

SnpEstimateTextDepth::IsStoryOverset code snippet

## Detecting Overset Text Frames

[Figure 1](#) shows two linked text frames associated with a story. Both are said to be overset, as the text in the story overruns each frame. You can determine whether a text frame is overset.

## Solution

If the frame has a span of 0 (zero), it is underset (i.e., no characters flow into it from a preceding frame). If the final character of the primary story thread, not including the mandatory carriage return, does not exist in the frame, it is overset.

The text must be fully composed. Follow these steps:

1. Use IMultiColumnTextFrame::TextSpan to get number of characters in the frame. If this is 0 (zero), the frame is underset.
2. Use IMultiColumnTextFrame::TextStart to get the starting character for the primary story thread within the frame. Add the text span to get the primary story thread index for the last character displayed in the text frame.
3. Use IMultiColumnTextFrame::QueryTextModel to get the text model (ITextModel) interface on the text story (kTextStoryBoss).
4. Use ITextModel::GetPrimaryStoryThreadSpan to get the number of characters in the primary story thread. If this number is greater than the index of the last character in the frame (calculated above), the text frame is overset.

## Sample Code

SnpEstimateTextDepth::IsTextFrameOverset code snippet

## Detecting Overset Parcels

You can determine whether the characters in a particular story thread extend beyond a particular parcel (IParcel).

### Solution

If the parcel has a span of 0 (zero), it is underset (i.e., no characters flow into it from a preceding parcel). If the final character of the primary story thread, not including the mandatory carriage return, does not exist in the parcel, it is overset.

This solution depends on the text being fully composed.

To detect if a parcel is overset, follow these steps:

1. Use IParcel::GetParcelKey to obtain the parcel key.
2. Use IParcel::QueryParcelList on the parcel object to get the parcel list (IParcelList) that maintains the relationship between text story threads and associated parcels.
3. Get the text parcel list interface (ITextParcelList) from the same boss object.
4. Use ITextParcelList::IsEmpty to determine whether the parcel is empty. If so, it is underset.
5. Use ITextParcelList::QueryStoryThread to get the story thread (ITextStoryThread) that represents the text in the parcel list.
6. Use ITextStoryThread::GetTextSpan to get the number of characters in the text story thread that is composed into this particular parcel list.
7. Use ITextParcelList::GetParcelContaining to access the parcel key that contains the final character for the text story thread. If this parcel key differs from the parcel key obtained above, the parcel is overset.

### Sample Code

SnpEstimateTextDepth::IsParcelOverset code snippet

## Determining if Text is “On a Path” (TOP)

Given a particular index, you can determine whether the composed text referred to by the index falls on a spline (rather than within a standard text frame (kFrameItemBoss)).

### Solution

The text must be fully composed. Follow these steps:

1. Obtain the frame item (in this case a kTOPFrameItemBoss) for the index as you would any other frame item. See [“Finding the Page Item that displays a given TextIndex” on page 75](#).
2. Test the frame item for the signature interface, ITOPFrameData.

## Threading Text Frames

Given two text containers (IMultiColumnTextFrame), you can link them to allow one story to be associated with both.

### Solution

Use ITextUtils::LinkTextFrames to link the two frames. If you need finer control over what happens with the text contained within the pre-existing text frames, first manipulate the text content in the required fashion (see “[Story Text](#) on page 55”), then use the kTextLinkCmdBoss to link the frames. This command requires the kMultiColumnItemBoss for both frames to be linked to be placed on the command’s item list.

### Sample Code

- SnpManipulateTextFrame::CanThreadTextFrames code snippet
- SnpManipulateTextFrame::ThreadTextFrames code snippet

## Unthreading Text Frames

Given two linked text frames (IMultiColumnTextFrame), you can unlink them.

### Solution

Use kTextUnlinkCmdBoss, passing in the frame the break is to occur after, on the command item list.

### Sample Code

- SnpManipulateTextFrame::CanUnlinkTextFrame code snippet
- SnpManipulateTextFrame::UnlinkTextFrames code snippet

## Navigating between Threaded Text Frames

Given a text frame (IMultiColumnTextFrame), you can navigate to the next frame through which the primary story thread flows.

### Solution

1. Use IMultiColumnTextFrame ::QueryFrameList to get the list of frames.
2. IFrameList::GetFrameIndex returns the index of the current frame in the list of frames.
3. Use IFrameList::GetFrameCount to get the total number of frames in the list.
4. Use IFrameList::QueryNthFrame to get a specified frame.

### Sample Code

SnpManipulateTextFrame::InspectFrameList code snippet

## Modifying Text Frame Options

A text frame has a set of associated options that describe how the text flows within the container, including the following:

- Number of columns.
- Column width.
- Gutter (space between columns) width.


You can modify the options for a text frame.

### Solution

To change the frame options for the current selection, use the `ITextFrameOptionsSuite` suite. For example, to increment the number of columns, follow these steps:

1. Use `ISelectionUtils::QuerySuite` (on the `kUtilsBoss` class) to get the text frame options suite interface (`ITextFrameOptionsSuite`).
2. Use `ITextFrameOptionsSuite::GetColumnsAndGutter` to get the number of existing columns.
3. Use `ITextFrameOptionsSuite::CanApplyTextFrameOptions` to test the ability to modify the frame options.
4. This suite uses a data object to maintain the collection of options available for text frame. The API provides an implementation that can be used (see `ITextFrameOptionsData` interface available on `kObjStylesTFOptionsCollectDataBoss`). Create this boss object, and set the required state.
5. Use `ITextFrameOptionsSuite::SetTFOColumns` to apply the new columns value defined in the data object to the selection.

To change the frame options for an arbitrary text frame (`IMultiColumnTextFrame` on `kMultiColumnItemBoss`), use API-supplied commands. See [Figure 2](#).

**FIGURE 2** Commands that Mutate Text Frame Options

### Sample Code

- See the `SnpManipulateTextFrame::IncrementNumberOfColumns` code snippet for an example of using lower-level commands to modify text-frame options.

## Modifying the Default Text Frame Options

### Description

A text frame has a set of associated options that describe how the text flows within the container. These options exist on the workspace (the session workspace, which is inherited by new documents on the document workspace). They include the following:

- Number of columns.
- Column width.
- Gutter (space between columns) width.

You can modify the default options for a text frame.


## Solution

Use the `ITextFrameOptionsSuite` suite. For example, to increment the number of columns, follow these steps:

1. Use `ISelectionUtils::QuerySuite` (on the `kUtilsBoss` class) to get the text frame options suite interface (`ITextFrameOptionsSuite`). With no open document, the suite applies to the session workspace defaults. With a document open and no selection, the suite applies to the document workspace defaults.
2. Use `ITextFrameOptionsSuite::GetColumnsAndGutter` to get the number of existing columns.
3. Use `ITextFrameOptionsSuite::CanApplyTextFrameOptions` to test the ability to modify the frame options.
4. This suite uses a data object to maintain the collection of options available for text frame. The API provides an implementation that can be used (see `ITextFrameOptionsData` interface available on `kObjStylesTFOptionsCollectDataBoss`). Create this boss object, and set the required state.
5. Use `ITextFrameOptionsSuite::SetTFOColumns` to apply the new columns value defined in the data object to the selection.

Alternatively, to modify the default settings regardless of whether a document is open (for example, to target a particular document or the session default value rather than the front-most document default value), use `kSetFramePrefsCmdBoss`. See [Figure 3](#), which shows the relationships between workspaces and text-frame options.

**FIGURE 3** *Commands that Mutate and Use Default Text-Frame Options*



## Sample Code

See the SnpManipulateTextPresentation::IncrementFrameColumns code snippet for an example of using the ITextFrameOptionsSuite suite interface to manipulate default text-frame options.

## Manipulating Text Wrap

A page item can define a relationship with text. This relationship specifies what happens when a text frame overlaps the page item, and it affects line-wrapping behavior. The behavior that can be specified includes the following:

- Wrapping text around the page item bounding box.
- Wrapping text around the spline shape.
- Flowing text only where the frame and bounding box (or spline shape) of the page item intersect.

You can prescribe the wrapping behavior a page item can enforce on text it overlaps.

## Solution

Use HighLevelAPI::ITextWrapFacade to control text-wrapping behavior.

Sometimes, you may need to use lower-level API commands such as the following:

- kStandOffModeCmdBoss
- kStandOffFormCmdBoss
- kStandOffMarginCmdBoss

## Sample Code

SnpManipulateTextFrame::ChangeTextWrapMode code snippet

---

## Rendered Text

This section contains common use cases related to rendered text. The set of glyphs that make up rendered text is called the *wax*.

## Getting Notified of Composition Completion

You can when text is composed.

## Solution

On completion of composition within a text frame, the message kRecomposeBoss is transmitted along the IID\_IFRAMECOMPOSER protocol to the frame item(kFrameItemBoss), spread (kSpreadBoss), and document (kDocBoss). To be notified of composition completion, attach

an observer to one of these objects. Which object you attach to depends on whether you want to restrict the notifications to a single spread or page item.

## Iterating the Wax for a Story

The SnpInspectTextModel::ReportWaxLineLeading SDK snippet iterates over each wax line and reports the leading for all lines of text in a story.

You must keep your IWaxIterator in scope, to keep an IWaxLine interface pointer valid. The following sample code demonstrates a common error caused when IWaxIterator is not kept in scope:

```
static IWaxLine* QueryWaxLineContaining(
    IWaxStrand* waxStrand, const TextIndex& textIndex)
{
    IWaxLine* line = nil;
    do{
        K2::scoped_ptr<IWaxIterator> waxIterator =
        waxIterator(waxStrand->NewWaxIterator());
        if (waxIterator == nil)
            break;
        IWaxLine* waxLine = waxIterator->GetFirstWaxLine(textIndex) ;
        if (waxLine == nil)
            break;
        line = waxLine;
        line->AddRef();
        // associated IWaxLine no longer valid when IWaxIterator is destructed.
    } while(false);
    return line; // Not a valid IWaxLine
}
```

To maintain references to several wax lines simultaneously, keep a wax iterator in scope for each wax line. The sample code discussed in “[Estimating the Composed Depth of Text in a Frame or Parcel](#)” on page 86 demonstrates this.

## Creating Wax Lines and Wax Runs

Wax lines and wax runs are created by a paragraph composer. The SingleLineComposer SDK sample is a paragraph composer that works on one line at a time. This sample demonstrate the construction of wax lines and wax runs.

## Finding the Wax displayed for a Range of Text

You can access the wax for a particular range of text.

### Solution

The text must be fully composed. Follow these steps:

1. Navigate to the frame list boss (kFrameListBoss), in one of two ways. If dealing with a page item, use IHierarchy::QueryChild, then IMultiColumnTextFrame ::QueryFrameList from the multi-column boss object (kMultiColumnItemBoss). If dealing with a text story (kTextStoryBoss), use ITextModel::QueryFrameList.
2. Obtain the wax strand (IWaxStrand) from the same boss object.
3. Use IWaxStrand::NewWaxIterator to get an iterator for the composed wax.
4. IWaxStrand::GetFirstWaxLine (IWaxStrand::GetNextWaxLine) returns a wax line (IWaxLine on kWaxLineBoss).

### Sample Code

SnpEstimateTextDepth code snippet

## Estimating the Composed Depth of Text in a Frame or Parcel

You can estimate the depth of text in a text frame (kFrameItemBoss).

### Solution

The text must be fully composed. Follow these steps:

1. Navigate to the frame list boss (kFrameListBoss), in one of two ways. If dealing with a page item, use IHierarchy::QueryChild, then IMultiColumnTextFrame::QueryFrameList from the multi-column boss object (kMultiColumnItemBoss). If dealing with a text story (kTextStoryBoss), use ITextModel::QueryFrameList.
2. Obtain the wax strand (IWaxStrand) from the same boss object.
3. Use IWaxStrand::NewWaxIterator to get an iterator for the composed wax. It takes an index into the wax; determine the start character index and end character index for the range of text you want to estimate. Create an iterator for each of these.
4. Use IWaxStrand::GetFirstWaxLine to get the wax line (IWaxLine on kWaxLineBoss) for each iterator. You now have the wax line (IWaxLine) relating to the first and last lines in the frame/parcel.
5. Use IWaxLine::GetYPosition to get the y position for the wax line. For horizontal text, the depth of the text in a frame can be roughly estimated as the y position of the last line of wax in the frame, minus the y position of the first line, plus the leading for the first line.

## Sample Code

SnpEstimateTextDepth code snippet

---

# Text Composition

## The Need to Recompose Text in a Story

Normally, damaged text that requires recomposition is fixed by background composition. Your code, however, may find the text in which it is interested is damaged; if so, it can force recomposition to fix the damage. For example, always check for damage before scanning the wax or relying on any spans that indicate the range of text stored in a frame or parcel.

## Recomposing Text

You can recompose text within a story by either the index into the text model (`TextIndex`) or the visual container used to display the text (a frame or parcel). The most general approach is to use the parcel list composer (`ITextParcelListComposer`), which works for any text that can be composed. For example, it works whether the text is displayed in a frame or a table cell.

Do not assume all text in the text model can be composed. Some features may store text in the text model that is never composed for display. See `HidTxtParcelListComposer.cpp` in the `HiddenText` example.

[Example 4](#) through [Example 7](#) show the most common approaches used to force text to be recomposed.

### **EXAMPLE 4 Recomposing Story Text by TextIndex using ITextParcelListComposer**

```
// Recompose text up to a given TextIndex. By using the parcel list
// composer, you can compose text that is displayed in frames, tables, or
// any other feature that supports text composition.
static void MyRecomposeThruTextIndex(ITextModel* textModel, TextIndex at)
{
    if (at >= 0 && at < textModel->TotalLength()) {
        InterfacePtr<ITextParcelList> tpl(textModel->QueryTextParcelList(at));
        InterfacePtr<ITextParcelListComposer> tpls(tpl, UseDefaultIID());
        if (tpls) {
            tpls->RecomposeThruTextIndex(at);
        }
    }
}
```

**EXAMPLE 5 Recomposing by Parcel using ITextParcelListComposer**

```
// Recompose text in the given parcel and preceding damaged parcels.
static void MyRecomposeThruParcel(IParcel* parcel)
{
    InterfacePtr<IParcelList> pl(parcel->QueryParcelList());
    InterfacePtr<ITextParcelList> tpl(pl, UseDefaultIID());
    InterfacePtr<ITextParcelListComposer>tplc(tpl, UseDefaultIID());
    if (tplc)
    {
        const ParcelKey key = parcel->GetParcelKey();
        tplc->RecomposeThruNthParcel(pl->GetParcelIndex(key));
    }
}
```

**EXAMPLE 6 Recomposing Story Text by TextIndex using IFrameListComposer**

```
// Recompose text in the primary story thread up to a given TextIndex.
static void MyRecomposeThruTextIndexByFrameList(ITextModel* textModel, TextIndex at)
{
    if (at >= 0 && at < textModel->GetPrimaryStoryThreadSpan()) {
        InterfacePtr<IFrameList> frameList(textModel->QueryFrameList());
        InterfacePtr<IFrameListComposer> flc(frameList, UseDefaultIID());
        if (flc) {
            flc->RecomposeThruTextIndex(at);
        }
    }
}
```

**EXAMPLE 7 Recomposing by Text Frame using IFrameComposer**

```
// Recompose text in the given frame and preceding damaged frames.
static void MyRecomposeThruFrame(ITextFrameColumn* textFrame)
{
    InterfacePtr<IFrameComposer> fc(textFrame, UseDefaultIID());
    if (fc != nil) {
        fc->RecomposeThruThisFrame();
    }
}
```

## Recomposing all Stories in a Document

IGlobalRecompose provides methods that force all stories to recompose. The interface marks damage that forces recomposition, even though the stories have not changed. See [Example 8](#).

**EXAMPLE 8 Recompose all Stories in a Document**

```
static void MyRecomposeAllStories(IDocument* document)
{
    InterfacePtr<IGlobalRecompose> globalRecompose(document, UseDefaultIID());
    if (globalRecompose != nil) {
        globalRecompose->RecomposeAllStories();
        globalRecompose->ForceRecompositionToComplete();
```

```
}
```

## Getting Notified when Text is Recomposed

It is hard to observe recombination, because to do so, you need to maintain an observer on each frame (kFrameItemBoss). See “[Observing Changes that affect Text](#)” on page 89 for an alternative approach that relies on observing the cause rather than the effect.

## Observing Changes that affect Text

Because many types of changes affect text, observing changes quickly becomes complex; for example:

- Changes to the geometry of the text layout (such as resize and text inset) are observed using a document observer.
- Changes to character and text attributes are observed by attaching an observer to each text model of interest.
- Changes to text styles are observed by attaching observers to the style name tables in the workspace.

An optimal strategy is to be aware recombination has occurred and not try to observe everything that might happen.

Any change to text, attributes, styles, or layout that affects lines breaks causes damage. The change counter on the frame list (IFrameList::GetChangeCounter) is incremented any time something happens that requires recombination. No notification is broadcast when the change counter is incremented, so you cannot catch the change immediately. In general, though, immediate feedback is not needed; the fact that something changed in a way that affects text needs to be determined only at fixed times.

For example, export a story from InDesign to a copy-editor application. When the story is imported back into InDesign, you may want to tell the user about changes to the layout or text styling that were made through InDesign. To arrange this, cache the value of IFrameList::GetChangeCounter when you export the story. You can then compare this cached value to the actual value when the story is imported. To notify users when layout changes are made that affect text, check IFrameList::GetChangeCounter using an idle task.

## Controlling the Paragraph Composer used to Compose Text

In the “Text Fundamentals” chapter of *Adobe InDesign CS4 Programming Guide*, see the section on “Paragraph Composers” for information on how to control the paragraph composer used to compose text. Programmatically, set the kTextAttrComposerBoss paragraph attribute to reference the paragraph composer to be used.

## Scanning Text

If you require access to only the character code data of a story, the simplest API to use is the `TextIterator` class. There are many code snippets that show how it is used, including `SnpInspectTextModel::ReportCharacters`. If you do not want to process character by character, use `IComposeScanner` to access the characters in a story in larger chunks. For a fully functional example, see the `TextExportFilter` SDK plug-in.

To access styled runs of text, use `IComposeScanner`. For an example, see “[Estimating Text Width](#)” on page 90.

## Estimating Text Width

You can estimate of the width of a character string for a given horizontal font using `IFontInstance::MeasureWText`. Code in the `FrameLabel` SDK sample plug-in `FrmLblAdornment::GetPaintedBBox()` demonstrates how to do this.

To apply this estimate to a range of text in a story, use `IComposeScanner` to access runs of characters with the same drawing style. [Example 9](#) illustrates this.

### **EXAMPLE 9 EstimateTextWidth**

```
/** Returns estimated width of given text range by scanning text using
 * IComposeScanner, then estimating width using IFontInstance.
 * @param textModel text model to be scanned.
 * @param startingIndex of the first character to be measured.
 * @param span the number of characters to be measured.
 * @return total estimated width of a given text range.
 */
static PMReal EstimateTextWidth(
    ITextModel* textModel, const TextIndex& startingIndex, const int32& span)
{
    // Use the story's compose scanner to access the text.
    InterfacePtr<IComposeScanner> composeScanner(textModel, UseDefaultIID());
    ASSERT(composeScanner);
    if (!composeScanner) return PMReal(0.0);
    // Width of the given text range.
    PMReal totalWidth = ::ToPMReal(0.0);
    // Drawing style for the current run.
    InterfacePtr<IDrawingStyle> drawingStyle(nil);
    // Font for the current run.
    InterfacePtr<IFontInstance> fontInstance(nil);
    // Current index into the text model.
    TextIndex index = startingIndex;
    // Number of characters still to be processed
    int32 length = span;
    // Number of characters returned by the compose scanner.
    int32 chunkLength = 0;
    // Character buffer.
    WideString run;
```

```
// The compose scanner may not return all the text
// in one call. So call it in a loop.
while (length > 0) {
    // Drawing style for the next run.
    IDrawingStyle* nextDrawingStyle = nil;
    // Get a chunk of text.
    TextIterator iter = composeScanner->QueryDataAt(
        index, &nextDrawingStyle, &chunkLength);
    if (iter.IsNull() || chunkLength == 0) break; // no more text.
    ASSERT(nextDrawingStyle);
    if (!nextDrawingStyle) break;

    // If the drawing style changes measure the width of
    // buffered text and switch to the new style and font.
    if (nextDrawingStyle != drawingStyle) {
        if (run.CharCount() > 0) {
            totalWidth += EstimateStringWidth(run, fontInstance);
            run.Clear();
        }
        drawingStyle.reset(nextDrawingStyle);
        fontInstance.reset(drawingStyle->QueryFontInstance(kFalse)); // assume horizontal.
        ASSERT(fontInstance);
        if (!fontInstance) break;
    } // end drawing style change
    else {
        // No change to drawing style but we still need to release.
        nextDrawingStyle->Release();
        nextDrawingStyle = nil;
    }

    // Buffer the characters returned by the compose scanner.
    if (chunkLength < length) {
        // Add all the characters to the run
        iter.AppendToStringAndIncrement(&run, chunkLength);
    }
    else {
        // Add only the characters we want to the run.
        // The compose scanner may return more data than we need.
        iter.AppendToStringAndIncrement(&run, length);
    }

    // Prepare for next iteration
    index += chunkLength;
    length -= chunkLength;
} // end while

// Process any buffered text.
if (run.CharCount() > 0 && fontInstance != nil) {
    totalWidth += EstimateStringWidth(run, fontInstance);
}
return totalWidth;
} // end EstimateTextWidth
```

## Measuring Composed Width or Depth more Accurately

Have the text flow into a story with a layout (text frames), and compose it with whatever paragraph composer you want. You can then scan the wax generated to find the width and depth measurement you want. This is the only way you can account for the many properties that affect the composed text, such as the paragraph composer's line-breaking algorithm, hyphenation, and text-style changes like font, point size, and leading, as well as the effect of layout properties like text wrap and first baseline offset. The SnpEstimateTextDepth SDK code snippet provides an example of wax scanning.

It is much harder to estimate the width or depth of text without having the text of a story flow into a layout. In principle, you can use the scanner and drawing style (IComposeScanner and IDrawingStyle) to scan the text and apply your own line-breaking rules. This quickly becomes a sort of mini paragraph composer and requires some of the code in sample plug-ins like SingleLineComposer. Look at this sample's SLCTileComposer class for the kind of code you might use.

---

## Text Hyphenation

Hyphenation is a service provided to composition. A composition engine uses the set of hyphenation providers installed and registered with the application. Hyphenation providers are responsible for providing the set of hyphenations points that exist for a particular word. This is used by the composition engine to help define line-breaking policies. The hyphenation service can be controlled by a set of paragraph attributes. This section contains use cases for controlling the default application hyphenation service.

### Turning Off Hyphenation

For a particular paragraph, you can turn off hyphenation.

#### Solution

Hyphenation function is controlled on a per-paragraph basis, using the kTextAttrHyphenModeBoss (signature interface ITextAttrHyphenMode) paragraph-level text attribute.

While four "modes" are defined by the interface (off, manual, dictionary, and algorithm), the default supplied hyphenation service uses only manual and algorithm. In manual mode, only hard hyphens and discretionary hyphens (added to the text using "Insert Special Character") are used. For the algorithm mode, hyphenation behavior is determined by hard hyphens, discretionary hyphens, hyphenation points provided by the dictionary, and a sophisticated algorithm used to determine best hyphenation.

#### Related Documentation

- ["Modifying the Value of an Attribute for Text" on page 68](#)

## Sample Code

SnpHyphenation

# Specifying Hyphenation of Capitalized Words

With the default hyphenation service, you can control hyphenation of capitalized words.

## Solution

Use the kTextAttrHyphenCapBoss paragraph-level text attribute (interface ITextAttrBoolean). If this is turned off, capitalized words with discretionary hyphens are still hyphenated.

## Related Documentation

- [“Modifying the Value of an Attribute for Text” on page 68](#)

## Sample Code

SnpHyphenation

# Specifying Hyphenation of Last Word in a Paragraph

With the default hyphenation service, you can control hyphenation of the last word in a paragraph.

## Solution

Use the kTextAttrHyphenLastBoss paragraph-level text attribute (interface ITextAttrBoolean). If this is turned off, last words with discretionary hyphens are still hyphenated.

## Related Documentation

- [“Modifying the Value of an Attribute for Text” on page 68](#)

## Sample Code

SnpHyphenation

# Specifying the Minimum Number of Characters before a Hyphen

## Solution

Use the kTextAttrMinBeforeBoss paragraph-level attribute (interface ITextAttrInt16).

If there are discretionary hyphens before the first hyphenation point, they are ignored; that is, the word does not hyphenate at discretionary hyphens that occur before the minimum number of characters, as specified by this attribute.

## Related Documentation

- [“Modifying the Value of an Attribute for Text” on page 68](#)

**Sample Code**

SnpHyphenation

## Specifying the Minimum Number of Characters after a Hyphen

**Solution**

Use the kTextAttrMinAfterBoss paragraph-level attribute (interface ITextAttrInt16).

If there are discretionary hyphens after a hyphenation point, they are ignored; that is, the word does not hyphenate at discretionary hyphens that occur after the minimum number of characters, as specified by this attribute.

**Related Documentation**

- [“Modifying the Value of an Attribute for Text” on page 68](#)

**Sample Code**

SnpHyphenation

## Specifying the Minimum Length of a Candidate Word for Hyphenation

**Solution**

Use the kTextAttrShortestWordBoss (interface ITextAttrInt16) paragraph-level attribute.

If there are discretionary hyphens in a word whose length is less than that specified by this attribute, they are ignored; that is the word is never be a candidate for hyphenation).

**Related Documentation**

- [“Modifying the Value of an Attribute for Text” on page 68](#)

**Sample Code**

SnpHyphenation

## Specifying the Maximum Number of Consecutive Hyphens

You can define the maximum number of consecutive hyphens (the *ladder*) for text.

**Solution**

Use the kTextAttrHyphenLadderBoss paragraph-level attribute (interface ITextAttrInt16).

**Related Documentation**

- [“Modifying the Value of an Attribute for Text” on page 68](#)

## Sample Code

SnpHyphenation

## Specifying the Hyphenation Zone

The *hyphenation zone* dictates the minimum space required by the word that is the hyphenation target. If that space is not available (i.e., the previous word encroaches on this zone), no hyphenation is done, and the hyphenation candidate is moved to the next line. You can control this function.

### Solution

Use the kTextAttrHyphenZoneBoss paragraph-level attribute (interface ITextAttrRealNumber). This specifies the minimum width assigned to a candidate word before a hyphenation point (modulo any preceding whitespace), before the word is pushed to the next line.

### Related Documentation

- “[Modifying the Value of an Attribute for Text](#)” on page 68

## Sample Code

SnpHyphenation

## Specifying the Hyphenation Weight

The algorithm used by the composer (in conjunction with the hyphenation service) to determine the hyphenation policy for text is complex. The hyphenation weight is a heuristic input used to guide the number of resulting hyphens. You can control this function.

### Solution

Use the kTextAttrHyphenWeightBoss paragraph-level attribute (interface ITextAttrInt16).

### Related Documentation

- “[Modifying the Value of an Attribute for Text](#)” on page 68

## Sample Code

SnpHyphenation

## Marking Text Unbreakable

### Description

Text can be specified as *no break*; that is, the text is not to be considered as a candidate for hyphenation.

### Solution

Use the kTextAttrNoBreakBoss character-level attribute (interface ITextAttrBoolean).

### Related Documentation

- [“Modifying the Value of an Attribute for Text” on page 68](#)

### Sample Code

SnpHyphenation

---

## Fonts

### Iterating through available Fonts

You can determine all fonts available to the application through the font subsystem.

### Solution

The SnpInspectFontMgr::ReportAllFonts code snippet shows how to iterate through all fonts available to the application, by calling IFontMgr directly.

The SnpPerformFontGroupIterator code snippet shows how to implement a FontGroupIteratorCallBack (see IFontMgr.h) to iterate all fonts.

### Controlling the Set of Installed Fonts

You can restrict the set of available fonts to a predefined set.

### Solution

Controlling the set of installed fonts is an operating-system-wide issue that cannot be solved directly with InDesign APIs. InDesign APIs can be used to detect installed fonts (in both the system folder and application fonts folder). To manage fonts, use operating-system platform APIs.

## Finding a Font

You can obtain a particular, named font.

### Solution

The solution depends on what information you have that identifies the font. See the SnpInspectFontMgr code snippet for several approaches, such as SnpInspectFontMgr::QueryFont.

Alternatively, implement a FontGroupIteratorCallBack (see SnpPerformFontGroupIterator.cpp) that finds the name of a PostScript font, given the full name of the font as returned by IPMFont::AppendFullName. For example, if you search for Courier Bold, you get the name of the PostScript font Courier-Bold.

## Finding the Font used to Display a Story's Text

### Solution

Use the values of the kTextAttrFontUIDBoss and kTextAttrFontStyleBoss text attributes. The UID in kTextAttrFontUIDBoss's ITextAttrUID interface can be used to instantiate an IFontFamily object. The PMString in kTextAttrFontStyleBoss's ITextAttrFont interface gives you the stylistic variant (for example, Regular or Bold). From these, you can find the name of the font, as shown in [Example 10](#):

#### **EXAMPLE 10 Finding a Font Name from Text Attributes**

```
static PMString FindFontName(
    IDataBase* db,
    ITextAttrUID* fontUID,
    ITextAttrFont* fontStyle)
{
    InterfacePtr<IFontFamily> family(db, fontUID->GetUIDData(), UseDefaultIID());
    InterfacePtr<IPMFont> font(family->QueryFace(fontStyle->GetFontName()));
    PMString fontName;
    font->AppendFontName(fontName);
    return fontName;
}
```

Alternately, use IComposeScanner to get the drawing style (IDrawingStyle) at a particular index in the text model, as shown in [Example 11](#):

#### **EXAMPLE 11 Finding a Font Name from the Drawing Style**

```
InterfacePtr<IComposeScanner> scanner(textModel, UseDefaultIID());
IDrawingStyle* style = scanner->GetCompleteStyleAt(textIndex);
InterfacePtr<IPMFont> font(style->QueryFont());
```

## Changing the Font used to Display a Story's Text

You can change the font used for either text in a story or a style that can be applied to text in a story.

### Solution

To set the font used to display text in a story, override the `kTextAttrFontUIDBoss` and `kTextAttrFontStyleBoss` text attributes in the text model. For information on overriding text attributes, see the “Text Fundamentals” chapter in *Adobe InDesign CS4 Programming Guide*.

To set the font for a text style, add or change the value of the `kTextAttrFontUIDBoss` and `kTextAttrFontStyleBoss` text attributes in the style.

## Getting the Name of a Font from its UID

### Solution

Use the UID to instantiate an `IFontFamily` interface, and get the name from there. Typically, the UID of a font is obtained from the `kTextAttrFontUIDBoss` text attribute, `IDocFontMgr::GetFontGroupUID`, or `IDocumentFontUsage::GetNthUsedFontUID`.

## Obtaining the List of Fonts used in all Stories

You can get information on the present or missing fonts used for the text in a story (not including non-rendered text, like that used in the notes feature).

### Solution

`SnpInspectFontMgr::ListFontsInDocument` shows how to use `IUsedFontList` on `kDocBoss` to determine which fonts are in use in a document’s stories. `SnpInspectFontMgr::ReportDocumentFontUsage` shows how to use the simpler `IDocumentFontUsage` API (existing on `kDocBoss`), a higher-level facade over the fonts used in a document. This mechanism does not report the fonts used in text for features like notes (text that is not displayed as part of the story). To catch all fonts used in all text in a story, regardless of whether it is visible in an exported asset, use the solution in “[Finding the Font used to Display a Story’s Text](#)” on page 97.

## Obtaining the List of Fonts used in or referenced from Placed Assets

You can get font information from (EPS or PDF) assets placed in a document.

### Solution

`IFontNames` (on `kEPSItem` or `kPlacedPDFItemBoss`) holds the set of fonts required by or embedded in a particular placed asset. `SnpInspectFontMgr::TestAssetsForFonts` shows how to obtain font information for placed assets. `SnpInspectFontMgr::ReportDocumentFontUsage` shows how to use the simpler `IDocumentFontUsage` API (existing on `kDocBoss`, a higher-level facade over the fonts used in a document).

## Obtaining the List of Fonts persistent in a Document

The set of fonts that are persistent in a document do not need to match the fonts used. You can access all fonts that exist in the persistent document.

### Solution

Use IDocFontMgr (on session or document workspace) to access the fonts in the workspace. For the session workspace, this represents the set of default fonts. For the document workspace, this includes all fonts used in the document (text frames, text notes, etc.); however, it does not include fonts contained in placed assets.

## Determining Restrictions that Apply to Installed Fonts

Given a particular font, sometimes it is useful to detect any use restrictions that might apply.

### Solution

SnpInspectFontMgr::ReportFontsWithRestrictions shows how to determine any use restrictions a particular font (IPMFont) might have.

## Detecting Font Subsystem Changes

If the user modifies the fonts installed during an instance of the application, the cooltype font subsystem is updated. You can be called when the application detects the font subsystem was updated (e.g., a font was added or removed).

### Solution

Attach an observer to the session (obtained from GetExecutionContextSession()) using the IID\_IFONTMGR protocol, listening for the kFontSystemChangedMessage.

## Detecting Accesses to Unavailable Fonts

Your plug-in can be called when an attempt is made to access a nonexistent font.

### Solution

Missing font responder services (IResponder implementation with service ID kMissingFontSignalResponderService) are called whenever the application queries the font manager for an unavailable font. The responder has the opportunity to respond with an alternative font to use (by populating the IMissingFontSignalData::SetResult with a valid font).

Only one missing font responder can dictate the font-replacement policy.

## Dealing with Font Face Variants

A font face can be described using different names (for example, “Regular” or “Plain” for a plain font face, “Italic” or “Cursive” for an italic font face, and “Bold” or “Heavy” for a bold font face).

### Solution

ITextUtils has four methods that can help you deal with font face variants:

- ITextUtils::IsPlainStyleName
- ITextUtils::IsItalicStyleName
- ITextUtils::IsBoldStyleName
- ITextUtils::IsBoldItalicStyleName

These methods implement the naming heuristics that define alternative names for font faces.

Given a particular font family (IFontFamily), you can get the index that identifies the correct font face, using the API IFontFamily::CorrectVariantIndex.

---

## Find/Change Text

InDesign gives users more control over the parts of a document that can be searched and modified via the find/change dialog. Similarly, there are interfaces that allow you to work more effectively with find/change.

InDesign not only provides interfaces to find/change plain text, but also to find/change text using grep (Global Regular Expression Parser) strings, glyphs using glyph IDs, and objects using frame attributes. Find/change object are discussed in the “Layout Fundamentals” chapter of *Adobe InDesign CS4 Products Programming Guide*. This section contains use cases dealing with text, grep, and glyph search.

For more information, see the “Text Fundamentals” and “Layout Fundamentals” chapters of *Adobe InDesign CS4 Programming Guide*.

## Related APIs

- IFindChangeOptions on kWorkspaceBoss maintains all find/change options.
- IFindChangeService on kFindChangeServiceBoss provides find/change individual find/change service.
- Commands — kCaseSensitiveCmdBoss, kEntireWordCmdBoss, kFindChangeFormatCmdBoss, kFindChangeGlyphIDCmdBoss, kFindSearchModeCmdBoss, kFindStringCmdBoss, kIncludeFootnotesCmdBoss, kIncludeHiddenLayersCmdBoss, kIncludeLockedLayersForFindCmdBoss, kIncludeLockedStoriesForFindCmdBoss, kIncludeMasterPagesCmdBoss, kKanaSensitiveCmdBoss, kScopeCmdBoss, kReplaceAllTextCmdBoss

dBoss kReplaceFindTextCmdBoss, kReplaceStringCmdBoss, kTWReplaceTextCmdBoss,  
kWidthSensitiveCmdBoss

**NOTE:** Although we use the same command boss to set find/change options for different search mode, you must explicitly set the IID\_IFINDCHANGEMODEDATA interface on the command bosses to appropriate search mode. Otherwise, these commands will use default mode, which is kTextSearch, and result in unexpected behavior.

## Searching for Text Strings

### Solution

To set up options and perform search, follow these steps::

1. Set the search mode to IFindChangeOptions::kTextSearch using kFindSearchModeCmdBoss.
2. Set the string to find in IFindChangeOptions, using kFindStringCmdBoss.
3. Set the search scope using kScopeCmdBoss. The scope can be current document, all open documents, a story, or within a selection.
4. Set other options, such as Entire Word, Case Sensitive, Include Locked Layers, Include Locked Stories, Include Hidden Layers, Include Master Pages, and Include FootNotes (corresponding to check boxes in the find/change dialog), using their respective commands.
5. Optionally, specify that you are looking for text with certain text attributes, by using kFindChangeFormatCmdBoss.
6. Perform search by doing either of the following:
  - Create kFindTextCmdBoss, set up appropriate text walker, then process the command.
  - Create kFindChangeServiceBoss and call IFindChangeService::SearchText().

### Sample Code

SnpFindAndReplace::Do\_FindText

## Replacing Text Strings

### Solution

To set up options and perform search, follow these steps. The first several steps are the same as for searching text strings.

1. Set the search mode to IFindChangeOptions::kTextSearch using kFindSearchModeCmdBoss.
2. Set the string to find in IFindChangeOptions, using kFindStringCmdBoss.
3. Set the search scope using kScopeCmdBoss. The scope can be current document, all open documents, a story, or within a selection.

4. Set other options, such as Entire Word, Case Sensitive, Include Hidden Layers, Include Master Pages, and Include FootNotes (corresponding to check boxes in the find/change dialog), using their respective commands.
5. Set the replace string in IFindChangeOptions, using kReplaceStringCmdBoss.
6. Optionally, specify find/change text attributes, by using kFindChangeFormatCmdBoss.
7. Perform the replace text action specified by the replace mode. If you already did a successful search, you can choose among replace all text, replace and search text, and replace found text. If you did not do a successful search yet, the only choice available is replace all text. You can do either the following:
  - Create kReplaceAllTextCmdBoss, kReplaceFindTextCmdBoss, or kTWReplaceTextCmdBoss, depending on the replace mode, set up an appropriate text walker, then process the appropriate command.
  - Create kFindChangeServiceBoss and call IFindChangeService::ReplaceAllText(), ReplaceAndSearchText(), or ReplaceText().

### **Sample Code**

SnpFindAndReplace::Do\_ReplaceText

## **Searching Text using grep**

You can search text matching regular expressions specified by a grep string.

### **Solution**

Searching using grep has the same interfaces as regular searching, and the processes are almost identical. The only differences are as follows:

- The search mode should be set to IFindChangeOptions::kGrepSearch.
- The find string stores the grep string, not the text.

### **Sample Code**

See SnpFindAndReplace::Do\_FindText. For grep search, IFindChangeOptions::kGrepSearch is passed in.

## Replacing Text using grep

You can text matching regular expressions specified in a grep string with new string also specified in grep.

### Solution

Replacing text with grep has the same interfaces and commands as standard text replacement. The only differences are as follows:

- The search mode should be set to IFindChangeOptions::kGrepSearch.
- The find string stores the grep string, not the text.
- The replace string stores the grep string, not the text.

### Sample Code

See SnpFindAndReplace::Do\_ReplaceText. For grep find/change, IFindChangeOptions::kGrepSearch is passed in.

## Searching for a Glyph

### Solution

Like searching for text, searching for a glyph involves setting find/change options and then performing a search. Follow these steps:

1. Set the search mode to IFindChangeOptions::kGlyphSearch, using kFindSearchModeCmdBoss.
2. Set the glyph to find in IFindChangeOptions, using kFindChangeGlyphIDCmdBoss. Remember to set the IBoolData on the command boss to kTrue. This tells the command to set the find glyph ID.
3. Set the search scope, using kScopeCmdBoss. The scope can be current document, a story, or within a selection.
4. Set other options, such as Include Locked Layers, Include Locked Stories, Include Hidden Layers, Include Master Pages, and Include FootNotes, using their respective commands.
5. Perform a glyph search action. You can do either of the following:
  - Create kFindTextCmdBoss, set up an appropriate text walker, then process the appropriate command.
  - Create kFindChangeServiceBoss and call IFindChangeService::SearchText().

### Sample Code

SnpFindAndReplace::Do\_FindGlyph

## Replacing a Glyph

### Solution

The relationship between finding and replacing a glyph is similar to that between finding and replacing text. In addition to setting find options, we also need to specify change options. Follow these steps:

1. Set the search mode to IFindChangeOptions::kGlyphSearch, using kFindSearchModeCmdBoss.
2. Set the glyph to find in IFindChangeOptions, using kFindChangeGlyphIDCmdBoss. Remember forget to set the IBoolData on the command boss to kTrue. This instructs the command to set the find glyph ID.
3. Set the replace glyph in IFindChangeOptions, using the same kFindChangeGlyphIDCmdBoss. Remember to set the IBoolData on the command boss to kFalse. This instructs the command to set the change glyph ID.
4. Set the search scope, using kScopeCmdBoss. The scope can be current document, a story, or within current selection.
5. Set other options, such as Include Hidden Layers, Include Master Pages, and Include Foot-Notes, using their respective commands.
6. Perform the replace glyph action specified by the replace mode. If you already did a successful glyph search, you can choose among replace all find glyph, replace and search text, and replace found text. If you did not do a successful search yet, the only choice available is replace all text. You can do either of the following:
  - Create kReplaceAllTextCmdBoss, kReplaceFindTextCmdBoss, or kTWReplaceTextCmdBoss (depending on the replace mode), set up an appropriate text walker, then process the appropriate command.
  - Create kFindChangeServiceBoss and call IFindChangeService::ReplaceAllText(), ReplaceAndSearchText(), or ReplaceText().

### Sample Code

```
SnpFindAndReplace::Do_ReplaceGlyph
```

# Tables

---

## Getting Started

This chapter presents table-related use cases. To learn to program with tables, do the following:

- Read “[Exploring Tables with SnippetRunner](#)” on page 105, to familiarize yourself with available related sample code and documentation.
- Read the “Tables” chapter in *Adobe® InDesign CS4 Programming Guide*.
- Study the TableAttributes and TableBasics SDK samples.

For help with specific programming issues, see the sections below for a use case that matches your needs.

### Exploring Tables with SnippetRunner

SnippetRunner is a plug-in supplied by the SDK that lets you run code snippets, which can help you explore your use case.

Run InDesign with the SnippetRunner plug-in loaded. Use SnippetRunner to run the snippets listed below under “Sample Code.” See the “Snippets” section of the API reference documentation for more information regarding snippets and instructions on using SnippetRunner itself. Browse the source code of the sample snippets.

#### Sample Code

- SnpAccessTableContent
- SnpCreateTable
- SnpInspectTableModel
- SnpIterTableUseDictHier
- SnpManipulateTableStyle
- SnpModifyTable
- SnpSetTableFill

#### Related APIs

- ICellContentManager
- ICellStyleSuit
- ICellStylesFacade
- ITableAttrAccessor
- ITableAttributes

- ITableAttrReport
- ITableCommands
- ITableFrame
- ITableFrameList
- ITableLayout
- ITableModel
- ITableSuite
- ITableStyleSuite
- ITableStylesFacade

## Editing Table and Cell Options with ITableSuite

A starting point for writing a plug-in that modifies a table through an active selection is to become familiar with the ITableSuite interface.

You can obtain the ITableSuite interface for the active selection from the ISelectionUtils interface aggregated on kUtilsBoss with code like the following:

```
InterfacePtr<ITableSuite> iTableSuite(static_cast<ITableSuite*>(<br> Utils<ISelectionUtils>() ->QuerySuite(ITableSuite::kDefaultIID)) ;
```

Obtaining this interface pointer does not necessarily mean you can exercise the capabilities. Always test the ITableSuite::Can<DoSomething> method to determine a particular capability is available in the target, before calling ITableSuite::<DoSomething>.

If there are capabilities that cannot be obtained through this interface—like adding text to a table cell—but you still want to work with an active selection, use the suite pattern to implement your own suite. To implement your own suite, you need to write add-ins for the integrator suite boss class and at least the table suite and text suite boss classes (if modifying an existing table) or the text suite boss class (if creating a new table in an existing story). Suite implementation code can obtain an ITableModel interface pointer (effectively, a reference to a kTableModelBoss object) in a straightforward way through ITableTarget. You can then use the core APIs (like ITableCommands) in addition to ITableModel, to manipulate the table properties.

If client code needs to work with tables that are chosen programmatically (rather than with tables for which the end user varies the active selection), you need to program using the APIs exposed on kTableModelBoss. Your task then is to find a table model (see “[Acquiring a Table Model Reference](#)” on page 107).

---

# Tables

## Acquiring a Table Model Reference

How you acquire an interface on an instance of kTableModelBoss depends on whether you are working with an active selection or searching through all tables in a given story or the story list.

If working with an active selection, first be sure you need to use the API on kTableModelBoss. If the capability exists on ITableSuite, use it first. If you definitely need to work with the kTableModelBoss API (e.g., ITableModel or ITableCommands), implement a suite pattern. ITable-Target identifies the table targeted for editing by a suite. For sample code, see [TableBasics](#).

There are two ways to search through the story list (see the `IStoryList` interface):

- The recommended way is to use `ITextStoryThreadDictHier`, aggregated on `kTextStoryBoss`. This contains a collection of references to objects, some of which expose an `ITableModel` interface. These are the tables embedded in the story represented by the given instance of `kTextStoryBoss`. See `SnpIterTableUseDictHier.cpp` for an example of how to acquire table model references through this mechanism.
- There also is an `ITableModelList` aggregated on `kTextStoryBoss`, but this should be regarded as deprecated; do not depend on it. For an example of this mechanism, see the `SnpIterTableStories.cpp` code snippet.

## Iterating over Tables in a Document

The recommended mechanism for iterating over tables in a document involves using the `ITextStoryThreadDictHier` interface to look for boss objects that have both the `ITextStoryThreadDict` and `ITableModel` interfaces.

Tables are embedded in stories, so first you need to iterate over the stories in a document through the `IStoryList` interface. Once you have a story, use its `ITextStoryThreadDictHier` interface and `NextUID` (beginning with the `UID` of the story) to iterate over the collection of story thread dictionaries. If a boss object with an `ITextStoryThreadDict` interface also has an `ITableModel` interface, it is a table model.

For an example of using this mechanism to locate tables, see the `SnpIterTableUseDictHier` code snippet.

There is another mechanism that can be used to iterate over tables in a document, but we do not recommend it: `ITableModelList` should be used only with caution, as this interface may not be in a future version of the API. From `ITableModelList`, you can iterate through the tables using the `GetModelCount` and `QueryNthModel` methods.

## Creating a New Table in a Story

To create a table in the story targeted by the active text selection, use `ITableSuite::CanInsertTable` and `ITableSuite::InsertTable`. To create a table at a `TextIndex` in a story chosen programmatically, call `ITableUtils::CanInsertTableAt` and `ITableUtils::InsertTable`. For sample code, see the `SnpCreateTable` SDK code snippet. The command that creates the table is `kNewTableCmdBoss`; however, as noted above, you do not need to process this command directly.

To convert the text range identified by the active text selection to a table, use `ITableSuite::CanConvertTextToTable` and `ITableSuite::ConvertTextToTable`. To convert a range of text in a story chosen programmatically to a table, call `ITableUtils::ConvertTextToTable`. The command that creates the table is `kTextToTableCmdBos`; however, as noted above, you do not need to process this command directly.

## Deleting a Table from a Story

To delete a table that is selected, use `ITableSuite::CanDeleteTable` and `ITableSuite::DeleteTable`. To delete a table chosen programmatically, process the command returned by `ITableCommands::QueryDeleteTableCmd`. The command used to delete a table is `kDeleteTableCmdBoss`; however, as noted above, you do not need to process this command directly.

## Copying and Pasting a Table

To copy and paste a table, use the `kTableCopyPasteCmdBoss` command. The data interface for this command, `ITableCopyPasteCmdData`, specifies the source and destination tables' `UIDRef` values, the grid address of the destination table at which you want to paste the source content, and the level to which you want to copy attributes from the source to the destination tables.

For sample code, see the `SnpCopyPasteTable` SDK code snippet.

## Sorting the Data in a Table

The `SnpSortTable` SDK code snippet indicates how to sort table data using table iterators, content access methods, and standard collections like `K2Vector`.

If the table has split or merged cells, the sorting operation is not well defined.

For most cases, sorting is done by the `WideString <` operator; however, if there is a special glyph in the text, you must define your own comparator function object. `SnpSortTable.cpp` indicates how to go about this, defining a comparator function object for a custom data class.

If your text contains end-user-defined characters (EUDC), you must get the character attribute at the special placeholder `textchar` (`kTextChar_SpecialGlyph` or `kTextChar_NonRomanSpecialGlyph`). The glyph ID is inserted as a character attribute strand so the composer can render it; this information is relevant to sorting.

---

# Tables and Cells

## Inserting and Deleting Rows and Columns

To edit a table selected by the end user using active selection, use methods on ITableSuite to insert or delete rows or columns. For example, call ITableSuite::CanInsertRows to determine whether you can insert rows into the selected table; if so, call ITableSuite::InsertRows. To get ITableSuite, query the selection manager (ISelectionManager) for it or call ISelectionUtils::QuerySuite to get ITableSuite for the active selection.

To edit a table selected programmatically, use ITableCommands.

### See Also

SnpModifyTable code snippet

## Changing the Dimensions of a Table

To change the dimensions of a table selected by the end user using active selection, use ITableSuite. Call ITableSuite::CanChangeTableDimensions to determine whether the selection target supports the capability you require; if it does, call ITableSuite::ChangeRowDimensions.

To change the dimensions of a table selected programmatically, use ITableCommands aggregated on kTableModelBoss.

## Changing the Height of Table Rows

Row height is one of many table attributes (see the ITableAttrReport interface). It is represented by kRowAttrHeightBoss. This attribute can be applied when the user selects a table through ITableSuite::ApplyRowOverrides, but it is more convenient to use the ITableSuite::ResizeRows wrapper method or ITableCommands::ResizeRows when the table is chosen programmatically.

## Merging or Splitting Cells

Merging or splitting cells can be done through ITableSuite for an abstract selection or through ITableCommands for a specific location within the table. The command of class kSplitCellCmdBoss does the work, but you can use ITableCommands::SplitCells and ITableCSuite::SplitCells rather than using the command directly.

## Editing Table and Cell Options using Table Attributes

You can set a table option that controls the appearance of the table or cell. For example, you may want to set the stroke or fill.

Apply an override for the table attribute. Table attributes define how the table appears. A table attribute (ITableAttrReport interface) describes a single table property.

To apply an override to the selected table or cells, use `ITableSuite`. To get `ITableSuite`, query the selection manager (`ISelectionManager`) for it or call `ISelectionUtils::QuerySuite` to get `ITableSuite` for the active selection.

To apply an override to a table or cells chosen programmatically, use `ITableCommands`.

#### See Also

- [SnpSetTableFill SDK code snippet](#)
- [TableAttributes SDK sample](#)
- [API reference documentation page for `ITableAttrReport`, for a complete list of all table attributes. Table attribute overrides are applied using methods provided by `ITableSuite` or `ITableCommands`.](#)

## Setting the Stroke for a Cell

To set the stroke for a cell, apply an attribute override. Use `ITableSuite::ApplyCellStrokes` to edit the stroke of cells that are selected. Use `ITableCommands::ApplyCellStrokes` to edit the stroke of cells chosen programmatically. This requires populating a data object defined in `ICellStrokeAttrData`, to target the cell sides to stroke and carry the parameters.

The following code fragment populates the data object for applying cell strokes to a cell:

```
ICellStrokeAttrData::Data data;
data.attrs.Set(ICellStrokeAttrData::eWeight);
data.attrs.Add(ICellStrokeAttrData::eTint);
data.sides = Tables::eTopSide;
data.weight = newWeight; // a PMReal specifying new weight in points
data.tintPercent = newTintPercent; // a PMReal giving tint in percent
```

## Setting the Fill Color for a Cell

To set the fill for a cell, apply an attribute override. Use `ITableSuite` to edit the fill of cells that are selected. Use `ITableCommands` to edit the fill of cells chosen programmatically. For sample code, see the `SnpSetTableFill` code snippet.

## Changing the Cell Content Text Direction

You can get the “rotation-follow-story” (yes or no) and rotation (angle) attributes using `kCellAttrRotationFollowStoryBoss` or `kCellAttrRotationBoss`. You may need to take account of the text direction when you determine whether a cell is overset.

## Adding a Background Image to a Cell

In some cases, the best approach is to put an inline graphic into the text model, into the text span associated with the cell, although this may not fill the cell exactly.

## Acquiring a Reference to a Table Frame

The table layout (ITableLayout) is aggregated on kTableModelBoss. It provides very detailed information about the layout of the table. Use ITableFrame::GetParcelFrameUID to get at an individual table frame to which a parcel is mapped. This method yields a reference to a kTableFrameBoss object. Alternately, IParcelList, which is aggregated on the kTableCellContentBoss (as described in the “[Getting a Parcel, given a Grid Address](#)” on page 112) also has a method, GetParcelFrameUID, that you can use it to get to the corresponding frame.

It also is possible to discover the table frames in a story from the owned item strand. This mechanism is more delicate and requires additional information (from ITextStrand) to determine where one table ends and another begins.

---

## Text in Tables

### Finding the Text Model in which a Table is Embedded

Table model boss objects (see kTableModelBoss) are dependants of a story (see kTextStoryBoss). Many tables can be nested within a single story, and tables can be nested within one another to an arbitrary depth.

The interface ITableTextContainer provides a connection between the table model (kTableModelBoss) and the text model (on kTextStoryBoss) that encapsulates its textual content.

If you have an ITableModel interface, you can find the text model in which it is embedded, by querying for ITableTextContainer through this interface and using ITableTextContainer::QueryTextModel.

### Editing the Text Displayed in a Table Cell

You can edit the text displayed in a table cell.

To set the text for a table cell, use ITableCommands::SetCellText.

To get the text for a table cell, locate the story thread (see interface ITextStoryThread) that stores the text the cell displays, then use TextIterator to access that range of text.

To format the text for a table cell, locate the story thread (see interface ITextStoryThread) that stores the text that the cell displays, then use ITextModelCmds::Apply::ApplyCmd to apply text attributes to that range of text.

#### See Also

- TableBasics, TblBscSuiteTextCSB::GetCellText, and TblBscSuiteTextCSB::SetCellText, SDK code samples
- SnpAccessTableContents SDK code snippet

## Relationship between Parcels and Cells

For every cell in the table, there is an associated parcel (IParcel) in a parcel list represented by IParcelList. Parcels are about geometry and represent the bounds of regions into which text composition can occur.

## Difference between IParcelList and ITextParcelList

The interface IParcelList should not be confused with ITextParcelList, which is a cache for the text spans associated with each parcel. ITextParcelList is a key part of text composition but does not represent geometry. ITextParcelList is not likely to be used in client code in most cases, unless you are trying to determine whether a particular cell is overset.

## Getting a Parcel, given a Grid Address

Text cells are represented by kTextCellContentBoss. This class aggregates an IParcelList interface, which contains a list of parcels; the length of the list is likely to be at most one.

The parcel list on a kTextCellContentBoss object might contain, for example, one instance of a kTextCellParcelBoss object, which exposes an IParcel interface.

To work with a table, if you have a grid address and an ITableModel, you can get a reference to a kTextCellContentBoss. There are at least two ways to get to a kTextCellContentBoss:

- The easiest way is to use ITableModel::QueryCellContentBoss, passing it the GridAddress of an anchor cell.
- A more efficient way is to use ITableModel::CreateContentBossAccessor, which is faster but cannot be used across structure changes (rows/columns being added or deleted, merges and splits, etc.).

The boss class kTextCellContentBoss aggregates ICellContent; when you have ICellContent, you can simply use QueryInterface to get IParcelList. Then you can use the methods on IParcelList (GetParcelCount and QueryNthParcel) to iterate over the parcel collection. There should be just one parcel that can be used to determine the bounds into which the cell text will be flowed. The SnpGetTableParcel SDK code snippet illustrates this concept.

## Getting to the Text, given a Grid Address

Given a grid address, there are several ways to get to cell text. You can use the method described above ([“Getting a Parcel, given a Grid Address” on page 112](#)) to acquire a reference to a cell content boss. For instance, when you have a content boss, check whether it aggregates ITextStoryThread; if it does, you can be confident it is a text cell. When you have an ITextStoryThread, you can ask it for the associated start, span, and text model (ITextModel). Once you have these three pieces of information, you can get the characters. For an example, see the SnpAccessTableContent::GetTextFromCell method SDK code snippet.

Alternatively, given an ITextModel (on kTextStoryBoss), query for IComposeScanner and use methods like IComposeScanner::QueryDataAt to acquire the characters.

It also is possible to use the ITableModel and ITextModel methods without interacting with ITextStoryThread methods directly. This is relatively easy. Given a GridAddress, turn it into a GridID by using ITableModel::GetGridID. Once you have a GridID, you can determine the text story thread associated with the given GridID. If you already have a table model reference, the quickest route is to use the ITableTextContainer interface (also on kTableModelBoss) to get the ITextModel (on kTextStoryBoss) in which the table is embedded, then find the thread start and span from the ITextModel.

## Knowing when a Cell is Overset

There is an ITextParcelList interface that is aggregated on kTextCellContentBoss. The ITex-tUtils::IsOverset method takes an ITextParcelList as a parameter.

To find out which cells in a given table were overset, do the following:

- Iterate through all cells in the table.
- Use one of the content access methods shown in SnpAccessTableContent.cpp to get references to each kTextCellContentBoss object that represents the content.
- Query for the ITextParcelList.
- Use the ITex-tUtils::IsOverset method.

---

# Table and Cell Styles

## Accessing the List of Supported Table/Cell Styles

Like paragraph and character styles, table and cell styles exist on the session or a particular document. You can get a list of table or cell styles available to a session or a document.

### Solution

Table style and cell style are represented by kTableStyleBoss and kCellStyleBoss, respectively. To get the list of the styles, obtain the session or document workspace, then query the IStyle-GroupManager interface identified by IID\_ITABLESTYLEGROUPMANAGER (for table styles) or IID\_ICELLSTYLEGROUPMANAGER (for cell styles). The interface provides the API, GetRootHierarchy(), which returns a pointer to IStyleGroupHierarchy at the root level. Use IStyleGroupHierarchy to iterate through the available styles.

### Sample Code

```
SnpManipulateTableAndCellStyle::ChooseStyle()
```

## Tables

### Table and Cell Styles

## Getting all Attributes of a Table/Cell Style

Within the document or application workspace, there is the concept of a root style. Except for the root table or cell style, each table or cell style has a parent style. A style inherits all attributes from its parent, maintaining only those attributes that are different from its immediate parent in its own attributes boss list. You can get all attributes of a given style.

### Solution

IStyleInfo on kTableStyleBoss and kCellStyleBoss provide the API IStyleInfo::GetBasedOn that stores its immediate parent style. You can traverse up to root to collect all applicable attributes. However, we recommend using either ITableStylesFacade::GetTableStyleAttrsResolved() or ICellStylesFacade::GetCellStyleAttrsResolved() to get the complete list of attributes.

### Sample Code

```
SnpManipulateTableAndCellStyle::GetRegionalStyle
```

## Determining the Value of an Attribute within a Style

You can determine what a style means to a particular attribute; that is, what value for a particular attribute would be applied to a table or cell.

### Solution

1. Since styles do not maintain a full set of attributes, you need to obtain a complete list of a style. See “[Getting all Attributes of a Table/Cell Style](#)” on page 114.
2. Query the list for the particular attribute of interest (use AttributeBossList::QueryByClassID()). This returns the desired attribute.
3. Obtain the value of the attribute via the appropriate interface.

### Sample Code

```
SnpManipulateTableAndCellStyle::GetRegionalStyle
```

## Creating a New Table/Cell Style

### Solution

You can create table and cell styles by processing the required command (kCreateTableStyleCmdBoss or kCreateCellStyleCmdBoss); however, we recommended you use ITableStylesFacade::CreateTableStyle() or ICellStylesFacade::CreateCellStyle(). You may pass style name, parent style (based on style), and your own attributes that are different from the parent's.

The style name should be unique. To generate a unique name, call IStyleUtils::CreateUniqueName().

## Sample Code

- SnpManipulateTableAndCellStyle::CreateCellStyle
- SnpManipulateTableAndCellStyle::CreateTableStyle

## Modifying an Existing Table/Cell Style

Given a table or cell style, you might need to modify it, either by modifying the attributes the style represents or changing some other definitions of the style, like its style name.

### Solution

You can handle changes to styles through the kEditTableStyleCmdBoss or kEditCellStyleCmdBoss command; however, we recommend using their respective facades: ITableStylesFacades::EditTableStyle() and ICellStylesFacades::EditCellStyle(). Generally, you will do the following:

1. Get and store current style definitions, like style name, parent style, and local attributes boss list. Since you are likely to change only some of the definitions, it is desirable to keep a copy of the original data.
2. Prepare the piece of data you want to change. For example, to change style name, you need to get a new unique name; to change a specific attribute, apply the new attribute to the attribute boss list obtained in previous step.
3. Modify the style by calling ITableStylesFacades::EditTableStyle() or ICellStylesFacades::EditCellStyle().

**NOTE:** If a style's parent style is changed, all inherited attributes of the style are changed except those attributes with local overrides.

### Related APIs

- SnpManipulatetableAndCellStyle::ModifyCellStyle
- SnpManipulatetableAndCellStyle::ModifyTableStyle

## Deleting a Table/Cell Style

You can delete a style from a document or a session.

### Solution

Since a table or cell could have been applied to table and cell in the document or used in to define other styles, you must provide an alternate style as a replacement style before deletion. To delete an existing style, call ITableStylesFacades::DeleteTableStyle() or ICellStylesFacades::DeleteCellStyle().

### **Sample Code**

- SnpManipulateTableAndCellStyle::DeleteCellStyle
- SnpManipulateTableAndCellStyle::DeleteTableStyle

## **Applying a Table/Cell Style to Table/Cell Selection**

Given a table or cell style, you can apply it to a table, cell, or the current selection.

### **Solution**

If you are dealing with a table/cell selection, query ITableStyleSuite or ICellStyleSuite from the active selection manager and call the ApplyTableStyle or ApplyCellStyle method to apply table or cell style to the selected table or cells.

To apply a table style to a table specified as a UIDRef of the table model, use ITableStylesFacade::ApplyTableStyle(). You have the options to override current table attribute overrides and cell styles applied.

To apply a cell style to one or more cells, use ICellStylesFacade::ApplyCellStyle(). You can specify the cell with a UIDRef of the table and a GridArea of the table.

### **Sample Code**

- SnpManipulateTableAndCellStyle::ApplyCellStyle
- SnpManipulateTableAndCellStyle::ApplyTableStyle

## **Obtaining the Applied Style of a Table/Cell**

You can determine the table or cell style for a specific table or cell.

### **Solution**

If you have a table/cell selection, obtain the selection suite interface ITableStyleSuite and ICellStyleSuite from the active selection manager and call the GetSelectedTableStyle or GetSelectedCellStyles method to get the applied table or cell styles.

To get the table style from a table specified as a UIDRef, use ITableStylesFacade::GetTableStyle().

To get the cell styles from cells specified by a UIDRef of the table and a GridArea, use ICellStylesFacade::GetSelectedCellStyles().

## Clearing Attribute Overrides for a Table/Cells

You can remove overrides of a table or cells, to leave the table and cells formatted to the applied table or cell style.

### Solution

If you have a table/cell selection, obtain the suite interface `ITableStyleSuite` or `ICellStyleSuite` via the active selection manager, then call `ITableStyleSuite::ClearLocalOverrides()` or `ICellStyleSuite::ClearOverrides()`.

To remove local overrides from a table specified by a `UIDRef` of the table model, use `ITableStylesFacade::ClearLocalOverrides()`. You have an option to clear all cell styles applied to the table cells.

To remove local overrides from cells specified by a `UIDRef` of the table and a `GridArea`, use `ICellStylesFacade::ClearCellStyleOverrides()`.

## Obtaining the Regional Cell Style of a Table Style

Each table style defines a set of regions such as headers and body rows. Each region can be assigned a cell style. You can get the cell style for a specific region in a table style.

### Solution

Regional cell styles are considered table attributes of a table style. To get the attribute value of the related attributes, see “[Determining the Value of an Attribute within a Style](#)” on page 114. The steps are described briefly below:

1. Get a complete list of table attributes of the table style, using `ITableStylesFacade::GetTableStyleAttrsResolved()`.
2. Prepare ClassIDs to represent table regions. Predefined regions include header rows, footer rows, left column, right column, and body rows. Except for body rows, each region has two related attributes, “cell style” and “use body,” that determine a regional style. For example, `kTableAttrHeaderCellStyleBoss` and `kTableAttrHeaderUseBodyCellStyleBoss` determine header rows regional style. Body rows regional style do not have a “use body” attribute.
3. Query the “cell style” and “use body” attributes from the complete list of attributes of the table style.
4. Get the result. If the region is not “body rows” and the value of the `ITableAttrBool16` interface of the “use body” attribute is `kTrue`, the regional cell style is the same as body rows; otherwise, the regional cell style is the value of the `ITableAttrUID` interface of the “cell style” attribute.

### See Also

For a table of bosses that define regions, see the “Tables” chapter of *Adobe InDesign CS4 Programming Guide*.

#### Sample Code

```
SnpManipulateTableAndCellStyle::GetRegionalStyle
```

### Setting the Regional Cell Style of a Table Style

You can set the cell style for specific regions in a table style.

#### Solution

Setting regional cell styles is the same process as modifying a table style. The steps are described briefly below:

1. Get the original settings of a table style, as described in [“Modifying an Existing Table/Cell Style” on page 115](#).
2. According to the region of interest, create appropriate “cell style” and/or “use body” attributes. (If the region is body rows, you do not need the “use body” attribute.) For example, if the region is the header row, create attribute kTableAttrHeaderCellStyleBoss and set ITableAttrUID to the cell style you want to set, then create kTableAttrHeaderUseBodyCellStyleBoss and set ITableAttrBool16 to kFalse.
3. Add the newly created attributes to the local attribute list of the table style, using AttributeBossList.ApplyAttribute().
4. Update the table style by calling ITableStylesFacade::EditTableStyle().

#### See Also

For a table of bosses that define regions, see the “Tables” chapter of *Adobe InDesign CS4 Programming Guide*.

#### Sample Code

```
SnpManipulateTableAndCellStyle::SetRegionalStyle
```

# Graphics

---

## Introduction

This chapter provides implementation hints for common use cases and answers frequently asked questions involving the Adobe InDesign graphics API.

---

## Paths

### Obtaining Path Information

You can get path information from a page item, such as a spline item, text outline, and text wrap.

#### Solution

Use the `IPathGeometry` interface to retrieve the path information, as follows:

1. Determine what type of path you are looking for, and make sure you look in the right page item for the path. (Do not confuse the graphic page item with the graphics frame.) For example:
  - For information about the clipping path, look in the graphic page item, not the graphics frame.
  - For information about the text wrap path of a graphic page item, look for the text wrap object (defined as `kStandOffPageItemBoss`).
  - For information about the path of a spline item (frames, lines, and curves), look for the `kSplineItemBoss` item.
  - For information about the outline paths of characters in a segment of text, you need to create the text outline and look for the newly created inline spline item.
2. Query the `IPathGeometry` interface on the page item boss to get the path information you want, using various methods to get such information as the number of paths, number of segments, number of path points, and path bounding box.

## Sample Code

- SnpInspectPathInfo.cpp
- SnpSelectShape.cpp

## Related API

- IPathGeometry

## Inserting a New Point into an Existing Path

### Solution

Use the kAddSplinePointsCmdBoss command, as follows:

1. First construct the PMPPathPoint item for the new path point, with an anchor point and two direction points.
2. Transform the coordinates of the new point such that they are in the same coordinate system as the existing points' coordinates. For example, if the coordinates of your new point are in pasteboard coordinates, apply a transformation to convert from pasteboard to inner coordinates.
3. Create the kAddSplinePointsCmdBoss command.
4. Query IModifyPathPointsCmdData on the command. Specify the path index of the path into which you want to insert the new point, the point index of the point before which you want to insert the new point, and the number of points you want to insert.
5. Query IPathGeometry on the command. Add a new path and append to it the path point you constructed in Step 1.
6. Process the command.

### Related APIs

- IModifyPathPointsCmdData
- IPathGeometry
- kAddSplinePointsCmdBoss

## Creating a Compound Path or Compound Shape from Selection

You can create a compound path or shape from selected paths or graphics frames that overlap each other. (Compound shapes are created with Pathfinder commands in the InDesign user interface). See “[Creating a Compound Path from Page Items](#)” on page 121.

## Solution

1. Query for IPPathOperationSuite, which provides methods for operations related to compound paths and compound shapes.
2. Call the appropriate precondition method to check whether the desired operation is possible on the selection target. (Normally, precondition method names are of the form CanDoXXX; for example, CanMakeCompoundPath.)
3. If the desired operation is possible on the selection target, call the performing method to execute the operation. (Normally, performing method names are of the form DoXXX; for example, MakeCompoundPath to make a compound path.) Check the returned error code to see whether the operation executed as expected.

## Sample Code

SnpManipulatePathandGraphics.cpp

## Related APIs

IPPathOperationSuite

## Creating a Compound Path from Page Items

You can create a compound path from the paths of several page items, which may or may not be selected. (If all the page items are selected, you can use the solution described in “[Creating a Compound Path or Compound Shape from Selection](#)” on page 120.) Since you will combine the page items into one page item, you can manipulate the resulting page item as a whole; for example, assign graphic attributes.

## Solution

1. Create the kMakeCompoundPathCmdBoss command.
2. Prepare the list of page items. InDesign cannot make a compound path from a text-on-path object, a locked page item, or a page item without paths. To filter out these items, use ISplineUtils::FilterMakeCompoundPathList.
3. Set the IBoolData field of the command boss to kTrue, to tell the command to reverse every other path (so releasing the compound path results in exactly the same original objects).
4. Process the command.

## Sample Code

SnpManipulatePathandGraphics.cpp

## Related APIs

- ISplineUtils
- kMakeCompoundPathCmdBoss

## Converting a Selected Spline Item to a New Shape

You can see the visual effects of using different shapes in the same bounding box. You can select an object and convert it to a new type of shape programmatically.

### Solution

The following steps assume the graphics frame already is selected.

1. Query for IConvertShapeSuite using ISelectionUtils.
2. Determine the shape you want to convert the selected item to, such as line, oval, rectangle, or polygon.
  - To convert to a polygon, you also need to determine the number of edges and star inset of the polygon.
  - To convert to a rectangle, you also may choose the corner effects you want to apply.
3. Call the ConvertPageItemShape method.

**NOTE:** IConvertShapeSuite has additional methods for connecting path points; however, these methods are not tested.

### Sample Code

SnpManipulatePathandGraphics.cpp

### Related APIs

IConvertShapeSuite

---

## Graphic Page Items

### Placing a Graphics File into a Spread

You can import a graphics file into an InDesign document and let the end user choose a position and size for placing the file in a spread.

### Solution

Use the kImportAndLoadPlaceGunCmdBoss command to import the file and load the place gun, so the end user can place the item in the spread. Follow these steps:

1. Create kImportAndLoadPlaceGunCmdBoss.
2. Query IIImportFileCmdData on the command and set the command data, including the IDataBase of the document, the IDFfile of the graphics file, and the UI flag.
3. Process the command.

**NOTE:** Generally, the process for importing a graphics file is the same as for importing other types of assets, like text.

## Related Documentation

- For other import commands, see the Adobe knowledge-base document <http://support.adobe.com/devsup/devsup.nsf/docs/52421.htm>.

## Sample Code

- XDocBkXMLPostImportIteration::ImportImage
- PnlTrvUtils::ImportImageAndLoadPlaceGun
- SDKLayoutHelper::PlaceFileInFrame

## Related APIs

- IImportFileCmdData
- kImportAndLoadPlaceGunCmdBoss

# Placing a Graphics File into an Existing Graphics Frame

## Solution

Use kImportAndPlaceCmdBoss to import the file and place the item into an existing graphics frame, as follows:

1. Create kImportAndPlaceCmdBoss.
2. Query IImportFileCmdData on the command and set the command data, including the IDataBase of the document, the IDFfile of the graphics file, and the UI flag.
3. Query IPlacePIData on the command, set the graphics frame as the parent page item, provide initial position, and set usePlaceGunContents to kFalse.
4. Process the command.

## Related Documentation

- For other import commands, see the Adobe knowledge-base document <http://support.adobe.com/devsup/devsup.nsf/docs/52421.htm>.

## Sample Code

SDKLayoutHelper.cpp

## Related APIs

- IImportFileCmdData
- kImportAndPlaceCmdBoss
- IPlacePIData

## Getting a Graphic Object from a Layout Selection

You can get the graphic page item from the layout selection, regardless of what is selected. You can get a list of page items from the layout selection target, but you do not know whether a selected item is the graphic page item itself or its graphics frame, and some settings are valid only on graphic page items, like clipping path and text wrap.

### Solution

Traverse the page item hierarchy and use an interface specific to graphic page items (like `IImageDataAdapter`) to identify graphic page items. Follow these steps:

1. For each page item, try to query `IImageDataAdapter`.
2. If the interface exists and has a low-resolution proxy image associated with it (using `IImageDataAdapter::GetLowResImageUID`), the item is the graphic page item itself.
3. If the item is not the graphic page item itself, check the item's children.
  - If the item has more than one hierarchical child, the item is not a graphic page item.
  - If the item has only one hierarchical child, check whether the child has the `IImageDataAdapter` interface by querying for it and a low-resolution proxy image associated with it. If the child has the interface, the child is the graphic page item; return it. Otherwise, the selected item does not contain graphics.

### Sample Code

`SnpGraphicHelper.cpp`

### Related APIs

- `IImageDataAdapter`
- `IHierarchy`

## Moving a Graphic Page Item within a Frame

You can shift a graphic within the graphics frame in which it was already placed.

### Solution

Graphic-page-item transformations (like moves) are performed the same as for page items. Follow these steps:

1. Query `ITransformFacade`, and call the `TransformItems` method.
2. Create `kTransformPageItemsCmdBoss`, set the command's parameter, and process the command.

### Sample Code

`BscDNDCustomFlavorHelper.cpp`

## Related API

ITransformCmdData, kTransformPageItemsCmdBoss.

## Fitting Graphics Content to its Frame

You can fit a graphic page item to its graphics frame or fill the frame with the graphic page item.

### Solution

If the content and/or frame is selected, use appropriate methods on IFrameContentSuite. This suite provides operations on selected items, like the IFrameContentSuite::FitFrameToContent method.

If you have a list of items, use appropriate methods on IFrameContentFacade, like the IFrameContentFacade::FitFrameToContent(UIDList& items) method.

Alternatively, create and directly process appropriate commands, like kFitFrameToContentCmdBoss, kFitContentToFrameCmdBoss, kFitContentPropCmdBoss, and kCenterContentInFrameCmdBoss. Note the following:

- kFitFrameToContentCmdBoss needs the frame as its item list; other commands need the contents as their item list. You can use IFrameContentUtils to get contents from frames and vice versa.
- kFitContentPropCmdBoss has an IBoolData interface that controls whether the command fits content to just barely fill the frame (kFalse to fit content proportionally) or fills all white space by stretching content to be larger than the frame (kTrue to fill frame proportionally).

### Sample Code

- SnpManipulatePathandGraphics.cpp
- SDKLayoutHelper.cpp

### Related APIs

- IFrameContentFacade
- IFrameContentSuite
- IFrameContentUtils
- kCenterContentInFrameCmdBoss
- kFitContentToFrameCmdBoss
- kFitContentPropCmdBoss
- kFitFrameToContentCmdBoss

## Creating a Clipping Path for a Selected Page Item

With graphics placed on a spread, you can create or set clipping paths for the graphic page item.

### Solution

Use IClippingPathSuite. This selection suite has everything that you need to perform clipping path operations, including getting the embedded Photoshop path and alpha channel, setting a clipping path, and converting a clipping path to a frame. Follow these steps:

1. Query IClippingPathSuite and get current clipping path settings by calling `QueryActiveClipSettings`.
2. Make necessary changes and call appropriate methods to set the settings.

**NOTE:** If the item is not selected, we recommend you first select the item first. It is much easier to use the selection suite than to set a clipping path directly.

### Sample Code

`SnpManipulatePathandGraphics.cpp`

### Related APIs

`ConvertPSResourcesToPMTags.h`, `IClippingPathSuite`

## Setting Text Wrap Mode

You can set text wrap mode for a list of page items.

**NOTE:** When a page item is created, the text wrap mode is set to `IStandOff::kNone` by default. This applies to graphic page items, as well.

### Solution

Do one of the following:

- We recommend you use the API `ITextWrapFacade::SetMode` facade.
- Alternatively, create and process `kStandOffModeCmdBoss` directly. Make sure the text wrap modes for the graphics frame and the graphic page item are the same; otherwise, the graphic page item's text wrap mode takes priority. You can set the graphics frame's mode to `kNone` and set the graphic page item's mode to the desired setting.

### Sample Code

`SnpManipulateTextFrame.cpp`

## Related APIs

- ITextWrapFacade
- ITextWrapSuite
- kStandOffModeCmdBoss

## Setting Text Wrap Contour Options

The effect of setting options is seen when the mode is set to Wrap Around Object Shape (IStandOff::kManualContour).

### Solution

The recommended solution is very similar to that for setting text wrap mode. We recommend you use ITextWrapFacade when possible. Normally, setting contour options involves the following steps:

1. Query ITextWrapFacade.
2. If the page item you have is a graphics frame, get the graphic page item. (See “[Getting a Graphic Object from a Layout Selection](#)” on page 124.)
3. Get current contour settings by calling the GetContourWrapSettings method. This method returns settings like threshold, tolerance, alpha channel index, and Photoshop path index.
4. Change parameters as needed, and call the SetContourWrapSettings method.

**NOTE:** You can process kSetContourWrapCmdBoss directly; however, you still need to get settings from the facade before you can set the command data.

### Sample Code

SnpManipulatePathandGraphics.cpp

## Related APIs

- ITextWrapFacade
- ITextWrapSuite
- kSetContourWrapCmdBoss

## Modifying Settings of a Display Performance Group

You can change the settings of a display performance group. (For most cases, the default settings are suitable.) Display performance groups are defined as session preferences.

## Solution

Use kSetDrawOptionsCmdBoss, as follows:

1. Declare a local DrawOptionsSet object. You can initialize the object by getting a display performance group set by ID from the IDrawOptions session preferences.
2. Choose one or more categories you want to change. For example, to change raster image settings, assign the DrawOptionsSet raster field to IDrawOptions::kRasterProxy or another value defined in IDrawOptions.
3. Create kSetDrawOptionsCmdBoss, set the command data, and process the command.

There are additional flags on the command that do not change the performance group but do change global preferences:

- Pass kTrue as the second parameter of ISetDrawOptionsCmdData::SetSet method, to set this performance group as the active group.
- Pass kTrue to ISetDrawOptionsCmdData::SetIgnore, to ignore page item overrides.
- Pass kTrue to ISetDrawOptionsCmdData::SetSaveLocalOverrides, to let page item overrides be saved with the document.

## Sample Code

SnpManipulateDisplayPerformance.cpp

## Related APIs

- DrawOptionsSet
- IDrawOptions
- kSetDrawOptionsCmdBoss

## Changing Layout Display Performance Settings

You can use a display performance group other than the default performance group for a layout window. Each layout window has a default display performance group.

For instructions to modify group settings, see “[Modifying Settings of a Display Performance Group](#)” on page 127.

## Solution

1. Obtain the layout window for which you want to change the display performance group.
2. Query IDrawOptionsSetID on kLayoutWidgetBoss.
3. Call IDrawOptionsSetID::SetID(groupID). The groupID could be set to IDrawOptions::kFastGroup, IDrawOptions::kTypicalGroup, or IDrawOptions::kHighQualityGroup.

## Sample Code

SnpManipulateDisplayPerformance.cpp

## Related APIs

- IDrawOptionsSetID
- kLayoutWidgetBoss

## Displaying High-resolution Graphics

Each graphic page item inherits the default display performance settings from the layout when the graphic page item is placed; however, you can force some graphic page items to be displayed at high resolution—using the high-quality performance group—under all circumstances.

### Solution

If you are setting display performance for selected page items, use `IDisplayPerformanceSuite::SetSelectionToHighQuality`. Otherwise, if you want to set display performance settings for an arbitrary set of graphic page items, follow these steps:

1. Create `kSetDrawOptionOverrideCmdBoss`.
2. Query `ISetDrawOptionOverrideCmdData` on the command, and pass `IDrawOptions::kHighQualityGroup` to the `SetDisplayOption` method.
3. Set the graphic page items as the command's `ItemList`.
4. Process the command.

This procedure sets the page item to be displayed using the high-quality performance group (group ID `kHighQualityGroup`). In standard setting, the high-quality performance group sets the highest quality possible in each category. In certain situations—for example, if the raster category of the group `kHighQualityGroup` is set to `IDrawOptions::kRasterGrayOut`—the raster image is displayed as a gray box.

To ensure the item always is displayed at high quality, set the display settings of the performance group first (see “[Modifying Settings of a Display Performance Group](#)” on page 127), and then set the page item’s override to this group.

To let the page item override take effect, the Allow Object-Level Display Setting flag must be selected (View > Display Performance menu). To set this flag programmatically, process `kSetDrawOptionsCmdBoss` and pass `kFalse` to `ISetDrawOptionsCmdData::SetIgnore`.

## Sample Code

`SnpManipulateDisplayPerformance.cpp`

## Related APIs

- `IDisplayPerformanceSuite`
- `IDrawOptions`
- `kSetDrawOptionOverrideCmdBoss`

---

## Colors and Swatches

### Adding a Custom Color

You can add a custom color; for example, to simulate a color from the Pantone Solid Coated library, PANTONE 368 C.

#### Solution

1. Determine the setting of the color. For example, PANTONE 368 C is defined as follows: CMYK 0.57 0 1 0 (PANTONE 368 C).
2. Create a temporary rendering object (as kPMColorBoss).
3. Set color data, including color space, color array, and ink type, as well as attributes of IRenderingObject, like swatch name.
4. Use ISwatchUtils::CreateNewSwatch to create a new color swatch.

#### Sample Code

SnpManipulateSwatches

#### Related APIs

- IColorData
- IIInkData
- IRenderingObject
- ISwatchList
- ISwatchUtils
- kPMColorBoss

### Creating a New Gradient Swatch

You can create a new gradient swatch based on an existing color.

#### Solution

1. Create a temporary rendering object (as kGradientRenderingObjectBoss).
2. Populate this temporary rendering object with the required information about stop colors, midpoints, and so on.
3. Use ISwatchUtils::CreateNewSwatch to create a new gradient swatch.

#### Sample Code

SnpManipulateSwatches

## Related APIs

- IRenderingObject
- ISwatchList
- ISwatchUtils
- IGradientFill
- kGradientRenderingObjectBoss

## Iterating through a Swatch List

You can iterate through the swatch list of a document or workspace to get information about the color or gradient information of the swatches.

### Solution

1. Obtain ISwatchList on the application workspace or on the document workspace. You can get the active swatch list using ISwatchUtils. (See [“How do I obtain an active swatch list?” on page 144](#).)
2. To get information about reserved swatches, such as None, Paper, and Black, use the appropriate methods on ISwatchList.
3. Iterate over the swatch list. Based on the type of swatch (color, gradient, none, or AGM-Black), instantiate respective interfaces on the boss and get the information you want.

### Sample Code

SnpManipulateSwatches::IterateSwatchList

## Related APIs

- IColorData
- IColorOverrides
- IGradientFill
- IIinkData
- IPersistUIDData
- IRenderingObject
- ISwatchList
- ISwatchUtils

## Iterating through an Ink List

You can iterate through the ink list of a document or workspace to get information about inks used.

### Solution

1. Obtain IInkList on the application workspace or document workspace. You also can get the ink list using methods provided by IInkMgrUtils. (See “[Using the Ink Manager](#)” on page 132.)
2. Iterate through the ink list. To get the information you want, instantiate appropriate interfaces, like IPMIinkBossData on kPMInkDataBoss.

### Sample Code

```
SnpManipulateSwatches::IterateInkList
```

### Related APIs

- IInkList
- IInkMgrUtils
- IPMIinkBossData
- kPMInkDataBoss

## Using the Ink Manager

You can get information on inks, such as what inks are defined in a workspace and a document, what inks are used for document preflight, and ink alias information.

### Solution

1. Obtain the utility class IInkMgrUtils on kUtilsBoss.
2. Use methods on the interface to perform various tasks, like assigning, changing, or viewing ink aliases; finding spot swatches corresponding to the spot ink; and obtaining ink lists from the document or workspace.
3. You also can get the utility class IInkMgrUIUtils on kUtilsBoss to invoke the Ink Manager dialog box.

### Related APIs

- IInkList
- IInkMgrUIUtils
- IInkMgrUtils
- IPMIinkBossData
- kPMInkDataBoss

## Getting all Images that use the same ICC Profile

You can get all images in a document that use a particular ICC profile; for example, the same profile as that used by the image you currently have.

### Solution

There is no backward link from the profile to the images that use that profile, so you must iterate through the images using the link manager interfaces to find the images that use a specific profile. Follow these steps:

1. Get the UID of the profile the current image uses, by querying the IID\_ICMSPROFILEUID interface and using IPersistUIDData->GetUID.
2. Get the ILinksManager interface from the document boss.
3. For each UIDRef of a link item gotten from ILinksManager::GetNthLinkUID, instantiate IID\_ICMSPROFILEUID and compare the UID of the ICC profile with the current image's profile UID. When the UIDs match, add the image to the list.

### Related APIs

- ICMSProfile
- ICMSProfileList
- ICMSUtils
- ILinksManager
- IPersistUIDData

---

## Graphic Attributes

### Applying Multiple Graphic Attributes to Page Items

You can apply multiple graphic attributes to page items.

### Solution

1. Determine the attributes you want apply. Typically, you should know the boss ClassID for each attribute.
2. Create kGfxApplyMultAttributesCmdBoss using CmdUtils::CreateCommand, and set a UIDList of the page items in the command's item list.
3. Create an instance of each appropriate attribute boss object, and set the appropriate attribute value. This can be done by using the CreateObject method (from CreateObject.h), querying for the attribute data interface (such as IGraphicAttrRealNumber), and setting the value. You also can use existing utility methods on IGraphicsAttributeUtils directly.

4. Obtain the IApplyMultAttributesCmdData command data interface, then call IApplyMultAttributesCmdData::AddAnAttribute to add the attribute to the list in the command. Repeat for all desired attributes.
5. Process the command.

**NOTE:** If you are applying attributes to the active selection, you may use a selection suite; for example, IGraphicAttributeSuite for page items, ITextAttributeSuite for text, or ITableSuite for tables. (See “[Applying Graphic Attributes to the Active Selection](#)” on [page 134](#).)

### Sample Code

- SnpManipulateGraphicAttributes
- SnpGraphicHelper

### Related APIs

- Graphic attributes — IGraphicAttributeSuite and IGraphicsAttributeUtils
- General — CmdUtils and CreateObject

## Applying Graphic Attributes to the Active Selection

You can apply graphic attribute to selected page items.

### Solution

Use a selection suite, like IStrokeAttributeSuite or IGraphicAttributeSuite for page items, ITextAttributeSuite for text, or ITableSuite for tables.

### Sample Code

- SnpManipulateGraphicAttributes
- StrokeWeightMutator sample

### Related APIs

- IGraphicAttributeSuite
- IStrokeAttributeSuite
- ITableSuite
- ITextAttributeSuite

## Applying one Graphic Attribute to Page Items

You can apply a single graphic attribute to any number of page items.

### Solution

Use the solution for multiple attributes presented in “[Applying Graphic Attributes to the Active Selection](#)” on page 134, or do one of the following:

- If there is an `IGraphicAttributeUtils::Create<XXX>Command` method for the attribute you want to apply, call that method, passing the attribute value. These methods create `kGfxApplyAttrOverrideCmdBoss` or `kBoss_GfxStateApplyROAttributeCmd` internally.
- Create an appropriate command. For information on what such a command should do, see “[Applying Graphic Attributes to the Active Selection](#)” on page 134. If the attribute you want to apply is a rendering attribute, use `kBoss_GfxStateApplyROAttributeCmd`; if the attribute is not a rendering attribute, use `kGfxApplyAttrOverrideCmdBoss`. Process the command.

### Sample Code

- `BscDNDDragSource`
- `BscShpActionComponent`

### Related APIs

- Graphic attributes — `IGraphicsAttributeUtils`
- `CmdUtils`
- `CreateObject`

## Getting one Graphic Attribute of a Page Item

You can get a specific graphic attribute value, like stroke weight or fill color, from a page item.

### Solution

1. Acquire `IGraphicStyleDescriptor` by querying the interface on the page item.
2. Look for an appropriate Get method on `IGraphicAttributeUtils`; for example, `GetStrokeWeight` for stroke weight. If such a method exists, call it to get the attribute value.
3. If no Get method is available for the graphic attribute you want, call that `QueryAttribute` method on the `IGraphicStyleDescriptor` directly, passing in the attribute ClassID and interface ID of the attribute value.

### Sample Code

`SnpManipulateGraphicAttributes`

### Related APIs

`IGraphicsAttributeUtils`

## Getting all Graphic Attributes of a Page Item

You can get a list of all graphic attributes of a page item.

### Solution

1. Acquire `IGraphicStyleDescriptor` by querying the interface on the page item.
2. Call the `IGraphicStyleDescriptor::CreateDescriptorCopy` method to get a list of attributes associated with the graphic style and overrides. This list is of type `IGraphicStyleAttributeBossList`.
3. (Optional) Call `IGraphicStyleAttributeBossList::GetAttributeCount` to get the number of attributes on the page item.
4. Call `IGraphicStyleAttributeBossList::CreateAttributeNCopy` to iterate through each attribute. To get specific values of attributes, you must further query for the data interface (for example, `IGraphicAttrBoolean`, `IGraphicAttrRealNumber`, `IGraphicAttrInt16`, `IGraphicAttrInt32`, and `IPersistUIDData`).

### Related APIs

- `IGraphicsAttributeUtils`
- `IGraphicStyleAttributeBossList`
- `IGraphicStyleDescriptor`

## Clearing Graphic Attributes from a Page Item

You can clear specific graphic attributes from a page item's override list. For example, when a new rendering attribute is changed, you need to remove the graphic attribute first, so the unused attribute boss is released.

### Solution

1. Call `IGraphicStateUtils::CreateGfxClearOverrideCommand` with the specific graphic attribute boss and a list of page items. This creates an underlying `kGfxClearAttrOverrideCmdBoss` command.
2. Process the command.

### Related APIs

- `IGraphicStateUtils`
- `IGraphicStyleAttributeBossList`
- `kGfxClearAttrOverrideCmdBoss`

## Changing Graphic Attributes of the Graphics State

You can change or set the graphic attributes of the graphics state.

**NOTE:** Changing graphic state is complex and should be avoided if possible.

### Solution

Check whether there is a selection suite (e.g., IStrokeAttributeSuite) you can use. If nothing is selected, calling a selection suite changes defaults (the graphics state).

Alternatively, look at utility methods in `IGraphicStateUtils`, such as `ProcessGfxStateApplyAttribute` or `ProcessGfxStateAddMultAttributes`, with the specific graphic attribute boss or attribute list passed in.

Otherwise, create appropriate commands. For rendering attributes, use `kUpdateDefRenderDataCmdBoss` and `kPrivateSetGSRenderDataCmdBoss`; for other attributes, use `kGfxStateChangeAttributeCmdBoss`. You also can use `kAddMultAttributesCmdBoss` to set any number of attributes. Fill in suitable command data and process the command.

### Related APIs

- `IGraphicStateUtils`
- `IGraphicStyleAttributeBossList`
- `IStrokeAttributeSuite`

## Applying Gill Color or a Gradient to a Page Item

You can fill a layout page item with color.

### Solution

Follow the procedure in “[Applying Graphic Attributes to the Active Selection](#)” on page 134 or “[Applying one Graphic Attribute to Page Items](#)” on page 135.

To fill page items that are selected, use the `IGraphicAttributeSuite::ChangeFillRenderObject(ClassID renderClassID, UID renderUID)` method, where `renderClass` is `kPMColorBoss` or `kGradientRenderingObjectBoss`, and `renderUID` is the UID of the color or gradient swatch.

Alternatively, to fill arbitrary page items, use utilities and commands as follows:

1. Create a `kBoss_GfxStateApplyROAttributeCmd` command.
2. The graphic attribute boss class `kGraphicStyleFillRenderingAttrBoss` represents the fill associated with a graphic page item in the layout. This boss class aggregates the interface `IPersistUIDRefData` (with interface identifier of `IID_IPERSISTUIDDATA`), which holds the UID of the fill color.
3. The command boss aggregates an `IPMUknownData` interface. This needs to be populated with a reference to an attribute boss object created in the previous step. Fill in other information of the command data with `IApplRendObjAttrCmdData`. You also can get the command filled with command data by using the utility method

IGraphicAttributeUtils::CreateFillRenderingCommand or IGraphicStateUtils::CreateGfx-ApplyOverrideCommand, passing in rendering class ID, rendering UID, and attribute boss class ID (in this case, kGraphicStyleFillRenderingAttrBoss).

4. Process the command.

#### Sample Code

- BscDNDDragSource
- BscShpActionComponent

#### Related APIs

- IApplyRendObjAttrCmdData
- IGraphicsAttributeUtils
- IGraphicStateUtils
- IPersistUIDRefData
- kPMColorBoss

## Applying Stroke Color or Gradient to a Range of Text

You can set a stroke color for of a range of text.

#### Solution

To set the stroke color of text that is selected, use IGraphicsAttributeSuite. Pass in graphic attributes instead of text attributes (e.g., kGraphicStyleStrokeRenderingAttrBoss).

Alternatively, set stroke color using commands, as follows:

1. Create an instance of an attribute override of type kTextAttrStrokeColorBoss. The key interface on this boss class is ITextAttrUID. This interface should be populated with the UID of a swatch, which can be created with methods on ISwatchUtils. Before creating the swatch, verify that it does not already exist.
2. Create a kUserApplyAttrCmdBoss command and set it to apply to a text range, specified by a position and length or by a RangeData object. There are several ways to create an instance of this command. There is a helper class, ITextAttrUtils, that can be used to create the command.
3. Process the command.

#### Related Documentation

- “[Applying Graphic Attributes to the Active Selection](#)” on page 134.
- “[Applying one Graphic Attribute to Page Items](#)” on page 135.
- “[Applying Gill Color or a Gradient to a Page Item](#)” on page 137.

## Sample Code

- CHDMUtils
- SnpInsertGlyph
- SnpTextAttrHelper

## Related APIs

- IGraphicsAttributeSuite
- ITextAttrUtils
- ITextAttrUID
- kPMColorBoss

## Setting Transparency Effect Attributes

You can set up the attribute values of a transparency effect.

### Solution

We recommend using utility functions provided in IXPAtributeSuite and IXPAtributeUtils. For example, to put a directional feather with a top width of 10 points on a given page item, see [Example 12](#):

#### **EXAMPLE 12 Set Transparency Attributes**

```
IXPAtributeSuite::AttributeList myList;
myList.push_back(IXPAtributeSuite::AttributeTypeAndValue(IXPAtributeSuite::kDirectionalFeatherApply, IXPAtributeSuite::AttributeValue(kTrue));
myList.push_back(IXPAtributeSuite::AttributeTypeAndValue(IXPAtributeSuite::kDirectionalFeatherWidthTop, IXPAtributeSuite::AttributeValue(PMReal(10)));
Utils<IXPAtributeUtils>() ->ApplyAttributes(myList, UIDList(pageItemRef));
```

## Related APIs

- IXPAtributeSuite
- IXPAtributeUtils

## Getting Transparency Effect Attributes

You can determine whether a page item has a particular transparency effect applied and the value of a transparency attribute.

### Solution

We recommend using utility functions provided in IXPAtributeSuite and IXPAtributeUtils. Find the attribute in which you are interested, then use the utility functions to get the value of the attribute. For example, to determine whether a given page item has a directional feather applied, see [Example 13](#):

**EXAMPLE 13 Get Transparency Attributes**

```

InterfacePtr<IGraphicStyleDescriptor> iGfxDesc(pageItemRef, UseDefaultIID());
IXPAttributeSuite::AttributeValue applied;
Utils<IXPAttributeUtils>()-
>GetAttributeValue(IXPAttributeSuite::kDirectionalFeatherApply, applied, iGfxDesc);
If (applied.GetBoolean())
{
    // yes, it's enabled on this page item
}

```

**Related APIs**

- IXPAttributeSuite
- IXPAttributeUtils

**Determining whether a Page Item or its Stroke, Fill, or Content has Transparency Effects Applied**

You can determine whether a page item has any transparency effect applied.

**Solution**

You must iterate through all transparency attributes that determine whether a particular attribute is applied. To get these attributes, see “[Getting Transparency Effect Attributes](#)” on page 139. Table 1 lists the attributes you should check to see if a page item has transparency effects. If any attribute value is not equal to the value in column 3 of the table, that effect is applied.

**TABLE 1 Transparency Attributes that Determine whether an Effect is Applied**

Transparency Effect	Attribute Type	Value When No Effect is Applied
Basic transparency	kBSOpacity	PMReal(100.)
	kPMBlendNormal	kPMBlendNormal
	kBSKnockoutGroup	kFalse
	kBSIsolationGroup	kFalse
Drop shadow	kDSMode	kDSMNone
Basic feather	kVTMode	kVTMNone
Inner shadow	kInnerShadowApply	kFalse
Outer glow	kOuterGlowApply	kFalse
Inner glow	kInnerGlowApply	kFalse
Bevel and emboss	kBevelEmbossApply	kFalse
Satin	kSatinApply	kFalse

Transparency Effect	Attribute Type	Value When No Effect is Applied
Directional feather	kDirectionalFeatherApply	kFalse
Gradient feather	kGradientFeatherApply	kFalse

**NOTE:** To check whether any transparency effect is applied to stroke, fill or content, you need to check their respective attribute types corresponding to the types listed in [Table 1](#). For more information about transparency effect attribute types, see the “Graphic Fundamentals” chapter of *Adobe InDesign CS4 Programming Guide*.

## Related APIs

- IXPAtributeSuite
- IXPAtributeUtils

# Drawing

## Detecting the Page Item Drawing Device

You can let a page item determine the device to which it is drawing. In theory, it should not matter to a page item whether it is drawing to print, PDF, or screen. The fact that the graphics port is specialized for different devices in these three cases is transparent to the drawing code. There may be situations, however, in which the context determines how an item draws. For example, guides can be set to draw to the screen but not to print.

## Solution

Use the IShape flag passed into the IShape::Draw method by the draw manager. See [“How do I detect a drawing device using drawing flags?” on page 149](#).

Alternatively, use the viewport information from the GraphicsData pointer passed into the DrawShape method. See [“How do I detect a drawing device using the viewport boss?” on page 149](#).

## Sample Code

BscDEHDrwEvtHandler.cpp

## Related APIs

- GraphicsData
- IShape

## Creating a Custom Shape

You can create a custom shape for a new type of page item.

**NOTE:** To do custom drawing of existing page items, use page item adornment or draw events.

### Solution

1. In resource definitions, define a new type of page item by inheriting kPageItemBoss or another existing page item.
2. Override the implementation of IID\_ISHAPE, IID\_IHANDLESHAPE, and IID\_IPATHEHANDSHAPE by modifying CShape.cpp, CPathShape.cpp, CGraphicFrameShape.cpp, and CHandleShape.cpp, included in the SDK.

### Sample Code

- Basic shape sample plug-in

### Related APIs

- IHandleShape
- IShape

## Creating Thumbnail Images for Page Items

You can create thumbnail images for page items. For example, you may want these images for previews.

### Solution

Use SnapshotUtilsEx, as follows:

1. Create and execute kGroupCmdBoss, to group the page items into a group.
2. Determine scale and resolution. You may want set them according to your desired minimal resolution, image size, and group bounding box.
3. Create an instance of SnapshotUtilsEx with additional parameters.
4. Draw a snapshot using the SnapshotUtilsEx::Draw method.
5. Export the snapshot to the thumbnail files in the desired format.
6. Ungroup the group item created in Step 1, by creating and executing kGroupCmdBoss.

Alternatively, use SnapshotUtilsEx, as follows:

1. Determine the boundaries of the page items. You will need the union of each individual bounding box, which can be obtained through IShape::GetPrintedBBox(::ParentToPasteboardMatrix(spreadShape)). You also may want to outset the bounds a little bit, so entire items fits within the bounds.

2. Determine scale and resolution. You may want to set them according your desired minimal resolution, image size, and bounding box calculated from the previous step.
3. Create an instance of SnapshotUtilsEx with additional parameters. Use the version of the constructor with the IDataBase\* parameter.
4. Draw each page item onto the snapshot, using the SnapshotUtilsEx::Draw method.
5. Export the snapshot to thumbnail files in the desired format.

### Sample Code

- Snapshot sample plug-in
- SnpCreateInddPreview.cpp

### Related APIs

- ICommand
- IDrawMgr
- IShape
- kGroupCmdBoss
- SnapshotUtils
- SnapshotUtilsEx

---

## Frequently Asked Questions

### How do I open or close a path?

Use the kOpenPathCmdBoss or kClosePathCmdBoss command.

Before processing the command, determine whether the path already is open or closed, using IPathGeometry::IsPathOpen.

### Can I manually change clipping path points?

You can change the clipping path through the user interface, by dragging path points using the Direct Selection tool. Programmatically, you can query IPathGeometry on the graphic page item and change the path points directly. We strongly recommend you use a command to change the points or encapsulate your changes in a command. See “[Inserting a New Point into an Existing Path](#)” on page 120.

## How do I obtain an active swatch list?

The swatch list is accessible through the interface ISwatchList on the application workspace or on the document workspace.

To obtain the active swatch list, use the code in [Example 14](#):

### **EXAMPLE 14 Obtaining the Swatch List**

```
InterfacePtr<ISwatchList> iSwatchList( 
    Utils<ISwatchUtils> () ->QueryActiveSwatchList() );
```

## How do I determine whether a swatch exists?

Before another swatch object (instance of kPMColorBoss) is created through a call to one of the ISwatchUtils::Create<XXX> methods, your code should verify whether it is necessary to do so—that is, whether the swatch already exists—using ISwatchUtils::GetNamedSwatch. If kInvalidUID is returned, the swatch does not exist in the current database and can be created.

## How do I delete a swatch?

We recommend you first find a swatch that can be used as a substitute for the swatch to be deleted. Use ISwatchUtils::ReplaceAndDeleteSwatches to delete the swatch and replace it with the substitute. By providing a substitute, you ensure the document will not have a dangling, broken reference to the deleted swatch.

## How do I add a new type of rendering object?

Adding a new rendering type is difficult and risky. Theoretically, you could implement a kRenderingObjectService and define a new rendering object with IID\_IRENDERINGOBJECT and other interfaces. The following is a brief list of interface a new rendering type needs to provide:

- IID\_IINKRESOURCES
- IID\_IRENDERINGOBJECT
- IID\_IRENDERINGOBJECTAPPLYACTION
- IID\_IRENDEROBJECTSERVICE
- IID\_IREFERENCECONVERTER
- IID\_IRIDXNOTIFIERHANDLER
- IID\_ISCRIPT
- IID\_ISCRIPTPROVIDER
- IID\_ISWATCHREFERENCEDATA

If this new rendering object type is to have user-interface components that the user can create, edit, delete, duplicate, and interact with the graphic state and object styles, more is required.

We recommend you avoid implementing a new type of rendering object.

## How do I get the current working RGB and CMYK profile?

We recommend you get the current workspace first, then query for the `IColorPresetsSettings` interface and get the working profile. See the sample code in [Example 15](#) and [Example 16](#):

### **EXAMPLE 15 Getting the Working Color Profile**

```
InterfacePtr<IWorkspace> (Utils<ILayoutUIUtils>() ->QueryActiveWorkspace()) ;
InterfacePtr<IColorPresetsSettings>
iColorPresetsSettings(workspace, UseDefaultIID());
InterfacePtr<ICMSProfile>
iRGBProfile(iColorPresetsSettings->QueryWorkingRGB());
InterfacePtr<ICMSProfile>
iCMYKProfile(iColorPresetsSettings->QueryWorkingCMYK());
You may also use ICMSUtils to get IColorPresetsSettings directly
```

### **EXAMPLE 16 Getting `IColorPresetsSettings`**

```
InterfacePtr<IColorPresetsSettings>
iColorPresetsSettings(Utils<CMSUtils>() ->QueryColorPresetsSettings());
```

## How do I turn off color management?

You cannot entirely disable color management; however, InDesign CS4 allows you to emulate the Color Management Off behavior of InDesign CS2 and earlier: use the `ICMSUtils::DoColorPresetsSettingsSetCmd` method. Remember to set the first parameter to `kTrue`. You also may pass other parameters from current color preset settings.

## How do I obtain `IGraphicStateRenderObject`?

To acquire the interface through the active graphic state, use the sample code in [Example 17](#) and [Example 18](#):

### **EXAMPLE 17 Acquiring `IGraphicStateRenderObject` through Active Graphic State**

```
InterfacePtr<IGraphicStateRenderObjects> iGfxStateRenderObjects (
    static_cast<IGraphicStateRenderObjects*>
    (Utils<IGraphicStateUtils> () ->QueryActiveGraphicState(
        IID_IGRAPHICSTATE_RENDEROBJECTS)));
```

To acquire the interface through `IDataBase`:

### **EXAMPLE 18 Acquiring `IGraphicStateRenderObject` through Database**

```
InterfacePtr<IGraphicStateRenderObjects>iGfxRenderObjects (
    static_cast<IGraphicStateRenderObjects*>
    (Utils<IGraphicStateUtils> () ->QueryGraphicState (iDataBase,
        IID_IGRAPHICSTATE_RENDEROBJECTS)));
```

## How do I apply rendering attributes to page items?

If you are applying a rendering attribute to a selection, use methods on `IGraphicAttributeSuite`; otherwise, use methods on `IGraphicStateUtils` or `IGraphicsAttributeUtils` to create appropriate commands and process them.

The code fragment in [Example 19](#) uses a command to change the fill color of a spline:

### **EXAMPLE 19 Applying a Rendering Attribute**

```
// Assume that splineUIDRef is the UIDRef of the page item
// to change fill color for, and we're going to fill it
// with a swatch with UID of colorUID
InterfacePtr<IPersistUIDData> fillRenderAttr(
    (IPersistUIDData*)::CreateObject(
        kGraphicStyleFillRenderingAttrBoss,
        IID_IPERSISTUIDDATA));
fillRenderAttr->SetUID(colorUID);

InterfacePtr< ICommand>
gfxApplyCmd(CmdUtils::CreateCommand(kBoss_GfxStateApplyROAttributeCmd));
gfxApplyCmd->SetItemList(UIDList(splineUIDRef));

InterfacePtr<IPMUknownData> pifUnknown(gfxApplyCmd, UseDefaultIID());
pifUnknown->SetPMUknown(fillRenderAttr);
InterfacePtr<IApplRendObjAttrCmdData> iCommandData(gfxApplyCmd, UseDefaultIID ());
iCommandData->SetAttributeClassID (kGraphicStyleFillRenderingAttrBoss);
iCommandData->SetRenderingClassID (kPMColorBoss);
iCommandData->SetDataBase (splineUIDRef.GetDataBase());
ErrorCode err = CmdUtils::ProcessCommand(gfxApplyCmd);
```

## Can rendering attributes be applied using the commands that apply to other kinds of graphic attributes?

The short answer is *no*. To apply rendering attributes, use `kBoss_GfxStateApplyROAttributeCmd`. For other attributes, use `kGfxApplyAttrOverrideCmd-Boss`.

By using utility methods from `IGraphicAttributeUtils`, however, you need to determine only the name of your attribute; the implementation of these methods selects the appropriate command for you.

## How do I write a new transparency effect?

InDesign provides API support for types like new and improved drop shadows and new feather-like features. See `IXPUtils::CreateImagePaintServer`, which along with `IGraphic-  
sPort::SetAlphaServer` allows you to do various kinds of soft masks, including drop shadows. The `SnapshotUtilsEx` class can obtain a grayscale alpha representation of any page item. Using these two, you can create a drop shadow, outer glow, or feather effect.

Other effects, like inner glow on text, are very difficult to create because of the inability to dynamically clip the effect to text as it is edited.

It is important to let the transparency manager know about changes to an item's transparency state, so it can properly track which pages have transparency. This is done through IXPManager::ItemXPChanged, which finds the transparency in your adornment only if your adornment implements the IFlattenerUsage interface, and responds appropriately.

Also, it is important to understand how to use the IGraphicsPort methods SetAlpha and SetAlphaServer, as well as starttransparencygroup and endtransparencygroup. These methods are critical for getting effects to draw correctly.

Two sample plug-ins are supplied in the SDK. The TransparencyEffect and TransparencyEffectUI SDK samples demonstrate how to create new transparency effects within InDesign documents.

## How do I change the stroke weight of a frame?

If there is a selection, use the IStrokeAttributeSuite::ApplyStrokeWeight method; otherwise, use IGraphicAttributeUtils::CreateStrokeWeightCommand to create a command, then process the command.

## How do I change the stroke color of a frame?

If there is a selection, use the IGraphicAttributeSuite::ChangeStrokeRenderObject method; otherwise, use IGraphicAttributeUtils::CreateStrokeRenderingCommand to create a command, then process the command.

## How do I change the fill color of a frame?

If there is a selection, use the IGraphicAttributeSuite::ChangeFillRenderObject method; otherwise, use IGraphicAttributeUtils::CreateFillRenderingCommand to create a command, then process the command.

See “[Applying Gill Color or a Gradient to a Page Item](#)” on page 137.

## How do I change the default stroke weight?

If nothing is selected, call the IStrokeAttributeSuite::ApplyStrokeWeight method; otherwise, follow the example in [Example 20](#):

### **EXAMPLE 20 Changing Default Stroke Weight**

```
// Create stroke weight attribute
InterfacePtr<IGraphicAttrRealNumber> newStrokeWeight
(Utils<IGraphicAttributeUtils>() ->CreateStrokeWeightAttribute(newWeight)) ;
```

```
// Create command
InterfacePtr< ICommand> command
(CmdUtils::CreateCommand(kGfxStateChangeAttributeCmdBoss)) ;

// Set command data. Assuming iDataBase is the default data base
InterfacePtr< IGraphicStateCmdData> gsCmdData(command, UseDefaultIID()) ;

InterfacePtr<IPMUnknown> iGfxStateData (Utils <IGraphicStateUtils> ()-
>QueryGraphicState (iDataBase));
gsCmdData->SetGraphicStateUIDRef(iDataBase, iGfxStateData) ;
gsCmdData->SetTarget(IGraphicStateData::kDefaultTarget, kTrue) ;
InterfacePtr<IPMUnknownData> attrInterface(command, UseDefaultIID());
attrInterface->SetPMUnknown(newStrokeWeight);
// Process command
error = CmdUtils::ProcessCommand(command) ;
```

See “[Changing Graphic Attributes of the Graphics State](#)” on page 137.

## Why do some methods of **IGraphicsAttributeSuite** take three parameters (int32 whichAttribute, ClassID, interfaceID)?

IGraphicsAttributeSuite is a selection-based suite. There is an implementation for selection and another for defaults (when there is no selection). Attributes have unique values when referring to defaults. All attribute classes may have multiple values when there are multiple selections.

For example, suppose the current selection contains a red-filled rectangle, a blue-filled oval, and a yellow-filled rectangle, and all three items have black stroke. If you query the active graphic attribute suite for the fill rendering attribute, it returns an attribute count of 3, because there are three different fills. It returns an attribute count of 1 for the stroke rendering attribute. In the fill case, if you want to know what the three fills are, you can use QueryAttribute and iterate on whichAttribute from index = 0 to index < 3. The attribute count tells you whether you have unique fill values.

## What is TargetType of GraphicState?

IGraphicStateData::TargetType enumerates three values:

- kCurrentTarget — Current means the current target and could be the same target as Default or Eyedropper.
- kDefaultTarget — Default refers to a state when nothing is selected or there is no document.
- kEyedropperTarget — Eyedropper is a special target for when the eyedropper tool is activated; this is where we temporarily store graphic attributes when using the eyedropper tool.

## How do I get **IGraphicsPort** from **GraphicsData**

The GraphicsData class provides the GetGraphicsPort method to directly access the graphics port in preparation for drawing. [Example 21](#) shows a sample code snippet:

**EXAMPLE 21 Getting the Graphics Port from GraphicsData**

```
void MyShape::DrawShape(GraphicsData* gd, int32 flags)
{
    // default DrawShape draws a frame with an X through it.
    IGraphicsPort* gPort = gd->GetGraphicsPort();
    // Draw to port...
}
```

**How do I detect a drawing device using drawing flags?**

The IShape class defines an enumeration of bit masks for the drawing flag argument supplied to IShape::Draw from the InDesign Draw Manager. The IShape::kPrinting mask indicates printing or PDF is taking place, as shown in [Example 22](#):

**EXAMPLE 22 Detecting a Drawing Device using IShape Drawing Flags**

```
void MyShape::DrawShape(GraphicsData* gd, int32 flags)
{
    if (flags & IShape::kPrinting)
    {
        // Device is PDF or print device...
    }
}
```

**How do I detect a drawing device using the viewport boss?**

The GraphicsData class provides finer detail about the drawing device. As shown in [Example 23](#), the GraphicsData class provides an accessor to the viewport attribute interface, which resides on the viewport boss associated with the current drawing operation. From the viewport attribute interface, the code queries for the IPDFDocPort interface. Its presence means the viewport boss is a kPDFViewPortBoss, indicating PDF output. If the port is not for PDF output, the next step is to test for a printing port. This is done using a method on the viewport attribute interface of the window port boss. The GetViewPortIsPrintingPort method reflects the value of the IShape drawing flag value for printing. If the port is a printing port, the IPrintObject interface verifies it is a PostScript printing port; otherwise, the window port corresponds to a screen draw.

**EXAMPLE 23 Determining Port Type**

```
// From a GraphicsData* gd, get an interface on the window port boss
IViewPortAttributes* iViewPortAtt = gd->GetViewPortAttributes();
// Is this a PDF?
InterfacePtr<IPDFDocPort> pdfDocPort(iViewPortAtt, IID_IPDFDOCPORT);
if (pdfDocPort != nil)
{
    // PDF export...
}
else
{
```

```
// Is it a printing port?
if (iViewPortAtt->GetViewPortIsPrintingPort())
{
    // OK, it's a printing port. But what kind? Ask the print object.
    // See PrintID.h, GraphicsExternal.h
    IGraphicsPort* gPort = gd->GetGraphicsPort();
    InterfacePtr<IPrintPort> iPrintPort (gPort, IID_IPRINTPORT);
    InterfacePtr<IPrintObject> iPrtObj (iPrintPort->GetPrintObject(),
    IID_IPRINTOBJECT);
    AGMDeviceType devType = kAGMPPostScript;
    iPrtObj->GetObject (kAGMPrtObjectItmsDeviceType, nil, &devType);
    if (devType == kAGMPPostScript)
    {
        // PS output
    }
    else
    {
        // Screen drawing...
    }
}
```

## How do I invalidate a layout view?

Invalidation can be caused by changes to the model (persistent data in a document) or direct invalidation. Both use the same mechanism for invalidating a view.

Views can be invalidated directly by using the ILayoutUtils::InvalidateViews method. The code segment in [Example 24](#) invalidates all views of the front document:

### **EXAMPLE 24** Invalidating Front View

```
IDocument* fntDoc = Utils<ILayoutUtils>()->GetFrontDocument();
if (fntDoc != nil)
    Utils<ILayoutUtils>()->InvalidateViews( fntDoc );
```

## How do I obtain a viewport?

You can get a viewport directly from a window or a control view through the ViewPortAccess template and AcquireViewPort class. See [Example 25](#).

### **EXAMPLE 25** Acquiring a Viewport

```
ViewPortAccess<IWindowPort> windowPort (WindowOrView, IID_IWINDOWPORT);
AcquireViewPort aqViewPort (windowPort);
```

Constructing an AcquireViewPort object lets you acquire the focus for the viewport, so you can do various drawing.

You also can access a viewport by doing either of the following:

- Given a graphics context, use IGraphicsContext::GetViewPort.
- Given a GraphicsData\*, use GraphicsData::GetGraphicsPort.

## How do I get (instantiate) graphics context in a control view?

An IGraphicsContext can be formed using the following:

```
AGMGraphicsContext gc(viewPort, this, invalidRgn);
```

viewPort and invalidRgn are the two parameters passed into the IControlView::Draw method. The “this” parameter is the “this” pointer to the control view object.

## How do I sort page items by z-order

Use ArrangeUtils. The code segment in [Example 26](#) illustrates the usage:

### **EXAMPLE 26 Arranging by Z-order**

```
UIDList unsortedItems;
Arranger arranger( &unsortedItems, Arranger::kNotSorted ) ;
arranger.SortItemsBackToFront( &unsortedItems );
```

## How do I add or remove adornments?

Adornment is part of the drawing for decorated page items. Any page item that can have an attached adornment has the IPagitemAdornmentList interface, which provides the methods for adding and removing adornments. These methods are encapsulated in the commands listed in [Table 2](#):

**TABLE 2 Page Item Adornment Commands**

Command Boss	Description
kAddPageitemAdornmentCmdBoss	Add page item adornment.
kRemovePageitemAdornmentCmdBoss	Remove adornments.
kAddPageitemHandleAdornmentCmdBoss	Add page item handle adornments.
kRemovePageitemHandleAdornmentCmdBoss	Remove page item handle adornments.

## How do I import InDesign documents?

You import InDesign documents the same way as other graphics files. To place an InDesign file into a document, follow the steps in [“Placing a Graphics File into a Spread” on page 122](#) and [“Placing a Graphics File into an Existing Graphics Frame” on page 123](#).



# Selection

---

## Getting Started

To learn how selection works, read the “Selection Fundamentals” chapter in *Adobe InDesign CS4 Programming Guide*. For help with your specific programming needs, look in this chapter for a use case that matches your needs.

### Exploring Selection with SDK Sample Code

The SDK provides several examples that help you learn how to work with selection. See [Table 3](#) and [Table 4](#).

**TABLE 3 Samples that use Selection Suites Provided by the API**

SDK Sample	Description
StrokeWeightMutator	Displays and changes stroke weight using a suite provided by the API (IStrokeAttributeSuite). Observes the selection and widgets in a single-observer implementation.
TableAttributes	Displays and changes table attributes using a suite provided by the API (ITableSuite). Observes the selection and widgets with multiple distinct observer implementations.

**TABLE 4 Samples that create New Selection Suites**

SDK Sample	Description
TableBasics	Implements a basic suite.
BasicPersistInterface	Extends the layout model by adding a custom data interface to a page item that stores an attribute. This implements an advanced suite to access and change this attribute, and it uses a selection extension to notify an ActiveSelectionObserver when this selection attribute changes.
BasicMenu	Enables an action or menu based on the state of the selection. Refer to this sample and to <i>Adobe InDesign CS4 Porting Guide</i> for information on porting Adobe InDesign® 2.x code that used IID_NEED_LAYOUTSELECTION or similar.
TransparencyEffectUI	Uses a suite from a dialog that can be previewed.
TransparencyEffect	Implements a suite for use by a dialog that can be previewed.

### Related APIs

- `kIntegratorSuiteBoss` — The API reference documentation page for this boss has a complete list of selection suites provided by the API.
- To use the selection suites provided by the API — `ISelectionManager`, `ISelectionUtils`, `ILayoutSelectionSuite`, `ITextSelectionSuite`, `ITableSelectionSuite`, and `IXMLNodeSelectionSuite`.
- To have your code be notified when the selection changes — `ActiveSelectionObserver` and `ISelectionMessage`.
- To create a new selection suite — `ILayoutTarget`, `ITextTarget`, `ITableTarget`, `IXMLNodeTarget`, `IIIntegratorTarget`, `ISelectionExtension`, and `ISelectionMessage`.

---

## Working with Selection Suites Provided by the API

### Finding Selection Suites Provided by the API

#### Description

You want to access or change a property of an object selected by the user, and you want to know whether the API provides a selection suite you can use.

#### Solution

See the API reference documentation page for `kIntegratorSuiteBoss`, which lists all suites available for use by client code; for example, `IGraphicAttributeSuite` and `ITextAttributeSuite`. Look first at the suite interface names; an interface name can help you decide whether the suite is likely to help you. Next, look at the methods on the interface, to see whether they do what you want to do. For information on how to acquire and then call a suite interface, see “[Calling a Selection Suite](#)” on page 155.

### Accessing or Changing the Properties of a Selected Object

#### Description

You want to access or change a property of an object selected by the user.

#### Solution

- Use a suite interface obtained from the selection manager. See “[Calling a Selection Suite](#)” on page 155.
- Client code can use a suite interface provided by the API, if one is available that meets your needs. See “[Finding Selection Suites Provided by the API](#)” on page 154.
- If the API does not provide a suite interface that meets your needs, your client code must use a custom suite implementation you write yourself. For an example, see the `BasicPersistInterface` sample. See “[Creating Selection Suites](#)” on page 160.

## Calling a Selection Suite

### Description

You want to call a selection suite interface (e.g., `ITableSuite`). How do you get its interface pointer?

### Solution

To get a selection suite interface pointer, you must query a selection manager (see the `ISelectionManager` interface) for the suite in which you are interested. If the suite is available, its interface pointer is returned; otherwise, nil is returned.

Choosing the selection manager interface to query for the suite depends on the kind of code you are writing (see “[Obtaining the Selection Manager](#)” on page 156). To work with the active selection, use `ISelectionUtils` to get its selection manager. The following code queries the active selection manager to get `ITableSuite`. If the suite is obtained, it is asked whether the capability `GetCellWidth` is available. If the capability is available, it is used.

```
ISelectionManager* iSelectionManager = Utils<ISelectionUtils>() ->GetActiveSelection();  
InterfacePtr<ITableSuite> iTableSuite(iSelectionManager, UseDefaultIID());  
if (iTableSuite && iTableSuite->CanGetCellWidth()) {  
    PMReal cellWidth = iTableSuite->GetCellWidth();  
    // ...  
}
```

The `ISelectionUtils::QuerySuite` utility provides a handy shortcut for obtaining a suite from the active selection. The following code queries the active selection manager for the suite, because `nil` is passed as the second parameter.

```
InterfacePtr<ITableSuite> tableSuite(  
    static_cast<ITableSuite*>  
    Utils<ISelectionUtils>() ->QuerySuite(ITableSuite::kDefaultIID, nil)));
```

Before using the active selection to obtain a suite as shown above, be sure this is the correct selection manager to use. Sometimes, the selection manager you should use is passed as a parameter (often as an `IActiveContext` parameter) or made available as a member of a C++ API base class. See “[Obtaining the Selection Manager](#)” on page 156 for details.

### Related Sample Code

`TblAttQueryMutHelper`

### Related APIs

- `ISelectionUtils`
- `ISelectionManager`

# Obtaining the Selection Manager

## Description

You want to acquire a selection manager interface (`ISelectionManager`); this is likely so you can obtain a suite interface from it (see “[Calling a Selection Suite](#)” on page 155).

## Solution

The selection manager (see the `ISelectionManager` interface) is the interface that identifies a boss class to be an abstract selection boss (ASB). Each document view has its own selection manager. The active selection is the selection manager for the document view with which the user is editing (i.e., the front document view).

To work with the active selection, use the utility `ISelectionUtils` to get its selection manager. Most of the time, however, either client code is passed a parameter that identifies the selection manager to use or the selection manager is implied by the kind of code being written.

Follow these steps:

- To implement client code that works with whatever is actively selected, use `ISelectionUtils::GetActiveSelection` to get the selection manager:

```
Utils<ISelectionUtils> iSelectionUtils;
if (iSelectionUtils != nil) {
    ISelectionManager* iSelectionManager = iSelectionUtils->GetActiveSelection();
}
```

- When you implement an action component (`IActionComponent`) or a dialog controller (`IDialogController`), use the `IAactiveContext` parameter you are passed to get the selection manager (`IAactiveContext::GetContextSelection`):

```
void FooActionComponent::DoAction(IAactiveContext* ac, ActionID actionID, ...)
{
    ...
    InterfacePtr<IFooSuite> fooSuite(ac->GetContextSelection(), UseDefaultIID());
    if (fooSuite) {
        // Use the suite.
    }
    ...
}
```

- When you implement a selection observer (`ActiveSelectionObserver`), the `fCurrentSelection` data member gives the selection manager:

```
void FooSelectionObserver::HandleSelectionChanged(const ISelectionMessage* msg)
{
    InterfacePtr<IFooSuite> fooSuite(fCurrentSelection, UseDefaultIID());
    if (fooSuite) {
        // Use the suite.
    }
}
```

- When you implement a tracker (ITracker), use ISelectionUtils::QueryViewSelectionManager to acquire the selection manager.
- When you implement a widget that is part of a layout document window, such as a descendant in the layout widget hierarchy, you probably are interested only in the selection manager of its ancestor (the layout widget). In this case, call ISelectionUtils::QueryViewSelectionManager to acquire the selection manager.

## Related Sample Code

- For sample code that uses suites provided by the API — StrokeWeightMutator and TableAttributes
- For samples that create and use their own selection suites — BasicMenu and BasicPersistInterface

## Related APIs

- ISelectionManager
- ISelectionUtils

## Making a Selection Programmatically

The interfaces in [Table 5](#) can be used to vary the selection programmatically.

**TABLE 5** *Interfaces used to make a Selection*

API	Purpose
ILayoutSelectionSuite	Select page items.
ISelectionManager	Select/deselect all.
ITableSelectionSuite	Select table cells.
ITextSelectionSuite	Select text in layout view,gGalley view, story editor view, and note view.
IXMLNodeSelectionSuite	Select XML structure.

## Related Sample Code

- For use of ISelectionManager — SnpManipulateXMLSelection
- For usage of ILayoutSelectionSuite — SnpManipulateTextFrame
- For usage of ITextSelectionSuite — SnpManipulateTextModel

# Updating the User Interface when the Selection Changes

## Description

You want to update your user interface or another piece of selection client code when the selection changes.

## Solution

Implement a selection observer (see `ActiveSelectionObserver`) and update your user interface when you receive messages from a suite. For sample code, see `StrokeWeightMutator` and `TableAttributes`.

**NOTE:** Selection observers may get called for changes that are not of interest. It is important you examine the content of any `ISelectionMessage*` parameter passed and update your user interface only if necessary. For an example of how to do this, see the sample code in `StrMutSelectionObserver::HandleSelectionAttributeChanged`.

If you cannot find an existing suite that sends the messages you need, implement a custom suite with a selection extension.

Most likely, you must make a design decision about how to observe changes to your widgets and to the selection. For example, suppose you have a widget that displays the stroke weight associated with the selection and allows that stroke weight to be changed. To synchronize the stroke weights displayed in the widget with the values associated with the selection, use a selection observer. To recognize a request by the user to change the stroke weight, use a widget observer. The main design decisions are as follows:

- Should you use one observer that observes both widgets and the selection or two distinct observers, a selection observer and a widget observer?
- Which selection manager should you use to get the suite that lets you get and change the attribute of interest?

## Using One Observer to Update the User Interface when the Selection Changes

The `StrokeWeightMutator` sample plug-in is based on a design that uses a single observer on the widget boss class to observe both the widget's subject and the selection. The observer subclasses `ActiveSelectionObserver` and, therefore, observes the active selection. To observe changes to your widget, follow these steps:

1. To attach and detach the appropriate protocols on the widget's subject, override `ActiveSelectionObserver::AutoAttach` and `ActiveSelectionObserver::AutoDetach`.
2. To handle messages from your widget, override `ActiveSelectionObserver::HandleSelectionUpdate`.
3. Call the superclass `ActiveSelectionObserver` methods from your specializations. The observer uses the selection manager referred to by `ActiveSelectionObserver::fCurrentSelection` to obtain any suite it needs.

## Using Two Observers to Update the User Interface when the Selection Changes

The TableAttributes sample plug-in is based on a design that uses two observers on the widget boss class.

The first observer is a selection observer that subclasses ActiveSelectionObserver. It updates the value displayed by the widget when it receives messages from a suite. It uses the selection manager referred to by ActiveSelectionObserver::fCurrentSelection to obtain any suite it needs.

The second observer observes the widget's subject and calls a suite to change the value of an attribute of the selection when the user changes the value of the widget. This is a good approach, and much of the application's user interface code uses it. A disadvantage to this approach is the lack of communication between the two observers. For example, how does the widget observer find the selection manager to use when it needs a suite? Most widgets use the application's active selection manager, because they are on panels and intended to reflect or change the active context. In this scenario, the widget's widget observer uses the selection manager found with ISelectionUtils::GetActiveSelection to obtain any suite it needs.

### Related Sample Code

StrokeWeightMutator, TableAttributes, and BasicPersistInterface

## Obtaining ITextSelectionSuite

Select text using interface ITextSelectionSuite; however, if you query for this interface using its default PMIID, you will not obtain it for note, galley, and story editor view selections. This interface does not use the default PMIID on these CSBs; instead, it uses IID\_IITEMPTEXTSELECTION\_SUITE. To obtain the suite, use code similar to the following:

```
InterfacePtr<ITextSelectionSuite> textSelectionSuite(selectionManager,
UseDefaultIID());
if (!textSelectionSuite) {
    // Temporary until text selection suites are unified.
    textSelectionSuite.reset(InterfacePtr<ITextSelectionSuite>(selectionManager,
        IID_IITEMPTEXTSELECTION_SUITE).forget());
}
if (textSelectionSuite) {
    textSelectionSuite->ChangeTextSelection(
        ITextSelectionSuite::kExtendSelection,
        ITextSelectionSuite::kWord, ITextSelectionSuite::kNext,
        Selection::kScrollIntoView);
}
```

### Related APIs

- ITextSelectionSuite
- ISelectionManager

# Creating Selection Suites

## Determining you need a Custom Suite

Before implementing a custom suite, look for a suite provided by the API to help you. In some cases, none of the suites provided by the API meets your exact needs. For example, suppose you want to detect whether one or more characters of text are selected, enable an action when text is chosen, and modify the selected text in some way when the action is chosen. Several interfaces (like `ITextAttributeSuite`) are available and provide methods to modify the selected text, but not in the specific way in which you want your action to modify the selected text. As a result, you must implement a custom suite.

## Defining the Interface of a Suite

Two kinds of method are required for a suite interface. The first kind of method returns `kTrue` if an action can be done; the second kind of method does the action:

```
class IYourSuite : public IPMUnknown
{
public:
    enum { kDefaultIID = IID_IYOURSUITE };
    virtual bool16 CanDoSomething(void) const = 0;
    virtual ErrorCode DoSomething(void) = 0;
};
```

In your plug-in's ID.h file, declare a PMIID for the suite interface:

```
DECLARE_PMIID(kInterfaceIDSpace, IID_IYOURSUITE, kYourPrefix + 10)
```

## Related Sample Code

<SDK>/source/sdksamples/tableattributes/TblAttQueryMutHelper.cpp

## Related APIs

- `ITableSuite`
- `ISelectionUtils`

## Implementing an Integrator Suite

Integrator suites have a very standard construction and usually are based on the templates provided in the API (see `SelectionASBTemplates.tpp`). The template is used to forward the call to the CSB suite and return its result to the caller, as follows:

```
bool16 YourSuiteASB::CanDoSomething(void) const
{
    return(AnyCSBSupports(make_functor(&IYourSuite::CanDoSomething), this));
}

ErrorCode YourSuiteASB::DoSomething(void)
```

```
{
    return (Process (make_functor (&IYourSuite::DoSomething) , this));
}
```

To prevent dead-stripping, declare an ID for the implementation and register it:

```
// put into the plug-in's ID.h file
DECLARE_PPID(kImplementationIDSpace, kYourSuiteASBImpl, kYourPrefix + 10)

// put into the plug-ins FactoryList.h file
REGISTER_INTERFACE(YourSuiteASB, kYourSuiteASBImpl)
```

## Related Sample Code

<SDK>/source/sdksamples/basicmenu/BscMnuSuiteASB.cpp

## Related API

[SelectionASBTemplates.tpp](#)

## Implementing a CSB Suite

The CSB suite implementation is made available to text selections using an AddIn on the text suite boss (kTextSuiteBoss):

```
AddIn
{
    kTextSuiteBoss,
    kInvalidClass,
    {
        IID_IYOURSUITE, kYourSuiteTextCSBImpl,
    }
},
```

**NOTE:** If you use only one AddIn, the suite is available to text selections in layout view, but not in story editor, galley, or note view. For your suite to be available for text selections in these other views, add your suite implementation into more suite boss classes. Often you can re-use the same implementation to do so.

Examine the text target (ITextTarget) to see if one or more characters are selected. If so, do something with the text selection:

```
bool16 YourSuiteTextCSB::CanDoSomething(void) const
{
    bool16 result = kFalse;
    InterfacePtr<ITextTarget> textTarget (this, UseDefaultIID());
    if (textTarget) {
        RangeData range = textTarget->GetRange();
        if (range.Length() > 0)
            result = kTrue;
    }
    return (result);
}
```

```
ErrorCode YourSuiteTextCSB::DoSomething(void)
{
    bool16 result = kFailure;
    InterfacePtr<ITextTarget> textTarget(this, UseDefaultIID());
    if(textTarget) {
        // Perform your unique action on this selection
        ...
    }
    return (result);
}
```

To prevent dead-stripping, declare IDs for the implementations and register them:

```
// into the plug-in's ID.h file
DECLARE_PPID(kImplementationIDSpace, kYourSuiteTextCSBImpl, kYourPrefix + 11)

// into the plug-ins FractoryList.h file
REGISTER_INTERFACE(YourSuiteTextCSB, kYourSuiteTextCSBImpl)
```

The implementation of a CSB suite deals with the selection format of that CSB. The only selection information the suite should need is from other interfaces on the CSB, primarily the target interface that identifies the selection target.

CSB suite implementation class names should align with the CSB they support; for example, XxxxSuiteLayoutCSB.cpp or XxxxSuiteTextCSB.cpp.

Your implementation can depend on the availability of interfaces on the suite boss class. For example, a text CSB suite can rely on any interface on kTextSuiteBoss. To access an interface on the CSB itself (for example, kTextSelectionBoss), check whether the returned interface pointer is nil, and gracefully handle the case when it is not available. Also do this to access one of the caches, such as ICellFocus on kTextSelectionBoss. This is required because scripting may reuse the suite boss classes, so some CSB interfaces may not be available all the time. For example, kTextScriptingSuiteBoss derives from kTextSuiteBoss and could use your suite.

### Related Sample Code

<SDK>/source/sdksamples/basicmenu/BscMnuSuiteLayoutCSB.cpp

### Related API

ILayoutTarget

## Writing the Client Code

This example implements an action component (IActionComponent) that uses the suite to enable an action.

Add the following ActionDef to your plug-in's .fr file:

```
kYourActionComponentBoss,
kYourDoSomethingActionID,
kYourDoSomethingMenuItemKey,
kOtherActionArea,
kNormalAction,
kDisableIfSelectionDoesNotSupportIID | kCustomEnabling,
```

```
IID_IYOURSUITE,
kSDKDefInvisibleInKBSCEditorFlag,
```

The kDisableIfSelectionDoesNotSupportIID flag indicates the action is disabled if the suite is not available. Your action component is not called unless the selection supports your suite. If the suite is available, the kCustomEnabling flag indicates your action component is to be called. A call to the suite finds out whether the action should be enabled:

```
void YourActionComponent::UpdateActionStates(
    IActiveContext* ac, IActionStateList* listToUpdate, GSysPoint mousePoint,
    IPMUknown* widget)
{
    ...
    case kYourActionID:
    {
        InterfacePtr<IYourSuite> iYourSuite(ac->GetContextSelection(), UseDefaultIID());
        if (iYourSuite != nil && iYourSuite->CanDoSomething() == kTrue)
        {
            listToUpdate->SetNthActionState(count, kEnabledAction);
        }
    }
    break;
    ...
}
```

Your suite can now enable an action and change the selected text when that action is clicked. Here is how to call your suite from your action component:

```
void YourActionComponent::DoAction(
    IActiveContext* ac, ActionID action, GSysPoint mousePoint, IPMUknown* widget)
{
    ...
    case kYourActionID:
    {
        InterfacePtr<IYourSuite> iYourSuite(ac->GetContextSelection(), UseDefaultIID());
        if (iYourSuite) {
            iYourSuite->DoSomething();
        }
    }
    break;
    ...
}
```

## Related Sample Code

`<SDK>/source/sdksamples/persistentlistui/PstLstUIActionComponent.cpp`

## Related API

IActiveContext

## Determining which CSBs to Support

Look for information about the CSBs on which your suite should be available. See [Table 6](#).

**TABLE 6 Concrete Selection Boss Classes and their Parent Suite Boss Classes**

CSB	Suite Boss Class	Target Interface
kNewLayoutSelectionBoss	kLayoutSuiteBoss	ILayoutTarget
kTextSelectionBoss	kTextSuiteBoss	ITextTarget
kTableSelectionBoss	kTableSuiteBoss	ITableTarget
kXMLStructureSelectionBoss	kXMLStructureSuiteBoss	IXMLNodeTarget
kNoteTextSelectionBoss	kNoteTextSuiteBoss	ITextTarget
kGalleyTextSelectionBoss	kGalleyTextSuiteBoss	ITextTarget
kStoryEditorSelectionBoss	kGalleyTextSuiteBoss(kStoryEditorSelectionBoss sub-classes kGalleyTextSelectionBoss)	ITextTarget
kDocWorkspaceBoss	kDocumentDefaultSuiteBoss	Not applicable. The suite targets whichever workspace interface contains its defaults
kWorkspaceBoss	kApplicationDefaultSuiteBoss	Not applicable

## Adding a Selection Extension ImplementationID

In your ID.h file, declare an ImplementationID for the selection extension.

This declaration is in addition to the ImplementationID needed for the basic suite implementation. The ImplementationID is of an ISelectionExtension interface, as shown below:

```
DECLARE_PPID(kImplementationIDSpace, kBPISuiteLayoutSelectionExtImpl, kBPIPIndex + 10)
```

### Related Documentation

<SDK>/source/sdksamples/hiddentext/HidTxtSuiteTextCSB.cpp

### Related Sample Code

BPIID.h

### Related API

ISelectionExtension

## Adding a Selection Extension Resource

This resource associates the selection extension implementation with its suite implementation:

```
resource kSelectionSuiteExt(1)
{
    kNewLayoutSelectionBoss,
    {
        kBPISuiteLayoutCSBImpl, kBPISuiteLayoutSelectionExtImpl,
    }
};
```

**NOTE:** You do not need to aggregate the selection extension implementation on any boss class; the selection subsystem creates it when needed.

### Related Sample Code

<SDK>/source/sdksamples/candlechart/CdlChart.fr

### Related API

kSelectionSuiteExt

## Implementing the Selection Extension Member Functions

Modify the suite implementation file as follows:

1. Include the selection extension templates:

```
#include "SelectionExtTemplates.tpp"
```

2. Add the following member functions to the suite declaration:

```
virtual void Startup(void);
virtual void Shutdown(void);
virtual void SelectionChanged(SuiteBroadcastData*, const PMIID&, void*);
virtual void SelectionAttributeChanged(SuiteBroadcastData*, const PMIID&, void*);
virtual void HandleIntegratorSuiteMessage(
    void*, const ClassID&, ISubject*, const PMIID&, void*, ISelectionManager* );
virtual ProtocolCollection* CreateObserverProtocolCollection(void);
```

3. Instantiate the template to make the selection extension implementation available to the application's object model. The parameter to the template is the suite implementation class:

```
template class SelectionExt<BPISuiteLayoutCSB>;
CREATE_PMINTERFACE (SelectionExt<BPISuiteLayoutCSB>,
kBPISuiteLayoutSelectionExtImpl)
```

**NOTE:** This implementation is in addition to the CREATE\_PMINTERFACE needed for your basic suite implementation.

4. Define the selection extension member functions in your suite. You do not need to write any code for the ISelectionExtension interface that provides the bridge between selection and these member functions in your suite.

### Related Sample Code

- BPISuiteCSB.cpp
- BPISuiteLayoutCSB.cpp

## Calling Selection Extensions when Selection Attributes Change

Each CSB is responsible for defining the mechanism used to call selection extensions when selection attributes change.

- The layout CSB uses a document observer all selection extensions can use. By returning additional protocols through their CreateObserverProtocolCollection suites, they use this shared observer to attach additional protocols to the document's subject.
- The text CSB uses a text focus (ITextFocus) on the kTextSelectionFocusBoss boss class to connect the selection to attribute changes.
- The table CSB uses a cell focus (ICellFocus).

Also, the text and table CSBs share the layout CSB's mechanism of observing the document's subject. This is required for commands that do not notify through the text focus or cell focus, but instead broadcast on the document's subject; for example, kChangeNumberOfColumnsCmdBoss and kOpticalMarginAlignmentCmdBoss. If you add custom attributes and find your selection extension is not being called when these attributes change, check that the command notifies the change on the appropriate subject.

## Registering the Selection Extension Implementation

The selection extension template must be used.

To prevent dead-stripping of your selection extension implementation, call the REGISTER\_PMINTERFACE macro:

```
REGISTER_PMINTERFACE (SelectionExt<BPILayoutCSB>, kBPILayoutCSBSelectionExtImpl)
```

### Related Sample Code

BPIFactoryList.h

## Determining Why your Selection Extension is not being Called

Try the following:

- Verify you declared a kSelectionSuiteExt resource for it in your plug-in's .fr file.
- Verify you registered your selection extension.

## Determining Why your Selection Extension's SelectionAttributeChanged is not being Called

Try the following:

- See whether the concrete selection you are targeting can extend the selection attributes for which changes can trigger notification.
- Verify you defined CreateObserverProtocolCollection to indicate the PMIIDs of any additional protocols to be observed (e.g., the PMIID of an interface you added to a page item).
- Verify your custom commands that change any custom data interfaces trigger notification of change through the subject the CSB is observing.



# User Interfaces

---

## Getting Started

### Factoring Model and User Interface Code

Before starting to develop a user interface, we recommend you factor your code into at least two plug-ins:

- A user-interface plug-in that is responsible for presentation to and interaction with the end user.
- A model plug-in that manipulates the model; for instance, implements extension patterns that enable you to store persistent data in a document or participate in a process like drawing or printing.

If you write a model plug-in that implements commands and/or suites, write a user interface plug-in that drives these commands and/or suites as a *client*. For example, to add a new feature <X> and drive this through a panel, write two plug-ins: one named <X> and the other <X>UI. This particular factorization is employed widely throughout the application code base, such as the TransparencyEffects/UI or CustomDataLink/UI SDK sample plug-ins.

### Developing a User Interface Plug-in

First, take full advantage of the tools delivered in the SDK. If you have a good idea of what the user interface is going to be, then with little effort, DollyXs generate most of the boilerplate you need for menus, dialogs, or panels, and they can create an arbitrary number of menu items for you.

Writing a user interface for an Adobe® InDesign CS4 plug-in is a complex task. This is because there is a strong connection between the user interface programming model and the persistence model for InDesign CS4. In addition, writing a cross-platform user interface API is difficult, and it is not easy to shield developers from the inherent complexity of the task. Not only is the API cross-platform, it operates across multiple locales, adding even more complexity. The following are the steps that a developer of a plug-in interface typically performs:

1. Discover the widget boss classes and ODFRez custom resource types needed in the initial analysis phase.
2. Work out what must be subclassed (both the widget boss class, and the ODFRez custom resource type) to achieve desired functionality, or whether widgets can be used as is (for example, static text widgets that display invariant text).
3. Determine widget hierarchy and geometry; this consists of determining the containment relationships for widgets and their bounding boxes.

4. Define symbolic constants, like constants for boss class IDs if there are subclassed widget boss classes, widget IDs, implementation IDs, and string table keys and their translations in the localized string tables for target locales.
5. Define new boss classes and associated ODFRez types, if needed.
6. Create ODFRez data statements to specify the initial states of the user interface elements and localized string data.
7. Implement required interfaces. For example, for the tree view control, there are two interfaces client code must implement.
8. Write observer implementations to handle Update messages from the change manager.

## Subclassing Widget Boss Classes and ODFRez Custom Resource Types

If all your controls are on a dialog and you want to collect the state of all the controls only when the dialog is being dismissed, you do not need to subclass. Typically, an existing boss class is subclasses to add an IObserver interface to a subclass of the widget boss class, to enable notification about changes to the data model of the widget boss object to be received. When an existing widget boss class is being subclassed, a new boss class should be defined in the boss type definition file (typically named *<project>.fr*). In more specialized cases, you must subclass to provide your own implementation of required interfaces, such as for a tree view control. To also change the drawing behavior, you may want to override the IControlView interface.

If a widget boss class is subclassed, there also must be a new ODFRez custom resource type created that is bound to the new boss class by class ID. When existing ODFRez custom resource types are extended, define the new ODFRez custom resource types to be added to the top-level framework resource file.

## Showing, Hiding, Enabling, and Disabling a Widget

Use the IControlView interface of a widget boss object; it has methods like SetVisible and Enable, which can toggle the state of a widget boss object. There are many other methods on this interface that can be used; for example, to vary its dimensions.

## Adding Tips to a Widget

There are two ways to add tips:

- Tips can be defined entirely in the resource data, in which case they are static tips.
- If a custom tip is required, a widget boss class can be extended to override the base implementation of the interface ITip (on kBaseWidgetBoss).

## Overriding an Event Handler (or not)

Typically, to be notified about widget events, you need to implement only IObserver; you subclass an existing widget boss class, adding in your implementation of IObserver to the new boss class. Overriding the event handler for a widget is required only when adding highly specialized behavior.

## Writing Safe Code and Debugging

Methods prefixed by “Get,” or “Find,” like IPanelControlData::GetWidget or FindWidget, do not increment the reference count, and the pointer returned should not be used as a constructor argument for an InterfacePtr. Methods named “Query”*<name>*, like IDialogController:QueryListControlDataInterface, are used as constructor arguments for an InterfacePtr, because the constructor tries to call AddRef and the destructor Release on the encapsulated pointer.

Encapsulate tests for interface pointers that can be nil in a construct, like the do ... while block in the following code, breaking when a nil pointer is encountered rather than causing the application to crash. We recommend the following pattern:

```
do {  
    // code here...  
    ASSERT(iMyInterfacePtr);  
    if(iMyInterfacePtr == nil) {  
        break;  
    }  
    // more code here...  
} while(kFalse);
```

Use statements like ASSERT and TRACEFLOW to check your assumptions. For instance, if you have an IControlView interface, see the API documentation to determine which boss classes aggregate this interface in the core set.

---

## Menus

### Creating Menu Entries

The easiest way to create menu entries is to use DollyXs. The main requirement is to create a boss class with an implementation of IActionComponent; for an example, see kBscMnuActionComponentBoss.

You also must create ODFRez data statements (ActionDef and MenuDef) specifying the menu properties. For every ActionID defined, there should be a corresponding MenuDef and ActionDef entry. The MenuDef specifies where a menu item appears in the set of menus, and the ActionDef specifies how it is handled and its enabling conditions; for instance, if it should be enabled only when there is a front document. [Example 27](#) has extracts from the MenuDef and ActionDef resources for the BasicMenu SDK sample:

**EXAMPLE 27 Menu-related Resources**

```

// In the ID.h file:
DECLARE_PPID(kActionIDSpace, kBscMnuAboutActionID,kBscMnuPrefix + 0)

// In .fr file:
resource MenuDef (kSDKDefMenuResourceID)
{
{
    //
    // The About Plug-ins sub-menu item for this plug-in.
    kBscMnuAboutActionID,// ActionID
    kBscMnuAboutMenuPath,// Menu Path.
    kSDKDefAlphabeticPosition, // Menu Position.
    kSDKDefIsNotDynamicMenuFlag, // Whether dynamic or not
    // other entries omitted

}
};

resource ActionDef (kSDKDefActionResourceID)
{
{
    //
    kBscMnuActionComponentBoss, // ClassID supporting this ActionID.
    kBscMnuAboutActionID,// ActionID.
    kBscMnuAboutMenuKey,// Sub-menu string.
    kHelpMenuActionArea,// Area name (see ActionDefs.h) .
    kNormalAction,// Type of action (see ActionDefs.h) .
    kDisableIfLowMem,// Enabling type (see ActionDefs.h) .
    kInvalidInterfaceID,// Selection InterfaceID
    kSDKDefInvisibleInKBSCEditorFlag,
    // Other entries omitted
}
};

```

You also need to define string keys for the menu path components, and translations of these keys when adding strings that do not already have translations. If you need to put your menu item in an existing menu, then you need have the parent menu's full path in the MenuDef. You would also need to know the positions of the menu items surrounding your intended menu location. To gather such information, the easiest way is to use the debug facility available in InDesign Build as describe below.

1. Choose Test:TRACE: menu - first turn on the trace output to either Debug Window, note-pad.exe or Debug log.
2. Choose Test:TRACE menu and turn on the trace category for 'menu building'
3. Click on the menu you care about, and look at the trace output. There's a bunch of output there, but the menu key strings are part of it.

Or alternatively, you can choose a test menu to output all the menu information to the trace output of your choice by choosing the following test menu:

Test>UI>Actions>Dump MenuMgr Info(all)

You should see a long log in your start up volume containing information such as:

```
Menu path #CondTextUI_PanelMenu
    #CondTextUI_NewConditionTagMenu(kNewConditionTagActionID[ConditionalTextUI + 2
(0x20802)]), pos 100.0000, Flags normal
    #CondTextUI_DeleteConditionTagMenu
(kDeleteConditionTagActionID[ConditionalTextUI + 11 (0x2080b)]), pos 110.0000,
Flags normal
    (kEditConditionSeparatorActionID[ConditionalTextUI + 12 (0x2080c)]), pos
120.0000, Flags separator
    #CondTextUI_EditConditionTagMenu(kEditConditionTagActionID[ConditionalTextUI +
13 (0x2080d)]), pos 130.0000, Flags normal
    (kLoadSeparatorActionID[ConditionalTextUI + 8 (0x20808)]), pos 200.0000, Flags
separator
    #CondTextUI_LoadConditionTagsMenu(kLoadConditionTagsActionID[ConditionalTextUI +
6 (0x20806)]), pos 300.0000, Flags normal
    #CondTextUI_LoadConditionTagsAndSetsMenu
(kLoadConditionTagsAndSetsActionID[ConditionalTextUI + 7 (0x20807)]), pos 400.0000,
Flags normal
```

The above entry tells you there is a menu path called “#CondTextUI\_PanelMenu”, it has an action associated with it which is called #CondTextUI\_NewConditionTagMenu. Followed by the ActionID for the action, its position in the menu and the menu flag as defined in the MenuDef. Then same action information follows for another action associated with the same menu.

## Handling Menu Items

When implementing a menu, you provide an implementation of the IActionComponent interface. The application framework calls the methods on the IActionComponent interface when the menu item is activated and at other points, such as if there is custom enabling specified in the ODFRez data statements.

Provide menu handling for each menu item you care about in the implementation of your IActionComponent interface.

## Adding a Contextual Menu to a Plug-in

There are several contextual menus, one for each context the application recognizes. The process of adding menu items to these context-sensitive menus is like that of adding normal menu items: in the MenuList resource, specify where the items should go and what the contents of the menu entries should be, by providing keys into the string tables.

## Finding the Panel to which a Pop-up Menu Belongs

IPalettePanelUtils contains a method for locating a panel given a WidgetID. Several SDK samples show how to navigate from the menu boss object to the panel boss object.

---

## Alerts

### Creating a Basic Alert

Alerts provide notifications to an end user; for instance, a warning or message about an error. They also can solicit a response from the end user, such as Yes, No, or some other response, so they can provide a means of data entry.

The function to create and work with alerts comes from the CAlert helper class; for details, see its API documentation. The CAlert class is straightforward to use, involving static methods with many default arguments. [Example 28](#) shows how to create a warning alert from client code:

#### **EXAMPLE 28** Displaying an Alert

```
// Here, translation(s) must exist for kWarningMessageKey.  
PMString string(kWarningMessageKey);  
CAlert::WarningAlert(string);
```

Alerts are an exception in the InDesign API, because you do not need to be concerned with boss classes or ODFRez types; these alerts are created using methods on the CAlert API helper class.

**NOTE:** The user interface PMString arguments always are translated, unless the client code explicitly marks them as non-translatable. Use non-translated strings only for *internal* strings or debugging purposes; otherwise, in accordance with the user interface architecture, provide string translations for any locale your user interface is likely to need.

### Creating an Error Alert

A common alert use is to display an error message of some kind. [Example 29](#) shows a very common pattern for this:

#### **EXAMPLE 29** Displaying an ErrorAlert

```
// assume some other code invoking PMSetGlobalErrorCode()  
ErrorCode result = possibleFailure();  
// determine the appropriate error message to display  
PMString string = ErrorUtils::PMGetErrorString(result);  
if(!string.IsNull()) {  
    // Display the translated error message  
    CAlert::ErrorAlert(string);  
    // reset the global error code to clear the error  
    ErrorUtils::PMSetGlobalErrorCode(kSuccess);  
}
```

## Creating other Kinds of Alerts

The ModalAlert methods provide the most flexibility in terms of labels on buttons, icons displayed, ordering of buttons, and return value to be queried. Instances of this are used across the SDK samples; for instance, the Snapshot sample uses a ModalAlert to solicit a yes/no response.

### Soliciting a Binary or Ternary Choice

Create a CAlert with two or three buttons. CAlert::ModalAlert returns the index of the button that was pressed, starting with “1” for the leftmost button.

### Line-breaking in Alert Messages

Line-breaking algorithms for the text displayed in alerts depend on the routines provided by the platform API; there is no control over the composition of text for alerts.

If you do not want to depend on the platform algorithm to break strings for display in an alert, you can segment the text to be displayed by using the kLineSeparatorString constant (defined in CoreResTypes.h) to specify where lines of text in the alert should break. [Example 30](#) shows how to define a string that would break across two lines in a predictable way:

#### **EXAMPLE 30 A String with Explicit Line Breaks**

```
"Here is a string" kLineSeparatorString " that takes up two lines."  
//The resource compiler combines these into one string with a carriage return.
```

---

## Progress Bars

### Creating Progress Bars

A progress bar widget shows progress on a lengthy task, like import, export, or an elaborate conversion. The progress bar manager (IProgressBarManager) mediates creation and interaction with progress bars; for details, see its API documentation.

A progress bar appears in its own dialog (kProgressBarDialogBoss), which consists of a progress bar widget (kProgressBarWidgetBoss) and a cancel button (kProgressBarCancelButtonBoss) to end the current task.

A progress bar combines information about the number of tasks and the range of display associated with each task. The default display range is the interval [0,1], and each task added fills in another division on the progress bar when completed.

To create a progress bar, use a subclass of BaseProgressBar, like RangeProgressBar or TaskProgressBar (see ProgressBar.h).

## Modifying a Progress Bar

Use progress bar helper class methods; for example, BaseProgressBar::SetPosition.

## Suppressing Progress Bars

Use the SuppressProgressBarDisplay API class.

---

# Dialogs

## Using a Dialog

Dialogs are used to solicit input from an end user. In InDesign CS4, this is a modal process; the end user must supply input or dismiss the dialog with a cancel gesture before returning to the main application.

A dialog created with the API is a window (kMovableModalWindowBoss) with a panel inside it. The kDialogBoss boss class and its descendants provide the panel's behavior. Classes k<whatever>DialogBoss, therefore, are *panel boss classes*; kDialogBoss extends kPrimaryResourcePanelWidgetBoss. Remember, when implementing the dialog, you are defining widgets within a panel that happens to be housed in a modal, movable window. [Table 7](#) lists dialog boss classes:

**TABLE 7** *Dialog Boss Classes*

Widget Boss Class	ODFRez Custom Type	Example of Use
kDialogBoss	DialogBoss	Ancestor for all dialog boss classes.
kResizeDialogBoss	ResizeDialogWidget	Create a resizable dialog.
kSelectableDialogBoss	SelectableDialogBoss	Create a selectable dialog.
kTabSelectableDialogBoss	TabSelectableDialogBoss	Create a tab-selectable dialog.

Most dialogs should have least two buttons:

- A button to accept the choices made (Done or OK, in English locales).
- A button to indicate the choices are to be revoked (Cancel).

Typically, the buttons derive their behavior from kButtonWidgetBoss and kCancelButtonWidgetBoss, respectively. The default value of the ButtonAttributes member is kTrue, meaning the OK control grabs the input focus when the dialog appears.

Although dialogs and panels appear to be quite different types of widgets, they share much behavior. The panel widget (`kPalettePanelWidgetBoss`) that provides the behavior for a panel housed within a floating palette uses much of the same code as the `kDialogBoss` class, which provides the behavior for a panel within a modal, moveable window.

The dialog architecture provides sophisticated features like preview capability, with the condition that dialogs that can be previewed also must be modal. A *modal dialog* is one in which the user must make a set of commitments (optionally previewing the result) and then dismiss the dialog with an affirmation to execute (OK or Done) or a Cancel. The end user cannot carry on with other activities while the modal dialog is open. The end user is blocked from other tasks, and the application waits for the end user to finish with a modal dialog before further processing can occur.

There are several examples in the SDK that involve working with dialogs, such as the `BasicDialog` SDK plug-in.

`ResizeDialogWidget` is a dialog resource that overrides the `IControlView` interface and replaces it with an `ErasablePanelView` implementation, to create a resizable dialog. For an example, see the Map Tags to Styles dialog on the Tags panel.

Although dialogs written with the InDesign API can be declared to be movable and modeless, in practice all dialogs in the application are movable but modal (see `kMovableModalWindowBoss`).

An abstraction called the dialog manager (`IDialogMgr`) instantiates new dialogs and queries for information about dialogs. Plug-ins that create dialogs, like `BasicDialog`, use this interface to instantiate the dialog. There also are selectable dialogs, where a list control is used to page through the dialog panels, and a tab-selectable dialog.

## Creating a Dialog

The standard method is to create a new boss class that subclasses `kDialogBoss`, a panel boss class. By convention, you also create other user interface elements that enable the dialog to be shown, like a menu component, shortcut, or button that brings up the dialog. Use the `DollyXs` template dialog to get a basic dialog.

The ancestor for all dialog boss classes is `kDialogBoss`. It is specialized by many subclasses, like `kSelectableDialogBoss`, providing behavior for a selectable dialog. It supports a preview capability, so end users can preview the effect of changes they might make without having to commit to changing the document.

The usual process to create a dialog is to subclass the `kDialogboss` class and provide an implementation of two interfaces, `IDialogController` (using the `CDialogController` helper class) and `IObserver` (using `CDialogObserver`).

The `CDialogObserver` partial implementation class has several responsibilities: it attaches observers to the standard OK (which should have the widget identifier `kOKButtonWidgetID`), Cancel (`kCancelButtonWidgetID`), and Preview buttons (`kPreviewButtonWidgetID`).

When creating a new dialog boss class, subclass the ODFRez custom resource type `DialogBoss`, and bind it onto the new dialog boss class. Also, define the view resources for each locale in a `LocaleIndex` resource.

Several SDK samples create dialogs; BasicDialog is the most stripped-down example.

## Creating a Selectable Dialog

Selectable dialogs have multiple panels, only one of which is visible at any time. This mechanism has been widely used across many applications. To move between panels in a selectable set, the dialog typically provides Prev (previous) and Next buttons (in the English locale). kSelectableDialogBoss and kTabSelectableDialogBoss provide the behavior for selectable dialogs. See the BasicSelectableDialog SDK sample.

The standard method is to create a new boss class that is a subclass of kSelectableDialogBoss or kTabSelectableDialogBoss. You must provide an implementation of the IDialogCreator interface and to add an IK2ServiceProvider interface that returns a number identifying the boss class as a dialog service provider. For more information, see the BasicSelectableDialog SDK sample plug-in.

There are two main use cases when working with selectable dialogs:

1. Adding a panel to an existing selectable dialog.
2. Creating a selectable dialog of one's own. This is shown in the BasicSelectableDialog SDK sample, which shows how to create a standard selectable dialog (like the Preferences dialog of the application) and a tab-selectable dialog.

## Creating a Previewable Dialog

Previewable dialogs allow an action to be previewed before it is committed. Previews of parameter effects are found in the context of modal dialogs within applications, like the Transform dialogs (move, rotate, scale, and shear). With modeless panels, it is harder to define the commit semantics than for modal dialogs; consequently, the preview feature is restricted to modal dialogs.

There must be a check box widget with identifier kPreviewButtonWidgetID. The expectation is that it has an ITriStateControlData interface, which is consistent with the radio and check box buttons.

A previewable dialog involves subclassing kDialogBoss; it should have a check-box widget with the well known widget ID kPreviewButtonWidgetID. The preview subsystem commits the commands executed only when the dialog is dismissed with a positive confirmation, like OK or Done; otherwise, a previewable dialog is an ordinary dialog. It requires no new interfaces to be added to the dialog boss class than would be required for a non-previewable dialog implementation; however, some specialized implementation code is required. The TransparencyEffects SDK sample shows how to make use of this feature.

## Dealing with Child Widgets

The kDialogBoss boss class and its descendants (typically named k<whatever>DialogBoss) aggregate the IDialogController and IObserver interfaces. To create and work with a dialog from client code, subclass kDialogBoss (or one of its descendants) and provide your own

implementations of IDialogController and IObserver by specializing CDialogObserver, to handle notifications from the child controls.

The interfaces exposed by boss class kDialogBoss are in the SDK online documentation. [Table 8](#) lists the responsibilities of some interfaces on this boss class:

**TABLE 8 Interfaces Exposed by kDialogBoss**

Interface	Description
IPanelControlData	Used to access the child widget hierarchy on the dialog.
ITextControlData	Used to set the dialog name.
IControlView	Uses the same implementation as panels to draw the appearance of the dialog panel.
IDialogController	Supports the dialog protocol and is unique to dialog boss classes. Helper methods connected with edit boxes are used to query and retrieve both strings and typed values, like real-valued numbers. Using the helper methods avoids locating the widget using methods like IPanlelControlData::FindWidget, or querying for an ITextControlData or ITextValue interface. Helper methods for boolean and tri-state controls provide shortcuts to query and set the state of these controls.
IObserver	Receives notifications about changes in the state of the dialog controls. By default, the partial implementation CDialogObserver handles the OK, Cancel, and Preview buttons. Subclass CDialogObserver for the IObserver implementation added to a dialog boss class.

## Receiving Messages

There are two key aspects of messaging associated with dialogs:

- Receiving notification about the controls on the dialog themselves (through IObserver, based on CDialogObserver).
- Messages sent through IDialogController that conform to the dialog protocol.

The dialog protocol consists of the message sequence sent to the IDialogController:

1. IDialogController::InitializeDialogFields
2. IDialogController::ValidateDialogFields
3. IDialogController::ApplyDialogFields

**NOTE:** It is possible that instead of IDialogController::ApplyDialogFields, the last message is IDialogController::ResetDialogFields. This happens when a Cancel button changes to a Reset button with the correct keyboard modifiers. In the event of IDialogController::ResetDialogFields, the IDialogController::InitializeDialogFields message is sent again.

Once the dialog is created, the first call made on the dialog is Open on the IDialog interface. Behind the scenes, this calls InitializeDialogFields on a IDialogController interface pointer obtained from the dialog boss object. Typically, a dialog uses the CDIALOGCONTROLLER utility class to provide most of the implementation of the methods of this interface, with an override of at least ApplyDialogFields. The following are the other key methods that can be overridden:

1. InitializeDialogFields — Delegates initially to the CDIALOGCONTROLLER::InitializeDialogFields method, and sets up initial values.
2. ValidateDialogFields — Returns kDefaultWidgetId if all fields are valid; otherwise, the offending widget ID.
3. ApplyDialogFields — the user accepted the choices and pressed the Done or OK button.

The implementation code behind dialogs provides careful bracketing of multiple commands invoked on ApplyDialogFields in the dialog controller. This ensures a command sequence is run when the OK button is pressed and the command sequence is aborted when the Cancel button is pressed. This mechanism works hand-in-hand with the preview capability to ensure that, when preview is operating, even if the effects of a command or command sequence are previewed, changes are not committed when the dialog is dismissed with a Cancel.

## Adding a Panel to a Selectable Dialog

Add a service that advertises itself as a panel creator. Provide an implementation of the IPanel-Creator interface, and make a binding in ODFRez code to the dialog to which the panel should be added.

## Adding Buttons to a Dialog

Typically, when adding buttons to a dialog, you should ensure at least OK (or Done) and Cancel buttons are present. These type of buttons should use the widget boss classes named kDefaultButtonWidgetBoss and kDefaultCancelButtonWidgetBoss, bound to the ODFRez types named DefaultButtonWidget and DefaultCancelButtonWidget. The buttons should use the standard widget identifiers.

## Adding a Check Box to a Panel

Create a new boss class that extends the kCheckBoxWidgetBoss boss class, and add an IOB-server interface to this new boss class. When the widget is shown, the AutoAttach message gets sent; when hidden, AutoDetach.

## Adding a Check Box to a Dialog

Add ODFRez data statements that use the ODFRez type named CheckBoxWidget. The client code attaches to the widget boss object on an AutoAttach message (when the dialog is shown) to the IOBserver implementation, and detaches on AutoDetach (when the dialog is hidden). Helper methods in CDIALOGOBSERVER, like as AttachToWidget, are useful for this process. The

client code registers for notifications along the IID\_ITRISTATECONTROLDATA protocol. When the check box is clicked, update messages are sent to this observer.

## Finding Out when a Dialog Repaints

One way to discover when a dialog is being repainted is to subclass the IControlView interface on a panel that covers the area of interest. On repainting, the IControlView::Draw message is sent.

## Palettes and Panels

A *palette* is an Adobe common user interface object, represented by a PaletteRef, which serves as a container for panels. A *panel* is a container for widgets (see IPaneldControlData).

## Using a Panel Widget

This section introduces some of the panel widgets in the InDesign API. There are two main distinctions for panel widgets:

- Those that can function as “root panels” in a tabbed-palette widget.
- Those intended to be general-purpose widget containers, but not necessarily the root panel in a floating palette.

A generic panel widget (kGenericPanelWidgetBoss) is a general-purpose container and is used in many places within the application. For example, the character panel consists of a set of generic panel widgets, with separator widgets to draw the lines on the panel. The generic panel widget is used on panels like the paragraph panel, transform panel, tab panel, and library panel. [Table 9](#) lists a selection of panel boss classes:

**TABLE 9** *Panel Boss Classes*

Widget boss class	ODFRez custom type	Description
kClusterPanelWidgetBoss	ClusterPanelWidget	Grouping widget required for mutually exclusive behavior of radio buttons (or check boxes). It draws without a border.
kControlStripWidgetBoss	ControlStripWidget	Basis of a control-strip panel.
kDetailKitPanelWidgetBoss	DetailKitPanelWidget	Used to provide your own PanelDetailController.
kErasableKitPanelWidgetBoss	ErasableKitPanelWidget	Top level kit. Erases before drawing.

Widget boss class	ODFRez custom type	Description
kErasablePrimaryResourcePanelWidgetBoss	ErasablePrimaryResourcePanelWidget	Used for a root panel in a palette, like the Links panel, that uses this rather than a PalettePanelWidget.
kGenericPanelWidgetBoss	GenericPanelWidget	Workhorse panel widget that can be used as a container for other widgets without border decoration.
kGroupPanelWidgetBoss	GroupPanelWidget	Widget for enclosing a group, which draws a border with an optional title.
kKitPanelWidgetBoss	KitPanelWidget	Top level kit. Does not erase before drawing.
kKitViewHorzBoss	KitViewHorzWidget	Container for kit views in the horizontal dock.
kKitViewTabPanelBoss	KitViewTabPanelWidget	Container for kit views in a standard tabbed palette. Best used if the view has one control set.
kKitViewTabPanelWithDetailBoss	KitViewTabPanelWithDetailWidget	Container for kit views in a standard tabbed palette. Allows cycling widget to operate on control sets specified in the resource.
kKitViewVertBoss	KitViewVertWidget	Container for kit views in the vertical dock.
kPalettePanelWidgetBoss	PalettePanelWidget	Used for the root panel in a tabbed palette.
kPanelWithHiliteBorderWidgetBoss	PanelWithHiliteBorderWidget	Border-decorated panel.
kPanelWithInverseHiliteBorderWidgetBoss	PanelWithInverseHiliteBorderWidget	Border-decorated panel.
kPrimaryResourcePanelWidgetBoss	PrimaryResourcePanelWidget	Used as a root panel in a tabbed palette.

## Creating a Panel Widget

Panels are containers for widgets and/or groups of widgets. Some are suitable as a root panel, while others can be only general-purpose containers. [Table 9](#) describes some capabilities and intended uses of panel boss classes.

The type definition for one of the key panel widgets is shown in [Example 31](#), and an instance of the ODFRez data defining a widget of the same type is shown in [Example 32](#).

#### **EXAMPLE 31 Type Definition for a Panel Widget**

```
// From Widgets.fh, NOT for use in your resource
type PrimaryResourcePanelWidget (kViewRsrcType) : Widget (ClassID =
kPrimaryResourcePanelWidgetBoss)
{
    ResourceSrcFileInfo;
    CControlView;
    CTextControlData;
    CPanelControlData;
};
```

#### **EXAMPLE 32 Sample Panel Widget Definition**

```
PrimaryResourcePanelWidget
(
    // ResourceSrcFileInfo properties
    PlatformPMString, // fFilename
    longint, // fLineno
    // CControlView properties
    kInvalidWidgetID, // widget ID
    kSysStaticTextPMRsrcId, // PMRsrc ID
    kBindNone, // frame binding
    Frame(0,0,85.0,25.0) // (left, top, right, bottom)
    kTrue, // visible
    kTrue, // enabled
    // CTextControlData properties
    PlatformPMString, // control label
    // CPanelControlData properties
    {
        // Put your child widgets here.
        // Note: CPanelControlData is defined in Widgets.fh
    }
),
```

## **Creating Dynamic Panels**

Panels can be created dynamically. The DynamicPanel SDK sample shows one mechanism to instantiate panels dynamically, and it creates an arbitrary sequence of panels that can be destroyed in the reverse order.

The general process for creating a dynamic panel is as follows:

1. Create a panel object (IControlView), using the RsrcSpec defined in your .fr file.
2. Set up the panel's attributes, like widget ID and panel text string.
3. Call IPanelMgr::RegisterPanel to put the panel in the new palette.
4. Add the panel action to Action Manager.

## Showing and Hiding Palettes and Panels

PaletteRefUtils provides the methods necessary to show and hide a palette using a PaletteRef. IPanel manager provides methods to show and hide panels based on widget and action identifiers. When the last panel in a palette is hidden, the palette also is hidden. The SnpShowPalette sample demonstrates these APIs.

To show and hide a palette, follow these steps:

1. Query IPanelMgr (aggregated on kPanelManagerBoss) directly from the application (IAplication::QueryPanelManager, where IApplication is available through GetExecutionContextSession()).
2. Use IPanelMgr::GetPanelFromWidgetID or IPanelMgr::GetPanelFromActionID to get to IControlView of the panel.
3. Call IPanelMgr::GetPaletteRefContainingPanel, passing in the panel's IControlView, to obtain the PaletteRef.
4. Call PaletteRefUtils::ShowHidePalette with the PaletteRef obtained from step 3 to show/hide the palette.

To show/hide a panel, follow these steps:


1. Query the IPanelMgr as described above for showing/hiding a palette.
2. Call IPanelMgr::ShowPanelByWidgetID or IPanelMgr::HidePanelByWidgetID with the panel's widget ID.

## Creating a Control Strip

The control strip is a panel based on ControlStripWidget, which uses the new selection architecture to gather different sets of widgets into itself, based on the current selection. Existing widgets from other panels are relatively easy to add to the control strip; observers are taken care of automatically. New controls also can be added, but with much more effort.

The appearance of the control strip changes depending on document and selection state. This is shown in [Figure 4](#) in a text-frame-selected state.

**FIGURE 4**      **Control Strip**



## Creating Kits


Kits are a form of dockable panel that collapses against the side of the workspace, as seen in the swatches panel. They are tab-selectable and open or collapse based on toggle-clicking the tab.

ErasableKitPanelWidget is the top-level kit. It erases before drawing. Most kits should use this. KitPanelWidget also is a top-level kit, but it does not erase before drawing. KitViewHorzWidget is the container for kit views that will be in the horizontal dock, and it also can be used for a tab-less floater view. KitViewVertWidget is the container for kit views that will be in the vertical dock, and it also can be used for a floater view without tabs.

KitViewTabPanelWidget is the container for kit views that will be in a standard tabbed palette. These are best used where the view has only one control set (especially a resizable one, since you must override the DetailController anyway). KitViewTabPanelWithDetailWidget is the deluxe container for kit views that will be in a standard tabbed palette. It is specialized to allow the cycling widget to operate on the specific control sets specified in resource, and it should be used most of the time.

[Figure 5](#) shows a kit-view widget participating in a tabbed palette. The same widget also can participate in a horizontal or vertical dock situation.


**FIGURE 5** Kit View in Tabbed Panel



## Creating Resizable Panels

Many panels within the user interface, like the Links panel, can be resized. The typical mechanism to create a resizable panel is to attach a window size-box widget to the panel to be resized. The developer must ensure the panel knows how to respond correctly to resize events. In practice, the key method to be implemented is IControlView::ConstrainDimensions. Resize events are generated automatically when the window size-box widget is activated by the end user. For an example of a resizable panel, see the SnippetRunner sample.

[Figure 6](#) shows a resizable panel, the Paragraph Styles panel from the application. The end user can change the size with the window size box widget.

**FIGURE 6** Resizable Panel

## Manipulating Panel Widgets

Typically, panel widgets are defined in terms of their relationship with their children. The key data interface is `IPanelControlData`, which allows access to their child widget hierarchy. Some widgets have a text label, accessible through `ITextControlData`.

Navigation through the child widgets on a panel is facilitated by `IPanelControlData`, the signature interface for a panel. The `IControlView` interface for panel widgets manipulates the visual representation. Typically, this involves delegating to the children to ensure they draw after the panel widget has drawn itself and any decorations. The `ITextControlData` interface allows the panel name to be set and queried.

## Iterating over a Panel's Child Widgets

A panel is a container widget that supports `IPanelControlData`. Given such an interface, it is necessary to call only `GetWidget` for the widget list of the panel control data; this navigates over the immediate children of a container, as follows:

```
// Assume panelControlData is valid ptr
// on a container widget boss object
for(int i=0; i < panelControlData->Length(); i++)
{ IControlView* nextWidget = panelControlData->GetWidget(i);
  ASSERT(nextWidget); // Go ahead and use nextWidget...
}
```

To add new child widgets, given a pointer to an `IControlView` on the child widget boss object, use `IPanelControlData::AddWidget`.

## Finding a Widget in the Panel Widget Hierarchy

The interface on the `IPanelControlData` container widget boss class provides a mechanism to traverse the widget hierarchy in the direction of the leaves, to search for a widget by ID. Then you can use the `IPanelControlData::FindWidget` method to get an `IControlView` pointer referring to that widget boss object.

## Grouping Widgets


A widget is contained within another widget when it is in the `CPanelControlData` list of the other widget. If the grouping widget is simply a frame, the ODFRez type `GroupPanelWidget` is appropriate. In the case of clustering of buttons, like radio buttons, check boxes, or other buttons that should be mutually exclusive, a `ClusterPanelWidget` is the correct type to use. This does not draw a frame, so a group panel widget is still required if a visible frame for the collection of widgets is required.

## Controlling Level of Detail on Panels

Many panels within the application show a feature of detail control, where either the set of widgets displayed or the physical properties of the widgets (like the height of rows in a tree view) change in response to a user gesture. This feature allows you to provide both a simplified user interface and a more elaborate interface for expert users. Alternatively, users may not always want to see the full range of configuration options, and this allows the widget set displayed in a panel to be varied by an end user. The SDK sample `DetailControlListSize` shows an example of varying tree-view row height.

[Figure 7](#) shows the swatches panel at two different levels of detail. The `IPanelDetailController` interface can switch the level of detail. There are two implementations, for widget size and widget set composition. For a detail-controlled set of widgets, override `IControlView::ConstrainDimensions`. This provides the correct behavior on resize of the detail-controlled panel, because changing the detail control level typically forces a resize when updating the panel.

**FIGURE 7**      *Detail-controlled Panel, showing Large and Small Rows*



## Varying the Set of Widgets Displayed on a Panel

You must add an IPanelDetailController interface to a panel boss class that hosts the variable numbers of elements.

## Setting the Minimum Size for a Resizable Panel

Override IControlView::ConstrainDimensions, a resizable panel control view. The client code defines the upper and lower dimensions of the panel. See the SnippetRunner SDK sample.

## Using Widgets on Panels

Working with controls on panels is not as straightforward as with controls on dialogs. Two patterns can be used:

- Observe the changes directly for each control by adding an IObservable interface to the widget boss class of interest, and attaching to the widget to listen for changes. This requires creating many new boss classes and new ODFRez custom resource types, and it leads to code bloat. We recommended this only if you have a small number of widgets to observe.
- Use the procedure described in the “User Interface Fundamentals” chapter of *Adobe InDesign CS4 Programming Guide*, in the section on “Widget Observer Pattern.” IControlViewObservers is useful for plug-in client code if you want to observe changes in the active context as well as widget-related changes. This is because you can add an observer interface for the active selection (CActiveSelectionObserver makes this easier) and one observer interface for all your widgets. This pattern is used widely throughout the InDesign code base for user interface plug-ins.

## Adding a Multi-line Static Text Widget to a Panel

You can add a multi-line static text widget to a panel and associate it with a scroll bar almost entirely with ODFRez data statements. The ODFRez custom resource type StaticMultiLineTextWidget or the ODFRez type DefinedBreakMultiLineTextWidget is associated with the ODFRez type ScrollBarWidget through widget identifiers. Unless you require notification of changes associated with the widgets, this suffices to create a multi-line static text widget.

## Adding a Text Edit Box to a Panel

There are edit boxes that provide highly specialized behavior; for instance, edit boxes can be created with an associated nudge control that is specialized for the display of text measures (like points) or units (like degrees). If the edit box is being added to a dialog, it typically is necessary to use only the correct ODFRez type and manipulate the edit-box widget through the utility methods on the CDialogController and CDialogObserver helper classes.

In the case where the edit box is added to a panel, if update events associated with Return or Enter being pressed are required, a subclass of an existing edit-box widget boss class is

required. This subclass exposes an IObserver interface. In addition, the associated ODFRez custom resource type is subclassed and bound to the new boss class.

## Adding a Specialized Combo Box to a Panel

Suppose you need to add a combo box that displays measurements in points. The correct procedure is to subclass the kTextMeasureComboBoxWidgetBoss API widget boss class to add an IObserver interface, and attach to the widget boss object in the AutoAttach method of the observer implementation. Similarly, there is a data statement in ODFRez in the localized framework resource file involving a subclass of the ODFRez custom resource type named TextMeasureComboBoxWidget.

The widget boss observer listens for changes along the IID\_I TEXTCONTROLDATA protocol. You must subclass the combo box when adding it to a panel, to get notified of change. Be sure the name you choose for the ODFRez subclass contains the name of the superclass. For example, MyTextMeasureComboBoxWidget is an acceptable name; MyWidget is not.

## Overriding the Default Draw Behavior for Panels

To create owner draw controls, override the IControlView::Draw method; however, the implementations of IControlView for the widgets in the widget set are complex, and the helper class CControlView provides only a minimal implementation. Usually, it is necessary to have the implementation header for the existing implementation (and its ancestors), and then subclass this implementation class.

For owner draw panels in the SDK, see the PanelTreeView and CustomDataLink SDK samples.

## Organizing Panels with Workspace Extensions

InDesign saves data related to panel-geometry properties in workspace XML files. There are a variety of preconfigured workspace files that get installed to InDesign's presets folder (<*app folder*>/Presets/InDesign Workspaces/en\_US/). The default workspace is named Essentials. When InDesign starts up with no saved preferences, the Essentials workspace is used to arrange the palettes and menus in the workspace.

When a user creates a new workspace from the Window > Workspace > New Workspace... menu, a workspace file with the specified name is saved to the Workspaces folder within the User's InDesign preferences folder. If the user modifies a workspace (e.g., dragging or hiding a panel), the updated workspace is saved to a new file in the User's InDesign Workspaces preference folder. The new file's name is the original workspace name with "\_CurrentWorkspace.xml" appended.

In the default workspace, all third-party panels are grouped in one panel container, and the container is not visible at start-up. As a result, when InDesign is installed and run for the first time, third-party panels are not visible. When the user chooses to show a third-party panel, it is shown in the same panel container as other third-party panels. To override this default workspace behavior, you can add a workspace extension.

Essentially, a workspace extension is a workspace XML file located in a predetermined location, so InDesign reads the XML file at startup. The extension file contains the definition of panel properties you want to override in the default workspace. Extension files are loaded after the “default” workspace, but before the “current” workspace. This allows your extension to override default settings for your panel, but it preserves any workspace changes made by the user.

## Generating a Workspace Extension

We recommend the following steps for generating your own workspace extension XML file:

1. Remove the InDesign preferences folder.
2. Launch InDesign with your plug-ins loaded, so your panels are available in the user interface.
3. Organize the panels as you want your user to see them for the first time.
4. Exit InDesign normally.
5. Locate the “Essentials\_CurrentWorkspace.xml” file in the InDesign preferences folder. Duplicate the file and edit it to remove extraneous tags, leaving the dock tags that contain your panels.
6. Distribute/Copy the workspace-extension XML file in the InDesign Workspace Extension folder (*<app folder>/Presets/InDesign Workspaces/en\_US/Workspace Extensions*). If the “Workspace Extensions” folder does not exist, create it. The easiest way to distribute the workspace-extension XML file might be in the same installer used to install your plug-ins.

**NOTE:** There also is an InCopy Workspaces folder, inside the Presets folder. It can be used to organize panels for InCopy.

**NOTE:** InDesign CS4 is backward compatible with InDesign CS3 workspace-extension files. The CS3 format allows you to define individual panel overrides, whereas the CS4 format requires you to define an entire workspace. For more information on the CS3 format, download the InDesign CS3 Products SDK and read “Working with User Interfaces.”

## Workspace Containment Hierarchy

Figure 8 is an overview of the InDesign workspace hierarchy. The XML structure of an InDesign workspace file follows this hierarchy, with one PaletteWorkspace root containing child nodes representing the elements shown here.


**FIGURE 8** Palette Workspace Hierarchy


Table 10 explains the relevant objects in the hierarchy for panel arrangement.

**TABLE 10 Relevant Objects in the Palette Workspace for Organizing Panels**

Name	Workspace XML Tag	Description
Tab Palette	<palette>	The palette is the object the user perceives as a unit whose position and size can be controlled. Each tab palette contains an InDesign panel.
Tab Group	<tab-group>	A collection of one or more palettes. A tab group has at most one active palette. The active palette is the tab whose content is shown and whose tab is front-most.
Tab Pane	<tab-pane>	An anchored container for tab groups.
Dock	<dock>	A list of connected tab panes.

Figure 9 shows a typical InDesign workspace, where toolbars and control bars are docked, and tab palettes are floating or docked.

**FIGURE 9** Sample Palette Workspace



### SDK Workspace Extensions

The SDK contains sample workspace extension files, in <SDK>/presets/InDesign Workspaces/workspace extensions. To use a sample extension file, follow these steps:


1. Delete the InDesign Preferences folder
2. Copy the SDK sample workspace extension file to the InDesign Workspace Extension folder (<app folder>/Presets/InDesign Workspaces/en\_US/Workspace Extensions). If the “Workspace Extensions” folder does not exist, create it.
3. Start InDesign.

# Static Text Widgets

## Using a Static Text Widget

Static text widgets are widely used throughout the application, typically as labels on panels and dialogs. They can display longer runs of text and provide for a scrolling display over multiple lines of text, with or without specified line breaks. In [Figure 10](#), static text widgets are used as labels on both the panel widget that frames the combo boxes and the combo boxes.

**FIGURE 10**      *Static Text Widgets*



Although static text widgets cannot be edited, it is possible to vary the appearance and text in response to user events.

There are text widgets provided by the API that also display large amounts of text that can be scrolled through. There also are fitted text widgets, which make sure the frame of the widget always allows text to be displayed with a fixed padding around the text, regardless of the font. There is another variant that allows the font to be both specified in the ODFRez data statements and, potentially, dynamically varied through a particular interface on the boss class.

[Table 11](#) shows the widget boss classes for static text widgets and the types they bind to, along with sample use in the application.

**TABLE 11** *Static Text Widget Boss Classes*

Widget Boss Class	ODFRez Custom Type	Use
kStaticTextWidgetBoss	StaticTextWidget	Displays a single line of static text. An example is on the Stroke panel, in the widget that displays Weight.
kFittedStaticTextWidgetBoss	FittedStaticTextWidget	Displays text that always fits inside its frame. Helpful where the full text always must be displayed.
kGroupPanelTitleTextWidgetBoss	GroupPanelTitleTextWidget	Renders text in theme color if WinXP theme is on.
kInfoStaticTextWidgetBoss	InfoStaticTextWidget	Displays text in a font that can be specified in the ODFRez data statements. Can be used where a bold font might be required.
kInfoStaticTextAngleWidgetBoss	InfoStaticTextAngleWidget	Same as InfoStaticTextWidget, but validates degree entries.

Widget Boss Class	ODFRez Custom Type	Use
kInfoStaticTextIntWidgetBoss	InfoStaticTextIntWidget	Same as InfoStaticTextWidget, but validates integer entries.
kInfoStaticTextPercentageWidgetBoss	InfoStaticTextPercentageWidget	Same as InfoStaticTextWidget, but validates percentage entries.
kInfoStaticTextXMeasurementWidgetBoss	InfoStaticTextXMeasurementWidget	Same as InfoStaticTextWidget, but validates X measurement entries.
kInfoStaticTextYMeasurementWidgetBoss	InfoStaticTextYMeasurementWidget	Same as InfoStaticTextWidget, but validates Y measurement entries.
kStaticMultiLineTextWidgetBoss	StaticMultiLineTextWidget	Displays multiple lines of text. Typically used in conjunction with a scroll bar widget for viewing.
kDefinedBreakMultiLineTextWidgetBoss	DefinedBreakMultiLineTextWidget	Allows developers to specify a character sequence that will create line breaks in a block of text. Any occurrences of the specified character sequence in the input text is replaced by a line break in the edit control.

## Creating a Static Text Widget

The ancestor of all static text widget boss classes is kStaticTextWidgetBoss. Text widgets using kInfoStaticTextWidgetBoss can have a variable font displayed. Text widgets using kFittedStaticTextWidgetBoss have a frame that is fitted to the size of the string in the font to display, with a specified padding. There also are two multi-line static text widgets, kStaticMultiLineTextWidgetBoss for the basic multiline widget, and kDefinedBreakMultiLineTextWidgetBoss for the type that accepts predefined line breaks.

Fitted static text widgets resize their frame to try to fit the text in the current drawing font with the specified padding. The kFittedStaticTextWidgetBoss boss class does not add any new interfaces compared with kStaticTextWidgetBoss. It overrides the implementation of the IControlView interface only to ensure the text fits when drawn.

The principal collaboration of interest is between the multi-line text widget types and the scroll-bar widget type, kScrollBarWidgetBoss. An association is established in the ODFRez between the multi-line text widgets and a scroll bar that is responsible for adjusting the views of the text drawn.

The ODFRez custom type associated with the kStaticTextWidgetBoss class is StaticTextWidget. Example 33 shows the type definition, which is found in Widgets.fh:

**EXAMPLE 33 Type Definition for Static Text Widget**

```
// From Widgets.fh, NOT for use in your resource
type StaticTextWidget (kViewRsrcType) : Widget (ClassID = kStaticTextWidgetBoss)
{
    CControlView;
    StaticTextAttributes;
    CTextControlData;
    AssociatedWidgetAttributes;
};
```

Example 34 shows a sample data definition for a static text widget:

**EXAMPLE 34 Sample Static Text Widget**

```
// Sample data definition for widget
StaticTextWidget
(
    // CControlView properties
    kInvalidWidgetID, // widget ID
    kSysStaticTextPMRsrcId, // PMRsrc ID
    kBindNone, // frame binding
    Frame(5.0,5.0,85.0,25.0) // left, top, right, bottom
    kTrue, // visible
    kTrue, // enabled
    // StaticTextAttributes properties
    kAlignLeft, // Alignment
    kDontEllipsize, // Ellipsiz style
    // CTextControlData properties
    "", // control label
    // AssociatedWidgetAttributes properties
    kInvalidWidgetID, // associated widget ID
),
```

## Manipulating a Static Text Widget

This control encapsulates data of type PMString. The text for a static text widget is initialized through the ITextControlData interface, using the SetString method. The initial value is defined in a key-value pair in the StringTable for each locale of interest, where the key is placed in the CTextControlData field in the ODFRez data statement.

The ITextControlData interface stores the state of the label on the static text widget. IStaticMultiLineTextAttr finds the associated scroll bar widget to scroll a multi-line text widget. Once a reference to the scroll bar widget is obtained (use IControlView::FindWidget), query for its ICounterControlData, and use the methods on this interface to control the view.

## Changing the Font of a Static Text Widget

Use the info-static text widget (kInfoStaticTextWidget), which is bound to the ODFRez type named InfoStaticTextWidget. The initial font the widget uses is defined in ODFRez data statements, and the font displayed can be changed through the IUIFontSpec interface on the widget boss object.


# Check Boxes and Radio Buttons

## Using Check Boxes and Radio Buttons

The API provides check-box buttons (`kCheckBoxWidgetBoss`) and radio buttons (`kRadioButtonWidgetBoss`) that operate like the equivalent platform controls. There also are fitted versions of the check boxes and radio buttons provided by the API; these have the additional feature that the button and associated text always fit within the frame, subject to a padding around the boundary. Radio button and check boxes are tri-state controls, and they aggregate an `ITriStateControlData` interface to represent their state.

[Figure 11](#) shows a pair of radio buttons and a pair of check boxes. The cluster panel widget that owns the radio button widgets is not shown, but it has a bounding box that contains the radio buttons it owns.

**FIGURE 11** *Radio Buttons and Check Boxes*



Radio buttons that operate as a logical unit should be contained within a cluster panel widget (`kClusterPanelWidgetBoss`), which has a bounding box that contains the union of their individual frames. Use the `ClusterPanelWidget` ODFRez type as an immediate parent.

The ODFRez custom resource type `CheckBoxWidget` is bound to the `kCheckBoxWidgetBoss` class. The ODFRez custom resource type `RadioButtonWidget` is bound to the `kRadioButtonWidgetBoss` class.

Check box and radio button widgets provided by the API are shown in [Table 12](#).

**TABLE 12** *Check Box and Radio Button Boss Classes*

Widget Boss Class	ODFRez Custom Type Associated	Use
<code>kRadioButtonWidgetBoss</code>	<code>RadioButtonWidget</code>	Displays a mutually exclusive set of choices, in conjunction with a cluster panel widget.
<code>kFittedRadioButtonWidgetBoss</code>	<code>FittedRadioButtonWidget</code>	A radio button that always fits within its frame.
<code>kCheckBoxWidgetBoss</code>	<code>CheckBoxWidget</code>	A standard check box.
<code>kFittedCheckBoxWidgetBoss</code>	<code>FittedCheckBoxWidget</code>	Check box that fits within frame, as frame resizes, with padding.

## Creating Check Boxes and Radio Buttons

The check box (kCheckBoxWidgetBoss) and radio button (kRadioButtonWidgetBoss) aggregate similar sets of interfaces. The fitted variants have the same interface profile, typically just replacing the IControlView implementation with one that draws the fitted text label. The interfaces aggregated are shown in the SDK online documentation. The ODFRez type expressions is in Widgets.fh.

[Example 35](#) shows the type expression for the ODFRez type RadioButtonWidget. It comprises the ODFRez type CControlView (bound to IControlView) and the ODFrez type CTextControlData, bound to ITextControlData, which represents the label.

### **EXAMPLE 35 Type Definition for Radio Button Widget**

```
// From Widgets.fh, NOT for use in your resource
type RadioButtonWidget (kViewRsrcType) :
    Widget (ClassID = kRadioButtonWidgetBoss)
{
    CControlView;
    CTextControlData;
};
```

[Example 36](#) shows a radio button widget being defined in ODFRez data statements:

### **EXAMPLE 36 Radio Button Widget**

```
RadioButtonWidget
(
    // CControlView properties
    kInvalidWidgetID, // widget ID
    kSysRadioButtonPMRsrcId, // PMRsrc ID
    kBindNone, // frame binding
    Frame(5.0,5.0,100.0,21.0) // (left, top, right, bottom)
    kTrue, // visible
    kTrue, // enabled
    // CTextControlData properties
    ', // control label string key would go here
),
```

## Manipulating Check Boxes and Radio Buttons

Check boxes and radio buttons have a data interface, ITriStateControlData, to access their state. Check boxes and radio buttons are said to be *tri-state*. The states are defined in an enumeration in the scope of the definition of ITriStateControlData. The states a tri-state control can be in are unselected, selected and unknown (or mixed). The state of these tri-state controls can be queried and set through the interface.

## Receiving Messages

The data model for kCheckBoxWidgetBoss and kRadioButtonWidgetBoss is tri-state and can be in one of following states: selected, unselected, or mixed. It is represented by the value stored on the ITriStateControlData of the given widget boss object.

When the state of controls, like kRadioButtonWidgetBoss and kCheckBoxWidgetBoss, changes, notification is sent along the IID\_ITRISTATECONTROLDATA protocol. The following messages are sent when the data model changes:

```
{ kTrueStateMessage, kFalseStateMessage, kUnknownStateMessage }
```

Messages are sent along the IID\_ITRISTATECONTROLDATA protocol. To receive notification of these changes, attach an observer to the button. If your controls are on a dialog, an implementation derived from CDIALOGObserver makes it straightforward to attach and detach from the widget of interest. The API on IDIALOGController also makes it easy to initialize the state of the check boxes or radio buttons.

**NOTE:** It is worth setting the doNotify flag on the calls to change the state to be kFalse. This avoids triggering unwanted IObserver::Update messages to one's own observer that are brought about by your own code rather than end user events.

## Ensuring Radio Buttons in a Group have Mutually Exclusive Behavior

Use a cluster panel widget. For example, for a radio button to interoperate with other radio buttons and ensure mutually exclusive selection, a collection of widgets of ODFRez type RadioButtonWidget are defined as children of an ODFRez ClusterPanelWidget.

This enforces mutually exclusive behavior among a group of widgets (not only radio buttons) that expose IBooleanControlData or ITriStateControlData interfaces.

---

# Button Widgets

## Using a Button Widget

This section describes some button widgets available in the API. We focus on kButtonWidgetBoss and its descendants. Iconic buttons are discussed in “[Image Widgets](#)” on page 206.

There is a nudge control widget (kNudgeControlWidgetBoss), which is a composite of two button-like widgets and is discussed briefly in this section. It is used in conjunction with edit boxes and combo boxes to provide the capability to nudge values up or down.

Buttons are used in many dialogs within the application. We do not recommend using the standard button (kButtonWidgetBoss) or its descendants on palette panels. Instead, use iconic buttons on palette panels, to conform with the application’s look and feel. Buttons that derive behavior from kButtonWidgetBoss or a descendant of this boss class are bi-state controls.

**Figure 12** shows a selection of button widgets. OK and Cancel buttons are on all dialogs. Whether other buttons are present depends on the requirements for the dialog. The enabling state of the buttons is set up initially by the dialog controller and can be modified by the dialog observer depending on the actions of the end user.

**FIGURE 12**      **Button Widgets**



A default button is one that has keyboard focus by default. If the user pressed Return, the default button's event handler processes the event, and an observer on the default button receives an `IOObserver::Update` message. `kButtonWidgetBoss` and an ODFRez type `DefaultButtonWidget` can be used if the default button is OK or Done—the button that allows an end user to confirm they accept their choices. The default button need not be OK or Done; it also can be Cancel (`kCancelButtonWidgetBoss`).

**Table 13** lists button widget boss classes.

**TABLE 13** **Button Widget Boss Classes**

Widget boss class	ODFRez type	Use
<code>kButtonWidgetBoss</code>	<code>ButtonWidget</code>	Used for any buttons on a panel or dialog.
<code>kButtonWidgetBoss</code>	<code>DefaultButtonWidget</code>	Represents the OK button on a dialog. Selected when the dialog appears.
<code>kCancelButtonWidgetBoss</code>	<code>CancelButtonWidget</code>	Used for a Cancel button on dialog.
<code>kNudgeControlWidgetBoss</code>	<code>NudgeControlWidget</code>	Wraps a nudge-up and a nudge-down button. Used with edit boxes and combo boxes.

## Creating a Button Widget

See the SDK online documentation for kButtonWidgetBoss and its descendants, to see the interfaces aggregated by button widgets, as well as some descendants of kButtonWidgetBoss in the required plug-in set.

The kButtonWidgetBoss class, in addition to taking the focus when a dialog appears, provides behavior to dismiss a dialog with an affirmation that the action should be executed or the commitments are completed. This class provides the behavior behind the button with a label like OK or Done that is intended to dismiss the dialog when it is pressed. kCancelButtonWidgetBoss is its counterpart and provides behavior behind a standard Cancel button on a dialog.

Nudge buttons collaborate with edit boxes and combo boxes to allow incremental changes in the control data model. The association is created by referencing a nudge button by widget ID in the definition of the edit box and combo box. Both these types of widgets have an ancestor responsible for dealing with any associated nudge buttons.

The ODFRez custom resource type corresponding to kButtonWidgetBoss is ButtonWidget or DefaultButtonWidget. The CTextControlData field specifies the label on the button. The type expression for ButtonWidget is shown in [Example 37](#).

### **EXAMPLE 37 Type Definition for a Button Widget**

```
// From Widgets.fh, NOT for use in your resource
type ButtonWidget (kViewRsrcType) : Widget (ClassID = kButtonWidgetBoss)
{
    CControlView;
    ButtonAttributes;
    CTextControlData;
};
```

[Example 38](#) shows ODFRez data statements defining a button widget. Because the ODFRez type ButtonWidget is not subclassed, changes in the data model of this control are handled by the dialog observer rather than an observer for the individual button widget.

### **EXAMPLE 38 Sample Button Widget**

```
ButtonWidget
(
    // CControlView properties
    kInvalidWidgetID, // widget ID
    kSysButtonPMRsrcId, // PMRsrc ID
    kBindNone, // frame binding
    Frame(5.0,5.0,100.0,25.0) // (left, top, right, bottom)
    kTrue, // visible
    kTrue, // enabled
    // ButtonAttributes
    kTrue, // default look true
    // CTextControlData properties
    '', // control label (string key) goes here
),
```

## Manipulating Button Widgets

IBooleanControlData and ITriStateControlData are the key interfaces in working with button widgets. The IBooleanControlData interface provides access to the data model of bi-state buttons. A boolean control like a standard button can be in one of two states, selected or unselected. The state is set through the IBooleanControlData interface. Update messages are sent along the IID\_IBOOLEANCONTROLDATA protocol.

For the bi-state buttons, it is possible to change the state and suppress the notification by calling the mutators with the notifyOfChange parameter set to kFalse.

The ITextControlData interface allows you to set button labels. The boss classes share the default implementation used by many of the controls.

## Receiving Messages

The data model for kButtonWidgetBoss and its descendants is a boolean, so these are bi-state controls. Their state is represented by the value stored on their IBooleanControlData interface, and they notify of changes in this state along the default identifier for this interface, IID\_IBOOLEANCONTROLDATA.

The button widget boss classes aggregate I<whatever>ControlData interfaces to allow the state to be queried and set. Usually, this results in a message being sent to attached observers that the control state has changed. It also is possible to set the state but suppress the notification about the change, to prevent observers from performing inappropriate updates when the state is set. In other words, the control change can be muted. This is done by setting the notifyOfChange to be kFalse in the mutator methods on these interfaces. This approach can be used when an observer listening for a notification on one or more controls wants to set up the state of a control it is observing, without receiving another notification about the state change. It is important not to be confused about how these controls work; typically the change parameter is expressed as a message identifier, rather than something more identifiable as a ClassID.

When the state of the controls that descend from kButtonWidgetBoss changes, notifications are sent along the IID\_IBOOLEANCONTROLDATA protocol. Additional information is sent via the ClassID. To receive notification about the state change caused by a button press, attach to the button widget boss object's ISubject interface, and listen along the IID\_IBOOLEANCONTROLDATA protocol.

## User Interface Guidelines

The user interface guidelines recommend the widget should be 20 pixels high and a multiple of 5 pixels wide.

**NOTE:** InDesign does not use standard button widgets (other than iconic varieties) on panels, and we recommend you not put standard button widgets on panels; use the iconic varieties instead.

## Using Buttons on Dialogs

Where controls are placed on a dialog, client code can use the helper partial implementation class CDIALOGController and specialize or implement the appropriate methods. CDIALOGObserver typically implements an IObserver. The IDIALOGController interface has utility methods relevant to working with button widgets that set the initial state.

We recommend the IObserver interface be added to the dialog boss object with the superclass CDIALOGObserver, which provides helper methods like AttachToWidget() and DetachFromWidget(). These methods simplify the process of attaching to or detaching from a widget.

When a button is pressed, an IObserver::Update message is sent through the IObserver interface on the dialog boss object. Check the classID of the change to determine whether it is a kTrueStateMessage.

## Edit Boxes

### Using an Edit-Box Widget

Edit boxes are displays of information that can be edited. In the application, they allow an end user to enter a value. The value can be constrained to be an integer or to be expressed in specific units, like picas, points, or degrees.

Edit boxes often are used with nudge button controls. The nudge button control provides precise, incremental control over the contents of edit boxes, particularly when control over parameters in layout-specific units is a requirement. This close coupling between the nudge and edit controls helps explain, in part, why the edit box boss classes descend from the kNudgeEditBoxWidgetBoss boss class.

The treatment of edit boxes is slightly different when they are used in dialogs rather than panels. In panels, typically a new boss class is created that derives from one of the <variant>EditBoxWidgetBoss classes, and it exposes an IObserver interface implemented in client code. This interface receives notifications of changes in the text edit box data model. If the specific ODFRez field controlling this property is kTrue, an observer attached to a particular control is notified on every keystroke. [Table 14](#) lists a selection of the edit-box-related boss classes.

**TABLE 14** Edit Box Boss Classes

Widget boss class	ODFRez custom type	Use
kTextEditBoxWidgetBoss	TextEditBoxWidget	Displays values that are strictly textual, or where you want to parse a value in your own code.
kAngleEditBoxWidgetBoss	AngleEditBoxWidget	Displays values in angular units. See the Rotation dialog.

Widget boss class	ODFRez custom type	Use
kIntEditBoxWidgetBoss	IntEditBoxWidget	Displays integer values. See the Page Setup dialog.
kRealEditBoxWidgetBoss	RealEditBoxWidget	Displays floating point values. See the Scale dialog.
kPercentageEditBoxWidgetBoss	PercentageEditBoxWidget	Displays values in percentage units. See the Scale dialog.
kTextMeasureEditBoxWidgetBoss	TextMeasureEditBoxWidget	Displays values in the current text measurement units. See the Character panel (line weight element).
kLineWtMeasureEditBoxWidgetBoss	LineWtMeasureEditBoxWidget	Displays values in line weight units. See the Stroke panel, when the Dashed line type is selected.
kXMeasureEditBoxWidgetBoss	XMeasureEditBoxWidget	Displays values in current horizontal measurement units.
kYMeasureEditBoxWidgetBoss	YMeasureEditBoxWidget	Displays values in current vertical measurement units.

## Creating an Edit-Box Widget

The main responsibility of the edit-box widget boss classes is to provide for managed input and display of text strings and unit-specific values. Unit-specific variants remove the responsibility for parsing the input strings from the developer. Similarly, the client-code developer does not need to format the output strings when using unit-specific edit boxes. The edit-box widget boss classes also provide for validation of data entry, which is conditional on settings in the ODFRez data statements.

The principal collaboration is with the kNudgeControlWidgetBoss class, which provides the behavior for nudge controls used to bump values up and down by small increments. The mapping between an edit box and a nudge control is established through the ODFRez data statement for an edit box; no code needs to be written to enforce this collaboration.

The main point about the class hierarchy of the edit-box widget bosses is that there is a common ancestor for all edit boxes, which is a nudge edit-box widget boss class (kNudgeEditBoxWidgetBoss). There also are specialized edit boxes that work in units like degrees, percent, real, or integer values, or in measurements like line weight, text, and the measurement unit currently in force in the horizontal or vertical direction.

**NOTE:** Treat the kNudgeEditBoxWidgetboss boss class as if it were an abstract type and not used directly.

There are ODFRez custom resource types that map directly onto each of these boss classes, with the usual naming convention that k<variant>EditBoxWidgetBoss has a related ODFRez custom resource type named <variant>EditBoxWidget. [Example 39](#) shows ODFRez data statements defining an edit-box widget.

**EXAMPLE 39 Sample Edit-Box Widget**

```
IntEditWidget
(
    // CControlView properties
    kInvalidWidgetID, // widget ID
    kSysEditBoxPMRsrcId, // PMRsrc ID
    kBindNone, // frame binding
    Frame(4.0,5.0,84.0,25.0) // left, top, right, bottom
    kTrue, // visible
    kTrue, // enabled
    // CEditBoxAttributes
    0, // nudgeWidgetId (0 or kInvalidWidgetID if no nudge required)
    1, // small nudge amount
    5, // large nudge amount
    0, // max num chars
    kFalse, // read only flag
    kFalse, // should notify on each key stroke
    // TextDataValidation properties
    kTrue, // range checking enabled
    kFalse, // blank entry allowed
    30, // upper limit
    0, // lower limit
    // CTextControlData properties
    "3", // control label
),
```

All edit boxes share the same ODFRez custom resource types in their composition as the IntEditWidget. The notable exception is the FontSpecTextEditWidget type, which adds another ODFRez field of UIFontSpec type.

## Manipulating Edit Boxes

The kNudgeEditWidgetBoss boss class aggregates interfaces like ITextControlData, ICursorRegion, INudgeObserver, and IEeditBoxAttributes, along with other key interfaces like IControlView and IEventHandler. ITextValue queries and sets the value for any unit-specific edit-box widgets. ITextValue accesses the data model of unit-specific edit boxes without having to parse the input string or format the output string. It allows a unit-specific value to be set or queried in an edit box.

ITextControlData is used for untyped edit-box widgets, like the widget with behavior provided by kTextEditWidgetBoss. The implementation of ICursorRegion determines how or whether the cursor changes when it enters an edit box.

## Receiving Messages

Attaching an observer to a subclass of an edit-box widget boss class provides for notification about changes when the end user presses Return or Enter within the edit control. It also is possible to get notification about every keystroke, by setting a flag in the ODFRez data statement associated with the edit-box definition. For examples, see any sample that uses an edit box.

An edit-box widget boss class has a data model that typically consists of a string, which is accessed through the ITextControlData interface aggregated by the particular edit-box widget boss class. The ITextControlData interface provides controlled access to the control's data model for simple text strings. This is appropriate for boss classes like kTextEditBoxWidgetBoss. For unit-specialized edit boxes, the key interface to get and set values is ITextValue. This enables access to the measurement data in points, regardless of what measurement is being displayed. This eliminates the need to parse the string read back from the control or format the data for the control when setting a value.

When the data model changes, registered observers are sent an update message with class ID kTextChangeStateMessage along the IID\_I TEXTCONTROLDATA protocol. For an observer on a unit-specific edit box, the client code in the update message should query for the ITextValue interface and call the GetTextAsValue method to determine the state of the edit box data model.

The most basic use of an edit box is in conjunction with a dialog. In this case, the value of the edit box can be queried only when the dialog is dismissed or the preview check box is selected, in the case of dialogs that allow preview. When the edit box is used on a panel, it is more practical to attach an observer to the edit control. The observer receives an update message when the content of the edit control changes; all keystrokes within the control result in a notification being sent to registered observers.

The simplest case to consider is when the edit box is attached to a dialog. If the dialog is implemented as recommended, using the CDlgController and CDlgObserver helper classes, setting and getting values from the text control is particularly simple. The application framework sends a sequence of messages to the dialog controller in this order:

- InitializeDialogFields()
- ValidateDialogFields()
- ApplyDialogFields()

This sequence of messages is referred to as the *dialog protocol*. In the case of the layer options dialog described previously, when the InitializeDialogFields message is sent to the dialog controller, the edit box is set up with an initial value through the CDlgController::SetTextControlData method. When the user presses OK, the dialog controller is sent a ValidateDialogFields message by the application framework; if this returns kDefaultWidgetId, an ApplyDialogFields message is sent.

## User Interface Guidelines

Adobe user interface guidelines specify that buttons should be 20 pixels high and a multiple of 5 pixels wide.

# Image Widgets

## Using an Image Widget

This section describes widgets used to display images, including icons. These widgets also can have button-like functionality. Image-based widgets are found throughout the application. There are many image-widget boss classes, but few are relevant when writing client code.

There are several icon and picture widgets in the API. Which widget to use depends on whether an icon resource has enough image information or a bitmap or PICT image is required. In either case, a platform-specific resource must be created to hold the image and a binding must be made in ODFRez data statements. If icon resources are sufficient and no button-like behavior is required, the ODFRez type IconSuiteWidget can be used. If a bitmap or PICT image is necessary, the ODFRez type PictureWidget is appropriate. See the PictureIcon SDK sample.

A good example is the Layers panel, which changes the image associated with the eyeball icon depending on whether the layer is visible. The key is to acquire an IControlView interface pointer from an image-widget boss object and call SetRsrcID on this interface to change the picture.

Some of the widget boss classes shown in [Table 15](#) do not respond to button clicks. Others are described here as *pseudo buttons*, to differentiate them from the boss classes that descend from kButtonWidgetBoss; however, they still respond to clicks and aggregate an IBooleanControlData interface. If you have a more complex requirement, like creating an image preview in a widget, the PanelTreeView SDK sample shows how to use a custom control view for a panel rather than an existing image-based widget.

To simplify the domain, client code should be able to perform most tasks using the following few widgets:

- kIconSuiteWidgetBoss, with its counterpart ODFRez IconSuiteWidget (for icons on panels and dialogs). See the PictureIcon SDK sample plug-in.
- kPictureWidgetBoss, and its counterpart ODFRez PictureWidget (for bitmap/PICT based widgets). See the PictureIcon SDK sample plug-in.
- Subclassing the kRollOverIconButtonBoss and one of the several ODFRez types to which it is bound (depending on your specific requirements). All SDK samples that have an About icon use this button.

**TABLE 15** *Image-Widget Boss Classes*

Widget Boss Class	ODFRez Custom Type	Description
kChainButtonBoss	ChainButtonWidget	Used for the constrain proportions button.
kIconFieldWidgetBoss	IconFieldWidget	Used in warnings; RollOverIconButtonWidget.

Widget Boss Class	ODFRez Custom Type	Description
kIconPopupBoss	No corresponding ODFRez custom resource type.	Used on tabbed palettes as the triangle icon for the pop-up menu. For internal use only.
kIconSuitePopupWidgetBoss	IconSuitePopupWidget	Used in places like the Info panel, where you see a small icon with a tiny triangle on the right-bottom corner. Clicking on the icon pops up a contextual menu.
kIconSuiteWidgetBoss	IconSuiteWidget	Used for icons on panels and dialogs. Examples include the warning icons on the Links panel and the top left icon on the Transform panel.
kOverPrintIconPushButtonBoss	OverPrintWidget	Not used.
kPictureWidgetBoss	PictureWidget	Used for some CJK widgets. The Toolbox has an instance of this boss class being subclassed.
kRollOverIconButtonBoss	RollOverIconWidget	Widely used for example SDK samples.
kRollOverIconPushButtonBoss	RollOverIconPushButtonWidget	Used in a control strip for vertical justification mode buttons.
kSimpleIconSuiteButtonWidgetBoss	SimpleIconSuiteButtonWidget	Little used. See the Stroke panel.

## Creating an Image Widget

Most ODFRez types comprise nothing more than a CControlView field with an additional flag specifying whether some appearance should be applied.

## Modifying Image Widgets

The principal interfaces of interest to client-code developers are IControlView (for switching the image displayed) and IBooleanControlData (or at least the role it plays in notification). The IControlView interface dynamically varies the visual representation of a widget. There may be occasions to switch to a different picture depending on state; the methods on the IControlView interface, like SetPluginRsrcID and SetRsrcID, are relevant in this context.

## Manipulating Image Widgets

Clients of the buttons with behavior provided by boss classes like kRollOverIconButtonBoss and derivatives can attach to the ISubject interface of an instance of a boss object and request notifications on the IID\_IBOOLEANCONTROLDATA protocol. An update message is sent depending on the state of the pseudo-button widget. If selected, a kTrueStateMessage value is

sent for the ClassID of the Update message with the IID\_IBOOLEANCONTROLDATA protocol. If the button is unselected, the ClassID is kFalseStateMessage with the same protocol.


A common requirement is using a change in the displayed image to signal a state transition. For example, the Layers panel uses iconic buttons to indicate that a layer is locked or unlocked, visible or invisible. This can be done through the IControlView interface on a particular widget. To switch the icon or picture displayed, acquire an IControlView interface through IPanelControlData::FindWidget, and send a SetRsrcID message to the widget boss object to change the image being displayed.

## Drop-Down Lists and Combo Boxes

### Using Drop-Down and Combo-Box Widgets

This section describes two widely used and closely related widget groups, drop-down lists and combo boxes. Drop-down lists are non-editable displays of lists of information; combo boxes also are used to display non-editable drop-down lists of information, but the end user interacts with the list in a different way. The relation between the two is that a combo box is a composite of an edit-box control (with nudge buttons) and a drop-down list. A combo box allows a user to select from a drop-down list or use a text-edit box to enter a new choice. For example, the Character panel in the application uses several different kinds of combo boxes; see [Figure 13](#). The widget that displays available fonts is a type-ahead combo box. There are several specialized combo boxes that display information in measurement units (see [Table 16](#)).

**FIGURE 13** Widgets used in the Character Panel



**TABLE 16 Drop-down List and Combo-box Boss Classes**

Widget Boss Class	ODFRez Custom Type	Example
kAngleComboBoxWidgetBoss	AngleComboBoxWidget	Displays a set of values in angular units. See the Transform panel.
kDropDownListWidgetBoss	DropDownListWidget	Displays a set of text values rather than numeric values, where no type-ahead or nudge is required. See the Stroke panel (Stroke-type).
kIntComboBoxWidgetBoss	IntComboBoxWidget	Displays a set of integer values. See the kerning combo box on the Character panel.
kLineWtMeasureComboBoxWidgetBoss	LineWtMeasureComboBoxWidget	Displays values in line weight units. See the Stroke panel.
kPercentageComboBoxWidgetBoss	PercentageComboBoxWidget	Displays values in percentage units. See the Transform panel.
kRealComboBoxWidgetBoss	RealComboBoxWidget	Displays a set of floating-point values.
kTextComboBoxWidgetBoss	TextComboBoxWidget	Displays textual values. See the Find/Change dialog.
kTextMeasureComboBoxWidgetBoss	TextMeasureComboBoxWidget	Displays units in the current text-measurement units. Use in the Character panel to specify leading.
kTypeaheadTextComboBoxWidgetBoss	TypeaheadTextComboBoxWidget	Allows a user to enter partial string and have the control predict the value to select. Used in the Character panel to display font families.
kXMeasureComboBoxWidgetBoss	XMeasureComboBoxWidget	Displays values in the current horizontal measurement units.
kYMeasureComboBoxWidgetBoss	YMeasureComboBoxWidget	Displays values in the current vertical measurement units.

The API has many combo-box widget boss classes that provide rich behavior for combo boxes. The combo box can cooperate with a nudge control widget, to allow incremental changes in input parameters. Combo boxes are appropriate for displaying units like measurement units, angles, and percentages.

When input is selected from a list of values, the combo box is more convenient than the drop-down list. Type-ahead combo boxes allow quick access to a value in a sorted list; the user can

enter keystrokes matching items in the list. For example, the font family combo box on the Character panel allows the first few characters of the font name to be entered, which scrolls the list to the desired location. The API has many types of combo boxes, some of which are shown in “[Widgets used in the Character Panel](#)” on page 208.

The following are the measurement units specific to the layout of drop-down lists and combo boxes:

- x-measurement units
- y-measurement units
- Line-weight measure
- Text measure

A different measurement system may be in force for each of these, and a combo box of a specialized type displays the choices in the contextually appropriate units. [Table 16](#) shows a selection of the combo boxes available in the API.

## Creating a Combo Box

Combo boxes are panel widgets; combo-box widget boss classes descend from `kGenericPanelWidgetBoss`. When instantiated, a combo-box widget boss object creates two children, a drop-down-list widget boss object and an edit-box widget boss object. There appear to be many widget boss classes related to combo boxes in the API, but those related to the encapsulated drop-down list and edit box within the combo-panel are implementation boss classes and not required for writing client code.

## Modifying a Combo Box

The data model for combo boxes consists of a string-list control data model for the drop-down (accessed via the `IStringListControlData` interface) and the data model for an edit box, represented by the `ITextControlData` interface. Changes in selection by the end user are sent to client code along the `IID_ITEXTCONTROLDATA` protocol. The edit box does not have an independent data model to the string list; it reflects the current selection in the drop-down list.

## Capabilities

`IStringListControlData` populates both drop-down lists and combo boxes dynamically. `IDropDownListController` changes the state of a drop-down list or combo box drop-down, and it controls the current selection of the drop-down list or combo box. For example, to specify the item selected, enable or disable the control. The `ITextControlData` interface exposed by the `kComboBoxWidget` boss relates to the child edit-box widget. Similarly, the `IEditBoxAttributes` interface relates to the child edit-box widget. However, changes to selection are notified along the `IID_ITEXTCONTROLDATA` protocol for a combo box, which is not intuitive; a list-control data protocol might have been expected.

---

# Splitter Widgets

## Using the Splitter Widget

The splitter widget manages the dimensions of multiple panels within one container. For example, the Pages panel exploits a splitter widget to create two regions that can be sized co-dependently. The splitter widget divides both vertically and horizontally. The setting is determined by the bindings, normally specified on the CControlView-related portion of the ODFRez data statements that define the splitter. [Table 17](#) shows some boss classes that implement splitters.

**TABLE 17** *Splitter Boss Classes*

Widget Boss Class	ODFRez Custom Type	Description
kSplitterWidgetBoss	SplitterWidget	Used in InCopy's Thesaurus panel.
kSplitterPanelWidgetBoss	SplitterPanelWidget	Used in XML panel.
kLayoutSplitterPanelWidgetBoss	LayoutSplitterPanelWidget	Used in Page panel.
kLinkedSplitterPanelWidgetBoss	LinkedSplitterPanelWidget	Used in XML Mapping and Word Preferences dialogs.

## Creating a Splitter Widget

The kSplitterWidgetBoss boss class and the kSplitterTrackerBossMessage tracker boss class cooperate to provide the behavior of the splitter widget. The splitter widget is initialized by ODFRez data statements. There is little need for additional customization of the splitter widget. The ODFRez custom resource type SplitterWidget is bound to the kSplitterWidgetBoss boss class. The superclass of kSplitterWidgetBoss is the base widget boss class, kBaseWidgetBoss.

## Manipulating a Splitter Widget

The kSplitterWidgetBoss boss class exposes interfaces like ISplitterControlData, which provides access to the list of managed widgets. The ICursorRegion interface effectively is a signature that the widget is bound to a cursor provider. The ISplitterControlData interface provides access to the list of splitter-managed widgets and queries methods about the properties of the control.

The kSplitterTrackerBossMessage boss class provides the behavior behind the tracker. Much of the widget's capability comes from the implementation of ITracker on this widget boss class. The splitter-widget boss class event handler serves only to create the tracker and send it a BeginTracking message.

---

## Scroll Bars

### Using a Scroll Bar

To provide scrolling views in the user interface, the API uses a pattern or assembly consisting of three elements, listed in [Table 18](#):

**TABLE 18 Elements for Providing Scrolling Views**

Elements	Description
Panoramas	An aspect of a scrollable object that can be accessed through an IPanorama interface. Scrollable objects expose this interface.
Panorama syncs	Abstractions in the API that coordinate a scrollable view with scroll-bar controls, with behavior provided by one of two boss classes named xxxScrollBarPanoramaSyncBoss. For internal use.
Scroll bars	Controls whose behavior derives from the kScrollBarWidgetBoss widget boss class.

A fundamental application of these elements is the layout widget. Scroll bars and panoramas occur widely within the application's plug-in code base.

Scroll bars are widgets with behavior deriving from kScrollBarWidgetBoss. The scroll bar data model is accessed through the ICounterControlData interface. Panoramas are aspects of objects that scroll; the IPanorama interface scrolls a view. The boss classes mentioned below expose an IPanorama interface.

### Creating a Scroll Bar

The kScrollBarWidgetBoss boss class extends kBaseWidgetBoss and is bound to the ODFRez custom resource type ScrollBarWidget. When a scroll bar is added to a control like a StaticMultiLineTextWidget, it works hand-in-hand with a panorama (IPanorama) to produce the correct scrolling behavior of the dependent widgets. The scroll bar receives input from the end user, and the implementation code manipulates the view through the IPanorama interface.

### Manipulating a Scroll Bar

The ICounterControlData interface is the key interface for scroll bars. It accesses the data model of a scroll-bar widget boss object and changes its state. The IPanorama interface manipulates a scrollable object's view.

## Receiving Messages

The kScrollBarWidgetBoss class exposes ICounterControlData, the data model for a scroll bar widget.

An observer requesting changes in the data model of a scroll bar widget object attaches to its ICounterControlData interface and requests notification on the IID\_ICOUNTERCONTROLDATA protocol. When the counter control data changes, registered observers are notified with an update message with the classID parameter of kCounterChangeStateMessage. The client also gets passed a pointer to a CounterControlUpdateParams object as the changedBy parameter of an IObserver::Update message.


---

## Sliders

### Using a Slider

A slider control is appropriate for situations in which an end user can enter a parameter that can vary continuously over a finite, determinate range. There are several *standard sliders* (descendants of kStdSliderWidgetBoss) in the application's user interface, such as on the Color panel, shown in [Figure 14](#).

**FIGURE 14**     *Slider Widgets*



A *pop-up slider* (descendant of kPopupSliderBoss) can be used in the same situation, when the slider should appear only when the user wants to change a particular value rather than be continuously visible. [Figure 15](#) shows an example of a pop-up slider in the Transparency panel. This slider controls the opacity of the selected page items. There also is a pop-up slider on the Swatches panel, which is used to vary the tint associated with a particular color in a swatch. This uses a class of pop-up slider specialized for the input of real-valued numbers.

**FIGURE 15**     *Pop-up Slider Combo-Box Widget*



Pop-up slider combo-box controls combine an edit box and a button. They are child widgets of a panel. The pop-up slider appears only when the end user clicks a button to show the slider in its own floating window. This pop-up slider is a relatively complex control, consisting of a cooperating assembly of an edit box, a button, a floating window, and a slider, which are owned and/or managed by a parent boss object that is a descendant of the generic panel widget boss class (`kGenericPanelWidgetBoss`). It allows you to pack more user interface into a given area of screen real estate than is possible with standard slider controls.

[Table 19](#) shows boss classes that implement sliders:

**TABLE 19 Slider Boss Classes**

Widget Boss Class	ODFRez Custom Type	Example
<code>kStdSliderWidgetBoss</code>	(none: you create your own)	Slider that is continuously available, as on the Color panel.
<code>kRealPopupSliderComboBoxWidgetBoss</code>	<code>RealPopupSliderComboBoxWidget</code>	Pop-up slider, as on the Swatches panel.
<code>kIntPopupSliderComboBoxWidgetBoss</code>	<code>IntPopupSliderComboBoxWidget</code>	Pop-up slider with integer values, as on the Inks panel.
<code>kPercentPopupSliderComboBoxWidgetBoss</code>	<code>PercentPopupSliderComboBoxWidget</code>	Pop-up slider with percentage values, as on the Transparency panel.

## Creating a Slider

To use the standard slider widget (`kStdSliderWidgetBoss`), create a new ODFRez custom resource type that can extend the ODFRez custom resource type `CControlView`, and add an ODFRez `SliderControlData` field. This new type is then bound to the subclass of `kStdSliderWidgetBoss` (`k<whatever>SliderWidgetBoss`). This new ODFRez custom resource type is bound to the boss class delivered by your own plug-in that extended the `kStdSliderWidgetBoss` boss class. There are other, subtle dependencies and interfaces required for the standard slider implementation to work correctly.

The slider pop-up widget is a compound widget, consisting of a panel, edit box, button widget, and slider. It is called a *combo-box slider* because it functions as if it were a combo box, with a slider replacing the traditional combo-box drop-down list.

The `kPopupSliderComboBoxWidgetBoss` boss class provides the core of the behavior for the combo-box slider. This boss class extends the `kComboBoxWidgetBoss` boss class. Do not use this `kPopupSliderComboBoxWidgetBoss` boss class directly; instead, use one of its subclasses, which have specified associated measurement units.

A pop-up slider has much functionality in common with combo-box widgets. A pop-up slider has part of its behavior provided by the `kPopupSliderBoss` boss class, which extends the standard slider widget boss (`kStdSliderWidgetBoss`).

The pop-up slider widget does not require an ODFRez CSliderControlData field to be initialized. Internally, the slider widget on the floating window does have an ISliderControlData interface, because the class kPopupSliderBoss derives from kStdSliderWidgetBoss; however, a pop-up slider is initialized by the settings obtained by querying through the ITextDataValidation interface. These setting specify the range through the interior ISliderControlData interface on the kPopupSliderBoss. The fields of the ODFRez type TextDataValidation in the ODFRez data statements defining the pop-up slider specify the maximum and minimum slider values.

## Manipulating a Slider

ISliderControlData is an interface aggregated on the kStdSliderWidgetBoss boss class. It encapsulates information about the maximum and minimum values exposed in the control's range, and the current value of the slider setting. If the data value changes, notifications with ClassID equivalent to kRealChangeStateMessage are sent to registered observers of the slider boss object.

The boss class aggregates an IEventHandler interface. This should not need to be overridden. The event handler with implementation ID of kCSliderEHIImpl is responsible for creating a tracker if required and calling the tracker methods in the appropriate sequence. There is an ICControlView interface on the slider control, whose default implementation uses the ISliderStateData and ISliderControlData interfaces on the widget boss object to determine how to draw the visual representation of the control.

When the data model of a pop-up slider changes, an IOObserver::Update message is sent to attached observers. Interested client code queries for the state of the pop-up slider by using the ITextValue interface. This allows the value of the slider state (percent, real, or integer) to be queried. Similarly, to set the state of the pop-up slider, use the ITextValue interface. Other properties of the pop-up slider are queried through the ISliderControlData interface. For example, this is used to determine the minimum or maximum of the pop-up slider range.

## Receiving Messages

The state of the standard slider is represented by ISliderControlData. Changes to this state are broadcast along IID\_ISLIDERCONTROLDATA.

The state of a pop-up slider is represented by ITextValue. Changes are broadcast with the IID\_ISLIDERCONTROLDATA protocol.

Notifications about changes to the state of a standard slider control are sent along the IID\_ISLIDERCONTROLDATA protocol to registered observers. The usual process in processing the IOObserver::Update message is to query the data value through ISliderControlData::GetValue, to determine the control state. Add an IOObserver interface to the kStdSliderWidgetBoss by subclassing. On receiving an AutoAttach message from the application core, the client code queries for the ISubject interface on the widget boss object and requests notifications along the IID\_ISLIDERCONTROLDATA protocol. The observer then detaches in AutoDetach.

When changes occur in the slider control's data, IObserver::Update messages are sent to this observer. A message with ClassID of kRealChangeStateMessage is sent to the observer. The ISliderControlData interface then retrieves the current data value associated with the slider.

Pop-up slider notifications also are sent along the IID\_ISLIDERCONTROLDATA protocol; however, the ClassID of the message is unique to the pop-up slider and is one of the following:

- kPopupSliderOpenMessage, sent when the slider opens.
- kPopupSliderApplyChangeMessage, sent when the value is being committed by the end user.
- kPopupSliderCloseMessage, sent when the slider is about to close.

## Implementation Details

The superclass for all pop-up sliders is kPopupSliderComboBoxWidgetBoss. The core behavior of pop-up sliders comes from the IControlView implementation aggregated on this boss class. Another boss class, kPopupSliderButtonBoss, provides the behavior behind the button on the pop-up slider combo-box widget. The IEventHandler implementation aggregated on this kPopupSliderButtonBoss class is responsible for creating a floating window and adding a child widget, which is the slider the user manipulates.

The appearance of the pop-up slider is determined by the implementation of the IControlView interface with identifier kPopupSliderComboBoxViewImpl. This implementation is responsible for creating the child widgets that provide the behavior of the pop-up slider. When the pop-up slider is restored from persistent data (plug-in binary resource first time, or saved data database if its representation exists in it), it creates an object of class kPopupSliderButtonBoss to provide the behavior behind the button that shows the slider. An object of class kComboBoxEditBoxWidgetBoss also is created, to support the behavior of the edit box in the pop-up slider combo-box widget. The pop-up slider itself (kPopupSliderBoss) is created on demand by the class that implements the IEventHandler interface for the composite pop-up slider combo-box widget. Typically, the slider is shown on a left-button down event. The implementation creates an object of class kWindowBoss and specifies it is a floating window. It then creates an object of class kPopupSliderBoss and adds it as a child of this new window boss object.

---

## Tree-view Widgets

### Using a Tree View


A tree-view widget allows you to display hierarchical data; users can expand or contract nodes in the tree to increase or decrease the amount of detail displayed. A tree-view widget can have vertical and/or horizontal scroll bars, to allow end users to scroll within the view of the tree structure.

The tree-view control is complex. The basic procedure is as follows:

1. Create a new ODFRez custom resource type for a tree-view widget that extends the ODFRez type TreeViewWidget. Define a resource of this new type, and add it to the dialog or panel where the tree view control will appear.
2. Create a new ODFRez custom resource type for a tree-node widget that extends the ODFRez type PrimaryResourcePanelWidget. Define branch node and leaf node resources based on this tree node widget type.
3. Define a tree-view widget boss that extends kTreeViewWidgetBoss. In this boss, aggregate at least ITreeViewHierarchyAdapter and ITreeViewWidgetMgr.
4. Provide an implementation for the ITreeViewHierarchyAdapter and ITreeViewWidgetMgr interfaces.
5. Initialize the tree view with ChangeRoot() of ITreeViewMgr. Also, inform InDesign of any tree model change through ITreeViewMgr.

Figure 16 shows a tree view and indicates the widget boss classes that provide the behavior for the components of the tree view. The kTreeViewWidgetBoss class provides the behavior for the main control, the kTreeNodeWidgetBoss class provides the bulk of the behavior for nodes in the tree, and kTreeExpanderWidgetBoss provides the behavior of the triangle-icon that can be used to show or hide the children shown for a specific node.

**FIGURE 16** Widgets involved in the Tree View



The following sections describe how to work with the tree-view control. The control is relatively complex and can be tricky to use. The PanelTreeView SDK sample shows how to use these controls.

The API to use a tree-view control is written differently than platform-specific APIs, such as the API for the TreeView control on Windows or the Java™/Swing tree-control. Instead of adding nodes to an InDesign tree-view control directly, client code provides the means for navigating through its own tree model. The tree-view control widget boss object (kTreeViewWidgetBoss) handles navigation, sends queries about the tree model, and asks for widgets for a particular node when it needs them. This is carried out by the framework sending messages to the client code, asking for, say, a root node in the tree or a widget that can be used to display a particular uniquely identified node.

[Table 20](#) shows boss classes that implement tree views:

**TABLE 20 Tree View Boss Classes**

Widget Boss Class	ODFRez Custom Type	Responsibility
kTreeViewWidgetBoss	TreeViewWidget	Provides the main behavior for tree controls.
kTreeNodeWidgetBoss	TreeNodeWidget	Represents a node in tree view. Subclass to hear expand/collapse events with an observer or to override the event handler.
kTreeExpanderWidgetBoss	TreeExpanderWidget	Provides behavior to expand/collapse nodes of tree with children.

The essence of working with the tree-view control is to subclass kTreeViewWidgetBoss and aggregate on it your implementation of the ITreeViewHierarchyAdapter interface. This enables you to *adapt* your data model to the needs of the InDesign tree-view control. You also are required to provide an implementation of the ITreeViewWidgetMgr interface, which allows your client code to specify which user interface widgets to create to display a given node, and also allows your client code to specify how the widgets should be placed.

Client code is required to notify the application framework when changes in the tree model take place, like nodes being added or deleted. This helps keep the tree model (based on your data) and the tree view synchronized. The key responsibilities of client code are as follows:

1. Return the representation of nodes at given locations in the tree's data model, such as the root, or at a given index in the children of a given node.
2. Manufacture widgets to render tree nodes given a uniquely identified node.
3. Render views of data at uniquely identified nodes.
4. Optionally provide information about the intended geometry of rendered nodes within the tree.

Client code provides methods for returning the root node and the parent or child node at a given index from any given node. Each node within the tree can have an associated data item. This might be a UID, in which case an API class (UIDNodeID) is used to represent each node. Alternatively, the data items may be entirely custom items that are unique to your client code, in which case it may be necessary to subclass an API type. Each node should be identified uniquely. This enables the application to render the correct view of the underlying data model provided by the client code.

When the tree view is updated, the application core may pass to the client code a reference to any node. It is up to the client code to provide an appropriate widget to render the node and populate the widget with a view of the associated data.

## Adapter Pattern

The tree-view control in the API uses the design pattern adapter, described in “Design Patterns” (Gamma, Helm, Johnson, and Vlissides, *Design Patterns*, Addison-Wesley, 1995). At its

most basic, the adapter pattern allows two existing but incompatible classes to work together without changing the public interface of either class. The classes required to work together are named in the pattern as *client* and *adaptee*.

**NOTE:** Do not confuse client in this pattern with client in plug-in client code.

An instance of the client sends particular messages to the target, an abstract API implemented by the adapter. The messages sent by the client are translated by the adapter into method calls on an adaptee. The adapter then manufactures an appropriate return value, if required, based on the adaptee's response. In terms of the tree control, the roles are occupied as shown in [Table 21](#).

**TABLE 21 Roles in the Adapter Pattern**

Role	Occupied by ...
Adaptee	The data model, such as a tree model representing the XML logical structure of a document.
Adapter	The plug-in client code's implementation of ITreeViewHierarchyAdapter.
Client	Application core, specifically, the widget run-time subsystem (not client code).
Target	The abstract API on ITreeViewHierarchyAdapter.

## Factory Method Pattern

The factory method pattern described in [Gamma et al, 1995] is used in implementing a working tree-view control. This pattern can be used when a framework needs to instantiate classes but has knowledge of only abstract classes, which cannot be instantiated directly. In implementing a tree control, a parameterized factory method is used, where an identifier is passed in by the framework specifying what type of object to manufacture. There is a factory method, ITreeViewWidgetMgr::CreateWidgetForNode, which is parameterized by passing a reference to the node being rendered. Client code is responsible for returning a new instance of an IControlView interface on a newly created widget boss object that can be used to render the node's associated data.

## Creating a Tree View

The core behavior for the tree view widget is determined by the kTreeViewWidgetBoss class. The first responsibility of client code is to subclass this boss class and create one's own boss class that provides implementations of ITreeViewHierarchyAdapter and ITreeViewWidgetMgr.

The behavior of individual nodes in the tree view control is provided by the kTreeNodeWidgetBoss boss class. Subclass this where you want to add an IObserver interface to obtain notification about, for instance, expansion or contraction events associated with tree nodes. There is a tree expander widget, with behavior provided by the kTreeExpanderWidgetBoss boss class. Key boss classes and their responsibilities are listed below.

There is an ODFRez custom resource type TreeViewWidget. Because client code must subclass kTreeViewWidgetBoss, it always is necessary to perform a corresponding subclass of TreeViewWidget and bind it to the new widget boss class, such as kMyTreeViewWidgetBoss. The ODFRez custom resource type TreeExpanderWidget is used on panels to render individual nodes in the tree. This widget allows the descendant nodes of a node to be displayed or collapsed. If no children are associated with a given node, a correct implementation is to hide this widget.

There also is a new ODFRez custom resource type created for displaying each node in the tree-view control. For tree-view controls on panels, a subclass of PrimaryResourcePanelWidget is appropriate. For tree-view controls on dialogs, an erasable panel is required, as the tree-view control does not know anything about erasing its own background. The PanelTreeView SDK sample shows how to use a tree-view control on a dialog and how to receive notification about different tree-related events.

## Manipulating a Tree View

### **ITreeViewHierarchyAdapter**

This is one of the two interfaces you *should* implement to obtain a working tree-view control. The ITreeViewHiearchyAdapter interface provides the means for navigating through your tree model. It is like the adapter pattern, in that it provides a way for the TreeView widget to navigate your tree model without requiring your tree model to conform to any given interface.

### **ITreeViewWidgetMgr**

Provide an implementation of this interface. ITreeViewWidgetMgr is where you create the tree-view control widgets in your client code and apply node data to the widget. There is a partial implementation of ITreeViewWidgetMgr, called CTreeViewWidgetMgr, that takes care of the widget placement implementation and simplifies the implementation of this interface.

### **ITreeViewMgr**

This interface is aggregated on the kTreeViewWidgetBoss boss class; you are *not* expected to provide your own implementation of this interface. The principal responsibility of this interface is to keep the tree view synchronized with changes to the tree model. Client code should call methods in this interface to let the tree know when changes to the tree occur.

For example, client code should call ITreeViewMgr::ChangeRoot() to initialize the tree-view control. Call this whenever you want to regenerate the tree, like when the tree view control was in a state where it did not hear about changes to the data model and wants to start fresh. There also is a debug-only version of ChangeRoot() that validates an implementation of ITreeViewHierarchyAdapter.

Client code calls ITreeViewMgr::NodeAdded() and ITreeViewMgr::BeforeNodeDeleted() when nodes are added and about to be removed from the tree model. Failure to call these methods when changes occur in the tree model causes problems in the tree view, like nodes unintentionally disappearing.

ITreeViewMgr::NodeChanged() should be called when a nodes data has changed that will not affect the nodes height. If the change will affect the node's height, call ITreeViewMgr::BeforeNodeDeleted(), followed by ITreeViewMgr::NodeAdded().

## Uniquely identifying each Node

On examining the ITreeViewHierarchyAdapter interface, notice the extensively used class NodeID. This is best explained by looking at the problem it is trying to solve. When the tree view asks for the root node, the client needs to uniquely identify that node. In a simple case, a UID may be all that is needed to identify the node.

Not all tree models, however, have UIDs associated with each node. For example, the PanelTreeView SDK sample represents views onto the local file system, and each node encapsulates a path in the file system, not a UID-based object. That leads us to return a class that can be specified by the client but derives from a class providing the methods required by the tree-view control.

The main problem is that we would need to return a pointer to this class, which leads to potential problems with clean-up. To make clean-up easier, the framework uses the NodeID class as a *smart pointer*. NodeID is a class that holds and deletes pointers to NodeIDClass classes.

If your tree is UID-based, there is an existing NodeIDClass-based class you can use, UIDNodeID. If you require different data to identify your tree nodes, create your own class based on NodeIDClass.

## NodeID and Related Classes

There are several classes that can be found as arguments and return types in the interfaces that should be implemented to create a working tree-view control. These are defined in the NodeID.h API header file. They have similar names, and confusion can arise between NodeID, which is like a smart pointer for the type NodeIDClass, and other classes, like UIDNodeID, which is a subclass of NodeIDClass. There also is a smart pointer, TreeNodePtr, which is used for descendants of type NodeIDClass, like UIDNodeID.

As discussed earlier, every node need to be identified uniquely. In InDesign, the NodeIDClass class represents an individual node. A subclass of this class, UIDNodeID, is available in the API. In reading UIDNodeID, remember it should have the suffix “-Class.”

To muddy the water further, there is a NodeID class that is like a smart pointer and is used to manage the lifetime of dynamically created NodeIDClass objects. This class is found as a parameter on methods in ITreeViewHierarchyAdapter and ITreeViewWidgetMgr.

In certain situations, it may be adequate to use a UID to identify a tree node. There is a class in the API called UIDNodeID that can be used for these cases. Otherwise, you need to implement your own subclass of NodeIDClass that identifies each node uniquely. For an example of how this can be done, see PanelTreeView.

Table 22 lists the classes related to the tree-view widget.

**TABLE 22 C++ Classes related to the Tree-View Widget and their Responsibility**

C++ Class	Responsibility
NodeIDClass	The data associated with each node. Allows each node to be uniquely identified. Subclass this type to create custom data nodes.
TreeNodePtr	A smart pointer that is the equivalent of InterfacePtr for NodeIDClass descendants.
NodeID_rv	A class for method return values similar to NodeID, except it gives up control of the encapsulated NodeIDClass rather than copying it.
NodeID	Manages the lifetime of objects of type NodeIDClass.

## Node Recycling

The tree-view widget contains instantiated widgets for visible nodes. For example, when the end user scrolls down, the node that was on top is no longer visible, and there is a new visible node at the bottom. The application framework removes the top widget, and if it is of the same type (based on the WidgetID obtained from ITreeViewWidgetMgr::CreateWidgetForNode()) as the widget needed for the bottom node, the framework re-uses the widget for the bottom node. This is one reason the ITreeViewWidgetMgr::CreateWidgetForNode() and ITreeViewWidgetMgr::ApplyNodeIDToWidget() methods are distinct. It is necessary for the application framework to create new widgets only when there are no widgets of the right type to recycle.

## Tree-View Attributes

The tree-view control also has attributes that determine scroll information and whether the root item is shown. The attributes are set in the resource for the TreeView. Vertical and horizontal scroll bars are provided by the tree view (if desired), so you do not need to add them yourself. Specify in the resource whether you want no scroll bar, vertical only scroll bars, or horizontal and vertical scroll bars.

The scroll amounts for both horizontal and vertical scroll bars also are set in the resource. You must set two values for each scroll bar:

- The scroll-button increment is the number of pixels that will scroll when you click on either scroll button.
- The thumb-scroll increment is the smallest number of pixels that will scroll when an end user moves the scroll bar thumb.

For example, the tree view control can be configured so the scroll button moves 20 pixels, but the thumb scroll moves just 1 pixel, allowing for greater accuracy. The thumb-scroll increment must be a factor of the scroll-button increment.

Another attribute on the TreeView specifies whether to display the root element. You should have only one root element, but you may not necessarily want to show it.

## Receiving Messages

Some APIs have an explicit tree model behind the tree control (for instance, in Java Swing). The InDesign API control, however, leaves it up to the client code to determine how the tree data model is represented. It requires only that client code can provide certain kinds of information as requested about its data model, like the number of children it has.

Other controls have a simpler data model and a simple notification structure that relates directly to this data model. For example, an edit box has an `ITextControlData` interface that, when changed, notifies along the `IID_I TEXTCONTROLDATA` protocol. The situation is more complex for tree view controls.

There are at least two kinds of changes in which client code might be interested:

- The end user changes the node selected in the tree-view control. To receive notifications of this, attach an observer (`IObserver` implementation of your own) to the `ISubject` interface of your `kTreeViewWidgetBoss` subclass, and listen along the `IID_ITREEVIEWCONTROLLER` protocol.
- A node in the tree expands or collapses. In this case, attach an observer (`IObserver`) to the `ISubject` interface of the `kTreeNodeWidgetBoss` subclass, and listen along the `IID_ITREEVIEWMGR` protocol.

If you use the shadow (proxy) event-handler pattern shown in the `PanelTreeView` SDK sample, it also is possible to receive notification of events like double-clicks within the nodes of the tree view.

## Implementing the Required Interfaces

### Implementing `ITreeViewHierarchyAdapter`

The `ITreeViewHierarchyAdapter` interface provides the means for navigating your tree. Its `GetRootNode()` method returns an instance of a node that represent your root node, with data allowing it to be uniquely identified as such.

The `ITreeViewHierarchyAdapter::GetParentNode()` method requests the parent node of a given node. If the given node is a root node, there is no parent for a root node, so return nil; otherwise, depending on the location of the node in your tree model, return its parent.

In implementing `ITreeViewHierarchyAdapter::GetNumChildren()`, return the number of children, given a node that is in your tree model. The `ITreeViewHierarchyAdapter::GetNthChild()` method is the counterpart to `ITreeViewHierarchyAdapter::GetParentNode()`. Since a node can have multiple children but only one parent, this method passes in the index position of the child node it is querying.

In implementing `ITreeViewHierarchyAdapter::GetChildIndex()`, the index refers to the index position used in the `ITreeViewHierarchyAdapter::GetNthChild()`, and the range of the index is from 0 to (number of children-1).

In implementing the `ITreeViewHierarchyAdapter::GetGenericNodeID()` method, simply return a dummy node that makes a generic node. This method is used primarily for persistence. When something is purged and the application framework must write out a

NodeIDClass, it uses the ReadWrite() method on the NodeIDClass. When the application framework needs to read it back in, it needs to be able to create instances of that NodeIDClass. It uses ITreeViewHierarchyAdapter::GetGenericNodeID() to create an instance, then calls ReadWrite() on the NodeIDClass to initialize it.

### **Implementing ITreeViewWidgetMgr**

The next implementation you need to provide is for ITreeViewWidgetMgr. This interface is like a widget factory method, because this is where you create widgets for the nodes in the tree. The two main methods are CreateWidgetForNode() and ApplyNodeIDToWidget().

The purpose of ITreeViewWidgetMgr::CreateWidgetForNode() is to create the right widget for the NodeID passed in. In this method, create the widget, but do not change the widget data to match the node.

Changing the widget data, such as setting the text of a static text widget on a panel to render the data associated with a node, happens in ITreeViewWidgetMgr::ApplyNodeIDToWidget().

These two methods are distinct, because the application framework re-uses widgets that are not needed. The framework creates the widget once in ITreeViewWidgetMgr::CreateWidgetForNode(), then uses it several times by calling ITreeViewWidgetMgr::ApplyNodeIDToWidget() and passing in a different NodeID. In this way, the framework is not continually creating and deleting widgets.

The implementation of the ITreeViewWidgetMgr::CreateWidgetForNode() method is where client code creates the widget from the resource, given a node. When the application framework wants to re-use a widget, it calls ITreeViewWidgetMgr::GetWidgetTypeForNode() to determine what widgets can be used with that node. GetWidgetTypeForNode() returns a WidgetID corresponding to the type of widget given.

When creating widgets for different types of nodes, the ITreeViewWidgetMgr::GetWidgetTypeForNode() method becomes significant. In the ITreeViewWidgetMgr::CreateWidgetForNode() method, you can look at the NodeID and determine what type of node to create.

The framework uses the widget's WidgetID to discriminate between different node types in the tree. The framework only calls ITreeViewWidgetMgr::ApplyNodeIDToWidget() with a widget that has the WidgetID returned in ITreeViewWidgetMgr::GetWidgetTypeForNode(). For this reason, widgets of the same type must have the same WidgetID.

# The Quick Apply Dialog

## Adding Elements to the Quick Apply Dialog

Elements are added to the quick-apply dialog using a quick-apply service-provider boss (signature interface `IQuickApplyService`). The quick-apply service provides a set of `QuickApplyFindListNodes` to the application. These identify the name of the item to be added, a type, and an icon to accompany the item in the quick-apply dialog. Once the user selects an item in the quick-apply dialog, each quick-apply service is called in turn until one handles the item.

The procedure for implementing a quick-apply service is as follows:

1. Create the quick-apply service boss class, using the standard `kQuickApplyRegisterProviderImpl` implementation for the `IK2ServiceProvider`, along with a custom implementation of the `IQuickApplyService`.
2. Define the action ID for the type of item to be used by the quick-apply service.
3. Provide the implementation of the `IQuickApplyService` interface. In the `IQuickApplyService::GetItemTypesHandled`, ensure the prefix key provided in the set of `QuickApplyItemRecords` does not clash with any previously registered prefix keys (available through the `existingItemTypes` parameter).

For an example of implementing a quick-apply service, see the SnippetRunner SDK sample.

## Filtering Elements from the Quick Apply Dialog

The quick-apply subsystem supports the ability to filter out elements as the quick-apply dialog is being populated through the quick-apply filter service. This is called as entities are added to the quick-apply dialog.

To implement a quick-apply filter service, follow these steps:

1. Create the quick-apply filter service boss class, providing a custom implementation for the `IK2ServiceProvider`, along with a custom implementation of the `IQuickApplyFilterService`.
2. In the custom service-provider implementation, the `GetServiceID` method should return `kQuickApplyFilterService`.
3. In the custom filter service implementation, remove the elements to be filtered from the `workingList` parameter of the `FilterItems` method.

For an example of implementing a quick-apply filter service, see the SuppUI SDK sample.



# XML

---

## The XML User Interface

### Showing or Hiding Tagged Frames or Element Markers

You can highlight information about tagged content items, by turning on the feature that shows either tagged frames or element markers in stories.

#### Solution

1. The IXMLPreferences interface stores this information on the (kWorkspaceBoss) session workspace. Its contents can be changed by processing low-level commands.
2. To change the visibility of tag markers, use the low-level command kShowTagMarkersCmdBoss. To change the visibility of tagged frames, use kShowTaggedFramesCmdBoss.

#### Sample Code

```
SnpXMLHelper::ShowHideTaggedFrames
```

#### Related APIs

- IXMLPreferences
- kWorkspaceBoss

### Changing the Visibility of the Structure View

You can show or hide the structure view.

#### Solution

1. The visibility of the structure view is stored in an IBoolData interface with PMIID of IID\_ISTRUCTUREISSHOWNBOOLDATA on a document window (kDocumentPresentationBoss). See SnpManipulateStructureView::IsStructureViewShowing().
2. If the structure view is not visible and you want to open it, you can toggle its state via an action. Ask the action manager (IActionManager) to perform an action on (kOpenStructureWinActionID), which toggles the visibility of the structure view. See SnpManipulateStructureView::ChangeStructureViewState.

#### Sample Code

```
SnpManipulateStructureView
```

## Related APIs

- IActionManager
- IBoolData

## Changing the Appearance of the Structure View

The structure view can show or hide information about element attributes, XML comments, processing instructions, and, if required, it can show snippets of text from XML elements that have text content. You can vary the information presented to your end users through the structure view and control its appearance.

### Solution

You can change the appearance of the structure view if you know how to change the data stored in the interface that controls its appearance. The appearance of the structure view is controlled by preferences stored in IStructureViewPrefs on the session workspace (kWorkspaceBoss). You can change these in one of two ways:

- Ask the action manager (IActionManager) to perform the appropriate action. For example, to toggle the visibility of text snippets in the logical structure view, ask the action manager to perform kStructureShowTextSnippetsActionID.
- Use the low-level command (kChangeStructureViewPrefsCmdBoss) that changes the data stored on this interface.

### Sample Code

```
SnpManipulateStructureView
```

## Related APIs

- IActionManager
- IStructureViewPrefs
- kChangeStructureViewPrefsCmdBoss
- kDocWorkspaceBoss

## Making a Selection in the Structure View

### Description

You can make a programmatic selection in the structure view; for example, to specify the target node in the logical structure where XML should be imported. You should do so *only if you are not concerned about trampling on the end-user's selection*, because there is no easy way for you to restore the end-user's selection after setting your own selection programmatically.

If there is a selection in the structure view, you can use the high-level suite interfaces to manipulate logical structure; for instance, to create, modify, and delete elements and attributes (IXMLStructureSuite).

## Solution

Use the *selection suite* named IXMLNodeSelectionSuite to select nodes in the structure view. An instance can be acquired from the selection manager (ISelectionManager).

The structure view must be visible to use the IXMLStructureSuite suite interface associated with an XML selection. The selection architecture is relatively complex but critical to programming InDesign; for details, see the “Selection” chapter of *Adobe InDesign CS4 Products Programming Guide*. The selection subsystem is a facade that tries to abstract away the model-specific details of different selection formats, to let client code deal with selections at a more abstract level.

Follow these steps:

1. Make sure the structure-view window is visible; if required, open it. See “[Changing the Visibility of the Structure View](#)” on page 227.
2. Acquire a reference to the panel in the structure view by widget ID (kXMLPanelWidgetID), defined in the header file XMediaUIID.h.
3. Obtain an ISelectionManager interface and from it IXMLNodeSelectionSuite, and use this to make the selection. You need to pass a vector of XMLReference objects, meaning you need to have a reference to each object you want to select.

## Sample Code

SnpManipulateStructureView

### Related API

- ISelectionManager
- IXMLNodeSelectionSuite
- kSelectionInterfaceAlwaysActiveBoss
- XMLReference

---

## XML Import

### Changing XML Import Options on a Document to Import

Suppose you are importing XML and you want to import XML into the selected element. For instance, you set a selection using the method described in “[Making a Selection in the Structure View](#)” on page 228. You have the choice of changing the option persisted with the document or setting the option to import into the selected element for one specific import.

## Solution

The preference you want is stored in IXMLImportOptions. To set up the option for a one-time import, you parameterize an instance of kImportXMLDataBoss through its IXMLImportOptions interface. To change the option stored in the document workspace, follow these steps:

1. Acquire the document workspace (kDocWorkspaceBoss) for the document of interest. See “[Acquiring the Correct Workspace for Storing or Obtaining Tags and Related Objects](#)” on page 238.
2. Use the low-level command kChangeXMLImportOptionsCmdBoss to change the interface IXMLImportOptions on the document workspace (kDocWorkspaceBoss).

## Sample Code

- SnpXMLHelper::SetImportIntoSelected

## Related API

- IXMLImportOptions
- kChangeXMLImportOptionsCmdBoss
- kDocWorkspaceBoss

## Importing an XML File with no Selection in the Structure View

Suppose that you know the path to an XML data file to import, the parent element for the imported elements, and that there is no selection in the structure view. You can import an XML file in this situation.

## Solution

To import an XML file without a selection, use a low-level command. You can specify the XML element to parent the new elements or specify kInvalidXMLReference, in which case the root becomes the parent for the new elements. Follow these steps:

1. Create an instance of a kImportXMLDataBoss boss class.
2. Set up its IIImportXMLData interface to specify the “import destination,” meaning the parent element.
3. Set up its IXMLImportOptions interface; for instance, you might copy IXMLImportOptions from the document workspace (kDocWorkspaceBoss).
4. You can ignore the other interfaces, unless you are interested in other use cases, like “[Transforming Imported XML](#)” on page 259.
5. Create an instance of the low-level command kImportXMLFileCmdBoss and parameterize its IPMUnknownData to refer to the data-boss object created above. Process the command.

## Sample Code

SnpImportExportXML

## Related API

- IIImportXMLData
- IXMLImportOptions
- kImportXMLFileCmdBoss

## Importing an XML File into a Selected Element

If you have a selected XML element in the structure view, you can set up the import option to import into the selected node and use a high-level suite interface.

### Solution

1. The preference to import into a selected node is controlled by IXMLImportOptions. See [“Changing XML Import Options on a Document to Import” on page 229](#).
2. Use IXMLStructureSuite to perform the import, testing IsImportable.

### Sample Code

SnpImportExportXML

## Importing Repeating Elements into an XML Template

### Description

Suppose you have XML content that contains repeat elements; for example, a set of classified advertisements. Suppose you want to flow all the ads into one tagged story, creating new elements within the story for each occurrence of the classified ad. You can do this by turning on the feature to import repeating elements. Since this feature is on by default, unless you do not want it on sometimes and need to turn it off and back on, or the user turns the feature off, you normally may not need to do anything.

### Solution

This is almost the same as importing XML normally, but you must enable the service that controls import of repeating elements if it is not enabled. The service is an instance of an import matchmaker service (kXMLRepeatTextElementsMatchMakerServiceBoss). For the service to run during import, the IXMLImportPreferences preference needs to be set up correctly.

1. Acquire the document workspace (kDocWorkspaceBoss) for the document of interest. See [“Acquiring the Correct Workspace for Storing or Obtaining Tags and Related Objects” on page 238](#). Obtain the IXMLImportOptionsPool interface from the document workspace.
2. Look up the import matchmaker service (kXMLRepeatTextElementsMatchMakerServiceBoss) in the service registry (IK2ServiceRegistry).

3. Set up its service-specific preference (IXMLImportPreferences) to turn on the preference to use the service. To see how XML import preferences (IXMLImportPreferences) are changed, see the XDocBookWorkflow sample.
4. Import XML as described elsewhere; see “[Importing an XML File with no Selection in the Structure View](#)” on page 230.

### Sample Code

- XDocBkFacade
- XDocBookWorkflow: XDocBkChangeServiceXMLImportPrefsCmd

### Related APIs

- IXMLImportOptionsPool
- IXMLImportPreferences
- IK2ServiceRegistry
- kDocWorkspaceBoss
- kXMLRepeatTextElementsMatchMakerServiceBoss

## Importing into an XML Template and Deleting Unmatched (Template) Elements

Suppose you have an XML template with optional elements (e.g., <copyright>). If these optional elements are not in the input, you can delete them from the XML template, which has placeholders for them, during the import process.

### Solution

This is almost the same as importing an XML file normally (as described in “[Importing an XML File with no Selection in the Structure View](#)” on page 230). The main difference is that you must set up service-specific preferences (IXMLImportPreferences), as the feature is not enabled by default. Follow these steps:

1. Acquire the document workspace (kDocWorkspace) from the document (kDocBoss) of interest, corresponding to your XML template document.
2. Look up the required import matchmaker service (kXMLImportMatchMakerSignalService) by ClassID (kXMLThrowAwayUnmatchedRightMatchMakerServiceBoss) in the service registry (IK2ServiceRegistry). This is the service that supports deleting unmatched existing elements. “Right” elements correspond to those in the XML template document; “left” elements, those in the incoming XML. The service object obtained should support the IXMLImportMatchmaker interface.

3. Change the service-specific preference (IXMLImportPreferences); the zero-th (boolean) preference controls turning the service on or off. To see how XML import preferences (IXMLImportPreferences) are changed, see the XDocBookWorkflow sample.
4. Do the XML import as usual; see “[Importing an XML File with no Selection in the Structure View](#)” on page 230.

### Sample Code

- XDocBkChangeServiceXMLImportPrefsCmd
- XDocBkFacade
- XDocBookWorkflow

### Related APIs

- IK2ServiceRegistry
- kDocWorkspaceBoss
- IXMLImportMatchMaker
- IXMLImportOptionsPool
- IXMLImportPreferences
- kXMLThrowAwayUnmatchedRightMatchMakerServiceBoss

## Importing into an XML Template and Deleting Unmatched Incoming Elements

Suppose you created an XML template and have XML-based data to import, with tagged placeholders for elements in the incoming XML you want to include in your document. There are optional elements in the incoming XML, which you do not want to include in your InDesign document once imported; for instance, an element <media-metadata>. You can delete incoming elements that do not have a match in the XML template.

### Solution

This is almost the same as importing an XML file normally (as described in “[Importing an XML File with no Selection in the Structure View](#)” on page 230). The main difference is that you must set up service-specific preferences (IXMLImportPreferences), as the feature is not enabled by default. Follow these steps:

1. Acquire the document workspace (kDocWorkspace) from the document (kDocBoss) of interest, corresponding to your XML template document.
2. Look up the required import matchmaker service (kXMLImportMatchMakerSignalService) by ClassID (kXMLThrowAwayUnmatchedLeftMatchMakerServiceBoss) in the service registry (IK2ServiceRegistry). This is the service that supports deleting unmatched incoming XML elements. “Right” elements correspond to those in the XML template document; “left” elements, those in the incoming XML. The service object obtained should support the IXMLImportMatchmaker interface.

3. Set the service-specific preferences (IXMLImportPreferences); the zero-th (boolean) preference controls turning the service on or off. To see how XML import preferences (IXMLImportPreferences) are changed, see the XDocBookWorkflow sample.
4. Do the XML import as usual; see “[Importing an XML File with no Selection in the Structure View](#)” on page 230.

### Sample Code

- XDocBkFacade
- XDocBookWorkflow: XDocBkChangeServiceXMLImportPrefsCmd

### Related APIs

- IK2ServiceRegistry
- IXMLImportOptionsPool
- IXMLImportPreferences
- kDocWorkspaceBoss
- kXMLThrowAwayUnmatchedLeftMatchMakerServiceBoss

## Importing a CALS Table as an InDesign Table

Suppose you have XML data that includes tables specified in CALS table format. You can import these tables into InDesign and manipulate them like InDesign tables.

### Solution

This is almost the same as importing an XML file normally (as described in “[Importing an XML File with no Selection in the Structure View](#)” on page 230). The main difference is that you must set up service-specific preferences (IXMLImportPreferences). Follow these steps:

1. Acquire the document workspace (kDocWorkspace) from the document (kDocBoss) of interest, corresponding to your XML template document.
2. Look up the required import matchmaker service (kXMLImportMatchMakerSignalService) by ClassID (kXMLTableMatchMakerServiceBoss) in the service registry (IK2ServiceRegistry). The service object obtained should support the IXMLImportMatchmaker interface.
3. Query and set the service-specific preferences (IXMLImportPreferences), using the IID\_IXMLIMPORTCALSPREFERENCES identifier. The zero-th (boolean) preference controls turning the service on or off. To see how XML import preferences (IXMLImportPreferences) are changed, see the XDocBookWorkflow sample. This service also supports deleting unmatched incoming XML elements (“left”) and/or existing elements (“Right”) for table cells.
4. Do the XML import as usual; see “[Importing an XML File with no Selection in the Structure View](#)” on page 230.

## Sample Code

- XDocBkFacade
- XDocBookWorkflow: XDocBkChangeServiceXMLImportPrefsCmd

## Related APIs

- IK2ServiceRegistry
- IXMLImportOptionsPool
- IXMLImportPreferences
- kDocWorkspaceBoss
- kXMLThrowAwayUnmatchedLeftMatchMakerServiceBoss

## Taking Control when the DOM is Serialized into the Document

Suppose you have custom content defined in an XML vocabulary embedded in XML that is being imported. You can take control when the DOM is serialized into the document.

### Solution

Implement a SAX DOM serializer handler (ISAXDOMSerializerHandler).

For instance, InDesign supports XML round-tripping of untagged tables and Ruby (annotations intended for Japanese and other ideographic writing systems) through this mechanism.

## Sample Code

- XDocBookWorkflow: XDocBkCALSContentHandler
- XMLDataUpdater: DataUpdaterDOMSerializerHandler

## Related API

ISAXDOMSerializerHandler

## Reading a Configuration from an XML File

Suppose you have configuration data expressed in XML, and you want to read this data but are not interested in importing the XML directly into a document. You can read XML data but use the application's XML parser.

### Solution

Implement a custom SAX content handler (ISAXContentHandler), which lets you take control when the XML parser encounters elements you registered to handle.

## Sample Code

XMLCatalogHandler

## Related API

ISAXContentHandler

---

# XML Export

## Controlling XML Export Options

You can vary XML export options, like whether to export from the selected element or vary the encoding of the XML exported from the default UTF-8.

### Solution

1. Export options are stored in the IXMLExportOptions interface of the workspace. Acquire the correct workspace, namely the document workspace (kDocWorkspaceBoss) for the document of interest. See [“Acquiring the Correct Workspace for Storing or Obtaining Tags and Related Objects” on page 238](#).
2. Use the low-level command kChangeXMLExportOptionsCmdBoss to change the data stored on the workspace interface.

### Sample Code

```
SnpXMLHelper::SetExportFromSelected
```

### Related APIs

- IXMLExportOptions
- kChangeXMLExportOptionsCmdBoss
- kDocWorkspaceBoss

## Exporting XML Data from a Selection in the Structure View

If you have one or more nodes selected in the structure view, you can export this as an XML data file.

### Solution

1. To perform the export, use IXMLStructureSuite, which depends on a selection of nodes in the structure view. Obtain this interface from the selection manager (ISelectionManager).
2. Verify the preconditions, and call the required method on IXMLStructureSuite.

### Sample Code

```
SnpManipulateXMLSelection::ExportFromSelection
```

## Related API

IXMLStructureSuite

## Exporting XML Data without a Selection in the Structure View

Suppose you want to export XML from the logical structure of your InDesign document. If you have a selection in the structure view, use a high-level suite interface, as described in “[Exporting XML Data from a Selection in the Structure View](#)” on page 236. Without a selection, you can use the lower-level export provider mechanism.

### Solution

XML export uses the standard export provider architecture, so you can use the service registry (IK2ServiceRegistry), as follows:

1. Obtain a reference to the XML export service from the service registry (IK2ServiceRegistry). You need the ServiceID that identifies an export service (kExportProviderService) and a ClassID for the XML export service (kXMLExportProviderBoss).
2. Pass a reference to a file to which you want to export (use SDKFileSaveHelper), and use the methods on IExportProvider to export the data.

### Sample Code

SnpImportExportXML

### Related APIs

- IExportProvider
- IXMLExportOptions
- kDocWorkspaceBoss
- kWorkspaceBoss
- kXMLExportProviderBoss

## Exporting XML from a Table

### Description

You can export a tagged table as an XML data file.

### Solution

1. If the table is tagged, it can be exported as part of XML export. A table is represented by kTableModelBoss, which may be associated with an element (IIDXMLElement) via IXMLreferenceData interface, if it is a tagged table.
2. Locate the associated element via IXMLReferenceData interface on the table (kTableModelBoss).

3. Export from the associated element using an appropriate method. See `SnpImportExportXML::ExportElement`.

### Sample Code

- `SnpImportExportXML::ExportElement`
- `SnpImportExportXML::ExportTable`

### Related APIs

- `IIXMLElement`
- `IXMLReferenceData`
- `kTableModelBoss (ITableModel)`

## Altering XML Structure during Export

If you have custom XML content, you can control the format of the content element when it is exported to XML file.

### Solution

Use the XML Export handler extension pattern. Implement an XML export handler (`IXMLEXportHandler`) as the provider of `kXMLExportHandlerSignalService`. In the provider, you can specify your custom way to write out specific XML elements.

For example, in the XML data updater sample plug-in, each data field is an XML element; however, during export, you can group all fields of a record into one XML element, to provide a more readable format.

### Sample Code

`XMLDataUpdater: DataUpdaterExportHandler`.

### Related API

`IXMLExportHandler`

---

## Tags

### Acquiring the Correct Workspace for Storing or Obtaining Tags and Related Objects

When you are creating tags and related objects (like tag-style mappings), you must decide where to store them. If you are acquiring references to objects that already exist, you also need to know where to look for them.

## Solution

The choice is highly constrained for objects like tags (kXMLLoaderBoss) and related tag-style mappings (IXMLTagToStyleMap, IXMLStyleToTagMap); it will be a workspace (IWorkspace) of some kind.

Tags are in the session workspace (kWorkspaceBoss) or document workspace (kDocWorkspaceBoss). To establish default tags for new documents, create tags in the session workspace (kWorkspaceBoss). If you want the objects to be available only within a particular document, you create tags in the document workspace (kDocWorkspaceBoss) for the document of interest; see IDocument::GetDocWorkspace().

There are other kinds of information stored at the workspace level; see the API documentation for kWorkspaceBoss or kDocWorkspaceBoss, and examine the interfaces that contain “XML.” Tag-to-style maps, style-to-tag maps, and import/export options are among the other kinds of information stored in workspaces.

To change this information, you must identify the target workspace in which the change is to take place.

How to obtain a reference to the workspace of interest depends on whether you are writing client code (user interface code) or model (model manipulation) code:

1. If you are writing client code and have an IActiveContext interface pointer, use IActiveContext::GetContextWorkspace().
2. If you are writing model code, use IDocument::GetDocWorkspace() to acquire a reference to the kDocWorkspaceBoss for a given document (IDocument).

There are several methods on IXMLUtils that let you acquire XML-related interfaces on the workspaces, given a document database (IDataBase).

## Sample Code

- SnpManipulateXMLTags
- SnpXMLHelper

## Related APIs

- IActiveContext
- IDocument
- IWorkspace
- IXMLUtils

## Loading Tags

Loading a set of tags from an XML file means they can be used to mark up content items in the document. You also can load tags through importing a DTD, in which case InDesign creates tags when it finds element declarations in the DTD.

### Solution

The tag list (see the API documentation for IXMLTagList) for a document is in the document workspace (kDocWorkspaceBoss). You can change the contents of the tag list through IXMLTagCommands, as follows:

1. Use the IXMLTagCommands command facade to load the tag list from the file specified.
2. Choose the workspace to target. See “[Acquiring the Correct Workspace for Storing or Obtaining Tags and Related Objects](#)” on page 238.
3. Use SDKFileHelper to make presenting a file-open dialog more straightforward, if one is required.

Loading tags means changing the tag list (IXMLTagList) stored in a workspace. Which workspace to target depends on whether you just want to set up a default tag set for subsequent new documents or create a tag set for a given document. Note the following:

- Tags loaded into the session workspace (kWorkspaceBoss) become the default set for new documents.
- Tags loaded into the document workspace (kDocWorkspaceBoss) can be used to mark up content items and create elements in the document.

Under the hood, the low-level command kLoadTagListCmdBoss is processed whenever a tag-list is imported.

[Example 40](#) is a sample tag list.

#### **EXAMPLE 40 Sample Tag List**

```
<?xml version="1.0" encoding="UTF-16" standalone="yes"?>
<article colorindex="4">
<articleinfo colorindex="6"/>
... (other elements omitted)
<ulink colorindex="19"/>
</article>
```

### Sample Code

SnpManipulateXMLTags::LoadTags

## Related API

- IXMLTagCommands
- IXMLTagList
- kDocWorkspaceBoss
- kWorkspaceBoss

## Saving Tags

You can save the tag list from a document, to enable the tags to be used in other documents or as defaults for new documents.

### Solution

First, decide which tag list you want to save; that is, what workspace does it come from, and where to save it in the file system. Then follow these steps:

1. To save a tag list programmatically, use IXMLTagCommands::SaveTags().
2. Choose the workspace to target, which is most likely a document workspace (kDocWorkspaceBoss) from a document of interest. See “[Acquiring the Correct Workspace for Storing or Obtaining Tags and Related Objects](#)” on page 238.
3. Specify the target file to save the tag list to, which normally has an extension of “.xml.” Use SDKFileHelper to make presenting a file-save dialog to the end user more straightforward, if one is required.

The tag list is exported as an XML document, with elements specifying the name and color index for each tag. A fragment of a tag list is shown in [Example 40](#).

### Sample Code

- SnpManipulateXMLTags::SaveTags

### Related APIs

- IXMLTagCommands
- IXMLTagList
- kDocWorkspaceBoss
- kWorkspaceBoss
- SDKFileHelper

## Creating Tags

To tag document content (for example, with tags like “headline”), you need to create tag objects (kXMLTagBoss) in the document’s tag list.

### Solution

Tag objects (kXMLTagBoss) are managed by the IXMLTagList interface on kDocWorkspaceBoss or kWorkspaceBoss. Follow these steps:

1. Choose the workspace in which the tag is to be created. See [“Acquiring the Correct Workspace for Storing or Obtaining Tags and Related Objects” on page 238](#).
2. Use IXMLTagCommands::CreateTag() to create a tag object (kXMLTagBoss).

### Sample Code

```
SnpXMLHelper::AcquireTag
```

### Related APIs

- IXMLTag
- IXMLTagCommands
- IXMLTagList
- kDocWorkspaceBoss
- kWorkspaceBoss
- kXMLTagBoss

## Acquiring a Reference to a Tag

To create an XML element, you need a reference to a tag (kXMLTagBoss) that represents its name. Similarly, to apply a tag to content, like a story (kTextStoryBoss), graphic frame, or text range, you need a reference to a tag object.

Tags (kXMLTagBoss) are stored in the tag list (IXMLTagList) in a workspace (kDocWorkspaceBoss, kWorkspaceBoss). The tags specific to a document are held in its workspace (kDocWorkspaceBoss). The tag list is a collection of boss objects (kXMLTagBoss) that represent tags.

### Solution

1. Choose the workspace in which the tag is stored. See [“Acquiring the Correct Workspace for Storing or Obtaining Tags and Related Objects” on page 238](#).
2. IXMLTagList::GetTag() returns the UID of the tag object (kXMLTagBoss) with the specified name, which can be used to instantiate an IXMLTag interface.
3. If the named tag does not exist, use IXMLTagCommands (kUtilsBoss) to create a new one with the specified name.

## Sample Code

```
SnpXMLHelper::AcquireTag
```

## Related APIs

- IXMLTag
- IXMLTagCommands
- IXMLTagList
- kDocWorkspaceBoss
- kWorkspaceBoss
- kXMLTagBoss

## Finding a Tag's Color

Tags are represented by kXMLTagBoss. The IPersistUIDData interface on kXMLTagBoss refers to an instance of kUIColorDataBoss, which stores the tag color.

## Solution

1. Acquire a reference to the tag whose color you want to find of; see “[Acquiring a Reference to a Tag](#)” on page 242
2. To determine the color of the tag as it appears in the user interface, navigate from the kXMLTagBoss object to the associated kUIColorDataBoss object that stores its color.

## Sample Code

```
SnpXMLHelper::AsString(const UIDRef& tagUIDRef)
```

## Related APIs

- IColorData
- IPersistUIDData
- IXMLTag
- IXMLTagCommands
- IUIColorUtils
- kUIColorDataBoss
- kXMLTagBoss

## Changing Tag Properties

You can change a tag's name and/or color. If you change the name, any tagged content items that used the old tag are tagged with the new tag.

### Solution

1. Acquire a reference to the tag you want to change the properties; see “[Acquiring a Reference to a Tag](#)” on page 242.
2. To change its properties, use the IXMLTagCommands command facade (kUtilsBoss). To change its color, acquire the UID of a kUIColorDataBoss object. One way to do this is through IUIColorUtils::GetUIColor(). To create a completely new UI color (kUIColorDataBoss), use kNewUIColorCmdBoss.

### Sample Code

```
SnpXMLHelper::ChangeTagName
```

### Related APIs

- IUIColorUtils
- kUIColorDataBoss
- kNewUIColorCmd
- kXMLTagBoss
- IXMLTagCommands

## Creating a Mapping from Tag to Style

You can specify the appearance of XML-based content once it is imported into InDesign.

### Solution

This mapping is stored in the IXMLTagToStyleMap interface on a workspace (kDocWorkspaceBoss/ kWorkspaceBoss). Follow these steps:

1. Choose the workspace containing the tag-to-style map to which you want to add. See “[Acquiring the Correct Workspace for Storing or Obtaining Tags and Related Objects](#)” on page 238.
2. Use IXMLElementCommands::MapTagToStyle() to set up an association between a tag and a paragraph or character style.

### Sample Code

```
SnpManipulateXMLTags
```

### Related API

IXMLElementCommands

## Creating a Mapping from Style to Tag

Suppose that have a document with systematically applied styles (character/paragraph styles); you can create a logical structure that takes advantage of the systematic way the styles are used.

### Solution

The first part of this process is creating a set of associations between styles that exist in the document and tags that will be used to mark up content in each style. This mapping (IXMLStyleToTagMap) is held in a workspace (kDocWorkspaceBoss/ kWorkspaceBoss). Follow these steps:

1. Choose the workspace containing the style-to-tag map to which you want to add. See [“Acquiring the Correct Workspace for Storing or Obtaining Tags and Related Objects” on page 238](#).
2. Acquire a reference to the style (kStyleBoss) you want to associate with a tag. These are held in the style-name tables (IStyleNameTable) on a workspace, with different PMIDs for paragraph styles and character styles.
3. Acquire a reference to the tag you want to associate with the given style, and use IXMLMappingCommands::MapStyleToTag().

### Sample Code

SnpManipulateXMLTags

### Related API

IXMLMappingCommands

## Applying Tag-to-Style Mapping to Style Incoming XML

You can use styles in a document to style incoming XML. Assume you already set up the associations between tags and styles in the XML template (as described in [“Creating a Mapping from Tag to Style” on page 244](#)). What you need to do is apply the mapping that is already set up within the document.

### Solution

Even if you added to the mapping new associations between tags and styles, the document would not appear any different until you *apply* the mapping to the document. To do this, you must process a low-level command, as follows:

1. Acquire the document workspace (kDocWorkspaceBoss) for the document of interest. See [“Acquiring the Correct Workspace for Storing or Obtaining Tags and Related Objects” on page 238](#).
2. Use kXMLApplyTagToStyleMappingCmdBoss, which applies the tag-to-style map stored in the IXMLElementToStyleMap interface of the document workspace (kDocWorkspaceBoss).

## Sample Code

SnpManipulateXMLTags

## Related APIs

- IXMLTagToStyleMap
- kDocWorkspaceBoss
- kXMLApplyTagToStyleMappingCmdBoss

## Applying Style-to-Tag Mapping to Structure a Document

Assume you created an associative mapping from styles to tags, because you want to apply structure to a document with systematically applied styles; see “[Creating a Mapping from Style to Tag](#)” on page 245. Having created the mapping within the document workspace, you need to apply the mapping, for the structure to be created in the document.

## Solution

1. Acquire the document workspace (kDocWorkspaceBoss) for the document of interest. See “[Acquiring the Correct Workspace for Storing or Obtaining Tags and Related Objects](#)” on page 238.
2. Identify the tag (kXMLTagBoss) you want to be applied.
3. Use kXMLCreateStyleToTagElementsCmdBoss, which styles the text in the document with the rules specified in the style-to-tag map stored in the IStyleToTagMap interface of the document workspace (kDocWorkspaceBoss).
4. Untagged stories after processing the command are tagged with the tag specified on the command data interface (IXMLCreateStyleToTagElementsCmdData). Text ranges in the styles identified in the mapping from styles-to-tags are tagged with the corresponding tags.

Pay attention to naming in this area, as there is a low-level command to process, kXMLCreateStyleToTagElementsCmdBoss, which has a slightly different name than the low-level command in “[Applying Tag-to-Style Mapping to Style Incoming XML](#)” on page 245. The name “kXMLCreateStyleToTagElementsCmdBoss” is logically correct, since when applying a style-to-tag mapping, you are creating new XML elements in the logical structure. The operation of applying a tag-to-style map does not *create* new styles, it only applies existing ones with the specified names.

## Sample Code

SnpManipulateXMLTags

## Related APIs

- IXMLCreateStyleToTagElementsCmdData
- IXMLStyleToTagMap
- IXMLElement
- kDocWorkspaceBoss
- kXMLCreateStyleToTagElementsCmdBoss
- kXMLElementBoss

---

# Elements and Content

## Acquiring a Reference to the Root Element

You can iterate through the logical structure from its root or start validating the logical structure from the root. For these use cases, you need a reference to the root element in the logical structure.

The root element is represented by a `kTextXMLElementBoss` class, manipulated through its `IIDXMLElement` interface.

### Solution

1. Get a reference to the root object through a method on `IXMLUtils`, given a reference to the document (`IDocument`, on `kDocBoss`) or its database (`IDatabase`). See [Example 41](#).
2. The interface pointer `IIDXMLElement` returns references to an instance of `kTextXMLElementBoss`, corresponding to the root element visible when the structure view is shown.

#### **EXAMPLE 41 Root Element**

```
// If you have a reference to a document database (IDatabase), you can write:  
// InterfacePtr<IIDXMLElement> rootXMLElement(  
//     Utils<IXMLUtils>() ->QueryRootElement(dataBase));  
// Alternatively, pass a reference to a document (IDocument).  
// See API docs for details.
```

### Sample Code

`SnpManipulateXMLElements`

## Related APIs

- `IIDXMLElement`
- `IXMLUtils`
- `kTextXMLElementBoss`

## Acquiring a Reference to the Document Element

The document element is the parent of the root element and peers of the root element, such as the DTD element and comments and processing instructions at the document level. To iterate through these top-level elements, you need a reference to the document element. You also need a reference to the document element when dealing with XML validation.

The document element is represented by the kXMLLoaderBoss class.

### Solution

Use a method on IXMLUtils to acquire a reference to the instance of kXMLLoaderBoss that represents the XML element for a given InDesign document.

### Sample Code

```
SnpManipulateXMLElements
```

### Related APIs

- IIDXMLElement
- IXMLUtils
- kXMLLoaderBoss

## Iterating through the Logical Structure

You can traverse the tree of XML elements in a document; for example, to find elements that match a particular specification and then take some action.

### Solution

To iterate through the logical structure during import, implement an extension pattern; in the “XML Fundamentals” chapter of *Adobe InDesign CS4 Programming Guide*, see the section on “Post-Import Responder.” To iterate through the logical structure once the document is fully loaded, start from the root, iterate through its children, and descend the tree recursively. Follow these steps:

1. Start by acquiring a reference to the root element, which gives you an IIDXMLElement interface pointer as a starting point.
2. Traverse the tree using the methods on IIDXMLElement like GetChildCount() and GetNthChild. For each XMLReference, use XMLReference::Instantiate to acquire an interface IIDXMLElement to continue the iteration.
3. Recursively descend the element tree using these methods. This lets you iterate over the elements (IIDXMLElement).
4. If the parent element is a story (kTextStoryBoss) and you are interested in the text ranges associated with children, use XMLContentIterator (constructed via a reference to an IIDM-LElement) to quickly find out the range of text associated with each XML element.

## Sample Code

SnpManipulateXMLElements

## Related APIs

- IIDXMLElement
- kXMLCommentBoss
- kTextXMLElementBoss
- kXMLPIBoss
- XMLContentIterator
- XMLReference

## Determining what can be Tagged

If you have a reference to a page item or other object, you can determine whether it can be tagged.

## Solution

The IXMLUtils utility interface has a method, IsTaggablePageItem, that allows client code to determine whether a given boss object can be tagged. There also is a method on IXMLUtils, GetActualContent, which lets client code acquire a reference (UIDRef) to the underlying object supporting the tagging operation (see IXMLReferenceData).

## Sample Code

SnpInspectSelectionXMLProperties::InspectLayoutObject

## Related APIs

- IXMLReferenceData
- IXMLUtils

## Finding Text associated with Tagged Text Ranges

If you have a tagged story, you can find out what text is tagged and by what element within each story.

## Solution

Use XMLContentIterator to traverse the child elements of a given element. This is particularly useful for elements with text content; e.g. tag text ranges.

## Sample Code

SnpInspectSelectionXMLProperties::InspectText

## Related API

XMLContentIterator

## Creating New Elements with Parent Selected

If you have a selection, or you know how to create a selection in the structure view programmatically, you can create new elements in the logical structure easily. If you have no selection or it is inconvenient or not possible to create one, use the method described in “[Creating New Elements with No Selection](#)” on page 250.

One way to add and remove elements from the logical structure is to use the IXMLNodeSelectionSuite suite interface to program a selection in the structure view, then use IXMLStructureSuite, which acts on a selection in the structure view.

Under the hood, when an element is created, the low-level command kXMLCreateElementCmdBoss is processed. When an element is deleted, the low-level command kXMLDeleteElementCmdBoss is processed.

You can create, modify, and delete attributes with methods on IXMLAttributeCommands.

## Solution

1. Make a selection in the structure view, if one does not exist already.
2. Obtain the tag (kXMLTagBoss) you need from the tag list (IXMLTagList) or add a tag for the element you want if it does not exist already.
3. Obtain the IXMLStructureSuite suite interface and use it to add an element based on the required tag.

## Related Documentation

[“Making a Selection in the Structure View” on page 228](#)

## Sample Code

SnpManipulateXMLSelection::CreateElementsInSelection

## Related API

IXMLStructureSuite

## Creating New Elements with No Selection

### Description

You can create new elements in the logical structure, with a known parent and no selection in any view. If you have a selection in the structure view that indicates the new parent, use the method described in “[Creating New Elements with Parent Selected](#)” on page 250.

## Solution

The IXMLElementCommands command facade provides methods (CreateElement overloads) to create a new element in the logical structure not associated with a content item. Follow these steps:

1. You need to know the XMLReference of the parent. For instance, use the XMLReference of the root element to create an element as a child of the root.
2. You need a reference to the tag (kXMLTagBoss) that will be associated with the element.
3. Use the IXMLElementCommands facade to create an instance of a new element (IIDXMLElement).

## Sample Code

- SnpManipulateXMLElements
- SnpManipulateXMLTags

## Related APIs

- IIDXMLElement
- IXMLTagList
- kTextXMLElementBoss
- kXMLTagBoss

## Modifying Attributes in a Selected Element

If you have a selected element in the structure view, you can modify its attributes; for example, create a new attribute, change an existing attribute, or delete an attribute.

## Solution

The IXMLStructureSuite suite interface, which can be used in the case of a selection in the structure view, provides methods to make this straightforward. Follow these steps:

1. Obtain an IXMLStructureSuite interface from the selection manager (ISelectionManager).
2. Verify CanAddAttribute/ CanAddSpecificAttribute and call AddAttribute.

## Sample Code

SnpManipulateXMLSelection

## Related APIs

- IXMLStructureSuite
- kUtilsBoss

## Modifying Attributes without a Selection

Assume that there is no selection of any kind. You can create, modify, or delete attributes of an element in the logical structure.

### Solution

There is a command facade (IXMLAttributeCommands) on the kUtilsBoss boss class, which provides methods to make this straightforward. Follow these steps:

1. Acquire an IXMLAttributeCommands interface from kUtilsBoss.
2. Use the appropriate facade method to create, delete, or update an attribute.

### Related API

IXMLAttributeCommands

## Tagging Graphics

You can tag a graphic frame as a placeholder for an image you will import later or already imported.

### Solution

The procedure depends on whether you have a selection. If you have no selection of any kind, follow these steps:

1. Acquire a reference to the tag that you want to use; see “[Acquiring a Reference to a Tag](#)” on page 242.
2. Acquire a reference to the graphic frame you want to tag; for instance, an object that exposes the IGraphicFrameData interface. The object you are trying to tag needs to support IXMLElement::IsTaggablePageItem().
3. Use IXMLElementCommands to tag the graphic frame; look for the overloaded CreateElement methods with the “UID contentItem” parameter in their method signature. Tagging an object in the layout creates an XML element; this is why you need the CreateElement methods.

If you have a selection, use the IXMLTagSuite interface. This suite is available in many views; for instance, if the graphic frame to be tagged is selected in the layout view, use IXMLTagSuite.

### Sample Code

- SnpManipulateXMLElements
- SnpManipulateXMLSelection

### Related APIs

- IXMLElementCommands
- IXMLTagSuite

## Tagging a Story

### Description

You can tag a story as a placeholder for stories in incoming XML, or tag an existing story.

### Solution

The solution depends on whether you have an existing selection. If there is no selection, follow these steps:

1. Acquire a reference to the story (kTextStoryBoss) of interest; for instance, through its ITextModel interface.
2. Acquire a reference to the tag (kXMLTagBoss) you want to use. See “[Acquiring a Reference to a Tag](#)” on page 242.
3. Use IXMLElementCommands facade. There is an overloaded CreateElement that takes the UIDRef of the tag and the story.

If there is an existing selection, follow these steps:

1. Acquire an IXMLTagSuite interface pointer.
2. Acquire a reference to the tag (kXMLTagBoss) you want to use.
3. Use the appropriate method on IXMLTagSuite (SetTag) to tag the story, verifying the pre-conditions (CanTag) before executing it.

### Sample Code

- SnpManipulateXMLElements
- SnpManipulateXMLSelection

### Related APIs

- IXMLElementCommands
- IXMLTagSuite
- kXMLTagBoss

## Tagging a Text Range

You can tag a range of text, either text within a paragraph or a paragraph itself.

### Solution

1. Tag the story in which the text range is located with the desired story-level tag, if it is not already tagged. Otherwise, the default Story tag is used.
2. Use the IXMLElementCommands command facade (kUtilsBoss).

## Sample Code

- SnpManipulateXMLElements
- SnpManipulateXMLSelection
- XMLMarkupInjector

## Related API

- IXMLElementCommands

## Tagging a Table

If you have an InDesign table, you can turn it into a structured table; for example, so it can be round-tripped through XML.

## Solution

1. Acquire a reference to the table model (kTableModelBoss) you want to tag; for instance, through its ITableModel interface. In the CHM documentation, search for the string literal “virtual ITableModel” (with quotes).
2. Use IXMLElementCommands::CreateTableElement to create an element for the table, and specify the names of tags to use for the table and cells within the table.

## Sample Code

SnpManipulateXMLElements::TagTable

## Related APIs

- ITableModel
- kTableModelBoss
- IXMLElementCommands

## Adding Comments and Processing Instructions

### Description

You can add comments and/or processing instructions, regardless of whether there is a selection.

## Solution

- If there is a selection, use IXMLTagSuite to add a comment and/or processing instructions, based on the selected text.
- If there is no selection, you must process low-level commands yourself. To create a comment (kXMLCommentBoss), process an instance of the kXMLCreateCommentCmdBoss command boss class. To create a processing instruction (kXMLPIBoss), process an instance of the kXMLCreatePICmdBoss command boss class.

## Sample Code

- SnpManipulateXMLElements
- SnpManipulateXMLSelection

## Related APIs

- IXMLTagSuite
- kXMLCommentBoss
- kXMLCreateCommentCmdBoss
- kXMLCreatePICmdBoss
- kXMLPIBoss

# Modifying and Deleting Comments and Processing Instructions

## Solution

Again the solution depends on whether there is a selection and, if there is a selection, what type of selection it is. Modifying comments and processing instructions without a selection involves processing low-level commands.

When there is a selection, follow these steps:

- To modify a comment or processing instruction, use IXMLTagSuite.
- If there is a selection in the structure view, you also can delete a comment or processing instruction, using the IXMLStructureSuite suite interface.

If there is no selection, follow these steps:

- To change an XML comment, use low-level commands like kXMLSetCommentCmdBoss. To change a processing instruction, use the low-level command kXMLPISetCmdBoss. There are no wrapper methods for these.
- Deleting processing instructions and comments is like deleting other XML elements, since they all aggregate IIDXMLElement, from which you can get an XMLReference (see IIDXMLElement::GetXMLReference). To delete comments and processing instructions, use the IXMLElementCommands command facade.

## Sample Code

SnpManipulateXMLElements

## Related APIs

- IIDXMLElement
- IXMLElementCommands
- IXMLStructureSuite
- IXMLTagSuite
- kXMLCommentBoss

- kXMLPIBoss
- kXMLSetCommentCmdBoss
- kXMLSetPICmdBoss

## Getting Notified of XML-related Changes in a Document

You can be notified when particular XML-related changes occur, such as an element being deleted.

When the logical structure is changed (e.g., elements are added or deleted, or associations are added to the tag-style mappings), notifications are sent out. If you know how the change is identified, you can attach your own observer to the correct subject and listen for these notifications.

Changes are notified to observers of changes to the backing-store subject. For instance, the structure-view tree widget has an observer on the backing store subject, to enable it to synchronize its state with the model's state.

### Solution

1. Acquire a reference to the backing store, a non-user-accessible story (kTextStoryBoss). See [Example 42](#).
2. Attach to its ISubject interface as an observer along the protocol of interest; for instance, IID\_IIDXMLEMENT.

#### **EXAMPLE 42** Code Acquiring the Backing Store Subject

```
// The XML document element lives in the backing store
InterfacePtr<IIDXMLElement> docElement(Utils<IXMLUtils>() ->QueryDocElement(db));
UIDRef baseUIDRef = docElement->GetXMLReference().GetUIDRef();
// baseUIDRef now refers to the backing store
InterfacePtr<ISubject> backingSubject(baseUIDRef, UseDefaultIID());
// This is the subject you need to attach to for notification on XML changes
```

### Related APIs

- ISubject
- kTextStoryBoss
- XMLReference

## Associating a DTD with a Document

### Description

You can associate a DTD with the logical structure of a document, to allow you to perform validation and other functions, like discovering what elements are valid to insert at a given node in the logical structure.

### Solution

Process the low-level command `kXMLLoaderDTDCmdBoss`. This creates an instance of the boss class `kXMLDTD Boss` in the document's backing store.

### Sample Code

```
SnpManipulateXMLElements
```

### Related API

```
kXMLLoaderDTDCmdBoss
```

## Validating Logical Structure against a DTD

If you associated a DTD with the logical structure of a document, you can determine the validity of the logical structure, given the grammar represented by the DTD.

### Solution

There are several ways to validate the logical structure of a document against a DTD:

- Use the action manager (`IActionManager`) to perform the equivalent action to when the corresponding structure menu item is executed (`kStructureValidateRootActionID` to validate from the root, for instance). If you have a selection in the structure view, you also can execute `kStructureValidateElementActionID`.
- Use `IXMLUtils::ValidateXML` and report the validation errors yourself.
- When there is a selection, use the `IXMLStructureSuite` suite interface and report the errors yourself. When the validation has run, `IXMLValidator` (on `kXMLDocumentBoss`) stores a collection of instances of `XMLDTDValidationError` containing information about the errors.

The ActionID for actions to validate the logical structure from the root can be found in the header file `source/public/includes/XMediaUIID.h`. Note that there is no public API to give you easy access to change the contents of the validation window in the InDesign user interface (see “XML validation errors window” in the Programming Guide chapter titled “XML fundamentals”) and you have to figure out how to display these errors yourself if you take this route.

## Sample Code

- SnpManipulateStructureView
- SnpManipulateXMLElements

## Related APIs

- IActionManager, IXMLOutils
- IXMLValidator, IIDXMLElement, kXMLDocumentBoss

# Finding Valid Elements to Insert, given a DTD

## Description

Suppose you imported a DTD into an InDesign document, as in “[Associating a DTD with a Document](#)” on page 257. You can constrain the elements that can be added by an end user at a given node in the logical structure.

## Solution

1. Use IIDXMLElement. On each XML element in the logical structure, this provides methods enabling you to find the list of elements that are valid to insert as a child or sibling of the element or are valid replacements for the element (given the DTD).
2. Pass the objects representing valid elements to insert directly to the command facade to create new elements (IXMLElementCommands).

## Related APIs

- IIDXMLElement
- IXMLElementCommands
- XMLDTDInsertElement
- XMLDTDInsertElementList

---

# XSLT

## Transforming Imported XML

You can transform incoming XML with an XSL stylesheet. Specifically, you can translate one XML vocabulary in which the source XML is expressed into another XML vocabulary that your XML template understands.

### Solution

In addition to implementing an XML transformer, you need to invoke the built-in XSLT engine within InDesign. Follow these steps:

1. If you implement an XML transformer that manipulates the DOM, use IXSLServices::Transform.
2. When implementing an XML transformer to transform incoming XML with XSLT, you can pass a reference to the stylesheet (IStylesheetData) to the import XML command through its data object (instance of kImportXMLDataBoss). The kImportXMLDataBoss boss class exposes the IStylesheetData interface.
3. From the context of the XML transformer, you have a reference to the importer governor (kXMLLoaderBoss). The IPMUknownData interface on this lets you acquire a reference to the data object (kImportXMLDataBoss). From the data object, you can recover the stylesheet (IStylesheetData) and parameters passed in from the client code processing the import, via kImportXMLFileCmdBoss.
4. Alternatively, if the inbound XML uses the “xml-stylesheet” processing instruction, you can parse this processing instruction in your XML transformer implementation, to discover what XSL stylesheet to use.

### Sample Code

- XDocBkXMLTransformer
- XDocBookWorkflow sample

### Related APIs

- IIImportXMLData
- IStylesheetData
- IXSLServices



# Versioning Persistent Data

---

## Getting Started

To learn how versioning persistent data works:

- Work through the activities in “[Exploring Versioning Persistent Data with SnippetRunner](#)” on page 261 to familiarize yourself with available sample code and documentation.
- Read the “Persistent Data and Data Conversion” chapter in *Adobe InDesign CS4 Programming Guide*.

For help with your specific programming problem, see the sections below for a use case that matches your need.

### Exploring Versioning Persistent Data with SnippetRunner

#### Description

SnippetRunner is an SDK-supplied plug-in that lets you run code snippets, which can help you explore your use case.

#### Recommendations

1. See the related sample code listed below, to see whether SDK code snippets exist to help you explore versioning persistent data.
2. If so, run Adobe InDesign® with the SnippetRunner plug-in loaded.
3. See `<sdk>/docs/references/index.chm` (or HTML format), and select the “Snippets” tab for more information about a snippet or instruction on using SnippetRunner itself.>
4. Browse the sample code of the snippets you have been running.
5. For additional help, see “Related API” below.

#### Related Sample Code

- For help identifying the string value of IDs when you are investigating versioning, see `<SDK>/source/sdksamples/codesnippets/SnpXMLResolutionHelper.cpp`.

#### Related API

- `IConversionProvider`, `IContentIteratorRegister`

### Finding Resources related to Versioning Persistent Data on the SDK

#### Description

Suppose you are looking for assets on the SDK that will help you program with versioning persistent data.

#### Recommendations

See <SDK>/docs/references/index.chm (or HTML format). SDK sample plug-in descriptions are available from the “Samples” tab. API documentation is available from the “API Classes” tab. Documentation for boss classes and their aggregated interfaces is available from the “Boss Classes” tab.

---

## Working with Data Conversion Strategies

### Prerequisite: Adding a Conversion Provider

To use the schema-based conversion mechanism, tell the conversion manager that your plug-in has a conversion provider. For an example, see <SDK>/source/sdksamples/persistentlist/PstLst.fr.

Implementations are supplied by the SDK. Remember to include ShuksanID.h in your .fr file.

### Changing the Format of Data Stored by a Persistent Implementation

To determine how to change the format of your plug-in's persistent data, follow these steps:

1. Note the current format number, and identify how your data is rearranged in each of your ReadWrite() methods. This helps you track changes.
2. Determine what you need to modify:
  - Does the order of any of the data types for the data change, or are you removing some data within an implementation? If so, write a schema for the SchemaList resource. (For details on these resources, see the “Persistent Data and Data Conversion” chapter in *Adobe InDesign CS4 Programming Guide*.) Then modify the ReadWrite() methods as needed.
  - Are you changing any boss class or implementation IDs? If so, add a set of directives in a DirectiveList resource. See “[Changing the ID of a Boss Class or Implementation](#)” on page 263.

## Adding and Removing Boss Classes or Implementations

No conversion is required to add boss classes or implementations. To remove a boss class or an implementation at a specific format number, use the RemoveClass, RemoveImplementation, or RemoveAllImplementation directives.

[Example 43](#) shows a resource that holds a list of individual directives that define the history of the plug-in's bosses and implementations:

**EXAMPLE 43 DirectiveList Resource for Removing Boss Classes or Implementations**

```
resource DirectiveList (kMyDirectiveRsrcID)
{
{
{RemoveClass{kSomeBoss, {1, 2}} },
{RemoveImplementation{kMyBoss, kMyDataImpl, {2, 1}} },
{RemoveAllImplementation {kMyDeadImpl, {4, 2}} },
}
};
```

You can put as many individual directives into a single DirectiveList resource as you like. Line by line, the preceding list of directives tells the conversion manager the following:

- Class kSomeBoss was completely removed from the document at format number 1.2.
- Implementation kMyDataImpl was removed from class kMyBoss at format number 2.1.
- Implementation kMyDeadImpl was removed from all classes at format number 4.2.

You might need to use this technique in the following situations:

- If you remove a persistent data interface from a page item, story, or workspace, record this removal in a DirectiveList.
- If you remove a dialog boss class from your plug-in, record this removal to allow the saved user interface state to recover properly.

## Changing the ID of a Boss Class or Implementation

To change the ID of a boss or of an implementation, use the ReplaceClass or ReplaceImplementation directives. See [Example 44](#).

**EXAMPLE 44 DirectiveList Resource for Changing Boss Classes or Implementations**

```
resource DirectiveList (kMyDirectiveRsrcID)
{
{
{ReplaceClass {kOldBossID, kNewBossID, {5, 2}} },
{ReplaceImplementation {kSomeBoss, kOldImplID, kNewImplID, {4, 12}} },
{ReplaceAllImplementation {kOldImplID, kNewImplID, {4, 12}} },
}
};
```

Line by line, the preceding list of directives tells the conversion manager the following:

- Change the ID from kOldBossID to kNewBossID. The new format number was first used in format number 5.2.
- Change implementation kOldImplID to kNewImplID for boss kSomeBoss. The new format number was first used in format number 4.12.
- Change implementation kOldImplID to kNewImplID in *all boss classes*. The new format number was first used in format number 4.12.

## Adding, Moving, or Removing a XferID() Call for ClassIDs or ImplementationIDs

If you change the ReadWrite() of a persistent implementation such that you are adding, moving, or removing an XferID() call (used to read or write ClassIDs and implementationIDs), you need a *content iterator*. If you do not have one, you will get an assert when the debug application shuts down, to remind you that you need one.

The conversion manager algorithm relies on the ability to find every ClassID and ImplementationID in a document. It then determines, for each ID, whether it needs to be converted. It finds all these IDs by iterating through the document database. At the outermost level, the conversion algorithm iterates through all UIDs in the database. Because each UID is a class, it first asks whether the class needs conversion. Next, it gets the content iterator for the class and iterates through all ImplementationIDs the class contains.

If an implementation does not need to be converted, the conversion manager checks whether there is a content iterator associated with the implementation. Unless the implementation contains embedded ClassIDs or ImplementationIDs, usually there is not an iterator, because the implementation reads and writes only simple data (for example, PMString and Int32). If there is a content iterator, however, the conversion manager looks at each ClassID and ImplementationID the implementation contains, to see whether it needs conversion. (This process is recursive.) The content iterator must match what the ReadWrite() routine does, or it fails.

To add a content iterator for your implementation, follow these steps:

1. Add a Content Iterator Register boss to your plug-in's ClassDescriptionTable, as shown below:

```
Class
{
    kSnapIteratorRegisterBoss,
    kInvalidClass,
    {
        IID_ICONTENTITERATORREGISTER, kSnapIteratorRegisterImpl,
        IID_IK2SERVICEPROVIDER, kContentIteratorRegisterServiceImpl,
    } },
```

2. Implement your own content iterator register, by extending IContentIteratorRegister. See <SDK>/source/sdksamples/snapshot/SnapIteratorRegister.cpp.

3. Use the schema-based iterator to provide a schema that describes what the data looks like, as shown below:

```
resource Schema (kFormatRsrcID)
{
    kFooImpl, // ImplementationID
    {RezLong(1), RezLong(0)}, // format number
    {
        // FieldID 1, default is empty string
        {PMString {0x0001, ""}}, // FieldID 2, default = 0
        {ClassID {0x0002, 0}}, // FieldID 3, default = 1.0
        {Real {0x0003, 1.0}}, // FieldID 4, default = 0
        {Bool16 {0x0004, 0}}, // FieldID 5, default = 512
        {Int32 {0x0005, 512}},
    }
};
```

For a working example of a content iterator, see <SDK>/source/sdksamples/snapshot.

## Incrementing Format Number without Changing Data Format (Null Conversions)

You might want to increment a plug-in's format number in the PluginVersion resource, even though you did not change the data format. In this case, you can perform a *null conversion* to tell the content manager about the new format number. See [Example 45](#).

### **EXAMPLE 45 SchemaFormatNumber Resource**

```
resource SchemaFormatNumber (1)
{
    {
        { kMyFirstPersistMajorVersionNumber, kMyFirstPersistMinorVersionNumber, }
        { kMyFirstPersistMajorVersionNumber, kMySecondPersistMinorVersionNumber, }
    }
};
```

This resource, along with the lack of any DirectiveList resources specific to these versions, causes the schema-based converter to generate a null conversion from format number 1.0 of each implementation to format number 2.1. Not including this resource causes an assert:Assert: "ConversionMgr::AddTargetConversion() - Unable to convert plugin 'MYPLUGIN.PLN' from format 1.0 to format 2.0."

**NOTE:** If you did not change the persistent data format, it is not necessary to increment the format number; leave it unchanged. Because the SDK samples use a macro for format numbers, you might need to edit your PluginVersion resource so the actual number stays the same. By not changing the format number, you can avoid unnecessary work by the conversion manager, and you will not need a conversion provider.

## Changes to Data Conversion-related APIs

To find out about changes to data conversion-related APIs, see the API Advisor reports, found at <SDK>/docs/references/APIAdvisorID3\_vs\_ID4.html.

## Why InDesign Won't Open Documents Saved with Older Versions of Your Plug-in

If your plug-in stores a persistent preference PMString on the kDocWorkspace, you might have done either of the following:

- Changed your persistent data implementation in some way but forgotten to tell the conversion manager. See “[Changing the Format of Data Stored by a Persistent Implementation](#)” on page 262.
- Changed the format number unintentionally, without changing your persistent data implementation. See “[Incrementing Format Number without Changing Data Format \(Null Conversions\)](#)” on page 265, or change the persistent data format number to be the same as that in the 2.0 version of your plug-in, so no conversion occurs.

## Which Types use Implicit Type Conversion

When specifying a schema resource, some fields might require implicit type conversion. [Table 23](#) shows which data types can be implicitly converted and which cause an illegal conversion. In the table, Y denotes a legal conversion, and N denotes an illegal conversion. Here are further notes on Y:

1. Y1 — False converts to zero; true converts to one.
2. Y2 — Zero converts to false; any other value converts to true.
3. Y3 — Nonnegative values are converted; negative values are a conversion error.
4. Y4 — Like Y3, with the restriction that positive values outside the range of the target are conversion errors.
5. Y5 — The real number is rounded to an integer, then treated like Y4.
6. Y6 — Values outside the range of the target are conversion errors.
7. Y7 — The real number is rounded to an integer, then treated like Y6.
8. Y8 — If the ID is invalid, the data is converted to kFalse; otherwise, it is converted to kTrue.

**TABLE 23 Implicit Type Conversion**

	Bool8	Bool16	Int8	Uint8	Int16	Uint16	Int32	Uint32	Real	ID	Obj	Ref
Bool8	---	Y	Y1	Y1	Y1	Y1	Y1	Y1	N	N	N	N
Bool16	Y	---	Y1	Y1	Y1	Y1	Y1	Y1	N	N	N	N
Int8	Y2	Y2	---	Y3	Y	Y3	Y	Y3	Y	N	N	N
Uint8	Y2	Y2	Y6	---	Y	Y	Y	Y	Y	N	N	N
Int16	Y2	Y2	Y6	Y4	---	Y3	Y	Y3	Y	N	N	N
Uint16	Y2	Y2	Y6	Y6	Y6	---	Y	Y	Y	N	N	N
Int32	Y2	Y2	Y6	Y4	Y6	Y4	---	Y3	Y	N	N	N
Uint32	Y2	Y2	Y6	Y6	Y6	Y6	Y6	---	Y	N	N	N
Real	N	N	Y7	Y5	Y7	Y5	Y7	Y5	---	N	N	N
ID	Y8	Y8	N	N	N	N	N	N	N	---	N	N
Obj	N	N	N	N	N	N	N	N	N	N	---	N
Ref	N	N	N	N	N	N	N	N	N	N	N	---



# Commands

This chapter describes use cases and frequently asked questions related to commands.

---

## Finding commands provided by the API

### Description

Suppose you want to find out whether an API is provided that can help you perform a task, such as the following:

- Create, open, save, or close a document.
- Create, modify, or delete an object in a document. For example, you may want to modify a text style, create a frame, or copy a frame to another document.
- Create, modify, or delete an object in defaults. For example, you may want to modify a text style preference.

### Solution

To find out whether an API is provided that will help you, follow these steps:

- See the chapters of this manual and *Adobe InDesign CS4 Solutions* on the domain that contains the objects you want to change. For example, to manipulate page items, see the “Layout Fundamentals” chapter of this manual and the “Layout” chapter of *Adobe InDesign CS4 Solutions*.
- Look for a utility that encapsulates processing of the commands required and saves you writing the code that processes commands. See `kUtilsBoss` in the *API Reference* for a list of utility interfaces. See `IDocumentCommands`, `IPathUtils`, `ITextModelCmds`, `ITableCommands`, and `IXMLUtils` for examples of those that are used often.
- To modify objects that are selected, or form part of the active context, look for a suite that does the modification you want. See `kIntegratorSuiteBoss` in the *API Reference* and the “Selection Fundamentals” chapter.
- Determine the command the application uses to effect the change in which you are interested. See “[Spying on command processing](#)” on page 270.
- Examine the *API Reference* page for the command, for detailed documentation. For example, see `kNewSpreadCmdBoss`.

### See also

- For a list of all commands: `ICommand` in the API Reference. Alternatively, search the *API Reference* for the string “`k*CmdBoss`.”
- “[Spying on command processing](#)” on page 270.

---

## Spying on command processing

### Description

Suppose you want to discover the commands the application uses to effect some change. For example, you want to find out the command that is processed when you use the Paragraph Options dialog to change a text style.

### Solution

Using the Spy plug-in, follow these steps:

- Start the debug build of InDesign.
- Open the Preferences dialog, by selecting `Test > Spy > Spy Preferences...`
- Check the `EnableSpy > SpyOnCommand` preference, and check the output sink you want to use to log the commands. For output on Windows®, use Notepad; on Mac OS®, use Debug Log.
- Perform the gesture in the application you are interested in, and examine the output to see the commands that were processed.

Using the Diagnostics plug-in, turn on command tracing, by selecting `Test > Diagnostics > Command > Trace All Commands`.

Treat the output with caution. It reveals the commands used to make the change, but a utility may exist that can process this command for you. Check the command’s documentation in the *API Reference* for information on available utilities.

### See also

- [“Finding commands provided by the API” on page 269.](#)

# Processing a command

## Description

Suppose you need to modify an object that persists in a document or defaults.

## Solution

Objects that persist in a database that supports undo, such as documents (see `kDocBoss`) or defaults (see `kWorkspaceBoss`), must be modified using commands. You must not call interfaces that set persistent data on these objects directly.

**NOTE:** Utilities are provided to encapsulate the processing of many commands, so you need not write that. See “[Finding commands provided by the API](#)” on page 269.

To process a command, follow these steps:

1. Create the command, using `CmdUtils::CreateCommand`.
2. Specify the command’s input parameters. Parameters are passed into a command using data interfaces on the command object and the command’s item list. Often, the objects to be operated on by the command are passed using the item list (see `ICommand::GetItemList`). Some other commands operate on predetermined objects or objects identified using a data interface on the command.
3. Process the command, using `CmdUtils::ProcessCommand`.
4. Check for errors. `CmdUtils::ProcessCommand` returns an error code; check for `kSuccess` before continuing. Alternatively, check the global error code (`ErrorUtils::PMGetGlobalErrorCode`).
5. On error, do not continue to process commands, just return to your caller. The application is responsible for reverting the model back to its state before the command was processed and informing the user of the error.

**NOTE:** If you continue to process commands while the global error code is set, protective shutdown occurs.

6. On success, continue and get the command’s output parameters (if appropriate).

**NOTE:** If you need more sophisticated flow control that allows for fail/retry semantics, use an abortable command sequence . See “[Processing an abortable command sequence](#)” on page 274.

## Commands

*Scheduling a command*

### See also

- CmdUtils and ICommand in the *API Reference*.
- For sample code: SnpProcessDocumentLayerCmds::CreateNewLayer and BPIHelper::ProcessBPISetDataCmd.

---

## Scheduling a command

### Description

Suppose you want to make a change to a document or defaults, but you need to delay the change so it occurs later. For example, when the application is launched, you want to automatically load some data into defaults. There is a service you can use to get called on start-up (see the IStartupShutdownService interface), but you need to wait until the application is fully initialized before loading the data.

### Solution

Schedule a command to be processed at a later time. The command is processed when the application is idle, based on the specified priority.

To schedule a command, follow these steps:

1. Create the command, using CmdUtils::CreateCommand
2. Specify the command's input parameters. Parameters are passed into a command using data interfaces on the command object and the command's item list.
3. Schedule processing of the command, using CmdUtils::ScheduleCommand.
4. CmdUtils::ScheduleCommand returns an error code that indicates whether the command was scheduled successfully.
5. The application processes the command later, using an idle task. If the command returns with the global error code set, the application is responsible for reverting the model back to its state before the command was processed and informing the user of the error.

### See also

- IStartupShutdownService in the *API Reference*.

# Processing a command sequence

## Description

Suppose you want to group a set of modifications into one undoable operation. For example, you want to place a set of images into a document and apply a special effect to each one. On undo, all images should be removed from the document; on redo, they should be restored.

## Solution

Process the commands that perform the changes within a new command sequence. Follow these steps:

1. Create an instance of the SequencePtr helper class. This class calls CmdUtils::BeginCommandSequence to begin a new command sequence in its constructor:

```
CmdUtils::SequencePtr cmdSeq;
```

**NOTE:** If you prefer that your commands join an existing command sequence if one exists, use SequenceContext as the helper class.

2. Optionally, give the sequence a name, using ICommandSequence::SetName. If you do not set the name, the sequence inherits the name of the first command processed within it.

```
cmdSeq->SetName ("Your sequence name");
```

3. Process the first command. See “[Processing a command](#)” on page 271.
4. Check for errors. CmdUtils::ProcessCommand returns an error code; check for kSuccess before continuing. If you called another utility that returns an error code, check it instead. Otherwise, check the global error code (ErrorUtils::PMGetGlobalErrorCode) for kSuccess.
5. On success, process the next command.
6. On error, do not continue processing commands. Optionally, you can change the global error code (ErrorUtils::PMSetGlobalErrorCode) to some other error, but you must not set it back to kSuccess.

**NOTE:** If you continue processing commands while the global error code is set, protective shutdown occurs.

7. When the SequencePtr class goes out of scope, its destructor ends the sequence using CmdUtils::EndCommandSequence.
8. Return to your caller. If an error was detected, either return an error code to your caller (if appropriate), or make sure the global error code is set before returning. The application is responsible for reverting the model back to its state before the command was processed and informing the user of the error.

### See also

- For sample code: CmdUtils::SequencePtr in the *API reference* and SnpManipulateInline::InsertInline.
- For sample code: CmdUtils::SequenceContext in the *API Reference* and SnpPerformXMP-Commands::ReplaceMetaDataFromFile.
- For sample code: ICommandSequence in the *API Reference* and SnpProcessDocument-LayerCmds::CopyToNewLayer.

---

## Processing an abortable command sequence

### Description

Suppose you want to group a set of modifications into one undoable operation and, within this operation, you need sophisticated flow control that allows for fail/retry semantics. For example, while refreshing the content of the files linked to a document, you find a file is missing and want to allow the user to browse for the missing file and then proceed.

**NOTE:** Abortable command sequences should be used only where absolutely necessary, since they incur a heavy performance overhead. If you are in any doubt, use a regular command sequence; see “[Processing a command sequence](#)” on page 273.

### Solution

To process two or more commands within an abortable command sequence, follow these steps:

1. Begin the sequence, using CmdUtils::BeginAbortableCmdSeq
2. Optionally, give the sequence a name using IAbortableCmdSeq::SetName. If you do not set the name, the sequence inherits the name of the first command you process.
3. Process commands and use CmdUtils::SetSequenceMark to mark points in the sequence to which you want to be able to roll back. On failure, use CmdUtils::RollBackCommandSequence to roll back. Reset the global error code (ErrorUtils) to kSuccess, and then process the commands in your retry strategy.
4. On success, end the sequence using CmdUtils::EndCommandSequence. On failure, end the sequence using CmdUtils::AbortCommandSequence; any changes made are aborted.

**NOTE:** If you continue processing commands while the global error code is set, protective shutdown occurs.

**EXAMPLE 46 Example of fail/retry semantics in an abortable command sequence**

```

IAabortableCmdSeq* sequ = CmdUtils::BeginAbabortableCmdSeq();
SequenceMark sequenceMark = CmdUtils::SetSequenceMark(sequ);
ErrorCode status = TrySomeCommands();
if (status != kSuccess)
{
    status = CmdUtils::RollBackCommandSequence(sequ, sequenceMark);
    if (status == kSuccess)
    {
        ErrorUtils::PMGetGlobalErrorCode(kSuccess);
        status = RetryOtherCommands();
    }
}
if (status == kSuccess)
{
    CmdUtils::EndCommandSequence(sequ);
}
else
{
    CmdUtils::AbortCommandSequence(sequ);
}

```

**See Also**

- IAabortableCmdSeq and CmdUtils in the *API Reference*.
- “Processing a command sequence” on page 273.

**Fixing assert “DataBase change outside of Begin/End Transaction!”****Description**

Suppose you call a method on an interface, and you get an assert “DataBase change outside of Begin/End Transaction!”

**Solution**

You must process a command to modify that interface. Call a utility that processes the command for you.

**See also**

- “Finding commands provided by the API” on page 269 and “Processing a command” on page 271.

## Commands

*Fixing assert "DataBase change outside of Begin/End Transaction!"*

# Notification

This section describes solutions to problems that can be encountered when working with notification.

## Finding responder events and their associated ServiceID

### Description

Suppose you want to know the predefined set of events for which the application calls responders. For example, the application can call responders when documents open and close.

### Solution

Each event has a corresponding ServiceID. A responder can register interest in one or more of these events by returning the ServiceIDs of interest from its IK2ServiceProvider implementation. [Table 24](#) lists the ServiceIDs for events in which responders frequently are interested.

**TABLE 24 Frequently used responder events and ServiceIDs**

Event	ServiceID	Signal-manager boss class
Create document	kBeforeNewDocSignalResponderService	kDocumentSignalMgrBoss
	kDuringNewDocSignalResponderService	kDocumentSignalMgrBoss
	kAfterNewDocSignalResponderService	kDocumentSignalMgrBoss
Open document	kBeforeOpenDocSignalResponderService	kDocumentSignalMgrBoss
	kDuringOpenDocSignalResponderService	kDocumentSignalMgrBoss
	kAfterOpenDocSignalResponderService	kDocumentSignalMgrBoss
Save document	kBeforeSaveDocSignalResponderService	kDocumentSignalMgrBoss
	kAfterSaveDocSignalResponderService	kDocumentSignalMgrBoss
Save document as a new file	kBeforeSaveAsDocSignalResponderService	kDocumentSignalMgrBoss
	kAfterSaveAsDocSignalResponderService	kDocumentSignalMgrBoss
Save copy of document	kBeforeSaveACopyDocSignalResponderService	kDocumentSignalMgrBoss
	kDuringSaveACopyDocSignalResponderService	kDocumentSignalMgrBoss
	kAfterSaveACopyDocSignalResponderService	kDocumentSignalMgrBoss

## Notification

*Finding responder events and their associated ServiceID*

Event	ServiceID	Signal-manager boss class
Revert document	kBeforeRevertDocSignalResponderService	kDocumentSignalMgrBoss
	kAfterRevertDocSignalResponderService	kDocumentSignalMgrBoss
Close document	kBeforeCloseDocSignalResponderService	kDocumentSignalMgrBoss
	kAfterCloseDocSignalResponderService	kDocumentSignalMgrBoss
Create new page item	kNewPISignalResponderService	kNewPISignalMgrBoss
Create new story	kNewStorySignalResponderService	kNewStorySignalMgrBoss
Delete story	kDeleteStoryRespService	kDeleteStoryCmdBoss

**Table 24** is not a complete list of the responder services provided by the application. See the documentation on working with a particular domain, such as layout or text, for information on the responder services the domain provides. If you do not find the information you need, you can determine the current set of responder services supported by the application as follows:

1. Search the public API headers for the string “kServiceIDSpace.” This gives the complete set of services available (only a subset of which are responder services). For example:

```
DECLARE_PPID(kServiceIDSpace, kComponentVersionService, ...)  
DECLARE_PPID(kServiceIDSpace, kMenuRegisterService, ...)  
...
```

2. Search the results above for the string “Resp”. For example:

```
DECLARE_PPID(kServiceIDSpace, kAppChangesSignalResponderService, ...)  
DECLARE_PPID(kServiceIDSpace, kDocChangesSignalResponderService, ...)  
...
```

3. This yields in the list of ServiceIDs for the predefined set of events the application makes available for responders to register interest in.

If the responder is to handle a single event, the API provides service-provider implementations that can be used to register interest. As a result, you need not write the C++ class that implements IK2ServiceProvider. For example, if a responder is required that reacts to the before close signal, the existing API-supplied implementation (kBeforeCloseDocSignalRespService-Impl) can be declared in the boss class definition. **Table 25** lists frequently used service-provider implementations provided by the API.

**TABLE 25 Frequently used responder service-provider implementations**

ServiceID	API-provided ImplementationID
kBeforeNewDocSignalResponderService	kBeforeNewDocSignalRespServiceImpl
kDuringNewDocSignalResponderService	kDuringNewDocSignalRespServiceImpl
kAfterNewDocSignalResponderService	kAfterNewDocSignalRespServiceImpl
kBeforeOpenDocSignalResponderService	kBeforeOpenDocSignalRespServiceImpl

ServiceID	API-provided ImplementationID
kDuringOpenDocSignalResponderService	kDuringOpenDocSignalRespServiceImpl
kAfterOpenDocSignalResponderService	kAfterOpenDocSignalRespServiceImpl
kBeforeSaveDocSignalResponderService	kBeforeSaveDocSignalRespServiceImpl
kAfterSaveDocSignalResponderService	kAfterSaveDocSignalRespServiceImpl
kBeforeSaveAsDocSignalResponderService	kBeforeSaveAsDocSignalRespServiceImpl
kAfterSaveAsDocSignalResponderService	kAfterSaveAsDocSignalRespServiceImpl
kBeforeSaveACopyDocSignalResponderService	kBeforeSaveACopyDocSignalRespServiceImpl
kDuringSaveACopyDocSignalResponderService	kDuringSaveACopyDocSignalRespServiceImpl
kAfterSaveACopyDocSignalResponderService	kAfterSaveACopyDocSignalRespServiceImpl
kBeforeRevertDocSignalResponderService	kBeforeRevertDocSignalRespServiceImpl
kAfterRevertDocSignalResponderService	kAfterRevertDocSignalRespServiceImpl
kBeforeCloseDocSignalResponderService	kBeforeCloseDocSignalRespServiceImpl
kAfterCloseDocSignalResponderService	kAfterCloseDocSignalRespServiceImpl
kNewPISignalResponderService	kNewPISignalRespServiceImpl
kNewStorySignalResponderService	kNewStorySignalRespServiceImpl
kDeleteStoryRespService	kDeleteStoryRespServiceImpl

## See also

- For general documentation on services: the “Service Providers” chapter.
- For a sample of a service provider implementation that registers interest in multiple events: DocWchServiceProvider in the DocWatch plug-in.
- For a sample of a responder that re-uses a service-provider implementation provided by the API: the boss class definition for kBPINewDocResponderBoss in the BasicPersistInterface sample.

## Notification

*Spying on observer notification broadcasts*

---

# Spying on observer notification broadcasts

## Description

Suppose you want to discover the broadcasts the application makes to notify a change.

## Solution

The Spy plug-in can be configured to log all commands that are executing, along with the subjects notified, the protocol used for notification, and the change that occurs. Perform the action of interest, and Spy provides the information required to observe the action.

Using the Spy plug-in, do the following:

- Start the debug build of InDesign.
- Open the preferences dialog, by selecting Test > Spy > Spy Preferences...
- Check the EnableSpy > SpyOnBroadcast preference, and check the output sink you want to use to log the commands. For output on Windows, use Notepad; for Mac OS, use Debug Log.
- Perform the gesture in the application you are interested in, and examine the output to see the notifications that were broadcast. For example, the ClassID of the subject and the message protocol used for the notification performed when you use the Paragraph Options dialog to change a text style is reported after the @ sign in the output:

```
> kEditTextStyleCmdBoss @ kDocWorkspaceBoss (IID_ISTYLEINFO)
```

---

# Accessing lazy notification data objects used by the application

## Description

Suppose you use lazy notification to observe objects in the model and want to access the information in the lazy notification data that is broadcast by the application.

## Solution

The lazy notification data objects used within the application are not documented in the public API.

**NOTE:** Refresh the observer's state entirely when `IObserver::LazyUpdate` is called.

Lazy notification data objects are data-carrying (C++) objects created by the message originator before they call `ISubject::ModelChange`. The type of data contained in a lazy notification data object varies. Each notification protocol used by the application either has a fixed C++ data type or does not use lazy notification data at all. Observers need to know the type, so they can safely cast a `LazyNotificationData` pointer to a concrete class. For example, changes to the spread list are notified on protocol `IID_ISPREADLIST`, using a type of `ListLazyNotificationData<UID>`.

## See also

- Material about lazy notification in the “Notification” chapter of *Adobe InDesign CS4 Solutions*.

## Using lazy notification data

### Description

Suppose you need to optimize lazy notification. For example, you observe a large number of objects in the model and present a view of all these objects in your user interface. Your command is changing only a small subset of those objects, and you want the observer to refresh the data in the view for only the objects that change.

### Solution

The API provides the templated lazy notification data types identified in [Table 26](#), which can be used to pass information about the objects that change, from the message originator into `IObserver::LazyUpdate`.

**TABLE 26 Useful lazy notification data types**

API	Note
<code>ListLazyNotificationData</code>	Templated class used to pass a list containing a given type. For example, <code>ListLazyNotificationData&lt;UID&gt;</code> can be used for a list of UIDs, and <code>ListLazyNotificationData&lt;ClassID&gt;</code> can be used to pass a list of ClassIDs.
<code>TreeLazyNotificationData</code>	Templated class used to pass a tree containing a given type. For example, <code>TreeLazyNotificationData&lt;UID&gt;</code> can be used to pass a tree of UIDs.

For example, consider a plug-in that adds a list of custom styles to a document and a panel that displays them. The panel has an observer that receives lazy notification when custom styles are

## Notification

*Using lazy notification data*

modified. If the observer receives a nil-pointer for the lazy notification data, this indicates that all custom styles were modified. The observer should examine all custom styles in the document and refresh the entire panel. If the observer receives a lazy notification data object that is not nil, the object can be used to discover the subset of custom styles that were modified. The observer needs to examine only the affected custom styles in the document and refresh their associated data in the panel.

Consider a command that can lock one custom style object at a time. The command notifies using the document's ISubject interface and broadcasts the UID of the affected custom style in a lazy notification data object, as shown in [Example 47](#).

**EXAMPLE 47 Broadcasting the UIDs of an affected object using *ListLazyNotificationData<UID>***

```
void LockYourStyleCmd::DoNotify()
{
    // Broadcast change to document subject
    UIDRef styleRef = this->GetItemList()->GetRef(0);
    IDataBase* db = styleRef.GetDataBase();
    InterfacePtr<IDocument> iDoc(db, db->GetRootUID(), UseDefaultIID());
    InterfacePtr<ISubject> docSubject(iDoc, UseDefaultIID());
    if (docSubject)
    {
        ListLazyNotificationData<UID>* lnData = new ListLazyNotificationData<UID>;
        // This command only locks one style at a time.
        lnData->ItemChanged(styleRef.GetUID());
        docSubject->ModelChange(kLockCustomStyleCmdBoss, IID_ICUSTOMSTYLELIST, this,
        lnData);
    }
}
```

Consider an observer that refreshes a list of these custom styles in a panel. It is attached to a document's ISubject interface for lazy notification when custom styles change. It can use the lazy notification data object to discover the custom style that was affected and optimize the objects that are refreshed, as shown in [Example 48](#).

**EXAMPLE 48 Receiving UIDs of affected objects via *ListLazyNotificationData***

```
void YourStyleObserver::LazyUpdate(ISubject* theSubject, const PMIID &protocol,
const LazyNotificationData* data)
{
    if (protocol == IID_ICUSTOMSTYLELIST)
    {
        // Cast the data pointer to the concrete type.
        const ListLazyNotificationData<UID>* lnData =
        static_cast<const ListLazyNotificationData<UID>*>(data);
        this->HandleUpdate(theSubject, lnData);
    }
}
```

```

void CustomStyleObserver::HandleUpdate(ISubject* theSubject, const
ListLazyNotificationData<UID>* lnData)
{
    if (lnData == nil)
    {
        // Refresh all objects in the panel...
    }
    else
    {
        // Discover the affected objects using the data.
        DataBase* db = ::GetDataBase(theSubject);
        K2Vector<UID> addedItems;
        K2Vector<UID> deletedItems;
        K2Vector<UID> changedItems;
        lnData->BreakoutChanges(&addedItems, &deletedItems, &changedItems);
        // Refresh the affected objects in the panel...
    }
}

```

## **Lazy notification data-object lifetime**

A lazy notification data object is created and populated by a message originator (the entity that calls ISubject::ModelChange, usually a command). The lazy notification data object is allocated on the heap using the new operator, and it is passed to the subject via the ISubject::ModelChange method; ownership passes to the application core. Since only one update message is set to observers for all messages sent (per protocol on a subject) in a sequence, changes in the lazy notification data object accumulate (see LazyNotificationData::Add()). For example, if within a command sequence a loop creates several page items, the creation of the page items being broadcast using lazy notification. Any lazy notification data objects passed into the ISubject::ModelChange method of the subject by the command creating the individual page items are merged. Only one lazy notification data object is passed to the lazy observers. Lazy notification data objects are tied to the lifetime of the command history; however, they can be purged in certain situations (such as low memory). Observers using lazy notification must not assume the existence of an lazy notification data.

## **Lazy-notification data and undo/redo**

Lazy notification data objects must deal appropriately with undo and redo. For example, if the do operation creates a page item, resulting in a UID being placed in the lazy notification data, some understanding of what this means must be provided for undo/redo. API-supplied lazy notification data objects dealing with UIDs generally maintain three sets, those that were added, those that were removed, and those that changed. On undo/redo, the lazy notification data object is invoked to provide a clone (see LazyNotificationData::Clone()). For our simple example, this means on undo the “removed” and “added” lists are swapped, and the observer is called with the cloned list.

## **Lazy-notification data values**

A lazy notification data parameter can be nil; in this case, the observer must re-build whatever information it requires directly from the model. The parameter also can be nil under certain circumstances (such as low memory conditions) controlled by the core application.

## Notification

*Using lazy notification data*

### Implementation

The abstract base class for lazy notification data classes is `LazyNotificationData`. To use the templated classes `ListLazyNotificationData` or `TreeLazyNotificationData` for your own types, follow the instructions provided in the *API Reference*. To implement a new type of lazy notification data object, provide an implementation of `LazyNotificationData`.

### See also

- Material about lazy notification in the “Notification” chapter of *Adobe InDesign CS4 Solutions*.

# Snippets

This chapter presents case studies of working with snippet export, snippet import, and snippets and libraries.

---

## Working with snippet export

### Exporting a snippet from a selection

#### Description

Suppose you have a selection or want to make one programmatically and export a snippet from the selection.

#### Solution

1. If you have no selection but want to create one and are not concerned about trampling the user selection, you can create a selection. For example, you can create a selection in the layout with `ILayoutSelectionSuite`, or select nodes in the structure view with `IXMLNodeSelectionSuite`.
2. Now that you have a selection, you can export (via `ISnippetExportSuite`) either a selection of XML elements in the structure view, or a text selection (as InCopy Interchange) or page items from the layout view.

#### See also

“Selection” chapter

#### Related APIs

- `ILayoutSelectionSuite`
- `ISnippetExportSuite`
- `ITextSelectionSuite`
- `IXMLNodeSelectionSuite`

#### Related function

- Test > Snippet > Export Selection (menu item on testing menu)

### Exporting page items to a snippet (without selection)

Suppose you want to export page items as a snippet, without involving the selection subsystem; for example, because you do not want to trample the end-user selection, or you do not have a view open onto the document.

#### Solution

If you want to export without involving selection, you are responsible for collecting the root objects for your snippet, which should have IDOMElement interfaces. That is, these objects must participate in the scripting DOM. To export page items, you need to create a PageItem snippet, which uses the default export policy. Follow these steps:

1. Identify the root objects you want to export; you need IDOMElement interfaces to refer to these objects for export. For information on acquiring references to page items in the layout, see the “Layout Fundamentals” chapter.
2. Once you identify the content you want to export and created a stream (IPMStream), you can use ISnippetExport::ExportPageitems.

#### See also

- “Snippet Fundamentals” chapter of *Adobe InDesign CS4 Products Programming Guide*

#### Sample code

- SnpImportExportSnippet

#### Related APIs

- IDOMElement
- ISnippetExport

### Exporting swatches to a snippet

Suppose you want to export all swatches in a given document to a snippet file, including all the gradients, solid colors, and tints. Alternately, you might be interested in exporting one or a set of swatches from a given document.

#### Solution

Use ISnippetExport::ExportDocumentResource(), as demonstrated in the SnpImportExportSnippet code snippet.

#### See also

- “Snippet Fundamentals” chapter of *Adobe InDesign CS4 Products Programming Guide*
- “Graphics Fundamentals” chapter (look for more information on swatches)

#### Sample code

SnpImportExportSnippet

## Related APIs (for swatches)

- IRenderingObject
- ISwatchList
- ISwatchUtils
- kGradientRenderingObjectBoss
- kPMColorBoss

## Exporting text styles to a snippet

Suppose you want to export all paragraph styles and character styles from a document, or export a subset of the styles to a snippet.

### Solution

Use `ISnippetExport::ExportAppPrefs()`, as demonstrated by the `SnpShareAppResources` code snippet.

### See also

- “Snippet Fundamentals” chapter of *Adobe InDesign CS4 Products Programming Guide*
- “Text Fundamentals” chapter

### Sample code

- `SnpShareAppResources`
- `SnpInspectTextStyles`
- `SnpManipulateTextStyle`

## Exporting object styles from a document to a snippet

Suppose you want to export all object styles in a given document, or a subset of those styles, to a snippet.

### Solution

Use `ISnippetExport::ExportDocumentResource()`, as demonstrated by the `SnpImportExport` code snippet.

### Sample code

- `SnpImportExportSnippet::ExportObjectStyles`

### Related APIs

- IObjectStyleInfo
- IObjectStylesFacade
- IObjectStylesSuite
- IStyleNameTable

## Exporting XML elements as a snippet

Suppose you want to export a set of nodes in the logical-structure tree, along with the placed content items, because you want to transfer the logical structure and the associated content items into another document. For example, you want to transfer part of one XML template into another, including the frames in the first document, as well as the logical structure.

### Solution

Export a snippet based on the set of XML elements of interest. This lets you import the snippet into another document, and the placed content items would be transferred over into the new document.

The difference between this and a normal XML export is that the normal export does not know how to export any information about the native InDesign document objects; for example, exported XML does not carry information about text frames, graphic frames, spread layers and so on. This information is represented in the snippet, which lets you interchange chunks of an InDesign document with another, carrying over all the dependencies.

Follow these steps:

1. Identify the elements (by XMLReference) you want to export.
2. Create a stream (IPMStream). See SDKFileChooser to ease the process of selecting an output file.
3. Acquire ISnippetExport (from kUtilsBoss), and call the appropriate overload of Export-toStream.

### See also

- “Snippet Fundamentals” chapter of *Adobe InDesign CS4 Products Programming Guide*

### Sample code

- SnpImportExportSnippet::ExportTaggedContentItem

---

# Working with snippet import

## Importing swatches from a snippet

Suppose you already exported some or all of the swatches from a document, and you want to import them into another document.

### Solution

You need to decide what node in the scripting DOM will be the target for the import. You need to target the document, which means you should parent the incoming snippet on the document (kDocBoss). Follow these steps:

1. Assume you opened a stream (IPMStream) onto the snippet file you want to import.
2. If you have a document interface (IDocument, say), you only need to query its IXMLFragment interface and use that in ISnippetImport::ImportFromStream.
3. Since you are importing into the document element in the scripting DOM, you should have an import policy of kDocElementImportBoss.

### See also

- “Snippet Fundamentals” chapter of *Adobe InDesign CS4 Products Programming Guide*.

### Sample code

- SnpImportExportSnippet::ImportToDocumentElement

## Importing paragraph and character styles from a snippet

Suppose you want to import a set of paragraph and/or character styles from a snippet.

### Solution

You can import these into the document element. If you have a document reference (IDocument), acquire the IXMLFragment interface and use ISnippetImport::ImportFromStream.

### See also

- “Snippet Fundamentals” chapter of *Adobe InDesign CS4 Products Programming Guide*

### Related API

- ISnippetImport

### Sample code

- SnpShareAppResources

### Importing object styles from a snippet

Suppose you want to import object styles previously exported as a snippet.

#### Solution

Use `ISnippetImport::ImportFromStream`, as demonstrated in [SnpImportExportSnippet](#).

### Importing styled text from a snippet

Suppose you want to import some styled text, and you are not sure exactly what the target for the import should be. Assume you exported a story and already have one in a snippet.

The behavior of the application when it comes to snippets containing text needs to be examined carefully. If the root object in the snippet is a story (from a `kTextStoryBoss` object), the snippet expects to be inside an ICML or INCX file. If you drag this onto a document, it places the styled text as you expect. If you change the snippet file extension to `.idms` or `.inds`, instead of `.icml` or `.incx`, the snippet will not create styled text on import; instead, you will see the XML content.

On the other hand, if you export from the containing frame, you can drag in an `.idms` or `.inds` file containing styled text and get back a text frame with your styled text in it.

#### Solution

Using the low-level snippet-import mechanism is not easy when importing a story from INCX. It is safer to use the InCopy import provider (`IImportProvider`).

#### See also

[Adobe InDesign CS4 Interchange \(INX\) File Format](#)

### Importing page items from a snippet

Suppose you want to import some page items you have already exported as described in [“Exporting page items to a snippet \(without selection\)” on page 286](#).

#### Solution

1. If you want the imported page item to be at the exact same location as when it was exported, set the “snippet import uses original location” preference (`kSetSnippetImportLocation-PrefCmdBoss`) to `kTrue`; otherwise, set it to `kFalse`.
2. If these are to be top-level elements on the page, target the spread element (`kSpreadBoss` in the boss DOM).
3. You may be importing into a group (`kGroupItemBoss`). For more information, see the “Layout Fundamentals” chapter; in particular, the section on groups.

#### Sample code

`SnpImportExportSnippet::ImportToSpreadElement`

## Importing XML elements from a snippet

Suppose you want to import a set of XML elements that were already exported as described in “[Exporting XML elements as a snippet](#)” on page 288. Suppose the XML elements were placed, and you want to create content in the layout on import.

### Solution

1. Open a stream (IPMStream) onto the snippet.
2. Decide what element on the scripting DOM (IDOMElement) to import the snippet into. To do this, you decide what XMLReference in the logical structure to target.
3. You may have to construct a proxy boss object (kXMLItemProxyScriptObjectBoss) associated with the XMLReference that should parent the snippet content. This lets you acquire an IXMLFragment reference that you need for ISnippetImport::ImportFromStream.

### See also

“Snippet Fundamentals” chapter of *Adobe InDesign CS4 Products Programming Guide*

### Sample code

`SnpImportExportSnippet::ImportXMLElements`

---

## Working with snippets and libraries

### Using asset libraries

To a large extent, the dependence of asset libraries on snippets is hidden from end users. If your customers use asset libraries in their workflow, however, and you have persistent data added to document objects, you need to add function so you can round-trip your data through snippets, because that is how assets with your data would be stored in asset libraries.

### Solution

Be sure any persistent data you add to the boss DOM also is added into the scripting DOM. This means making at least the persistent data in your plug-in scriptable.

### See also

- The “Scriptable Plug-in Fundamentals” chapter

### Sample code

`CandleChart`

## Converting the InDesign CS (Version 3) asset library to the current version

Suppose you have an InDesign CS (version 3) asset library (INDL) file, and you want to update it to the current version.

### Solution

Use the ConvertToSnippets method on ILibraryAssetCollection.

### See also

- The “Scriptable Plug-in Fundamentals” chapter

### Sample code

- CandleChart

## Exporting snippets directly from an asset library

Since assets are held as snippet in library files, is there some way to get at the data? For example, suppose your end users create asset libraries locally, but you do not want to store libraries in the back-end database; rather, you want to just store the assets in them as individual snippets, and re-create the libraries from snippets stored in your back-end database. You then have a requirement to break apart an asset library into individual snippets. Fortunately, because the asset library is just a wrapper around snippets with other directory-type information, it is relatively easy to do this.

### Solution

If you just wanted to place a page item from an existing asset library to a document, you would use the existing API; e.g., ILibrarySuite or ILibraryCmdUtils. Both of these require you to be familiar with the representation of assets in the library, so some of the content is still relevant to that use case.

Suppose, however, you want to export the contents of an asset library as individual snippet files. Follow these steps:

1. Assets in an asset library (kSnippetBasedCatalogBoss) are represented by kLibraryAssetBoss. If you examine the profile of the interfaces kLibraryAssetBoss exposes, you can see ILibraryAssetContents.
2. ILibraryAssetContents has methods to let you acquire the data for the asset as a sequence of bytes, which correspond to the serialized asset in snippet format.
3. Save the memory-based buffer to a file-based stream (IPMStream), and you have a snippet file.

### Sample code

SnpImportExportSnippets

## Related APIs

- [ILibrary](#)
- [ILibraryAsset](#)
- [ILibraryAssetCollection](#)
- [ILibraryAssetContents \(kLibraryAssetBoss\)](#)

## Adding a snippet directly to an asset library

Suppose you have a snippet file and want to somehow add it directly into an asset library, without going through the operation of placing the file into a document and then adding it from the document into the asset library.

### Solution

If you just want to add an existing page item in a document to an asset library (kSnippetBasedCatalogBoss), there are APIs like [ILibrarySuite](#) and [ILibraryCmdUtils](#) that help in this operation.

A more interesting operation from the snippet perspective is adding a snippet directly from a file into an asset library (kSnippetBasedCatalogBoss), without first placing the snippet in a document. Implementing this operation on the current public API is impossible. You might think of going through the scrap database rather than having to create a document, but you cannot import a snippet file into the scrap database, as it does not have a DOM element (IDOMElement) hierarchy; see [kScrapDocBoss](#) and compare with [kDocBoss](#).



# InCopy: Assignments

## Creating an assignment

Suppose you want to create a new assignment in an InDesign document.

### Solution

There are several ways to create a new assignment:

- If you want the end user to have full user-interface control, call `IAssignmentUIUtils::NewAssignment`, which returns a `UIDRef` of the new assignment. You can get `IAssignmentUIUtils` because it is aggregated into `kUtilsBoss`.
- If you do not want any user interface, use `IAssignmentMgr::CreateAssignmentCmd`, which returns an `IAssignment` pointer. You can get `IAssignmentMgr` from `kSessionBoss` because it is aggregated into `kSessionBoss`.
- To use `kAssignDocCmdBoss` directly, you need to pass the command various data. For an example, see the code snippet provided in the SDK.

### Sample code

```
SnpManipulateAssignment::NewAssignment
```

### Related APIs

- `IAssignment`
- `IAssignmentMgr`
- `IAssignmentUIUtils`
- `kAssignDocCmdBoss`

---

## Adding content to an assignment

Suppose you want to add text stories or images to an existing assignment.

### Solution

1. Get IAssignmentSelectionSuite from active context.
2. Use IAssignmentSelectionSuite::Assign.

### Sample code

```
SnpManipulateAssignment::AddToAssignment
```

### Related APIs

- IAssignmentMgr
- IAssignmentSelectionSuite
- kAddToAssignmentCmdBoss

---

## Examining the content of an assignment

Suppose you want to know the content of an assignment.

### Solution

1. Instantiate the IAssignment interface of the assignment.
2. Get information about the assignment from the interface, like assignment name, assignee, and assignment file path.
3. Get a list of IAssignedStory objects from IAssignment::GetStories.
4. See whether each assigned story is a text story or an image story, by examining the ClassID of the object.
5. Get information about each assigned story through the IAssignedStory interface.

### Sample code

```
SnpManipulateAssignment::InspectAssignment
```

## Related APIs

- IAssignedStory
- kAssignedStoryBoss
- IAssignment
- kAssignedImageBoss

---

## Deleting an assignment

Suppose you want to delete an existing assignment from a document.

### Solution

1. Create kUnassignDocCmdBoss.
2. Get the assignment file path from the IAssignment interface.
3. Pass the document UIDRef as the command's ItemList, and pass the assignment file path as command data.
4. Process the command.

### Sample code

```
SnpManipulateAssignment::DeleteAssignment
```

## Related APIs

- IAssignment
- IID\_ISTRINGDATA
- kUnassignDocCmdBoss



# Flash/FlexUI

---

## Getting Started

InDesign CS4 can display Flash SWF content internally. This is implemented in several ways; here, we discuss how to do it with a C++ plug-in and with ScriptUI.

### Why use Flash/Flex in InDesign?

- Adobe Flex® provides a very easy way to build a user interface.
- InDesign can export to SWF and can contain Flash content. The ability to show Flash content in a panel can be very useful; for example, in page transitions.
- You gain the ability to re-use a user interface in multiple applications; for example, a kuler panel that works in Photoshop, InDesign, etc.

### Guidelines for using a C++ plug-in versus ScriptUI

Use a C++ plug-in in the following cases:

- Your user interface is displaying/accessing data not accessible from scripting.
- You are building a panel that displays information about the InDesign model and must remain up to date.
- You want to add a Flash user interface to an existing plug-in user interface or replace an existing plug-in user interface.

Use ScriptUI in the following cases:

- Your data is accessible from scripting.
- It is acceptable if your user interface is not always up to date. (This probably is best as a modal dialog solution.)
- You want to add a Flash user interface to an existing ScriptUI solution.

---

## Flash/Flex from a C++ plug-in

### Introduction and use

- How to implement a panel containing a Flash SWF.
- How to connect a selection observer to an OWLFlashPlayerWidget by specializing ActiveSelectionObserver.
- How to call methods within a Flash SWF from a plug-in.
- How to call methods within a C++ plug-in from a Flash SWF.

The flexuistroke sample plug-in shows how to implement FlexUI in InDesign using an OWLFlashPlayerWidget in a panel. If the panel is not visible on start-up, it can be shown from the Windows menu. The panel contains an OWLFlashPlayerWidget, and it aggregates an ActiveSelectionObserver. When the panel is created, the observer loads the flexuistroke SWF into the OWLFlashPlayerWidget. The combo-box component in the SWF is programmed to mimic the behavior of the weight widget on the application's Stroke Weight panel.

The flexuistroke sample plug-in comprises two projects: an InDesign plug-in and a Flex Builder™ 3 project. The InDesign plug-in components are in the typical SDK sample locations, and the Flex Builder component is in the flexuistrokemxml folder within the plug-in's source folder. The SWF file has already been built for this plug-in; it is in flexuistrokemxml/bin. The plug-in expects to find the SWF file (flexuistroke.swf) in the same folder as the plug-in's executable file (on Windows, FlexUIStroke.sdk.pln; on Mac OS, FlexUIStroke.sdk.InDesignPlugin).

The plug-in project files have a custom build step that copies the SWF from its bin folder to the same folder as the plug-in's executable.

The Flex Builder project is available in the flexuistrokemxml folder. To use the Flex project, follow these steps:

- Run Flex Builder 3.
- Right click in the Flex Navigator window and choose Import... > General > Existing Projects into Workspace.
- Click Next.
- Choose "Select root directory" and browse to the flexuistroke sample plug-in's flexuistrokemxml folder.
- Click Finish.

### Classes

- FlexUIStrokeActionComponent — Implements IActionComponent; performs the actions that are executed when the plug-in's menu items are selected.
- FlexUIStrokePanelSelectionObserver — Implements an observer, IObserver based on ActiveSelectionObserver, that updates the stroke weight displayed in the panel's widget

when the stroke weight of the selected objects change, and updates the stroke weight of the selected objects when the user changes the value of the panel's stroke weight widget.

- kFlexUIStrokeActionComponentBoss — This boss class supports two interfaces: IActionComponent and IPMPersist.
- kFlexUIStrokePanelWidgetBoss — This boss class inherits from an API panel boss class, and adds an interface to control a pop-up menu on the panel.

## Architecture

The plug-in has a panel, kFlexUIStrokePanelWidgetBoss, which contains an OWLFlashPlayerWidget, kOWLFlashPlayerWidgetBoss. The OWLFlashPlayerWidget is responsible for loading and sending communication to and from the Flash SWF. The panel aggregates a selection observer, FlexUIStrokePanelSelectionObserver, that has been extended to observe selection.

When the selection changes in InDesign, FlexUIStrokePanelSelectionObserver queries for the current stroke weight via the IStrokeAttributeSuite suite. Then, the stroke weight is sent to the SWF, by calling IOWLFlashPlayerController's CallMovieFunction. The SWF is then responsible for displaying the stroke weight in its combo-box component.

When the user selects a new stroke weight in the Flex combo-box component, the SWF uses ExternalInterface to send the selected weight to the FlexUIStrokePanelSelectionObserver's registered callback function, FlexUIStrokeSWFCallback. This function tells the IStrokeAttributeSuite to change the current selection's stroke weight to the one passed in from the SWF.

## Connecting Flex and InDesign

There are two connection points in a plug-in where you can connect to your SWF. Both points are implemented by OWLFlashPlayerController. OWLFlashPlayerController passes along incoming transactions by calling a static method in your plug-in, and it provides a method to send outgoing transactions to your SWF.

There also are two connection points in a SWF where you can connect to your plug-in. Both points are implemented by ExternalInterface. ExternalInterface allows you to define callback methods in your SWF, and it provides a method for calling the methods located in your plug-in.

### Incoming transactions (from SWF to plug-in)

Create a static member function in your plug-in, and call OWLFlashPlayerController's SetAppFunctionCallback() to define the static method as the callback method in your plug-in. Then, from your ActionScript code, use ExternalInterface.call() to call the plug-in's static method.

In C++ class declaration:

```
static PMString MySWFCallback(const PMString& request, void* refPtr);
// note: refPtr is the object who owns the static callback method.
```

In C++, after loading the SWF into the panel:

```
ErrorCode err = playerController->SetAppFunctionCallback (&MySWFCallback, this);
```

In ActionScript:

```
if(ExternalInterface.available) {  
    ExternalInterface.call("MySWFCallback", parameter1, parameterN);  
}
```

### Outgoing transactions (from plug-in to SWF)

In ActionScript, use ExternalInterface to declare your SWF's method as a callback. The first parameter specifies the callback name to use from your plug-in, and the second parameter is a reference to your callback method. Then, from your C++ plug-in, call the SWF's callback by using OWLFlashPlayerController's CallMovieFunction() method.

In ActionScript:

```
public function Init() : void {  
    ExternalInterface.addCallback  
    ("myPlugInCallback", myPlugInCallbackHandler);  
}  
  
public function myPlugInCallbackHandler(parameter:String) : void {  
    doSomething();  
}
```

In C++:

```
PMString request("<invoke name=\"myPlugInCallback\" returntype=\"xml\">");  
request.Append("<arguments>");  
request.Append("<string>" + paramStr + "</string>");  
request.Append("</arguments>");  
request.Append("</invoke>");  
  
InterfacePtr<IOWLFlashPlayerController> playerController  
(flashWidgetView, UseDefaultIID());  
if (playerController) {  
    PMString result;  
    ErrorCode err = playerController->CallMovieFunction(request, result);  
}
```

### XML packets

For both connection points, communication is achieved by sending XML packets back and forth. In your plug-in, this XML packet is a PMString containing XML data. Your plug-in is responsible for creating outgoing XML and parsing incoming XML. In your SWF, ExternalInterface takes care of creating and parsing the XML for you.

- *Request packet* — A request packet is used when calling a SWF method and when the SWF calls your plug-in. A typical request uses an <invoke> tag to specify the method being called, along with an <arguments> tag to specify the arguments to the method. For example:

```
<invoke name="functionName" returnType="xml">
<arguments>
<string>Trevor</string>
<number>31</number>
<true/>
</arguments>
</invoke>
```

- *Result packet* — A result packet is used for sending a plug-in method's result back to the SWF and when the SWF returns a value from one of its methods. A typical result uses an `<object>` tag, along with `<property>` tags defining the member data of that object. For example:

```
<object>
<property id="strokeWeight">
<string>strokeWeightValue</string>
</property>
</object>
```

- *Valid types* — The valid type tags that can be used are as follows:

```
<number>2.5</number>
<string>Trevor</string>
<false/>
<true/>
<null/>
<undefined/>
<date>1137840611674</date>
<class>com.adobe.MyClass</class>
<object>
<property id="x"><string>value10</string></property>
<property id="y"><string>value12</string></property>
...
</object>
<array>
<property id="0"><string>value10</string></property>
<property id="1"><string>value12</string></property>
...
</array>
```

#### Notes:

- The `<date>` type represents the number of milliseconds since Jan 1 1970 GMT. This is the standard representation ECMAScript uses to represent time.
- The `<class>` type is used to represent a class object. It is of type Class in ActionScript.
- The `<property>` values of `<object>` or `<array>` can be any of the above types, including other objects and arrays. This can be used to build nested data structures, but it cannot contain circular references.

## See also

- [IStrokeAttributeSuite](#)
- [IGraphicAttributeSuite](#)
- “Selection Fundamentals” chapter in *Adobe InDesign CS4 Products Programming Guide*

---

# Flash/Flex from ScriptUI

## Introduction and use

- How to implement a ScriptUI panel containing a Flash SWF.
- How to call methods within a Flash SWF from a JavaScript script.
- How to call methods within a JavaScript script from a Flash SWF.
- How to attach a script to document events.

The FlexUIBasicScriptUI sample plug-in shows how to implement FlexUI in InDesign using flashplayer in a ScriptUI palette window. If the palette window is not visible on start-up, it can be shown from the Windows menu by invoking the FlexUIBasicScriptUI item. The palette window contains a flashplayer component. When the palette window is created, the JavaScript script uses the loadMovie method of the flashplayer to load our SWF that was created using Flex.

The FlexUIBasicScriptUI sample plug-in comprises a JavaScript file, FlexUIBasicScriptUI.jsx, and the FlexBuilder 3 components necessary to build the SWF: FlexUIBasicScriptUI.mxml and the Flex project files (.actionScriptProperties, .flexProperties, and .project). The SWF file has already been built for this plug-in; it is located at the top level of the flexuibasicscriptui folder.

To run the sample, copy both FlexUIBasicScriptUI.jsx and FlexUIBasicScriptUI.swf to your Scripts/Startup Scripts folder in your InDesign installation. If the Startup Scripts folder does not already exist, create it.

The SWF contained in the panel has two tabs, Document Info and Add Page.

- The *Document Info* tab displays the document name, number of pages, and the list of paragraph styles for the document, and it has an Update Info button. Use the Update Info button to force an update to the info for the current document. The information is updated automatically for some events, because the script attaches itself to afterNew, afterOpen, afterClose, and afterSave events. When one of these events occurs, the script is notified, and it performs the update. You will notice that the Document Info panel does not always stay current. For example, if you use InDesign's Layout menu to add pages or you select another document, the information does not update. This is because scripting does not provide us with attach points for events like model- or selection-change events. If you use the Update Info button, the information is updated. If you want to have your FlexUI respond to other events (like selection changes or object model changes), you need to implement a C++ plug-in that uses an observer to detect the change. The C++ plug-in can create a panel that hosts

a SWF, and it can communicate with the SWF through the panel's flashPlayer via ExternalInterface. The SDK sample, flexuistroke, demonstrates this technique using a selection observer.

- The Add Page tab contains a text-entry box and an Add Page button. Use the text-entry box to enter the text you want to be displayed on the new page. Click Add Page to add a new page to the current document. The new page contains a page-sized text frame with the text you entered. If no document is open, a new document is created, and the first page of the document contains the text you typed.

To use the Flex project, follow these steps:

- Run Flex Builder 3.
- Right click in the Flex Navigator window and choose Import... > General > Existing Projects into Workspace.
- Click Next.
- Choose "Select root directory" and browse to the flexuibasicscriptui folder.
- Click Finish.

FlexBuilder is not required to compile the MXML into a SWF. Instead, you can install the free Flex3 SDK and use the command-line compiler. The compiler is located in the bin folder of the Flex SDK installation folder. Open a command line or Terminal window, set the current directory to the bin folder, the use the following command line (changing the path to flexuibasicstrokeui.mxml as necessary):

```
mxmlc <SDK>/source/sdksamples/flexuibasicscriptui/FlexUIBasicScriptUI.mxml
```

## Architecture

The JavaScript script (FlexUIBasicScriptUI.jsx) uses ScriptUI to create a palette window containing a flashplayer widget. The flashplayer widget is responsible for loading and communicating with the Flash SWF (FlexUIBasicScriptUI.swf).

The JavaScript script contains two methods that the SWF can call, addPage and getDocInfo. These methods are called from Flex by using the ExternalInterface call method.

The flex ActionScript code has one method that can be called from the JavaScript script, doUpdateDocInfo. This method is called from the JavaScript by using the flashplayer component's invokePlayerFunction method.

## Data types

ExternalInterface serializes and de-serializes common data types, allowing Flex and JavaScript to pass data back and forth. The allowed ActionScript types include String, Number, Array, and Object. An Object contains named properties which also are of the common types. When creating an object with named properties in JavaScript, you must declare the object using new Object(). For details, go to:

[http://livedocs.adobe.com/flex/3/html/help.html?content=passingarguments\\_4.html](http://livedocs.adobe.com/flex/3/html/help.html?content=passingarguments_4.html)

The FlexUIBasicScriptUI sample plug-in uses an object with named properties to represent the InDesign Document info. The object is created in the JavaScript method, `getDocInfo()`, and it contains the following named properties:

```
name: String  
numPages: Number  
paragraphStyles: Array of String
```

## Events

The script attaches itself to `afterNew`, `afterOpen`, `afterClose`, and `afterSave` events. When one of these events occurs, `updateDocInfoEvent()` in the JavaScript gets called. `updateDocInfoEvent()` calls `getDocInfo()`, which creates a new object with the named properties specified above and populates the object with information about the document. `updateDocInfoEvent()` then calls `invokePlayerFunction()` on the `flashplayer` component, passing `doUpdateDocInfo` as the method to call in the SWF and passing the `docInfoObject` as a parameter to the `doUpdateDocInfo` method.

## JavaScript target engine

To implement a ScriptUI in InDesign, the JavaScript needs to remain active while InDesign is running. In InDesign scripting, this is done by using the script as a Startup Script (place the script in the startup scripts folder), and creating a target engine for the script:

```
#targetengine "FlexUIBasicScriptUI"
```

The target engine is declared as an object containing data and methods. All methods and data, except the initialization code in the main body of the script are defined as members of the target engine. The target engine must have a unique name; in the FlexUIBasicScriptUI sample plug-in, it is named `FlexUIBasicScriptUI`.

To define a method in the target engine, we use the following syntax:

```
FlexUIBasicScriptUI.invokeMenuItem = function() { ... }
```

To define data in the target engine, we use the following syntax:

```
FlexUIBasicScriptUI.myPath = "";
```

To call a function of the target engine, we use the following syntax:

```
FlexUIBasicScriptUI.installMenuItem();
```

## Connecting Flex and InDesign ScriptUI

There are two connection points in an InDesign JavaScript script where you can connect to your SWF. Both points are implemented by the `ScriptUI` component, `flashplayer`. The `flashplayer` component allows you to define callback methods in your script, and it provides a method for calling the methods located in your SWF.

There also are two connection points in an SWF where you can connect to your InDesign script. Both points are implemented by `ExternalInterface`. `ExternalInterface` allows you to define callback methods in your SWF, and it provides a method for calling the methods located in your InDesign script.

## Incoming transactions (from SWF to InDesign script)

Create a named property in your flashplayer component, setting both its name and value to the name of the JavaScript method. Then, from your ActionScript code, use ExternalInterface.call() to call the InDesign script's method.

In JavaScript, after loading the SWF into the panel:

```
FlexUIBasicScriptUI.flashPlayerRef.getDocInfo = FlexUIBasicScriptUI.getDocInfo;  
FlexUIBasicScriptUI.getDocInfo = function(myDocument) { ... }
```

In ActionScript:

```
var docInfo:Object = ExternalInterface.call("getDocInfo");
```

## Outgoing transactions (from InDesign script to SWF)

In ActionScript, use ExternalInterface to declare your SWF's method as a callback. The first parameter specifies the callback name to use from your InDesign script, and the second parameter is a reference to your callback method. Then, from your InDesign script, call the SWF callback by using the flashplayer component's invokePlayerFunction() method. In ActionScript:

```
ExternalInterface.addCallback("updateDocInfo", doUpdateDocInfo);  
public function doUpdateDocInfo(docInfo:Object):void { ... }
```

In JavaScript:

```
FlexUIBasicScriptUI.flashPlayerRef.invokePlayerFunction("updateDocInfo",  
docInfoObject);
```

---

## Limitations

- You cannot drag/drop from the Flash user interface to InDesign.
- Flex widgets do not have the same conversion routines and input limiters built-in as InDesign widgets.
- ScriptUI solutions can respond to only a limited number of events, and they cannot implement an observer on the model.