

Installing the data broker in Google Cloud Platform

Cloud Manager

Ben Cammett September 01, 2021

This PDF was generated from https://docs.netapp.com/us-en/occm/task_sync_installing_gcp.html on October 11, 2021. Always check docs.netapp.com for the latest.

Table of Contents

n	stalling the data broker in Google Cloud Platform
	Supported GCP regions
	Networking requirements
	Permissions required to deploy the data broker in GCP
	Permissions required for the service account
	Installing the data broker
	Providing permissions to use buckets in other Google Cloud projects
	Details about the data broker VM instance

Installing the data broker in Google Cloud Platform

When you create a new data broker, choose the GCP Data Broker option to deploy the data broker software on a new virtual machine instance in a VPC. Cloud Sync guides you through the installation process, but the requirements and steps are repeated on this page to help you prepare for installation.

You also have the option to install the data broker on an existing Linux host in the cloud or on your premises. Learn more.

Supported GCP regions

All regions are supported.

Networking requirements

 The data broker needs an outbound internet connection so it can poll the Cloud Sync service for tasks over port 443.

When Cloud Sync deploys the data broker in GCP, it creates a security group that enables the required outbound communication.

If you need to limit outbound connectivity, see the list of endpoints that the data broker contacts.

• NetApp recommends configuring the source, target, and data broker to use a Network Time Protocol (NTP) service. The time difference between the three components should not exceed 5 minutes.

Permissions required to deploy the data broker in GCP

Ensure that the GCP user who deploys the data broker has the following permissions:

```
- compute.networks.list
- compute.regions.list
- deploymentmanager.deployments.create
- deploymentmanager.deployments.delete
- deploymentmanager.operations.get
- iam.serviceAccounts.list
```

Permissions required for the service account

When you deploy the data broker, you need to select a service account that has the following permissions:

- logging.logEntries.create
- resourcemanager.projects.get
- storage.buckets.get
- storage.buckets.list
- storage.objects.*
- iam.serviceAccounts.signJwt



The "iam.serviceAccounts.signJwt" permission is required only if you're planning to set up the data broker to use an external HashiCorp vault.

Installing the data broker

You can install a data broker in GCP when you create a sync relationship.


Steps

- Click Create New Sync.
- 2. On the **Define Sync Relationship** page, choose a source and target and click **Continue**.

Complete the steps until you reach the **Data Broker** page.

3. On the **Select a Data Broker** page, click the **Create Data Broker** and then select **Google Cloud Platform**.

If you already have a data broker, you'll need to click the + icon first.



- 4. Enter a name for the data broker and click **Continue**.
- 5. If you're prompted, log in with your Google account.

The form is owned and hosted by Google. Your credentials are not provided to NetApp.

6. Select a project and service account and then choose a location for the data broker, including whether you want to enable or disable a public IP address.

If you don't enable a public IP address, then you'll need to define a proxy server in the next step.



7. Specify a proxy configuration, if a proxy is required for internet access in the VPC.

If a proxy is required for internet access, then the proxy must be in Google Cloud and use the same service account as the data broker.

8. Once the data broker is available, click Continue in Cloud Sync.

The instance takes approximately 5 to 10 minutes to deploy. You can monitor the progress from the Cloud Sync service, which automatically refreshes when the instance is available.

9. Complete the pages in the wizard to create the new sync relationship.

Result

You've deployed a data broker in GCP and created a new sync relationship. You can use this data broker with additional sync relationships.

Providing permissions to use buckets in other Google Cloud projects

When you create a sync relationship and choose Google Cloud Storage as the source or target, Cloud Sync enables you to choose from the buckets that the data broker's service account has permissions to use. By default, this includes the buckets that are in the *same* project as the data broker service account. But you can choose buckets from *other* projects if you provide the required permissions.

Steps

- 1. Open the Google Cloud Platform console and load the Cloud Storage service.
- 2. Click the name of the bucket that you'd like to use as a source or target in a sync relationship.
- 3. Click Permissions.
- 4. Click Add.
- 5. Enter the name of the data broker's service account.
- 6. Select a role that provides the same permissions as shown above.
- 7. Click Save.

Result

When you set up a sync relationship, you can now choose that bucket as the source or target in the sync relationship.

Details about the data broker VM instance

Cloud Sync creates a data broker in Google Cloud using the following configuration.

Machine type

n1-standard-4

vCPUs

4

RAM

15 GB

Operating system

Red Hat Enterprise Linux 7.7

Disk size and type

20 GB HDD pd-standard

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.