

Getting started with Cloud Data Sense for Amazon S3

Cloud Manager

Tom Onacki, Ben Cammett August 16, 2021

This PDF was generated from https://docs.netapp.com/us-en/occm/task_scanning_s3.html on October 11, 2021. Always check docs.netapp.com for the latest.

Table of Contents

Getting started with Cloud Data Sense for Amazon S3	. 1
Quick start	. 1
Reviewing S3 prerequisites	. 1
Deploying the Cloud Data Sense instance	. 2
Activating Data Sense on your S3 working environment	. 3
Enabling and disabling compliance scans on S3 buckets	. 4
Scanning buckets from additional AWS accounts	. 5

Getting started with Cloud Data Sense for Amazon S3

Cloud Data Sense can scan your Amazon S3 buckets to identify the personal and sensitive data that resides in S3 object storage. Cloud Data Sense can scan any bucket in the account, regardless if it was created for a NetApp solution.

Quick start

Get started quickly by following these steps, or scroll down to the remaining sections for full details.



Set up the S3 requirements in your cloud environment

Ensure that your cloud environment can meet the requirements for Cloud Data Sense, including preparing an IAM role and setting up connectivity from Data Sense to S3. See the complete list.



Deploy the Cloud Data Sense instance

Deploy Cloud Data Sense if there isn't already an instance deployed.



Activate Data Sense on your S3 working environment

Select the Amazon S3 working environment, click **Enable**, and select an IAM role that includes the required permissions.



Select the buckets to scan

Select the buckets that you'd like to scan and Cloud Data Sense will start scanning them.

Reviewing S3 prerequisites

The following requirements are specific to scanning S3 buckets.

Set up an IAM role for the Cloud Data Sense instance

Cloud Data Sense needs permissions to connect to the S3 buckets in your account and to scan them. Set up an IAM role that includes the permissions listed below. Cloud Manager prompts you to select an IAM role when you enable Data Sense on the Amazon S3 working environment.

```
{
  "Version": "2012-10-17",
  "Statement": [
      {
          "Effect": "Allow",
          "Action": [
              "s3:Get*",
              "s3:List*",
              "s3:PutObject",
          ],
          "Resource": "*"
      },
          "Effect": "Allow",
          "Action": [
              "iam:GetPolicyVersion",
              "iam:GetPolicy",
              "iam:ListAttachedRolePolicies"
          ],
          "Resource": [
               "arn:aws:iam::*:policy/*",
              "arn:aws:iam::*:role/*"
          ]
      }
 1
}
```

Provide connectivity from Cloud Data Sense to Amazon S3

Cloud Data Sense needs a connection to Amazon S3. The best way to provide that connection is through a VPC Endpoint to the S3 service. For instructions, see AWS Documentation: Creating a Gateway Endpoint.

When you create the VPC Endpoint, be sure to select the region, VPC, and route table that corresponds to the Cloud Data Sense instance. You must also modify the security group to add an outbound HTTPS rule that enables traffic to the S3 endpoint. Otherwise, Data Sense can't connect to the S3 service.

If you experience any issues, see AWS Support Knowledge Center: Why can't I connect to an S3 bucket using a gateway VPC endpoint?

An alternative is to provide the connection by using a NAT Gateway.



You can't use a proxy to get to S3 over the internet.

Deploying the Cloud Data Sense instance

Deploy Cloud Data Sense in Cloud Manager if there isn't already an instance deployed.

You need to deploy the instance in an AWS Connector so that Cloud Manager automatically discovers the S3

buckets in this AWS account and displays them in an Amazon S3 working environment.

Note: Deploying Cloud Data Sense in an on-premises location is not currently supported when scanning S3 buckets.

Activating Data Sense on your S3 working environment


Enable Cloud Data Sense on Amazon S3 after you verify the prerequisites.

Steps

- 1. At the top of Cloud Manager, click Canvas.
- 2. Select the Amazon S3 working environment.



3. In the Data Sense pane on the right, click **Enable**.



4. When prompted, assign an IAM role to the Cloud Data Sense instance that has the required permissions.



5. Click Enable.



You can also enable compliance scans for a working environment from the Configuration page by clicking the button and selecting **Activate Data Sense**.

Result

Cloud Manager assigns the IAM role to the instance.

Enabling and disabling compliance scans on S3 buckets

After Cloud Manager enables Cloud Data Sense on Amazon S3, the next step is to configure the buckets that you want to scan.

When Cloud Manager is running in the AWS account that has the S3 buckets you want to scan, it discovers those buckets and displays them in an Amazon S3 working environment.


Cloud Data Sense can also scan S3 buckets that are in different AWS accounts.

Steps

- 1. Select the Amazon S3 working environment.
- 2. In the pane on the right, click Configure Buckets.



3. Enable mapping-only scans, or mapping and classification scans, on your buckets.



То:	Do this:
Enable mapping-only scans on a bucket	Click Map
Enable full scans on a bucket	Click Map & Classify
Disable scanning on a bucket	Click Off

Result

Cloud Data Sense starts scanning the S3 buckets that you enabled. If there are any errors, they'll appear in the Status column, alongside the required action to fix the error.

Scanning buckets from additional AWS accounts

You can scan S3 buckets that are under a different AWS account by assigning a role from that account to access the existing Cloud Data Sense instance.

Steps

1. Go to the target AWS account where you want to scan S3 buckets and create an IAM role by selecting **Another AWS account**.










Select type of trusted entity










Allows entities in other accounts to perform actions in this account. Learn more

Specify accounts that can use this role



Be sure to do the following:

- Enter the ID of the account where the Cloud Data Sense instance resides.
- Change the Maximum CLI/API session duration from 1 hour to 12 hours and save that change.
- · Attach the Cloud Data Sense IAM policy. Make sure it has the required permissions.


```
"Version": "2012-10-17",
"Statement": [
        "Effect": "Allow",
        "Action": [
             "s3:Get*",
             "s3:List*",
             "s3:PutObject",
        ],
        "Resource": "*"
    },
]
```

- 2. Go to the source AWS account where the Data Sense instance resides and select the IAM role that is attached to the instance.
 - a. Change the Maximum CLI/API session duration from 1 hour to 12 hours and save that change.
 - b. Click Attach policies and then click Create policy.
 - c. Create a policy that includes the "sts:AssumeRole" action and specify the ARN of the role that you created in the target account.

```
"Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": "sts:AssumeRole",
            "Resource": "arn:aws:iam::<ADDITIONAL-ACCOUNT-
ID>:role/<ADDITIONAL ROLE NAME>"
        },
            "Effect": "Allow",
            "Action": [
                "iam:GetPolicyVersion",
                "iam:GetPolicy",
                "iam:ListAttachedRolePolicies"
            1,
            "Resource": [
                "arn:aws:iam::*:policy/*",
                "arn:aws:iam::*:role/*"
            1
    ]
}
```

The Cloud Data Sense instance profile account now has access to the additional AWS account.

Go to the Amazon S3 Configuration page and the new AWS account is displayed. Note that it can take a
few minutes for Cloud Data Sense to sync the new account's working environment and show this
information.



4. Click Activate Data Sense & Select Buckets and select the buckets you want to scan.

Result

Cloud Data Sense starts scanning the new S3 buckets that you enabled.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.