



Introduction to Networks

Cisco Networking Academy®
Mind Wide Open®





- 9.0 Introduction
- 9.1 Subnetting an IPv4 Network
- 9.2 Addressing Schemes
- 9.3 Design Considerations for IPv6
- 9.4 Summary

Chapter 9: Objectives

Upon completion of this chapter, you will be able to:

- Explain why routing is necessary for hosts on different networks to communicate.
- Describe IP as a communication protocol used to identify a single device on a network.
- Given a network and a subnet mask, calculate the number of host addresses available.
- Calculate the necessary subnet mask in order to accommodate the requirements of a network.
- Describe the benefits of variable length subnet masking (VLSM).
- Explain how IPv6 address assignments are implemented in a business network.











Reasons for Subnetting

Subnetting is the process of segmenting a network into multiple smaller network spaces called subnetworks or subnets.

- Large networks must be segmented into smaller subnetworks, creating smaller groups of devices and services to:
 - Control traffic by containing broadcast traffic within each subnetwork.
 - Reduce overall network traffic and improve network performance.

Communication Between Subnets


- A router is necessary for devices on different networks and subnets to communicate.
- Each router interface must have an IPv4 host address that belongs to the network or subnet that the router interface is connected.
- Devices on a network and subnet use the router interface attached to their LAN as their default gateway.

Cisco Confidential

IP Subnetting is FUNdamental The Plan

Planning the Network






Planning requires decisions on each subnet in terms of size, the number of hosts per subnet, and how host addresses will be assigned.




Subnetting an IPv4 Network Basic Subnetting

- Borrowing Bits to Create Subnets
- Borrowing 1 bit $2^1 = 2$ subnets






Subnetting an IPv4 Network Subnets in Use



Subnet 0

Network 192.168.1.0-127/25




Subnet 1

Network 192.168.1.128-255/25

Network	Address					
110-120-1	11001000	170	2	COLUMN TO A STATE OF THE PARTY	THE PLANTS	
192.	168.	1.	0	900	9999	= 192.168.1.0
First Hos	st Address					
192.	168.	1.	0	000	0001	= 192.168.1.1
Last Hos	t Address					
192.	168.	1.	0	111	1110	= 192.168.1.126
Broadca	st Address					
192.	168.	1.	0	111	1111	= 192.168.1.127
	Address	s Rang	e f	or 192	2.168.1.	128/25 Subnet
Network	Address	s Rang	e f	or 192	2.168.1.	100.100.7.10
Network					0000	128/25 Subnet
192.	Address	1.				128/25 Subnet
192.	Address 168. st Address	1.	1	000		128/25 Subnet
192. First Hos	Address 168. st Address	1.	1	000	0000	128/25 Subnet = 192.168.1.128
192. First Hos	Address 168. st Address 168.	1.	1	000	0000	128/25 Subnet = 192.168.1.128 = 192.168.1.129
192. First Hos 192. Last Hos 192.	Address 168. st Address 168.	1.	1	000	0000	128/25 Subnet = 192.168.1.128 = 192.168.1.129


Subnetting Formulas





Creating 4 Subnets

Borrowing 2 bits to create 4 subnets. $2^2 = 4$ subnets





Creating Eight Subnets

Borrowing 3 bits to Create 8 Subnets. $2^3 = 8$ subnets

	Network	192.	168.	1.	000	0 0000	192.168.1.0
Net 0	First	192.	168.	1.	000	0 0001	192.168.1.1
	Last	192.	168.	1.	000	1 1110	192.168.1.30
	Broadcast	192.	168.	1.	000	1 1111	192.168.1.31
	Network	192.	168.	1.	001	0 0000	192.168.1.32
Net 1	First	192.	168.	1.	001	0 0001	192.168.1.33
	Last	192.	168.	1.	001	1 1110	192.168.1.62
	Broadcast	192.	168.	1.	001	1 1111	192.168.1.63
	Network	192.	168.	1.	010	0 0000	192.168.1.64
Net 2	First	192.	168.	1.	010	0 0001	192.168.1.65
333335	Last	192.	168.	1.	010	1 1110	192.168.1.94
	Broadcast	192.	168.	1.	010	1 1111	192.168.1.95
	Network	192.	168.	1.	010	0 0000	192.168.1.96
Net 3	First	192.	168.	1.	010	0 0001	192.168.1.97
	Last	192.	168.	1.	010	1 1110	192.168.1.126
	Broadcast	192.	168.	1.	010	1 1111	192.168.1.127






Creating Eight Subnets (Cont.)

	Network	192.	168.	1.	100	0 0000	192.168.1.128
Net 4	Fist	192.	168.	1.	100	0 0001	192.168.1.129
W. = 10.00	Last	192.	168.	1.	100	1 1110	192.168.1.158
	Broadcast	192.	168.	1.	100	1 1111	192.168.1.159
	Network	192.	168.	1.	101	0 0000	192.168.1.160
Net 5	Fist	192.	168.	1.	101	0 0001	192.168.1.161
	Last	192.	168.	1.	101	1 1110	192.168.1.190
	Broadcast	192.	168.	1.	101	1 1111	192.168.1.191
	Network	192.	168.	1.	110	0 0000	192.168.1.192
Net 6	Fist	192.	168.	1.	110	0 0001	192.168.1.193
	Last	192.	168.	1.	110	1 1110	192.168.1.222
	Broadcast	192.	168.	1.	110	1 1111	192.168.1.223
	Network	192.	168.	1.	111	0 0000	192.168.1.224
Net 7	Fist	192.	168.	1.	111	0 0001	192.168.1.225
	Last	192.	168.	1.	111	1 1110	192.168.1.254
	Broadcast	192.	168.	1.	111	1 1111	192.168.1.255

Creating Eight Subnets (Cont.)





Determining the Subnet Mask

Subnetting Based on Host Requirements

Two considerations when planning subnets:

- Number of subnets required
- Number of host addresses required


Formula to determine number of usable hosts: 2ⁿ-2

- 2ⁿ (where *n* is the number of remaining host bits) is used to calculate the number of hosts.
- -2 (The subnetwork ID and broadcast address cannot be used on each subnet.)

Subnetting Network-Based Requirements

Calculate the number of subnets:


- 2ⁿ (where n is the number of bits borrowed)
- Subnet needed for each department.



Determining the Subnet Mask

Subnetting To Meet Network Requirements

- Balance the required number of subnets and hosts for the largest subnet.
- Design the addressing scheme to accommodate the maximum number of hosts for each subnet.
- Allow for growth in each subnet.






Subnetting To Meet Network Requirements

```
Subnets and Addresses
   10101100.00010000.000000000.00000000 172.16.0.0/22
   10101100.00010000.000000000.00000000 172.16.0.0/26
   10101100.00010000.000000000.01000000 172.16.0.64/26
   10101100.00010000.000000000.10000000 172.16.0.128/26
   10101100.00010000.000000000.11000000 172.16.0.192/26
   10101100.00010000.000000001.00000000 172.16.1.0/26
   10101100.00010000.000000001.01000000 172.16.1.64/26
   10101100.00010000.000000001.10000000 172.16.1.128/26
                    Nets 7 - 14 not shown
15 10101100.00010000.000000011.10000000 172.16.3.128/26
  10101100.00010000.00000011.11000000 172.16.3.192/26
                         2^4 = 16
                                  2^{6}-2=62
                         subnets
                                   Hosts per
                                   subnet
```


Benefits of Variable Length Subnet Masking Traditional Subnetting Wastes Addresses

- Traditional subnetting Uses the same number of addresses is allocated for each subnet.
- Subnets that require fewer addresses have unused (wasted) addresses; for example, WAN links only need two addresses.




Benefits of Variable Length Subnet Masking Variable Length Subnet Masks (VLSM)

- The variable-length subnet mask (VLSM) or subnetting a subnet provides more efficient use of addresses.
- VLSM allows a network space to be divided in unequal parts.
- Subnet mask varies, depending on how many bits have been borrowed for a particular subnet.
- Network is first subnetted, and then the subnets are resubnetted.




Benefits of Variable Length Subnet Masking Basic VLSM





- Using VLSM subnets, the LAN and WAN segments in example below can be addressed with minimum waste.
- Each LANs will be assigned a subnet with /27 mask.
- Each WAN link will be assigned a subnet with /30 mask.





VLSM Subnetting of 192.168.20.0 /24

	/27 Network	Hosts
Bldg A	.0	.130
Bldg B	.32	.3362
Bldg C	.64	.6594
Bldg D	.96	.97126
Unused	.128	.129158
Unused	.160	.161190
Unused	.192	.193222
	.224	.225254

	/30 Network	Hosts
WAN R1-R2	.224	.225226
WAN R2-R3	.228	.229230
WAN R3-R4	.232	.233234
Unused	.236	.237238
Unused	.240	.241242
Unused	.244	.245246
Unused	.248	.249250
Unused	.252	.253254



9.2 Addressing Schemes







Planning to Address the Network

Allocation of network addresses should be planned and documented for the purposes of:

- Preventing duplication of addresses
- Providing and controlling access
- Monitoring security and performance

Client addresses – Usually dynamically assigned using the Dynamic Host Configuration Protocol (DHCP).

Sample Network Addressing Plan

Use	First	Last
Host Devices	.1	.229
Servers	.230	.239
Printers	.240	.249
Intermediary Devices	.250	.253
Gateway (router LAN interface)	.254	




9.3 Design Considerations for IPv6






Subnetting an IPv6 Network Subnetting Using the Subnet ID

An IPv6 Network Space is subnetted to support hierarchical, logical design of the network











Subnetting into the Interface ID

IPv6 bits can be borrowed from the interface ID to create additional IPv6 subnets.





9.3 Summary







Chapter 9: Summary

In this chapter, you learned that:

- Subnetting is the process of segmenting a network, by dividing it into multiple smaller network spaces.
- Subnetting a subnet, or using VLSM, was designed to avoid wasting addresses.
- IPv6 address space is subnetted to support the hierarchical, logical design of the network.
- Size, location, use, and access requirements are all considerations in the address planning process.
- IP networks must be tested to verify connectivity and operational performance.

Cisco | Networking Academy® | Mind Wide Open®