# lib3mf

Release v2.3.1

**3MF Consortium** 

# **CONTENTS**

1	API documentation 3						
	1.1	C++-language bindings	3				
		1.1.1 Minimal Example Project	4				
		1.1.2 General Information	6				
		1.1.3 API-Classes	17				
	1.2	C-language bindings	62				
	1.3 Python-language bindings						
	1.4	Pascal-language bindings	62				
	1.5	C#-language bindings	62				
	1.6	Golang-language bindings	62				
	1.7	NodeJS-language bindings	62				
2	Obtaining lib3mf						
3	Using lib3mf						
4	4 Meta Information						
5	5 Indices and tables						
In	ndex						

Welcome! This is the documentation for lib3mf v2.3.1.

lib3mf is an implementation of the 3D Manufacturing Format file standard.

It provides 3MF reading and writing capabilities, as well as conversion and validation tools for input and output data. lib3mf runs on Windows, Linux and MacOS and offers a clean and easy-to-use API in various programming languages to speed up the development and keep integration costs at a minimum.

As 3MF shall become an universal 3D Printing standard, its quick adoption is very important. This library shall lower all barriers of adoption to any possible user, let it be software providers, hardware providers, service providers or middleware tools.

CONTENTS 1

2 CONTENTS

**CHAPTER** 

ONE

# **API DOCUMENTATION**

- C++
- C
- Python
- Pascal
- C#
- Golang
- NodeJS

# 1.1 C++-language bindings

This space describes the usage of lib3mf in a C++ host application.

The C++-language bindings come in two different flavors:

Cpp

CppDynamic

If you include the header Cpp/lib3mf\_implicit.hpp, lib3mf will be loaded dynamically during *load-time* of your host application through your operating system's mechanism for loading libraries.

```
Lib3MF::PWrapper wrapper = CWrapper::loadLibrary();
```

The shared library file lib3mf.\*. needs to reside in a path that your operating systems checks when loading libraries.

If you include the header CppDynamic/lib3mf\_dynamic.hpp, Lib3MF will be loaded dynamically during *run-time* of your host application through an explicit call to

Linux

Mac OSX

Windows

```
Lib3MF::PWrapper wrapper = Lib3MF::CWrapper::loadLibrary("LibraryLocation/lib3mf.so");
```

```
Lib3MF::PWrapper wrapper = Lib3MF::CWrapper::loadLibrary("LibraryLocation/lib3mf.dylib");
```

```
Lib3MF::PWrapper wrapper = Lib3MF::CWrapper::loadLibrary("LibraryLocation/lib3mf.dll");
```

i.e. you need to explicitly provide the location of the shared library file lib3mf.\*.

The Lib3MF::PWrapper object provides access to all functionality within lib3mf.

Both flavors of the C++-bindings are header-only which makes it extremly easy to include them into existing projects:

# 1.1.1 Minimal Example Project

Minimal application code:

Cpp

CppDynamic

```
#include <iostream>
#include "lib3mf_implicit.hpp"
int main()
  try
    auto wrapper = Lib3MF::CWrapper::loadLibrary();
    Lib3MF_uint32 nMajor, nMinor, nMicro;
    wrapper->GetLibraryVersion(nMajor, nMinor, nMicro);
    std::cout << "Lib3MF.Version = " << nMajor << "." << nMinor << "." << nMicro;</pre>
    std::string sPreReleaseInfo;
    if (wrapper->GetPrereleaseInformation(sPreReleaseInfo)) {
      std::cout << "-" << sPreReleaseInfo;</pre>
    }
    std::string sBuildInfo;
    if (wrapper->GetBuildInformation(sBuildInfo)) {
      std::cout << "+" << sBuildInfo;</pre>
    std::cout << std::endl;</pre>
  catch (std::exception &e)
    std::cout << e.what() << std::endl;</pre>
    return 1;
  }
  return 0;
```

(continues on next page)

(continued from previous page)

```
auto wrapper = Lib3MF::CWrapper::loadLibrary(libpath + "/lib3mf."); // TODO: add_
→correct suffix of the library
   Lib3MF_uint32 nMajor, nMinor, nMicro;
   wrapper->GetLibraryVersion(nMajor, nMinor, nMicro);
   std::cout << "Lib3MF.Version = " << nMajor << "." << nMinor << "." << nMicro;</pre>
   std::string sPreReleaseInfo;
   if (wrapper->GetPrereleaseInformation(sPreReleaseInfo)) {
     std::cout << "-" << sPreReleaseInfo;</pre>
   }
   std::string sBuildInfo;
   if (wrapper->GetBuildInformation(sBuildInfo)) {
     std::cout << "+" << sBuildInfo;</pre>
   }
   std::cout << std::endl;</pre>
 catch (std::exception &e)
   std::cout << e.what() << std::endl;</pre>
   return 1;
 }
 return 0;
```

CMakeLists.txt for minimal project:

Cpp

CppDynamic

The examples in the Cpp/CppDynamic-folders of the binary SDK follow exactly this pattern.

The remainder of this space is an in-depth API-reference for the functionality of lib3mf.

## 1.1.2 General Information

## The wrapper class CWrapper

## class Lib3MF::CWrapper

All types of the 3MF Library reside in the namespace Lib3MF and all functionality of the 3MF Library resides in Lib3MF::CWrapper.

A suitable way to use Lib3MF::CWrapper is as a singleton.

void **GetLibraryVersion**(*Lib3MF\_uint32* &nMajor, *Lib3MF\_uint32* &nMinor, *Lib3MF\_uint32* &nMicro) retrieves the binary version of this library.

#### **Parameters**

- nMajor returns the major version of this library
- nMinor returns the minor version of this library
- nMicro returns the micro version of this library

## bool **GetPrereleaseInformation**(std::string &sPrereleaseInfo)

retrieves prerelease information of this library.

#### Returns

Does the library provide prerelease version?

# **Parameters**

**sPrereleaseInfo** – retrieves prerelease information of this library.

bool **GetBuildInformation**(std::string &sBuildInformation)

retrieves build information of this library.

#### Returns

Does the library provide build version?

## **Parameters**

**sBuildInformation** – retrieves build information of this library.

void **GetSpecificationVersion** (const std::string &sSpecificationURL, bool &bIsSupported, *Lib3MF\_uint32* &nMajor, *Lib3MF\_uint32* &nMinor, *Lib3MF\_uint32* &nMicro)

retrieves whether a specification is supported, and if so, which version.

#### **Parameters**

- sSpecificationURL URL of extension to check
- **bIsSupported** returns whether this specification is supported
- nMajor returns the major version of the extension (if IsSupported)
- **nMinor** returns the minor version of the extension (if IsSupported)
- nMicro returns the micro version of the extension (if IsSupported)

#### PModel CreateModel()

creates an empty model instance.

#### Returns

returns an empty model instance

void Release(CBase \*pInstance)

releases shared ownership of an object instance

#### **Parameters**

pInstance – the object instance to release

void Acquire(CBase \*pInstance)

acquires shared ownership of an object instance

#### **Parameters**

pInstance – the object instance to acquire

void SetJournal(const std::string &sJournalPath)

Sets the journal file path

#### **Parameters**

**sJournalPath** – File name of the journal file

bool **GetLastError**(*CBase* \*pInstance, std::string &sLastErrorString)

Retrieves the last error string of an instance

#### **Parameters**

- pInstance Object where the error occured.
- **sLastErrorString** Last Error String

## Returns

Returns if the instance has a last error.

void **RetrieveProgressMessage** (const eProgressIdentifier eTheProgressIdentifier, std::string &sProgressMessage)

Return an English text for a progress identifier.|Note: this is the only function you can call from your callback function.

### **Parameters**

- eTheProgressIdentifier the progress identifier that is passed to the callback function
- **sProgressMessage** English text for the progress identifier

sColor RGBAToColor (const Lib3MF\_uint8 nRed, const Lib3MF\_uint8 nGreen, const Lib3MF\_uint8 nBlue, const Lib3MF\_uint8 nAlpha)

Creates a Color from uint8 RGBA values

### **Parameters**

- **nRed** Red value of color (0-255)
- nGreen Green value of color (0-255)
- **nBlue** Blue value of color (0-255)
- nAlpha Alpha value of color (0-255)

#### **Returns**

Assembled color

sColor FloatRGBAToColor (const Lib3MF\_single fRed, const Lib3MF\_single fGreen, const Lib3MF\_single fBlue, const Lib3MF\_single fAlpha)

Creates a Color from uint8 RGBA values

#### **Parameters**

- **fRed** Red value of color (0-1)
- **fGreen** Green value of color (0-1)
- **fBlue** Blue value of color (0-1)
- **fAlpha** Alpha value of color (0-1)

#### Returns

Assembled color

void **ColorToRGBA**(const *sColor* &TheColor, *Lib3MF\_uint8* &nRed, *Lib3MF\_uint8* &nGreen, *Lib3MF\_uint8* &nBlue, *Lib3MF\_uint8* &nAlpha)

Calculates uint8-RGBA-values from a Color

#### **Parameters**

- TheColor Color to handle
- **nRed** Red value of color (0-255)
- nGreen Green value of color (0-255)
- **nBlue** Blue value of color (0-255)
- nAlpha Alpha value of color (0-255)

void ColorToFloatRGBA(const sColor & TheColor, Lib3MF\_single & fRed, Lib3MF\_single & fGreen, Lib3MF\_single & fBlue, Lib3MF\_single & fAlpha)

Calculates float-RGBA-values from a Color

#### **Parameters**

- TheColor Color to handle
- **fRed** Red value of color (0-1)
- **fGreen** Green value of color (0-1)
- **fBlue** Blue value of color (0-1)
- **fAlpha** Alpha value of color (0-1)

#### sTransform GetIdentityTransform()

Creates an identity transform

## Returns

Transformation matrix.

sTransform GetUniformScaleTransform(const  $Lib3MF\_single$  fFactor)

Creates a uniform scale transform

#### **Parameters**

**fFactor** – Factor in X, Y and Z

# Returns

Transformation matrix.

# sTransform GetScaleTransform(const Lib3MF\_single fFactorX, const Lib3MF\_single fFactorY, const Lib3MF single fFactorZ)

Creates a scale transform

#### **Parameters**

- $\mathbf{fFactorX}$  Factor in X
- **fFactorY** Factor in Y
- **fFactorZ** Factor in Z.

#### Returns

Transformation matrix.

sTransform GetTranslationTransform(const Lib3MF\_single fVectorX, const Lib3MF\_single fVectorY, const Lib3MF\_single fVectorZ)

Creates an translation transform

#### **Parameters**

- fVectorX Translation in X
- fVectorY Translation in Y
- **fVectorZ** Translation in Z

#### Returns

Transformation matrix.

typedef std::shared\_ptr<CWrapper> Lib3MF::PWrapper

# Types used in the 3MF Library

## Simple types

```
typedef uint8_t Lib3MF_uint8

typedef uint16_t Lib3MF_uint16

typedef uint32_t Lib3MF_uint32

typedef uint64_t Lib3MF_uint64

typedef int8_t Lib3MF_int8

typedef int16_t Lib3MF_int16

typedef int32_t Lib3MF_int32

typedef int64_t Lib3MF_int64

typedef float Lib3MF_single

typedef double Lib3MF_double

using Lib3MF_pvoid = void*

using Lib3MFResult = Lib3MF_int32
```

## **Enumerations**

```
enum class ePropertyType : Lib3MF_int32
    enumerator NoPropertyType = 0
    enumerator BaseMaterial = 1
    enumerator TexCoord = 2
    enumerator Colors = 3
    enumerator Composite = 4
    enumerator Multi = 5
enum class eSlicesMeshResolution: Lib3MF_int32
    enumerator Fullres = 0
    enumerator Lowres = 1
enum class eModelUnit: Lib3MF_int32
    enumerator MicroMeter = 0
    enumerator MilliMeter = 1
    enumerator CentiMeter = 2
    enumerator Inch = 3
    enumerator Foot = 4
    enumerator Meter = 5
enum class e0bjectType : Lib3MF_int32
    enumerator Other = 0
    enumerator Model = 1
    enumerator Support = 2
    enumerator SolidSupport = 3
enum class eTextureType : Lib3MF_int32
    enumerator Unknown = 0
    enumerator PNG = 1
    enumerator JPEG = 2
enum class eTextureTileStyle: Lib3MF_int32
    enumerator \mathbf{Wrap} = 0
    enumerator Mirror = 1
```

```
enumerator Clamp = 2
        enumerator NoTileStyle = 3
    enum class eTextureFilter: Lib3MF_int32
        enumerator Auto = 0
        enumerator Linear = 1
        enumerator Nearest = 2
    enum class eBeamLatticeCapMode: Lib3MF_int32
        enumerator Sphere = 0
        enumerator HemiSphere = 1
        enumerator Butt = 2
    enum class eBeamLatticeClipMode: Lib3MF_int32
        enumerator NoClipMode = 0
        enumerator Inside = 1
        enumerator Outside = 2
enum class eBeamLatticeBallMode: Lib3MF_int32
        enumerator None = 0
        enumerator Mixed = 1
        enumerator \mathbf{A11} = 2
    enum class eProgressIdentifier: Lib3MF_int32
        enumerator QUERYCANCELED = 0
        enumerator DONE = 1
        enumerator CLEANUP = 2
        enumerator READSTREAM = 3
        enumerator EXTRACTOPCPACKAGE = 4
        enumerator READNONROOTMODELS = 5
        enumerator READROOTMODEL = 6
        enumerator READRESOURCES = 7
        enumerator READMESH = 8
        enumerator READSLICES = 9
        enumerator READBUILD = 10
        enumerator READCUSTOMATTACHMENT = 11
```

```
enumerator READTEXTURETACHMENTS = 12
   enumerator CREATEOPCPACKAGE = 13
   enumerator WRITEMODELSTOSTREAM = 14
   enumerator WRITEROOTMODEL = 15
   enumerator WRITENONROOTMODELS = 16
   enumerator WRITEATTACHMENTS = 17
   enumerator WRITECONTENTTYPES = 18
   enumerator WRITENOBJECTS = 19
   enumerator WRITENODES = 20
   enumerator WRITETRIANGLES = 21
   enumerator WRITESLICES = 22
   enumerator WRITEKEYSTORE = 23
enum class eBlendMethod : Lib3MF_int32
   enumerator NoBlendMethod = 0
   enumerator \mathbf{Mix} = 1
   enumerator Multiply = 2
enum class eEncryptionAlgorithm: Lib3MF_int32
   enumerator AES256\_GCM = 1
enum class eWrappingAlgorithm: Lib3MF_int32
   enumerator RSA\_OAEP = 0
enum class eMgfAlgorithm: Lib3MF_int32
   enumerator MGF1\_SHA1 = 160
   enumerator MGF1\_SHA224 = 224
   enumerator MGF1\_SHA256 = 256
   enumerator MGF1\_SHA384 = 384
   enumerator MGF1\_SHA512 = 512
enum class eDigestMethod: Lib3MF_int32
   enumerator SHA1 = 160
   enumerator SHA256 = 256
enum class eCompression : Lib3MF_int32
   enumerator NoCompression = 0
   enumerator Deflate = 1
```

## **Structs**

All structs are defined as packed, i.e. with the

```
#pragma pack (1)
struct sTriangle
    Lib3MF_uint32 m_Indices[3]
struct sTriangleProperties
    Lib3MF_uint32 m_ResourceID
    Lib3MF_uint32 m_PropertyIDs[3]
struct sPosition
    Lib3MF_single m_Coordinates[3]
struct sPosition2D
    Lib3MF_single m_Coordinates[2]
struct sCompositeConstituent
    Lib3MF_uint32 m_PropertyID
    Lib3MF_double m_MixingRatio
struct sMultiPropertyLayer
    Lib3MF uint32 m_ResourceID
    eBlendMethod \ m\_TheBlendMethod
struct sTex2Coord
    Lib3MF\_double\ \mathbf{m\_U}
    Lib3MF_double m_V
struct sTransform
    Lib3MF_single m_Fields[4][3]
struct sBox
    Lib3MF_single m_MinCoordinate[3]
    Lib3MF_single m_MaxCoordinate[3]
struct sColor
    Lib3MF_uint8 m_Red
    Lib3MF_uint8 m_Green
    Lib3MF_uint8 m_Blue
```

```
Lib3MF_uint8 m_Alpha

struct sBeam

Lib3MF_uint32 m_Indices[2]

Lib3MF_double m_Radii[2]

eBeamLatticeCapMode m_CapModes[2]

struct sBall

Lib3MF_uint32 m_Index

Lib3MF_double m_Radius
```

# **Function types**

```
using ProgressCallback = void (*)(bool*, Lib3MF_double, Lib3MF::eProgressIdentifier, Lib3MF_pvoid)
```

A callback function

#### Return

Returns whether the calculation should be aborted

## Param dProgressValue

The value of the progress function: values in the interval [0,1] are progress; < mean no progress update

## Param eProgressIdentifier

An identifier of progress

## Param pUserData

Userdata that is passed to the callback function

```
using WriteCallback = void (*)(Lib3MF_uint64, Lib3MF_uint64, Lib3MF_pvoid)
```

Callback to call for writing a data chunk

## Param nByteData

Pointer to the data to be written

# Param nNumBytes

Number of bytes to write

## Param pUserData

Userdata that is passed to the callback function

```
using ReadCallback = void (*)(Lib3MF_uint64, Lib3MF_uint64, Lib3MF_pvoid)
```

Callback to call for reading a data chunk

# Param nByteData

Pointer to a buffer to read data into

#### Param nNumBytes

Number of bytes to read

## Param pUserData

Userdata that is passed to the callback function

## using **SeekCallback** = void (\*)(*Lib3MF\_uint64*, *Lib3MF\_pvoid*)

Callback to call for seeking in the stream

## Param nPosition

Position in the stream to move to

## Param pUserData

Userdata that is passed to the callback function

using RandomNumberCallback = void (\*)(Lib3MF\_uint64, Lib3MF\_uint64, Lib3MF\_uint64, Lib3MF\_uint64\*)

Callback to generate random numbers

#### Param nByteData

Pointer to a buffer to read data into

## Param nNumBytes

Size of available bytes in the buffer

#### Param pUserData

Userdata that is passed to the callback function

#### Return

Number of bytes generated when succeed. 0 or less if failed.

using **KeyWrappingCallback** = void (\*)(Lib3MF\_AccessRight, *Lib3MF\_uint8*\*, *Lib3MF\_uint8*\*\*, *Lib3MF\_uint64*\*)

A callback used to wrap (encrypt) the content key available in keystore resource group

## Param pKEKParams

The information about the parameters used used to wrap the key to the contents

### Param nInBufferBufferSize

Buffer to the input value. When encrypting, this should be the plain key. When decrypting, this should be the key cipher.

## Param nInBufferBufferSize

buffer of Buffer to the input value. When encrypting, this should be the plain key. When decrypting, this should be the key cipher.

## Param nOutBufferBufferSize

Number of elements in buffer

#### Param pOutBufferNeededCount

will be filled with the count of the written elements, or needed buffer size.

# Param pOutBufferBuffer

buffer of Buffer where the data will be placed. When encrypting, this will be the key cipher. When decrypting, this will be the plain key. When buffer is null, neededBytes contains the required bytes to run.

## Param pUserData

Userdata that is passed to the callback function

## Return

The needed/encrypted/decrypted bytes when succeed or zero when error.

using **ContentEncryptionCallback** = void (\*)(Lib3MF\_ContentEncryptionParams, *Lib3MF\_uint8*\*, *Lib3MF\_uint8*\*\*, *Lib3MF\_uint8*\*\*, *Lib3MF\_uint64*\*)

A callback to encrypt/decrypt content called on each resource encrypted. This might be called several

times depending on content size. If Input is not available(either null or size is 0), clients must return the result of authenticated tag generation/validation.

### Param pCEKParams

The params of the encryption process. Client must set/check AuthenticationTag when closing the encryption/decryption process.

## Param nInputBufferSize

Buffer to the original data. In encrypting, this will be the plain data. If decrypting, this will be the cipher data

## Param nInputBufferSize

buffer of Buffer to the original data. In encrypting, this will be the plain data. If decrypting, this will be the cipher data

## Param nOutputBufferSize

Number of elements in buffer

# Param pOutputNeededCount

will be filled with the count of the written elements, or needed buffer size.

## Param pOutputBuffer

buffer of Buffer to hold the transformed data. When encrypting, this will be the cipher data. When decrypting, this shall be the plain data. If buffer is null, neededBytes return the necessary amount of bytes.

## Param pUserData

Userdata that is passed to the callback function

#### Return

The needed/encrypted/decrypted/verified bytes when succeed or zero when error.

## **ELib3MFException:** The standard exception class of the 3MF Library

Errors in the 3MF Library are reported as Exceptions. It is recommended to not throw these exceptions in your client code.

class Lib3MF::ELib3MFException

void ELib3MFException::what() const noexcept

Returns error message

#### **Returns**

the error message of this exception

*Lib3MFResult* ELib3MFException::getErrorCode() const noexcept

Returns error code

## Returns

the error code of this exception

## CInputVector: Adapter for passing arrays as input for functions

Several functions of the 3MF Library expect arrays of integral types or structs as input parameters. To not restrict the interface to, say, std::vector<type>, and to have a more abstract interface than a location in memory and the number of elements to input to a function the 3MF Library provides a templated adapter class to pass arrays as input for functions.

Usually, instances of CInputVector are generated anonymously (or even implicitly) in the call to a function that expects an input array.

returns the number of elements captured by this CInputVector

## 1.1.3 API-Classes

## **CAccessRight**

```
class Lib3MF::CAccessRight : public CBase
     PConsumer GetConsumer()
          Gets the consumer associated with this access right
               Returns
                   The consumer instance
     eWrappingAlgorithm GetWrappingAlgorithm()
          Gets the associated encryption algorithm
               Returns
                   The algorithm used for the key in this accessright
     eMgfAlgorithm GetMgfAlgorithm()
          Gets the associated mask generation function algorithm
               Returns
                   The MFG1 algorithm
     eDigestMethod GetDigestMethod()
          Gets the digest method assoicated
               Returns
                  The digest method for this accessright
typedef std::shared_ptr<CAccessRight> Lib3MF::PAccessRight
```

Shared pointer to CAccessRight to easily allow reference counting.

## **CAttachment**

```
{\tt class\ Lib3MF:: CAttachment: public\ \it CBase}
```

std::string GetPath()

Retrieves an attachment's package path. This function will be removed in a later release.

#### Returns

returns the attachment's package path string

void SetPath(const std::string &sPath)

Sets an attachment's package path. This function will be removed in a later release.

#### Parameters 4 8 1

**sPath** – new path of the attachment.

# PPackagePart PackagePart()

Returns the PackagePart that is this attachment.

#### Returns

The PackagePart of this attachment.

## std::string GetRelationShipType()

Retrieves an attachment's relationship type

#### **Returns**

returns the attachment's package relationship type string

## void SetRelationShipType(const std::string &sPath)

Sets an attachment's relationship type.

# **Parameters**

**sPath** – new relationship type string.

void WriteToFile(const std::string &sFileName)

Writes out the attachment as file.

## **Parameters**

**sFileName** – file to write into.

void ReadFromFile(const std::string &sFileName)

Reads an attachment from a file.

## **Parameters**

**sFileName** – file to read from.

## Lib3MF uint64 GetStreamSize()

Retrieves the size of the attachment stream

## Returns

the stream size

# $\label{lem:cond} \mbox{ void $W$riteToBuffer} (\mbox{std::vector} < \mbox{$Lib3MF\_uint8} > \mbox{\&BufferBuffer}) \\$

Writes out the attachment into a buffer

## **Parameters**

**BufferBuffer** – Buffer to write into

## void ReadFromBuffer(const CInputVector<Lib3MF\_uint8> &BufferBuffer)

Reads an attachment from a memory buffer

## **Parameters**

**BufferBuffer** – Buffer to read from

typedef std::shared\_ptr<CAttachment> Lib3MF::PAttachment

Shared pointer to CAttachment to easily allow reference counting.

## **CBase**

class Lib3MF::CBase

typedef std::shared\_ptr<CBase> Lib3MF::PBase

Shared pointer to CBase to easily allow reference counting.

## **CBaseMaterialGroup**

class Lib3MF::CBaseMaterialGroup : public CResource

The BaseMaterialGroup corresponds to a basematerials-element within a 3MF document

Lib3MF\_uint32 GetCount()

Retrieves the count of base materials in the material group.

#### Returns

returns the count of base materials.

void **GetAllPropertyIDs**(std::vector<*Lib3MF\_uint32*> &PropertyIDsBuffer)

returns all the PropertyIDs of all materials in this group

## **Parameters**

**PropertyIDsBuffer** – PropertyID of the material in the material group.

*Lib3MF\_uint32* **AddMaterial** (const std::string &sName, const *sColor* &DisplayColor)

Adds a new material to the material group

## **Parameters**

- **sName** new name of the base material.
- **DisplayColor** Display color of the material

# Returns

returns new PropertyID of the new material in the material group.

void RemoveMaterial(const Lib3MF\_uint32 nPropertyID)

Removes a material from the material group.

#### **Parameters**

**nPropertyID** – PropertyID of the material in the material group.

std::string **GetName**(const *Lib3MF\_uint32* nPropertyID)

Returns the base material's name

#### **Parameters**

**nPropertyID** – PropertyID of the material in the material group.

## Returns

returns the name of the base material.

void **SetName** (const *Lib3MF\_uint32* nPropertyID, const std::string &sName)

Sets a base material's name

## **Parameters**

- **nPropertyID** PropertyID of the material in the material group.
- **sName** new name of the base material.

void **SetDisplayColor** (const *Lib3MF\_uint32* nPropertyID, const *sColor* &TheColor)

Sets a base material's display color.

#### **Parameters**

- **nPropertyID** PropertyID of the material in the material group.
- **TheColor** The base material's display color

sColor GetDisplayColor(const Lib3MF\_uint32 nPropertyID)

Returns a base material's display color.

#### **Parameters**

**nPropertyID** – PropertyID of the material in the material group.

#### Returns

The base material's display color

typedef std::shared\_ptr<CBaseMaterialGroup> Lib3MF::PBaseMaterialGroup

Shared pointer to CBaseMaterialGroup to easily allow reference counting.

## **CBaseMaterialGroupIterator**

class Lib3MF::CBaseMaterialGroupIterator : public CResourceIterator

PBaseMaterialGroup GetCurrentBaseMaterialGroup()

Returns the MaterialGroup the iterator points at.

## Returns

returns the BaseMaterialGroup instance.

 $typedef\ std:: shared\_ptr < \textit{CBaseMaterialGroupIterator} > \texttt{Lib3MF}:: \textbf{PBaseMaterialGroupIterator}$ 

Shared pointer to CBaseMaterialGroupIterator to easily allow reference counting.

## **CBeamLattice**

class Lib3MF::CBeamLattice: public CBase

Lib3MF double GetMinLength()

Returns the minimal length of beams for the beamlattice.

## Returns

minimal length of beams for the beamlattice

void SetMinLength(const Lib3MF\_double dMinLength)

Sets the minimal length of beams for the beamlattice.

#### **Parameters**

**dMinLength** – minimal length of beams for the beamlattice

void **GetClipping**(*eBeamLatticeClipMode* &eClipMode, *Lib3MF\_uint32* &nUniqueResourceID)

Returns the clipping mode and the clipping-mesh for the beamlattice of this mesh.

#### **Parameters**

- eClipMode contains the clip mode of this mesh
- nUniqueResourceID filled with the UniqueResourceID of the clipping meshobject or an undefined value if pClipMode is MODELBEAMLATTICECLIP-MODE NONE

void **SetClipping**(const *eBeamLatticeClipMode* eClipMode, const *Lib3MF\_uint32* nUniqueResourceID)

Sets the clipping mode and the clipping-mesh for the beamlattice of this mesh.

#### **Parameters**

- eClipMode contains the clip mode of this mesh
- **nUniqueResourceID** the UniqueResourceID of the clipping mesh-object. This mesh-object has to be defined before setting the Clipping.

bool **GetRepresentation**(*Lib3MF\_uint32* &nUniqueResourceID)

Returns the representation-mesh for the beamlattice of this mesh.

## Returns

flag whether the beamlattice has a representation mesh.

#### **Parameters**

 ${\tt nUniqueResourceID}$  - filled with the UniqueResourceID of the clipping meshobject.

void SetRepresentation(const Lib3MF\_uint32 nUniqueResourceID)

Sets the representation-mesh for the beamlattice of this mesh.

#### **Parameters**

**nUniqueResourceID** – the UniqueResourceID of the representation mesh-object. This mesh-object has to be defined before setting the representation.

void GetBallOptions(eBeamLatticeBallMode &eBallMode, Lib3MF\_double &dBallRadius)

Returns the ball mode and the default ball radius for the beamlattice of this mesh. Returns the ball mode and the default ball radius for the beamlattice of this mesh.

#### param eBallMode

contains the ball mode of this mesh

## param dBallRadius

default ball radius of balls for the beamlattice

typedef std::shared\_ptr<CBeamLattice> Lib3MF::PBeamLattice

Shared pointer to CBeamLattice to easily allow reference counting.

## **CBeamSet**

```
class Lib3MF:: CBeamSet: public CBase
```

void SetName(const std::string &sName)

Sets a beamset's name string

#### **Parameters**

**sName** – new name of the beamset.

std::string GetName()

Retrieves a beamset's name string

### Returns

returns the name of the beamset.

void SetIdentifier(const std::string &sIdentifier)

Sets a beamset's identifier string

#### **Parameters**

**sIdentifier** – new name of the beamset.

std::string GetIdentifier()

Retrieves a beamset's identifier string

#### **Returns**

returns the identifier of the beamset.

## Lib3MF\_uint32 GetReferenceCount()

Retrieves the reference count of a beamset

#### Returns

returns the reference count

void **SetReferences**(const *CInputVector*<*Lib3MF\_uint32*> &ReferencesBuffer)

Sets the references of a beamset

#### **Parameters**

**ReferencesBuffer** – the new indices of all beams in this beamset

void GetReferences(std::vector<Lib3MF\_uint32> &ReferencesBuffer)

Retrieves the references of a beamset

#### **Parameters**

**ReferencesBuffer** – retrieves the indices of all beams in this beamset

# Lib3MF\_uint32 GetBallReferenceCount()

Retrieves the ball reference count of a beamset

### **Returns**

returns the ball reference count

void **SetBallReferences**(const *CInputVector*<*Lib3MF\_uint32*> &BallReferencesBuffer)

Sets the ball references of a beamset

#### **Parameters**

**BallReferencesBuffer** – the new indices of all balls in this beamset

void **GetBallReferences**(std::vector<*Lib3MF\_uint32*> &BallReferencesBuffer)

Retrieves the ball references of a beamset

## **Parameters**

**BallReferencesBuffer** – retrieves the indices of all balls in this beamset

typedef std::shared\_ptr<CBeamSet> Lib3MF::PBeamSet

Shared pointer to CBeamSet to easily allow reference counting.

## **CBuildItem**

class Lib3MF::CBuildItem: public CBase

#### PObject GetObjectResource()

Retrieves the object resource associated to a build item

#### Returns

returns the associated resource instance

## std::string **GetUUID**(bool &bHasUUID)

returns, whether a build item has a UUID and, if true, the build item's UUID

## **Parameters**

**bHasUUID** – flag whether the build item has a UUID

#### Returns

void SetUUID(const std::string &sUUID)

sets the build item's UUID

#### **Parameters**

## Lib3MF\_uint32 GetObjectResourceID()

Retrieves the object UniqueResourceID associated to a build item

#### Returns

returns the UniqueResourceID of the object

## bool HasObjectTransform()

Checks, if a build item has a non-identity transformation matrix

#### Returns

returns true, if the transformation matrix is not the identity

## sTransform GetObjectTransform()

Retrieves a build item's transformation matrix.

## Returns

returns the transformation matrix

## void SetObjectTransform(const sTransform &Transform)

Sets a build item's transformation matrix.

## **Parameters**

**Transform** – new transformation matrix

## std::string GetPartNumber()

Retrieves a build item's part number string

#### Returns

Returns a build item's part number string

## void SetPartNumber(const std::string &sSetPartnumber)

Sets a build item's part number string

#### Parameters

**sSetPartnumber** – new part number string for referencing parts from the outside world

## PMetaDataGroup GetMetaDataGroup()

Returns the metadatagroup of this build item

#### Returns

returns an Instance of the metadatagroup of this build item

## sBox GetOutbox()

Returns the outbox of a build item

#### Returns

Outbox of this build item

typedef std::shared\_ptr<CBuildItem> Lib3MF::PBuildItem

Shared pointer to CBuildItem to easily allow reference counting.

## **CBuildItemIterator**

```
class Lib3MF::CBuildItemIterator : public CBase
```

## bool MoveNext()

Iterates to the next build item in the list.

#### **Returns**

Iterates to the next build item in the list.

## bool MovePrevious()

Iterates to the previous build item in the list.

#### Returns

Iterates to the previous build item in the list.

## PBuildItem GetCurrent()

Returns the build item the iterator points at.

#### Returns

returns the build item instance.

# PBuildItemIterator Clone()

Creates a new build item iterator with the same build item list.

#### **Returns**

returns the cloned Iterator instance

# Lib3MF\_uint64 Count()

Returns the number of build items the iterator captures.

## Returns

returns the number of build items the iterator captures.

typedef std::shared\_ptr<CBuildItemIterator> Lib3MF::PBuildItemIterator

Shared pointer to CBuildItemIterator to easily allow reference counting.

# **CColorGroup**

```
class Lib3MF::CColorGroup: public CResource
     Lib3MF_uint32 GetCount()
           Retrieves the count of base materials in this Color Group.
               Returns
                   returns the count of colors within this color group.
     void GetAllPropertyIDs(std::vector<Lib3MF_uint32> &PropertyIDsBuffer)
           returns all the PropertyIDs of all colors within this group
               Parameters
                   PropertyIDsBuffer – PropertyID of the color in the color group.
     Lib3MF uint32 AddColor(const sColor &TheColor)
           Adds a new value.
               Parameters
                   TheColor – The new color
               Returns
                   PropertyID of the new color within this color group.
     void RemoveColor(const Lib3MF_uint32 nPropertyID)
           Removes a color from the color group.
               Parameters
                   nPropertyID – PropertyID of the color to be removed from the color group.
     void SetColor (const Lib3MF_uint32 nPropertyID, const sColor &TheColor)
           Sets a color value.
               Parameters
                   • nPropertyID – PropertyID of a color within this color group.
                   • TheColor - The color
     sColor GetColor(const Lib3MF_uint32 nPropertyID)
           Sets a color value.
               Parameters
                   nPropertyID – PropertyID of a color within this color group.
               Returns
                   The color
typedef std::shared_ptr<CColorGroup> Lib3MF::PColorGroup
```

Shared pointer to CColorGroup to easily allow reference counting.

# **CColorGroupIterator**

```
class Lib3MF::CColorGroupIterator : public CResourceIterator
```

## PColorGroup GetCurrentColorGroup()

Returns the ColorGroup the iterator points at.

#### Returns

returns the ColorGroup instance.

typedef std::shared\_ptr<CColorGroupIterator> Lib3MF::PColorGroupIterator

Shared pointer to CColorGroupIterator to easily allow reference counting.

## **CComponent**

```
class Lib3MF::CComponent: public CBase
```

## PObject GetObjectResource()

Returns the Resource Instance of the component.

#### Returns

filled with the Resource Instance.

## Lib3MF\_uint32 GetObjectResourceID()

Returns the UniqueResourceID of the component.

#### Returns

returns the UniqueResourceID.

# std::string **GetUUID**(bool &bHasUUID)

returns, whether a component has a UUID and, if true, the component's UUID

### **Parameters**

**bHasUUID** – flag whether the component has a UUID

## Returns

void SetUUID(const std::string &sUUID)

sets the component's UUID

#### **Parameters**

## bool HasTransform()

Returns, if the component has a different transformation than the identity matrix

## Returns

if true is returned, the transformation is not equal than the identity

## sTransform GetTransform()

Returns the transformation matrix of the component.

## Returns

filled with the component transformation matrix

```
void SetTransform(const sTransform &Transform)
```

Sets the transformation matrix of the component.

## **Parameters**

**Transform** – new transformation matrix

typedef std::shared ptr<*CComponent*> Lib3MF::**PComponent** 

Shared pointer to CComponent to easily allow reference counting.

# **CComponentsObject**

```
class Lib3MF::CComponentsObject : public CObject
```

PComponent AddComponent (CObject \*pObjectResource, const sTransform &Transform)

Adds a new component to a components object.

#### **Parameters**

- pObjectResource object to add as component. Must not lead to circular references!
- **Transform** optional transform matrix for the component.

## Returns

new component instance

PComponent GetComponent (const Lib3MF\_uint32 nIndex)

Retrieves a component from a component object.

#### **Parameters**

**nIndex** – index of the component to retrieve (0 to component count - 1)

# Returns

component instance

## Lib3MF\_uint32 GetComponentCount()

Retrieves a component count of a component object.

## Returns

returns the component count

typedef std::shared\_ptr<CComponentsObject> Lib3MF::PComponentsObject

Shared pointer to CComponentsObject to easily allow reference counting.

# **CComponentsObjectIterator**

```
class Lib3MF::CComponentsObjectIterator : public CResourceIterator
```

## PComponentsObject GetCurrentComponentsObject()

Returns the ComponentsObject the iterator points at.

## Returns

returns the ComponentsObject instance.

 $typedef\ std:: shared\_ptr < \textit{CComponentsObjectIterator} > \texttt{Lib3MF}:: \textbf{PComponentsObjectIterator}$ 

Shared pointer to CComponentsObjectIterator to easily allow reference counting.

## **CCompositeMaterials**

class Lib3MF::CCompositeMaterials: public CResource

Lib3MF uint32 GetCount()

Retrieves the count of Composite-s in the CompositeMaterials.

#### Returns

returns the count of Composite-s

void **GetAllPropertyIDs**(std::vector<*Lib3MF\_uint32*> &PropertyIDsBuffer)

returns all the PropertyIDs of all Composite-Mixing Values in this CompositeMaterials

#### **Parameters**

 $\label{lem:propertyIDsBuffer} \textbf{PropertyID} \ of the \ Composite-Mixing \ Values \ in \ the \ Composite Materials.$ 

PBaseMaterialGroup GetBaseMaterialGroup()

Obtains the BaseMaterialGroup instance of this CompositeMaterials.

#### Returns

returns the BaseMaterialGroup instance of this CompositeMaterials

Lib3MF\_uint32 AddComposite(const CInputVector<sCompositeConstituent> &CompositeBuffer)

Adds a new Composite-Mixing Values to the CompositeMaterials.

#### **Parameters**

CompositeBuffer – The Composite Constituents to be added as composite

#### Returns

returns new PropertyID of the new Composite in the CompositeMaterials.

void RemoveComposite(const Lib3MF\_uint32 nPropertyID)

Removes a Composite-Maxing Ratio from the CompositeMaterials.

#### **Parameters**

**nPropertyID** – PropertyID of the Composite-Mixing Values in the CompositeMaterials to be removed.

void **GetComposite**(const *Lib3MF\_uint32* nPropertyID, std::vector<*sCompositeConstituent*> &CompositeBuffer)

Obtains a Composite-Maxing Ratio of this CompositeMaterials.

## **Parameters**

- nPropertyID the PropertyID of the Composite-Maxing Ratio in the CompositeMaterials.
- CompositeBuffer The Composite-Mixing Values with the given PropertyID

typedef std::shared\_ptr<CCompositeMaterials> Lib3MF::PCompositeMaterials

Shared pointer to CCompositeMaterials to easily allow reference counting.

## **CCompositeMaterialsIterator**

```
class Lib3MF::CCompositeMaterialsIterator : public CResourceIterator
```

PCompositeMaterials GetCurrentCompositeMaterials()

Returns the CompositeMaterials the iterator points at.

#### **Returns**

returns the CompositeMaterials instance.

typedef std::shared\_ptr<*CCompositeMaterialsIterator*> Lib3MF::**PCompositeMaterialsIterator**Shared pointer to CCompositeMaterialsIterator to easily allow reference counting.

## **CConsumer**

```
class Lib3MF::CConsumer : public CBase
std::string GetConsumerID()
```

Gets the consumerid

#### Returns

A unique identifier for the consumers

std::string GetKeyID()

Getts the keyid

## Returns

The identifier for the key of this consumer

std::string GetKeyValue()

Gets the keyvalue associated with this consumer

## Returns

The public key, when available, of this consumer

typedef std::shared\_ptr<CConsumer> Lib3MF::PConsumer

Shared pointer to CConsumer to easily allow reference counting.

## **CContentEncryptionParams**

```
class Lib3MF::CContentEncryptionParams: public CBase
```

 $e Encryption Algorithm \ \textbf{GetEncryptionAlgorithm} \ ()$ 

Returns the encryption method to be used in this encryption process

# Returns

void GetKey(std::vector<Lib3MF\_uint8> &ByteDataBuffer)

Gets the key for the resource associated

#### **Parameters**

**ByteDataBuffer** – Pointer to a buffer where to place the key.

void GetInitializationVector(std::vector<Lib3MF\_uint8> &ByteDataBuffer)

Gets the IV data

#### **Parameters**

ByteDataBuffer – Pointer to a buffer where to place the data.

## void **GetAuthenticationTag**(std::vector<*Lib3MF\_uint8*> &ByteDataBuffer)

A handler descriptor that uniquely identifies the context of the resource. Each resource will be assigned a different value

#### **Parameters**

**ByteDataBuffer** – Pointer to a buffer where to place the data.

# void **SetAuthenticationTag**(const *CInputVector*<*Lib3MF\_uint8*> &ByteDataBuffer)

Sets the authentication tag

#### **Parameters**

ByteDataBuffer – The authentication tag size

## void **GetAdditionalAuthenticationData**(std::vector<*Lib3MF\_uint8*> &ByteDataBuffer)

A handler descriptor that uniquely identifies the context of the resource. Each resource will be assigned a different value

#### **Parameters**

ByteDataBuffer - Buffer where the data will be placed

## Lib3MF\_uint64 GetDescriptor()

A handler descriptor that uniquely identifies the context of the resource. Each resource will be assigned a different value

## Returns

## std::string GetKeyUUID()

Gets the resourcedatagroup keyuuid

#### **Returns**

The resourcedatagroup keyuuid that may be use to reference an external key

 $typedef\ std:: shared\_ptr < \textit{CContentEncryptionParams} > \texttt{Lib3MF}:: \textbf{PContentEncryptionParams}$ 

Shared pointer to CContentEncryptionParams to easily allow reference counting.

# **CKeyStore**

class Lib3MF:: CKeyStore: public CBase

*PConsumer* **AddConsumer**(const std::string &sConsumerID, const std::string &sKeyID, const std::string &sKeyValue)

Adds a consumer to the keystore

### **Parameters**

- **sConsumerID** A unique identifier for the consumer
- **sKeyID** The id of the key of the consumer
- **sKeyValue** The public key for this consumer in PEM format

#### Returns

The consumer instance

## Lib3MF uint64 GetConsumerCount()

Gets the number of consumers in the keystore

## Returns

The consumer count

## PConsumer GetConsumer(const Lib3MF\_uint64 nConsumerIndex)

Get a consumer from the keystore

#### **Parameters**

**nConsumerIndex** – The index of the consumer

#### Returns

The consumer instance

## void RemoveConsumer(CConsumer \*pConsumer)

Removes a consumer from the keystore

#### **Parameters**

**pConsumer** – The consumer instance to remove

## PConsumer FindConsumer(const std::string &sConsumerID)

Finds a consumer by ID

#### **Parameters**

**sConsumerID** – The ID of the consumer

#### Returns

The consumer instance

#### Lib3MF uint64 GetResourceDataGroupCount()

Gets the number of resource data group in the keysore

#### Returns

The number of resource data available

## PResourceDataGroup AddResourceDataGroup()

Adds a resource data group into the keystore.

## Returns

The resource data group instance

## PResourceDataGroup GetResourceDataGroup(const Lib3MF\_uint64 nResourceDataIndex)

Gets a resource data group

## **Parameters**

nResourceDataIndex - The index of the resource data

#### Returns

The resource data group instance

## void **RemoveResourceDataGroup** \*pResourceDataGroup)

Removes a resource data group

# **Parameters**

**pResourceDataGroup** – The resource data group instance

# $\textit{PResourceDataGroup} \textbf{FindResourceDataGroup}(\textit{CPackagePart}\ *pPartPath)$

Finds a resource data group that contains a particular resourcedata

#### **Parameters**

**pPartPath** – The target path for the resourcedata hold by the resource data group

## Returns

The data resource instance

PResourceData AddResourceData(CResourceDataGroup \*pResourceDataGroup, CPackagePart \*pPartPath, const eEncryptionAlgorithm eAlgorithm, const eCompression eCompression, const CInputVector<Lib3MF\_uint8> &AdditionalAuthenticationDataBuffer)

Add resourcedata to resourcedatagroup element

#### **Parameters**

- pResourceDataGroup The resource data group where to add this resource data
- **pPartPath** The path of the part to be encrypted
- eAlgorithm The encryption algorithm to be used to encrypt this resource
- eCompression Whether compression should be used prior to encryption
- Additional Authentication Data Buffer Additional data to be encrypted along the contents for better security

#### Returns

The data resource instance

## void RemoveResourceData(CResourceData\*pResourceData)

Removes a resource data

#### **Parameters**

pResourceData - The resource data to be removed

## PResourceData FindResourceData(CPackagePart \*pResourcePath)

Finds a resource data on this resource group

#### **Parameters**

**pResourcePath** – The target path for the resourcedata

## Returns

The resource data instance

## Lib3MF uint64 GetResourceDataCount()

Gets the number of resource data in the keysore

## Returns

The number of resource data available

## PResourceData GetResourceData(const Lib3MF\_uint64 nResourceDataIndex)

Gets a resource data

## **Parameters**

nResourceDataIndex - The index of the resource data

### **Returns**

The data resource instance

## std::string **GetUUID**(bool &bHasUUID)

Gets the keystore UUID

#### **Parameters**

**bHasUUID** – flag whether the keystore has a UUID

## Returns

returns the keystore uuid.

```
void SetUUID(const std::string &sUUID)
```

Sets the keystore UUID

#### **Parameters**

**sUUID** – The new keystore uuid.

typedef std::shared\_ptr<CKeyStore> Lib3MF::PKeyStore

Shared pointer to CKeyStore to easily allow reference counting.

# **CMeshObject**

```
class Lib3MF::CMeshObject : public CObject
```

# Lib3MF\_uint32 GetVertexCount()

Returns the vertex count of a mesh object.

#### Returns

filled with the vertex count.

# Lib3MF\_uint32 GetTriangleCount()

Returns the triangle count of a mesh object.

#### **Returns**

filled with the triangle count.

#### sPosition GetVertex(const Lib3MF uint32 nIndex)

Returns the vertex count of a mesh object.

#### **Parameters**

**nIndex** – Index of the vertex (0 to vertexcount - 1)

#### Returns

filled with the vertex coordinates.

# void **SetVertex**(const *Lib3MF\_uint32* nIndex, const *sPosition* &Coordinates)

Sets the coordinates of a single vertex of a mesh object

# **Parameters**

- **nIndex** Index of the vertex (0 to vertexcount 1)
- **Coordinates** contains the vertex coordinates.

# Lib3MF uint32 AddVertex(const sPosition &Coordinates)

Adds a single vertex to a mesh object

# **Parameters**

**Coordinates** – contains the vertex coordinates.

#### Returns

Index of the new vertex

#### void GetVertices(std::vector<sPosition> & VerticesBuffer)

Obtains all vertex positions of a mesh object

# **Parameters**

**VerticesBuffer** – contains the vertex coordinates.

#### sTriangle GetTriangle(const Lib3MF\_uint32 nIndex)

Returns indices of a single triangle of a mesh object.

#### **Parameters**

**nIndex** – Index of the triangle (0 to trianglecount - 1)

#### Returns

filled with the triangle indices.

void **SetTriangle**(const *Lib3MF uint32* nIndex, const *sTriangle* &Indices)

Sets the indices of a single triangle of a mesh object.

#### **Parameters**

- **nIndex** Index of the triangle (0 to trianglecount 1)
- **Indices** contains the triangle indices.

# *Lib3MF\_uint32* **AddTriangle** (const *sTriangle* &Indices)

Adds a single triangle to a mesh object

# **Parameters**

**Indices** – contains the triangle indices.

#### Returns

Index of the new triangle

# void GetTriangleIndices(std::vector<sTriangle> &IndicesBuffer)

Get all triangles of a mesh object

#### **Parameters**

**IndicesBuffer** – contains the triangle indices.

# void **SetObjectLevelProperty**(const *Lib3MF\_uint32* nUniqueResourceID, const *Lib3MF\_uint32* nPropertyID)

Sets the property at the object-level of the mesh object.

#### **Parameters**

- nUniqueResourceID the object-level Property UniqueResourceID.
- **nPropertyID** the object-level PropertyID.

bool GetObjectLevelProperty(Lib3MF\_uint32 &nUniqueResourceID, Lib3MF\_uint32 &nPropertyID)

Gets the property at the object-level of the mesh object.

## **Parameters**

- nUniqueResourceID the object-level Property UniqueResourceID.
- **nPropertyID** the object-level PropertyID.

# Returns

Has an object-level property been specified?

void SetTriangleProperties (const Lib3MF\_uint32 nIndex, const sTriangleProperties & Properties)

Sets the properties of a single triangle of a mesh object.

#### **Parameters**

- **nIndex** Index of the triangle (0 to trianglecount 1)
- **Properties** contains the triangle properties.

# void GetTriangleProperties (const Lib3MF\_uint32 nIndex, sTriangleProperties & Property)

Gets the properties of a single triangle of a mesh object.

### **Parameters**

- **nIndex** Index of the triangle (0 to trianglecount 1)
- **Property** returns the triangle properties.

# void **SetAllTriangleProperties**(const *CInputVector*<*sTriangleProperties*> & PropertiesArrayBuffer)

Sets the properties of all triangles of a mesh object. Sets the object level property to the first entry of the passed triangle properties, if not yet specified.

#### **Parameters**

**PropertiesArrayBuffer** – contains the triangle properties array. Must have trianglecount elements.

# $void \ \textbf{GetAllTriangleProperties} (std::vector < \textit{sTriangleProperties}) \ \& Properties Array Buffer)$

Gets the properties of all triangles of a mesh object.

#### **Parameters**

**PropertiesArrayBuffer** – returns the triangle properties array. Must have trianglecount elements.

# void ClearAllProperties()

Clears all properties of this mesh object (triangle and object-level).

# void **SetGeometry**(const *CInputVector*<*sPosition*> &VerticesBuffer, const *CInputVector*<*sTriangle*> &IndicesBuffer)

Set all triangles of a mesh object

#### **Parameters**

- **VerticesBuffer** contains the positions.
- **IndicesBuffer** contains the triangle indices.

#### bool IsManifoldAndOriented()

Retrieves, if an object describes a topologically oriented and manifold mesh, according to the core spec.

### Returns

returns, if the object is oriented and manifold.

# PBeamLattice BeamLattice()

Retrieves the BeamLattice within this MeshObject.

#### Returns

the BeamLattice within this MeshObject

#### typedef std::shared ptr<*CMeshObject*> Lib3MF::**PMeshObject**

Shared pointer to CMeshObject to easily allow reference counting.

# **CMeshObjectIterator**

```
class Lib3MF::CMeshObjectIterator : public CResourceIterator
```

#### PMeshObject GetCurrentMeshObject()

Returns the MeshObject the iterator points at.

#### Returns

returns the MeshObject instance.

typedef std::shared\_ptr<CMeshObjectIterator> Lib3MF::PMeshObjectIterator

Shared pointer to CMeshObjectIterator to easily allow reference counting.

#### **CMetaData**

```
class Lib3MF::CMetaData: public CBase
```

std::string GetNameSpace()

returns the namespace URL of the metadata

#### Returns

the namespace URL of the metadata

void SetNameSpace(const std::string &sNameSpace)

sets a new namespace URL of the metadata

### **Parameters**

**sNameSpace** – the new namespace URL of the metadata

std::string GetName()

returns the name of a metadata

#### Returns

the name of the metadata

void SetName(const std::string &sName)

sets a new name of a metadata

#### **Parameters**

**sName** – the new name of the metadata

std::string GetKey()

returns the (namespace+name) of a metadata

#### Returns

the key (namespace+name) of the metadata

# bool GetMustPreserve()

returns, whether a metadata must be preserved

#### Returns

returns, whether a metadata must be preserved

void SetMustPreserve(const bool bMustPreserve)

sets whether a metadata must be preserved

# **Parameters**

**bMustPreserve** – a new value whether a metadata must be preserved

# std::string GetType()

returns the type of a metadata

### Returns

the type of the metadata

void SetType(const std::string &sType)

sets a new type of a metadata. This must be a simple XML type

#### **Parameters**

**sType** – a new type of the metadata

std::string GetValue()

returns the value of the metadata

#### **Returns**

the value of the metadata

void SetValue(const std::string &sValue)

sets a new value of the metadata

#### **Parameters**

**sValue** – a new value of the metadata

typedef std::shared\_ptr<CMetaData> Lib3MF::PMetaData

Shared pointer to CMetaData to easily allow reference counting.

# **CMetaDataGroup**

class Lib3MF::CMetaDataGroup : public CBase

# Lib3MF\_uint32 GetMetaDataCount()

returns the number of metadata in this metadatagroup

# Returns

returns the number metadata

PMetaData GetMetaData(const Lib3MF\_uint32 nIndex)

returns a metadata value within this metadatagroup

#### **Parameters**

nIndex - Index of the Metadata.

## Returns

an instance of the metadata

PMetaData GetMetaDataByKey (const std::string &sNameSpace, const std::string &sName)

returns a metadata value within this metadatagroup

#### **Parameters**

- **sNameSpace** the namespace of the metadata
- sName the name of the Metadata

#### Returns

an instance of the metadata

```
void RemoveMetaDataByIndex(const Lib3MF_uint32 nIndex)
```

removes metadata by index from the model.

### **Parameters**

**nIndex** – Index of the metadata to remove

void **RemoveMetaData**(*CMetaData* \*pTheMetaData)

removes metadata from the model.

#### **Parameters**

**pTheMetaData** – The metadata to remove

PMetaData AddMetaData(const std::string &sNameSpace, const std::string &sName, const std::string &sValue, const std::string &sType, const bool bMustPreserve)

adds a new metadata to this metadatagroup

#### **Parameters**

- sNameSpace the namespace of the metadata
- sName the name of the metadata
- sValue the value of the metadata
- **sType** the type of the metadata
- bMustPreserve shuold the metadata be preserved

#### Returns

a new instance of the metadata

```
typedef std::shared ptr<CMetaDataGroup> Lib3MF::PMetaDataGroup
```

Shared pointer to CMetaDataGroup to easily allow reference counting.

#### **CModel**

```
class Lib3MF:: CModel: public CBase
```

#### PPackagePart RootModelPart()

Returns the PackagePart within the OPC package that holds the root model.

# Returns

the PackagePart within the OPC package that holds the model-file

PPackagePart FindOrCreatePackagePart (const std::string &sAbsolutePath)

Returns a new PackagePart for use within the OPC package.

#### **Parameters**

**sAbsolutePath** – the absolute Path (physical location) within the OPC package

#### Returns

the new PackagePart within the OPC package

void SetUnit(const eModelUnit eUnit)

sets the units of a model.

## **Parameters**

eUnit - Unit enum value for the model unit

```
returns the units of a model.
         Returns
             Unit enum value for the model unit
std::string GetLanguage()
     retrieves the language of a model
         Returns
             language identifier
void SetLanguage(const std::string &sLanguage)
     sets the language of a model
         Parameters
             sLanguage – language identifier
PWriter QueryWriter(const std::string &sWriterClass)
     creates a model writer instance for a specific file type
         Parameters
             sWriterClass – string identifier for the file type
         Returns
             string identifier for the file type
PReader QueryReader(const std::string &sReaderClass)
     creates a model reader instance for a specific file type
         Parameters
             sReaderClass – string identifier for the file type
         Returns
             string identifier for the file type
PTexture2D GetTexture2DByID(const Lib3MF_uint32 nUniqueResourceID)
     finds a model texture by its UniqueResourceID
         Parameters
             \textbf{nUniqueResourceID} - UniqueResourceID
         Returns
             returns the texture2d instance
ePropertyType GetPropertyTypeByID(const Lib3MF_uint32 nUniqueResourceID)
     returns a Property's type
         Parameters
             nUniqueResourceID - Resource ID of the Property to Query
             returns a Property's type
PBaseMaterialGroup GetBaseMaterialGroupByID(const Lib3MF_uint32 nUniqueResourceID)
     finds a model base material group by its UniqueResourceID
         Parameters
             nUniqueResourceID - UniqueResourceID
         Returns
             returns the BaseMaterialGroup instance
```

eModelUnit GetUnit()

```
PTexture2DGroup GetTexture2DGroupByID(const Lib3MF_uint32 nUniqueResourceID)
     finds a model texture2d group by its UniqueResourceID
         Parameters
            nUniqueResourceID - UniqueResourceID
         Returns
             returns the Texture2DGroup instance
PCompositeMaterials GetCompositeMaterialsByID(const Lib3MF uint32 nUniqueResourceID)
     finds a model CompositeMaterials by its UniqueResourceID
         Parameters
            nUniqueResourceID - UniqueResourceID
         Returns
             returns the CompositeMaterials instance
PMultiPropertyGroup GetMultiPropertyGroupByID(const Lib3MF_uint32 nUniqueResourceID)
     finds a model MultiPropertyGroup by its UniqueResourceID
         Parameters
            nUniqueResourceID - UniqueResourceID
         Returns
            returns the MultiPropertyGroup instance
PMeshObject GetMeshObjectByID(const Lib3MF_uint32 nUniqueResourceID)
     finds a mesh object by its UniqueResourceID
         Parameters
            \textbf{nUniqueResourceID} - UniqueResourceID
         Returns
             returns the mesh object instance
PComponentsObject GetComponentsObjectByID(const Lib3MF_uint32 nUniqueResourceID)
     finds a components object by its UniqueResourceID
         Parameters
            \textbf{nUniqueResourceID} - UniqueResourceID
         Returns
             returns the components object instance
PColorGroup GetColorGroupByID (const Lib3MF_uint32 nUniqueResourceID)
     finds a model color group by its UniqueResourceID
         Parameters
            nUniqueResourceID - UniqueResourceID
            returns the ColorGroup instance
PSliceStack GetSliceStackByID(const Lib3MF_uint32 nUniqueResourceID)
     finds a model slicestack by its UniqueResourceID
         Parameters
            nUniqueResourceID - UniqueResourceID
         Returns
            returns the slicestack instance
```

# std::string GetBuildUUID(bool &bHasUUID)

returns, whether a build has a UUID and, if true, the build's UUID

#### **Parameters**

**bHasUUID** – flag whether the build has a UUID

#### Returns

# void SetBuildUUID(const std::string &sUUID)

sets the build's UUID

#### **Parameters**

#### PBuildItemIterator GetBuildItems()

creates a build item iterator instance with all build items.

#### Returns

returns the iterator instance.

#### sBox GetOutbox()

Returns the outbox of a Model

#### Returns

Outbox of this Model

# PResourceIterator GetResources()

creates a resource iterator instance with all resources.

#### Returns

returns the iterator instance.

# PObjectIterator GetObjects()

creates a resource iterator instance with all object resources.

# Returns

returns the iterator instance.

#### PMeshObjectIterator GetMeshObjects()

creates a resource iterator instance with all mesh object resources.

# Returns

returns the iterator instance.

# PComponentsObjectIterator GetComponentsObjects()

creates a resource iterator instance with all components object resources.

# Returns

returns the iterator instance.

#### PTexture2DIterator GetTexture2Ds()

creates a Texture2DIterator instance with all texture2d resources.

# Returns

returns the iterator instance.

# $PB as e Material Group Iterator \ {\tt GetBaseMaterialGroups}()$

creates a BaseMaterialGroupIterator instance with all base material resources.

#### Returns

returns the iterator instance.

# PColorGroupIterator GetColorGroups()

creates a ColorGroupIterator instance with all ColorGroup resources.

#### Returns

returns the iterator instance.

# PTexture2DGroupIterator GetTexture2DGroups()

creates a Texture2DGroupIterator instance with all base material resources.

#### Returns

returns the iterator instance.

# PCompositeMaterialsIterator GetCompositeMaterials()

creates a CompositeMaterialsIterator instance with all CompositeMaterials resources.

#### Returns

returns the iterator instance.

# PMultiPropertyGroupIterator GetMultiPropertyGroups()

creates a MultiPropertyGroupsIterator instance with all MultiPropertyGroup resources.

#### Returns

returns the iterator instance.

#### PSliceStackIterator GetSliceStacks()

creates a resource iterator instance with all slice stack resources.

#### Returns

returns the iterator instance.

#### PModel MergeToModel()

Merges all components and objects which are referenced by a build item into a mesh. The memory is duplicated and a new model is created.

#### Returns

returns the merged model instance

# PMeshObject AddMeshObject()

adds an empty mesh object to the model.

### Returns

returns the mesh object instance

#### PComponentsObject AddComponentsObject()

adds an empty component object to the model.

#### **Returns**

returns the components object instance

# PSliceStack AddSliceStack(const Lib3MF\_double dZBottom)

creates a new model slicestack by its id

#### **Parameters**

**dZBottom** – Bottom Z value of the slicestack

# Returns

returns the new slicestack instance

# PTexture2D AddTexture2DFromAttachment(CAttachment\*pTextureAttachment)

adds a texture2d resource to the model. Its path is given by that of an existing attachment.

#### **Parameters**

**pTextureAttachment** – attachment containing the image data.

#### Returns

returns the new texture instance.

# PBaseMaterialGroup AddBaseMaterialGroup()

adds an empty BaseMaterialGroup resource to the model.

#### Returns

returns the new base material instance.

# PColorGroup AddColorGroup()

adds an empty ColorGroup resource to the model.

#### Returns

returns the new ColorGroup instance.

# PTexture2DGroup AddTexture2DGroup(CTexture2D \*pTexture2DInstance)

adds an empty Texture2DGroup resource to the model.

#### **Parameters**

**pTexture2DInstance** – The texture2D instance of the created Texture2DGroup.

#### Returns

returns the new Texture2DGroup instance.

# $PComposite Materials \ \textbf{AddCompositeMaterials} \ (CBase Material Group \ *pBase Material Group Instance)$

adds an empty CompositeMaterials resource to the model.

# **Parameters**

 $\label{lem:problem} \textbf{pBaseMaterialGroupInstance} - The \ BaseMaterialGroup \ instance \ of \ the \ created \ CompositeMaterials.$ 

#### Returns

returns the new CompositeMaterials instance.

# PMultiPropertyGroup AddMultiPropertyGroup()

adds an empty MultiPropertyGroup resource to the model.

# Returns

returns the new MultiPropertyGroup instance.

# PBuildItem AddBuildItem(CObject \*pObject, const sTransform &Transform)

adds a build item to the model.

#### **Parameters**

- **p0bject** Object instance.
- Transform Transformation matrix.

#### Returns

returns the build item instance.

# void RemoveBuildItem(CBuildItem \*pBuildItemInstance)

removes a build item from the model

# **Parameters**

**pBuildItemInstance** – Build item to remove.

#### PMetaDataGroup GetMetaDataGroup()

Returns the metadata of the model as MetaDataGroup

#### Returns

returns an Instance of the metadatagroup of the model

# PAttachment AddAttachment (const std::string &sURI, const std::string &sRelationShipType)

adds an attachment stream to the model. The OPC part will be related to the model stream with a certain relationship type.

#### **Parameters**

- **sURI** Path of the attachment
- **sRelationShipType** Relationship type of the attachment

### Returns

Instance of the attachment object

# void RemoveAttachment(CAttachment \*pAttachmentInstance)

Removes attachment from the model.

#### **Parameters**

**pAttachmentInstance** – Attachment instance to remove

#### PAttachment GetAttachment (const Lib3MF uint32 nIndex)

retrieves an attachment stream object from the model..

#### **Parameters**

**nIndex** – Index of the attachment stream

#### **Returns**

Instance of the attachment object

# PAttachment FindAttachment(const std::string &sURI)

retrieves an attachment stream object from the model.

#### **Parameters**

**sURI** – Path URI in the package

# Returns

Instance of the attachment object

# Lib3MF uint32 GetAttachmentCount()

retrieves the number of attachments of the model.

#### Returns

Returns the number of attachments.

# bool HasPackageThumbnailAttachment()

Retrieve whether the OPC package contains a package thumbnail.

#### Returns

returns whether the OPC package contains a package thumbnail

# PAttachment CreatePackageThumbnailAttachment()

Create a new or the existing package thumbnail for the OPC package.

# Returns

Instance of a new or the existing thumbnailattachment object.

# PAttachment GetPackageThumbnailAttachment()

Get the attachment to the OPC package containing the package thumbnail.

#### Returns

Instance of the thumbnailattachment object or NULL.

#### void RemovePackageThumbnailAttachment()

Remove the attachment to the OPC package containing the package thumbnail.

void **AddCustomContentType**(const std::string &sExtension, const std::string &sContentType)

Adds a new Content Type to the model.

#### **Parameters**

- **sExtension** File Extension
- sContentType Content Type Identifier

void RemoveCustomContentType(const std::string &sExtension)

Removes a custom Content Type from the model (UTF8 version).

#### **Parameters**

**sExtension** – File Extension

void **SetRandomNumberCallback** (const *RandomNumberCallback* pTheCallback, const *Lib3MF\_pvoid* pUserData)

Sets the random number generator callback for use in the library

#### **Parameters**

- pTheCallback The callback used to generate random numbers
- pUserData Userdata to be passed to the callback function

# PKeyStore GetKeyStore()

Gets the keystore associated with this model

#### Returns

The package keystore

typedef std::shared\_ptr<*CModel*> Lib3MF::**PModel** 

Shared pointer to CModel to easily allow reference counting.

# **CMultiPropertyGroup**

```
class Lib3MF:: CMultiPropertyGroup: public CResource
```

```
Lib3MF_uint32 GetCount()
```

Retrieves the count of MultiProperty-s in the MultiPropertyGroup.

#### Returns

returns the count of MultiProperty-s

void **GetAllPropertyIDs**(std::vector<*Lib3MF uint32*> &PropertyIDsBuffer)

returns all the PropertyIDs of all MultiProperty-s in this MultiPropertyGroup

# **Parameters**

**PropertyIDsBuffer** – PropertyID of the MultiProperty-s in the MultiPropertyGroup.

# Lib3MF\_uint32 AddMultiProperty(const CInputVector<Lib3MF\_uint32> &PropertyIDsBuffer)

Adds a new MultiProperty to the MultiPropertyGroup.

#### **Parameters**

**PropertyIDsBuffer** – The PropertyIDs of the new MultiProperty.

#### Returns

returns the PropertyID of the new MultiProperty in the MultiPropertyGroup.

void **SetMultiProperty**(const *Lib3MF\_uint32* nPropertyID, const *CInputVector<Lib3MF\_uint32*> &PropertyIDsBuffer)

Sets the PropertyIDs of a MultiProperty.

#### **Parameters**

- **nPropertyID** the PropertyID of the MultiProperty to be changed.
- **PropertyIDsBuffer** The new PropertyIDs of the MultiProperty

void **GetMultiProperty**(const *Lib3MF\_uint32* nPropertyID, std::vector<*Lib3MF\_uint32*> &PropertyIDsBuffer)

Obtains the PropertyIDs of a MultiProperty.

#### **Parameters**

- **nPropertyID** the PropertyID of the MultiProperty to be queried.
- **PropertyIDsBuffer** The PropertyIDs of the MultiProperty

void **RemoveMultiProperty**(const *Lib3MF\_uint32* nPropertyID)

Removes a MultiProperty from this MultiPropertyGroup.

#### **Parameters**

**nPropertyID** – the PropertyID of the MultiProperty to be removed.

#### Lib3MF uint32 GetLayerCount()

Retrieves the number of layers of this MultiPropertyGroup.

# Returns

returns the number of layers

## *Lib3MF uint32* **AddLayer**(const *sMultiPropertyLayer* &TheLayer)

Adds a MultiPropertyLayer to this MultiPropertyGroup.

# **Parameters**

**TheLayer** – The MultiPropertyLayer to add to this MultiPropertyGroup

# Returns

returns the index of this MultiPropertyLayer

# sMultiPropertyLayer GetLayer(const Lib3MF\_uint32 nLayerIndex)

Obtains a MultiPropertyLayer of this MultiPropertyGroup.

# **Parameters**

nLayerIndex - The Index of the MultiPropertyLayer queried

#### Returns

The MultiPropertyLayer with index LayerIndex within MultiPropertyGroup

# void RemoveLayer(const Lib3MF\_uint32 nLayerIndex)

Removes a MultiPropertyLayer from this MultiPropertyGroup.

#### **Parameters**

nLayerIndex – The Index of the MultiPropertyLayer to be removed

typedef std::shared\_ptr<CMultiPropertyGroup> Lib3MF::PMultiPropertyGroup

Shared pointer to CMultiPropertyGroup to easily allow reference counting.

# **CMultiPropertyGroupIterator**

class Lib3MF:: CMultiPropertyGroupIterator: public CResourceIterator

PMultiPropertyGroup GetCurrentMultiPropertyGroup()

Returns the MultiPropertyGroup the iterator points at.

#### Returns

returns the MultiPropertyGroup instance.

 $typedef\ std:: shared\_ptr < \textit{CMultiPropertyGroupIterator} > \texttt{Lib3MF::} \textbf{PMultiPropertyGroupIterator}$ 

Shared pointer to CMultiPropertyGroupIterator to easily allow reference counting.

# **CObject**

class Lib3MF::CObject : public CResource

eObjectType GetType()

Retrieves an object's type

#### **Returns**

returns object type enum.

void SetType(const eObjectType eObjectType)

Sets an object's type

## **Parameters**

**e0bjectType** – object type enum.

std::string GetName()

Retrieves an object's name

# Returns

returns object name.

void SetName(const std::string &sName)

Sets an object's name string

# **Parameters**

**sName** – new object name.

std::string GetPartNumber()

Retrieves an object's part number

#### **Returns**

returns object part number.

void SetPartNumber(const std::string &sPartNumber)

Sets an objects partnumber string

#### **Parameters**

**sPartNumber** – new object part number.

# bool IsMeshObject()

Retrieves, if an object is a mesh object

#### Returns

returns, whether the object is a mesh object

# bool IsComponentsObject()

Retrieves, if an object is a components object

#### Returns

returns, whether the object is a components object

#### bool IsValid()

Retrieves, if the object is valid according to the core spec. For mesh objects, we distinguish between the type attribute of the object:In case of object type other, this always means false.In case of object type model or solidsupport, this means, if the mesh suffices all requirements of the core spec chapter 4.1.In case of object type support or surface, this always means true.A component objects is valid if and only if it contains at least one component and all child components are valid objects.

#### Returns

returns whether the object is a valid object description

# void SetAttachmentAsThumbnail(CAttachment \*pAttachment)

Use an existing attachment as thumbnail for this object

# **Parameters**

pAttachment – Instance of a new or the existing thumbnailattachment object.

#### PAttachment GetThumbnailAttachment()

Get the attachment containing the object thumbnail.

#### Returns

Instance of the thumbnailattachment object or NULL.

# void ClearThumbnailAttachment()

Clears the attachment. The attachment instance is not removed from the package.

# sBox GetOutbox()

Returns the outbox of a build item

#### Returns

Outbox of this build item

#### std::string **GetUUID**(bool &bHasUUID)

Retrieves an object's unid string (see production extension specification)

#### **Parameters**

**bHasUUID** – flag whether the build item has a UUID

### Returns

returns object uuid.

# void SetUUID(const std::string &sUUID)

Sets a build object's uuid string (see production extension specification)

#### **Parameters**

**sUUID** – new object unid string.

#### PMetaDataGroup GetMetaDataGroup()

Returns the metadatagroup of this object

#### Returns

returns an Instance of the metadatagroup of this object

# $void \ \textbf{SetSlicesMeshResolution} (const\ \textit{eSlicesMeshResolution}\ \textbf{eMeshResolution})$

set the meshresolution of the mesh object

#### **Parameters**

eMeshResolution - meshresolution of this object

# eSlicesMeshResolution()

get the meshresolution of the mesh object

#### Returns

meshresolution of this object

#### bool **HasSlices** (const bool bRecursive)

returns whether the Object has a slice stack. If Recursive is true, also checks whether any references object has a slice stack

#### **Parameters**

**bRecursive** – check also all referenced objects?

#### Returns

does the object have a slice stack?

#### void ClearSliceStack()

unlinks the attached slicestack from this object. If no slice stack is attached, do noting.

# PSliceStack GetSliceStack()

get the Slicestack attached to the object

#### Returns

returns the slicestack instance

# void AssignSliceStack(CSliceStack \*pSliceStackInstance)

assigns a slicestack to the object

### **Parameters**

**pSliceStackInstance** – the new slice stack of this Object

typedef std::shared ptr<*CObject*> Lib3MF::**PObject** 

Shared pointer to CObject to easily allow reference counting.

# **CObjectIterator**

```
class Lib3MF::CObjectIterator: public CResourceIterator
```

# PObject GetCurrentObject()

Returns the Object the iterator points at.

# Returns

returns the Object instance.

# typedef std::shared\_ptr<CObjectIterator> Lib3MF::PObjectIterator

Shared pointer to CObjectIterator to easily allow reference counting.

# **CPackagePart**

```
class Lib3MF:: CPackagePart : public CBase
```

std::string GetPath()

Returns the absolute path of this PackagePart.

#### Returns

Returns the absolute path of this PackagePart

void SetPath(const std::string &sPath)

Sets the absolute path of this PackagePart.

#### **Parameters**

**sPath** – Sets the absolute path of this PackagePart.

typedef std::shared ptr<*CPackagePart*> Lib3MF::**PPackagePart** 

Shared pointer to CPackagePart to easily allow reference counting.

#### **CReader**

```
class Lib3MF::CReader: public CBase
```

void ReadFromFile(const std::string &sFilename)

Reads a model from a file. The file type is specified by the Model Reader class

#### **Parameters**

**sFilename** – Filename to read from

void ReadFromBuffer(const CInputVector<Lib3MF\_uint8> &BufferBuffer)

Reads a model from a memory buffer.

#### **Parameters**

**BufferBuffer** – Buffer to read from

void **ReadFromCallback** (const *ReadCallback* pTheReadCallback, const *Lib3MF\_uint64* nStreamSize, const *SeekCallback* pTheSeekCallback, const *Lib3MF\_pvoid* pUserData)

Reads a model and from the data provided by a callback function

# **Parameters**

- pTheReadCallback Callback to call for reading a data chunk
- nStreamSize number of bytes the callback returns
- pTheSeekCallback Callback to call for seeking in the stream.
- pUserData Userdata that is passed to the callback function

void SetProgressCallback (const ProgressCallback pProgressCallback, const Lib3MF\_pvoid pUserData)

Set the progress callback for calls to this writer

#### **Parameters**

- **pProgressCallback** pointer to the callback function.
- pUserData pointer to arbitrary user data that is passed without modification to the callback.

#### void AddRelationToRead(const std::string &sRelationShipType)

Adds a relationship type which shall be read as attachment in memory while loading

#### **Parameters**

**sRelationShipType** – String of the relationship type

# void RemoveRelationToRead(const std::string &sRelationShipType)

Removes a relationship type which shall be read as attachment in memory while loading

#### **Parameters**

**sRelationShipType** – String of the relationship type

# void SetStrictModeActive(const bool bStrictModeActive)

Activates (deactivates) the strict mode of the reader.

#### **Parameters**

**bStrictModeActive** – flag whether strict mode is active or not.

#### bool GetStrictModeActive()

Queries whether the strict mode of the reader is active or not

#### Returns

returns flag whether strict mode is active or not.

# std::string **GetWarning**(const *Lib3MF\_uint32* nIndex, *Lib3MF\_uint32* &nErrorCode)

Returns Warning and Error Information of the read process

#### **Parameters**

- nIndex Index of the Warning. Valid values are 0 to WarningCount 1
- **nErrorCode** filled with the error code of the warning

# Returns

the message of the warning

# Lib3MF\_uint32 GetWarningCount()

Returns Warning and Error Count of the read process

# Returns

filled with the count of the occurred warnings.

# void **AddKeyWrappingCallback** (const std::string &sConsumerID, const *KeyWrappingCallback* pTheCallback, const *Lib3MF\_pvoid* pUserData)

Registers a callback to deal with key wrapping mechanism from keystore

#### **Parameters**

- sConsumerID The ConsumerID to register for
- **pTheCallback** The callback used to decrypt data key
- pUserData Userdata that is passed to the callback function

# $\label{local_const} \begin{tabular}{ll} \textbf{Void SetContentEncryptionCallback} \ \textbf{pTheCallback}, const. \\ \textbf{Lib3MF\_pvoid} \ \textbf{pUserData}) \end{tabular}$

Registers a callback to deal with encryption of content

#### **Parameters**

- pTheCallback The callback used to encrypt content
- pUserData Userdata that is passed to the callback function

```
typedef std::shared_ptr<CReader> Lib3MF::PReader
```

Shared pointer to CReader to easily allow reference counting.

#### **CResource**

```
class Lib3MF:: CResource: public CBase
```

```
Lib3MF_uint32 GetResourceID()
```

Retrieves the unique id of this resource within a package. This function will be removed in a later release in favor of GetUniqueResourceID

#### Returns

Retrieves the unique id of this resource within a package.

# Lib3MF\_uint32 GetUniqueResourceID()

Retrieves the unique id of this resource within a package.

#### Returns

Retrieves the unique id of this resource within a package.

# PPackagePart PackagePart()

Returns the PackagePart within which this resource resides

#### Returns

the PackagePart within which this resource resides.

```
void SetPackagePart(CPackagePart *pPackagePart)
```

Sets the new PackagePart within which this resource resides

#### **Parameters**

**pPackagePart** – the new PackagePart within which this resource resides.

# Lib3MF uint32 GetModelResourceID()

Retrieves the id of this resource within a model.

# Returns

Retrieves the id of this resource within a model.

```
typedef std::shared_ptr<CResource> Lib3MF::PResource
```

Shared pointer to CResource to easily allow reference counting.

# **CResourceData**

```
class Lib3MF::CResourceData: public CBase
```

```
PPackagePart GetPath()
```

Gets the encrypted part path

# **Returns**

The part path

# eEncryptionAlgorithm ()

Gets the encryption algorithm used to encrypt this ResourceData

#### Returns

The encryption algorithm

```
eCompression GetCompression()
```

Tells whether this ResourceData is compressed or not

#### Returns

The compression method

void GetAdditionalAuthenticationData(std::vector<Lib3MF\_uint8> &ByteDataBuffer)

Tells whether this ResourceData is compressed or not

#### **Parameters**

 $\textbf{ByteDataBuffer} - The\ compression\ method$ 

typedef std::shared\_ptr<CResourceData> Lib3MF::PResourceData

Shared pointer to CResourceData to easily allow reference counting.

# **CResourceDataGroup**

```
class Lib3MF::CResourceDataGroup: public CBase
```

std::string GetKeyUUID()

Sets the resourcedatagroup keyuuid

#### **Returns**

The new resourcedatagroup keyuuid.

PAccessRight AddAccessRight(CConsumer \*pConsumer, const eWrappingAlgorithm eWrappingAlgorithm, const eMgfAlgorithm eMgfAlgorithm, const eDigestMethod)

Add accessright to resourcedatagroup element

#### Parameters

- **pConsumer** The Consumer reference
- eWrappingAlgorithm The key wrapping algorithm to be used
- eMgfAlgorithm The mask generation function to be used
- eDigestMethod The digest mechanism to be used

# Returns

The acess right instance

# PAccessRight FindAccessRightByConsumer(CConsumer \*pConsumer)

Finds the AccessRight associated with a Consumer

#### **Parameters**

**pConsumer** – The Consumer instance

# Returns

The AcessRight instance

void RemoveAccessRight(CConsumer \*pConsumer)

Removes access from a Consumer on this resource data group

#### **Parameters**

**pConsumer** – The Consumer instance

typedef std::shared\_ptr<CResourceDataGroup> Lib3MF::PResourceDataGroup

Shared pointer to CResourceDataGroup to easily allow reference counting.

# **CResourcelterator**

```
class Lib3MF::CResourceIterator: public CBase
```

#### bool MoveNext()

Iterates to the next resource in the list.

#### Returns

Iterates to the next resource in the list.

# bool MovePrevious()

Iterates to the previous resource in the list.

#### Returns

Iterates to the previous resource in the list.

# PResource GetCurrent()

Returns the resource the iterator points at.

#### Returns

returns the resource instance.

# PResourceIterator Clone()

Creates a new resource iterator with the same resource list.

#### Returns

returns the cloned Iterator instance

#### Lib3MF uint64 Count()

Returns the number of resoucres the iterator captures.

# Returns

returns the number of resoucres the iterator captures.

```
typedef std::shared_ptr<CResourceIterator> Lib3MF::PResourceIterator
```

Shared pointer to CResourceIterator to easily allow reference counting.

# **CSlice**

```
class Lib3MF::CSlice: public CBase
```

void SetVertices(const CInputVector<sPosition2D> &VerticesBuffer)

Set all vertices of a slice. All polygons will be cleared.

# **Parameters**

**VerticesBuffer** – contains the positions.

void GetVertices(std::vector<sPosition2D> &VerticesBuffer)

Get all vertices of a slice

#### **Parameters**

**VerticesBuffer** – contains the positions.

# Lib3MF\_uint64 GetVertexCount()

Get the number of vertices in a slice

#### Returns

the number of vertices in the slice

# Lib3MF\_uint64 AddPolygon(const CInputVector<Lib3MF\_uint32> &IndicesBuffer)

Add a new polygon to this slice

#### **Parameters**

**IndicesBuffer** – the new indices of the new polygon

#### Returns

the index of the new polygon

# Lib3MF uint64 GetPolygonCount()

Get the number of polygons in the slice

#### **Returns**

the number of polygons in the slice

void **SetPolygonIndices**(const *Lib3MF\_uint64* nIndex, const *CInputVector*<*Lib3MF\_uint32*> &IndicesBuffer)

Set all indices of a polygon

#### **Parameters**

- nIndex the index of the polygon to manipulate
- **IndicesBuffer** the new indices of the index-th polygon

void **GetPolygonIndices**(const *Lib3MF\_uint64* nIndex, std::vector<*Lib3MF\_uint32*> &IndicesBuffer)

Get all vertices of a slice

#### **Parameters**

- nIndex the index of the polygon to manipulate
- **IndicesBuffer** the indices of the index-th polygon

# Lib3MF\_uint64 GetPolygonIndexCount (const Lib3MF\_uint64 nIndex)

Get the number of vertices in a slice

#### **Parameters**

**nIndex** – the index of the polygon to manipulate

#### Returns

the number of indices of the index-th polygon

# Lib3MF\_double GetZTop()

Get the upper Z-Coordinate of this slice.

## Returns

the upper Z-Coordinate of this slice

typedef std::shared\_ptr<*CSlice*> Lib3MF::**PSlice** 

Shared pointer to CSlice to easily allow reference counting.

# **CSliceStack**

```
class Lib3MF::CSliceStack : public CResource
     Lib3MF double GetBottomZ()
           Get the lower Z-Coordinate of the slice stack.
               Returns
                   the lower Z-Coordinate the slice stack
     Lib3MF_uint64 GetSliceCount()
           Returns the number of slices
               Returns
                   the number of slices
     PSlice GetSlice(const Lib3MF uint64 nSliceIndex)
           Query a slice from the slice stack
               Parameters
                   nSliceIndex – the index of the slice
               Returns
                   the Slice instance
     PSlice AddSlice(const Lib3MF_double dZTop)
           Returns the number of slices
               Parameters
                   dZTop – upper Z coordinate of the slice
               Returns
                   a new Slice instance
     Lib3MF uint64 GetSliceRefCount()
           Returns the number of slice refs
               Returns
                   the number of slicereferences
     void AddSliceStackReference(CSliceStack *pTheSliceStack)
           Adds another existing slicestack as sliceref in this slicestack
               Parameters
                   pTheSliceStack – the slicestack to use as sliceref
     PSliceStack GetSliceStackReference(const Lib3MF_uint64 nSliceRefIndex)
           Adds another existing slicestack as sliceref in this slicestack
               Parameters
                   nSliceRefIndex - the index of the slice ref
               Returns
                   the slicestack that is used as sliceref
```

# void CollapseSliceReferences()

Removes the indirection of slices via slice-refs, i.e. creates the slices of all slice refs of this SliceStack as actual slices of this SliceStack. All previously existing slices or slicerefs will be removed.

```
void SetOwnPath(const std::string &sPath)
```

Sets the package path where this Slice should be stored. Input an empty string to reset the path

#### **Parameters**

**sPath** – the package path where this Slice should be stored

```
std::string GetOwnPath()
```

Obtains the package path where this Slice should be stored. Returns an empty string if the slicestack is stored within the root model.

#### Returns

the package path where this Slice will be stored

```
typedef std::shared_ptr<CSliceStack> Lib3MF::PSliceStack
```

Shared pointer to CSliceStack to easily allow reference counting.

#### **CSliceStackIterator**

```
class Lib3MF::CSliceStackIterator : public CResourceIterator
```

```
PSliceStack GetCurrentSliceStack()
```

Returns the SliceStack the iterator points at.

#### Returns

returns the SliceStack instance.

```
typedef std::shared_ptr<CSliceStackIterator> Lib3MF::PSliceStackIterator
```

Shared pointer to CSliceStackIterator to easily allow reference counting.

# CTexture2D

```
class Lib3MF::CTexture2D: public CResource
```

```
PAttachment GetAttachment()
```

Retrieves the attachment located at the path of the texture.

#### **Returns**

attachment that holds the texture's image information.

```
void SetAttachment(CAttachment *pAttachment)
```

Sets the texture's package path to the path of the attachment.

# **Parameters**

**pAttachment** – attachment that holds the texture's image information.

```
eTextureType GetContentType()
```

Retrieves a texture's content type.

# Returns

returns content type enum.

void SetContentType(const eTextureType eContentType)

Retrieves a texture's content type.

#### **Parameters**

**eContentType** – new Content Type

void **GetTileStyleUV**(eTextureTileStyle &eTileStyleU, eTextureTileStyle &eTileStyleV)

Retrieves a texture's tilestyle type.

### **Parameters**

- eTileStyleU returns tilestyle type enum.
- eTileStyleV returns tilestyle type enum.

void **SetTileStyleUV**(const *eTextureTileStyle* eTileStyleU, const *eTextureTileStyle* eTileStyleV)

Sets a texture's tilestyle type.

#### **Parameters**

- eTileStyleU new tilestyle type enum.
- eTileStyleV new tilestyle type enum.

```
eTextureFilter GetFilter()
```

Retrieves a texture's filter type.

#### **Returns**

returns filter type enum.

void SetFilter(const eTextureFilter eFilter)

Sets a texture's filter type.

#### **Parameters**

**eFilter** – sets new filter type enum.

typedef std::shared\_ptr<*CTexture2D*> Lib3MF::**PTexture2D** 

Shared pointer to CTexture2D to easily allow reference counting.

# CTexture2DGroup

```
class Lib3MF::CTexture2DGroup: public CResource
```

```
Lib3MF_uint32 GetCount()
```

Retrieves the count of tex2coords in the Texture2DGroup.

#### Returns

returns the count of tex2coords.

void GetAllPropertyIDs(std::vector<Lib3MF\_uint32> &PropertyIDsBuffer)

returns all the PropertyIDs of all tex2coords in this Texture2DGroup

# **Parameters**

**PropertyIDsBuffer** – PropertyID of the tex2coords in the Texture2DGroup.

Lib3MF\_uint32 AddTex2Coord(const sTex2Coord &UVCoordinate)

Adds a new tex2coord to the Texture2DGroup

#### **Parameters**

**UVCoordinate** – The u/v-coordinate within the texture, horizontally right/vertically up from the origin in the lower left of the texture.

#### Returns

returns new PropertyID of the new tex2coord in the Texture2DGroup.

# sTex2Coord GetTex2Coord(const Lib3MF\_uint32 nPropertyID)

Obtains a tex2coord to the Texture2DGroup

#### **Parameters**

**nPropertyID** – the PropertyID of the tex2coord in the Texture2DGroup.

#### Returns

The u/v-coordinate within the texture, horizontally right/vertically up from the origin in the lower left of the texture.

# void RemoveTex2Coord(const Lib3MF\_uint32 nPropertyID)

Removes a tex2coords from the Texture2DGroup.

#### **Parameters**

**nPropertyID** – PropertyID of the tex2coords in the Texture2DGroup.

# PTexture2D GetTexture2D()

Obtains the texture 2D instance of this group.

# Returns

the texture2D instance of this group.

# typedef std::shared\_ptr<*CTexture2DGroup*> Lib3MF::**PTexture2DGroup**

Shared pointer to CTexture2DGroup to easily allow reference counting.

# CTexture2DGroupIterator

class Lib3MF::CTexture2DGroupIterator : public CResourceIterator

# PTexture2DGroup GetCurrentTexture2DGroup()

Returns the Texture2DGroup the iterator points at.

#### Returns

returns the Texture2DGroup instance.

# typedef std::shared\_ptr<*CTexture2DGroupIterator*> Lib3MF::**PTexture2DGroupIterator**

Shared pointer to CTexture2DGroupIterator to easily allow reference counting.

# **CTexture2DIterator**

class Lib3MF::CTexture2DIterator: public CResourceIterator

# PTexture2D GetCurrentTexture2D()

Returns the Texture2D the iterator points at.

#### Returns

returns the Texture2D instance.

# typedef std::shared\_ptr<CTexture2DIterator> Lib3MF::PTexture2DIterator

Shared pointer to CTexture2DIterator to easily allow reference counting.

# **CWriter**

class Lib3MF::CWriter : public CBase

void WriteToFile(const std::string &sFilename)

Writes out the model as file. The file type is specified by the Model Writer class.

#### **Parameters**

**sFilename** – Filename to write into

Lib3MF\_uint64 GetStreamSize()

Retrieves the size of the full 3MF file stream.

#### Returns

the stream size

void WriteToBuffer(std::vector<Lib3MF\_uint8> &BufferBuffer)

Writes out the 3MF file into a memory buffer

#### **Parameters**

**BufferBuffer** – buffer to write into

void **WriteToCallback** (const *WriteCallback* pTheWriteCallback, const *SeekCallback* pTheSeekCallback, const *Lib3MF\_pvoid* pUserData)

Writes out the model and passes the data to a provided callback function. The file type is specified by the Model Writer class.

#### **Parameters**

- pTheWriteCallback Callback to call for writing a data chunk
- pTheSeekCallback Callback to call for seeking in the stream
- pUserData Userdata that is passed to the callback function

void **SetProgressCallback** (const *ProgressCallback* pProgressCallback, const *Lib3MF\_pvoid* pUserData) Set the progress callback for calls to this writer

### **Parameters**

- **pProgressCallback** pointer to the callback function.
- **pUserData** pointer to arbitrary user data that is passed without modification to the callback.

# Lib3MF uint32 GetDecimalPrecision()

Returns the number of digits after the decimal point to be written in each vertex coordinate-value.

#### Returns

The number of digits to be written in each vertex coordinate-value after the decimal point.

void **SetDecimalPrecision**(const *Lib3MF\_uint32* nDecimalPrecision)

Sets the number of digits after the decimal point to be written in each vertex coordinate-value.

#### **Parameters**

**nDecimalPrecision** – The number of digits to be written in each vertex coordinate-value after the decimal point.

void SetStrictModeActive(const bool bStrictModeActive)

Activates (deactivates) the strict mode of the reader.

#### **Parameters**

**bStrictModeActive** – flag whether strict mode is active or not.

# bool GetStrictModeActive()

Queries whether the strict mode of the reader is active or not

#### Returns

returns flag whether strict mode is active or not.

std::string **GetWarning**(const *Lib3MF uint32* nIndex, *Lib3MF uint32* &nErrorCode)

Returns Warning and Error Information of the read process

#### **Parameters**

- nIndex Index of the Warning. Valid values are 0 to WarningCount 1
- **nErrorCode** filled with the error code of the warning

#### **Returns**

the message of the warning

# Lib3MF\_uint32 GetWarningCount()

Returns Warning and Error Count of the read process

#### Returns

filled with the count of the occurred warnings.

void **AddKeyWrappingCallback** (const std::string &sConsumerID, const *KeyWrappingCallback* pTheCallback, const *Lib3MF\_pvoid* pUserData)

Registers a callback to deal with data key encryption/decryption from keystore

## **Parameters**

- sConsumerID The ConsumerID to register for
- pTheCallback The callback to be callede for wrapping and encryption key
- pUserData Userdata that is passed to the callback function

void **SetContentEncryptionCallback** (const *ContentEncryptionCallback* pTheCallback, const *Lib3MF\_pvoid* pUserData)

Registers a callback to deal with encryption of content

#### **Parameters**

- **pTheCallback** The callback used to encrypt content
- pUserData Userdata that is passed to the callback function

typedef std::shared\_ptr<CWriter> Lib3MF::PWriter

Shared pointer to CWriter to easily allow reference counting.

# 1.2 C-language bindings

This space describes the usage of lib3mf in a C host application.  $\label{topological} \mbox{TODO}$ 

# 1.3 Python-language bindings

TODO

# 1.4 Pascal-language bindings

TODO

# 1.5 C#-language bindings

This space describes the usage of lib3mf in a C# host application. TODO

# 1.6 Golang-language bindings

**TODO** 

# 1.7 NodeJS-language bindings

TODO

CHAPT	ER
TW	10

# **OBTAINING LIB3MF**

 $Simply\ download\ the\ precompiled\ binary\ SDK\ https://github.com/3MFConsortium/lib3mf/releases.$ 

**CHAPTER** 

**THREE** 

# **USING LIB3MF**

Allthough the different language bindings are kept as similar as possible, the usage of lib3mf still depends your programming language. You are best-off starting with one of the examples distributed in the SDK (https://github.com/ $\frac{3MFConsortium}{lib3mf/releases}$ ).

In addition, the home pages for each language binding give detailed instructions on how to use them.

# CHAPTER

# **FOUR**

# **META INFORMATION**

source/license

Reporting Bugs

The 3MF Consortium

Specification of the 3MF format

# CHAPTER

# **FIVE**

# **INDICES AND TABLES**

- genindex
- search

# **INDEX**

С	eBeamLatticeBallMode::eProgressIdentifier
ContentEncryptionCallback (C++ type), 15	(C++enum), 11
contened type to heart back (e + 1 type), 13	eBeamLatticeBallMode::eProgressIdentifier::CLEANUP
E	(C++ enumerator), 11
aPaper atticaPallMode (Ct   anum) 11	eBeamLatticeBallMode::eProgressIdentifier::CREATEOPCPACKAC
eBeamLatticeBallMode (C++ enum), 11	(C++ enumerator), 12
eBeamLatticeBallMode::All (C++ enumerator), 11 eBeamLatticeBallMode::eBlendMethod (C++	eBeamLatticeBallMode::eProgressIdentifier::DONE
`	(C++ enumerator), 11
enum), 12	eBeamLatticeBallMode::eProgressIdentifier::EXTRACTOPCPACKA
eBeamLatticeBallMode::eBlendMethod::Mix	(C++ enumerator), 11
(C++ enumerator), 12	eBeamLatticeBallMode::eProgressIdentifier::QUERYCANCELED
eBeamLatticeBallMode::eBlendMethod::Multiply	(C++ enumerator), 11
(C++ enumerator), 12	eBeamLatticeBallMode::eProgressIdentifier::READBUILD ethod (C++ enumerator), 11
eBeamLatticeBallMode::eBlendMethod::NoBlendMe	(C++ enumerator), 11
(C++ enumerator), 12	eBeamLatticeBallMode::eProgressIdentifier::READCUSTOMATTAG
eBeamLatticeBallMode::eCompression $(C++$	(C++ enumerator), 11
enum), 12	eBeamLatticeBallMode::eProgressIdentifier::READMESH
eBeamLatticeBallMode::eCompression::Deflate	(C)   anymarator) 11
(C++ enumerator), 12	eBeamLatticeBallMode::eProgressIdentifier::READNONROOTMODE (C++ enumerator), 11
eBeamLatticeBallMode::eCompression::NoCompres	(C++ enumerator), 11
(C++ enumerator), 12	eBeamLatticeBallMode::eProgressIdentifier::READRESOURCES
eBeamLatticeBallMode::eDigestMethod $(C++$	(C++ enumerator), 11
enum), 12	eBeamLatticeBallMode::eProgressIdentifier::READROOTMODEL
eBeamLatticeBallMode::eDigestMethod::SHA1	(C++ enumerator), 11
(C++ enumerator), 12	eBeamLatticeBallMode::eProgressIdentifier::READSLICES
eBeamLatticeBallMode::eDigestMethod::SHA256	(C++ enumerator), 11
(C++ enumerator), 12	eBeamLatticeBallMode::eProgressIdentifier::READSTREAM
eBeamLatticeBallMode::eEncryptionAlgorithm	(C)   anymarator) 11
(C++enum), 12	eBeamLatticeBallMode::eProgressIdentifier::READTEXTURETACE LES256_GCM (C++ enumerator), 11
eBeamLatticeBallMode::eEncryptionAlgorithm::A	AES256_GCM (C++ enumerator), 11
(C++ enumerator), 12	eBeamLatticeBallMode::eProgressIdentifier::WRITEATTACHMENT
eBeamLatticeBallMode::eMgfAlgorithm ( $C++$	(C + + onumerator) 12
enum), 12	eBeamLatticeBallMode::eProgressIdentifier::WRITECONTENTTYF (C++ enumerator), 12
eBeamLatticeBallMode::eMgfAlgorithm::MGF1_SHA	(C++ enumerator), 12
(C++ enumerator), 12	eBeamLatticeBallMode::eProgressIdentifier::WRITEKEYSTORE (C++ enumerator), 12
eBeamLatticeBallMode::eMgfAlgorithm::MGF1_SHA	(C++ enumerator), 12
(C++ enumerator), 12	eBeamLatticeBallMode::eProgressIdentifier::WRITEMODELSTOST (C++ enumerator), 12
eBeamLatticeBallMode::eMgfAlgorithm::MGF1_SHA	(C++ enumerator), 12
(C++ enumerator), 12	eBeamLatticeBallMode::eProgressIdentifier::WRITENOBJECTS (C++ enumerator), 12
eBeamLatticeBallMode::eMgfAlgorithm::MGF1_SHA	(C++ enumerator), 12
(C++ enumerator), 12	eBeamLatticeBallMode::eProgressIdentifier::WRITENODES (C++ enumerator), 12
eBeamLatticeBallMode::eMgfAlgorithm::MGF1_SHA	(C++ enumerator), 12
(C++ enumerator), 12	(- · · · · · · · · · //

```
eBeamLatticeBallMode::eProgressIdentifier::WRIGTANONROGHMDDELSC++ enum), 11
        (C++enumerator), 12
                                                eTextureFilter::Auto (C++ enumerator), 11
eBeamLatticeBallMode::eProgressIdentifier::WRICTEROOITMeDELter::Linear(C++ enumerator), 11
                                                eTextureFilter::Nearest (C++ enumerator), 11
        (C++enumerator), 12
eBeamLatticeBallMode::eProgressIdentifier::WRICTEStifleStyle(C++ enum), 10
        (C++enumerator), 12
                                                eTextureTileStyle::Clamp (C++ enumerator), 10
eBeamLatticeBallMode::eProgressIdentifier::WRIJFATKIJANGLESeStyle::Mirror(C++ enumerator), 10
        (C++enumerator), 12
                                                eTextureTileStyle::NoTileStyle (C++ enumera-
eBeamLatticeBallMode::eWrappingAlgorithm
                                                         tor), 11
                                                eTextureTileStyle::Wrap (C++ enumerator), 10
        (C++enum), 12
eBeamLatticeBallMode::eWrappingAlgorithm::RSA_@MEPtureType(C++ enum), 10
        (C++enumerator), 12
                                                eTextureType:: JPEG (C++ enumerator), 10
eBeamLatticeBallMode::Mixed (C++ enumerator),
                                                eTextureType::PNG(C++ enumerator), 10
                                                eTextureType::Unknown (C++ enumerator), 10
eBeamLatticeBallMode::None (C++ enumerator), 11
                                                K
eBeamLatticeCapMode (C++ enum), 11
eBeamLatticeCapMode::Butt (C++ enumerator), 11
                                                KeyWrappingCallback (C++type), 15
eBeamLatticeCapMode::HemiSphere (C++ enumera-
        tor), 11
eBeamLatticeCapMode::Sphere (C++ enumerator),
                                                Lib3MF::CAccessRight (C++ class), 17
        11
                                                Lib3MF::CAccessRight::GetConsumer (C++ func-
eBeamLatticeClipMode (C++ enum), 11
                                                         tion), 17
eBeamLatticeClipMode::Inside (C++ enumerator),
                                                Lib3MF::CAccessRight::GetDigestMethod (C++
                                                        function), 17
eBeamLatticeClipMode::NoClipMode (C++ enumer-
                                                Lib3MF::CAccessRight::GetMgfAlgorithm (C++
       ator), 11
                                                        function), 17
eBeamLatticeClipMode::Outside (C++ enumera-
                                                Lib3MF::CAccessRight::GetWrappingAlgorithm
       tor), 11
                                                         (C++ function), 17
eModelUnit (C++ enum), 10
                                                Lib3MF::CAttachment (C++ class), 18
eModelUnit::CentiMeter (C++ enumerator), 10
                                                Lib3MF::CAttachment::GetPath (C++ function), 18
eModelUnit::Foot (C++ enumerator), 10
                                                Lib3MF::CAttachment::GetRelationShipType
eModelUnit::Inch (C++ enumerator), 10
                                                         (C++ function), 18
eModelUnit::Meter (C++ enumerator), 10
                                                Lib3MF::CAttachment::GetStreamSize (C++ func-
eModelUnit::MicroMeter (C++ enumerator), 10
                                                         tion), 18
eModelUnit::MilliMeter (C++ enumerator), 10
                                                Lib3MF::CAttachment::PackagePart (C++ func-
eObjectType (C++ enum), 10
                                                         tion), 18
eObjectType::Model (C++ enumerator), 10
                                                Lib3MF::CAttachment::ReadFromBuffer
                                                                                           (C++
eObjectType::Other (C++ enumerator), 10
                                                        function), 18
eObjectType::SolidSupport (C++ enumerator), 10
                                                Lib3MF::CAttachment::ReadFromFile (C++ func-
eObjectType::Support (C++ enumerator), 10
                                                         tion), 18
ePropertyType (C++enum), 10
                                                Lib3MF::CAttachment::SetPath(C++ function), 18
ePropertyType::BaseMaterial (C++ enumerator),
                                                Lib3MF::CAttachment::SetRelationShipType
                                                         (C++ function), 18
ePropertyType::Colors (C++ enumerator), 10
                                                Lib3MF::CAttachment::WriteToBuffer (C++ func-
ePropertyType::Composite (C++ enumerator), 10
ePropertyType::Multi(C++ enumerator), 10
                                                Lib3MF::CAttachment::WriteToFile (C++ func-
ePropertyType::NoPropertyType (C++ enumera-
                                                         tion), 18
       tor), 10
                                                Lib3MF::CBase (C++ class), 19
ePropertyType::TexCoord (C++ enumerator), 10
                                                Lib3MF::CBaseMaterialGroup (C++ class), 19
eSlicesMeshResolution (C++ enum), 10
                                                Lib3MF::CBaseMaterialGroup::AddMaterial
eSlicesMeshResolution::Fullres (C++ enumera-
                                                         (C++ function), 19
       tor), 10
                                                Lib3MF::CBaseMaterialGroup::GetAllPropertyIDs
eSlicesMeshResolution::Lowres (C++ enumera-
                                                         (C++function), 19
        tor), 10
```

Lib3MF::CBaseMaterialGroup::GetCount	( <i>C</i> ++	function), 23
function), 19	c 1	Lib3MF::CBuildItem::GetObjectResourceID
Lib3MF::CBaseMaterialGroup::GetDisplay	Color	(C++ function), 23
(C++ function), 20	$(C \cup I)$	Lib3MF::CBuildItem::GetObjectTransform (C++ function), 23
Lib3MF::CBaseMaterialGroup::GetName function), 19	(C++	Lib3MF::CBuildItem::GetOutbox(C++function), 24
Lib3MF::CBaseMaterialGroup::RemoveMate	rial	Lib3MF::CBuildItem::GetOutbox(C++ func-
(C++function), 19	:1141	tion), 23
Lib3MF::CBaseMaterialGroup::SetDisplayColor		Lib3MF::CBuildItem::GetUUID (C++ function), 23
(C++ function), 20	00101	Lib3MF::CBuildItem::HasObjectTransform (C++
Lib3MF::CBaseMaterialGroup::SetName	(C++	function), 23
function), 19	·	Lib3MF::CBuildItem::SetObjectTransform (C++
Lib3MF::CBaseMaterialGroupIterator	(C++	function), 23
<i>class</i> ), 20		Lib3MF::CBuildItem::SetPartNumber (C++ func-
Lib3MF::CBaseMaterialGroupIterator::Ge	tCurrer	
(C++ function), 20		Lib3MF::CBuildItem::SetUUID(C++function), 23
Lib3MF::CBeamLattice(C++ class), 20		Lib3MF::CBuildItemIterator(C++ class), 24
Lib3MF::CBeamLattice::GetBallOptions function), 21	(C++	Lib3MF::CBuildItemIterator::Clone (C++ function), 24
$\verb Lib3MF::CBeamLattice::GetClipping  (C+-$	+ func-	Lib3MF::CBuildItemIterator::Count (C++ func-
tion), 20		tion), 24
Lib3MF::CBeamLattice::GetMinLength $(C+$	+ func-	Lib3MF::CBuildItemIterator::GetCurrent (C++
tion), 20		function), 24
Lib3MF::CBeamLattice::GetRepresentatio	'n	Lib3MF::CBuildItemIterator::MoveNext (C++
(C++ function), 21	£	function), 24
Lib3MF::CBeamLattice::SetClipping $(C+-tion)$ , 21	+ <i>Junc</i> -	Lib3MF::CBuildItemIterator::MovePrevious (C++ function), 24
$\verb Lib3MF::CBeamLattice::SetMinLength  (C+$	+ func-	Lib3MF::CColorGroup (C++ class), 25
<i>tion</i> ), 20		Lib3MF::CColorGroup::AddColor(C++function), 25
Lib3MF::CBeamLattice::SetRepresentatio (C++ function), 21	n	Lib3MF::CColorGroup::GetAllPropertyIDs (C++ function), 25
Lib3MF::CBeamSet $(C++class)$ , 21		Lib3MF::CColorGroup::GetColor(C++function), 25
Lib3MF::CBeamSet::GetBallReferenceCoun	ıt	Lib3MF::CColorGroup::GetCount(C++function), 25
(C++ function), 22		Lib3MF::CColorGroup::RemoveColor (C++ func-
Lib3MF::CBeamSet::GetBallReferences	(C++	tion), 25
function), 22		Lib3MF::CColorGroup::SetColor(C++function),25
${\tt Lib3MF::CBeamSet::GetIdentifier}\ (C++\mathit{fu}$	inction),	Lib3MF::CColorGroupIterator(C++ class), 26
22		Lib3MF::CColorGroupIterator::GetCurrentColorGroup
Lib3MF::CBeamSet::GetName (C++ function),		(C++function), 26
Lib3MF::CBeamSet::GetReferenceCount	(C++	Lib3MF::CComponent $(C++ class)$ , 26
function), 22	\	Lib3MF::CComponent::GetObjectResource (C++
Lib3MF::CBeamSet::GetReferences $(C++fu)$	nction),	function), 26
22 Lib3MF::CBeamSet::SetBallReferences	(C++	Lib3MF::CComponent::GetObjectResourceID (C++ function), 26
function), 22	(СТТ	Lib3MF::CComponent::GetTransform (C++ func-
Lib3MF::CBeamSet::SetIdentifier $(C++fu$	inction)	tion), 26
$\frac{22}{2}$	nenon),	Lib3MF::CComponent::GetUUID (C++ function), 26
.ib3MF::CBeamSet::SetName(C++ function), 21		Lib3MF::CComponent::HasTransform (C++ func-
Lib3MF::CBeamSet::SetReferences (C++ function),		tion), 26
22	,,	Lib3MF::CComponent::SetTransform (C++ func-
Lib3MF::CBuildItem (C++ class), 23		tion), 26
Lib3MF::CBuildItem::GetMetaDataGroup	(C++	Lib3MF::CComponent::SetUUID(C++ function), 26
function), 23		Lib3MF::CComponentsObject(C++ class), 27
Lib3MF::CBuildItem::GetObjectResource	(C++	Lib3MF::CComponentsObject::AddComponent

```
(C++ function), 27
                                                         (C++ function), 17
Lib3MF::CComponentsObject::GetComponent
                                                Lib3MF::CInputVector::CInputVector::size
        (C++ function), 27
                                                         (C++ function), 17
Lib3MF::CComponentsObject::GetComponentCount Lib3MF::CKeyStore (C++ class), 30
        (C++ function), 27
                                                Lib3MF::CKeyStore::AddConsumer (C++ function),
Lib3MF::CComponentsObjectIterator (C++ class),
                                                Lib3MF::CKeyStore::AddResourceData (C++ func-
Lib3MF::CComponentsObjectIterator::GetCurrentComponentsObject
        (C++ function), 27
                                                 Lib3MF::CKeyStore::AddResourceDataGroup
Lib3MF::CCompositeMaterials (C++ class), 28
                                                         (C++ function), 31
Lib3MF::CCompositeMaterials::AddComposite
                                                Lib3MF::CKeyStore::FindConsumer (C++ function),
        (C++ function), 28
Lib3MF::CCompositeMaterials::GetAllPropertyIDsLib3MF::CKeyStore::FindResourceData
                                                                                           (C++
        (C++ function), 28
                                                        function), 32
Lib3MF::CCompositeMaterials::GetBaseMaterialGroitp3MF::CKeyStore::FindResourceDataGroup
        (C++ function), 28
                                                         (C++ function), 31
Lib3MF::CCompositeMaterials::GetComposite
                                                Lib3MF::CKeyStore::GetConsumer (C++ function),
        (C++ function), 28
                                               Lib3MF::CKeyStore::GetConsumerCount
Lib3MF::CCompositeMaterials::GetCount (C++
                                                                                           (C++
       function), 28
                                                        function), 30
Lib3MF::CCompositeMaterials::RemoveComposite Lib3MF::CKeyStore::GetResourceData (C++ func-
        (C++ function), 28
                                                         tion), 32
Lib3MF::CCompositeMaterialsIterator
                                          (C++ Lib3MF::CKeyStore::GetResourceDataCount
        class), 29
                                                         (C++ function), 32
Lib3MF::CCompositeMaterialsIterator::GetCurrentilmAMMbsidHeMAterniælsGetResourceDataGroup
        (C++ function), 29
                                                         (C++ function), 31
Lib3MF::CConsumer (C++ class), 29
                                                Lib3MF::CKeyStore::GetResourceDataGroupCount
Lib3MF::CConsumer::GetConsumerID (C++ func-
                                                         (C++function), 31
                                                Lib3MF::CKeyStore::GetUUID(C++ function), 32
        tion), 29
Lib3MF::CConsumer::GetKeyID(C++ function), 29
                                                Lib3MF::CKeyStore::RemoveConsumer (C++ func-
Lib3MF::CConsumer::GetKeyValue (C++ function),
                                                         tion), 31
                                                Lib3MF::CKeyStore::RemoveResourceData (C++
Lib3MF::CContentEncryptionParams (C++ class),
                                                        function), 32
                                                Lib3MF::CKeyStore::RemoveResourceDataGroup
Lib3MF::CContentEncryptionParams::GetAdditionalAuthen(Ceant from Diatra). 31
        (C++ function), 30
                                                Lib3MF::CKeyStore::SetUUID(C++ function), 32
Lib3MF::CContentEncryptionParams::GetAuthentidaihiaMFapCMeshObject (C++ class), 33
        (C++ function), 29
                                                Lib3MF::CMeshObject::AddTriangle (C++ func-
Lib3MF::CContentEncryptionParams::GetDescriptor
                                                         tion), 34
                                                Lib3MF::CMeshObject::AddVertex (C++ function),
        (C++ function), 30
Lib3MF::CContentEncryptionParams::GetEncryptionAlgorithm
        (C++ function), 29
                                                Lib3MF::CMeshObject::BeamLattice (C++ func-
Lib3MF::CContentEncryptionParams::GetInitializationVection), 35
        (C++ function), 29
                                                Lib3MF::CMeshObject::ClearAllProperties
Lib3MF::CContentEncryptionParams::GetKey
                                                         (C++ function), 35
                                                Lib3MF::CMeshObject::GetAllTriangleProperties
        (C++ function), 29
Lib3MF::CContentEncryptionParams::GetKeyUUID
                                                         (C++ function), 35
        (C++ function), 30
                                                Lib3MF::CMeshObject::GetObjectLevelProperty
Lib3MF::CContentEncryptionParams::SetAuthenticationTagC++ function), 34
        (C++ function), 30
                                                Lib3MF::CMeshObject::GetTriangle (C++ func-
Lib3MF::CInputVector (C++ class), 17
                                                         tion), 33
Lib3MF::CInputVector::CInputVector (C++ func-
                                                Lib3MF::CMeshObject::GetTriangleCount (C++
        tion), 17
                                                        function), 33
Lib3MF::CInputVector::CInputVector::data
                                                Lib3MF::CMeshObject::GetTriangleIndices
```

```
(C++ function), 34
                                                         (C++ function), 37
Lib3MF::CMeshObject::GetTriangleProperties
                                                Lib3MF::CModel (C++ class), 38
                                                Lib3MF::CModel::AddAttachment(C++function), 44
        (C++ function), 34
Lib3MF::CMeshObject::GetVertex (C++ function),
                                                Lib3MF::CModel::AddBaseMaterialGroup
                                                         function), 43
Lib3MF::CMeshObject::GetVertexCount
                                          (C++ Lib3MF::CModel::AddBuildItem(C++ function), 43
        function), 33
                                                Lib3MF::CModel::AddColorGroup(C++function), 43
Lib3MF::CMeshObject::GetVertices (C++ func-
                                                Lib3MF::CModel::AddComponentsObject
                                                                                           (C++
                                                        function), 42
        tion), 33
Lib3MF::CMeshObject::IsManifoldAndOriented
                                                Lib3MF::CModel::AddCompositeMaterials
                                                                                          (C++
        (C++ function), 35
                                                        function), 43
Lib3MF::CMeshObject::SetAllTriangleProperties Lib3MF::CModel::AddCustomContentType
                                                                                           (C++
        (C++ function), 35
                                                        function), 45
                                                Lib3MF::CModel::AddMeshObject(C++function), 42
Lib3MF::CMeshObject::SetGeometry (C++ func-
                                                Lib3MF::CModel::AddMultiPropertyGroup (C++
        tion), 35
Lib3MF::CMeshObject::SetObjectLevelProperty
                                                         function), 43
        (C++ function), 34
                                                Lib3MF::CModel::AddSliceStack(C++function), 42
Lib3MF::CMeshObject::SetTriangle (C++ func-
                                                Lib3MF::CModel::AddTexture2DFromAttachment
                                                         (C++function), 42
        tion), 34
Lib3MF::CMeshObject::SetTriangleProperties
                                                Lib3MF::CModel::AddTexture2DGroup (C++ func-
        (C++ function), 34
                                                         tion), 43
Lib3MF::CMeshObject::SetVertex (C++ function),
                                                Lib3MF::CModel::CreatePackageThumbnailAttachment
                                                         (C++function), 44
Lib3MF::CMeshObjectIterator (C++ class), 36
                                                Lib3MF::CModel::FindAttachment (C++ function),
Lib3MF::CMeshObjectIterator::GetCurrentMeshObject
        (C++ function), 36
                                                Lib3MF::CModel::FindOrCreatePackagePart
Lib3MF::CMetaData(C++ class), 36
                                                         (C++ function), 38
Lib3MF::CMetaData::GetKey(C++ function), 36
                                                Lib3MF::CModel::GetAttachment(C++function),44
Lib3MF::CMetaData::GetMustPreserve (C++ func-
                                                Lib3MF::CModel::GetAttachmentCount (C++ func-
        tion), 36
                                                         tion), 44
Lib3MF::CMetaData::GetName (C++ function), 36
                                                Lib3MF::CModel::GetBaseMaterialGroupByID
Lib3MF::CMetaData::GetNameSpace (C++ function),
                                                         (C++ function), 39
                                                Lib3MF::CModel::GetBaseMaterialGroups (C++
Lib3MF::CMetaData::GetType(C++ function), 36
                                                        function), 41
                                                Lib3MF::CModel::GetBuildItems(C++function),41
Lib3MF::CMetaData::GetValue (C++ function), 37
Lib3MF::CMetaData::SetMustPreserve (C++ func-
                                                Lib3MF::CModel::GetBuildUUID(C++ function), 40
        tion), 36
                                                Lib3MF::CModel::GetColorGroupByID (C++ func-
Lib3MF::CMetaData::SetName (C++ function), 36
                                                         tion), 40
Lib3MF::CMetaData::SetNameSpace (C++ function),
                                                Lib3MF::CModel::GetColorGroups (C++ function),
Lib3MF::CMetaData::SetType (C++ function), 37
                                                Lib3MF::CModel::GetComponentsObjectByID
Lib3MF::CMetaData::SetValue (C++ function), 37
                                                         (C++ function), 40
Lib3MF::CMetaDataGroup (C++ class), 37
                                                Lib3MF::CModel::GetComponentsObjects
                                                                                           (C++
Lib3MF::CMetaDataGroup::AddMetaData
                                                        function), 41
                                          (C++
                                                Lib3MF::CModel::GetCompositeMaterials
                                                                                          (C++
        function), 38
Lib3MF::CMetaDataGroup::GetMetaData
                                          (C++
                                                         function), 42
                                                Lib3MF::CModel::GetCompositeMaterialsByID
        function), 37
Lib3MF::CMetaDataGroup::GetMetaDataByKey
                                                         (C++function), 40
        (C++ function), 37
                                                Lib3MF::CModel::GetKeyStore (C++ function), 45
Lib3MF::CMetaDataGroup::GetMetaDataCount
                                                Lib3MF::CModel::GetLanguage (C++ function), 39
        (C++ function), 37
                                                Lib3MF::CModel::GetMeshObjectByID (C++ func-
Lib3MF::CMetaDataGroup::RemoveMetaData (C++
                                                         tion), 40
        function), 38
                                                Lib3MF::CModel::GetMeshObjects (C++ function),
Lib3MF::CMetaDataGroup::RemoveMetaDataByIndex
                                                         41
```

```
Lib3MF::CModel::GetMetaDataGroup (C++ func-
                                                         function), 46
        tion), 43
                                                 Lib3MF::CMultiPropertyGroup::GetLayerCount
Lib3MF::CModel::GetMultiPropertyGroupByID
                                                         (C++ function), 46
        (C++ function), 40
                                                 Lib3MF::CMultiPropertyGroup::GetMultiProperty
Lib3MF::CModel::GetMultiPropertyGroups (C++
                                                         (C++ function), 46
        function), 42
                                                 Lib3MF::CMultiPropertyGroup::RemoveLayer
Lib3MF::CModel::GetObjects(C++ function), 41
                                                         (C++ function), 46
Lib3MF::CModel::GetOutbox (C++ function), 41
                                                 Lib3MF::CMultiPropertyGroup::RemoveMultiProperty
Lib3MF::CModel::GetPackageThumbnailAttachment
                                                         (C++ function), 46
                                                 Lib3MF::CMultiPropertyGroup::SetMultiProperty
        (C++ function), 44
Lib3MF::CModel::GetPropertyTypeByID
                                          (C++
                                                         (C++ function), 46
                                                 Lib3MF::CMultiPropertyGroupIterator
        function), 39
                                                                                           (C++
Lib3MF::CModel::GetResources (C++ function), 41
                                                         class), 47
Lib3MF::CModel::GetSliceStackByID (C++ func-
                                                 Lib3MF::CMultiPropertyGroupIterator::GetCurrentMultiPropertyGroupIterator:
                                                         (C++ function), 47
        tion), 40
Lib3MF::CModel::GetSliceStacks (C++ function),
                                                Lib3MF::CObject (C++ class), 47
                                                 Lib3MF::CObject::AssignSliceStack (C++ func-
Lib3MF::CModel::GetTexture2DByID (C++ func-
                                                 Lib3MF::CObject::ClearSliceStack (C++ func-
        tion), 39
Lib3MF::CModel::GetTexture2DGroupByID
                                                         tion), 49
        function), 39
                                                 Lib3MF::CObject::ClearThumbnailAttachment
Lib3MF::CModel::GetTexture2DGroups (C++ func-
                                                         (C++ function), 48
                                                 Lib3MF::CObject::GetMetaDataGroup (C++ func-
        tion), 42
Lib3MF::CModel::GetTexture2Ds(C++function),41
                                                         tion), 48
Lib3MF::CModel::GetUnit(C++ function), 38
                                                 Lib3MF::CObject::GetName (C++ function), 47
Lib3MF::CModel::HasPackageThumbnailAttachment Lib3MF::CObject::GetOutbox(C++ function), 48
        (C++ function), 44
                                                 Lib3MF::CObject::GetPartNumber (C++ function),
Lib3MF::CModel::MergeToModel (C++ function), 42
Lib3MF::CModel::QueryReader (C++ function), 39
                                                 Lib3MF::CObject::GetSlicesMeshResolution
Lib3MF::CModel::QueryWriter(C++ function), 39
                                                         (C++ function), 49
Lib3MF::CModel::RemoveAttachment (C++ func-
                                                Lib3MF::CObject::GetSliceStack (C++ function),
        tion), 44
Lib3MF::CModel::RemoveBuildItem(C++ function),
                                                 Lib3MF::CObject::GetThumbnailAttachment
                                                         (C++ function), 48
Lib3MF::CModel::RemoveCustomContentType
                                                 Lib3MF::CObject::GetType (C++ function), 47
                                                 Lib3MF::CObject::GetUUID(C++ function), 48
        (C++ function), 45
Lib3MF::CModel::RemovePackageThumbnailAttachmeImib3MF::CObject::HasSlices(C++ function), 49
        (C++ function), 45
                                                 Lib3MF::CObject::IsComponentsObject
                                                                                           (C++
Lib3MF::CModel::RootModelPart(C++function), 38
                                                         function), 48
Lib3MF::CModel::SetBuildUUID(C++ function), 41
                                                 Lib3MF::CObject::IsMeshObject(C++function), 47
Lib3MF::CModel::SetLanguage (C++ function), 39
                                                 Lib3MF::CObject::IsValid (C++ function), 48
Lib3MF::CModel::SetRandomNumberCallback
                                                 Lib3MF::CObject::SetAttachmentAsThumbnail
        (C++ function), 45
                                                         (C++ function), 48
Lib3MF::CModel::SetUnit(C++ function), 38
                                                 Lib3MF::CObject::SetName (C++ function), 47
Lib3MF::CMultiPropertyGroup (C++ class), 45
                                                 Lib3MF::CObject::SetPartNumber (C++ function),
Lib3MF::CMultiPropertyGroup::AddLayer (C++
                                                 Lib3MF::CObject::SetSlicesMeshResolution
        function), 46
Lib3MF::CMultiPropertyGroup::AddMultiProperty
                                                         (C++ function), 49
        (C++ function), 45
                                                 Lib3MF::CObject::SetType (C++ function), 47
Lib3MF::CMultiPropertyGroup::GetAllPropertyIDsLib3MF::CObject::SetUUID(C++ function), 48
        (C++ function), 45
                                                 Lib3MF::CObjectIterator (C++ class), 49
Lib3MF::CMultiPropertyGroup::GetCount
                                          (C++ Lib3MF::CObjectIterator::GetCurrentObject
        function), 45
                                                         (C++ function), 49
Lib3MF::CMultiPropertyGroup::GetLayer (C++ Lib3MF::CPackagePart (C++ class), 50
```

```
Lib3MF::CPackagePart::GetPath (C++function), 50 Lib3MF::CResourceIterator (C++class), 54
Lib3MF::CPackagePart::SetPath(C++function), 50 Lib3MF::CResourceIterator::Clone (C++function)
Lib3MF::CReader (C++ class), 50
                                                          tion), 54
Lib3MF::CReader::AddKeyWrappingCallback
                                                 Lib3MF::CResourceIterator::Count (C++ func-
        (C++ function), 51
                                                          tion), 54
Lib3MF::CReader::AddRelationToRead (C++ func-
                                                 Lib3MF::CResourceIterator::GetCurrent
                                                                                            (C++
                                                          function), 54
Lib3MF::CReader::GetStrictModeActive
                                          (C++ Lib3MF::CResourceIterator::MoveNext
                                                                                            (C++
        function), 51
                                                          function), 54
                                                 Lib3MF::CResourceIterator::MovePrevious
Lib3MF::CReader::GetWarning(C++ function), 51
Lib3MF::CReader::GetWarningCount (C++ func-
                                                          (C++ function), 54
                                                 Lib3MF::CSlice (C++ class), 54
        tion), 51
Lib3MF::CReader::ReadFromBuffer(C++ function),
                                                 Lib3MF::CSlice::AddPolygon (C++ function), 54
                                                 Lib3MF::CSlice::GetPolygonCount (C++ function),
Lib3MF::CReader::ReadFromCallback (C++ func-
        tion), 50
                                                 Lib3MF::CSlice::GetPolygonIndexCount
                                                                                             (C++
Lib3MF::CReader::ReadFromFile(C++function), 50
                                                          function), 55
Lib3MF::CReader::RemoveRelationToRead (C++
                                                 Lib3MF::CSlice::GetPolygonIndices (C++ func-
        function), 51
                                                          tion), 55
Lib3MF::CReader::SetContentEncryptionCallback Lib3MF::CSlice::GetVertexCount (C++ function),
        (C++ function), 51
                                                          54
Lib3MF::CReader::SetProgressCallback
                                           (C++ Lib3MF::CSlice::GetVertices (C++ function), 54
                                                 Lib3MF::CSlice::GetZTop(C++ function), 55
        function), 50
Lib3MF::CReader::SetStrictModeActive
                                           (C++ Lib3MF::CSlice::SetPolygonIndices (C++ func-
        function), 51
                                                          tion), 55
Lib3MF::CResource (C++ class), 52
                                                 Lib3MF::CSlice::SetVertices (C++ function), 54
Lib3MF::CResource::GetModelResourceID
                                          (C++ Lib3MF::CSliceStack (C++ class), 56
        function), 52
                                                 Lib3MF::CSliceStack::AddSlice(C++function), 56
Lib3MF::CResource::GetResourceID (C++ func-
                                                 Lib3MF::CSliceStack::AddSliceStackReference
        tion), 52
                                                          (C++ function), 56
Lib3MF::CResource::GetUniqueResourceID (C++ Lib3MF::CSliceStack::CollapseSliceReferences
        function), 52
                                                          (C++function), 56
Lib3MF::CResource::PackagePart (C++ function),
                                                 Lib3MF::CSliceStack::GetBottomZ(C++ function),
                                                          56
Lib3MF::CResource::SetPackagePart (C++ func- Lib3MF::CSliceStack::GetOwnPath (C++ function),
        tion), 52
Lib3MF::CResourceData (C++ class), 52
                                                 Lib3MF::CSliceStack::GetSlice(C++ function), 56
Lib3MF::CResourceData::GetAdditionalAuthenticatilm3MDataCSliceStack::GetSliceCount (C++ func-
        (C++ function), 53
                                                          tion), 56
{\tt Lib3MF}::{\tt CResourceData}::{\tt GetCompression} \quad (C++ {\tt Lib3MF}::{\tt CSliceStack}::{\tt GetSliceRefCount} \quad (C++ {\tt Compression})
        function), 52
                                                          function), 56
Lib3MF::CResourceData::GetEncryptionAlgorithm Lib3MF::CSliceStack::GetSliceStackReference
        (C++ function), 52
                                                          (C++ function), 56
Lib3MF::CResourceData::GetPath\ (C++\ function),\ Lib3MF::CSliceStack::SetOwnPath\ (C++\ function),
Lib3MF::CResourceDataGroup (C++ class), 53
                                                 Lib3MF::CSliceStackIterator (C++ class), 57
                                                 Lib3MF::CSliceStackIterator::GetCurrentSliceStack
Lib3MF::CResourceDataGroup::AddAccessRight
        (C++ function), 53
                                                          (C++ function), 57
Lib3MF::CResourceDataGroup::FindAccessRightByCoils3MMer:CTexture2D (C++ class), 57
                                                 Lib3MF::CTexture2D::GetAttachment (C++ func-
        (C++ function), 53
{\tt Lib3MF::CResourceDataGroup::GetKeyUUID} (C++
                                                          tion), 57
                                                 Lib3MF::CTexture2D::GetContentType (C++ func-
        function), 53
Lib3MF::CResourceDataGroup::RemoveAccessRight
                                                          tion), 57
        (C++ function), 53
                                                 Lib3MF::CTexture2D::GetFilter(C++ function), 58
```

```
Lib3MF::CTexture2D::GetTileStyleUV (C++ func- Lib3MF::CWrapper::RetrieveProgressMessage
        tion), 57
                                                         (C++ function), 7
                                                 Lib3MF::CWrapper::RGBAToColor(C++ function), 7
Lib3MF::CTexture2D::SetAttachment (C++ func-
                                                 Lib3MF::CWrapper::SetJournal(C++ function), 7
        tion), 57
Lib3MF::CTexture2D::SetContentType (C++ func-
                                                 Lib3MF::CWriter (C++ class), 60
        tion), 57
                                                 Lib3MF::CWriter::AddKeyWrappingCallback
Lib3MF::CTexture2D::SetFilter(C++function), 58
                                                         (C++ function), 61
Lib3MF::CTexture2D::SetTileStyleUV (C++ func-
                                                 Lib3MF::CWriter::GetDecimalPrecision
                                                                                            (C++
                                                         function), 60
        tion), 58
                                                 Lib3MF::CWriter::GetStreamSize (C++ function),
Lib3MF::CTexture2DGroup (C++ class), 58
Lib3MF::CTexture2DGroup::AddTex2Coord (C++
                                                 Lib3MF::CWriter::GetStrictModeActive
        function), 58
                                                                                            (C++
Lib3MF::CTexture2DGroup::GetAllPropertyIDs
                                                         function), 61
        (C++ function), 58
                                                 Lib3MF::CWriter::GetWarning (C++ function), 61
Lib3MF::CTexture2DGroup::GetCount (C++ func-
                                                 Lib3MF::CWriter::GetWarningCount (C++ func-
        tion), 58
                                                          tion), 61
Lib3MF::CTexture2DGroup::GetTex2Coord (C++ Lib3MF::CWriter::SetContentEncryptionCallback
       function), 58
                                                         (C++ function), 61
Lib3MF::CTexture2DGroup::GetTexture2D (C++
                                                 Lib3MF::CWriter::SetDecimalPrecision
                                                                                            (C++
        function), 59
                                                         function), 60
Lib3MF::CTexture2DGroup::RemoveTex2Coord
                                                 Lib3MF::CWriter::SetProgressCallback
                                                                                            (C++
        (C++ function), 59
                                                         function), 60
Lib3MF::CTexture2DGroupIterator(C++ class), 59 Lib3MF::CWriter::SetStrictModeActive
                                                                                            (C++
Lib3MF::CTexture2DGroupIterator::GetCurrentTexture2DGroupIterator), 60
        (C++ function), 59
                                                 Lib3MF::CWriter::WriteToBuffer (C++ function),
Lib3MF::CTexture2DIterator (C++ class), 59
{\tt Lib3MF}::{\tt CTexture2DIterator}::{\tt GetCurrentTexture2Dib3MF}::{\tt CWriter}::{\tt WriteToCallback} (C++ func-
        (C++ function), 59
                                                         tion), 60
Lib3MF::CWrapper (C++ class), 6
                                                 Lib3MF::CWriter::WriteToFile (C++ function), 60
Lib3MF::CWrapper::Acquire (C++ function), 7
                                                 Lib3MF::ELib3MFException (C++ class), 16
Lib3MF::CWrapper::ColorToFloatRGBA (C++ func-
                                                 Lib3MF::ELib3MFException::ELib3MFException::getErrorCode
        tion), 8
                                                          (C++ function), 16
Lib3MF::CWrapper::ColorToRGBA(C++ function), 8
                                                 Lib3MF::ELib3MFException::ELib3MFException::what
Lib3MF::CWrapper::CreateModel (C++ function), 6
                                                         (C++function), 16
                                                 Lib3MF::PAccessRight (C++tvpe), 17
Lib3MF::CWrapper::FloatRGBAToColor (C++ func-
        tion), 7
                                                 Lib3MF::PAttachment (C++type), 19
Lib3MF::CWrapper::GetBuildInformation (C++ \text{ Lib3MF}::PBase (C++ type), 19)
        function), 6
                                                 Lib3MF::PBaseMaterialGroup (C++ type), 20
Lib3MF::CWrapper::GetIdentityTransform (C++ \text{Lib3MF}::PBaseMaterialGroupIterator}(C++ \text{type}),
                                                          20
        function), 8
Lib3MF::CWrapper::GetLastError(C++function),7
                                                 Lib3MF::PBeamLattice (C++type), 21
Lib3MF::CWrapper::GetLibraryVersion
                                          (C++
                                                 Lib3MF::PBeamSet (C++type), 22
        function), 6
                                                 Lib3MF::PBuildItem (C++type), 24
Lib3MF::CWrapper::GetPrereleaseInformation
                                                 Lib3MF::PBuildItemIterator(C++ type), 24
                                                 Lib3MF:: PColorGroup (C++type), 25
        (C++ function), 6
Lib3MF::CWrapper::GetScaleTransform
                                          (C++ Lib3MF::PColorGroupIterator (C++ type), 26
                                                 Lib3MF::PComponent (C++ type), 27
        function), 8
Lib3MF::CWrapper::GetSpecificationVersion
                                                 Lib3MF::PComponentsObject (C++type), 27
                                                 Lib3MF::PComponentsObjectIterator (C++ type),
        (C++function), 6
Lib3MF::CWrapper::GetTranslationTransform
        (C++ function), 9
                                                 Lib3MF::PCompositeMaterials(C++ type), 28
Lib3MF::CWrapper::GetUniformScaleTransform
                                                 Lib3MF::PCompositeMaterialsIterator
                                                                                            (C++
        (C++ function), 8
                                                          type), 29
Lib3MF::CWrapper::Release (C++ function), 7
                                                 Lib3MF::PConsumer (C++type), 29
```

```
Lib3MF::PContentEncryptionParams (C++tvpe), 30
                                                 sBeam::m_Indices (C++ member), 14
Lib3MF::PKeyStore (C++ type), 33
                                                 sBeam::m_Radii(C++ member), 14
                                                 sBox(C++struct), 13
Lib3MF::PMeshObject (C++type), 35
Lib3MF::PMeshObjectIterator(C++ type), 36
                                                 sBox::m_MaxCoordinate(C++ member), 13
Lib3MF::PMetaData (C++type), 37
                                                 sBox::m_MinCoordinate(C++ member), 13
Lib3MF::PMetaDataGroup (C++type), 38
                                                 sColor(C++ struct), 13
Lib3MF::PModel (C++tvpe), 45
                                                 sColor::m_Alpha (C++ member), 13
Lib3MF::PMultiPropertyGroup (C++ type), 47
                                                 sColor::m_Blue (C++ member), 13
Lib3MF::PMultiPropertyGroupIterator
                                          (C++
                                                 sColor::m_Green (C++ member), 13
                                                 sColor::m_Red(C++ member), 13
        type), 47
Lib3MF::PObject (C++ type), 49
                                                 sCompositeConstituent(C++ struct), 13
Lib3MF::PObjectIterator (C++ type), 49
                                                 sCompositeConstituent::m_MixingRatio
                                                                                           (C++
Lib3MF::PPackagePart (C++ type), 50
                                                         member), 13
                                                 sCompositeConstituent::m_PropertyID
                                                                                            (C++
Lib3MF::PReader (C++type), 51
Lib3MF::PResource (C++type), 52
                                                         member), 13
Lib3MF::PResourceData(C++ type), 53
                                                 SeekCallback (C++type), 14
Lib3MF::PResourceDataGroup (C++ type), 53
                                                 sMultiPropertyLayer (C++ struct), 13
Lib3MF::PResourceIterator (C++type), 54
                                                 sMultiPropertyLayer::m_ResourceID (C++ mem-
Lib3MF::PSlice (C++type), 55
                                                         ber), 13
                                                 sMultiPropertyLayer::m_TheBlendMethod (C++
Lib3MF::PSliceStack (C++type), 57
Lib3MF::PSliceStackIterator(C++ type), 57
                                                         member), 13
Lib3MF::PTexture2D (C++type), 58
                                                 sPosition (C++ struct), 13
                                                 sPosition2D(C++ struct), 13
Lib3MF::PTexture2DGroup (C++ type), 59
Lib3MF::PTexture2DGroupIterator (C++ type), 59
                                                 sPosition2D::m_Coordinates (C++ member), 13
Lib3MF::PTexture2DIterator (C++ type), 59
                                                 sPosition::m_Coordinates (C++ member), 13
Lib3MF::PWrapper (C++type), 9
                                                 sTex2Coord(C++ struct), 13
Lib3MF::PWriter (C++ type), 61
                                                 sTex2Coord::m_U (C++ member), 13
Lib3MF_double (C++type), 9
                                                 sTex2Coord::m_V (C++ member), 13
Lib3MF_int16 (C++type), 9
                                                 sTransform(C++struct), 13
Lib3MF_int32 (C++type), 9
                                                 sTransform::m_Fields (C++ member), 13
Lib3MF_int64 (C++type), 9
                                                 sTriangle (C++ struct), 13
Lib3MF_int8 (C++type), 9
                                                 sTriangle::m_Indices (C++ member), 13
                                                 sTriangleProperties (C++ struct), 13
Lib3MF_pvoid (C++type), 9
Lib3MF_single (C++ type), 9
                                                 sTriangleProperties::m_PropertyIDs (C++ mem-
Lib3MF_uint16 (C++tvpe), 9
                                                         ber), 13
Lib3MF_uint32 (C++ type), 9
                                                 sTriangleProperties::m_ResourceID (C++ mem-
Lib3MF_uint64 (C++type), 9
                                                         ber), 13
Lib3MF_uint8 (C++type), 9
                                                 W
Lib3MFResult (C++type), 9
                                                 WriteCallback (C++ type), 14
Р
ProgressCallback (C++ type), 14
R
RandomNumberCallback (C++type), 15
ReadCallback (C++ type), 14
S
sBall(C++struct), 14
sBall::m\_Index (C++ member), 14
sBall::m_Radius (C++ member), 14
sBeam (C++ struct), 14
sBeam::m_CapModes (C++ member), 14
```